# QXD0013 - Sistemas Operacionais Comunicação entre Processos II

Thiago Werlley Bandeira da Silva<sup>1</sup>

<sup>1</sup>Universidade Federal do Ceará, Brazil

09/11/2021











 Quando a capacidade do semáforo de fazer contagem não é necessária, uma versão simplificada às vezes é usada chamada de mutex







- Quando a capacidade do semáforo de fazer contagem não é necessária, uma versão simplificada às vezes é usada chamada de mutex
- Abreviação de Mutual Exclusion







- Quando a capacidade do semáforo de fazer contagem não é necessária, uma versão simplificada às vezes é usada chamada de mutex
- Abreviação de Mutual Exclusion
- Mutexes são bons somente para gerenciar a exclusão mútua de algum recurso ou trecho de código compartilhados.





- Quando a capacidade do semáforo de fazer contagem não é necessária, uma versão simplificada às vezes é usada chamada de mutex
- Abreviação de Mutual Exclusion
- Mutexes são bons somente para gerenciar a exclusão mútua de algum recurso ou trecho de código compartilhados.
- Mutex é uma variável compartilhada de dois estados: destravado/travado





- Quando a capacidade do semáforo de fazer contagem não é necessária, uma versão simplificada às vezes é usada chamada de mutex
- Abreviação de Mutual Exclusion
- Mutexes são bons somente para gerenciar a exclusão mútua de algum recurso ou trecho de código compartilhados.
- Mutex é uma variável compartilhada de dois estados: destravado/travado
- Duas rotinas s\(\tilde{a}\) o usadas com mutexes (thread ou processo):
   mutex\_lock(destravado)/mutex\_unlock(travado)





- Quando a capacidade do semáforo de fazer contagem não é necessária, uma versão simplificada às vezes é usada chamada de mutex
- Abreviação de Mutual Exclusion
- Mutexes são bons somente para gerenciar a exclusão mútua de algum recurso ou trecho de código compartilhados.
- Mutex é uma variável compartilhada de dois estados: destravado/travado
- Duas rotinas s\(\tilde{a}\) o usadas com mutexes (thread ou processo):
   mutex\_lock(destravado)/mutex\_unlock(travado)
- Mutexes são muito simples, eles podem ser facilmente implementados no espaço do usuário, desde que uma instrução TSL ou XCHG esteja disponível.











• Segue testando a trava repetidamente (espera ocupada):







- Segue testando a trava repetidamente (espera ocupada):
  - o Processos: escalonador realiza alternância







- Segue testando a trava repetidamente (espera ocupada):
  - o Processos: escalonador realiza alternância
  - o Threads: não há alternância







- Segue testando a trava repetidamente (espera ocupada):
  - o Processos: escalonador realiza alternância
  - Threads: não há alternância
- Thread precisa bloquear-se







- Segue testando a trava repetidamente (espera ocupada):
  - o Processos: escalonador realiza alternância
  - o Threads: não há alternância
- Thread precisa bloquear-se
  - o thread\_yield: dentro do espaço de usuário

#### mutex lock:

TSL REGISTER,MUTEX CMP REGISTER,#0 JZE ok CALL thread\_yield JMP mutex\_lock

ok: RET

copy mutex to register and set mutex to 1 was mutex zero?

if it was zero, mutex was unlocked, so return mutex is busy; schedule another thread try again

return to caller; critical region entered

#### mutex unlock:

MOVE MUTEX,#0 RET store a 0 in mutex return to caller





- Segue testando a trava repetidamente (espera ocupada):
  - o Processos: escalonador realiza alternância
  - o Threads: não há alternância
- Thread precisa bloquear-se
  - o thread\_yield: dentro do espaço de usuário

#### mutex lock:

TSL REGISTER, MUTEX CMP REGISTER, #0

JZE ok

CALL thread\_yield JMP mutex\_lock

RET

copy mutex to register and set mutex to 1 was mutex zero?

if it was zero, mutex was unlocked, so return mutex is busy; schedule another thread try again

return to caller; critical region entered

Tentativa acesso desimpedido

mutex\_unlock:

ok:

MOVE MUTEX,#0

store a 0 in mutex return to caller

MUTEX = 0 REGISTER = \*





- Segue testando a trava repetidamente (espera ocupada):
  - o Processos: escalonador realiza alternância
  - o Threads: não há alternância
- Thread precisa bloquear-se
  - o thread\_yield: dentro do espaço de usuário

#### mutex lock:

→ TSL REGISTER,MUTEX
CMP REGISTER,#0
JZE ok
CALL thread\_yield

JMP mutex\_lock ok: RET

copy mutex to register and set mutex to 1 was mutex zero?

if it was zero, mutex was unlocked, so return mutex is busy; schedule another thread try again return to caller; critical region entered

Tentativa acesso desimpedido

mutex\_unlock:

MOVE MUTEX,#0 RET store a 0 in mutex return to caller

MUTEX = 1 REGISTER = 0





- Segue testando a trava repetidamente (espera ocupada):
  - Processos: escalonador realiza alternância.
  - o Threads: não há alternância
- Thread precisa bloquear-se
  - o thread\_yield: dentro do espaço de usuário

#### mutex lock:

TSL REGISTER,MUTEX

→ CMP REGISTER,#0

JZE ok

CALL thread\_yield

JMP mutex\_lock

ok: RET

copy mutex to register and set mutex to 1 was mutex zero?

if it was zero, mutex was unlocked, so return mutex is busy; schedule another thread try again return to caller; critical region entered

Tentativa acesso desimpedido

MUTEX = 1 REGISTER = 0

mutex\_unlock:

MOVE MUTEX,#0

store a 0 in mutex return to caller





- Segue testando a trava repetidamente (espera ocupada):
  - o Processos: escalonador realiza alternância
  - o Threads: não há alternância
- Thread precisa bloquear-se
  - o thread\_yield: dentro do espaço de usuário

mutex\_lock:

TSL REGISTER,MUTEX

CMP REGISTER,#0

→ JZE ok

CALL thread\_yield

JMP mutex\_lock

ok:

RET

copy mutex to register and set mutex to 1 was mutex zero?

if it was zero, mutex was unlocked, so return mutex is busy; schedule another thread try again return to caller; critical region entered

Tentativa acesso desimpedido

MUTEX = 1 REGISTER = 0

mutex\_unlock:

MOVE MUTEX,#0 RET store a 0 in mutex return to caller





- Segue testando a trava repetidamente (espera ocupada):
  - o Processos: escalonador realiza alternância
  - o Threads: não há alternância
- Thread precisa bloquear-se
  - o thread\_yield: dentro do espaço de usuário

```
mutex_lock:
```

TSL REGISTER, MUTEX CMP REGISTER, #0 JZE ok

CALL thread\_yield
JMP mutex\_lock

ok: → RET

copy mutex to register and set mutex to 1 was mutex zero?

if it was zero, mutex was unlocked, so return mutex is busy; schedule another thread try again

return to caller; critical region entered

Tentativa acesso desimpedido

mutex\_unlock:

MOVE MUTEX,#0

store a 0 in mutex return to caller

MUTEX = 1

REGISTER = 0





- Segue testando a trava repetidamente (espera ocupada):
  - o Processos: escalonador realiza alternância
  - o Threads: não há alternância
- Thread precisa bloquear-se
  - o thread\_yield: dentro do espaço de usuário

#### mutex lock:

TSL REGISTER, MUTEX CMP REGISTER, #0

JZE ok

CALL thread\_yield
JMP mutex\_lock

RET

copy mutex to register and set mutex to 1 was mutex zero?

if it was zero, mutex was unlocked, so return mutex is busy; schedule another thread try again

return to caller; critical region entered

Tentativa acesso impedido

mutex\_unlock:

ok:

MOVE MUTEX,#0

store a 0 in mutex return to caller

MUTEX = 1

REGISTER = \*





- Segue testando a trava repetidamente (espera ocupada):
  - Processos: escalonador realiza alternância
  - o Threads: não há alternância
- Thread precisa bloquear-se
  - o thread\_yield: dentro do espaço de usuário

#### mutex lock:

→ TSL REGISTER,MUTEX
CMP REGISTER,#0
JZE ok
CALL thread\_yield

JMP mutex lock

ok: RET

copy mutex to register and set mutex to 1 was mutex zero?

if it was zero, mutex was unlocked, so return mutex is busy; schedule another thread try again

return to caller; critical region entered

(Tentativa acesso impedido

mutex\_unlock:

MOVE MUTEX,#0 RET store a 0 in mutex return to caller

MUTEX = 1 REGISTER = 1





- Segue testando a trava repetidamente (espera ocupada):
  - o Processos: escalonador realiza alternância
  - o Threads: não há alternância
- Thread precisa bloquear-se
  - o thread\_yield: dentro do espaço de usuário

#### mutex lock:

TSL REGISTER,MUTEX

→ CMP REGISTER,#0

JZE ok

CALL thread\_yield

JMP mutex\_lock

ok: RET

copy mutex to register and set mutex to 1 was mutex zero?

if it was zero, mutex was unlocked, so return mutex is busy; schedule another thread try again return to caller; critical region entered

Tentativa acesso impedido

mutex\_unlock:

MOVE MUTEX,#0 RET store a 0 in mutex return to caller

MUTEX = 1 REGISTER = 1





- Segue testando a trava repetidamente (espera ocupada):
  - Processos: escalonador realiza alternância.
  - Threads: não há alternância
- Thread precisa bloquear-se
  - o thread\_yield: dentro do espaço de usuário

```
mutex lock:
       TSL REGISTER, MUTEX
       CMP REGISTER,#0
       JZE ok
    → CALL thread_yield
```

JMP mutex lock

RET ok:

Tentativa acesso impedido

mutex\_unlock:

MOVE MUTEX,#0 RFT

MUTFX = 1

copy mutex to register and set mutex to 1

mutex is busy; schedule another thread

if it was zero, mutex was unlocked, so return

store a 0 in mutex return to caller

was mutex zero?

try again

return to caller; critical region entered

REGISTER = 1











 Hipótese → com um pacote de threads de espaço de usuário não há um problema com múltiplas threads terem acesso ao mesmo mutex, já que todos os threads operam em um espaço de endereçamento comum





- Hipótese → com um pacote de threads de espaço de usuário não há um problema com múltiplas threads terem acesso ao mesmo mutex, já que todos os threads operam em um espaço de endereçamento comum
- Threads: Espaço de usuário





- Hipótese → com um pacote de threads de espaço de usuário não há um problema com múltiplas threads terem acesso ao mesmo mutex, já que todos os threads operam em um espaço de endereçamento comum
- Threads: Espaço de usuário
- Processos:





- Hipótese → com um pacote de threads de espaço de usuário não há um problema com múltiplas threads terem acesso ao mesmo mutex, já que todos os threads operam em um espaço de endereçamento comum
- Threads: Espaço de usuário
- Processos:
  - $\circ$  Centralizado no núcleo o Acesso via chamadas do sistema





- Hipótese → com um pacote de threads de espaço de usuário não há um problema com múltiplas threads terem acesso ao mesmo mutex, já que todos os threads operam em um espaço de endereçamento comum
- Threads: Espaço de usuário
- Processos:
  - $\circ$  Centralizado no núcleo o Acesso via chamadas do sistema
  - o SO oferece meios de compartilhamento de estruturas de dados





- Hipótese → com um pacote de threads de espaço de usuário não há um problema com múltiplas threads terem acesso ao mesmo mutex, já que todos os threads operam em um espaço de endereçamento comum
- Threads: Espaço de usuário
- Processos:
  - $\circ$  Centralizado no núcleo o Acesso via chamadas do sistema
  - o SO oferece meios de compartilhamento de estruturas de dados
- Mecanismo mais eficiente em threads de usuário











• Com o paralelismo cada vez maior, a sincronização eficiente e o travamento são muito importantes para o desempenho.







- Com o paralelismo cada vez maior, a sincronização eficiente e o travamento são muito importantes para o desempenho.
- Travamento → desperdiçam ciclos de CPU







- Com o paralelismo cada vez maior, a sincronização eficiente e o travamento são muito importantes para o desempenho.
- Travamento → desperdiçam ciclos de CPU
- Chaveamento contínuo para o núcleo o Alto custo





- Com o paralelismo cada vez maior, a sincronização eficiente e o travamento são muito importantes para o desempenho.
- **Travamento** → desperdiçam ciclos de CPU
- Chaveamento contínuo para o núcleo o Alto custo
- Solução de meio termo para Linux implementando travamento básico





- Com o paralelismo cada vez maior, a sincronização eficiente e o travamento são muito importantes para o desempenho.
- Travamento → desperdiçam ciclos de CPU
- Chaveamento contínuo para o núcleo  $\rightarrow$  Alto custo
- Solução de meio termo para Linux implementando travamento básico
  - o mutex rápido de espaço de usuário (Futex: fast user space mutex)





- Com o paralelismo cada vez maior, a sincronização eficiente e o travamento são muito importantes para o desempenho.
- **Travamento** → desperdiçam ciclos de CPU
- Chaveamento contínuo para o núcleo o Alto custo
- Solução de meio termo para Linux implementando travamento básico
  - o mutex rápido de espaço de usuário (Futex: fast user space mutex)
- Futex (semelhante com mutex), mas evita adentrar o núcleo, a não ser que ele realmente tenha de fazê-lo.





- Com o paralelismo cada vez maior, a sincronização eficiente e o travamento são muito importantes para o desempenho.
- **Travamento** → desperdiçam ciclos de CPU
- Chaveamento contínuo para o núcleo o Alto custo
- Solução de meio termo para Linux implementando travamento básico
  - o mutex rápido de espaço de usuário (Futex: fast user space mutex)
- Futex (semelhante com mutex), mas evita adentrar o núcleo, a não ser que ele realmente tenha de fazê-lo.
- Instrução atômica em modo usuário (TSL)





- Com o paralelismo cada vez maior, a sincronização eficiente e o travamento são muito importantes para o desempenho.
- **Travamento** → desperdiçam ciclos de CPU
- Chaveamento contínuo para o núcleo o Alto custo
- Solução de meio termo para Linux implementando travamento básico
  - o mutex rápido de espaço de usuário (Futex: fast user space mutex)
- Futex (semelhante com mutex), mas evita adentrar o núcleo, a não ser que ele realmente tenha de fazê-lo.
- Instrução atômica em modo usuário (TSL)
- Chaveamento para o núcleo apenas quando:





- Com o paralelismo cada vez maior, a sincronização eficiente e o travamento são muito importantes para o desempenho.
- **Travamento** → desperdiçam ciclos de CPU
- Chaveamento contínuo para o núcleo o Alto custo
- Solução de meio termo para Linux implementando travamento básico
  - o mutex rápido de espaço de usuário (Futex: fast user space mutex)
- Futex (semelhante com mutex), mas evita adentrar o núcleo, a não ser que ele realmente tenha de fazê-lo.
- Instrução atômica em modo usuário (TSL)
- Chaveamento para o núcleo apenas quando:
  - o thread Bloqueio





- Com o paralelismo cada vez maior, a sincronização eficiente e o travamento são muito importantes para o desempenho.
- **Travamento** → desperdiçam ciclos de CPU
- Chaveamento contínuo para o núcleo o Alto custo
- Solução de meio termo para Linux implementando travamento básico
  - o mutex rápido de espaço de usuário (Futex: fast user space mutex)
- Futex (semelhante com mutex), mas evita adentrar o núcleo, a não ser que ele realmente tenha de fazê-lo.
- Instrução atômica em modo usuário (TSL)
- Chaveamento para o núcleo apenas quando:
  - o thread Bloqueio
  - o thread Desbloqueio





#### Exclusão Mútua - Mutexes e Pthread

Algumas chamadas de Pthreads relacionadas a mutexes.

Thread call	Description
Pthread_mutex_init	Create a mutex
Pthread_mutex_destroy	Destroy an existing mutex
Pthread_mutex_lock	Acquire a lock or block
Pthread_mutex_trylock	Acquire a lock or fail
Pthread_mutex_unlock	Release a lock











 Pthreads proporcionam uma série de funções que podem ser usadas para sincronizar threads.





- Pthreads proporcionam uma série de funções que podem ser usadas para sincronizar threads.
- Mutex  $\rightarrow$  Permitir/bloquear acesso de threads





- Pthreads proporcionam uma série de funções que podem ser usadas para sincronizar threads.
- Mutex → Permitir/bloquear acesso de threads
- ullet Variável de condição o Bloqueio condicional





- Pthreads proporcionam uma série de funções que podem ser usadas para sincronizar threads.
- Mutex  $\rightarrow$  Permitir/bloquear acesso de threads
- Variável de condição o Bloqueio condicional
  - o Condição para bloqueio/despertar





- Pthreads proporcionam uma série de funções que podem ser usadas para sincronizar threads.
- Mutex → Permitir/bloquear acesso de threads
- Variável de condição → Bloqueio condicional
  - Condição para bloqueio/despertar
- Cabe ao programador assegurar que os threads as usem corretamente.





#### Exclusão Mútua - Mutexes e Pthread

Algumas das chamadas de Pthreads relacionadas com variáveis de condição.

Thread call	Description
Pthread_cond_init	Create a condition variable
Pthread_cond_destroy	Destroy a condition variable
Pthread_cond_wait	Block waiting for a signal
Pthread_cond_signal	Signal another thread and wake it up
Pthread_cond_broadcast	Signal multiple threads and wake all of them





#include <stdio.h>
#include <pthread.h>
#define MAX 1000000000
pthread\_mutex\_t the\_mutex;
pthread\_cond\_t condc, condp;
int buffer = 0;

/\* how many numbers to produce \*/

/\* buffer used between producer and consumer \*/





#include <stdio.h>
#include <pthread.h>
#define MAX 100000000
pthread\_mutex\_t the\_mutex;
pthread\_cond\_t condo, condp;
int buffer = 0:

/\* how many numbers to produce \*/

/\* buffer used between producer and consumer \*/

```
int main(int argc, char **argv) {
    pthread_t pro, con;
    pthread_mutex_init(&the_mutex, 0);
    pthread_cond_init(&condc, 0);
    pthread_cond_init(&condp, 0);
    pthread_create(&con, 0, consumer, 0);
    pthread_create(&pro, 0, producer, 0);
    pthread_join(pro, 0);
    pthread_join(con, 0);
    pthread_cond_destroy(&condc);
    pthread_cond_destroy(&condp);
    pthread_mutex_destroy(&the_mutex);
}
```





```
#include <stdio.h>
#include <pthread.h>
#define MAX 1000000000
                                               /* how many numbers to produce */
othread mutex t the mutex:
pthread_cond_t condc, condp;
int buffer = 0:
                                               /* buffer used between producer and consumer */
void *consumer(void *ptr)
                                               /* consume data */
      int i:
                                                                                    int main(int argc, char **argv)
      for (i = 1; i \le MAX; i++) {
           pthread_mutex_lock(&the_mutex); /* get exclusive access to buffer */
                                                                                         pthread_t pro, con;
           while (buffer ==0) pthread_cond_wait(&condc, &the_mutex);
                                                                                         pthread_mutex_init(&the_mutex, 0):
           buffer = 0:
                                               /* take item out of buffer */
                                                                                         pthread_cond_init(&condc, 0):
                                               /* wake up producer */
           pthread_cond_signal(&condp);
                                                                                         pthread_cond_init(&condp. 0):
           pthread_mutex_unlock(&the_mutex):/* release access to buffer */
                                                                                         pthread_create(&con, 0, consumer, 0):
                                                                                         pthread_create(&pro, 0, producer, 0);
      pthread_exit(0);
                                                                                         pthread_join(pro, 0);
                                                                                         pthread_join(con, 0);
                                                                                         pthread_cond_destroy(&condc);
                                                                                         pthread_cond_destroy(&condp);
                                                                                         pthread_mutex_destroy(&the_mutex);
```





```
#include <stdio.h>
#include <pthread.h>
                                               /* how many numbers to produce */
#define MAX 1000000000
othread mutex t the mutex:
pthread_cond_t condc, condp;
int buffer = 0:
                                               /* buffer used between producer and consumer */
void *consumer(void *ptr)
                                                /* consume data */
      int i:
                                                                                     int main(int argc, char **argv)
      for (i = 1; i \le MAX; i++) {
           pthread_mutex_lock(&the_mutex); /* get exclusive access to buffer */
                                                                                          pthread_t pro, con;
           while (buffer ==0) pthread_cond_wait(&condc, &the_mutex);
                                                                                          pthread_mutex_init(&the_mutex, 0):
           buffer = 0:
                                                /* take item out of buffer */
                                                                                          pthread_cond_init(&condc, 0):
           pthread_cond_signal(&condp);
                                                /* wake up producer */
                                                                                          pthread_cond_init(&condp. 0):
           pthread_mutex_unlock(&the_mutex):/* release access to buffer */
                                                                                          pthread_create(&con, 0, consumer, 0):
                                                                                          pthread_create(&pro, 0, producer, 0);
      pthread_exit(0);
                                                                                          pthread_join(pro, 0);
                                                                                          pthread_join(con, 0);
                                                                                          pthread_cond_destroy(&condc);
void *producer(void *ptr)
                                               /* produce data */
                                                                                          pthread_cond_destroy(&condp);
     int i:
                                                                                          pthread_mutex_destroy(&the_mutex);
     for (i= 1: i <= MAX: i++) {
          pthread_mutex_lock(&the_mutex): /* get exclusive access to buffer */
          while (buffer != 0) pthread_cond_wait(&condp, &the_mutex):
```

/\* put item in buffer \*/

pthread\_mutex\_unlock(&the\_mutex);/\* release access to buffer \*/

/\* wake up consumer \*/

buffer = i:

pthread\_exit(0);

pthread cond signal(&condc):





```
#include <stdio.h>
#include <pthread.h>
                                              /* how many numbers to produce */
#define MAX 1000000000
othread mutex t the mutex:
pthread_cond_t condc, condp;
int buffer = 0:
                                              /* buffer used between producer and consumer */
void *consumer(void *ptr)
                                               /* consume data */
      int i:
                                                                                    int main(int argc, char **argv)
      for (i = 1; i \le MAX; i++) {
           pthread_mutex_lock(&the_mutex); /* get exclusive access to buffer */
                                                                                        pthread_t pro, con;
           while (buffer ==0) pthread_cond_wait(&condc, &the_mutex);
                                                                                         pthread_mutex_init(&the_mutex, 0):
           buffer = 0:
                                               /* take item out of buffer */
                                                                                         pthread_cond_init(&condc, 0):
           pthread_cond_signal(&condp);
                                               /* wake up producer */
                                                                                         pthread_cond_init(&condp. 0):
           pthread_mutex_unlock(&the_mutex):/* release access to buffer */
                                                                                         pthread_create(&con, 0, consumer, 0):
                                                                                         pthread_create(&pro, 0, producer, 0);
      pthread_exit(0);
                                                                                         pthread_join(pro, 0);
                                                                                         pthread_join(con, 0);
                                                                                         pthread_cond_destroy(&condc);
void *producer(void *ptr)
                                              /* produce data */
                                                                                         pthread_cond_destroy(&condp);
     int i:
                                                                                         pthread_mutex_destroy(&the_mutex);
     for (i= 1: i <= MAX: i++) {
          pthread_mutex_lock(&the_mutex): /* get exclusive access to buffer */
          while (buffer != 0) pthread_cond_wait(&condp, &the_mutex):
          buffer = i:
                                              /* put item in buffer */
                                                                                  Cria identificadores de threads
          pthread cond signal(&condc):
                                              /* wake up consumer */
          pthread_mutex_unlock(&the_mutex);/* release access to buffer */
```

pthread\_exit(0);





```
#include <stdio.h>
#include <pthread.h>
                                               /* how many numbers to produce */
#define MAX 1000000000
othread mutex t the mutex:
pthread_cond_t condc, condp;
int buffer = 0:
                                               /* buffer used between producer and consumer */
void *consumer(void *ptr)
                                                /* consume data */
      int i:
                                                                                    int main(int argc, char **argv)
      for (i = 1; i \le MAX; i++) {
           pthread_mutex_lock(&the_mutex); /* get exclusive access to buffer */
                                                                                          pthread_t pro, con;
           while (buffer ==0) pthread_cond_wait(&condc, &the_mutex);
                                                                                       pthread_mutex_init(&the_mutex, 0):
                                               /* take item out of buffer */
           buffer = 0:
                                                                                          pthread_cond_init(&condc, 0):
           pthread_cond_signal(&condp);
                                               /* wake up producer */
                                                                                          pthread_cond_init(&condp. 0):
           pthread_mutex_unlock(&the_mutex):/* release access to buffer */
                                                                                         pthread_create(&con, 0, consumer, 0):
                                                                                         pthread_create(&pro, 0, producer, 0);
      pthread_exit(0);
                                                                                          pthread_join(pro, 0);
                                                                                         pthread_join(con, 0);
                                                                                          pthread_cond_destroy(&condc);
void *producer(void *ptr)
                                               /* produce data */
                                                                                          pthread_cond_destroy(&condp);
     int i:
                                                                                         pthread_mutex_destroy(&the_mutex);
     for (i= 1: i <= MAX: i++) {
          pthread_mutex_lock(&the_mutex): /* get exclusive access to buffer */
          while (buffer != 0) pthread_cond_wait(&condp, &the_mutex):
          buffer = i:
                                               /* put item in buffer */
                                                                                   Inicializa mutex
          pthread cond signal(&condc):
                                               /* wake up consumer */
          pthread_mutex_unlock(&the_mutex);/* release access to buffer */
     pthread_exit(0);
```





```
#include <stdio.h>
#include <pthread.h>
                                               /* how many numbers to produce */
#define MAX 1000000000
othread mutex t the mutex:
pthread_cond_t condc, condp;
int buffer = 0:
                                               /* buffer used between producer and consumer */
void *consumer(void *ptr)
                                                /* consume data */
      int i:
                                                                                     int main(int argc, char **argv)
      for (i = 1; i \le MAX; i++) {
           pthread_mutex_lock(&the_mutex); /* get exclusive access to buffer */
                                                                                          pthread_t pro, con;
           while (buffer ==0) pthread_cond_wait(&condc, &the_mutex);
                                                                                          pthread_mutex_init(&the_mutex, 0):
           buffer = 0:
                                                /* take item out of buffer */
                                                                                        pthread_cond_init(&condc, 0):
           pthread_cond_signal(&condp);
                                                /* wake up producer */
                                                                                          pthread_cond_init(&condp, 0);
           pthread_mutex_unlock(&the_mutex):/* release access to buffer */
                                                                                          pthread_create(&con, 0, consumer, 0):
                                                                                          pthread_create(&pro, 0, producer, 0);
      pthread_exit(0);
                                                                                          pthread_join(pro, 0);
                                                                                          pthread_join(con, 0);
                                                                                          pthread_cond_destroy(&condc);
void *producer(void *ptr)
                                               /* produce data */
                                                                                          pthread_cond_destroy(&condp);
     int i:
                                                                                          pthread_mutex_destroy(&the_mutex);
     for (i= 1: i <= MAX: i++) {
          pthread_mutex_lock(&the_mutex): /* get exclusive access to buffer */
          while (buffer != 0) pthread_cond_wait(&condp, &the_mutex):
          buffer = i:
                                               /* put item in buffer */
```

/\* wake up consumer \*/

pthread\_mutex\_unlock(&the\_mutex);/\* release access to buffer \*/

Inicializa variável de condição

pthread\_exit(0);

pthread cond signal(&condc):





```
#include <stdio.h>
#include <pthread.h>
                                               /* how many numbers to produce */
#define MAX 1000000000
othread mutex t the mutex:
pthread_cond_t condc, condp;
int buffer = 0:
                                               /* buffer used between producer and consumer */
void *consumer(void *ptr)
                                                /* consume data */
      int i:
                                                                                     int main(int argc, char **argv)
      for (i = 1; i \le MAX; i++) {
           pthread_mutex_lock(&the_mutex); /* get exclusive access to buffer */
                                                                                          pthread_t pro, con;
           while (buffer ==0) pthread_cond_wait(&condc, &the_mutex);
                                                                                          pthread_mutex_init(&the_mutex, 0):
           buffer = 0:
                                                /* take item out of buffer */
                                                                                          pthread_cond_init(&condc, 0):
           pthread_cond_signal(&condp);
                                                /* wake up producer */
                                                                                          pthread_cond_init(&condp. 0):
           pthread_mutex_unlock(&the_mutex):/* release access to buffer */
                                                                                          pthread_create(&con, 0, consumer, 0):
                                                                                          pthread_create(&pro, 0, producer, 0);
      pthread_exit(0);
                                                                                          pthread_join(pro, 0);
                                                                                          pthread_join(con, 0);
                                                                                          pthread_cond_destroy(&condc);
void *producer(void *ptr)
                                               /* produce data */
                                                                                          pthread_cond_destroy(&condp);
     int i:
                                                                                          pthread_mutex_destroy(&the_mutex);
     for (i= 1: i <= MAX: i++) {
          pthread_mutex_lock(&the_mutex): /* get exclusive access to buffer */
          while (buffer != 0) pthread_cond_wait(&condp, &the_mutex):
          buffer = i:
                                               /* put item in buffer */
```

/\* wake up consumer \*/

pthread\_mutex\_unlock(&the\_mutex);/\* release access to buffer \*/

Inicializa variável de condição

pthread\_exit(0);

pthread cond signal(&condc):





```
#include <stdio.h>
#include <pthread.h>
                                              /* how many numbers to produce */
#define MAX 1000000000
othread mutex t the mutex:
pthread_cond_t condc, condp;
int buffer = 0:
                                              /* buffer used between producer and consumer */
void *consumer(void *ptr)
                                               /* consume data */
      int i:
                                                                                    int main(int argc, char **argv)
      for (i = 1; i \le MAX; i++) {
           pthread_mutex_lock(&the_mutex); /* get exclusive access to buffer */
                                                                                         pthread_t pro, con;
           while (buffer ==0) pthread_cond_wait(&condc, &the_mutex);
                                                                                         pthread_mutex_init(&the_mutex, 0):
           buffer = 0:
                                               /* take item out of buffer */
                                                                                         pthread_cond_init(&condc, 0):
           pthread_cond_signal(&condp);
                                               /* wake up producer */
                                                                                         pthread_cond_init(&condp. 0):
           pthread_mutex_unlock(&the_mutex):/* release access to buffer */
                                                                                       pthread_create(&con, 0, consumer, 0);
                                                                                         pthread_create(&pro, 0, producer, 0);
      pthread_exit(0);
                                                                                         pthread_join(pro, 0);
                                                                                         pthread_join(con, 0);
                                                                                         pthread_cond_destroy(&condc);
void *producer(void *ptr)
                                              /* produce data */
                                                                                         pthread_cond_destroy(&condp);
     int i:
                                                                                         pthread_mutex_destroy(&the_mutex);
     for (i= 1: i <= MAX: i++) {
          pthread_mutex_lock(&the_mutex): /* get exclusive access to buffer */
          while (buffer != 0) pthread_cond_wait(&condp, &the_mutex):
          buffer = i:
                                              /* put item in buffer */
                                                                                  Cria thread do consumidor
          pthread cond signal(&condc):
                                              /* wake up consumer */
          pthread_mutex_unlock(&the_mutex);/* release access to buffer */
```

pthread\_exit(0);





```
#include <stdio.h>
#include <pthread.h>
                                               /* how many numbers to produce */
#define MAX 1000000000
othread mutex t the mutex:
pthread_cond_t condc, condp;
int buffer = 0:
                                               /* buffer used between producer and consumer */
void *consumer(void *ptr)
                                                /* consume data */
      int i:
                                                                                    int main(int argc, char **argv)
      for (i = 1; i \le MAX; i++) {
           pthread_mutex_lock(&the_mutex); /* get exclusive access to buffer */
                                                                                         pthread_t pro, con;
           while (buffer ==0) pthread_cond_wait(&condc, &the_mutex);
                                                                                         pthread_mutex_init(&the_mutex, 0):
           buffer = 0:
                                               /* take item out of buffer */
                                                                                         pthread_cond_init(&condc, 0):
           pthread_cond_signal(&condp);
                                               /* wake up producer */
                                                                                         pthread_cond_init(&condp. 0):
           pthread_mutex_unlock(&the_mutex):/* release access to buffer */
                                                                                         pthread_create(&con, 0, consumer, 0):
                                                                                       pthread_create(&pro, 0, producer, 0);
      pthread_exit(0);
                                                                                         pthread_join(pro, 0);
                                                                                         pthread_join(con, 0);
                                                                                         pthread_cond_destroy(&condc);
void *producer(void *ptr)
                                               /* produce data */
                                                                                         pthread_cond_destroy(&condp);
     int i:
                                                                                         pthread_mutex_destroy(&the_mutex);
     for (i= 1: i <= MAX: i++) {
          pthread_mutex_lock(&the_mutex): /* get exclusive access to buffer */
          while (buffer != 0) pthread_cond_wait(&condp, &the_mutex):
          buffer = i:
                                               /* put item in buffer */
                                                                                   Cria thread do produtor
          pthread cond signal(&condc):
                                               /* wake up consumer */
          pthread_mutex_unlock(&the_mutex);/* release access to buffer */
     pthread_exit(0);
```





```
#include <stdio.h>
#include <pthread.h>
                                               /* how many numbers to produce */
#define MAX 1000000000
othread mutex t the mutex:
pthread_cond_t condc, condp;
int buffer = 0:
                                               /* buffer used between producer and consumer */
void *consumer(void *ptr)
                                                /* consume data */
      int i:
                                                                                    int main(int argc, char **argv)
      for (i = 1; i \le MAX; i++) {
           pthread_mutex_lock(&the_mutex); /* get exclusive access to buffer */
                                                                                          pthread_t pro, con;
           while (buffer ==0) pthread_cond_wait(&condc, &the_mutex);
                                                                                          pthread_mutex_init(&the_mutex, 0):
           buffer = 0:
                                                /* take item out of buffer */
                                                                                          pthread_cond_init(&condc, 0):
           pthread_cond_signal(&condp);
                                                /* wake up producer */
                                                                                          pthread_cond_init(&condp. 0):
           pthread_mutex_unlock(&the_mutex):/* release access to buffer */
                                                                                          pthread_create(&con, 0, consumer, 0):
                                                                                          pthread_create(&pro, 0, producer, 0);
      pthread_exit(0);
                                                                                        pthread_join(pro, 0);
                                                                                          pthread_join(con, 0);
                                                                                          pthread_cond_destroy(&condc);
void *producer(void *ptr)
                                               /* produce data */
                                                                                          pthread_cond_destroy(&condp);
     int i:
                                                                                          pthread_mutex_destroy(&the_mutex);
     for (i= 1: i <= MAX: i++) {
          pthread_mutex_lock(&the_mutex): /* get exclusive access to buffer */
          while (buffer != 0) pthread_cond_wait(&condp, &the_mutex):
```

/\* put item in buffer \*/

pthread\_mutex\_unlock(&the\_mutex);/\* release access to buffer \*/

/\* wake up consumer \*/

Espera saida do produtor

buffer = i:

pthread\_exit(0);

pthread cond signal(&condc):





```
#include <stdio.h>
#include <pthread.h>
                                              /* how many numbers to produce */
#define MAX 1000000000
othread mutex t the mutex:
pthread_cond_t condc, condp;
int buffer = 0:
                                              /* buffer used between producer and consumer */
void *consumer(void *ptr)
                                               /* consume data */
      int i:
                                                                                    int main(int argc, char **argv)
      for (i = 1; i \le MAX; i++) {
           pthread_mutex_lock(&the_mutex); /* get exclusive access to buffer */
                                                                                         pthread_t pro, con;
           while (buffer ==0) pthread_cond_wait(&condc, &the_mutex);
                                                                                         pthread_mutex_init(&the_mutex, 0):
           buffer = 0:
                                               /* take item out of buffer */
                                                                                         pthread_cond_init(&condc, 0):
           pthread_cond_signal(&condp);
                                               /* wake up producer */
                                                                                         pthread_cond_init(&condp. 0):
           pthread_mutex_unlock(&the_mutex):/* release access to buffer */
                                                                                         pthread_create(&con, 0, consumer, 0):
                                                                                         pthread_create(&pro, 0, producer, 0);
      pthread_exit(0);
                                                                                         pthread_join(pro, 0);
                                                                                       pthread_join(con, 0);
                                                                                         pthread_cond_destroy(&condc);
void *producer(void *ptr)
                                              /* produce data */
                                                                                         pthread_cond_destroy(&condp);
     int i:
                                                                                         pthread_mutex_destroy(&the_mutex);
     for (i= 1: i <= MAX: i++) {
          pthread_mutex_lock(&the_mutex): /* get exclusive access to buffer */
          while (buffer != 0) pthread_cond_wait(&condp, &the_mutex):
          buffer = i:
                                              /* put item in buffer */
                                                                                   Espera saida do consumidor
          pthread cond signal(&condc):
                                              /* wake up consumer */
          pthread_mutex_unlock(&the_mutex);/* release access to buffer */
```

pthread\_exit(0);





```
#include <stdio.h>
#include <pthread.h>
                                              /* how many numbers to produce */
#define MAX 1000000000
othread mutex t the mutex:
pthread_cond_t condc, condp;
int buffer = 0:
                                              /* buffer used between producer and consumer */
void *consumer(void *ptr)
                                               /* consume data */
      int i:
                                                                                    int main(int argc, char **argv)
      for (i = 1; i \le MAX; i++) {
           pthread_mutex_lock(&the_mutex); /* get exclusive access to buffer */
                                                                                         pthread_t pro, con;
           while (buffer ==0) pthread_cond_wait(&condc, &the_mutex);
                                                                                         pthread_mutex_init(&the_mutex, 0):
           buffer = 0:
                                               /* take item out of buffer */
                                                                                         pthread_cond_init(&condc, 0):
           pthread_cond_signal(&condp);
                                               /* wake up producer */
                                                                                         pthread_cond_init(&condp. 0):
           pthread_mutex_unlock(&the_mutex):/* release access to buffer */
                                                                                         pthread_create(&con, 0, consumer, 0):
                                                                                         pthread_create(&pro, 0, producer, 0);
      pthread_exit(0);
                                                                                         pthread_join(pro, 0);
                                                                                         pthread_join(con, 0);
                                                                                         pthread_cond_destroy(&condc);
void *producer(void *ptr)
                                              /* produce data */
                                                                                         pthread_cond_destroy(&condp);
     int i:
                                                                                         pthread_mutex_destroy(&the_mutex);
     for (i= 1: i <= MAX: i++) {
          pthread_mutex_lock(&the_mutex): /* get exclusive access to buffer */
          while (buffer != 0) pthread_cond_wait(&condp, &the_mutex):
          buffer = i:
                                              /* put item in buffer */
                                                                                   Destrói variável de Condição
          pthread cond signal(&condc):
                                              /* wake up consumer */
          pthread_mutex_unlock(&the_mutex);/* release access to buffer */
```

pthread\_exit(0);





```
#include <stdio.h>
#include <pthread.h>
                                               /* how many numbers to produce */
#define MAX 1000000000
othread mutex t the mutex:
pthread_cond_t condc, condp;
int buffer = 0:
                                               /* buffer used between producer and consumer */
void *consumer(void *ptr)
                                               /* consume data */
      int i:
                                                                                    int main(int argc, char **argv)
      for (i = 1; i \le MAX; i++) {
           pthread_mutex_lock(&the_mutex); /* get exclusive access to buffer */
                                                                                         pthread_t pro, con;
           while (buffer ==0) pthread_cond_wait(&condc, &the_mutex);
                                                                                         pthread_mutex_init(&the_mutex, 0):
           buffer = 0:
                                               /* take item out of buffer */
                                                                                         pthread_cond_init(&condc, 0):
           pthread_cond_signal(&condp);
                                               /* wake up producer */
                                                                                         pthread_cond_init(&condp. 0):
           pthread_mutex_unlock(&the_mutex):/* release access to buffer */
                                                                                         pthread_create(&con, 0, consumer, 0):
                                                                                         pthread_create(&pro, 0, producer, 0);
      pthread_exit(0);
                                                                                         pthread_join(pro, 0);
                                                                                         pthread_join(con, 0);
                                                                                         pthread_cond_destroy(&condc);
void *producer(void *ptr)
                                               /* produce data */
                                                                                         pthread_cond_destroy(&condp);
     int i:
                                                                                         pthread_mutex_destroy(&the_mutex);
     for (i= 1: i <= MAX: i++) {
          pthread_mutex_lock(&the_mutex): /* get exclusive access to buffer */
          while (buffer != 0) pthread_cond_wait(&condp, &the_mutex):
          buffer = i:
                                               /* put item in buffer */
                                                                                   Destrói variável de Condição
          pthread cond signal(&condc):
                                               /* wake up consumer */
          pthread_mutex_unlock(&the_mutex);/* release access to buffer */
     pthread_exit(0);
```





```
#include <stdio.h>
#include <pthread.h>
                                               /* how many numbers to produce */
#define MAX 1000000000
othread mutex t the mutex:
pthread_cond_t condc, condp;
int buffer = 0:
                                               /* buffer used between producer and consumer */
void *consumer(void *ptr)
                                                /* consume data */
      int i:
                                                                                    int main(int argc, char **argv)
      for (i = 1; i \le MAX; i++) {
           pthread_mutex_lock(&the_mutex); /* get exclusive access to buffer */
                                                                                         pthread_t pro, con;
           while (buffer ==0) pthread_cond_wait(&condc. &the_mutex);
                                                                                         pthread_mutex_init(&the_mutex, 0):
           buffer = 0:
                                               /* take item out of buffer */
                                                                                          pthread_cond_init(&condc, 0):
           pthread_cond_signal(&condp);
                                               /* wake up producer */
                                                                                          pthread_cond_init(&condp. 0):
           pthread_mutex_unlock(&the_mutex):/* release access to buffer */
                                                                                         pthread_create(&con, 0, consumer, 0):
                                                                                         pthread_create(&pro, 0, producer, 0);
      pthread_exit(0);
                                                                                          pthread_join(pro, 0);
                                                                                         pthread_join(con, 0);
                                                                                         pthread_cond_destroy(&condc);
void *producer(void *ptr)
                                               /* produce data */
                                                                                          pthread_cond_destroy(&condp);
     int i:
                                                                                         pthread_mutex_destroy(&the_mutex);
     for (i= 1: i <= MAX: i++) {
          pthread_mutex_lock(&the_mutex): /* get exclusive access to buffer */
          while (buffer != 0) pthread_cond_wait(&condp, &the_mutex):
          buffer = i:
                                               /* put item in buffer */
                                                                                   Destrói mutex
          pthread cond signal(&condc):
                                               /* wake up consumer */
          pthread_mutex_unlock(&the_mutex);/* release access to buffer */
     pthread_exit(0);
```





```
#include <stdio.h>
#include <pthread.h>
                                               /* how many numbers to produce */
#define MAX 1000000000
othread mutex t the mutex:
pthread_cond_t condc, condp;
int buffer = 0:
                                               /* buffer used between producer and consumer */
void *consumer(void *ptr)
                                                /* consume data */
      int i:
                                                                                    int main(int argc, char **argv)
      for (i = 1; i \le MAX; i++) {
           pthread_mutex_lock(&the_mutex); /* get exclusive access to buffer */
                                                                                         pthread_t pro, con;
           while (buffer ==0) pthread_cond_wait(&condc, &the_mutex);
                                                                                         pthread_mutex_init(&the_mutex, 0):
           buffer = 0:
                                               /* take item out of buffer */
                                                                                         pthread_cond_init(&condc, 0):
           pthread_cond_signal(&condp);
                                               /* wake up producer */
                                                                                         pthread_cond_init(&condp. 0):
           pthread_mutex_unlock(&the_mutex):/* release access to buffer */
                                                                                         pthread_create(&con, 0, consumer, 0):
                                                                                         pthread_create(&pro, 0, producer, 0);
      pthread_exit(0);
                                                                                         pthread_join(pro, 0);
                                                                                         pthread_join(con, 0);
                                                                                         pthread_cond_destroy(&condc);
void *producer(void *ptr)
                                               /* produce data */
                                                                                         pthread_cond_destroy(&condp);
     int i:
                                                                                         pthread_mutex_destroy(&the_mutex);
     for (i= 1: i <= MAX: i++) {
          pthread_mutex_lock(&the_mutex): /* get exclusive access to buffer */
          while (buffer != 0) pthread_cond_wait(&condp, &the_mutex):
          buffer = i:
                                               /* put item in buffer */
                                                                                   Cons. acessa região crítica
          pthread cond signal(&condc):
                                               /* wake up consumer */
          pthread_mutex_unlock(&the_mutex);/* release access to buffer */
     pthread_exit(0);
```





```
#include <stdio.h>
#include <pthread.h>
                                              /* how many numbers to produce */
#define MAX 1000000000
othread mutex t the mutex:
pthread_cond_t condc, condp;
int buffer = 0:
                                              /* buffer used between producer and consumer */
void *consumer(void *ptr)
                                               /* consume data */
      int i:
                                                                                    int main(int argc, char **argv)
      for (i = 1; i \le MAX; i++) {
           pthread_mutex_lock(&the_mutex); /* get exclusive access to buffer */
                                                                                         pthread_t pro, con;
           while (buffer ==0) pthread_cond_wait(&condc, &the_mutex);
                                                                                         pthread_mutex_init(&the_mutex, 0):
           buffer = 0:
                                               /* take item out of buffer */
                                                                                         pthread_cond_init(&condc, 0):
           pthread_cond_signal(&condp);
                                               /* wake up producer */
                                                                                         pthread_cond_init(&condp. 0):
           pthread_mutex_unlock(&the_mutex):/* release access to buffer */
                                                                                         pthread_create(&con, 0, consumer, 0):
                                                                                         pthread_create(&pro, 0, producer, 0);
      pthread_exit(0);
                                                                                        pthread_join(pro, 0);
                                                                                         pthread_join(con, 0);
                                                                                         pthread_cond_destroy(&condc);
void *producer(void *ptr)
                                              /* produce data */
                                                                                         pthread_cond_destroy(&condp);
     int i:
                                                                                         pthread_mutex_destroy(&the_mutex);
     for (i= 1: i <= MAX: i++) {
          pthread_mutex_lock(&the_mutex): /* get exclusive access to buffer */
          while (buffer != 0) pthread_cond_wait(&condp, &the_mutex):
          buffer = i:
                                              /* put item in buffer */
                                                                                   Cons. libera mutex/espera cond
          pthread cond signal(&condc):
                                              /* wake up consumer */
          pthread_mutex_unlock(&the_mutex);/* release access to buffer */
     pthread_exit(0);
```





```
#include <stdio.h>
#include <pthread.h>
                                               /* how many numbers to produce */
#define MAX 1000000000
othread mutex t the mutex:
pthread_cond_t condc, condp;
int buffer = 0:
                                               /* buffer used between producer and consumer */
void *consumer(void *ptr)
                                                /* consume data */
      int i:
                                                                                     int main(int argc, char **argv)
      for (i = 1; i \le MAX; i++) {
           pthread_mutex_lock(&the_mutex); /* get exclusive access to buffer */
                                                                                          pthread_t pro, con;
           while (buffer ==0) pthread_cond_wait(&condc, &the_mutex);
                                                                                          pthread_mutex_init(&the_mutex, 0):
           buffer = 0:
                                                /* take item out of buffer */
                                                                                          pthread_cond_init(&condc, 0):
           pthread_cond_signal(&condp);
                                                /* wake up producer */
                                                                                          pthread_cond_init(&condp. 0):
           pthread_mutex_unlock(&the_mutex):/* release access to buffer */
                                                                                          pthread_create(&con, 0, consumer, 0):
                                                                                          pthread_create(&pro, 0, producer, 0);
      pthread_exit(0);
                                                                                         pthread_join(pro, 0);
                                                                                          pthread_join(con, 0);
                                                                                          pthread_cond_destroy(&condc);
void *producer(void *ptr)
                                               /* produce data */
                                                                                          pthread_cond_destroy(&condp);
     int i:
                                                                                          pthread_mutex_destroy(&the_mutex);
     for (i= 1: i <= MAX: i++) {
          pthread_mutex_lock(&the_mutex): /* get exclusive access to buffer */
          while (buffer != 0) pthread_cond_wait(&condp, &the_mutex):
```

/\* put item in buffer \*/

pthread\_mutex\_unlock(&the\_mutex);/\* release access to buffer \*/

/\* wake up consumer \*/

Prod. acessa região crítica

buffer = i:

pthread\_exit(0);





```
#include <stdio.h>
#include <pthread.h>
                                               /* how many numbers to produce */
#define MAX 1000000000
othread mutex t the mutex:
pthread_cond_t condc, condp;
int buffer = 0:
                                               /* buffer used between producer and consumer */
void *consumer(void *ptr)
                                                /* consume data */
      int i:
                                                                                     int main(int argc, char **argv)
      for (i = 1; i \le MAX; i++) {
           pthread_mutex_lock(&the_mutex); /* get exclusive access to buffer */
                                                                                          pthread_t pro, con;
           while (buffer ==0) pthread_cond_wait(&condc, &the_mutex);
                                                                                          pthread_mutex_init(&the_mutex, 0):
           buffer = 0:
                                                /* take item out of buffer */
                                                                                          pthread_cond_init(&condc, 0):
           pthread_cond_signal(&condp);
                                                /* wake up producer */
                                                                                          pthread_cond_init(&condp. 0):
           pthread_mutex_unlock(&the_mutex):/* release access to buffer */
                                                                                          pthread_create(&con, 0, consumer, 0):
                                                                                          pthread_create(&pro, 0, producer, 0);
      pthread_exit(0);
                                                                                         pthread_join(pro, 0);
                                                                                          pthread_join(con, 0);
                                                                                          pthread_cond_destroy(&condc);
void *producer(void *ptr)
                                               /* produce data */
                                                                                          pthread_cond_destroy(&condp);
     int i:
                                                                                          pthread_mutex_destroy(&the_mutex);
     for (i= 1: i <= MAX: i++) {
          pthread_mutex_lock(&the_mutex): /* get exclusive access to buffer */
          while (buffer != 0) pthread_cond_wait(&condp, &the_mutex):
```

/\* put item in buffer \*/

pthread\_mutex\_unlock(&the\_mutex);/\* release access to buffer \*/

/\* wake up consumer \*/

Prod. não entra no laço

buffer = i:

pthread\_exit(0);





```
#include <stdio.h>
#include <pthread.h>
                                               /* how many numbers to produce */
#define MAX 1000000000
othread mutex t the mutex:
pthread_cond_t condc, condp;
int buffer = 0:
                                               /* buffer used between producer and consumer */
void *consumer(void *ptr)
                                                /* consume data */
      int i:
                                                                                     int main(int argc, char **argv)
      for (i = 1; i \le MAX; i++) {
           pthread_mutex_lock(&the_mutex); /* get exclusive access to buffer */
                                                                                          pthread_t pro, con;
           while (buffer ==0) pthread_cond_wait(&condc, &the_mutex);
                                                                                          pthread_mutex_init(&the_mutex, 0):
           buffer = 0:
                                                /* take item out of buffer */
                                                                                          pthread_cond_init(&condc, 0):
           pthread_cond_signal(&condp);
                                                /* wake up producer */
                                                                                          pthread_cond_init(&condp. 0):
           pthread_mutex_unlock(&the_mutex):/* release access to buffer */
                                                                                          pthread_create(&con, 0, consumer, 0):
                                                                                          pthread_create(&pro, 0, producer, 0);
      pthread_exit(0);
                                                                                          pthread_join(pro, 0);
                                                                                          pthread_join(con, 0);
                                                                                          pthread_cond_destroy(&condc);
void *producer(void *ptr)
                                               /* produce data */
                                                                                          pthread_cond_destroy(&condp);
     int i:
                                                                                          pthread_mutex_destroy(&the_mutex);
     for (i= 1: i <= MAX: i++) {
          pthread_mutex_lock(&the_mutex): /* get exclusive access to buffer */
          while (buffer != 0) pthread_cond_wait(&condp, &the_mutex):
          buffer = i:
                                               /* put item in buffer */
```

/\* wake up consumer \*/

pthread\_mutex\_unlock(&the\_mutex);/\* release access to buffer \*/

Prod. gera novo item

pthread\_exit(0);





```
#include <stdio.h>
#include <pthread.h>
                                               /* how many numbers to produce */
#define MAX 1000000000
othread mutex t the mutex:
pthread_cond_t condc, condp;
int buffer = 0:
                                               /* buffer used between producer and consumer */
void *consumer(void *ptr)
                                                /* consume data */
      int i:
                                                                                     int main(int argc, char **argv)
      for (i = 1; i \le MAX; i++) {
           pthread_mutex_lock(&the_mutex); /* get exclusive access to buffer */
                                                                                          pthread_t pro, con;
           while (buffer ==0) pthread_cond_wait(&condc, &the_mutex);
                                                                                          pthread_mutex_init(&the_mutex, 0):
           buffer = 0:
                                                /* take item out of buffer */
                                                                                          pthread_cond_init(&condc, 0):
           pthread_cond_signal(&condp);
                                                /* wake up producer */
                                                                                          pthread_cond_init(&condp. 0):
           pthread_mutex_unlock(&the_mutex):/* release access to buffer */
                                                                                          pthread_create(&con, 0, consumer, 0):
                                                                                          pthread_create(&pro, 0, producer, 0);
      pthread_exit(0);
                                                                                          pthread_join(pro, 0);
                                                                                          pthread_join(con, 0);
                                                                                          pthread_cond_destroy(&condc);
void *producer(void *ptr)
                                               /* produce data */
                                                                                          pthread_cond_destroy(&condp);
     int i:
                                                                                          pthread_mutex_destroy(&the_mutex);
     for (i= 1: i <= MAX: i++) {
          pthread_mutex_lock(&the_mutex): /* get exclusive access to buffer */
          while (buffer != 0) pthread_cond_wait(&condp, &the_mutex):
                                               /* put item in buffer */
          buffer = i:
```

/\* wake up consumer \*/

pthread\_mutex\_unlock(&the\_mutex);/\* release access to buffer \*/

Prod. desperta Cons.

pthread\_exit(0);





```
#include <stdio.h>
#include <pthread.h>
                                               /* how many numbers to produce */
#define MAX 1000000000
othread mutex t the mutex:
pthread_cond_t condc, condp;
int buffer = 0:
                                               /* buffer used between producer and consumer */
void *consumer(void *ptr)
                                                /* consume data */
      int i:
                                                                                     int main(int argc, char **argv)
      for (i = 1; i \le MAX; i++) {
           pthread_mutex_lock(&the_mutex); /* get exclusive access to buffer */
                                                                                          pthread_t pro, con;
           while (buffer ==0) pthread_cond_wait(&condc, &the_mutex);
                                                                                          pthread_mutex_init(&the_mutex, 0):
           buffer = 0:
                                                /* take item out of buffer */
                                                                                          pthread_cond_init(&condc, 0):
           pthread_cond_signal(&condp);
                                                /* wake up producer */
                                                                                          pthread_cond_init(&condp. 0):
           pthread_mutex_unlock(&the_mutex):/* release access to buffer */
                                                                                          pthread_create(&con, 0, consumer, 0):
                                                                                          pthread_create(&pro, 0, producer, 0);
      pthread_exit(0);
                                                                                          pthread_join(pro, 0);
                                                                                          pthread_join(con, 0);
                                                                                          pthread_cond_destroy(&condc);
void *producer(void *ptr)
                                               /* produce data */
                                                                                          pthread_cond_destroy(&condp);
     int i:
                                                                                          pthread_mutex_destroy(&the_mutex);
     for (i= 1: i <= MAX: i++) {
          pthread_mutex_lock(&the_mutex): /* get exclusive access to buffer */
          while (buffer != 0) pthread_cond_wait(&condp, &the_mutex):
          buffer = i:
                                               /* put item in buffer */
```

/\* wake up consumer \*/

pthread\_mutex\_unlock(&the\_mutex);/\* release access to buffer \*/

Cons. retira item do buffer

pthread\_exit(0);





```
#include <stdio.h>
#include <pthread.h>
                                               /* how many numbers to produce */
#define MAX 1000000000
othread mutex t the mutex:
pthread_cond_t condc, condp;
int buffer = 0:
                                               /* buffer used between producer and consumer */
void *consumer(void *ptr)
                                                /* consume data */
      int i:
                                                                                    int main(int argc, char **argv)
      for (i = 1; i \le MAX; i++) {
           pthread_mutex_lock(&the_mutex); /* get exclusive access to buffer */
                                                                                         pthread_t pro, con;
           while (buffer ==0) pthread_cond_wait(&condc, &the_mutex);
                                                                                         pthread_mutex_init(&the_mutex, 0):
           buffer = 0:
                                               /* take item out of buffer */
                                                                                          pthread_cond_init(&condc, 0):
           pthread_cond_signal(&condp);
                                               /* wake up producer */
                                                                                          pthread_cond_init(&condp. 0):
           pthread_mutex_unlock(&the_mutex):/* release access to buffer */
                                                                                         pthread_create(&con, 0, consumer, 0):
                                                                                          pthread_create(&pro, 0, producer, 0);
      pthread_exit(0);
                                                                                         pthread_join(pro, 0);
                                                                                          pthread_join(con, 0);
                                                                                          pthread_cond_destroy(&condc);
void *producer(void *ptr)
                                               /* produce data */
                                                                                          pthread_cond_destroy(&condp);
     int i:
                                                                                          pthread_mutex_destroy(&the_mutex);
     for (i= 1: i <= MAX: i++) {
          pthread_mutex_lock(&the_mutex): /* get exclusive access to buffer */
          while (buffer != 0) pthread_cond_wait(&condp, &the_mutex):
          buffer = i:
                                               /* put item in buffer */
                                                                                   Cons. acorda Prod.
          pthread_cond_signal(&condc);
                                               /* wake up consumer */
          pthread_mutex_unlock(&the_mutex);/* release access to buffer */
     pthread_exit(0);
```





# Exclusão Mútua - Variáveis de Condição e Pthread

```
#include <stdio.h>
#include <pthread.h>
                                               /* how many numbers to produce */
#define MAX 1000000000
othread mutex t the mutex:
pthread_cond_t condc, condp;
int buffer = 0:
                                               /* buffer used between producer and consumer */
void *consumer(void *ptr)
                                                /* consume data */
      int i:
                                                                                     int main(int argc, char **argv)
      for (i = 1; i \le MAX; i++) {
           pthread_mutex_lock(&the_mutex); /* get exclusive access to buffer */
                                                                                          pthread_t pro, con;
           while (buffer ==0) pthread_cond_wait(&condc. &the_mutex):
                                                                                          pthread_mutex_init(&the_mutex, 0):
           buffer = 0:
                                                /* take item out of buffer */
                                                                                          pthread_cond_init(&condc, 0):
           pthread_cond_signal(&condp);
                                                /* wake up producer */
                                                                                          pthread_cond_init(&condp. 0):
           pthread_mutex_unlock(&the_mutex):/* release access to buffer */
                                                                                          pthread_create(&con, 0, consumer, 0):
                                                                                          pthread_create(&pro, 0, producer, 0);
      pthread_exit(0);
                                                                                          pthread_join(pro, 0);
                                                                                          pthread_join(con, 0);
                                                                                          pthread_cond_destroy(&condc);
void *producer(void *ptr)
                                               /* produce data */
                                                                                          pthread_cond_destroy(&condp);
     int i:
                                                                                          pthread_mutex_destroy(&the_mutex);
     for (i= 1: i <= MAX: i++) {
          pthread_mutex_lock(&the_mutex): /* get exclusive access to buffer */
          while (buffer != 0) pthread_cond_wait(&condp, &the_mutex):
          buffer = i:
                                               /* put item in buffer */
```

/\* wake up consumer \*/

pthread\_mutex\_unlock(&the\_mutex);/\* release access to buffer \*/

Cons. sai da região crítica

pthread\_exit(0);

pthread\_cond\_signal(&condc);





Com semáforos e mutexes a comunicação entre processos parece fácil, certo?





```
#define N 100
                                                 /* number of slots in the buffer */
typedef int semaphore:
                                                /* semaphores are a special kind of int */
                                                /* controls access to critical region */
semaphore mutex = 1:
semaphore empty = N;
                                                /* counts empty buffer slots */
semaphore full = 0;
                                                 /* counts full buffer slots */
void producer(void)
     int item:
                                                /* TRUE is the constant 1 */
     while (TRUE) (
          item = produce_item():
                                                /* generate something to put in buffer */
          down(&empty);
                                                /* decrement empty count */
          down(&mutex):
                                                /* enter critical region */
                                                /* put new item in buffer */
          insert_item(item):
          up(&mutex);
                                                /* leave critical region */
          up(&full);
                                                /* increment count of full slots */
void consumer(void)
     int item:
     while (TRUE) (
                                                /* infinite loop */
          down(&full):
                                                 /* decrement full count */
          down(&mutex);
                                                /* enter critical region */
          item = remove_item():
                                                /* take item from buffer */
          up(&mutex);
                                                /* leave critical region */
          up(&empty);
                                                /* increment count of empty slots */
          consume_item(item);
                                                /* do something with the item */
```





```
#define N 100
                                                /* number of slots in the buffer */
typedef int semaphore:
                                                /* semaphores are a special kind of int */
                                                /* controls access to critical region */
semaphore mutex = 1:
semaphore empty = N;
                                                /* counts empty buffer slots */
semaphore full = 0;
                                                /* counts full buffer slots */
void producer(void)
     int item:
                                                /* TRUE is the constant 1 */
     while (TRUE) (
          item = produce_item():
                                                /* generate something to put in buffer */
       down(&empty);
                                                /* decrement empty count */
        down(&mutex):
                                                /* enter critical region */
          insert_item(item):
                                                /* put new item in buffer */
          up(&mutex);
                                                /* leave critical region */
          up(&full);
                                                /* increment count of full slots */
void consumer(void)
     int item:
     while (TRUE) (
                                                /* infinite loop */
          down(&full):
                                                /* decrement full count */
          down(&mutex);
                                                /* enter critical region */
          item = remove_item():
                                                /* take item from buffer */
          up(&mutex);
                                                /* leave critical region */
          up(&empty);
                                                /* increment count of empty slots */
          consume_item(item);
                                                /* do something with the item */
```





```
#define N 100
                                                 /* number of slots in the buffer */
typedef int semaphore:
                                                /* semaphores are a special kind of int */
                                                /* controls access to critical region */
semaphore mutex = 1:
semaphore empty = N;
                                                /* counts empty buffer slots */
semaphore full = 0;
                                                 /* counts full buffer slots */
void producer(void)
     int item:
     while (TRUE) (
                                                /* TRUE is the constant 1 */
          item = produce_item():
                                                /* generate something to put in buffer */
          down(&mutex):
                                                /* enter critical region */
          down(&empty);
                                                /* decrement empty count */
                                                /* put new item in buffer */
          insert_item(item):
          up(&mutex);
                                                /* leave critical region */
          up(&full);
                                                /* increment count of full slots */
void consumer(void)
     int item:
     while (TRUE) (
                                                /* infinite loop */
          down(&full):
                                                 /* decrement full count */
          down(&mutex);
                                                /* enter critical region */
          item = remove_item():
                                                /* take item from buffer */
          up(&mutex);
                                                /* leave critical region */
          up(&empty);
                                                /* increment count of empty slots */
          consume_item(item);
                                                /* do something with the item */
```





```
#define N 100
                                                /* number of slots in the buffer */
typedef int semaphore:
                                               /* semaphores are a special kind of int */
                                               /* controls access to critical region */
semaphore mutex = 1:
semaphore empty = N;
                                               /* counts empty buffer slots */
semaphore full = 0;
                                                /* counts full buffer slots */
void producer(void)
     int item:
   while (TRUE) {
                                                /* TRUE is the constant 1 */
          item = produce_item():
                                               /* generate something to put in buffer */
          down(&mutex):
                                               /* enter critical region */
          down(&empty);
                                               /* decrement empty count */
                                               /* put new item in buffer */
          insert_item(item):
          up(&mutex);
                                               /* leave critical region */
          up(&full);
                                               /* increment count of full slots */
                                                 MUTEX = 1
                                                 EMPTY = 0
void consumer(void)
     int item:
     while (TRUE) (
                                               /* infinite loop */
          down(&full):
                                                /* decrement full count */
          down(&mutex);
                                               /* enter critical region */
          item = remove_item():
                                               /* take item from buffer */
                                               /* leave critical region */
          up(&mutex);
          up(&empty);
                                               /* increment count of empty slots */
          consume_item(item);
                                               /* do something with the item */
```





```
#define N 100
                                                /* number of slots in the buffer */
typedef int semaphore:
                                               /* semaphores are a special kind of int */
                                               /* controls access to critical region */
semaphore mutex = 1:
semaphore empty = N;
                                               /* counts empty buffer slots */
semaphore full = 0;
                                                /* counts full buffer slots */
void producer(void)
     int item:
     while (TRUE) (
                                                /* TRUE is the constant 1 */
          item = produce_item():
          down(&mutex):
                                               /* enter critical region */
          down(&empty);
                                               /* decrement empty count */
                                               /* put new item in buffer */
          insert_item(item):
          up(&mutex);
                                               /* leave critical region */
          up(&full);
                                               /* increment count of full slots */
                                                 MUTEX = 1
                                                 EMPTY = 0
void consumer(void)
     int item:
     while (TRUE) (
                                               /* infinite loop */
          down(&full):
                                                /* decrement full count */
          down(&mutex);
                                               /* enter critical region */
          item = remove_item():
                                               /* take item from buffer */
                                               /* leave critical region */
          up(&mutex);
          up(&empty);
                                               /* increment count of empty slots */
          consume_item(item);
                                               /* do something with the item */
```

```
/* generate something to put in buffer */
```





```
#define N 100
                                                /* number of slots in the buffer */
typedef int semaphore:
                                               /* semaphores are a special kind of int */
                                               /* controls access to critical region */
semaphore mutex = 1:
semaphore empty = N;
                                               /* counts empty buffer slots */
semaphore full = 0;
                                                /* counts full buffer slots */
void producer(void)
     int item:
     while (TRUE) (
                                                /* TRUE is the constant 1 */
          item = produce_item():
          down(&mutex):
                                               /* enter critical region */
          down(&empty);
                                               /* decrement empty count */
                                               /* put new item in buffer */
          insert_item(item):
          up(&mutex);
                                               /* leave critical region */
          up(&full);
                                               /* increment count of full slots */
                                                 MUTEX = 0
                                                 EMPTY = 0
void consumer(void)
     int item:
     while (TRUE) (
                                               /* infinite loop */
          down(&full):
                                                /* decrement full count */
          down(&mutex);
                                               /* enter critical region */
          item = remove_item():
                                               /* take item from buffer */
          up(&mutex);
                                               /* leave critical region */
          up(&empty);
                                               /* increment count of empty slots */
          consume_item(item);
                                               /* do something with the item */
```

```
/* generate something to put in buffer */
```





```
#define N 100
typedef int semaphore:
semaphore mutex = 1:
semaphore empty = N;
semaphore full = 0;
void producer(void)
     int item:
     while (TRUE) (
          item = produce_item():
          down(&mutex):
          down(&empty);
          insert_item(item):
          up(&mutex);
          up(&full);
void consumer(void)
     int item:
     while (TRUE) (
          down(&full):
          down(&mutex);
          item = remove_item():
          up(&mutex);
          up(&empty);
          consume_item(item);
```

```
/* number of slots in the buffer */
/* semaphores are a special kind of int */
/* controls access to critical region */
/* counts empty buffer slots */
/* counts full buffer slots */
/* TRUE is the constant 1 */
/* generate something to put in buffer */
/* enter critical region */
/* decrement empty count */
/* put new item in buffer */
/* leave critical region */
/* increment count of full slots */
 MUTEX = 0
 EMPTY = 0
/* infinite loop */
/* decrement full count */
/* enter critical region */
/* take item from buffer */
/* leave critical region */
/* increment count of empty slots */
/* do something with the item */
```





```
#define N 100
typedef int semaphore:
semaphore mutex = 1:
semaphore empty = N;
semaphore full = 0;
void producer(void)
     int item:
     while (TRUE) (
          item = produce_item():
          down(&mutex):
          down(&empty);
          insert_item(item):
          up(&mutex);
          up(&full);
void consumer(void)
     int item:
     while (TRUE) (
          down(&full):
          down(&mutex);
          item = remove_item():
          up(&mutex);
          up(&empty);
          consume_item(item);
```

```
/* number of slots in the buffer */
/* semaphores are a special kind of int */
/* controls access to critical region */
/* counts empty buffer slots */
/* counts full buffer slots */
/* TRUE is the constant 1 */
/* generate something to put in buffer */
/* enter critical region */
/* decrement empty count */
/* put new item in buffer */
/* leave critical region */
/* increment count of full slots */
 MUTEX = 0
 EMPTY = 0
/* infinite loop */
/* decrement full count */
/* enter critical region */
/* take item from buffer */
/* leave critical region */
/* increment count of empty slots */
/* do something with the item */
```





```
#define N 100
                                               /* number of slots in the buffer */
typedef int semaphore:
                                               /* semaphores are a special kind of int */
                                               /* controls access to critical region */
semaphore mutex = 1:
semaphore empty = N;
                                               /* counts empty buffer slots */
semaphore full = 0;
                                               /* counts full buffer slots */
void producer(void)
                                                   DEADLOCK
     int item:
     while (TRUE) (
                                               /* TRUE is the constant 1 */
          item produce_item():
                                               /* generate something to put in buffer */
          down(&mutex):
                                               /* enter critical region */
          down(&empty);
                                               /* decrement empty count */
          insert_item(item):
                                               /* put new item in buffer */
          up(&mutex);
                                               /* leave critical region */
          up(&full);
                                               /* increment count of full slots */
                                                MUTEX = 0
                                                EMPTY = 0
void consumer(void)
     int item:
     while (TRUE) (
                                               /* infinite loop */
          down(&full): /
                                               /* decrement full count */
          down(&mutex);
                                               /* enter critical region */
          item = remove_item():
                                               /* take item from buffer */
          up(&mutex);
                                               /* leave critical region */
          up(&empty);
                                               /* increment count of empty slots */
          consume_item(item);
                                               /* do something with the item */
```











• Complexidade no uso de semáforos: Similar à programação de baixo nível







- Complexidade no uso de semáforos: Similar à programação de baixo nível
- Para facilitar a escrita de programas corretos, Brinch Hansen (1973) / Hoare (1974) → propuseram uma primitiva de sincronização de nível mais alto chamada Monitor





- Complexidade no uso de semáforos: Similar à programação de baixo nível
- Para facilitar a escrita de programas corretos, Brinch Hansen (1973) / Hoare (1974) → propuseram uma primitiva de sincronização de nível mais alto chamada Monitor
- Monitor:





- Complexidade no uso de semáforos: Similar à programação de baixo nível
- Para facilitar a escrita de programas corretos, Brinch Hansen (1973) / Hoare (1974) → propuseram uma primitiva de sincronização de nível mais alto chamada Monitor
- Monitor:
  - o Unidade básica de sincronização de alto nível





- Complexidade no uso de semáforos: Similar à programação de baixo nível
- Para facilitar a escrita de programas corretos, Brinch Hansen (1973) / Hoare (1974) → propuseram uma primitiva de sincronização de nível mais alto chamada Monitor
- Monitor:
  - o Unidade básica de sincronização de alto nível
  - o Coleção de rotinas, variáveis e estruturas de dados





- Complexidade no uso de semáforos: Similar à programação de baixo nível
- Para facilitar a escrita de programas corretos, Brinch Hansen (1973) / Hoare (1974) → propuseram uma primitiva de sincronização de nível mais alto chamada Monitor
- Monitor:
  - o Unidade básica de sincronização de alto nível
  - o Coleção de rotinas, variáveis e estruturas de dados
  - Processos têm acesso apenas às rotinas





- Complexidade no uso de semáforos: Similar à programação de baixo nível
- Para facilitar a escrita de programas corretos, Brinch Hansen (1973) / Hoare (1974) → propuseram uma primitiva de sincronização de nível mais alto chamada Monitor
- Monitor:
  - o Unidade básica de sincronização de alto nível
  - o Coleção de rotinas, variáveis e estruturas de dados
  - o Processos têm acesso apenas às rotinas
  - o Propriedade básica: apenas um processo ativo em um monitor





- Complexidade no uso de semáforos: Similar à programação de baixo nível
- Para facilitar a escrita de programas corretos, Brinch Hansen (1973) / Hoare (1974) → propuseram uma primitiva de sincronização de nível mais alto chamada Monitor
- Monitor:
  - o Unidade básica de sincronização de alto nível
  - o Coleção de rotinas, variáveis e estruturas de dados
  - Processos têm acesso apenas às rotinas
  - o Propriedade básica: apenas um processo ativo em um monitor
- Monitores são uma construção da linguagem de programação







- Complexidade no uso de semáforos: Similar à programação de baixo nível
- Para facilitar a escrita de programas corretos, Brinch Hansen (1973) / Hoare (1974) → propuseram uma primitiva de sincronização de nível mais alto chamada Monitor
- Monitor:
  - o Unidade básica de sincronização de alto nível
  - o Coleção de rotinas, variáveis e estruturas de dados
  - Processos têm acesso apenas às rotinas
  - o Propriedade básica: apenas um processo ativo em um monitor
- Monitores são uma construção da linguagem de programação
- Compilador implementa exclusão mútua (mutex)





- Complexidade no uso de semáforos: Similar à programação de baixo nível
- Para facilitar a escrita de programas corretos, Brinch Hansen (1973) / Hoare (1974) → propuseram uma primitiva de sincronização de nível mais alto chamada Monitor
- Monitor:
  - Unidade básica de sincronização de alto nível
  - o Coleção de rotinas, variáveis e estruturas de dados
  - o Processos têm acesso apenas às rotinas
  - o Propriedade básica: apenas um processo ativo em um monitor
- Monitores são uma construção da linguagem de programação
- Compilador implementa exclusão mútua (mutex)
- ullet Variáveis condicionais o Bloquear processos quando necessário





- Complexidade no uso de semáforos: Similar à programação de baixo nível
- Para facilitar a escrita de programas corretos, Brinch Hansen (1973) / Hoare (1974) → propuseram uma primitiva de sincronização de nível mais alto chamada Monitor
- Monitor:
  - o Unidade básica de sincronização de alto nível
  - o Coleção de rotinas, variáveis e estruturas de dados
  - o Processos têm acesso apenas às rotinas
  - o Propriedade básica: apenas um processo ativo em um monitor
- Monitores são uma construção da linguagem de programação
- Compilador implementa exclusão mútua (mutex)
- ullet Variáveis condicionais o Bloquear processos quando necessário
  - wait/signal











 Para evitar ter dois processos ativos no monitor ao mesmo tempo, precisamos de uma regra dizendo o que acontece depois de um signal.





- Para evitar ter dois processos ativos no monitor ao mesmo tempo, precisamos de uma regra dizendo o que acontece depois de um signal.
- O que ocorre quando signal é chamado?







- Para evitar ter dois processos ativos no monitor ao mesmo tempo, precisamos de uma regra dizendo o que acontece depois de um signal.
- O que ocorre quando signal é chamado?
- Hoare





- Para evitar ter dois processos ativos no monitor ao mesmo tempo, precisamos de uma regra dizendo o que acontece depois de um signal.
- O que ocorre quando signal é chamado?
- Hoare
  - Chaveamento instantâneo propôs deixar o processo recentemente desperto executar, suspendendo o outro





- Para evitar ter dois processos ativos no monitor ao mesmo tempo, precisamos de uma regra dizendo o que acontece depois de um signal.
- O que ocorre quando signal é chamado?
- Hoare
  - Chaveamento instantâneo propôs deixar o processo recentemente desperto executar, suspendendo o outro
- Brinch Hansen





- Para evitar ter dois processos ativos no monitor ao mesmo tempo, precisamos de uma regra dizendo o que acontece depois de um signal.
- O que ocorre quando signal é chamado?
- Hoare
  - Chaveamento instantâneo propôs deixar o processo recentemente desperto executar, suspendendo o outro
- Brinch Hansen
  - Último comando da rotina propôs uma saída inteligente para o problema, exigindo que um processo realizando um signal deva sair do monitor imediatamente





- Para evitar ter dois processos ativos no monitor ao mesmo tempo, precisamos de uma regra dizendo o que acontece depois de um signal.
- O que ocorre quando signal é chamado?
- Hoare
  - Chaveamento instantâneo propôs deixar o processo recentemente desperto executar, suspendendo o outro
- Brinch Hansen
  - Último comando da rotina propôs uma saída inteligente para o problema, exigindo que um processo realizando um signal deva sair do monitor imediatamente
- Terceira opção





- Para evitar ter dois processos ativos no monitor ao mesmo tempo, precisamos de uma regra dizendo o que acontece depois de um signal.
- O que ocorre quando signal é chamado?
- Hoare
  - Chaveamento instantâneo propôs deixar o processo recentemente desperto executar, suspendendo o outro
- Brinch Hansen
  - Último comando da rotina propôs uma saída inteligente para o problema, exigindo que um processo realizando um signal deva sair do monitor imediatamente
- Terceira opção
  - o Esperar que processo saia do monitor





Um esqueleto do problema produtor-consumidor com monitores. Somente uma rotina do monitor está ativa por vez. O buffer tem N vagas.

monitor ProducerConsumer

```
condition full, empty;
                                                        integer count;
procedure producer;
begin
                                                        procedure insert(item: integer);
      while true do
                                                        begin
      begin
                                                              if count = N then wait(full);
            item = produce_item;
                                                              insert_item(item);
            ProducerConsumer.insert(item)
                                                              count := count + 1:
      end
                                                              if count = 1 then signal(empty)
end:
                                                        end:
procedure consumer;
                                                        function remove: integer;
begin
                                                        begin
      while true do
                                                              if count = 0 then wait(empty);
      begin
                                                              remove = remove item:
            item = ProducerConsumer.remove;
                                                              count := count - 1;
            consume_item(item)
                                                              if count = N - 1 then signal(full)
      end
                                                        end:
end:
                                                       count := 0:
                                                 end monitor;
```











• Java: exemplo de linguagem com suporte a monitores







- Java: exemplo de linguagem com suporte a monitores
- ullet Palavra chave  $\mathit{synchronized} o \mathsf{Exclus\~ao}$  mútua







#### **Monitores**

- Java: exemplo de linguagem com suporte a monitores
- Palavra chave synchronized → Exclusão mútua

```
static class our monitor {// este é o monitor
  private int buffer[] = new int[N];
  private int count = 0, lo = 0, hi = 0; // contadores e índices
  public synchronized void insert(int val) {
     if (count == N) go to sleep(); // se o buffer estiver cheio, vá dormir
     buffer [hi] = val; // insere um item no buffer
     hi = (hi + 1) % N; // lugar para colocar o próximo item
     count = count + 1; // mais um item no buffer agora
     if (count == 1) notify(): // se o consumidor estava dormindo, acorde-o
  public synchronized int remove() {
     int val:
     if (count == 0) go to sleep(); // se o buffer estiver vazio, vá dormir
     val = buffer [lo]; // busca um item no buffer
     lo = (lo + 1) % N; // lugar de onde buscar o próximo item
     count = count - 1: // um item a menos no buffer
     if (count == N - 1) notify(); // se o produtor estava dormindo, acorde-o
     return val:
  private void go_to_sleep() { try{wait();} catch(InterruptedException exc) {};}
```





#### **Monitores**

- Java: exemplo de linguagem com suporte a monitores
- Palavra chave synchronized → Exclusão mútua

```
static class our_monitor {// este é o monitor
  private int buffer[] = new int[N];
  private int count = 0, lo = 0, hi = 0; // contadores e índices
  public synchronized void insert(int val) {
     if (count == N) go_to_sleep(); // se o buffer estiver cheio, vá dormir
     buffer [hi] = val; // insere um item no buffer
     hi = (hi + 1) % N; // lugar para colocar o próximo item
     count = count + 1; // mais um item no buffer agora
     if (count == 1) notify(): // se o consumidor estava dormindo, acorde-o
                                         EXCLUSÃO MÚTUA
  public synchronized int remove()
     int val:
     if (count == 0) go to sleep(); // se o buffer estiver vazio, vá dormir
     val = buffer [lo]; // busca um item no buffer
     lo = (lo + 1) % N; // lugar de onde buscar o próximo item
     count = count - 1: // um item a menos no buffer
     if (count == N - 1) notify(); // se o produtor estava dormindo, acorde-o
     return val:
  private void go_to_sleep() { try{wait();} catch(InterruptedException exc) {};}
```





#### **Monitores**

- Java: exemplo de linguagem com suporte a monitores
- Palavra chave  $synchronized \rightarrow Exclusão mútua$

```
static class producer extends Thread {
  public void run() {// o método run contém o código do thread
    int item:
    while (true) { // laco do produtor
       item = produce_item();
       mon.insert(item);
  private int produce_item() { ... } // realmente produz
static class consumer extends Thread {
  public void run() {método run contém o código do thread
    int item:
    while (true) {
                   // laço do consumidor
       item = mon.remove():
       consume item (item);
  private void consume_item(int item) { ... }// realmente consome
```











• Projetados para resolver exclusão mútua







- Projetados para resolver exclusão mútua
- Problema com monitores, e também com semáforos é que







- Projetados para resolver exclusão mútua
- Problema com monitores, e também com semáforos é que
  - eles foram projetados para solucionar o problema da exclusão mútua em uma ou mais CPUs





- Projetados para resolver exclusão mútua
- Problema com monitores, e também com semáforos é que
  - eles foram projetados para solucionar o problema da exclusão mútua em uma ou mais CPUs
  - o Todas com acesso a uma memória comum





- Projetados para resolver exclusão mútua
- Problema com monitores, e também com semáforos é que
  - eles foram projetados para solucionar o problema da exclusão mútua em uma ou mais CPUs
  - o Todas com acesso a uma memória comum
- Quando movemos para um sistema distribuído





- Projetados para resolver exclusão mútua
- Problema com monitores, e também com semáforos é que
  - o eles foram projetados para solucionar o problema da exclusão mútua em uma ou mais CPUs
  - o Todas com acesso a uma memória comum
- Quando movemos para um sistema distribuído
  - o consistindo em múltiplas CPUs





- Projetados para resolver exclusão mútua
- Problema com monitores, e também com semáforos é que
  - o eles foram projetados para solucionar o problema da exclusão mútua em uma ou mais CPUs
  - o Todas com acesso a uma memória comum
- Quando movemos para um sistema distribuído
  - o consistindo em múltiplas CPUs
  - o cada uma com sua própria memória privada e,





- Projetados para resolver exclusão mútua
- Problema com monitores, e também com semáforos é que
  - o eles foram projetados para solucionar o problema da exclusão mútua em uma ou mais CPUs
  - o Todas com acesso a uma memória comum
- Quando movemos para um sistema distribuído
  - o consistindo em múltiplas CPUs
  - o cada uma com sua própria memória privada e,
  - o conectada por uma rede de área local





- Projetados para resolver exclusão mútua
- Problema com monitores, e também com semáforos é que
  - eles foram projetados para solucionar o problema da exclusão mútua em uma ou mais CPUs
  - o Todas com acesso a uma memória comum
- Quando movemos para um sistema distribuído
  - o consistindo em múltiplas CPUs
  - o cada uma com sua própria memória privada e,
  - o conectada por uma rede de área local
- Semáforos e monitores são primitivas que se tornam inaplicáveis





- Projetados para resolver exclusão mútua
- Problema com monitores, e também com semáforos é que
  - eles foram projetados para solucionar o problema da exclusão mútua em uma ou mais CPUs
  - o Todas com acesso a uma memória comum
- Quando movemos para um sistema distribuído
  - o consistindo em múltiplas CPUs
  - o cada uma com sua própria memória privada e,
  - o conectada por uma rede de área local
- Semáforos e monitores são primitivas que se tornam inaplicáveis
- Os semáforos são de um nível baixo demais e os monitores não são utilizáveis, exceto em algumas poucas linguagens de programação











• Método de comunicação entre processos (troca de mensagens)







- Método de comunicação entre processos (troca de mensagens)
- Esse método de comunicação entre processos usa duas primitivas send / receive





- Método de comunicação entre processos (troca de mensagens)
- Esse método de comunicação entre processos usa duas primitivas send / receive
  - Chamadas de sistema como semáforos





- Método de comunicação entre processos (troca de mensagens)
- Esse método de comunicação entre processos usa duas primitivas send / receive
  - Chamadas de sistema como semáforos
  - Não são construções de linguagem como monitores





- Método de comunicação entre processos (troca de mensagens)
- Esse método de comunicação entre processos usa duas primitivas send / receive
  - Chamadas de sistema como semáforos
  - Não são construções de linguagem como monitores
- send(destino,&msg)





- Método de comunicação entre processos (troca de mensagens)
- Esse método de comunicação entre processos usa duas primitivas send / receive
  - Chamadas de sistema como semáforos
  - Não são construções de linguagem como monitores
- send(destino,&msg)
  - o Envia msg para destino





- Método de comunicação entre processos (troca de mensagens)
- Esse método de comunicação entre processos usa duas primitivas send / receive
  - Chamadas de sistema como semáforos
  - Não são construções de linguagem como monitores
- send(destino,&msg)
  - o Envia msg para destino
- receive(fonte,&msg)





- Método de comunicação entre processos (troca de mensagens)
- Esse método de comunicação entre processos usa duas primitivas send / receive
  - Chamadas de sistema como semáforos
  - Não são construções de linguagem como monitores
- send(destino,&msg)
  - o Envia msg para destino
- receive(fonte,&msg)
  - o Recebe *msg* de *fonte*





- Método de comunicação entre processos (troca de mensagens)
- Esse método de comunicação entre processos usa duas primitivas send / receive
  - Chamadas de sistema como semáforos
  - Não são construções de linguagem como monitores
- send(destino,&msg)
  - o Envia msg para destino
- receive(fonte,&msg)
  - o Recebe msg de fonte
  - o Caso não existam mensagens recebidas receptor bloqueia











 Sistemas de troca de mensagens têm muitos problemas e questões de projeto que não surgem com semáforos ou com monitores







- Sistemas de troca de mensagens têm muitos problemas e questões de projeto que não surgem com semáforos ou com monitores
- Mensagens enviadas que não chegam





- Sistemas de troca de mensagens têm muitos problemas e questões de projeto que não surgem com semáforos ou com monitores
- Mensagens enviadas que não chegam
  - Perda de pacotes na rede





- Sistemas de troca de mensagens têm muitos problemas e questões de projeto que não surgem com semáforos ou com monitores
- Mensagens enviadas que não chegam
  - Perda de pacotes na rede
  - o Confirmação de recebimento (acknowledgment)





- Sistemas de troca de mensagens têm muitos problemas e questões de projeto que não surgem com semáforos ou com monitores
- Mensagens enviadas que não chegam
  - Perda de pacotes na rede
  - o Confirmação de recebimento (acknowledgment)
  - Retransmissão





- Sistemas de troca de mensagens têm muitos problemas e questões de projeto que não surgem com semáforos ou com monitores
- Mensagens enviadas que não chegam
  - Perda de pacotes na rede
  - Confirmação de recebimento (acknowledgment)
  - Retransmissão
- Confirmação que não chega





- Sistemas de troca de mensagens têm muitos problemas e questões de projeto que não surgem com semáforos ou com monitores
- Mensagens enviadas que não chegam
  - Perda de pacotes na rede
  - Confirmação de recebimento (acknowledgment)
  - Retransmissão
- Confirmação que não chega
  - Múltiplas recepções da mesma informação





- Sistemas de troca de mensagens têm muitos problemas e questões de projeto que não surgem com semáforos ou com monitores
- Mensagens enviadas que não chegam
  - Perda de pacotes na rede
  - Confirmação de recebimento (acknowledgment)
  - Retransmissão
- Confirmação que não chega
  - Múltiplas recepções da mesma informação
  - Distinção entre multiplas transmissões





- Sistemas de troca de mensagens têm muitos problemas e questões de projeto que não surgem com semáforos ou com monitores
- Mensagens enviadas que não chegam
  - o Perda de pacotes na rede
  - Confirmação de recebimento (acknowledgment)
  - Retransmissão
- Confirmação que não chega
  - Múltiplas recepções da mesma informação
  - Distinção entre multiplas transmissões
  - o Contador de transmissão





- Sistemas de troca de mensagens têm muitos problemas e questões de projeto que não surgem com semáforos ou com monitores
- Mensagens enviadas que não chegam
  - Perda de pacotes na rede
  - Confirmação de recebimento (acknowledgment)
  - Retransmissão
- Confirmação que não chega
  - Múltiplas recepções da mesma informação
  - Distinção entre multiplas transmissões
  - Contador de transmissão
- Ambiguidade entre múltiplos destinos/fontes





- Sistemas de troca de mensagens têm muitos problemas e questões de projeto que não surgem com semáforos ou com monitores
- Mensagens enviadas que não chegam
  - Perda de pacotes na rede
  - o Confirmação de recebimento (acknowledgment)
  - Retransmissão
- Confirmação que não chega
  - Múltiplas recepções da mesma informação
  - Distinção entre multiplas transmissões
  - Contador de transmissão
- Ambiguidade entre múltiplos destinos/fontes
  - o Autenticação





# Troca de mensagens

- Sistemas de troca de mensagens têm muitos problemas e questões de projeto que não surgem com semáforos ou com monitores
- Mensagens enviadas que não chegam
  - o Perda de pacotes na rede
  - o Confirmação de recebimento (acknowledgment)
  - Retransmissão
- Confirmação que não chega
  - Múltiplas recepções da mesma informação
  - Distinção entre multiplas transmissões
  - Contador de transmissão
- Ambiguidade entre múltiplos destinos/fontes
  - Autenticação
- Menos eficiente que semáforos/monitores











 Grupos de processos – em vez de situações que envolvem dois processos do tipo produtor-consumidor





- Grupos de processos em vez de situações que envolvem dois processos do tipo produtor-consumidor
- Algumas aplicações são divididas em fases







- Grupos de processos em vez de situações que envolvem dois processos do tipo produtor-consumidor
- Algumas aplicações são divididas em fases
  - Passagem apenas quando todos processos prontos





- Grupos de processos em vez de situações que envolvem dois processos do tipo produtor-consumidor
- Algumas aplicações são divididas em fases
  - o Passagem apenas quando todos processos prontos
- Tal comportamento pode ser conseguido colocando uma barreira (barrier) no fim de cada fase.





- Grupos de processos em vez de situações que envolvem dois processos do tipo produtor-consumidor
- Algumas aplicações são divididas em fases
  - Passagem apenas quando todos processos prontos
- Tal comportamento pode ser conseguido colocando uma barreira (barrier) no fim de cada fase.
- Quando um processo atinge a barreira, ele é bloqueado até que todos os processos tenham atingido a barreira.





- Grupos de processos em vez de situações que envolvem dois processos do tipo produtor-consumidor
- Algumas aplicações são divididas em fases
  - o Passagem apenas quando todos processos prontos
- Tal comportamento pode ser conseguido colocando uma barreira (barrier) no fim de cada fase.
- Quando um processo atinge a barreira, ele é bloqueado até que todos os processos tenham atingido a barreira.
- Isso **permite** que grupos de processos **sincronizem**.





- Grupos de processos em vez de situações que envolvem dois processos do tipo produtor-consumidor
- Algumas aplicações são divididas em fases
  - Passagem apenas quando todos processos prontos
- Tal comportamento pode ser conseguido colocando uma barreira (barrier) no fim de cada fase.
- Quando um processo atinge a barreira, ele é bloqueado até que todos os processos tenham atingido a barreira.
- Isso **permite** que grupos de processos **sincronizem**.
- Exemplo:





- Grupos de processos em vez de situações que envolvem dois processos do tipo produtor-consumidor
- Algumas aplicações são divididas em fases
  - Passagem apenas quando todos processos prontos
- Tal comportamento pode ser conseguido colocando uma barreira (barrier) no fim de cada fase.
- Quando um processo atinge a barreira, ele é bloqueado até que todos os processos tenham atingido a barreira.
- Isso **permite** que grupos de processos **sincronizem**.
- Exemplo:
  - $\circ \ \ \mathsf{Matriz} \to \mathsf{Temperaturas} \ \mathsf{em} \ \mathsf{placa} \ \mathsf{de} \ \mathsf{metal}$





- Grupos de processos em vez de situações que envolvem dois processos do tipo produtor-consumidor
- Algumas aplicações são divididas em fases
  - o Passagem apenas quando todos processos prontos
- Tal comportamento pode ser conseguido colocando uma barreira (barrier) no fim de cada fase.
- Quando um processo atinge a barreira, ele é bloqueado até que todos os processos tenham atingido a barreira.
- Isso permite que grupos de processos sincronizem.
- Exemplo:
  - $\circ$  Matriz  $\to$  Temperaturas em placa de metal
  - o Cálculo do efeito de uma fonte de calor pontual





- Grupos de processos em vez de situações que envolvem dois processos do tipo produtor-consumidor
- Algumas aplicações são divididas em fases
  - o Passagem apenas quando todos processos prontos
- Tal comportamento pode ser conseguido colocando uma barreira (barrier) no fim de cada fase.
- Quando um processo atinge a barreira, ele é bloqueado até que todos os processos tenham atingido a barreira.
- Isso permite que grupos de processos sincronizem.
- Exemplo:
  - $\circ$  Matriz  $\to$  Temperaturas em placa de metal
  - o Cálculo do efeito de uma fonte de calor pontual
  - $\circ$  Leis da termondinâmica  $\rightarrow$  Evolução da matriz a cada instante n





- Grupos de processos em vez de situações que envolvem dois processos do tipo produtor-consumidor
- Algumas aplicações são divididas em fases
  - Passagem apenas quando todos processos prontos
- Tal comportamento pode ser conseguido colocando uma barreira (barrier) no fim de cada fase.
- Quando um processo atinge a barreira, ele é bloqueado até que todos os processos tenham atingido a barreira.
- Isso permite que grupos de processos sincronizem.
- Exemplo:
  - $\circ$  Matriz  $\rightarrow$  Temperaturas em placa de metal
  - o Cálculo do efeito de uma fonte de calor pontual
  - o Leis da termondinâmica  $\rightarrow$  Evolução da matriz a cada instante n
  - $\circ$  Matriz muito grande  $\to$  Processamento paralelo





- Grupos de processos em vez de situações que envolvem dois processos do tipo produtor-consumidor
- Algumas aplicações são divididas em fases
  - o Passagem apenas quando todos processos prontos
- Tal comportamento pode ser conseguido colocando uma barreira (barrier) no fim de cada fase.
- Quando um processo atinge a barreira, ele é bloqueado até que todos os processos tenham atingido a barreira.
- Isso permite que grupos de processos sincronizem.
- Exemplo:
  - $\circ \ \mathsf{Matriz} \to \mathsf{Temperaturas} \ \mathsf{em} \ \mathsf{placa} \ \mathsf{de} \ \mathsf{metal}$
  - o Cálculo do efeito de uma fonte de calor pontual
  - $\circ$  Leis da termondinâmica  $\rightarrow$  Evolução da matriz a cada instante n
  - $\circ$  Matriz muito grande  $\to$  Processamento paralelo
  - $\circ$  Início do cálculo em n depende o resultado em n-1





