



# **CYBERSECURITY FOUNDATION V2**

**Lab 4: Configuring Authentication** 

Document Version: 2022-12-22

Copyright © 2022 Network Development Group, Inc. www.netdevgroup.com

NETLAB+ is a registered trademark of Network Development Group, Inc.

Palo Alto Networks and the Palo Alto Networks logo are trademarks or registered trademarks of Palo Alto Networks, Inc.



# **Contents**

Introduc	ction	3
	/e	
	ology	
•	ings	
	nfiguring Authentication	
	Load Lab Configuration	
	Configure a Local User Account and Authentication Profile	
1.2	_	
	Create an Authentication Policy	
	Commit and Test Authentication Policy	



### Introduction

In this lab, you will configure the Firewall to use a Captive Portal to authenticate users by using a local user account and Authentication Policy.


## **Objective**

In this lab, you will perform the following tasks:

- Configure a Local User Account and Authentication Profile
- Enable the Captive Portal and Enable Web-Form based Logins
- Create an Authentication Policy
- Commit and Test Authentication Policy



# **Lab Topology**





# **Lab Settings**

The information in the table below will be needed in order to complete the lab. The task sections below provide details on the use of this information.

Virtual Machine	IP Address	Account (if needed)	Password (if needed)
Client	192.168.1.20	lab-user	Pal0Alt0!
DMZ	192.168.50.10	root	Pal0Alt0!
Firewall	192.168.1.254	admin	Pal0Alt0!



## 1 Configuring Authentication

## 1.0 Load Lab Configuration

In this section, you will load the Firewall configuration file.

1. Click on the Client tab to access the Client PC.




- 2. Log in to the Client PC as username lab-user, password Pal0Alt0!.
- 3. Double-click the **Chromium Web Browser** icon located on the Desktop.



4. In the *Chromium* address field, type https://192.168.1.254 and press **Enter**.



5. You will see a "Your connection is not private" message. Click on the **ADVANCED** link.






If you experience the "Unable to connect" or "502 Bad Gateway" message while attempting to connect to the specified IP above, please wait an additional 1-3 minutes for the Firewall to fully initialize. Refresh the page to continue.



6. Click on Proceed to 192.168.1.254 (unsafe).




7. Log in to the Firewall web interface as username admin, password PalOAltO!.







 In the web interface, navigate to Device > Setup > Operations and click on Load named configuration snapshot underneath the Configuration Management section.



9. In the *Load Named Configuration* window, select **pan-cf-lab-04.xml** from the *Name* dropdown box and click **OK**.




10. In the Loading Configuration window, a message will show *Configuration is being loaded*. *Please check the Task Manager for its status. You should reload the page when the task is completed*. Click **Close** to continue.






11. Click the **Tasks** icon located at the bottom-right of the web interface.



12. In the *Task Manager – All Tasks* window, verify the *Load* type has successfully completed. Click **Close.** 




13. Click the **Commit** link located at the top-right of the web interface.






14. In the Commit window, click Commit to proceed with committing the changes.



15. When the commit operation successfully completes, click **Close** to continue.








The commit process takes changes made to the Firewall and copies them to the running configuration, which will activate all configuration changes since the last commit.

### 1.1 Configure a Local User Account and Authentication Profile


In this section, you will configure a local user account. Then, you will create a local authentication profile, which will later be assigned to a security policy.

1. Navigate to **Network > Zones**, and click on the **inside** zone.





2. In the *Zone* window, click the **Enable User Identification** checkbox under the *User Identification ACL*. Then, click the **OK** button.







This will enable the inside zone to use a Username for authentication.



3. Navigate to **Device > Local User Database > Users > Add**. You may need to scroll down on the left pane.




4. In the *Local User* window, type lab-web in the *Name* field. Then, type Pal0Alt0 in the *Password* and *Confirm Password* fields. Finally, click the **OK** button.






5. Navigate to **Device > Authentication Profile > Add**. You may need to scroll up on the left pane.




6. In the *Authentication Profile* window, type Local-Auth-Profile in the *Name* field. Then, select **Local Database** from the *Type* dropdown.






7. In the *Authentication Profile* window, click on the **Advanced** tab. Then, click on the **Add** button. Next, select **all** from the dropdown in the *Allow List* column. Finally, click the **OK** button.



### 1.2 Enable the Authentication Portal and Enable Web-Form based Logins

In this section, you will enable a captive portal. In that captive portal, you will use a webform for login.

1. Navigate to **Device > User Identification > Authentication Portal Settings**, and click on the **gear** icon.








Authentication Portal may also be identified as Captive Portal, which was the name used in versions prior to PAN-OS 10.


2. In the *Authentication Portal* window, click the **Enable Authentication Portal** checkbox. Then, select **Local-Auth-Profile** from the *Authentication Profile* dropdown. Finally, click the **OK** button.






This will turn on the Authentication Portal for web-form logins and associate it with the **Local-Auth-Profile** you created earlier.

3. Navigate to **Objects > Authentication**. You may need to scroll down on the left pane.







4. Click the checkbox beside the **default-web-form** and click **Clone**.



5. In the Clone window, click the **OK** button to confirm the clone.




6. You will notice a new entry named default-web-form-1 has been created; click on **default-web-form-1**.





7. In the Authentication Enforcement window, type local-web-form-auth in the Name field. Then, select Local-Auth-Profile in the Authentication Profile dropdown. Next, click the **OK** button.






## 1.3 Create an Authentication Policy


In this section, you will enable a captive portal. A captive portal redirects web requests that match the authentication policy and forces the user to use a login to continue. This is typically seen in corporate guest networks, hotels, and Wi-Fi hotspots. In this captive portal, you will use a web-form for login.

1. Navigate to Policies > Authentication > Add.






2. In the *Authentication Policy Rule* window, type web-form-policy in the *Name* field




3. In the *Authentication Policy Rule* window, click on the **Source** tab. Then, click the **Add** button in the *Source Zone* section. Next, select **inside**.






4. In the *Authentication Policy Rule* window, click on the **Destination** tab. Then, click the **Add** button in the *Destination Zone* section. Next, select **outside**.




5. In the *Authentication Policy Rule* window, click on the **Service/URL Category** tab. Then, click on the **Add** button in the *Service* section. Next, select **service-https**.






6. In the *Authentication Policy Rule* window, click on the **Actions** tab. Then, select **local-web-form-auth** from the *Authentication Enforcement* dropdown. Then, click the **OK** button.



## 1.4 Commit and Test Authentication Policy


In this section, you will commit your changes and test the authentication policy with the captive portal.

1. Click the **Commit** link located at the top-right of the web interface.






2. In the Commit window, click Commit to proceed with committing the changes.



3. When the commit operation successfully completes, click **Close** to continue.



4. Open a second **Chromium Web Browser** from the taskbar.






5. In the Chromium address field, type http://www.facebook.com and press Enter.



6. You will see a "Your connection is not private" message. Click on the ADVANCED Link, and then click Proceed to www.facebook.com (unsafe).







You are seeing this error because the Firewall is intercepting traffic coming from the inside zone to the outside zone. The Firewall serves as a man-in-the-middle until authenticated.



7. You will see a web-form login, type lab-web as the username. Then, type PalOAltO as the password. Finally, click the Login button.



8. You will then see Facebook after you successfully authenticate to the Firewall as lab-web.






again, or open a new tab in Chromium and enter http://www.facebook.com in the address bar, then press **Enter**.



9. Click the **X** in the upper-right to close **Chromium**.



- 10. Navigate to Monitor > Logs > Traffic.
- 11. In the logs, you will see that the entries to **facebook-base** are associated with the **lab-web** user. You may need to manually refresh logs or check additional pages at the bottom.



12. The lab is now complete; you may end the reservation.