



Developer Guide

Amazon API Gateway



Amazon API Gateway: Developer Guide

Copyright © 2026 Amazon Web Services, Inc. and/or its affiliates. All rights reserved.

Amazon's trademarks and trade dress may not be used in connection with any product or service that is not Amazon's, in any manner that is likely to cause confusion among customers, or in any manner that disparages or discredits Amazon. All other trademarks not owned by Amazon are the property of their respective owners, who may or may not be affiliated with, connected to, or sponsored by Amazon.

Table of Contents

What is Amazon API Gateway?	1
Architecture of API Gateway	2
Features of API Gateway	2
API Gateway use cases	3
Use API Gateway to create REST APIs	3
Use API Gateway to create HTTP APIs	4
Use API Gateway to create WebSocket APIs	5
Who uses API Gateway?	5
Accessing API Gateway	6
Part of AWS serverless infrastructure	7
How to get started with Amazon API Gateway	7
API Gateway concepts	7
Choose between REST APIs and HTTP APIs	13
Endpoint type	13
Security	14
Authorization	14
API management	15
Development	16
Monitoring	17
Integrations	17
Get started with the REST API console	18
Step 1: Create a Lambda function	19
Step 2: Create a REST API	20
Step 3: Create a Lambda proxy integration	20
Step 4: Deploy your API	21
Step 5: Invoke your API	21
(Optional) Step 6: Clean up	22
Prerequisites	24
Sign up for an AWS account	24
Create a user with administrative access	24
Get started	26
Step 1: Create a Lambda function	27
Step 2: Create an HTTP API	27
Step 3: Test your API	28

(Optional) Step 4: Clean up	29
Next steps	30
Tutorials and workshops	32
REST API tutorials	33
Choose a Lambda integration tutorial	33
Tutorial: Create a REST API by importing an example	57
Choose an HTTP integration tutorial	67
Tutorial: Create a REST API with a private integration	81
Tutorial: Create a REST API with an AWS integration	87
Tutorial: Create a calculator REST API with three integrations	93
Tutorial: Create a REST API as an Amazon S3 proxy	120
Tutorial: Create a REST API as an Amazon Kinesis proxy	164
Tutorial: Create a REST API using AWS SDKs or the AWS CLI	209
Tutorial: Create a private REST API	243
HTTP API tutorials	249
Tutorial: Build a CRUD HTTP API with Lambda and DynamoDB	249
Tutorial: Create an HTTP API with a private integration to Amazon ECS	262
WebSocket API tutorials	269
Tutorial: Create a WebSocket chat app	269
Tutorial: Create a WebSocket API with an AWS integration	274
API Gateway REST APIs	288
Develop	288
Example resource for a REST API	289
Additional REST API features for development	292
API Gateway endpoint types	294
Security policies	298
IP address types for REST APIs in API Gateway	316
Methods	318
Access control	337
Integrations	423
Request validation	513
Data transformations	543
Gateway responses	624
CORS	635
Binary media types	649
Invoke	680

OpenAPI	713
Publish	727
Deploy REST APIs	728
Custom domain names	773
Optimize	842
Cache settings	842
Content encoding	855
Distribute	861
Usage plans	861
API documentation	888
SDK generation	951
Sell your APIs as SaaS	979
Protect	983
Mutual TLS	984
Client certificates	991
AWS WAF	1031
Throttling	1034
Private REST APIs	1037
Monitor	1093
CloudWatch metrics	1094
CloudWatch logs	1102
Firehose	1107
Variables for access logging for API Gateway	1109
X-Ray	1122
API Gateway portals	1136
Considerations	1136
Portal product	1137
Pet adoption portal product example	1137
Next steps	1139
Create a portal product	1139
Create a product REST endpoint	1141
Create a product page	1143
Update a portal product	1145
Update a product REST endpoint	1145
Update product page	1146
Share portal products	1146

Enable try it for a product REST endpoint in your portal	1152
Delete a portal product	1153
Create a portal	1154
Choose a domain name	1154
Create a portal	1155
Update a portal	1157
Update a portal	1157
Preview a portal	1157
Considerations	1158
Preview a portal	1158
Publish a portal	1158
Considerations	1158
Publish a portal	1158
Use a portal	1159
Use a portal	1159
Troubleshoot your portal	1160
Disable a portal	1161
Disable a portal	1161
Delete a portal	1161
Delete a portal	1161
API Gateway HTTP APIs	1163
Develop	1163
Creating an HTTP API	1164
Routes	1165
IP address types for HTTP APIs in API Gateway	1168
Access control	1170
Integrations	1189
CORS	1207
Parameter mapping	1210
OpenAPI	1217
Publish	1227
Stages	1228
Security policy for HTTP APIs in API Gateway	1230
Custom domain names	1233
Protect	1242
Throttling	1242

Mutual TLS	1243
Monitor	1250
Metrics	1250
Logging	1253
Troubleshooting	1263
Lambda integrations	1263
JWT authorizers	1266
API Gateway WebSocket APIs	1268
Overview of WebSocket APIs	1268
Use routes for a WebSocket API	1269
Send data to connected client apps	1270
WebSocket API status codes	1270
Manage connected users and client apps	1271
Invoke your backend integration	1274
WebSocket selection expressions	1278
Develop	1286
Create and configure	1287
IP address types for WebSocket APIs in API Gateway	1288
Routes	1290
Access control	1298
Integrations	1307
Request validation	1316
Data transformations	1319
Binary media types	1331
Invoke	1331
Publish	1334
Stages	1335
Deploy a WebSocket API	1337
Security policy for WebSocket APIs in API Gateway	1340
Custom domain names	1342
Protect	1350
Account-level throttling per Region	1350
Route-level throttling	1351
Monitor	1351
Metrics	1352
Logging	1354

API Gateway ARNs	1362
HTTP API and WebSocket API resources	1362
REST API resources	1365
Domain names resources	1369
execute-api (HTTP APIs, WebSocket APIs, and REST APIs)	1370
OpenAPI extensions	1371
x-amazon-apigateway-any-method	1372
x-amazon-apigateway-any-method examples	1373
x-amazon-apigateway-cors	1374
x-amazon-apigateway-cors example	1374
x-amazon-apigateway-api-key-source	1375
x-amazon-apigateway-api-key-source example	1376
x-amazon-apigateway-auth	1377
x-amazon-apigateway-auth example	1377
x-amazon-apigateway-authorizer	1378
x-amazon-apigateway-authorizer examples for REST APIs	1381
x-amazon-apigateway-authorizer examples for HTTP APIs	1385
x-amazon-apigateway-authtype	1387
x-amazon-apigateway-authtype example	1387
See also	1389
x-amazon-apigateway-binary-media-type	1389
x-amazon-apigateway-binary-media-types example	1389
x-amazon-apigateway-documentation	1389
x-amazon-apigateway-documentation example	1390
x-amazon-apigateway-endpoint-access-mode	1391
x-amazon-apigateway-endpoint-access-mode example	1391
x-amazon-apigateway-endpoint-configuration	1391
x-amazon-apigateway-endpoint-configuration examples	1392
x-amazon-apigateway-gateway-responses	1392
x-amazon-apigateway-gateway-responses example	1393
x-amazon-apigateway-gateway-responses.gatewayResponse	1393
x-amazon-apigateway-gateway-responses.gatewayResponse example	1394
x-amazon-apigateway-gateway-responses.responseParameters	1395
x-amazon-apigateway-gateway-responses.responseParameters example	1395
x-amazon-apigateway-gateway-responses.responseTemplates	1395
x-amazon-apigateway-gateway-responses.responseTemplates example	1396

x-amazon-apigateway-importexport-version	1396
x-amazon-apigateway-importexport-version example	1396
x-amazon-apigateway-integration	1397
x-amazon-apigateway-integration examples	1404
x-amazon-apigateway-integrations	1406
x-amazon-apigateway-integrations example	1406
x-amazon-apigateway-integration.requestTemplates	1408
x-amazon-apigateway-integration.requestTemplates example	1408
x-amazon-apigateway-integration.requestParameters	1409
x-amazon-apigateway-integration.requestParameters example	1410
x-amazon-apigateway-integration.responses	1410
x-amazon-apigateway-integration.responses example	1412
x-amazon-apigateway-integration.response	1412
x-amazon-apigateway-integration.response example	1414
x-amazon-apigateway-integration.responseTemplates	1414
x-amazon-apigateway-integration.responseTemplate example	1415
x-amazon-apigateway-integration.responseParameters	1415
x-amazon-apigateway-integration.responseParameters example	1416
x-amazon-apigateway-integration.tlsConfig	1416
x-amazon-apigateway-integration.tlsConfig examples	1418
x-amazon-apigateway-minimum-compression-size	1419
x-amazon-apigateway-minimum-compression-size example	1419
x-amazon-apigateway-policy	1419
x-amazon-apigateway-policy example	1419
x-amazon-apigateway-request-validator	1420
x-amazon-apigateway-request-validator example	1420
x-amazon-apigateway-requestValidators	1421
x-amazon-apigateway-requestValidators example	1422
x-amazon-apigateway-requestValidators.requestValidator	1422
x-amazon-apigateway-requestValidators.requestValidator example	1423
x-amazon-apigateway-security-policy	1423
x-amazon-apigateway-security-policy example	1423
x-amazon-apigateway-tag-value	1424
x-amazon-apigateway-tag-value example	1424
Security	1425
Data protection	1426

Data encryption	1427
Internetwork traffic privacy	1429
Identity and access management	1429
Audience	1430
Authenticating with identities	1430
Managing access using policies	1431
How Amazon API Gateway works with IAM	1433
Identity-based policy examples	1438
Resource-based policy examples	1449
Troubleshooting	1450
Using service-linked roles	1451
Logging and monitoring	1456
Working with CloudTrail	1458
Working with AWS Config	1461
Compliance validation	1464
Resilience	1464
Infrastructure security	1465
Configuration and vulnerability analysis	1466
Best practices	1466
Tagging	1468
API Gateway resources that can be tagged	1468
Tag inheritance in the Amazon API Gateway V1 API	1470
Tag restrictions and usage conventions	1471
Attribute-based access control	1471
Limit actions based on resource tags	1472
Allow actions based on resource tags	1473
Deny tagging operations	1474
Allow tagging operations	1475
API references	1476
API Gateway service endpoints	1476
IPv4 endpoints	1476
Dualstack (IPv4 and IPv6) endpoints	1477
Specifying endpoints	1477
Using IPv6 addresses in IAM policies	1478
Quotas and important notes	1480
API Gateway account-level quotas, per Region	1480

API Gateway quotas for creating, deploying and managing an API	1481
REST API quotas	1484
Best practices to reduce your quotas	1490
HTTP API quotas	1492
Best practices to reduce your quotas	1494
Portal quotas	1495
WebSocket API quotas	1496
Important notes	1498
Amazon API Gateway important notes for HTTP APIs	1498
Amazon API Gateway important notes for HTTP and WebSocket APIs	1499
Important notes for REST APIs and WebSocket APIs	1499
Important notes for WebSocket APIs	1499
Important notes for REST APIs	1499
Document history	1506
Earlier updates	1518

What is Amazon API Gateway?

Amazon API Gateway is an AWS service for creating, publishing, maintaining, monitoring, and securing REST, HTTP, and WebSocket APIs at any scale. API developers can create APIs that access AWS or other web services, as well as data stored in the [AWS Cloud](#). As an API Gateway API developer, you can create APIs for use in your own client applications. Or you can make your APIs available to third-party app developers. For more information, see [the section called "Who uses API Gateway?"](#).

API Gateway creates RESTful APIs that:

- Are HTTP-based.
- Enable stateless client-server communication.
- Implement standard HTTP methods such as GET, POST, PUT, PATCH, and DELETE.

For more information about API Gateway REST APIs and HTTP APIs, see [the section called "Choose between REST APIs and HTTP APIs"](#), [API Gateway HTTP APIs](#), [the section called "Use API Gateway to create REST APIs"](#), and [the section called "Develop"](#).

API Gateway creates WebSocket APIs that:

- Adhere to the [WebSocket](#) protocol, which enables stateful, full-duplex communication between client and server.
- Route incoming messages based on message content.

For more information about API Gateway WebSocket APIs, see [the section called "Use API Gateway to create WebSocket APIs"](#) and [the section called "Overview of WebSocket APIs"](#).


Topics

- [Architecture of API Gateway](#)
- [Features of API Gateway](#)
- [API Gateway use cases](#)
- [Accessing API Gateway](#)
- [Part of AWS serverless infrastructure](#)
- [How to get started with Amazon API Gateway](#)

- [Amazon API Gateway concepts](#)
- [Choose between REST APIs and HTTP APIs](#)
- [Get started with the REST API console](#)

Architecture of API Gateway

The following diagram shows API Gateway architecture.



This diagram illustrates how the APIs you build in Amazon API Gateway provide you or your developer customers with an integrated and consistent developer experience for building AWS serverless applications. API Gateway handles all the tasks involved in accepting and processing up to hundreds of thousands of concurrent API calls. These tasks include traffic management, authorization and access control, monitoring, and API version management.

API Gateway acts as a "front door" for applications to access data, business logic, or functionality from your backend services, such as workloads running on Amazon Elastic Compute Cloud (Amazon EC2), code running on AWS Lambda, any web application, or real-time communication applications.

Features of API Gateway

Amazon API Gateway offers features such as the following:

- Support for stateful ([WebSocket](#)) and stateless ([HTTP](#) and [REST](#)) APIs.
- Powerful, flexible [authentication](#) mechanisms, such as AWS Identity and Access Management policies, Lambda authorizer functions, and Amazon Cognito user pools.
- [Canary release deployments](#) for safely rolling out changes.
- [CloudTrail](#) logging and monitoring of API usage and API changes.
- CloudWatch access logging and execution logging, including the ability to set alarms. For more information, see [the section called “CloudWatch metrics”](#) and [the section called “Metrics”](#).
- Ability to use CloudFormation templates to enable API creation. For more information, see [Amazon API Gateway Resource Types Reference](#) and [Amazon API Gateway V2 Resource Types Reference](#).
- Support for [custom domain names](#).
- Integration with [AWS WAF](#) for protecting your APIs against common web exploits.
- Integration with [AWS X-Ray](#) for understanding and triaging performance latencies.

For a complete list of API Gateway feature releases, see [Document history](#).

API Gateway use cases

The following use cases section presents an overview of the different types of API Gateway APIs and the different kinds of developers who use API Gateway. For more detailed information about the difference between REST APIs and HTTP APIs, see [the section called “Choose between REST APIs and HTTP APIs”](#).

Topics

- [Use API Gateway to create REST APIs](#)
- [Use API Gateway to create HTTP APIs](#)
- [Use API Gateway to create WebSocket APIs](#)
- [Who uses API Gateway?](#)

Use API Gateway to create REST APIs

An API Gateway REST API is made up of resources and methods. A resource is a logical entity that an app can access through a resource path. A method corresponds to a REST API request that is submitted by the user of your API and the response returned to the user.

For example, `/incomes` could be the path of a resource representing the income of the app user. A resource can have one or more operations that are defined by appropriate HTTP verbs such as GET, POST, PUT, PATCH, and DELETE. A combination of a resource path and an operation identifies a method of the API. For example, a POST `/incomes` method could add an income earned by the caller, and a GET `/expenses` method could query the reported expenses incurred by the caller.

The app doesn't need to know where the requested data is stored and fetched from on the backend. In API Gateway REST APIs, the frontend is encapsulated by *method requests* and *method responses*. The API interfaces with the backend by means of *integration requests* and *integration responses*.

For example, with DynamoDB as the backend, the API developer sets up the integration request to forward the incoming method request to the chosen backend. The setup includes specifications of an appropriate DynamoDB action, required IAM role and policies, and required input data transformation. The backend returns the result to API Gateway as an integration response.

To route the integration response to an appropriate method response (of a given HTTP status code) to the client, you can configure the integration response to map required response parameters from integration to method. You then translate the output data format of the backend to that of the frontend, if necessary. API Gateway enables you to define a schema or model for the [payload](#) to facilitate setting up the body mapping template.

API Gateway provides REST API management functionality such as the following:

- Support for generating SDKs and creating API documentation using API Gateway extensions to OpenAPI
- Throttling of HTTP requests

Use API Gateway to create HTTP APIs

HTTP APIs enable you to create RESTful APIs with lower latency and lower cost than REST APIs.

You can use HTTP APIs to send requests to AWS Lambda functions or to any publicly routable HTTP endpoint.

For example, you can create an HTTP API that integrates with a Lambda function on the backend. When a client calls your API, API Gateway sends the request to the Lambda function and returns the function's response to the client.

HTTP APIs support [OpenID Connect](#) and [OAuth 2.0](#) authorization. They come with built-in support for cross-origin resource sharing (CORS) and automatic deployments.

To learn more, see [the section called “Choose between REST APIs and HTTP APIs”](#).

Use API Gateway to create WebSocket APIs

In a WebSocket API, the client and the server can both send messages to each other at any time. Backend servers can easily push data to connected users and devices, avoiding the need to implement complex polling mechanisms.

For example, you could build a serverless application using an API Gateway WebSocket API and AWS Lambda to send and receive messages to and from individual users or groups of users in a chat room. Or you could invoke backend services such as AWS Lambda, Amazon Kinesis, or an HTTP endpoint based on message content.

You can use API Gateway WebSocket APIs to build secure, real-time communication applications without having to provision or manage any servers to manage connections or large-scale data exchanges. Targeted use cases include real-time applications such as the following:

- Chat applications
- Real-time dashboards such as stock tickers
- Real-time alerts and notifications

API Gateway provides WebSocket API management functionality such as the following:

- Monitoring and throttling of connections and messages
- Using AWS X-Ray to trace messages as they travel through the APIs to backend services
- Easy integration with HTTP/HTTPS endpoints

Who uses API Gateway?

There are two kinds of developers who use API Gateway: API developers and app developers.

An API developer creates and deploys an API to enable the required functionality in API Gateway. The API developer must be a user in the AWS account that owns the API.

An app developer builds a functioning application to call AWS services by invoking a WebSocket or REST API created by an API developer in API Gateway.

The app developer is the customer of the API developer. The app developer doesn't need to have an AWS account, provided that the API either doesn't require IAM permissions or supports authorization of users through third-party federated identity providers supported by [Amazon Cognito user pool identity federation](#). Such identity providers include Amazon, Amazon Cognito user pools, Facebook, and Google.

Creating and managing an API Gateway API

An API developer works with the API Gateway service component for API management, named `apigateway`, to create, configure, and deploy an API.

As an API developer, you can create and manage an API by using the API Gateway console, described in [Get started with API Gateway](#), or by calling the [API references](#). There are several ways to call this API. They include using the AWS Command Line Interface (AWS CLI), or by using an AWS SDK. In addition, you can enable API creation with [AWS CloudFormation templates](#) or (in the case of REST APIs and HTTP APIs) [OpenAPI extensions for API Gateway](#).

For a list of Regions where API Gateway is available, as well as the associated control service endpoints, see [Amazon API Gateway Endpoints and Quotas](#).

Calling an API Gateway API

An app developer works with the API Gateway service component for API execution, named `execute-api`, to invoke an API that was created or deployed in API Gateway. The underlying programming entities are exposed by the created API. There are several ways to call such an API. To learn more, see [Invoke REST APIs in API Gateway](#) and [Invoke WebSocket APIs](#).

Accessing API Gateway

You can access Amazon API Gateway in the following ways:

- **AWS Management Console** – The AWS Management Console provides a web interface for creating and managing APIs. After you complete the steps in [Prerequisites](#), you can access the API Gateway console at <https://console.aws.amazon.com/apigateway>.
- **AWS SDKs** – If you're using a programming language that AWS provides an SDK for, you can use an SDK to access API Gateway. SDKs simplify authentication, integrate easily with your development environment, and provide access to API Gateway commands. For more information, see [Tools for Amazon Web Services](#).

- **API Gateway V1 and V2 APIs** – If you're using a programming language that an SDK isn't available for, see the [Amazon API Gateway Version 1 API Reference](#) and [Amazon API Gateway Version 2 API Reference](#).
- **AWS Command Line Interface** – For more information, see [Getting Set Up with the AWS Command Line Interface](#) in the *AWS Command Line Interface User Guide*.
- **AWS Tools for Windows PowerShell** – For more information, see [Setting Up the AWS Tools for Windows PowerShell](#) in the *AWS Tools for PowerShell User Guide*.

Part of AWS serverless infrastructure

Together with [AWS Lambda](#), API Gateway forms the app-facing part of the AWS serverless infrastructure. To learn more about getting started with serverless, see the [Serverless Developer Guide](#).

For an app to call publicly available AWS services, you can use Lambda to interact with required services and expose Lambda functions through API methods in API Gateway. AWS Lambda runs your code on a highly available computing infrastructure. It performs the necessary execution and administration of computing resources. To enable serverless applications, API Gateway supports [streamlined proxy integrations](#) with AWS Lambda and HTTP endpoints.

How to get started with Amazon API Gateway

For an introduction to Amazon API Gateway, see the following:

- [Get started](#), which provides a walkthrough for creating an HTTP API.
- [Serverless land](#), which provides instructional videos.
- [Happy Little API Shorts](#), which is a series of brief instructional videos.

Amazon API Gateway concepts

The following section describes introductory concepts for using API Gateway.

API Gateway

API Gateway is an AWS service that supports the following:

- Creating, deploying, and managing a [RESTful](#) application programming interface (API) to expose backend HTTP endpoints, AWS Lambda functions, or other AWS services.

- Creating, deploying, and managing a [WebSocket](#) API to expose AWS Lambda functions or other AWS services.
- Invoking exposed API methods through the frontend HTTP and WebSocket endpoints.

API Gateway REST API

A collection of HTTP resources and methods that are integrated with backend HTTP endpoints, Lambda functions, or other AWS services. You can deploy this collection in one or more stages. Typically, API resources are organized in a resource tree according to the application logic. Each API resource can expose one or more API methods that have unique HTTP verbs supported by API Gateway. For more information, see [the section called “Choose between REST APIs and HTTP APIs”](#).

API Gateway HTTP API

A collection of routes and methods that are integrated with backend HTTP endpoints or Lambda functions. You can deploy this collection in one or more stages. Each route can expose one or more API methods that have unique HTTP verbs supported by API Gateway. For more information, see [the section called “Choose between REST APIs and HTTP APIs”](#).

API Gateway WebSocket API

A collection of WebSocket routes and route keys that are integrated with backend HTTP endpoints, Lambda functions, or other AWS services. You can deploy this collection in one or more stages. API methods are invoked through frontend WebSocket connections that you can associate with a registered custom domain name.

API deployment

A point-in-time snapshot of your API Gateway API. To be available for clients to use, the deployment must be associated with one or more API stages.

API developer

Your AWS account that owns an API Gateway deployment (for example, a service provider that also supports programmatic access).

API endpoint

A hostname for an API in API Gateway that is deployed to a specific Region. The hostname is of the form `{api-id}.execute-api.{region}.amazonaws.com`. The following types of API endpoints are supported:

- [Edge-optimized API endpoint](#)

- [Private API endpoint](#)
- [Regional API endpoint](#)

API key

An alphanumeric string that API Gateway uses to identify an app developer who uses your REST or WebSocket API. API Gateway can generate API keys on your behalf, or you can import them from a CSV file. You can use API keys together with [Lambda authorizers](#) or [usage plans](#) to control access to your APIs.

See [API endpoints](#).

API owner

See [API developer](#).

API stage

A logical reference to a lifecycle state of your API (for example, 'dev', 'prod', 'beta', 'v2'). API stages are identified by API ID and stage name.

App developer

An app creator who may or may not have an AWS account and interacts with the API that you, the API developer, have deployed. App developers are your customers. An app developer is typically identified by an [API key](#).

Callback URL

When a new client is connected to through a WebSocket connection, you can call an integration in API Gateway to store the client's callback URL. You can then use that callback URL to send messages to the client from the backend system.

Developer portal

An application where API providers can share their APIs and API documentation to API consumers. APIs are grouped into products, which are a collection of REST API endpoints, API documentation, and supplemental product documentation.

See [API Gateway portals](#).

Edge-optimized API endpoint

The default hostname of an API Gateway API that is deployed to the specified Region while using a CloudFront distribution to facilitate client access typically from across AWS Regions. API

requests are routed to the nearest CloudFront Point of Presence (POP), which typically improves connection time for geographically diverse clients.

See [API endpoints](#).

Integration request

The internal interface of a WebSocket API route or REST API method in API Gateway, in which you map the body of a route request or the parameters and body of a method request to the formats required by the backend.

Integration response

The internal interface of a WebSocket API route or REST API method in API Gateway, in which you map the status codes, headers, and payload that are received from the backend to the response format that is returned to a client app.

Mapping template

A script in [Velocity Template Language \(VTL\)](#) that transforms a request body from the frontend data format to the backend data format, or that transforms a response body from the backend data format to the frontend data format. Mapping templates can be specified in the integration request or in the integration response. They can reference data made available at runtime as context and stage variables.

The mapping can be as simple as an [identity transform](#) that passes the headers or body through the integration as-is from the client to the backend for a request. The same is true for a response, in which the payload is passed from the backend to the client.

Method request

The public interface of an API method in API Gateway that defines the parameters and body that an app developer must send in requests to access the backend through the API.

Method response

The public interface of a REST API that defines the status codes, headers, and body models that an app developer should expect in responses from the API.

Mock integration

In a mock integration, API responses are generated from API Gateway directly, without the need for an integration backend. As an API developer, you decide how API Gateway responds to a mock integration request. For this, you configure the method's integration request and integration response to associate a response with a given status code.

Model

A data schema specifying the data structure of a request or response payload. A model is required for generating a strongly typed SDK of an API. It is also used to validate payloads. A model is convenient for generating a sample mapping template to initiate creation of a production mapping template. Although useful, a model is not required for creating a mapping template.

Portal

See [Developer portal](#).

Portal Product

A service or functionality that you want to share. Your portal product is a collection of product REST endpoints and product pages. Product REST endpoints are the access points to your portal product, and they consist of the path and method of a REST API and the stage it's deployed to. Product pages are documentation that you provide to explain how API consumers can use your product endpoints. You can share products across AWS accounts to add them to portals.

See [Create a product](#).

Private API

See [Private API endpoint](#).

Private API endpoint

An API endpoint that is exposed through interface VPC endpoints and allows a client to securely access private API resources inside a VPC. Private APIs are isolated from the public internet, and they can only be accessed using VPC endpoints for API Gateway that have been granted access.

Private integration

An API Gateway integration type for a client to access resources inside a customer's VPC through a private REST API endpoint without exposing the resources to the public internet.

Proxy integration

A simplified API Gateway integration configuration. You can set up a proxy integration as an HTTP proxy integration or a Lambda proxy integration.

For HTTP proxy integration, API Gateway passes the entire request and response between the frontend and an HTTP backend. For Lambda proxy integration, API Gateway sends the entire

request as input to a backend Lambda function. API Gateway then transforms the Lambda function output to a frontend HTTP response.

In REST APIs, proxy integration is most commonly used with a proxy resource, which is represented by a greedy path variable (for example, {proxy+}) combined with a catch-all ANY method.

Quick create

You can use quick create to simplify creating an HTTP API. Quick create creates an API with a Lambda or HTTP integration, a default catch-all route, and a default stage that is configured to automatically deploy changes. For more information, see [the section called “Create an HTTP API by using the AWS CLI”](#).

Regional API endpoint

The host name of an API that is deployed to the specified Region and intended to serve clients, such as EC2 instances, in the same AWS Region. API requests are targeted directly to the Region-specific API Gateway API without going through any CloudFront distribution. For in-Region requests, a Regional endpoint bypasses the unnecessary round trip to a CloudFront distribution.

In addition, you can apply [latency-based routing](#) on Regional endpoints to deploy an API to multiple Regions using the same Regional API endpoint configuration, set the same custom domain name for each deployed API, and configure latency-based DNS records in Route 53 to route client requests to the Region that has the lowest latency.

See [API endpoints](#).

Route

A WebSocket route in API Gateway is used to direct incoming messages to a specific integration, such as an AWS Lambda function, based on the content of the message. When you define your WebSocket API, you specify a route key and an integration backend. The route key is an attribute in the message body. When the route key is matched in an incoming message, the integration backend is invoked.

A default route can also be set for non-matching route keys or to specify a proxy model that passes the message through as-is to backend components that perform the routing and process the request.

Route request

The public interface of a WebSocket API method in API Gateway that defines the body that an app developer must send in the requests to access the backend through the API.

Route response

The public interface of a WebSocket API that defines the status codes, headers, and body models that an app developer should expect from API Gateway.

Usage plan

A [usage plan](#) provides selected API clients with access to one or more deployed REST or WebSocket APIs. You can use a usage plan to configure throttling and quota limits, which are enforced on individual client API keys.

WebSocket connection

API Gateway maintains a persistent connection between clients and API Gateway itself. There is no persistent connection between API Gateway and backend integrations such as Lambda functions. Backend services are invoked as needed, based on the content of messages received from clients.

Choose between REST APIs and HTTP APIs

REST APIs and HTTP APIs are both RESTful API products. REST APIs support more features than HTTP APIs, while HTTP APIs are designed with minimal features so that they can be offered at a lower price. Choose REST APIs if you need features such as API keys, per-client throttling, request validation, AWS WAF integration, or private API endpoints. Choose HTTP APIs if you don't need the features included with REST APIs.

The following sections summarize core features that are available in REST APIs and HTTP APIs. When necessary, additional links are provided to navigate between the REST API and HTTP API sections of the API Gateway Developer Guide.

Endpoint type

The endpoint type refers to the endpoint that API Gateway creates for your API. For more information, see [the section called “API Gateway endpoint types”](#).

Endpoint types	REST API	HTTP API
<u>Edge-optimized</u>	Yes	No
<u>Regional</u>	Yes	Yes
<u>Private</u>	Yes	No

Security

API Gateway provides a number of ways to protect your API from certain threats, like malicious actors or spikes in traffic. To learn more, see [the section called “Protect”](#) and [the section called “Protect”](#).

Security features	REST API	HTTP API
<u>Mutual TLS authentication</u>	<u>Yes</u>	<u>Yes</u>
<u>Certificates for backend authentication</u>	Yes	No
<u>AWS WAF</u>	Yes	No

Authorization

API Gateway supports multiple mechanisms for controlling and managing access to your API. For more information, see [the section called “Access control”](#) and [the section called “Access control”](#).

Authorization options	REST API	HTTP API
IAM	Yes	Yes
Resource policies	Yes	No
Amazon Cognito	Yes	Yes ¹
Custom authorization with an AWS Lambda function	Yes	Yes
JSON Web Token (JWT) ²	No	Yes

¹ You can use Amazon Cognito with a [JWT authorizer](#).

² You can use a [Lambda authorizer](#) to validate JWTs for REST APIs.

API management

Choose REST APIs if you need API management capabilities such as API keys and per-client rate limiting. For more information, see [the section called “Distribute”](#), [the section called “Custom domain names”](#), and [the section called “Custom domain names”](#).

Features	REST API	HTTP API
Custom domains	Yes	Yes
API keys	Yes	No
Per-client rate limiting	Yes	No

Features	REST API	HTTP API
Per-client usage throttling	Yes	No
Developer portal	Yes	No

Development

As you're developing your API Gateway API, you decide on a number of characteristics of your API. These characteristics depend on the use case of your API. For more information see [the section called "Develop"](#) and [the section called "Develop"](#).

Features	REST API	HTTP API
CORS configuration	Yes	Yes
Test invocations	Yes	No
Caching	Yes	No
User-controlled deployments	Yes	Yes
Automatic deployments	No	Yes
Custom gateway responses	Yes	No
Canary release deployments	Yes	No

Features	REST API	HTTP API
Request validation	Yes	No
Request parameter transformation	Yes	Yes
Request body transformation	Yes	No

Monitoring

API Gateway supports several options to log API requests and monitor your APIs. For more information, see [the section called “Monitor”](#) and [the section called “Monitor”](#).

Feature	REST API	HTTP API
Amazon CloudWatch metrics	Yes	Yes
Access logs to CloudWatch Logs	Yes	Yes
Access logs to Amazon Data Firehose	Yes	No
Execution logs	Yes	No
AWS X-Ray tracing	Yes	No

Integrations

Integrations connect your API Gateway API to backend resources. For more information, see [the section called “Integrations”](#) and [the section called “Integrations”](#).


Feature	REST API	HTTP API
<u>Public HTTP endpoints</u>	<u>Yes</u>	<u>Yes</u>
<u>AWS services</u>	<u>Yes</u>	<u>Yes</u>
<u>AWS Lambda functions</u>	<u>Yes</u>	<u>Yes</u>
<u>Private integrations with Network Load Balancers</u>	<u>Yes</u>	<u>Yes</u>
<u>Private integrations with Application Load Balancers</u>	<u>Yes</u>	Yes
<u>Private integrations with AWS Cloud Map</u>	No	Yes
<u>Mock integrations</u>	Yes	No
<u>Response streaming</u>	Yes	No

Get started with the REST API console

In this getting started exercise, you create a serverless REST API using the API Gateway REST API console. Serverless APIs let you focus on your applications instead of spending your time provisioning and managing servers. This exercise should take less than 20 minutes to complete, and is possible within the [AWS Free Tier](#).

First, you create a Lambda function using the Lambda console. Next, you create a REST API using the API Gateway REST API console. Then, you create an API method and integrate it with a Lambda function using a Lambda proxy integration. Finally, you deploy and invoke your API.

When you invoke your REST API, API Gateway routes the request to your Lambda function. Lambda runs the function and returns a response to API Gateway. API Gateway then returns that response to you.



To complete this exercise, you need an AWS account and an AWS Identity and Access Management (IAM) user with console access. For more information, see [Set up to use API Gateway](#).

Topics

- [Step 1: Create a Lambda function](#)
- [Step 2: Create a REST API](#)
- [Step 3: Create a Lambda proxy integration](#)
- [Step 4: Deploy your API](#)
- [Step 5: Invoke your API](#)
- [\(Optional\) Step 6: Clean up](#)

Step 1: Create a Lambda function

You use a Lambda function for the backend of your API. Lambda runs your code only when needed and scales automatically, from a few requests per day to thousands per second.

For this exercise, you use a default Node.js function in the Lambda console.

To create a Lambda function

1. Sign in to the Lambda console at <https://console.aws.amazon.com/lambda>.
2. Choose **Create function**.
3. Under **Basic information**, for **Function name**, enter **my-function**.
4. For all other options, use the default setting.
5. Choose **Create function**.

The default Lambda function code should look similar to the following:

```
export const handler = async (event) => {
  const response = {
    statusCode: 200,
    body: JSON.stringify('The API Gateway REST API console is great!'),
  };
  return response;
};
```

You can modify your Lambda function for this exercise, as long as the function's response aligns with the [format that API Gateway requires](#).

Replace the default response body (Hello from Lambda!) with The API Gateway REST API console is great!. When you invoke the example function, it returns a 200 response to clients, along with the updated response.

Step 2: Create a REST API

Next, you create a REST API with a root resource (/).

To create a REST API

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Do one of the following:
 - To create your first API, for **REST API**, choose **Build**.
 - If you've created an API before, choose **Create API**, and then choose **Build for REST API**.
3. For **API name**, enter **my-rest-api**.
4. (Optional) For **Description**, enter a description.
5. Keep **API endpoint type** set to **Regional**.
6. For **IP address type**, select **IPv4**.
7. Choose **Create API**.

Step 3: Create a Lambda proxy integration

Next, you create an API method for your REST API on the root resource (/) and integrate the method with your Lambda function using a proxy integration. In a Lambda proxy integration, API Gateway passes the incoming request from the client directly to the Lambda function.

To create a Lambda proxy integration

1. Select the / resource, and then choose **Create method**.
2. For **Method type**, select ANY.
3. For **Integration type**, select **Lambda**.
4. Turn on **Lambda proxy integration**.
5. For **Lambda function**, enter **my-function**, and then select your Lambda function.
6. Choose **Create method**.

Step 4: Deploy your API

Next, you create an API deployment and associate it with a stage.

To deploy your API

1. Choose **Deploy API**.
2. For **Stage**, select **New stage**.
3. For **Stage name**, enter **Prod**.
4. (Optional) For **Description**, enter a description.
5. Choose **Deploy**.

Now clients can call your API. To test your API before deploying it, you can optionally choose the **ANY** method, navigate to the **Test** tab, and then choose **Test**.

Step 5: Invoke your API

To invoke your API

1. From the main navigation pane, choose **Stage**.
2. Under **Stage details**, choose the copy icon to copy your API's invoke URL.

The screenshot shows the 'Stage details' section of the Lambda function configuration. It includes fields for Stage name (Prod), Rate (10000), Burst (5000), Web ACL (-), Client certificate (-), and Default method-level caching (-). Below this, the 'Invoke URL' is listed as <https://abcd123.execute-api.us-east-1.amazonaws.com/Prod>, which is highlighted with a red border. At the bottom, it shows an active deployment labeled 'efg456 on June 01, 2023, 15:00 (UTC-07:00)'.

3. Enter the invoke URL in a web browser.

The full URL should look like `https://abcd123.execute-api.us-east-2.amazonaws.com/Prod`.

Your browser sends a GET request to the API.

4. Verify your API's response. You should see the text "The API Gateway REST API console is great!" in your browser.

(Optional) Step 6: Clean up

To prevent accruing unnecessary costs to your AWS account, delete the resources that you created as part of this exercise. The following steps delete your REST API, your Lambda function, and the associated resources.

To delete your REST API

1. In the **Resources** pane, choose **API actions**, **Delete API**.
2. In the **Delete API** dialog box, enter **confirm**, and then choose **Delete**.

To delete your Lambda function

1. Sign in to the Lambda console at <https://console.aws.amazon.com/lambda>.
2. On the **Functions** page, select your function. Choose **Actions**, **Delete**.

3. In the **Delete 1 functions** dialog box, enter **delete**, and then choose **Delete**.

To delete your Lambda function's log group

1. Open the [Log groups page](#) of the Amazon CloudWatch console.
2. On the **Log groups** page, select your function's log group (/aws/lambda/my-function). Then, for **Actions**, choose **Delete log group(s)**.
3. In the **Delete log group(s)** dialog box, choose **Delete**.

To delete your Lambda function's execution role

1. Open the [Roles page](#) of the IAM console.
2. (Optional) On the **Roles** page, in the search box, enter **my-function**.
3. Select your function's role (for example, my-function-*31exmpl*), and then choose **Delete**.
4. In the **Delete my-function-*31exmpl*?** dialog box, enter the name of the role, and then choose **Delete**.

 **Tip**

You can automate the creation and cleanup of AWS resources by using AWS CloudFormation or AWS Serverless Application Model (AWS SAM). For some example CloudFormation templates, see the [example templates for API Gateway](#) in the **awsdocs** GitHub repository.

Set up to use API Gateway

Before you use Amazon API Gateway for the first time, complete the following tasks.

Sign up for an AWS account

If you do not have an AWS account, complete the following steps to create one.

To sign up for an AWS account

1. Open <https://portal.aws.amazon.com/billing/signup>.
2. Follow the online instructions.

Part of the sign-up procedure involves receiving a phone call or text message and entering a verification code on the phone keypad.

When you sign up for an AWS account, an *AWS account root user* is created. The root user has access to all AWS services and resources in the account. As a security best practice, assign administrative access to a user, and use only the root user to perform [tasks that require root user access](#).

AWS sends you a confirmation email after the sign-up process is complete. At any time, you can view your current account activity and manage your account by going to <https://aws.amazon.com/> and choosing **My Account**.

Create a user with administrative access

After you sign up for an AWS account, secure your AWS account root user, enable AWS IAM Identity Center, and create an administrative user so that you don't use the root user for everyday tasks.

Secure your AWS account root user

1. Sign in to the [AWS Management Console](#) as the account owner by choosing **Root user** and entering your AWS account email address. On the next page, enter your password.

For help signing in by using root user, see [Signing in as the root user](#) in the *AWS Sign-In User Guide*.

2. Turn on multi-factor authentication (MFA) for your root user.

For instructions, see [Enable a virtual MFA device for your AWS account root user \(console\)](#) in the *IAM User Guide*.

Create a user with administrative access

1. Enable IAM Identity Center.

For instructions, see [Enabling AWS IAM Identity Center](#) in the *AWS IAM Identity Center User Guide*.

2. In IAM Identity Center, grant administrative access to a user.

For a tutorial about using the IAM Identity Center directory as your identity source, see [Configure user access with the default IAM Identity Center directory](#) in the *AWS IAM Identity Center User Guide*.

Sign in as the user with administrative access

- To sign in with your IAM Identity Center user, use the sign-in URL that was sent to your email address when you created the IAM Identity Center user.

For help signing in using an IAM Identity Center user, see [Signing in to the AWS access portal](#) in the *AWS Sign-In User Guide*.

Assign access to additional users

1. In IAM Identity Center, create a permission set that follows the best practice of applying least-privilege permissions.

For instructions, see [Create a permission set](#) in the *AWS IAM Identity Center User Guide*.

2. Assign users to a group, and then assign single sign-on access to the group.

For instructions, see [Add groups](#) in the *AWS IAM Identity Center User Guide*.

Get started with API Gateway

In this getting started exercise, you create a serverless API. Serverless APIs let you focus on your applications, instead of spending time provisioning and managing servers. This exercise takes less than 20 minutes to complete, and is possible within the [AWS Free Tier](#).


First, you create a Lambda function using the AWS Lambda console. Next, you create an HTTP API using the API Gateway console. Then, you invoke your API.

Note

This exercise uses an HTTP API. API Gateway also supports REST APIs, which include more features. For a tutorial using a REST API, see [the section called “Get started with the REST API console”](#).

For more information about the difference between HTTP APIs and REST APIs, see [the section called “Choose between REST APIs and HTTP APIs”](#).

When you invoke your HTTP API, API Gateway routes the request to your Lambda function. Lambda runs the Lambda function and returns a response to API Gateway. API Gateway then returns a response to you.



To complete this exercise, you need an AWS account and an AWS Identity and Access Management user with console access. For more information, see [Prerequisites](#).

Topics

- [Step 1: Create a Lambda function](#)
- [Step 2: Create an HTTP API](#)
- [Step 3: Test your API](#)
- [\(Optional\) Step 4: Clean up](#)

- [Next steps](#)

Step 1: Create a Lambda function

You use a Lambda function for the backend of your API. Lambda runs your code only when needed and scales automatically, from a few requests per day to thousands per second.

For this example, you use the default Node.js function from the Lambda console.

To create a Lambda function

1. Sign in to the Lambda console at <https://console.aws.amazon.com/lambda>.
2. Choose **Create function**.
3. For **Function name**, enter **my-function**.
4. For all other options, use the default setting.
5. Choose **Create function**.

The example function returns a 200 response to clients, and the text Hello from Lambda!.

You can modify your Lambda function, as long as the function's response aligns with the [format that API Gateway requires](#).

The default Lambda function code should look similar to the following:

```
export const handler = async (event) => {
  const response = {
    statusCode: 200,
    body: JSON.stringify('Hello from Lambda!'),
  };
  return response;
};
```

Step 2: Create an HTTP API

Next, you create an HTTP API. API Gateway also supports REST APIs and WebSocket APIs, but an HTTP API is the best choice for this exercise. REST APIs support more features than HTTP APIs, but we don't need those features for this exercise. HTTP APIs are designed with minimal features so

that they can be offered at a lower price. WebSocket APIs maintain persistent connections with clients for full-duplex communication, which isn't required for this example.

The HTTP API provides an HTTP endpoint for your Lambda function. API Gateway routes requests to your Lambda function, and then returns the function's response to clients.

To create an HTTP API

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Do one of the following:
 - To create your first API, for **HTTP API**, choose **Build**.
 - If you've created an API before, choose **Create API**, and then choose **Build** for **HTTP API**.
3. For **Integrations**, choose **Add integration**.
4. Choose **Lambda**.
5. For **Lambda function**, enter **my-function**.
6. For **API name**, enter **my-http-api**.
7. Choose **Next**.
8. Review the *route* that API Gateway creates for you, and then choose **Next**.
9. Review the *stage* that API Gateway creates for you, and then choose **Next**.
10. Choose **Create**.

Now you've created an HTTP API with a Lambda integration that's ready to receive requests from clients.

Step 3: Test your API

Next, you test your API to make sure that it's working. For simplicity, use a web browser to invoke your API.

To test your API

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose your API.
3. Note your API's invoke URL.

my-http-api

Stage: - ▾

Deploy

API details

Edit

API ID
abcd1234**Protocol**
HTTP**Created**
2023-10-30**Description**
My first HTTP API**Default endpoint**
 Enabled**ARN**<https://abcd1234.execute-api.us-west-1.amazonaws.com>[arn:aws:apigateway:us-west-1::apis/abcd1234](#)

Stages for my-http-api (1)

 Find resources

Stage name	Invoke URL	Attached deployment	Auto deploy	Last updated
\$default	https://abcd1234.execute-api.us-west-1.amazonaws.com	aaa111	enabled	2023-10-30

4. Copy your API's invoke URL, and enter it in a web browser. Append the name of your Lambda function to your invoke URL to call your Lambda function. By default, the API Gateway console creates a route with the same name as your Lambda function, *my-function*.

The full URL should look like `https://abcdef123.execute-api.us-east-2.amazonaws.com/my-function`.

Your browser sends a GET request to the API.

5. Verify your API's response. You should see the text "Hello from Lambda!" in your browser.

(Optional) Step 4: Clean up

To prevent unnecessary costs, delete the resources that you created as part of this getting started exercise. The following steps delete your HTTP API, your Lambda function, and associated resources.

To delete an HTTP API

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. On the APIs page, select an API. Choose **Actions**, and then choose **Delete**.
3. Choose **Delete**.

To delete a Lambda function

1. Sign in to the Lambda console at <https://console.aws.amazon.com/lambda>.
2. On the **Functions** page, select a function. Choose **Actions**, and then choose **Delete**.
3. Choose **Delete**.

To delete a Lambda function's log group

1. In the Amazon CloudWatch console, open the [Log groups page](#).
2. On the **Log groups** page, select the function's log group (/aws/lambda/my-function). Choose **Actions**, and then choose **Delete log group**.
3. Choose **Delete**.

To delete a Lambda function's execution role

1. In the AWS Identity and Access Management console, open the [Roles page](#).
2. Select the function's role, for example, my-function-*31exmpl*.
3. Choose **Delete role**.
4. Choose **Yes, delete**.

You can automate the creation and cleanup of AWS resources by using CloudFormation or AWS SAM. For example CloudFormation templates, see [example CloudFormation templates](#).

Next steps

For this example, you used the AWS Management Console to create a simple HTTP API. The HTTP API invokes a Lambda function and returns a response to clients.

The following are next steps as you continue to work with API Gateway.

- [Configure additional types of API integrations](#), including:
 - [HTTP endpoints](#)
 - [Private resources in a VPC, such as Amazon ECS services](#)
 - [AWS services such as Amazon Simple Queue Service, AWS Step Functions, and Kinesis Data Streams](#)

- [Control access to your APIs](#)
- [Enable logging for your APIs](#)
- [Configure throttling for your APIs](#)
- [Configure custom domains for your APIs](#)

To get help with Amazon API Gateway from the community, see the [API Gateway Discussion Forum](#). When you enter this forum, AWS might require you to sign in.

To get help with API Gateway directly from AWS, see the support options on the [AWS Support page](#).

See also our [frequently asked questions \(FAQs\)](#), or [contact us directly](#).

Amazon API Gateway tutorials and workshops

The following tutorials and workshops provide hands-on exercises to help you learn about API Gateway. To get started, we recommend that you complete [the section called “Tutorial: Create a REST API with a Lambda proxy integration”](#).

REST API tutorials

- [Choose an AWS Lambda integration tutorial](#)
- [Tutorial: Create a REST API by importing an example](#)
- [Choose an HTTP integration tutorial](#)
- [Tutorial: Create a REST API with a private integration](#)
- [Tutorial: Create a REST API with an AWS integration](#)
- [Tutorial: Create a calculator REST API with two AWS service integrations and one Lambda non-proxy integration](#)
- [Tutorial: Create a REST API as an Amazon S3 proxy](#)
- [Tutorial: Create a REST API as an Amazon Kinesis proxy](#)
- [Tutorial: Create a REST API using AWS SDKs or the AWS CLI](#)
- [Tutorial: Create a private REST API](#)

HTTP API tutorials

- [Tutorial: Create a CRUD HTTP API with Lambda and DynamoDB](#)
- [Tutorial: Create an HTTP API with a private integration to an Amazon ECS service](#)

WebSocket API tutorials

- [Tutorial: Create a WebSocket chat app with a WebSocket API, Lambda and DynamoDB](#)

Workshops

- [Build a serverless web application](#)
- [CI/CD for serverless applications](#)
- [Serverless security workshop](#)

- [Serverless identity management, authentication and authorization](#)
- [The Amazon API Gateway Workshop](#)

Amazon API Gateway REST API tutorials

The following tutorials provide hands-on exercises to help you learn about API Gateway REST APIs.

Topics

- [Choose an AWS Lambda integration tutorial](#)
- [Tutorial: Create a REST API by importing an example](#)
- [Choose an HTTP integration tutorial](#)
- [Tutorial: Create a REST API with a private integration](#)
- [Tutorial: Create a REST API with an AWS integration](#)
- [Tutorial: Create a calculator REST API with two AWS service integrations and one Lambda non-proxy integration](#)
- [Tutorial: Create a REST API as an Amazon S3 proxy](#)
- [Tutorial: Create a REST API as an Amazon Kinesis proxy](#)
- [Tutorial: Create a REST API using AWS SDKs or the AWS CLI](#)
- [Tutorial: Create a private REST API](#)

Choose an AWS Lambda integration tutorial

To build an API with Lambda integrations, you can use Lambda proxy integration or Lambda non-proxy integration.

In Lambda proxy integration, the input to the Lambda function can be expressed as any combination of request headers, path variables, query string parameters, body, and API configuration data. You only need to choose a Lambda function. API Gateway configures the integration request and integration response for you. Once set up, your API method can evolve without modifying the existing settings. This is possible because the backend Lambda function parses the incoming request data and responds to the client.

In Lambda non-proxy integration, you must ensure that input to the Lambda function is supplied as the integration request payload. You must map any input data the client supplied as request

parameters into the proper integration request body. You might also need to translate the client-supplied request body into a format recognized by the Lambda function.

In either a Lambda proxy or a Lambda non-proxy integration, you can use a Lambda function in a different account from the account where you created your API.

Topics

- [Tutorial: Create a REST API with a Lambda proxy integration](#)
- [Tutorial: Create a REST API with a Lambda non-proxy integration](#)
- [Tutorial: Create a REST API with a cross-account Lambda proxy integration](#)

Tutorial: Create a REST API with a Lambda proxy integration

[Lambda proxy integration](#) is a lightweight, flexible API Gateway API integration type that allows you to integrate an API method – or an entire API – with a Lambda function. The Lambda function can be written in [any language that Lambda supports](#). Because it's a proxy integration, you can change the Lambda function implementation at any time without needing to redeploy your API.

In this tutorial, you do the following:

- Create a "Hello, World!" Lambda function to be the backend for the API.
- Create and test a "Hello, World!" API with Lambda proxy integration.

Topics

- [Create a "Hello, World!" Lambda function](#)
- [Create a "Hello, World!" API](#)
- [Deploy and test the API](#)

Create a "Hello, World!" Lambda function

To create a "Hello, World!" Lambda function in the Lambda console

1. Sign in to the Lambda console at <https://console.aws.amazon.com/lambda>.
2. On the AWS navigation bar, choose an [AWS Region](#).

Note

Note the region where you create the Lambda function. You'll need it when you create the API.

3. Choose **Functions** in the navigation pane.
4. Choose **Create function**.
5. Choose **Author from scratch**.
6. Under **Basic information**, do the following:
 - a. In **Function name**, enter **GetStartedLambdaProxyIntegration**.
 - b. For **Runtime**, choose either the latest supported **Node.js** or **Python** runtime.
 - c. For **Architecture**, keep the default setting.
 - d. Under **Permissions**, expand **Change default execution role**. For **Execution role** dropdown list, choose **Create new role from AWS policy templates**.
 - e. In **Role name**, enter **GetStartedLambdaBasicExecutionRole**.
 - f. Leave the **Policy templates** field blank.
 - g. Choose **Create function**.
7. Under **Function code**, in the inline code editor, copy/paste the following code:

Node.js

```
export const handler = async(event, context) => {
    console.log('Received event:', JSON.stringify(event, null, 2));
    var res ={
        "statusCode": 200,
        "headers": {
            "Content-Type": "*/*"
        }
    };
    var greeter = 'World';
    if (event.greeter && event.greeter!=="") {
        greeter = event.greeter;
    } else if (event.body && event.body !== "") {
        var body = JSON.parse(event.body);
        if (body.greeter && body.greeter !== "") {
            greeter = body.greeter;
        }
    }
}
```

```
        }
    } else if (event.queryStringParameters &&
event.queryStringParameters.greeter && event.queryStringParameters.greeter !==
 "") {
    greeter = event.queryStringParameters.greeter;
} else if (event.multiValueHeaders && event.multiValueHeaders.greeter &&
event.multiValueHeaders.greeter != "") {
    greeter = event.multiValueHeaders.greeter.join(" and ");
} else if (event.headers && event.headers.greeter && event.headers.greeter !=
 "") {
    greeter = event.headers.greeter;
}
res.body = "Hello, " + greeter + "!";
return res
};
```

Python

```
import json


def lambda_handler(event, context):
    print(event)

    greeter = 'World'

    try:
        if (event['queryStringParameters']) and (event['queryStringParameters']
['greeter']) and (
            event['queryStringParameters']['greeter'] is not None):
            greeter = event['queryStringParameters']['greeter']
    except KeyError:
        print('No greeter')

    try:
        if (event['multiValueHeaders']) and (event['multiValueHeaders']
['greeter']) and (
            event['multiValueHeaders']['greeter'] is not None):
            greeter = " and ".join(event['multiValueHeaders']['greeter'])
    except KeyError:
        print('No greeter')

    try:
```

```
if (event['headers']) and (event['headers']['greeter']) and (
    event['headers']['greeter'] is not None):
    greeter = event['headers']['greeter']
except KeyError:
    print('No greeter')

if (event['body']) and (event['body'] is not None):
    body = json.loads(event['body'])
    try:
        if (body['greeter']) and (body['greeter'] is not None):
            greeter = body['greeter']
    except KeyError:
        print('No greeter')

res = {
    "statusCode": 200,
    "headers": {
        "Content-Type": "*/*"
    },
    "body": "Hello, " + greeter + "!"
}

return res
```

8. Choose Deploy.

Create a "Hello, World!" API

Now create an API for your "Hello, World!" Lambda function by using the API Gateway console.

To create a "Hello, World!" API

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. If this is your first time using API Gateway, you see a page that introduces you to the features of the service. Under **REST API**, choose **Build**. When the **Create Example API** popup appears, choose **OK**.

If this is not your first time using API Gateway, choose **Create API**. Under **REST API**, choose **Build**.

3. For **API name**, enter **LambdaProxyAPI**.
4. (Optional) For **Description**, enter a description.

5. Keep **API endpoint type** set to **Regional**.
6. For **IP address type**, select **IPv4**.
7. Choose **Create API**.

After you create an API, you create a resource. Typically, API resources are organized in a resource tree according to the application logic. For this example, you create a **/helloworld** resource.

To create a resource

1. Choose **Create resource**.
2. Keep **Proxy resource** turned off.
3. Keep **Resource path** as **/**.
4. For **Resource name**, enter **helloworld**.
5. Keep **CORS (Cross Origin Resource Sharing)** turned off.
6. Choose **Create resource**.

In a proxy integration, the entire request is sent to the backend Lambda function as-is, via a catch-all ANY method that represents any HTTP method. The actual HTTP method is specified by the client at run time. The ANY method allows you to use a single API method setup for all of the supported HTTP methods: DELETE, GET, HEAD, OPTIONS, PATCH, POST, and PUT.

To create an ANY method

1. Select the **/helloworld** resource, and then choose **Create method**.
2. For **Method type**, select **ANY**.
3. For **Integration type**, select **Lambda function**.
4. Turn on **Lambda proxy integration**.
5. For **Lambda function**, select the AWS Region where you created your Lambda function, and then enter the function name.
6. To use the default timeout value of 29 seconds, keep **Default timeout** turned on. To set a custom timeout, choose **Default timeout** and enter a timeout value between 50 and 29000 milliseconds.
7. Choose **Create method**.

Deploy and test the API

To deploy your API

1. Choose **Deploy API**.
2. For **Stage**, select **New stage**.
3. For **Stage name**, enter **test**.
4. (Optional) For **Description**, enter a description.
5. Choose **Deploy**.
6. Under **Stage details**, choose the copy icon to copy your API's invoke URL.

Use browser and cURL to test an API with Lambda proxy integration

You can use a browser or [cURL](#) to test your API.

To test GET requests using only query string parameters, you can enter the URL for the API's helloworld resource into a browser address bar.

To create the URL for the API's helloworld resource, append the resource helloworld and the query string parameter ?greeter=John to your invoke URL. Your URL should look like the following.

```
https://r275xc9bmd.execute-api.us-east-1.amazonaws.com/test/helloworld?greeter=John
```

For other methods, you must use more advanced REST API testing utilities, such as [POSTMAN](#) or [cURL](#). This tutorial uses cURL. The cURL command examples below assume that cURL is installed on your computer.

To test your deployed API using cURL:

1. Open a terminal window.
2. Copy the following cURL command and paste it into the terminal window, and replace the invoke URL with the one you copied in the previous step and add /helloworld to the end of the URL.

 **Note**

If you're running the command on Windows, use this syntax instead:

```
curl -v -X POST "https://r275xc9bmd.execute-api.us-east-1.amazonaws.com/test/helloworld" -H "content-type: application/json" -d "{\"greeter\": \"John\" }"
```

- a. To call the API with the query string parameter of ?greeter=John:

```
curl -X GET 'https://r275xc9bmd.execute-api.us-east-1.amazonaws.com/test/helloworld?greeter=John'
```

- b. To call the API with a header parameter of greeter:John:

```
curl -X GET https://r275xc9bmd.execute-api.us-east-1.amazonaws.com/test/helloworld \
-H 'content-type: application/json' \
-H 'greeter: John'
```

- c. To call the API with a body of {"greeter":"John"}:

```
curl -X POST https://r275xc9bmd.execute-api.us-east-1.amazonaws.com/test/helloworld \
-H 'content-type: application/json' \
-d '{ \"greeter\": \"John\" }'
```

In all the cases, the output is a 200 response with the following response body:

```
Hello, John!
```

Tutorial: Create a REST API with a Lambda non-proxy integration

In this walkthrough, we use the API Gateway console to build an API that enables a client to call Lambda functions through the Lambda non-proxy integration (also known as custom integration). For more information about AWS Lambda and Lambda functions, see the [AWS Lambda Developer Guide](#).

To facilitate learning, we chose a simple Lambda function with minimal API setup to walk you through the steps of building an API Gateway API with the Lambda custom integration. When

necessary, we describe some of the logic. For a more detailed example of the Lambda custom integration, see [Tutorial: Create a calculator REST API with two AWS service integrations and one Lambda non-proxy integration](#).

Before creating the API, set up the Lambda backend by creating a Lambda function in AWS Lambda, described next.

Topics

- [Create a Lambda function for Lambda non-proxy integration](#)
- [Create an API with Lambda non-proxy integration](#)
- [Test invoking the API method](#)
- [Deploy the API](#)
- [Test the API in a deployment stage](#)
- [Clean up](#)

Create a Lambda function for Lambda non-proxy integration

Note

Creating Lambda functions may result in charges to your AWS account.

In this step, you create a "Hello, World!"-like Lambda function for the Lambda custom integration. Throughout this walkthrough, the function is called `GetStartedLambdaIntegration`.

The implementation of this `GetStartedLambdaIntegration` Lambda function is as follows:

Node.js

```
'use strict';
var days = ['Sunday', 'Monday', 'Tuesday', 'Wednesday', 'Thursday', 'Friday',
'Saturday'];
var times = ['morning', 'afternoon', 'evening', 'night', 'day'];

export const handler = async(event) => {
  console.log(event);
  // Parse the input for the name, city, time and day property values
  let name = event.name === null || event.name === undefined || event.name === "" ?
  'you' : event.name;
```

```
let city = event.city === undefined ? 'World' : event.city;
let time = times.indexOf(event.time)<0 ? 'day' : event.time;
let day = days.indexOf(event.day)<0 ? null : event.day;

// Generate a greeting
let greeting = 'Good ' + time + ', ' + name + ' of ' + city + '. ';
if (day) greeting += 'Happy ' + day + '!';

// Log the greeting to CloudWatch
console.log('Hello: ', greeting);

// Return a greeting to the caller
return {"greeting": greeting}
};
```

Python

```
import json

days = [
    'Sunday',
    'Monday',
    'Tuesday',
    'Wednesday',
    'Thursday',
    'Friday',
    'Saturday']
times = ['morning', 'afternoon', 'evening', 'night', 'day']

def lambda_handler(event, context):
    print(event)
    # parse the input for the name, city, time, and day property values
    name = event.get("name") or 'you'
    city = event.get("city") or 'World'
    try:
        if event['time'] in times:
            time = event['time']
        else:
            time = 'day'
    except KeyError:
        time = 'day'
    try:
```

```
if event['day'] in days:
    day = event['day']
else:
    day = ''
except KeyError:
    day = ''
# Generate a greeting
greeting = 'Good ' + time + ', ' + name + ' of ' + \
    city + '.' + ['', ' Happy ' + day + '!'][day != '']
# Log the greeting to CloudWatch
print(greeting)

# Return a greeting to the caller
return {"greeting": greeting}
```

For the Lambda custom integration, API Gateway passes the input to the Lambda function from the client as the integration request body. The event object of the Lambda function handler is the input.

Our Lambda function is simple. It parses the input event object for the name, city, time, and day properties. It then returns a greeting, as a JSON object of {"message":greeting}, to the caller. The message is in the "Good [morning|afternoon|day], [*name*|you] in [*city*] World]. Happy *day*!" pattern. It is assumed that the input to the Lambda function is of the following JSON object:

```
{
  "city": "...",
  "time": "...",
  "day": "...",
  "name" : "..."
}
```

For more information, see the [AWS Lambda Developer Guide](#).

In addition, the function logs its execution to Amazon CloudWatch by calling `console.log(...)`. This is helpful for tracing calls when debugging the function. To allow the `GetStartedLambdaIntegration` function to log the call, set an IAM role with appropriate policies for the Lambda function to create the CloudWatch streams and add log entries to the streams. The Lambda console guides you through to create the required IAM roles and policies.

If you set up the API without using the API Gateway console, such as when [importing an API from an OpenAPI file](#), you must explicitly create, if necessary, and set up an invocation role and policy for API Gateway to invoke the Lambda functions. For more information on how to set up Lambda invocation and execution roles for an API Gateway API, see [Control access to a REST API with IAM permissions](#).

Compared to `GetStartedLambdaProxyIntegration`, the Lambda function for the Lambda proxy integration, the `GetStartedLambdaIntegration` Lambda function for the Lambda custom integration only takes input from the API Gateway API integration request body. The function can return an output of any JSON object, a string, a number, a Boolean, or even a binary blob. The Lambda function for the Lambda proxy integration, in contrast, can take the input from any request data, but must return an output of a particular JSON object. The `GetStartedLambdaIntegration` function for the Lambda custom integration can have the API request parameters as input, provided that API Gateway maps the required API request parameters to the integration request body before forwarding the client request to the backend. For this to happen, the API developer must create a mapping template and configure it on the API method when creating the API.

Now, create the `GetStartedLambdaIntegration` Lambda function.

To create the `GetStartedLambdaIntegration` Lambda function for Lambda custom integration

1. Open the AWS Lambda console at <https://console.aws.amazon.com/lambda/>.
2. Do one of the following:
 - If the welcome page appears, choose **Get Started Now** and then choose **Create function**.
 - If the **Lambda > Functions** list page appears, choose **Create function**.
3. Choose **Author from scratch**.
4. In the **Author from scratch** pane, do the following:
 - a. For **Name**, enter **GetStartedLambdaIntegration** as the Lambda function name.
 - b. For **Runtime**, choose either the latest supported **Node.js** or **Python** runtime.
 - c. For **Architecture**, keep the default setting.
 - d. Under **Permissions**, expand **Change default execution role**. For **Execution role** dropdown list, choose **Create new role from AWS policy templates**.

- e. For **Role name**, enter a name for your role (for example, **GetStartedLambdaIntegrationRole**).
 - f. For **Policy templates**, choose **Simple microservice permissions**.
 - g. Choose **Create function**.
5. In the **Configure function** pane, under **Function code** do the following:
- a. Copy the Lambda function code listed in the beginning of this section and paste it in the inline code editor.
 - b. Leave the default choices for all other fields in this section.
 - c. Choose **Deploy**.
6. To test the newly created function, choose the **Test** tab.
- a. For **Event name**, enter **HelloWorldTest**.
 - b. For **Event JSON**, replace the default code with the following.

```
{  
  "name": "Jonny",  
  "city": "Seattle",  
  "time": "morning",  
  "day": "Wednesday"  
}
```

- c. Choose **Test** to invoke the function. The **Execution result: succeeded** section is shown. Expand **Details** and you see the following output.

```
{  
  "greeting": "Good morning, Jonny of Seattle. Happy Wednesday!"  
}
```

The output is also written to CloudWatch Logs.

As a side exercise, you can use the IAM console to view the IAM role (**GetStartedLambdaIntegrationRole**) that was created as part of the Lambda function creation. Attached to this IAM role are two inline policies. One stipulates the most basic permissions for Lambda execution. It permits calling the CloudWatch **CreateLogGroup** for any CloudWatch resources of your account in the region where the Lambda function is

created. This policy also allows creating the CloudWatch streams and logging events for the GetStartedLambdaIntegration Lambda function.

JSON

```
{  
    "Version": "2012-10-17",  
    "Statement": [  
        {  
            "Effect": "Allow",  
            "Action": "logs>CreateLogGroup",  
            "Resource": "arn:aws:logs:us-east-1:111111111111:*"  
        },  
        {  
            "Effect": "Allow",  
            "Action": [  
                "logs>CreateLogStream",  
                "logs>PutLogEvents"  
            ],  
            "Resource": [  
                "arn:aws:logs:us-east-1:111111111111:log-group:/aws/lambda/  
                GetStartedLambdaIntegration:<*"  
            ]  
        }  
    ]  
}
```

The other policy document applies to invoking another AWS service that is not used in this example. You can skip it for now.

Associated with the IAM role is a trusted entity, which is lambda.amazonaws.com. Here is the trust relationship:

JSON

```
{  
    "Version": "2012-10-17",  
    "Statement": [  
        {  
            "Effect": "Allow",  
            "Principal": "lambda.amazonaws.com",  
            "Action": "stsAssumeRole"  
        }  
    ]  
}
```

```
    "Principal": {  
        "Service": "lambda.amazonaws.com"  
    },  
    "Action": "sts:AssumeRole"  
}  
]  
}
```

The combination of this trust relationship and the inline policy makes it possible for the Lambda function to invoke a `console.log()` function to log events to CloudWatch Logs.

Create an API with Lambda non-proxy integration

With the Lambda function (`GetStartedLambdaIntegration`) created and tested, you are ready to expose the function through an API Gateway API. For illustration purposes, we expose the Lambda function with a generic HTTP method. We use the request body, a URL path variable, a query string, and a header to receive required input data from the client. We turn on the API Gateway request validator for the API to ensure that all of the required data is properly defined and specified. We configure a mapping template for API Gateway to transform the client-supplied request data into the valid format as required by the backend Lambda function.

To create an API with a Lambda non-proxy integration

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. If this is your first time using API Gateway, you see a page that introduces you to the features of the service. Under **REST API**, choose **Build**. When the **Create Example API** popup appears, choose **OK**.

If this is not your first time using API Gateway, choose **Create API**. Under **REST API**, choose **Build**.

3. For **API name**, enter **LambdaNonProxyAPI**.
4. (Optional) For **Description**, enter a description.
5. Keep **API endpoint type** set to **Regional**.
6. For **IP address type**, select **IPv4**.
7. Choose **Create API**.

After creating your API, you create a **/{city}** resource. This is an example of a resource with a path variable that takes an input from the client. Later, you map this path variable into the Lambda function input using a mapping template.

To create a resource

1. Choose **Create resource**.
2. Keep **Proxy resource** turned off.
3. Keep **Resource path** as **/**.
4. For **Resource name**, enter **{city}**.
5. Keep **CORS (Cross Origin Resource Sharing)** turned off.
6. Choose **Create resource**.

After creating your **/{city}** resource, you create an ANY method. The ANY HTTP verb is a placeholder for a valid HTTP method that a client submits at run time. This example shows that ANY method can be used for Lambda custom integration as well as for Lambda proxy integration.

To create an ANY method

1. Select the **/{city}** resource, and then choose **Create method**.
2. For **Method type**, select **ANY**.
3. For **Integration type**, select **Lambda function**.
4. Keep **Lambda proxy integration** turned off.
5. For **Lambda function**, select the AWS Region where you created your Lambda function, and then enter the function name.
6. Choose **Method request settings**.

Now, you turn on a request validator for a URL path variable, a query string parameter, and a header to ensure that all of the required data is defined. For this example, you create a time query string parameter and a day header.

7. For **Request validator**, select **Validate query string parameters and headers**.
8. Choose **URL query string parameters** and do the following:
 - a. Choose **Add query string**.
 - b. For **Name**, enter **time**.

- c. Turn on **Required**.
 - d. Keep **Caching** turned off.
9. Choose **HTTP request headers** and do the following:
- a. Choose **Add header**.
 - b. For **Name**, enter **day**.
 - c. Turn on **Required**.
 - d. Keep **Caching** turned off.
10. Choose **Create method**.

After turning on a request validator, you configure the integration request for the ANY method by adding a body-mapping template to transform the incoming request into a JSON payload, as required by the backend Lambda function.

To configure the integration request

1. On the **Integration request** tab, under the **Integration request settings**, choose **Edit**.
2. For **Request body passthrough**, select **When there are no templates defined (recommended)**.
3. Choose **Mapping templates**.
4. Choose **Add mapping template**.
5. For **Content type**, enter **application/json**.
6. For **Template body**, enter the following code:

```
#set($inputRoot = $input.path('$'))  
{  
    "city": "$input.params('city')",  
    "time": "$input.params('time')",  
    "day": "$input.params('day')",  
    "name": "$inputRoot.callerName"  
}
```

7. Choose **Save**.

Test invoking the API method

The API Gateway console provides a testing facility for you to test invoking the API before it is deployed. You use the Test feature of the console to test the API by submitting the following request:

```
POST /Seattle?time=morning
day:Wednesday

{
    "callerName": "John"
}
```

In this test request, you'll set ANY to POST, set {city} to Seattle, assign Wednesday as the day header value, and assign "John" as the callerName value.

To test the ANY method

1. Choose the **Test** tab. You might need to choose the right arrow button to show the tab.
2. For **Method type**, select POST.
3. For **Path**, under **city**, enter **Seattle**.
4. For **Query strings**, enter **time=morning**.
5. For **Headers**, enter **day:Wednesday**.
6. For **Request Body**, enter **{ "callerName": "John" }**.
7. Choose **Test**.

Verify that the returned response payload is as follows:

```
{
    "greeting": "Good morning, John of Seattle. Happy Wednesday!"
}
```

You can also view the logs to examine how API Gateway processes the request and response.

```
Execution log for request test-request
Thu Aug 31 01:07:25 UTC 2017 : Starting execution for request: test-invoke-request
Thu Aug 31 01:07:25 UTC 2017 : HTTP Method: POST, Resource Path: /Seattle
Thu Aug 31 01:07:25 UTC 2017 : Method request path: {city=Seattle}
Thu Aug 31 01:07:25 UTC 2017 : Method request query string: {time=morning}
```

```
Thu Aug 31 01:07:25 UTC 2017 : Method request headers: {day=Wednesday}
Thu Aug 31 01:07:25 UTC 2017 : Method request body before transformations:
{ "callerName": "John" }
Thu Aug 31 01:07:25 UTC 2017 : Request validation succeeded for content type
application/json
Thu Aug 31 01:07:25 UTC 2017 : Endpoint request URI: https://
lambda.us-west-2.amazonaws.com/2015-03-31/functions/arn:aws:lambda:us-
west-2:123456789012:function:GetStartedLambdaIntegration/invocations
Thu Aug 31 01:07:25 UTC 2017 : Endpoint request headers: {x-amzn-lambda-integration-
tag=test-request,
Authorization=*****,
X-Amz-Date=20170831T010725Z, x-amzn-apigateway-api-id=beags1mnid, X-Amz-
Source-Arn=arn:aws:execute-api:us-west-2:123456789012:beags1mnid/null/POST/
{city}, Accept=application/json, User-Agent=AmazonAPIGateway_beags1mnid,
X-Amz-Security-Token=FQoDYXdzELL//////////wEaDMHGzEdE0T/VvGhabiK3AzgKrJw
+3zLqJZG4Ph0q12K6W21+QotY2rrZy0zqhLoiuRg3CAYNQ2eqgL5D54+63ey9bIdtwHGoyBdq8ecWxJK/
YUnT2Rau0L9HCG5p7FC05h3Ivw1FfvcidQNxeYvsKJTLXI05/
yEnY3ttIAnpNYL0ezD9Es8rBfyruHfJf0qextKlsC8DymCcqlGkig8qLKcZ0hWJWVwiPJiFgL7laabXs+
+ZhCa4hdZo4iqlG729DE4gaV1mJVdoAagIUwLMo+y4NxFDu0r7I0/
E05nYcCrppGVVBViGk7H4T6sXuhTkbNNqVmXtV3ch5b0lh7 [TRUNCATED]
Thu Aug 31 01:07:25 UTC 2017 : Endpoint request body after transformations: {
  "city": "Seattle",
  "time": "morning",
  "day": "Wednesday",
  "name" : "John"
}
Thu Aug 31 01:07:25 UTC 2017 : Sending request to https://lambda.us-
west-2.amazonaws.com/2015-03-31/functions/arn:aws:lambda:us-
west-2:123456789012:function:GetStartedLambdaIntegration/invocations
Thu Aug 31 01:07:25 UTC 2017 : Received response. Integration latency: 328 ms
Thu Aug 31 01:07:25 UTC 2017 : Endpoint response body before transformations:
{"greeting":"Good morning, John of Seattle. Happy Wednesday!"}
Thu Aug 31 01:07:25 UTC 2017 : Endpoint response headers: {x-amzn-Remapped-Content-
Length=0, x-amzn-RequestId=c0475a28-8de8-11e7-8d3f-4183da788f0f, Connection=keep-
alive, Content-Length=62, Date=Thu, 31 Aug 2017 01:07:25 GMT, X-Amzn-Trace-
Id=root=1-59a7614d-373151b01b0713127e646635;sampled=0, Content-Type=application/json}
Thu Aug 31 01:07:25 UTC 2017 : Method response body after transformations:
{"greeting":"Good morning, John of Seattle. Happy Wednesday!"}
Thu Aug 31 01:07:25 UTC 2017 : Method response headers: {X-Amzn-Trace-
Id=sampled=0;root=1-59a7614d-373151b01b0713127e646635, Content-Type=application/json}
Thu Aug 31 01:07:25 UTC 2017 : Successfully completed execution
Thu Aug 31 01:07:25 UTC 2017 : Method completed with status: 200
```

The logs show the incoming request before the mapping and the integration request after the mapping. When a test fails, the logs are useful for evaluating whether the original input is correct or the mapping template works correctly.

Deploy the API

The test invocation is a simulation and has limitations. For example, it bypasses any authorization mechanism enacted on the API. To test the API execution in real time, you must deploy the API first. To deploy an API, you create a stage to create a snapshot of the API at that time. The stage name also defines the base path after the API's default host name. The API's root resource is appended after the stage name. When you modify the API, you must redeploy it to a new or existing stage before the changes take effect.

To deploy the API to a stage

1. Choose **Deploy API**.
2. For **Stage**, select **New stage**.
3. For **Stage name**, enter **test**.

 **Note**

The input must be UTF-8 encoded (i.e., unlocalized) text.

4. (Optional) For **Description**, enter a description.
5. Choose **Deploy**.

Under **Stage details**, choose the copy icon to copy your API's invoke URL. The general pattern of the API's base URL is `https://api-id.region.amazonaws.com/stageName`. For example, the base URL of the API (beags1mnid) created in the us-west-2 region and deployed to the test stage is `https://beags1mnid.execute-api.us-west-2.amazonaws.com/test`.

Test the API in a deployment stage

There are several ways you can test a deployed API. For GET requests using only URL path variables or query string parameters, you can enter the API resource URL in a browser. For other methods, you must use more advanced REST API testing utilities, such as [POSTMAN](#) or [cURL](#).

To test the API using cURL

1. Open a terminal window on your local computer connected to the internet.
2. To test POST /Seattle?time=evening:

Copy the following cURL command and paste it into the terminal window.

```
curl -v -X POST \
  'https://beags1mnid.execute-api.us-west-2.amazonaws.com/test/Seattle?
  time=evening' \
  -H 'content-type: application/json' \
  -H 'day: Thursday' \
  -H 'x-amz-docs-region: us-west-2' \
  -d '{
    "callerName": "John"
}'
```

You should get a successful response with the following payload:

```
{"greeting":"Good evening, John of Seattle. Happy Thursday!"}
```

If you change POST to PUT in this method request, you get the same response.

Clean up

If you no longer need the Lambda functions you created for this walkthrough, you can delete them now. You can also delete the accompanying IAM resources.

Warning

If you plan to complete the other walkthroughs in this series, do not delete the Lambda execution role or the Lambda invocation role. If you delete a Lambda function that your APIs rely on, those APIs will no longer work. Deleting a Lambda function cannot be undone.

If you want to use the Lambda function again, you must re-create the function.

If you delete an IAM resource that a Lambda function relies on, that Lambda function will no longer work, and any APIs that rely on that function will no longer work. Deleting an IAM resource cannot be undone. If you want to use the IAM resource again, you must re-create the resource.

To delete the Lambda function

1. Sign in to the AWS Management Console and open the AWS Lambda console at <https://console.aws.amazon.com/lambda/>.
2. From the list of functions, choose **GetStartedLambdaIntegration**, choose **Actions**, and then choose **Delete function**. When prompted, choose **Delete** again.

To delete the associated IAM resources

1. Open the IAM console at <https://console.aws.amazon.com/iam/>.
2. From **Details**, choose **Roles**.
3. From the list of roles, choose **GetStartedLambdaIntegrationRole**, choose **Role Actions**, and then choose **Delete Role**. Follow the steps in the console to delete the role.

Tutorial: Create a REST API with a cross-account Lambda proxy integration

You can now use an AWS Lambda function from a different AWS account as your API integration backend. Each account can be in any region where Amazon API Gateway is available. This makes it easy to centrally manage and share Lambda backend functions across multiple APIs.

In this section, we show how to configure cross-account Lambda proxy integration using the Amazon API Gateway console.

Create API for API Gateway cross-account Lambda integration

To create an API

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. If this is your first time using API Gateway, you see a page that introduces you to the features of the service. Under **REST API**, choose **Build**. When the **Create Example API** popup appears, choose **OK**.

If this is not your first time using API Gateway, choose **Create API**. Under **REST API**, choose **Build**.

3. For **API name**, enter **CrossAccountLambdaAPI**.
4. (Optional) For **Description**, enter a description.
5. Keep **API endpoint type** set to **Regional**.

6. For **IP address type**, select **IPv4**.
7. Choose **Create API**.

Create Lambda integration function in another account

Now you'll create a Lambda function in a different account from the one in which you created the example API.

Creating a Lambda function in another account

1. Log in to the Lambda console in a different account from the one where you created your API Gateway API.
2. Choose **Create function**.
3. Choose **Author from scratch**.
4. Under **Author from scratch**, do the following:
 - a. For **Function name**, enter a name.
 - b. From the **Runtime** drop-down list, choose a supported Node.js runtime.
 - c. For **Architecture**, keep the default setting.
 - d. Under **Permissions**, expand **Choose or create an execution role**. You can create a role or choose an existing role.
 - e. Choose **Create function** to continue.
5. Scroll down to the **Function code** pane.
6. Enter the Node.js function implementation from [the section called "Tutorial: Create a REST API with a Lambda proxy integration"](#).
7. Choose **Deploy**.
8. Note the full ARN for your function (in the upper right corner of the Lambda function pane). You'll need it when you create your cross-account Lambda integration.

Configure cross-account Lambda integration

Once you have a Lambda integration function in a different account, you can use the API Gateway console to add it to your API in your first account.

Note

If you are configuring a cross-region, cross-account authorizer, the `sourceArn` that is added to the target function should use the region of the function, not the region of the API.

After you create an API, you create a resource. Typically, API resources are organized in a resource tree according to the application logic. For this example, you create a `/helloworld` resource.

To create a resource

1. Choose **Create resource**.
2. Keep **Proxy resource** turned off.
3. Keep **Resource path** as `/`.
4. For **Resource name**, enter `helloworld`.
5. Keep **CORS (Cross Origin Resource Sharing)** turned off.
6. Choose **Create resource**.

After you create an resource, you create a GET method. You integrate the GET method with a Lambda function in another account.

To create a GET method

1. Select the `/helloworld` resource, and then choose **Create method**.
2. For **Method type**, select **GET**.
3. For **Integration type**, select **Lambda function**.
4. Turn on **Lambda proxy integration**.
5. For **Lambda function**, enter the full ARN of your Lambda function from Step 1.

In the Lambda console, you can find the ARN for your function in the upper right corner of the console window.

6. When you enter the ARN, a `aws lambda add-permission` command string will appear. This policy grants your first account access to your second account's Lambda function. Copy and paste the `aws lambda add-permission` command string into an AWS CLI window that is configured for your second account.

7. Choose **Create method**.

You can see your updated policy for your function in the Lambda console.

(Optional) To see your updated policy

1. Sign in to the AWS Management Console and open the AWS Lambda console at <https://console.aws.amazon.com/lambda/>.
2. Choose your Lambda function.
3. Choose **Permissions**.

You should see an Allow policy with a Condition clause in which the in the AWS:SourceArn is the ARN for your API's GET method.

Tutorial: Create a REST API by importing an example

You can use the Amazon API Gateway console to create and test a simple REST API with the HTTP integration for a PetStore website. The API definition is preconfigured as a OpenAPI 2.0 file. After loading the API definition into API Gateway, you can use the API Gateway console to examine the API's basic structure or simply deploy and test the API.

The PetStore example API supports the following methods for a client to access the HTTP backend website of `http://petstore-demo-endpoint.execute-api.com/petstore/pets`.

Note

This tutorial uses an HTTP endpoint as an example. When you create your own APIs, we recommend you use HTTPS endpoints for your HTTP integrations.

- GET `/`: for read access of the API's root resource that is not integrated with any backend endpoint. API Gateway responds with an overview of the PetStore website. This is an example of the MOCK integration type.
- GET `/pets`: for read access to the API's `/pets` resource that is integrated with the like-named backend `/pets` resource. The backend returns a page of available pets in the PetStore. This is an example of the HTTP integration type. The URL of the integration endpoint is `http://petstore-demo-endpoint.execute-api.com/petstore/pets`.

- POST /pets: for write access to the API's /pets resource that is integrated with the backend /petstore/pets resource. Upon receiving a correct request, the backend adds the specified pet to the PetStore and returns the result to the caller. The integration is also HTTP.
- GET /pets/{petId}: for read access to a pet as identified by a petId value as specified as a path variable of the incoming request URL. This method also has the HTTP integration type. The backend returns the specified pet found in the PetStore. The URL of the backend HTTP endpoint is `http://petstore-demo-endpoint.execute-api.com/petstore/pets/n`, where n is an integer as the identifier of the queried pet.

The API supports CORS access via the OPTIONS methods of the MOCK integration type. API Gateway returns the required headers supporting CORS access.

The following procedure walks you through the steps to create and test an API from an example using the API Gateway Console.

To import, build, and test the example API

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Do one of the following:
 - To create your first API, for **REST API**, choose **Build**.
 - If you've created an API before, choose **Create API**, and then choose **Build** for **REST API**.
3. Under **Create REST API**, choose **Example API** and then choose **Create API** to create the example API.

Create REST API

API details

New API
Create a new REST API.

Clone existing API
Create a copy of an API in this AWS account.

Import API
Import an API from an OpenAPI definition.

Example API
Learn about API Gateway with an example API.

```
1  {
2      "swagger": "2.0",
3      "info": {
4          "description": "Your first API with Amazon API Gateway. This is a sample API that integrates via HTTP w
ith our demo Pet Store endpoints",
5          "title": "PetStore"
6      },
7      "schemes": [
8          "https"
9      ],
10     "paths": {
11         "/": {
12             "get": {
13                 "tags": [
14                     "pets"
15                 ],
16                 "description": "PetStore HTML web page containing API usage information",
17                 "consumes": [
18                     "application/json"
19                 ],

```

You can scroll down the OpenAPI definition for details of this example API before choosing **Create API**.

4. In the main navigation pane, choose **Resources**. The newly created API is shown as follows:

Resources

[API actions ▾](#)[Deploy API](#)

The screenshot shows the Amazon API Gateway interface. On the left, a tree view of API resources is displayed:

- / (Root)
 - GET
 - /pets
 - GET
 - OPTIONS
 - POST
 - {petId}
 - GET
 - OPTIONS

On the right, the details for the root resource (/) are shown:

Resource details

Path: /

Resource ID: efg456


Methods (1)

Method type	Integration type	Authorization	API key
GET	Mock	None	Not required

Buttons: [Update documentation](#), [Enable CORS](#), [Delete](#), [Create method](#)

The **Resources** pane shows the structure of the created API as a tree of nodes. API methods defined on each resource are edges of the tree. When a resource is selected, all of its methods are listed in the **Methods** table on the right. Displayed with each method is the method type, integration type, authorization type, and API key requirement.

5. To view the details of a method, to modify its set-up, or to test the method invocation, choose the method name from either the method list or the resource tree. Here, we choose the POST /pets method as an illustration:



The resulting **Method execution** pane presents a logical view of the chosen (POST /pets) method's structure and behaviors.

The **Method request** and **Method response** represent the API's interface with the frontend, and the **Integration request** and **Integration response** represent the API's interface with the backend.

A client uses the API to access a backend feature through the **Method request**. API Gateway translates the client request, if necessary, into the form acceptable to the backend in **Integration request** before forwarding the incoming request to the backend. The transformed request is known as the integration request. Similarly, the backend returns the response to API Gateway in **Integration response**. API Gateway then routes it to **Method Response** before sending it to the client. Again, if necessary, API Gateway can map the backend response data to a form expected by the client.

For the POST method on an API resource, the method request payload can be passed through to the integration request without modification, if the method request's payload is of the same format as the integration request's payload.

The GET / method request uses the MOCK integration type and is not tied to any real backend endpoint. The corresponding **Integration response** is set up to return a static HTML page.

When the method is called, the API Gateway simply accepts the request and immediately returns the configured integration response to the client by way of **Method response**. You can use the mock integration to test an API without requiring a backend endpoint. You can also use it to serve a local response, generated from a response body-mapping template.

As an API developer, you control the behaviors of your API's frontend interactions by configuring the method request and a method response. You control the behaviors of your API's backend interactions by setting up the integration request and integration response. These involve data mappings between a method and its corresponding integration. For now, we focus on testing the API to provide an end-to-end user experience.

6. Select the **Test** tab. You might need to choose the right arrow button to show the tab.
7. For example, to test the POST /pets method, enter the following `{"type": "dog", "price": 249.99}` payload into the **Request body**, and then choose **Test**.



Test method

Make a test call to your method. When you make a test call, API Gateway skips authorization and directly invokes your method.

Query strings

```
param1=value1&param2=value2
```

Headers

Enter a header name and value separated by a colon (:). Use a new line for each header.

```
header1:value1  
header2:value2
```

Client certificate

No client certificates have been generated.



Request body

```
1 ▼ {  
2   "type" : "dog", "price": 249.99  
3 }
```

The input specifies the attributes of the pet that we want to add to the list of pets on the PetStore website.

8. The results display as follows:

/pets - POST method test results		
Request	Latency ms	Status
/pets	13	200
Response body		
{ "pet": { "type": "dog", "price": 249.99 }, "message": "success" }		
Response headers		
{ "Access-Control-Allow-Origin": "*", "Content-Type": "application/json", "X-Amzn-Trace-Id": "Root=1-67928ab3-ade6b7bdc102614983b74a5f" }		
Logs		
Execution log for request 06089002-b249-47e9-b485-5530e4843290 Thu Jan 23 18:30:11 UTC 2025 : Starting execution for request: 06089002-b249-47e9-b485-		

The **Log** entry of the output shows the state changes from the method request to the integration request, and from the integration response to the method response. This can be useful for troubleshooting any mapping errors that cause the request to fail. In this example, no mapping is applied: the method request payload is passed through the integration request to the backend and, similarly, the backend response is passed through the integration response to the method response.

To test the API using a client other than the API Gateway test-invoke-request feature, you must first deploy the API to a stage.

9. To deploy the sample API, choose **Deploy API**.

Resources

The screenshot shows the 'Resources' section of the Amazon API Gateway console. On the left, a tree view lists resources: '/' (Path: /, Methods: GET, OPTIONS, POST), '/pets' (Path: /pets, Methods: GET, OPTIONS), and '/{petId}' (Path: /{petId}, Methods: GET, OPTIONS). On the right, the details for the root resource '/' are shown. The 'Resource details' pane includes the path '/', a 'Resource ID' of 'efg456', and buttons for 'Update documentation' and 'Enable CORS'. The 'Methods (1)' pane shows one method: a GET method with integration type 'Mock', authorization 'None', and API key requirement 'Not required'. A 'Create method' button is also present.

10. For **Stage**, select **New stage**, and then enter **test**.
11. (Optional) For **Description**, enter a description.
12. Choose **Deploy**.
13. In the resulting **Stages** pane, under **Stage details**, the **Invoke URL** displays the URL to invoke the API's GET / method request.

Stage details [Info](#)

Stage name Prod	Rate Info 10000	Web ACL -
Cache cluster Info <input checked="" type="radio"/> Inactive	Burst Info 5000	Client certificate -
Default method-level caching <input checked="" type="radio"/> Inactive		

Invoke URL
<https://abcd1234.execute-api.us-east-1.amazonaws.com/Prod>

Active deployment
efg456 on June 01, 2023, 15:00 (UTC-07:00)

14. Choose the copy icon to copy your API's invoke URL, and then enter your API's invoke URL in a web browser. A successful response return the result, generated from the mapping template in the integration response.
15. In the **Stages** navigation pane, expand the **test** stage, select **GET** on `/pets/{petId}`, and then copy the **Invoke URL** value of `https://api-id.execute-api.region.amazonaws.com/test/pets/{petId}`. `{petId}` stands for a path variable.

Paste the **Invoke URL** value (obtained in the previous step) into the address bar of a browser, replacing `{petId}` by, for example, 1, and press Enter to submit the request. A 200 OK response should return with the following JSON payload:

```
{  
  "id": 1,  
  "type": "dog",  
  "price": 249.99  
}
```

Invoking the API method as shown is possible because its **Authorization** type is set to NONE. If the AWS_IAM authorization were used, you would sign the request using the [Signature Version 4 \(SigV4\)](#) or [Signature Version 4a \(SigV4a\)](#) protocols. For an example of such a request, see [the section called “Tutorial: Create a REST API with an HTTP non-proxy integration”](#).

Choose an HTTP integration tutorial

To build an API with HTTP integration, you can use either an HTTP proxy integration or an HTTP custom integration.

In an HTTP proxy integration, you only need to set the HTTP method and the HTTP endpoint URI, according to the backend requirements. We recommend that you use the HTTP proxy integration, whenever possible, to take advantage of the streamlined API set up.

You might want to use an HTTP custom integration if you need to transform client request data for the backend or transform the backend response data for the client.

Topics

- [Tutorial: Create a REST API with an HTTP proxy integration](#)
- [Tutorial: Create a REST API with an HTTP non-proxy integration](#)

Tutorial: Create a REST API with an HTTP proxy integration

HTTP proxy integration is a simple, powerful, and versatile mechanism to build an API that allows a web application to access multiple resources or features of the integrated HTTP endpoint, for example the entire website, with a streamlined setup of a single API method. In HTTP proxy integration, API Gateway passes the client-submitted method request to the backend. The request data that is passed through includes the request headers, query string parameters, URL path variables, and payload. The backend HTTP endpoint or the web server parses the incoming request data to determine the response that it returns. HTTP proxy integration makes the client and backend interact directly with no intervention from API Gateway after the API method is set up, except for known issues such as unsupported characters, which are listed in [the section called “Important notes”](#).

With the all-encompassing proxy resource `{proxy+}`, and the catch-all ANY verb for the HTTP method, you can use an HTTP proxy integration to create an API of a single API method. The method exposes the entire set of the publicly accessible HTTP resources and operations of a website. When the backend web server opens more resources for public access, the client can use these new resources with the same API setup. To enable this, the website developer must communicate clearly to the client developer what the new resources are and what operations are applicable for each of them.

As a quick introduction, the following tutorial demonstrates the HTTP proxy integration. In the tutorial, we create an API using the API Gateway console to integrate with the PetStore website through a generic proxy resource {proxy+}, and create the HTTP method placeholder of ANY.

Topics

- [Create an API with HTTP proxy integration using the API Gateway console](#)
- [Test an API with HTTP proxy integration](#)

Create an API with HTTP proxy integration using the API Gateway console

The following procedure walks you through the steps to create and test an API with a proxy resource for an HTTP backend using the API Gateway console. The HTTP backend is the PetStore website (<http://petstore-demo-endpoint.execute-api.com/petstore/pets>) from [Tutorial: Create a REST API with an HTTP non-proxy integration](#), in which screenshots are used as visual aids to illustrate the API Gateway UI elements. If you are new to using the API Gateway console to create an API, you may want to follow that section first.

To create an API

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. If this is your first time using API Gateway, you see a page that introduces you to the features of the service. Under **REST API**, choose **Build**. When the **Create Example API** popup appears, choose **OK**.

If this is not your first time using API Gateway, choose **Create API**. Under **REST API**, choose **Build**.

3. For **API name**, enter **HTTPProxyAPI**.
4. (Optional) For **Description**, enter a description.
5. Keep **API endpoint type** set to **Regional**.
6. For **IP address type**, select **IPv4**.
7. Choose **Create API**.

In this step, you create a proxy resource path of {proxy+}. This is the placeholder of any of the backend endpoints under <http://petstore-demo-endpoint.execute-api.com/>. For example, it can be petstore, petstore/pets, and petstore/pets/{petId}. API Gateway

creates the ANY method when you create the `{proxy+}` resource and serves as a placeholder for any of the supported HTTP verbs at run time.

To create a `{proxy+}` resource

1. Choose your API.
2. In the main navigation pane, choose **Resources**.
3. Choose **Create resource**.
4. Turn on **Proxy resource**.
5. Keep **Resource path** as `/`.
6. For **Resource name**, enter `{proxy+}`.
7. Keep **CORS (Cross Origin Resource Sharing)** turned off.
8. Choose **Create resource**.

Create resource

Resource details

Proxy resource [Info](#)
Proxy resources handle requests to all sub-resources. To create a proxy resource use a path parameter that ends with a plus sign, for example `{proxy+}`.

Resource path	Resource name
<input type="text" value="/{proxy+}/"/>	<input type="text" value="{}proxy+{}/"/>
<input type="checkbox"/> CORS (Cross Origin Resource Sharing) Info Create an OPTIONS method that allows all origins, all methods, and several common headers.	

[Cancel](#) [Create resource](#)

In this step, you integrate the ANY method with a backend HTTP endpoint, using a proxy integration. In a proxy integration, API Gateway passes the client-submitted method request to the backend with no intervention from API Gateway.

To create an ANY method

1. Choose the **/{proxy+}** resource.
2. Choose the **ANY** method.
3. Under the warning symbol, choose **Edit integration**. You cannot deploy an API that has a method without an integration.
4. For **Integration type**, select **HTTP**.
5. Turn on **HTTP proxy integration**.
6. For **HTTP method**, select **ANY**.
7. For **Endpoint URL**, enter **http://petstore-demo-endpoint.execute-api.com/{proxy}**.
8. Choose **Save**.

Test an API with HTTP proxy integration

Whether a particular client request succeeds depends on the following:

- If the backend has made the corresponding backend endpoint available and, if so, has granted the required access permissions.
- If the client supplies the correct input.

For example, the PetStore API used here does not expose the /petstore resource. As such, you get a 404 Resource Not Found response containing the error message of Cannot GET / petstore.

In addition, the client must be able to handle the output format of the backend in order to parse the result correctly. API Gateway does not mediate to facilitate interactions between the client and backend.

To test an API integrated with the PetStore website using HTTP proxy integration through the proxy resource

1. Select the **Test** tab. You might need to choose the right arrow button to show the tab.
2. For **Method type**, select **GET**.
3. For **Path**, under **proxy**, enter **petstore/pets**.

4. For **Query strings**, enter **type=fish**.

5. Choose **Test**.

The screenshot shows the AWS Lambda Test interface. At the top, there are five tabs: 'Test' (which is highlighted with a red box), 'Integration request', 'Integration response', 'Method response', and 'Test' (which is also highlighted with a red box). Below the tabs, there is a section titled 'Test method' with the sub-instruction: 'Make a test call to your method. When you make a test call, API Gateway skips authorization and directly invokes your method.' Underneath this, there are three input fields: 'Method type' (set to 'GET'), 'Path' (set to 'proxy/petstore/pets'), and 'Query strings' (set to 'type=fish').

Because the backend website supports the GET /petstore/pets?type=fish request, it returns a successful response similar to the following:

```
[  
 {  
   "id": 1,  
   "type": "fish",  
   "price": 249.99  
 },  
 {  
   "id": 2,  
   "type": "fish",  
   "price": 124.99  
 },  
 {  
   "id": 3,  
   "type": "fish",  
   "price": 0.99  
 }
```

]

If you try to call GET /petstore, you get a 404 response with an error message of Cannot GET /petstore. This is because the backend does not support the specified operation. If you call GET /petstore/pets/1, you get a 200 OK response with the following payload, because the request is supported by the PetStore website.

```
{  
    "id": 1,  
    "type": "dog",  
    "price": 249.99  
}
```

You can also use a browser to test your API. Deploy your API and associate it to a stage to create your API's Invoke URL.

To deploy your API

1. Choose **Deploy API**.
2. For **Stage**, select **New stage**.
3. For **Stage name**, enter **test**.
4. (Optional) For **Description**, enter a description.
5. Choose **Deploy**.

Now clients can call your API.

To invoke your API

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose your API.
3. In the main navigation pane, choose **Stage**.
4. Under **Stage details**, choose the copy icon to copy your API's invoke URL.

Enter your API's invoke URL in a web browser.

The full URL should look like https://*abcdef123*.execute-api.*us-east-2*.amazonaws.com/*test*/petstore/pets?type=fish.

- Your browser sends a GET request to the API.
5. The result should be the same as returned when you use **Test** in the API Gateway console.

Tutorial: Create a REST API with an HTTP non-proxy integration

In this tutorial, you create an API from scratch using the Amazon API Gateway console. You can think of the console as an API design studio and use it to scope the API features, to experiment with its behaviors, to build the API, and to deploy your API in stages.

Topics

- [Create an API with HTTP custom integration](#)
- [\(Optional\) Map request parameters](#)

Create an API with HTTP custom integration

This section walks you through the steps to create resources, expose methods on a resource, configure a method to achieve the desired API behaviors, and to test and deploy the API.

In this step, you create an empty API. In the following steps you create resources and methods to connect your API to the `http://petstore-demo-endpoint.execute-api.com/petstore/pets` endpoint, using a non-proxy HTTP integration.

To create an API

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. If this is your first time using API Gateway, you see a page that introduces you to the features of the service. Under **REST API**, choose **Build**. When the **Create Example API** popup appears, choose **OK**.

If this is not your first time using API Gateway, choose **Create API**. Under **REST API**, choose **Build**.

3. For **API name**, enter **HTTPNonProxyAPI**.
4. (Optional) For **Description**, enter a description.
5. Keep **API endpoint type** set to **Regional**.
6. For **IP address type**, select **IPv4**.
7. Choose **Create API**.

The **Resources** tree shows the root resource (/) without any methods. In this exercise, we will build the API with the HTTP custom integration of the PetStore website (<http://petstore-demo-endpoint.execute-api.com/petstore/pets>.) For illustration purposes, we will create a /pets resource as a child of the root and expose a GET method on this resource for a client to retrieve a list of available Pets items from the PetStore website.

To create a /pets resource

1. Choose **Create resource**.
2. Keep **Proxy resource** turned off.
3. Keep **Resource path** as /.
4. For **Resource name**, enter **pets**.
5. Keep **CORS (Cross Origin Resource Sharing)** turned off.
6. Choose **Create resource**.

In this step, you create a GET method on the /**pets** resource. The GET method is integrated with the <http://petstore-demo-endpoint.execute-api.com/petstore/pets> website. Other options for an API method include the following:

- **POST**, primarily used to create child resources.
- **PUT**, primarily used to update existing resources (and, although not recommended, can be used to create child resources).
- **DELETE**, used to delete resources.
- **PATCH**, used to update resources.
- **HEAD**, primarily used in testing scenarios. It is the same as GET but does not return the resource representation.
- **OPTIONS**, which can be used by callers to get information about available communication options for the target service.

For the integration request's **HTTP method**, you must choose one supported by the backend. For HTTP or Mock integration, it makes sense that the method request and the integration request use the same HTTP verb. For other integration types the method request will likely use an HTTP verb different from the integration request. For example, to call a Lambda function, the integration request must use POST to invoke the function, whereas the method request may use any HTTP verb depending on the logic of the Lambda function.

To create a GET method on the /pets resource

1. Select the **/pets** resource.
2. Choose **Create method**.
3. For **Method type**, select **GET**.
4. For **Integration type**, select **HTTP integration**.
5. Keep **HTTP proxy integration** turned off.
6. For **HTTP method**, select **GET**.
7. For **Endpoint URL**, enter **http://petstore-demo-endpoint.execute-api.com/petstore/pets**.

The PetStore website allows you to retrieve a list of Pet items by the pet type, such as "Dog" or "Cat", on a given page.

8. For **Content handling**, select **Passthrough**.
9. Choose **URL query string parameters**.

The PetStore website uses the type and page query string parameters to accept an input. You add query string parameters to the method request and map them into corresponding query string parameters of the integration request.

10. To add the query string parameters, do the following:
 - a. Choose **Add query string**.
 - b. For **Name**, enter **type**
 - c. Keep **Required** and **Caching** turned off.

Repeat the previous steps to create an additional query string with the name **page**.

11. Choose **Create method**.

The client can now supply a pet type and a page number as query string parameters when submitting a request. These input parameters must be mapped into the integration's query string parameters to forward the input values to our PetStore website in the backend.

To map input parameters to the Integration request

1. On the **Integration request** tab, under **Integration request settings**, choose **Edit**.

2. Choose **URL query string parameters**, and then do the following:
 - a. Choose **Add query string parameter**.
 - b. For **Name**, enter **type**.
 - c. For **Mapped from**, enter **method.request.querystring.type**
 - d. Keep **Caching** turned off.
 - e. Choose **Add query string parameter**.
 - f. For **Name**, enter **page**.
 - g. For **Mapped from**, enter **method.request.querystring.page**
 - h. Keep **Caching** turned off.
3. Choose **Save**.

To test the API

1. Choose the **Test** tab. You might need to choose the right arrow button to show the tab.
2. For **Query strings**, enter **type=Dog&page=2**.
3. Choose **Test**.

The result is similar to the following:

Method request | Integration request | Integration response | Method response | **Test**

Test method

Make a test call to your method. When you make a test call, API Gateway skips authorization and directly invokes your method.

Query strings

```
type=Dog&page=2
```

Headers

Enter a header name and value separated by a colon (:). Use a new line for each header.

```
header1:value1  
header2:value2
```

Client certificate

```
None
```

Test

ⓘ /pets - GET method test results

Request

```
/pets?type=Dog&page=2
```

Latency ms

```
10
```

Status

```
200
```

Response body

```
[  
 {  
   "id": 4,  
   "type": "Dog",  
   "price": 999.99
```

Now that the test is successful, we can deploy the API to make it publicly available.

4. Choose **Deploy API**.
5. For **Stage**, select **New stage**.
6. For **Stage name**, enter **Prod**.
7. (Optional) For **Description**, enter a description.
8. Choose **Deploy**.
9. (Optional) Under **Stage details**, for **Invoke URL**, you can choose the copy icon to copy your API's invoke URL. You can use this with tools such as [Postman](#) and [cURL](#) to test your API.

If you use an SDK to create a client, you can call the methods exposed by the SDK to sign the request. For implementation details, see the [AWS SDK](#) of your choosing.

 **Note**

When changes are made to your API, you must redeploy the API to make the new or updated features available before invoking the request URL again.

(Optional) Map request parameters

Map request parameters for an API Gateway API

This tutorial shows how to create a path parameter of `{petId}` on the API's method request to specify an item ID, map it to the `{id}` path parameter in the integration request URL, and send the request to the HTTP endpoint.

 **Note**

If you enter the incorrect case of a letter, such as lowercase letter instead of an uppercase letter, this will cause errors later in the walkthrough.

Step 1: Create resources

In this step, you create a resource with a path parameter `{petId}`.

To create the `{petId}` resource

1. Select the `/pets` resource, and then choose **Create resource**.
2. Keep **Proxy resource** turned off.
3. For **Resource path**, select `/pets/`.
4. For **Resource name**, enter `{petId}`.

Use the curly braces (`{ }`) around `petId` so that `/pets/{petId}` is displayed.

5. Keep **CORS (Cross Origin Resource Sharing)** turned off.
6. Choose **Create resource**.

Step 2: Create and test the methods

In this step, you create a GET method with a `{petId}` path parameter.

To set up GET method

1. Select the `/{{petId}}` resource, and then choose **Create method**.
2. For **Method type**, select **GET**.
3. For **Integration type**, select **HTTP integration**.
4. Keep **HTTP proxy integration** turned off.
5. For **HTTP method**, select **GET**.
6. For **Endpoint URL**, enter `http://petstore-demo-endpoint.execute-api.com/petstore/pets/{id}`
7. For **Content handling**, select **Passthrough**.
8. Keep the **Default timeout** turned on.
9. Choose **Create method**.

Now you map the `{petId}` path parameter that you just created to the `{id}` path parameter in the HTTP endpoint URL of the integration request. The HTTP endpoint URL was `http://petstore-demo-endpoint.execute-api.com/petstore/pets/{id}`.

To map the `{petId}` path parameter

1. On the **Integration request** tab, under **Integration request settings**, choose **Edit**.
2. Choose **URL path parameters**.
3. API Gateway creates a path parameter for the integration request named **petId**, however this path parameter isn't valid for the HTTP endpoint URL that you set as the backend integration. The HTTP endpoint uses `{id}` as the path parameter. For **Name**, delete **petId** and enter **id**.

This maps the method request's path parameter of `petId` to the integration request's path parameter of `id`.

4. Choose **Save**.

Now you test the method.

To test the method

1. Choose the **Test** tab. You might need to choose the right arrow button to show the tab.
2. Under **Path** for **petId**, enter **4**.
3. Choose **Test**.

If successful, **Response body** displays the following:

```
{  
  "id": 4,  
  "type": "bird",  
  "price": 999.99  
}
```

Step 3: Deploy the API

In this step, you deploy the API so that you can begin calling it outside of the API Gateway console.

To deploy the API

1. Choose **Deploy API**.
2. For **Stage**, select **Prod**.
3. (Optional) For **Description**, enter a description.
4. Choose **Deploy**.

Step 4: Test the API

In this step, you go outside of the API Gateway console and use your API to access the HTTP endpoint.

1. In the main navigation pane, choose **Stage**.
2. Under **Stage details**, choose the copy icon to copy your API's invoke URL.

It should look something like this:

```
https://my-api-id.execute-api.region-id.amazonaws.com/prod
```

3. Enter this URL in the address box of a new browser tab and append /pets/4 to the URL before you submit your request.
4. The browser will return the following:

```
{  
  "id": 4,  
  "type": "bird",  
  "price": 999.99  
}
```

Next steps

You can further customize your API by turning on request validation, transforming data, or creating custom gateway responses.

To explore more ways to customize your API, see the following tutorials:

- For more information about request validation, see [Set up basic request validation in API Gateway](#).
- For information about how to transform request and response payloads, see [Tutorial: Modify the integration request and response for integrations to AWS services](#).
- For information about how to create custom gateway responses see, [Set up a gateway response for a REST API using the API Gateway console](#).

Tutorial: Create a REST API with a private integration


In this tutorial, you create a REST API that connects to an Amazon ECS service that runs in an Amazon VPC. Clients outside of your Amazon VPC can use the API to access your Amazon ECS service.

This tutorial takes approximately an hour to complete. First, you use a CloudFormation template to create a Amazon VPC and Amazon ECS service. Then you use the API Gateway console to create a VPC link V2. The VPC link allows API Gateway to access the Amazon ECS service that runs in your Amazon VPC. Next, you create a REST API that uses the VPC link V2 to connect to your Amazon ECS service. Lastly, you test your API.

When you invoke your REST API, API Gateway routes the request to your Amazon ECS service through your VPC link V2, and then returns the response from the service.

Note

This tutorial was previously supported for HTTP APIs, and now is supported for REST APIs using VPC link V2.



To complete this tutorial, you need an AWS account and an AWS Identity and Access Management user with console access. For more information, see [Prerequisites](#).

Topics

- [Step 1: Create an Amazon ECS service](#)
- [Step 2: Create a VPC link](#)
- [Step 3: Create a REST API](#)
- [Step 4: Test your API](#)
- [Step 5: Deploy your API](#)
- [Step 6: Call your API](#)
- [Step 7: Clean up](#)

Step 1: Create an Amazon ECS service

Amazon ECS is a container management service that makes it easy to run, stop, and manage Docker containers on a cluster. In this tutorial, you run your cluster on a serverless infrastructure that's managed by Amazon ECS.

Download and unzip [this CloudFormation template](#), which creates all of the dependencies for the service, including an Amazon VPC. You use the template to create an Amazon ECS service that uses an Application Load Balancer.

To create an CloudFormation stack

1. Open the CloudFormation console at <https://console.aws.amazon.com/cloudformation>.
2. Choose **Create stack** and then choose **With new resources (standard)**.
3. For **Specify template**, choose **Upload a template file**.
4. Select the template that you downloaded.
5. Choose **Next**.
6. For **Stack name**, enter **rest-api-private-integrations-tutorial** and then choose **Next**.
7. For **Configure stack options**, choose **Next**.
8. For **Capabilities**, acknowledge that CloudFormation can create IAM resources in your account.
9. Choose **Next**, and then choose **Submit**.

CloudFormation provisions the ECS service, which can take a few minutes. When the status of your CloudFormation stack is **CREATE_COMPLETE**, you're ready to move on to the next step.

Step 2: Create a VPC link

A VPC link allows API Gateway to access private resources in an Amazon VPC. You use a VPC link to allow clients to access your Amazon ECS service through your REST API.

To create a VPC link

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. On the main navigation pane, choose **VPC links** and then choose **Create**.
You might need to choose the menu icon to open the main navigation pane.
3. For **Choose a VPC link version**, select **VPC link V2**.
4. For **Name**, enter **private-integrations-tutorial**.
5. For **VPC**, choose the VPC that you created in step 1. The name should start with **RestApiStack**.
6. For **Subnets**, select the two private subnets in your VPC. Their names end with **PrivateSubnet**.

7. For **Security groups**, select the Group ID that starts with `private-integrations-tutorial` and has the description of `RestApiStack/RestApiTutorialService/Service/SecurityGroup`.
8. Choose **Create**.

After you create your VPC link V2, API Gateway provisions Elastic Network Interfaces to access your VPC. The process can take a few minutes. In the meantime, you can create your API.

Step 3: Create a REST API

The REST API provides an HTTP endpoint for your Amazon ECS service.

To create a REST API

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose **Create API**, and then for **REST API**, choose **Build**.
3. For **Name**, enter `private-integration-api`.
4. For **IP address type**, select **IPv4**.
5. Choose **Create API**.

After you create your API, you create a method.

6. Choose **Create method**, and then do the following:
 - a. For **Method type**, select **GET**.
 - b. For **Integration type**, select **VPC link**.
 - c. Turn on **VPC proxy integration**.
 - d. For **HTTP method**, select **GET**.
 - e. For **VPC link**, choose the VPC link V2 you created in the previous step.
 - f. For **Integration target**, enter the load balancer that you created with the CloudFormation template in Step 1. Its name should start with `rest-`.
 - g. For **Endpoint URL**, enter `http://private-integrations-tutorial.com`.

The URL is used to set the Host header of the integration request. In this case, the host header is `private-integrations-tutorial`.

- h. Choose **Create method**.

With the proxy integration, the API is ready to test.

Step 4: Test your API

Next, you test invoking the API method.

To test your API

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose your API.
3. Choose the **Test** tab. You might need to choose the right arrow button to show the tab.
4. Choose **Test**

Verify that your API's response is a welcome message that tells you that your app is running on Amazon ECS.

Step 5: Deploy your API

Next, you deploy your API.

To deploy your API

1. Choose **Deploy API**.
2. For **Stage**, select **New stage**.
3. For **Stage name**, enter **Prod**.
4. (Optional) For **Description**, enter a description.
5. Choose **Deploy**.

Step 6: Call your API

After your API is deployed, you can call it.

To call your API

1. Enter the invoke URL in a web browser.

The full URL should look like `https://abcd123.execute-api.us-east-2.amazonaws.com/Prod`.

Your browser sends a GET request to the API.

- Verify that your API's response is a welcome message that tells you that your app is running on Amazon ECS.

If you see the welcome message, you successfully created an Amazon ECS service that runs in an Amazon VPC, and you used an API Gateway REST API with a VPC link V2 to access the Amazon ECS service.

Step 7: Clean up

To prevent unnecessary costs, delete the resources that you created as part of this tutorial. The following steps delete your VPC link V2, CloudFormation stack, and REST API.

To delete a REST API

- Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
- On the APIs page, select an API. Choose **Actions**, choose **Delete**, and then confirm your choice.

To delete a VPC link

- Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
- Choose **VPC link**.
- Select your VPC link, choose **Delete**, and then confirm your choice.

To delete an CloudFormation stack

- Open the CloudFormation console at <https://console.aws.amazon.com/cloudformation>.
- Select your CloudFormation stack.
- Choose **Delete** and then confirm your choice.

Tutorial: Create a REST API with an AWS integration

Both the [Tutorial: Create a REST API with a Lambda proxy integration](#) and [Tutorial: Create a REST API with a Lambda non-proxy integration](#) topics describe how to create an API Gateway API to expose the integrated Lambda function. In addition, you can create an API Gateway API to expose other AWS services, such as Amazon SNS, Amazon S3, Amazon Kinesis, and even AWS Lambda. This is made possible by the AWS integration. The Lambda integration or the Lambda proxy integration is a special case, where the Lambda function invocation is exposed through the API Gateway API.

All AWS services support dedicated APIs to expose their features. However, the application protocols or programming interfaces are likely to differ from service to service. An API Gateway API with the AWS integration has the advantage of providing a consistent application protocol for your client to access different AWS services.

In this walkthrough, we create an API to expose Amazon SNS. For more examples of integrating an API with other AWS services, see [Amazon API Gateway tutorials and workshops](#).

Unlike the Lambda proxy integration, there is no corresponding proxy integration for other AWS services. Hence, an API method is integrated with a single AWS action. For more flexibility, similar to the proxy integration, you can set up a Lambda proxy integration. The Lambda function then parses and processes requests for other AWS actions.

API Gateway does not retry when the endpoint times out. The API caller must implement retry logic to handle endpoint timeouts.

This walkthrough builds on the instructions and concepts in [Tutorial: Create a REST API with a Lambda non-proxy integration](#). If you have not yet completed that walkthrough, we suggest that you do it first.

Topics

- [Prerequisites](#)
- [Step 1: Create the AWS service proxy execution role](#)
- [Step 2: Create the resource](#)
- [Step 3: Create the GET method](#)
- [Step 4: Specify method settings and test the method](#)
- [Step 5: Deploy the API](#)

- [Step 6: Test the API](#)
- [Step 7: Clean up](#)

Prerequisites

Before you begin this walkthrough, do the following:

1. Complete the steps in [Set up to use API Gateway](#).
2. Create a new API named MyDemoAPI. For more information, see [Tutorial: Create a REST API with an HTTP non-proxy integration](#).
3. Deploy the API at least once to a stage named test. For more information, see [Deploy the API](#) in [Choose an AWS Lambda integration tutorial](#).
4. Complete the rest of the steps in [Choose an AWS Lambda integration tutorial](#).
5. Create at least one topic in Amazon Simple Notification Service (Amazon SNS). You will use the deployed API to get a list of topics in Amazon SNS that are associated with your AWS account. To learn how to create a topic in Amazon SNS, see [Create a Topic](#). (You do not need to copy the topic ARN mentioned in step 5.)

Step 1: Create the AWS service proxy execution role

To allow the API to invoke Amazon SNS actions, you must have the appropriate IAM policies attached to an IAM role. In this step, you create a new IAM role.

To create the AWS service proxy execution role

1. Sign in to the AWS Management Console and open the IAM console at <https://console.aws.amazon.com/iam/>.
2. Choose **Roles**.
3. Choose **Create role**.
4. Choose **AWS service** under **Select type of trusted entity**, and then select **API Gateway** and select **Allows API Gateway to push logs to CloudWatch Logs**.
5. Choose **Next**, and then choose **Next**.
6. For **Role name**, enter **APIGatewaySNSProxyPolicy**, and then choose **Create role**.
7. In the **Roles** list, choose the role you just created. You may need to scroll or use the search bar to find the role.

8. For the selected role, select the **Add permissions** tab.
9. Choose **Attach policies** from the dropdown list.
10. In the search bar, enter **AmazonSNSReadOnlyAccess** and choose **Add permissions**.

 **Note**

This tutorial uses a managed policy for simplicity. As a best practice, you should create your own IAM policy to grant the minimum permissions required.

11. Note the newly created **Role ARN**, you will use it later.

Step 2: Create the resource

In this step, you create a resource that enables the AWS service proxy to interact with the AWS service.

To create the resource

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose your API.
3. Select the root resource, **/**, represented by a single forward slash (**/**), and then choose **Create resource**.
4. Keep **Proxy resource** turned off.
5. Keep **Resource path** as **/**.
6. For **Resource name**, enter **mydemoawsproxy**.
7. Keep **CORS (Cross Origin Resource Sharing)** turned off.
8. Choose **Create resource**.

Step 3: Create the GET method

In this step, you create a GET method that enables the AWS service proxy to interact with the AWS service.

To create the GET method

1. Select the **/mydemoawsproxy** resource, and then choose **Create method**.

2. For method type, select **GET**.
3. For **Integration type**, select **AWS service**.
4. For **AWS Region**, select the AWS Region where you created your Amazon SNS topic.
5. For **AWS service**, select **Amazon SNS**.
6. Keep **AWS subdomain** blank.
7. For **HTTP method**, select **GET**.
8. For **Action type**, select **Use action name**.
9. For **Action name**, enter **ListTopics**.
10. For **Execution role**, enter the role ARN for **APIGatewaySNSSProxyPolicy**.
11. Choose **Create method**.

Step 4: Specify method settings and test the method

You can now test your GET method to verify that it has been properly set up to list your Amazon SNS topics.

To test the GET method

1. Choose the **Test** tab. You might need to choose the right arrow button to show the tab.
2. Choose **Test**.

The result displays response similar to the following:

```
{  
  "ListTopicsResponse": {  
    "ListTopicsResult": {  
      "NextToken": null,  
      "Topics": [  
        {  
          "TopicArn": "arn:aws:sns:us-east-1:80398EXAMPLE:MySNSTopic-1"  
        },  
        {  
          "TopicArn": "arn:aws:sns:us-east-1:80398EXAMPLE:MySNSTopic-2"  
        },  
        ...  
        {  
          "TopicArn": "arn:aws:sns:us-east-1:80398EXAMPLE:MySNSTopic-N"  
        }  
      ]  
    }  
  }  
}
```

```
        }
    ],
},
"ResponseMetadata": {
    "RequestId": "abc1de23-45fa-6789-b0c1-d2e345fa6b78"
}
}
```

Step 5: Deploy the API

In this step, you deploy the API so that you can call it from outside of the API Gateway console.

To deploy the API

1. Choose **Deploy API**.
2. For **Stage**, select **New stage**.
3. For **Stage name**, enter **test**.
4. (Optional) For **Description**, enter a description.
5. Choose **Deploy**.

Step 6: Test the API

In this step, you go outside of the API Gateway console and use your AWS service proxy to interact with the Amazon SNS service.

1. In the main navigation pane, choose **Stage**.
2. Under **Stage details**, choose the copy icon to copy your API's invoke URL.

It should look like this:

```
https://my-api-id.execute-api.region-id.amazonaws.com/test
```

3. Enter the URL into the address box of a new browser tab.
4. Append /mydemoawsproxy so that the URL looks like this:

```
https://my-api-id.execute-api.region-id.amazonaws.com/test/mydemoawsproxy
```

Browse to the URL. Information similar to the following should be displayed:

```
{"ListTopicsResponse": {"ListTopicsResult": {"NextToken": null, "Topics": [{"TopicArn": "arn:aws:sns:us-east-1:80398EXAMPLE:MySNSTopic-1"}, {"TopicArn": "arn:aws:sns:us-east-1:80398EXAMPLE:MySNSTopic-2"}, ..., {"TopicArn": "arn:aws:sns:us-east-1:80398EXAMPLE:MySNSTopic-N"}]}, "ResponseMetadata": {"RequestId": "abc1de23-45fa-6789-b0c1-d2e345fa6b78"}}}
```

Step 7: Clean up

You can delete the IAM resources the AWS service proxy needs to work.

Warning

If you delete an IAM resource an AWS service proxy relies on, that AWS service proxy and any APIs that rely on it will no longer work. Deleting an IAM resource cannot be undone. If you want to use the IAM resource again, you must re-create it.

To delete the associated IAM resources

1. Open the IAM console at <https://console.aws.amazon.com/iam/>.
2. In the **Details** area, choose **Roles**.
3. Select **APIGatewayAWSProxyExecRole**, and then choose **Role Actions, Delete Role**. When prompted, choose **Yes, Delete**.
4. In the **Details** area, choose **Policies**.
5. Select **APIGatewayAWSProxyExecPolicy**, and then choose **Policy Actions, Delete**. When prompted, choose **Delete**.

You have reached the end of this walkthrough. For more detailed discussions about creating API as an AWS service proxy, see [Tutorial: Create a REST API as an Amazon S3 proxy](#), [Tutorial: Create a calculator REST API with two AWS service integrations and one Lambda non-proxy integration](#), or [Tutorial: Create a REST API as an Amazon Kinesis proxy](#).

Tutorial: Create a calculator REST API with two AWS service integrations and one Lambda non-proxy integration

The [the section called “Tutorial: Create a REST API with a Lambda non-proxy integration”](#) uses Lambda Function integration exclusively. Lambda Function integration is a special case of the AWS Service integration type that performs much of the integration setup for you, such as automatically adding the required resource-based permissions for invoking the Lambda function. Here, two of the three integrations use AWS Service integration. In this integration type, you have more control, but you'll need to manually perform tasks like creating and specifying an IAM role containing appropriate permissions.

In this tutorial, you'll create a Calc Lambda function that implements basic arithmetic operations, accepting and returning JSON-formatted input and output. Then you'll create a REST API and integrate it with the Lambda function in the following ways:

1. By exposing a GET method on the /calc resource to invoke the Lambda function, supplying the input as query string parameters. (AWS Service integration)
2. By exposing a POST method on the /calc resource to invoke the Lambda function, supplying the input in the method request payload. (AWS Service integration)
3. By exposing a GET on nested /calc/{operand1}/{operand2}/{operator} resources to invoke the Lambda function, supplying the input as path parameters. (Lambda Function integration)

In addition to trying out this tutorial, you may wish to study the [OpenAPI definition file](#) for the Calc API, which you can import into API Gateway by following the instructions in [the section called “OpenAPI”](#).

Topics

- [Create an assumable IAM role](#)
- [Create a Calc Lambda function](#)
- [Test the Calc Lambda function](#)
- [Create a Calc API](#)
- [Integration 1: Create a GET method with query parameters to call the Lambda function](#)
- [Integration 2: Create a POST method with a JSON payload to call the Lambda function](#)

- [Integration 3: Create a GET method with path parameters to call the Lambda function](#)
- [OpenAPI definitions of sample API integrated with a Lambda function](#)

Create an assumable IAM role

In order for your API to invoke your Calc Lambda function, you'll need to have an API Gateway assumable IAM role, which is an IAM role with the following trusted relationship:

JSON

```
{  
    "Version": "2012-10-17",  
    "Statement": [  
        {  
            "Sid": "",  
            "Effect": "Allow",  
            "Principal": {  
                "Service": "apigateway.amazonaws.com"  
            },  
            "Action": "sts:AssumeRole"  
        }  
    ]  
}
```

The role you create will need to have Lambda [InvokeFunction](#) permission. Otherwise, the API caller will receive a `500 Internal Server Error` response. To give the role this permission, you'll attach the following IAM policy to it:

JSON

```
{  
    "Version": "2012-10-17",  
    "Statement": [  
        {  
            "Effect": "Allow",  

```

{

Here's how to accomplish all this:

Create an API Gateway assumable IAM role

1. Log in to the IAM console.
2. Choose **Roles**.
3. Choose **Create Role**.
4. Under **Select type of trusted entity**, choose **AWS Service**.
5. Under **Choose the service that will use this role**, choose **Lambda**.
6. Choose **Next: Permissions**.
7. Choose **Create Policy**.

A new **Create Policy** console window will open up. In that window, do the following:

- a. In the **JSON** tab, replace the existing policy with the following:

JSON

```
{  
    "Version": "2012-10-17",  
    "Statement": [  
        {  
            "Effect": "Allow",  
            "Action": "lambda:InvokeFunction",  
            "Resource": "*"  
        }  
    ]  
}
```

- b. Choose **Review policy**.
- c. Under **Review Policy**, do the following:
 - i. For **Name**, type a name such as **lambda_execute**.
 - ii. Choose **Create Policy**.

8. In the original **Create Role** console window, do the following:

- a. Under **Attach permissions policies**, choose your **lambda_execute** policy from the dropdown list.

If you don't see your policy in the list, choose the refresh button at the top of the list.
(Don't refresh the browser page!)

- b. Choose **Next:Tags**.
- c. Choose **Next:Review**.
- d. For the **Role name**, type a name such as
lambda_invoke_function_assume_apigw_role.
- e. Choose **Create role**.

9. Choose your **lambda_invoke_function_assume_apigw_role** from the list of roles.

10. Choose the **Trust relationships** tab.

11. Choose **Edit trust relationship**.

12. Replace the existing policy with the following:

JSON

```
{
    "Version": "2012-10-17",
    "Statement": [
        {
            "Sid": "",
            "Effect": "Allow",
            "Principal": {
                "Service": [
                    "lambda.amazonaws.com",
                    "apigateway.amazonaws.com"
                ]
            },
            "Action": "sts:AssumeRole"
        }
    ]
}
```

13. Choose **Update Trust Policy**.

14. Make a note of the role ARN for the role you just created. You'll need it later.

Create a Calc Lambda function

Next you'll create a Lambda function using the Lambda console.

1. In the Lambda console, choose **Create function**.
2. Choose **Author from Scratch**.
3. For **Name**, enter **Calc**.
4. For **Runtime**, choose either the latest supported **Node.js** or **Python** runtime.
5. For all other options, use the default setting.
6. Choose **Create function**.
7. Copy the following Lambda function in your preferred runtime and paste it into the code editor in the Lambda console.

Node.js

```
export const handler = async function (event, context) {
    console.log("Received event:", JSON.stringify(event));

    if (
        event.a === undefined ||
        event.b === undefined ||
        event.op === undefined
    ) {
        return "400 Invalid Input";
    }

    const res = {};
    res.a = Number(event.a);
    res.b = Number(event.b);
    res.op = event.op;
    if (isNaN(event.a) || isNaN(event.b)) {
        return "400 Invalid Operand";
    }
    switch (event.op) {
        case "+":
        case "add":
```

```
        res.c = res.a + res.b;
        break;
    case "-":
    case "sub":
        res.c = res.a - res.b;
        break;
    case "*":
    case "mul":
        res.c = res.a * res.b;
        break;
    case "/":
    case "div":
        if (res.b == 0) {
            return "400 Divide by Zero";
        } else {
            res.c = res.a / res.b;
        }
        break;
    default:
        return "400 Invalid Operator";
    }

    return res;
};
```

Python

```
import json


def lambda_handler(event, context):
    print(event)

    try:
        (event['a']) and (event['b']) and (event['op'])
    except KeyError:
        return '400 Invalid Input'

    try:
        res = {
            "a": float(
                event['a']), "b": float(
                event['b']), "op": event['op']}
    
```

```
except ValueError:  
    return '400 Invalid Operand'  
  
if event['op'] == '+':  
    res['c'] = res['a'] + res['b']  
elif event['op'] == '-':  
    res['c'] = res['a'] - res['b']  
elif event['op'] == '*':  
    res['c'] = res['a'] * res['b']  
elif event['op'] == '/':  
    if res['b'] == 0:  
        return '400 Divide by Zero'  
    else:  
        res['c'] = res['a'] / res['b']  
else:  
    return '400 Invalid Operator'  
  
return res
```

8. Under Execution role, choose **Choose an existing role**.
9. Enter the role ARN for the **lambda_invoke_function_assume_apigw_role** role you created earlier.
10. Choose **Deploy**.

This function requires two operands (a and b) and an operator (op) from the event input parameter. The input is a JSON object of the following format:

```
{  
  "a": "Number" | "String",  
  "b": "Number" | "String",  
  "op": "String"  
}
```

This function returns the calculated result (c) and the input. For an invalid input, the function returns either the null value or the "Invalid op" string as the result. The output is of the following JSON format:

```
{
```

```
"a": "Number",
"b": "Number",
"op": "String",
"c": "Number" | "String"
}
```

You should test the function in the Lambda console before integrating it with the API in the next step.

Test the Calc Lambda function

Here's how to test your Calc function in the Lambda console:

1. Choose the **Test** tab.
2. For the test event name, enter **calc2plus5**.
3. Replace the test event definition with the following:

```
{
  "a": "2",
  "b": "5",
  "op": "+"
}
```

4. Choose **Save**.
5. Choose **Test**.
6. Expand **Execution result: succeeded**. You should see the following:

```
{
  "a": 2,
  "b": 5,
  "op": "+",
  "c": 7
}
```

Create a Calc API

The following procedure shows how to create an API for the Calc Lambda function you just created. In subsequent sections, you'll add resources and methods to it.

To create an API

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. If this is your first time using API Gateway, you see a page that introduces you to the features of the service. Under **REST API**, choose **Build**. When the **Create Example API** popup appears, choose **OK**.

If this is not your first time using API Gateway, choose **Create API**. Under **REST API**, choose **Build**.

3. For **API name**, enter **LambdaCalc**.
4. (Optional) For **Description**, enter a description.
5. Keep **API endpoint type** set to **Regional**.
6. For **IP address type**, select **IPv4**.
7. Choose **Create API**.

Integration 1: Create a GET method with query parameters to call the Lambda function

By creating a GET method that passes query string parameters to the Lambda function, you enable the API to be invoked from a browser. This approach can be useful, especially for APIs that allow open access.

After you create an API, you create a resource. Typically, API resources are organized in a resource tree according to the application logic. For this step, you create a **/calc** resource.

To create a **/calc** resource

1. Choose **Create resource**.
2. Keep **Proxy resource** turned off.
3. Keep **Resource path** as **/**.
4. For **Resource name**, enter **calc**.
5. Keep **CORS (Cross Origin Resource Sharing)** turned off.
6. Choose **Create resource**.

By creating a GET method that passes query string parameters to the Lambda function, you enable the API to be invoked from a browser. This approach can be useful, especially for APIs that allow open access.

In this method, Lambda requires that the POST request be used to invoke any Lambda function. This example shows that the HTTP method in a frontend method request can be different from the integration request in the backend.

To create a GET method

1. Select the **/calc** resource, and then choose **Create method**.
2. For **Method type**, select **GET**.
3. For **Integration type**, select **AWS service**.
4. For **AWS Region**, select the AWS Region where you created your Lambda function.
5. For **AWS service**, select **Lambda**.
6. Keep **AWS subdomain** blank.
7. For **HTTP method**, select **POST**.
8. For **Action type**, select **Use path override**. This option allows us to specify the ARN of the [Invoke](#) action to execute our Calc function.
9. For **Path override**, enter **2015-03-31/functions/arn:aws:lambda:*us-east-2:account-id:function:Calc/invocations***. For **account-id**, enter your AWS account ID. For **us-east-2**, enter the AWS Region where you created your Lambda function.
10. For **Execution role**, enter the role ARN for **lambda_invoke_function_assume_apigw_role**.
11. Do not change the settings of **Credential cache** and **Default timeout**.
12. Choose **Method request settings**.
13. For **Request validator**, select **Validate query string parameters and headers**.

This setting will cause an error message to return if the client does not specify the required parameters.

14. Choose **URL query string parameters**.

Now you set up query string parameters for the **GET** method on the **/calc** resource so it can receive input on behalf of the backend Lambda function.

To create the query string parameters do the following:

- a. Choose **Add query string**.
- b. For **Name**, enter **operand1**.
- c. Turn on **Required**.
- d. Keep **Caching** turned off.

Repeat the same steps and create a query string named **operand2** and a query string named **operator**.

15. Choose **Create method**.

Now, you create a mapping template to translate the client-supplied query strings to the integration request payload as required by the Calc function. This template maps the three query string parameters declared in **Method request** into designated property values of the JSON object as the input to the backend Lambda function. The transformed JSON object will be included as the integration request payload.

To map input parameters to the integration request

1. On the **Integration request** tab, under **Integration request settings**, choose **Edit**.
2. For **Request body passthrough**, select **When there are no templates defined (recommended)**.
3. Choose **Mapping templates**.
4. Choose **Add mapping template**.
5. For **Content type**, enter **application/json**.
6. For **Template body**, enter the following code:

```
{  
    "a": "$input.params('operand1')",  
    "b": "$input.params('operand2')",  
    "op": "$input.params('operator')"  
}
```

7. Choose **Save**.

You can now test your GET method to verify that it has been properly set up to invoke the Lambda function.

To test the GET method

1. Choose the **Test** tab. You might need to choose the right arrow button to show the tab.
2. For **Query strings**, enter **operand1=2&operand2=3&operator=+**.
3. Choose **Test**.

The results should look similar to this:

/calc - GET method test results		
Request	Latency ms	Status
/calc? operand1=2&operand2=3&operator=+	555	200
Response body		
{ "a": 2, "b": 3, "op": "+", "c": 5 }		

Integration 2: Create a POST method with a JSON payload to call the Lambda function

By creating a POST method with a JSON payload to call the Lambda function, you make it so that the client must provide the necessary input to the backend function in the request body. To ensure that the client uploads the correct input data, you'll enable request validation on the payload.

To create a POST method with a JSON payload

1. Select the **/calc** resource, and then choose **Create method**.
2. For **Method type**, select **POST**.
3. For **Integration type**, select **AWS service**.
4. For **AWS Region**, select the AWS Region where you created your Lambda function.
5. For **AWS service**, select **Lambda**.
6. Keep **AWS subdomain** blank.
7. For **HTTP method**, select **POST**.
8. For **Action type**, select **Use path override**. This option allows us to specify the ARN of the [Invoke](#) action to execute our Calc function.
9. For **Path override**, enter **2015-03-31/functions/arn:aws:lambda:*us-east-2:account-id:function:Calc/invocations***. For **account-id**, enter your AWS account ID. For **us-east-2**, enter the AWS Region where you created your Lambda function.

10. For **Execution role**, enter the role ARN for `lambda_invoke_function_assume_apigw_role`.
11. Do not change the settings of **Credential cache** and **Default timeout**.
12. Choose **Create method**.

Now you create an **input** model to describe the input data structure and validate the incoming request body.

To create an input model

1. In the main navigation pane, choose **Models**.
2. Choose **Create model**.
3. For **Name**, enter **input**.
4. For **Content type**, enter **application/json**.

If no matching content type is found, request validation is not performed. To use the same model regardless of the content type, enter **\$default**.

5. For **Model schema**, enter the following model:

```
{  
    "type": "object",  
    "properties": {  
        "a": {"type": "number"},  
        "b": {"type": "number"},  
        "op": {"type": "string"}  
    "title": "input"  
}
```

6. Choose **Create model**.

You now create an **output** model. This model describes the data structure of the calculated output from the backend. It can be used to map the integration response data to a different model. This tutorial relies on the passthrough behavior and does not use this model.

To create an output model

1. Choose **Create model**.

2. For **Name**, enter **output**.
3. For **Content type**, enter **application/json**.

If no matching content type is found, request validation is not performed. To use the same model regardless of the content type, enter **\$default**.

4. For **Model schema**, enter the following model:

```
{  
    "type": "object",  
    "properties": {  
        "c": {"type": "number"}  
    },  
    "title": "output"  
}
```

5. Choose **Create model**.

You now create a **result** model. This model describes the data structure of the returned response data. It references both the **input** and **output** schemas defined in your API.

To create a result model

1. Choose **Create model**.
2. For **Name**, enter **result**.
3. For **Content type**, enter **application/json**.

If no matching content type is found, request validation is not performed. To use the same model regardless of the content type, enter **\$default**.

4. For **Model schema**, enter the following model with your *restapi-id*. Your *restapi-id* is listed in parenthesis at the top of the console in the following flow: API Gateway > APIs > LambdaCalc (*abc123*).

```
{  
    "type": "object",  
    "properties": {  
        "input": {  
            "$ref": "https://apigateway.amazonaws.com/restapis/restapi-id/models/  
input"  
        },  
    },  
}
```

```
        "output":{  
            "$ref":"https://apigateway.amazonaws.com/restapis/restapi-id/models/  
output"  
        },  
        "title":"result"  
    }  
}
```

5. Choose **Create model**.

You now configure the method request of your POST method to enable request validation on the incoming request body.

To enable request validation on the POST method

1. In the main navigation pane, choose **Resources**, and then select the POST method from the resource tree.
2. On the **Method request** tab, under **Method request settings**, choose **Edit**.
3. For **Request validator**, select **Validate body**.
4. Choose **Request body**, and then choose **Add model**.
5. For **Content type**, enter **application/json**.

If no matching content type is found, request validation is not performed. To use the same model regardless of the content type, enter **\$default**.

6. For **Model**, select **input**.
7. Choose **Save**.

You can now test your POST method to verify that it has been properly set up to invoke the Lambda function.

To test the POST method

1. Choose the **Test** tab. You might need to choose the right arrow button to show the tab.
2. For **Request body**, enter the following JSON payload.

```
{  
    "a": 1,  
}
```

```
"b": 2,  
"op": "+"  
}
```

3. Choose **Test**.

You should see the following output:


```
{  
  "a": 1,  
  "b": 2,  
  "op": "+",  
  "c": 3  
}
```

Integration 3: Create a GET method with path parameters to call the Lambda function

Now you'll create a GET method on a resource specified by a sequence of path parameters to call the backend Lambda function. The path parameter values specify the input data to the Lambda function. You'll use a mapping template to map the incoming path parameter values to the required integration request payload.

The resulting API resource structure will look like this:

Resources



To create a `/{operand1}/{operand2}/{operator}` resource

1. Choose **Create resource**.
2. For **Resource path**, select `/calc`.
3. For **Resource name**, enter `{operand1}`.
4. Keep **CORS (Cross Origin Resource Sharing)** turned off.
5. Choose **Create resource**.
6. For **Resource path**, select `/calc/{operand1}/`.
7. For **Resource name**, enter `{operand2}`.
8. Keep **CORS (Cross Origin Resource Sharing)** turned off.
9. Choose **Create resource**.
10. For **Resource path**, select `/calc/{operand1}/{operand2}/`.
11. For **Resource name**, enter `{operator}`.

12. Keep **CORS (Cross Origin Resource Sharing)** turned off.

13. Choose **Create resource**.

This time you'll use the built-in Lambda integration in the API Gateway console to set up the method integration.

To set up a method integration

1. Select the **/{operand1}/{operand2}/{operator}** resource, and then choose **Create method**.
2. For **Method type**, select **GET**.
3. For **Integration type**, select **Lambda**.
4. Keep **Lambda proxy integration** turned off.
5. For **Lambda function**, select the AWS Region where you created your Lambda function and enter **Calc**.
6. Keep **Default timeout** turned on.
7. Choose **Create method**.

You now create a mapping template to map the three URL path parameters, declared when the **/calc/{operand1}/{operand2}/{operator}** resource was created, into designated property values in the JSON object. Because URL paths must be URL-encoded, the division operator must be specified as %2F instead of /. This template translates the %2F into '/' before passing it to the Lambda function.

To create a mapping template

1. On the **Integration request** tab, under **Integration request settings**, choose **Edit**.
2. For **Request body passthrough**, select **When there are no templates defined (recommended)**.
3. Choose **Mapping templates**.
4. For **Content type**, enter **application/json**.
5. For **Template body**, enter the following code:

```
{  
  "a": "$input.params('operand1')",  
  "b": "$input.params('operand2')",
```

```
"op":  
#if($input.params('operator')=='%2F')"/#${else}"$input.params('operator')"#end  
}
```

6. Choose **Save**.

You can now test your GET method to verify that it has been properly set up to invoke the Lambda function and pass the original output through the integration response without mapping.

To test the GET method

1. Choose the **Test** tab. You might need to choose the right arrow button to show the tab.
2. For the **Path**, do the following:
 - a. For **operand1**, enter **1**.
 - b. For **operand2**, enter **1**.
 - c. For **operator**, enter **+**.
3. Choose **Test**.
4. The result should look like this:

/calc/{operand1}/{operand2}/{operator}		GET method test results	
Request	/calc/1/1/+	Latency ms	285
Response body			Status
{ "a":1,"b":1,"op": "+","c":2 }			200

Next, you model the data structure of the method response payload after the result schema.

By default, the method response body is assigned an empty model. This will cause the integration response body to be passed through without mapping. However, when you generate an SDK for one of the strongly-type languages, such as Java or Objective-C, your SDK users will receive an empty object as the result. To ensure that both the REST client and SDK clients receive the desired result, you must model the response data using a predefined schema. Here you'll define a model for the method response body and to construct a mapping template to translate the integration response body into the method response body.

To create a method response

1. On the **Method response** tab, under **Response 200**, choose **Edit**.
2. Under **Response body**, choose **Add model**.
3. For **Content type**, enter **application/json**.
4. For **Model**, select **result**.
5. Choose **Save**.

Setting the model for the method response body ensures that the response data will be cast into the `result` object of a given SDK. To make sure that the integration response data is mapped accordingly, you'll need a mapping template.

To create a mapping template

1. On the **Integration response** tab, under **Default - Response**, choose **Edit**.
2. Choose **Mapping templates**.
3. For **Content type**, enter **application/json**.
4. For **Template body**, enter the following code:

```
#set($inputRoot = $input.path('$'))  
{  
    "input" : {  
        "a" : $inputRoot.a,  
        "b" : $inputRoot.b,  
        "op" : "$inputRoot.op"  
    },  
    "output" : {  
        "c" : $inputRoot.c  
    }  
}
```

5. Choose **Save**.

To test the mapping template

1. Choose the **Test** tab. You might need to choose the right arrow button to show the tab.
2. For the **Path**, do the following:

- a. For **operand1**, enter **1**.
 - b. For **operand2**, enter **2**.
 - c. For **operator**, enter **+**.
3. Choose **Test**.
4. The result will look like the following:

```
{  
  "input": {  
    "a": 1,  
    "b": 2,  
    "op": "+"  
  },  
  "output": {  
    "c": 3  
  }  
}
```

At this point, you can only call the API using the **Test** feature in the API Gateway console. To make it available to clients, you'll need to deploy your API. Always be sure to redeploy your API whenever you add, modify, or delete a resource or method, update a data mapping, or update stage settings. Otherwise, new features or updates will not be available to clients of your API. as follows:

To deploy the API

1. Choose **Deploy API**.
2. For **Stage**, select **New stage**.
3. For **Stage name**, enter **Prod**.
4. (Optional) For **Description**, enter a description.
5. Choose **Deploy**.
6. (Optional) Under **Stage details**, for **Invoke URL**, you can choose the copy icon to copy your API's invoke URL. You can use this with tools such as [Postman](#) and [cURL](#) to test your API.

Note

Always redeploy your API whenever you add, modify, or delete a resource or method, update a data mapping, or update stage settings. Otherwise, new features or updates will not be available to clients of your API.

OpenAPI definitions of sample API integrated with a Lambda function

OpenAPI 2.0

```
{  
  "swagger": "2.0",  
  "info": {  
    "version": "2017-04-20T04:08:08Z",  
    "title": "LambdaCalc"  
  },  
  "host": "uojnr9hd57.execute-api.us-east-1.amazonaws.com",  
  "basePath": "/test",  
  "schemes": [  
    "https"  
  ],  
  "paths": {  
    "/calc": {  
      "get": {  
        "consumes": [  
          "application/json"  
        ],  
        "produces": [  
          "application/json"  
        ],  
        "parameters": [  
          {  
            "name": "operand2",  
            "in": "query",  
            "required": true,  
            "type": "string"  
          },  
          {  
            "name": "operator",  
            "in": "query",  
            "type": "string"  
          }  
        ]  
      }  
    }  
  }  
}
```

```
        "required": true,
        "type": "string"
    },
    {
        "name": "operand1",
        "in": "query",
        "required": true,
        "type": "string"
    }
],
"responses": {
    "200": {
        "description": "200 response",
        "schema": {
            "$ref": "#/definitions/Result"
        },
        "headers": {
            "operand_1": {
                "type": "string"
            },
            "operand_2": {
                "type": "string"
            },
            "operator": {
                "type": "string"
            }
        }
    }
},
"x-amazon-apigateway-request-validator": "Validate query string parameters and headers",
"x-amazon-apigateway-integration": {
    "credentials": "arn:aws:iam::123456789012:role/apigAwsProxyRole",
    "responses": {
        "default": {
            "statusCode": "200",
            "responseParameters": {
                "method.response.header.operator": "integration.response.body.op",
                "method.response.header.operand_2": "integration.response.body.b",
                "method.response.header.operand_1": "integration.response.body.a"
            },
            "responseTemplates": {

```

```
        "application/json": "#set($res = $input.path('$'))\n{\n    \"result\"\n    : \"$res.a, $res.b, $res.op => $res.c\",\\n    \"a\": \"$res.a\",\\n    \"b\":\n    \"$res.b\",\\n    \"op\": \"$res.op\",\\n    \"c\": \"$res.c\"\n}\n},\n    \"uri\": \"arn:aws:apigateway:us-west-2:lambda:path/2015-03-31/functions/\narn:aws:lambda:us-west-2:123456789012:function:Calc/invocations\",\n    \"passthroughBehavior\": \"when_no_match\",\n    \"httpMethod\": \"POST\",\n    \"requestTemplates\": {\n        \"application/json\": \"{\\n            \"a\": \"$input.params('operand1')\",\\n            \"b\": \"$input.params('operand2')\", \\n            \"op\": \"$input.params('operator')\"\n        }\"\\n    },\n    \"type\": \"aws\"\n},\n},\n    \"post\": {\n        \"consumes\": [\n            \"application/json\"\n        ],\n        \"produces\": [\n            \"application/json\"\n        ],\n        \"parameters\": [\n            {\n                \"in\": \"body\",\n                \"name\": \"Input\",\n                \"required\": true,\n                \"schema\": {\n                    \"$ref\": \"#/definitions/Input\"\n                }\n            }\n        ],\n        \"responses\": {\n            \"200\": {\n                \"description\": \"200 response\",\n                \"schema\": {\n                    \"$ref\": \"#/definitions/Result\"\n                }\n            }\n        },\n        \"x-amazon-apigateway-request-validator\": \"Validate body\",
```

```
"x-amazon-apigateway-integration": {
    "credentials": "arn:aws:iam::123456789012:role/apigAwsProxyRole",
    "responses": {
        "default": {
            "statusCode": "200",
            "responseTemplates": {
                "application/json": "#set($inputRoot = $input.path('$'))\n{\n  \"a\" : $inputRoot.a,\n  \"b\" : $inputRoot.b,\n  \"op\" : $inputRoot.op,\n  \"c\" : $inputRoot.c\n}"
            }
        }
    },
    "uri": "arn:aws:apigateway:us-west-2:lambda:path/2015-03-31/functions/arn:aws:lambda:us-west-2:123456789012:function:Calc/invocations",
    "passthroughBehavior": "when_no_templates",
    "httpMethod": "POST",
    "type": "aws"
},
"/calc/{operand1}/{operand2}/{operator}": {
    "get": {
        "consumes": [
            "application/json"
        ],
        "produces": [
            "application/json"
        ],
        "parameters": [
            {
                "name": "operand2",
                "in": "path",
                "required": true,
                "type": "string"
            },
            {
                "name": "operator",
                "in": "path",
                "required": true,
                "type": "string"
            },
            {
                "name": "operand1",
                "in": "path",
                "required": true,
                "type": "string"
            }
        ]
    }
}
```

```
        "required": true,
        "type": "string"
    ],
],
"responses": {
    "200": {
        "description": "200 response",
        "schema": {
            "$ref": "#/definitions/Result"
        }
    }
},
"x-amazon-apigateway-integration": {
    "credentials": "arn:aws:iam::123456789012:role/apigAwsProxyRole",
    "responses": {
        "default": {
            "statusCode": "200",
            "responseTemplates": {
                "application/json": "#set($inputRoot = $input.path('$'))\n\\\"input\\\" : {\n    \\\"a\\\" : $inputRoot.a,\n    \\\"b\\\" : $inputRoot.b,\n    \\\"op\\\" : \"$inputRoot.op\"\n},\n    \\\"output\\\" : {\n        \\\"c\\\" : $inputRoot.c\n    }\n}"
            }
        }
    },
    "uri": "arn:aws:apigateway:us-west-2:lambda:path/2015-03-31/functions/arn:aws:lambda:us-west-2:123456789012:function:Calc/invocations",
    "passthroughBehavior": "when_no_templates",
    "httpMethod": "POST",
    "requestTemplates": {
        "application/json": "{\n    \\\"a\\\": \"$input.params('operand1')\",\n    \\\"b\\\": \"$input.params('operand2')\",\n    \\\"op\\\":\n        #if($input.params('operator')=='%2F')\n            #else\n                \"$input.params('operator')\n            #end\n        \\n\n    }\n},\n        \"contentHandling\": \"CONVERT_TO_TEXT\","
    },
    "type": "aws"
}
},
"definitions": {
    "Input": {
        "type": "object",
        "required": [

```

```
"a",
"b",
"op"
],
"properties": {
  "a": {
    "type": "number"
  },
  "b": {
    "type": "number"
  },
  "op": {
    "type": "string",
    "description": "binary op of [ '+', 'add', ' - ', 'sub', ' * ', 'mul', '%2F',
'div' ]"
  }
},
"title": "Input"
},
"Output": {
  "type": "object",
  "properties": {
    "c": {
      "type": "number"
    }
  },
  "title": "Output"
},
"Result": {
  "type": "object",
  "properties": {
    "input": {
      "$ref": "#/definitions/Input"
    },
    "output": {
      "$ref": "#/definitions/Output"
    }
  },
  "title": "Result"
}
},
"x-amazon-apigateway-requestValidators": {
  "Validate body": {
    "validateRequestParameters": false,
```

```
        "validateRequestBody": true
    },
    "Validate query string parameters and headers": {
        "validateRequestParameters": true,
        "validateRequestBody": false
    }
}
```

Tutorial: Create a REST API as an Amazon S3 proxy

As an example to showcase using a REST API in API Gateway to proxy Amazon S3, this section describes how to create and configure a REST API to expose the following Amazon S3 operations:

- Expose GET on the API's root resource to [list all of the Amazon S3 buckets of a caller](#).
- Expose GET on a Folder resource to [view a list of all of the objects in an Amazon S3 bucket](#).
- Expose GET on a Folder/Item resource to [view or download an object from an Amazon S3 bucket](#).

You might want to import the sample API as an Amazon S3 proxy, as shown in [OpenAPI definitions of the sample API as an Amazon S3 proxy](#). This sample contains more exposed methods. For instructions on how to import an API using the OpenAPI definition, see [Develop REST APIs using OpenAPI in API Gateway](#).

Note

To integrate your API Gateway API with Amazon S3, you must choose a region where both the API Gateway and Amazon S3 services are available. For region availability, see [Amazon API Gateway Endpoints and Quotas](#).

Topics

- [Set up IAM permissions for the API to invoke Amazon S3 actions](#)
- [Create API resources to represent Amazon S3 resources](#)
- [Expose an API method to list the caller's Amazon S3 buckets](#)
- [Expose API methods to access an Amazon S3 bucket](#)
- [Expose API methods to access an Amazon S3 object in a bucket](#)

- [OpenAPI definitions of the sample API as an Amazon S3 proxy](#)
- [Call the API using a REST API client](#)

Set up IAM permissions for the API to invoke Amazon S3 actions

To allow the API to invoke Amazon S3 actions, you must have the appropriate IAM policies attached to an IAM role. In this step, you create a new IAM role.

To create the AWS service proxy execution role

1. Sign in to the AWS Management Console and open the IAM console at <https://console.aws.amazon.com/iam/>.
2. Choose **Roles**.
3. Choose **Create role**.
4. Choose **AWS service** under **Select type of trusted entity**, and then select **API Gateway** and select **Allows API Gateway to push logs to CloudWatch Logs**.
5. Choose **Next**, and then choose **Next**.
6. For **Role name**, enter **APIGatewayS3ProxyPolicy**, and then choose **Create role**.
7. In the **Roles** list, choose the role you just created. You may need to scroll or use the search bar to find the role.
8. For the selected role, select the **Add permissions** tab.
9. Choose **Attach policies** from the dropdown list.
10. In the search bar, enter **AmazonS3FullAccess** and choose **Add permissions**.

 **Note**

This tutorial uses a managed policy for simplicity. As a best practice, you should create your own IAM policy to grant the minimum permissions required.

11. Note the newly created **Role ARN**, you will use it later.

Create API resources to represent Amazon S3 resources

You use the API's root (/) resource as the container of an authenticated caller's Amazon S3 buckets. You also create a Folder and Item resources to represent a particular Amazon S3 bucket and a

particular Amazon S3 object, respectively. The folder name and object key will be specified, in the form of path parameters as part of a request URL, by the caller.

 **Note**

When accessing objects whose object key includes / or any other special character, the character needs to be URL encoded. For example, test/test.txt should be encoded to test%2Ftest.txt.

To create an API resource that exposes the Amazon S3 service features

1. In the same AWS Region you created your Amazon S3 bucket, create an API named **MyS3**. This API's root resource (/) represents the Amazon S3 service. In this step, you create two additional resources **/{folder}** and **/{item}**.
2. Choose **Create resource**.
3. Keep **Proxy resource** turned off.
4. For **Resource path**, select /.
5. For **Resource name**, enter **{folder}**.
6. Keep **CORS (Cross Origin Resource Sharing)** unchecked.
7. Choose **Create resource**.
8. Select the **/{folder}** resource, and then choose **Create resource**.
9. Use the previous steps to create a child resource of **/{folder}** named **{item}**.

Your final API should look similar to the following:

The screenshot shows the 'Resources' section of the Amazon API Gateway console. On the left, a tree view shows a root resource with three child resources: '/', '{folder}', and '{item}'. A 'Create resource' button is located at the top of this tree. To the right, the 'Resource details' panel shows the path '/{folder}/{item}' and a 'Resource ID' of 'efg456'. There are buttons for 'Delete', 'Update documentation', and 'Enable CORS'. Below this is the 'Methods (0)' panel, which includes columns for 'Method type', 'Integration type', 'Authorization', and 'API key'. It displays 'No methods' and 'No methods defined.'.

Expose an API method to list the caller's Amazon S3 buckets

Getting the list of Amazon S3 buckets of the caller involves invoking the [GET Service](#) action on Amazon S3. On the API's root resource, (/), create the GET method. Configure the GET method to integrate with the Amazon S3, as follows.

To create and initialize the API's GET / method

1. Select the / resource, and then choose **Create method**.
2. For method type, select **GET**.
3. For **Integration type**, select **AWS service**.
4. For **AWS Region**, select the AWS Region where you created your Amazon S3 bucket.
5. For **AWS service**, select **Amazon Simple Storage Service**.
6. Keep **AWS subdomain** blank.
7. For **HTTP method**, select **GET**.
8. For **Action type**, select **Use path override**.

With path override, API Gateway forwards the client request to Amazon S3 as the corresponding [Amazon S3 REST API path-style request](#), in which a Amazon S3 resource is expressed by the resource path of the s3-host-name/bucket/key pattern. API Gateway sets the s3-host-name and passes the client specified bucket and key from the client to Amazon S3.


9. For **Path override**, enter /.

10. For **Execution role**, enter the role ARN for **APIGatewayS3ProxyPolicy**.

11. Choose **Method request settings**.

You use the method request settings to control who can call this method of your API.

12. For **Authorization**, from the dropdown menu, select AWS_IAM.



13. Choose **Create method**.

This setup integrates the frontend GET `https://your-api-host/stage/` request with the backend GET `https://your-s3-host/`.

For your API to return successful responses and exceptions properly to the caller, you declare the 200, 400 and 500 responses in **Method response**. You use the default mapping for 200 responses so that backend responses of the status code not declared here will be returned to the caller as 200 ones.

To declare response types for the GET / method

1. On the **Method response** tab, under **Response 200**, choose **Edit**.
2. Choose **Add header** and do the following:
 - a. For **Header name**, enter **Content-Type**.
 - b. Choose **Add header**.

Repeat these steps to create a **Timestamp** header and a **Content-Length** header.

3. Choose **Save**.
4. On the **Method response** tab, under **Method responses**, choose **Create response**.
5. For **HTTP status code**, enter **400**.

You do not set any headers for this response.

6. Choose **Save**.
7. Repeat the following steps to create the 500 response.

You do not set any headers for this response.

Because the successful integration response from Amazon S3 returns the bucket list as an XML payload and the default method response from API Gateway returns a JSON payload, you must map the backend Content-Type header parameter value to the frontend counterpart. Otherwise, the client will receive application/json for the content type when the response body is actually an XML string. The following procedure shows how to set this up. In addition, you also want to display to the client other header parameters, such as Date and Content-Length.

To set up response header mappings for the GET / method

1. On the **Integration response** tab, under **Default - Response**, choose **Edit**.
2. For the **Content-Length** header, enter **integration.response.header.Content-Length** for the mapping value.
3. For the **Content-Type** header, enter **integration.response.header.ContentType** for the mapping value.
4. For the **Timestamp** header, enter **integration.response.header.Date** for the mapping value.
5. Choose **Save**. The result should look similar to the following:

The screenshot shows the 'Integration response' tab selected in the top navigation bar. Below it, the 'Integration responses' section is displayed. It includes a 'Default - Response' card with fields for 'HTTP status regex' (empty), 'Content handling' (Passthrough), and 'Method response status code' (200). A 'Default mapping' of 'True' is also shown. Below this is a 'Header mappings' section containing three entries: 'method.response.header.Content-Length' maps to 'integration.response.header.Content-Length', 'method.response.header.Content-Type' maps to 'integration.response.header.Content-Type', and 'method.response.header.Timestamp' maps to 'integration.response.header.Date'. At the bottom, a 'Mapping templates' section indicates 'No templates' and states 'You don't have any mapping templates.'

Method request | Integration request | **Integration response** | Method

Integration responses

[Create response](#)

Default - Response

HTTP status regex [Info](#)
-

Content handling [Learn more](#) ↗
Passthrough

Method response status code
200

Default mapping
True

Header mappings (3)

Name	Mapping value
method.response.header.Content-Length	integration.response.header.Content-Length
method.response.header.Content-Type	integration.response.header.Content-Type
method.response.header.Timestamp	integration.response.header.Date

Mapping templates (0)

No templates

You don't have any mapping templates.

6. On the **Integration response** tab, under **Integration responses**, choose **Create response**.
7. For **HTTP status regex**, enter **4\d{2}**. This maps all 4xx HTTP response status codes to the method response.
8. For **Method response status code**, select **400**.
9. Choose **Create**.
10. Repeat the following steps to create an integration response for the 500 method response. For **HTTP status regex**, enter **5\d{2}**.

As a good practice, you can test the API you have configured so far.

To test the GET / method

1. Choose the **Test** tab. You might need to choose the right arrow button to show the tab.
2. Choose **Test**. The result should look like the following image:

The screenshot shows the AWS Lambda Test API interface. At the top, there are tabs: Method request, Integration request, Integration response, Method response, and Test. The Test tab is selected. Below the tabs, there's a section titled "Test method" with the sub-instruction "Make a test call to your method. When you make a test call, API Gateway skips authorization and directly invokes your method." Under "Query strings", the value "param1=value1¶m2=value2" is shown. Under "Headers", the values "header1:value1" and "header2:value2" are listed. Under "Client certificate", it says "No client certificates have been generated." A "Test" button is highlighted in yellow. Below the button is a table with one row:

Request	Latency ms	Status
/	74	200

Under the table, the "Response body" is displayed as an XML document:

```
<?xml version="1.0" encoding="UTF-8"?>
<ListAllMyBucketsResult xmlns="http://s3.amazonaws.com/doc/2006-03-01/"><Owner>
<ID>abcd123456789abcd</ID><DisplayName>weizhang</DisplayName></Owner><Buckets><Bucket>
<Name>amzn-s3-demo-bucket</Name><CreationDate>2023-06-29T17:52:42.000</CreationDate>
</Bucket><Bucket><Name>amzn-s3-demo-bucket1</Name><CreationDate>2023-02-
```

Expose API methods to access an Amazon S3 bucket

To work with an Amazon S3 bucket, you expose the GET method on the `{folder}` resource to list objects in a bucket. The instructions are similar to those described in [Expose an API method to list the caller's Amazon S3 buckets](#). For more methods, you can import the sample API here, [OpenAPI definitions of the sample API as an Amazon S3 proxy](#).

To expose the GET method on a folder resource

1. Select the **{folder}** resource, and then choose **Create method**.
2. For method type, select **GET**.
3. For **Integration type**, select **AWS service**.
4. For **AWS Region**, select the AWS Region where you created your Amazon S3 bucket.
5. For **AWS service**, select **Amazon Simple Storage Service**.
6. Keep **AWS subdomain** blank.
7. For **HTTP method**, select **GET**.
8. For **Action type**, select **Use path override**.
9. For **Path override**, enter **{bucket}**.
10. For **Execution role**, enter the role ARN for **APIGatewayS3ProxyPolicy**.
11. Choose **Create method**.

You set the **{folder}** path parameter in the Amazon S3 endpoint URL. You need to map the **{folder}** path parameter of the method request to the **{bucket}** path parameter of the integration request.

To map **{folder}** to **{bucket}**

1. On the **Integration request** tab, under **Integration request settings**, choose **Edit**.
2. Choose **URL path parameters**, and then choose **Add path parameter**.
3. For **Name**, enter **bucket**.
4. For **Mapped from**, enter **method.request.path.folder**.
5. Choose **Save**.

Now, you test your API.

To test the **/{folder}** GET method.

1. Choose the **Test** tab. You might need to choose the right arrow button to show the tab.
2. Under **Path**, for **folder**, enter the name of your bucket.
3. Choose **Test**.

The test result will contain a list of object in your bucket.

Test method

Make a test call to your method. When you make a test call, API Gateway skips authorization and directly invokes your method.

Path

folder

amzn-s3-demo-bucket

Query strings

param1=value1¶m2=value2

Headers

Enter a header name and value separated by a colon (:). Use a new line for each header.

header1:value1
header2:value2

Client certificate

No client certificates have been generated.

Test

/{folder} - GET method test results

Request
/amzn-s3-demo-bucket

Latency ms

59

Status

200

Response body

```
<?xml version="1.0" encoding="UTF-8"?>
<ListBucketResult xmlns="http://s3.amazonaws.com/doc/2006-03-01/"><Name>amzn-s3-demo-
bucket</Name><Prefix></Prefix><Marker></Marker><MaxKeys>1000</MaxKeys>
<IsTruncated>false</IsTruncated><Contents><Key>test.txt</Key><LastModified>2023-10-
```

Expose API methods to access an Amazon S3 object in a bucket

Amazon S3 supports GET, DELETE, HEAD, OPTIONS, POST and PUT actions to access and manage objects in a given bucket. In this tutorial, you expose a GET method on the {folder}/{item} resource to get an image from a bucket. For more applications of the {folder}/{item} resource, see the sample API, [OpenAPI definitions of the sample API as an Amazon S3 proxy](#).

To expose the GET method on a item resource

1. Select the **{item}** resource, and then choose **Create method**.
2. For method type, select **GET**.
3. For **Integration type**, select **AWS service**.

4. For **AWS Region**, select the AWS Region where you created your Amazon S3 bucket.
5. For **AWS service**, select **Amazon Simple Storage Service**.
6. Keep **AWS subdomain** blank.
7. For **HTTP method**, select **GET**.
8. For **Action type**, select **Use path override**.
9. For **Path override**, enter **{bucket}/{object}**.
10. For **Execution role**, enter the role ARN for **APIGatewayS3ProxyPolicy**.
11. Choose **Create method**.

You set the **{folder}** and **{item}** path parameters in the Amazon S3 endpoint URL. You need to map the path parameter of the method request to the path parameter of the integration request.

In this step, you do the following:

- Map the **{folder}** path parameter of the method request to the **{bucket}** path parameter of the integration request.
- Map the **{item}** path parameter of the method request to the **{object}** path parameter of the integration request.

To map **{folder}** to **{bucket}** and **{item}** to **{object}**

1. On the **Integration request** tab, under **Integration request settings**, choose **Edit**.
2. Choose **URL path parameters**.
3. Choose **Add path parameter**.
4. For **Name**, enter **bucket**.
5. For **Mapped from**, enter **method.request.path.folder**.
6. Choose **Add path parameter**.
7. For **Name**, enter **object**.
8. For **Mapped from**, enter **method.request.path.item**.
9. Choose **Save**.

To test the **/{folder}/{object}** GET method.

1. Choose the **Test** tab. You might need to choose the right arrow button to show the tab.

2. Under **Path**, for **folder**, enter the name of your bucket.
3. Under **Path**, for **item**, enter the name of an item.
4. Choose **Test**.

The response body will contain the contents of the item.

Test method

Make a test call to your method. When you make a test call, API Gateway skips authorization and directly invokes your method.

Path

folder

item

Query strings

Headers

Enter a header name and value separated by a colon (:). Use a new line for each header.

Client certificate

No client certificates have been generated.

Test

/{folder}/{item} - GET method test results

Request

/amzn-s3-demo-bucket/test.txt

Latency ms

61

Status

200

Response body

Hello World

The request correctly returns the plain text of ("Hello world") as the content of the specified file (test.txt) in the given Amazon S3 bucket (amzn-s3-demo-bucket).

To download or upload binary files, which in API Gateway is considered anything other than utf-8 encoded JSON content, additional API settings are necessary. This is outlined as follows:

To download or upload binary files from S3

1. Register the media types of the affected file to the API's `binaryMediaTypes`. You can do this in the console:
 - a. Choose **API settings** for the API.
 - b. Under **Binary media types**, choose **Manage media types**.
 - c. Choose **Add binary media type**, and then enter the required media type, for example, `image/png`.
 - d. Choose **Save changes** to save the setting.
2. Add the `Content-Type` (for upload) and/or `Accept` (for download) header to the method request to require the client to specify the required binary media type and map them to the integration request.
3. Set **Content Handling** to `Passthrough` in the integration request (for upload) and in a integration response (for download). Make sure that no mapping template is defined for the affected content type. For more information, see [the section called “Data transformations”](#).

The payload size limit is 10 MB. See [Quotas for configuring and running a REST API in API Gateway](#).

Make sure that files on Amazon S3 have the correct content types added as the files' metadata. For streamable media content, `Content-Disposition:inline` may also need to be added to the metadata.

For more information about the binary support in API Gateway, see [Content type conversions in API Gateway](#).

OpenAPI definitions of the sample API as an Amazon S3 proxy

The following OpenAPI definitions describes an API that works as an Amazon S3 proxy. This API contains more Amazon S3 operations than the API you created in the tutorial. The following methods are exposed in the OpenAPI definitions:

- Expose GET on the API's root resource to [list all of the Amazon S3 buckets of a caller](#).
- Expose GET on a Folder resource to [view a list of all of the objects in an Amazon S3 bucket](#).
- Expose PUT on a Folder resource to [add a bucket to Amazon S3](#).
- Expose DELETE on a Folder resource to [remove a bucket from Amazon S3](#).
- Expose GET on a Folder/Item resource to [view or download an object from an Amazon S3 bucket](#).

- Expose PUT on a Folder/Item resource to [upload an object to an Amazon S3 bucket](#).
- Expose HEAD on a Folder/Item resource to [get object metadata in an Amazon S3 bucket](#).
- Expose DELETE on a Folder/Item resource to [remove an object from an Amazon S3 bucket](#).

For instructions on how to import an API using the OpenAPI definition, see [Develop REST APIs using OpenAPI in API Gateway](#).

For instructions on how to create a similar API, see [Tutorial: Create a REST API as an Amazon S3 proxy](#).

To learn how to invoke this API using [Postman](#), which supports the AWS IAM authorization, see [Call the API using a REST API client](#).

OpenAPI 2.0

```
{  
  "swagger": "2.0",  
  "info": {  
    "version": "2016-10-13T23:04:43Z",  
    "title": "MyS3"  
  },  
  "host": "9gn28ca086.execute-api.{region}.amazonaws.com",  
  "basePath": "/S3",  
  "schemes": [  
    "https"  
  ],  
  "paths": {  
    "/": {  
      "get": {  
        "produces": [  
          "application/json"  
        ],  
        "responses": {  
          "200": {  
            "description": "200 response",  
            "schema": {  
              "$ref": "#/definitions/Empty"  
            },  
            "headers": {  
              "Content-Length": {  
                "type": "string"  
              },  
              "Content-Type": {  
                "type": "string"  
              }  
            }  
          }  
        }  
      }  
    }  
  }  
}
```

```
        "Timestamp": {
            "type": "string"
        },
        "Content-Type": {
            "type": "string"
        }
    },
    "400": {
        "description": "400 response"
    },
    "500": {
        "description": "500 response"
    }
},
"security": [
{
    "sigv4": []
}
],
"x-amazon-apigateway-integration": {
    "credentials": "arn:aws:iam::123456789012:role/apigAwsProxyRole",
    "responses": {
        "4\d{2}": {
            "statusCode": "400"
        },
        "default": {
            "statusCode": "200",
            "responseParameters": {
                "method.response.header.Content-Type": "integration.response.header.Content-Type",
                "method.response.header.Content-Length": "integration.response.header.Content-Length",
                "method.response.header.Timestamp": "integration.response.header.Date"
            }
        },
        "5\d{2}": {
            "statusCode": "500"
        }
    },
    "uri": "arn:aws:apigateway:us-west-2:s3:path//",
    "passthroughBehavior": "when_no_match",
    "httpMethod": "GET",
}
```

```
        "type": "aws"
    }
}
},
"/{folder}": {
    "get": {
        "produces": [
            "application/json"
        ],
        "parameters": [
            {
                "name": "folder",
                "in": "path",
                "required": true,
                "type": "string"
            }
        ],
        "responses": {
            "200": {
                "description": "200 response",
                "schema": {
                    "$ref": "#/definitions/Empty"
                },
                "headers": {
                    "Content-Length": {
                        "type": "string"
                    },
                    "Date": {
                        "type": "string"
                    },
                    "Content-Type": {
                        "type": "string"
                    }
                }
            },
            "400": {
                "description": "400 response"
            },
            "500": {
                "description": "500 response"
            }
        },
        "security": [
            {

```

```
        "sigv4": []
    },
],
"x-amazon-apigateway-integration": {
    "credentials": "arn:aws:iam::123456789012:role/apigAwsProxyRole",
    "responses": {
        "4\\d{2)": {
            "statusCode": "400"
        },
        "default": {
            "statusCode": "200",
            "responseParameters": {
                "method.response.header.Content-Type":
                    "integration.response.header.Content-Type",
                "method.response.header.Date": "integration.response.header.Date",
                "method.response.header.Content-Length":
                    "integration.response.header.content-length"
            }
        },
        "5\\d{2)": {
            "statusCode": "500"
        }
    },
    "requestParameters": {
        "integration.request.path.bucket": "method.request.path.folder"
    },
    "uri": "arn:aws:apigateway:us-west-2:s3:path/{bucket}",
    "passthroughBehavior": "when_no_match",
    "httpMethod": "GET",
    "type": "aws"
},
"put": {
    "produces": [
        "application/json"
    ],
    "parameters": [
        {
            "name": "Content-Type",
            "in": "header",
            "required": false,
            "type": "string"
        },
        {

```

```
        "name": "folder",
        "in": "path",
        "required": true,
        "type": "string"
    }
],
"responses": {
    "200": {
        "description": "200 response",
        "schema": {
            "$ref": "#/definitions/Empty"
        },
        "headers": {
            "Content-Length": {
                "type": "string"
            },
            "Content-Type": {
                "type": "string"
            }
        }
    },
    "400": {
        "description": "400 response"
    },
    "500": {
        "description": "500 response"
    }
},
"security": [
    {
        "sigv4": []
    }
],
"x-amazon-apigateway-integration": {
    "credentials": "arn:aws:iam::123456789012:role/apigAwsProxyRole",
    "responses": {
        "4\\d{2)": {
            "statusCode": "400"
        },
        "default": {
            "statusCode": "200",
            "responseParameters": {
                "method.response.header.Content-Type": "integration.response.header.Content-Type",
                "integration.response.header.Content-Type": "
            }
        }
    }
}
```

```
        "method.response.header.Content-Length":  
    "integration.response.header.Content-Length"  
    }  
},  
"5\\d{2}": {  
    "statusCode": "500"  
}  
},  
"requestParameters": {  
    "integration.request.path.bucket": "method.request.path.folder",  
    "integration.request.header.Content-Type":  
"method.request.header.Content-Type"  
},  
"uri": "arn:aws:apigateway:us-west-2:s3:path/{bucket}",  
"passthroughBehavior": "when_no_match",  
"httpMethod": "PUT",  
"type": "aws"  
}  
,  
"delete": {  
    "produces": [  
        "application/json"  
],  
    "parameters": [  
        {  
            "name": "folder",  
            "in": "path",  
            "required": true,  
            "type": "string"  
        }  
],  
    "responses": {  
        "200": {  
            "description": "200 response",  
            "schema": {  
                "$ref": "#/definitions/Empty"  
            },  
            "headers": {  
                "Date": {  
                    "type": "string"  
                },  
                "Content-Type": {  
                    "type": "string"  
                }  
            }  
        }  
    }  
}
```

```
        }
    },
    "400": {
        "description": "400 response"
    },
    "500": {
        "description": "500 response"
    }
},
"security": [
{
    "sigv4": []
}
],
"x-amazon-apigateway-integration": {
    "credentials": "arn:aws:iam::123456789012:role/apigAwsProxyRole",
    "responses": {
        "4\\d{2)": {
            "statusCode": "400"
        },
        "default": {
            "statusCode": "200",
            "responseParameters": {
                "method.response.header.Content-Type":
                    "integration.response.header.Content-Type",
                "method.response.header.Date": "integration.response.header.Date"
            }
        },
        "5\\d{2)": {
            "statusCode": "500"
        }
    },
    "requestParameters": {
        "integration.request.path.bucket": "method.request.path.folder"
    },
    "uri": "arn:aws:apigateway:us-west-2:s3:path/{bucket}",
    "passthroughBehavior": "when_no_match",
    "httpMethod": "DELETE",
    "type": "aws"
}
},
"/{folder}/{item)": {
    "get": {
```

```
"produces": [
    "application/json"
],
"parameters": [
    {
        "name": "item",
        "in": "path",
        "required": true,
        "type": "string"
    },
    {
        "name": "folder",
        "in": "path",
        "required": true,
        "type": "string"
    }
],
"responses": {
    "200": {
        "description": "200 response",
        "schema": {
            "$ref": "#/definitions/Empty"
        },
        "headers": {
            "content-type": {
                "type": "string"
            },
            "Content-Type": {
                "type": "string"
            }
        }
    },
    "400": {
        "description": "400 response"
    },
    "500": {
        "description": "500 response"
    }
},
"security": [
    {
        "sigv4": []
    }
],
```

```
"x-amazon-apigateway-integration": {
    "credentials": "arn:aws:iam::123456789012:role/apigAwsProxyRole",
    "responses": {
        "4\\d{2)": {
            "statusCode": "400"
        },
        "default": {
            "statusCode": "200",
            "responseParameters": {
                "method.response.header.content-type":
                    "integration.response.header.content-type",
                "method.response.header.Content-Type":
                    "integration.response.header.Content-Type"
            }
        },
        "5\\d{2)": {
            "statusCode": "500"
        }
    },
    "requestParameters": {
        "integration.request.path.object": "method.request.path.item",
        "integration.request.path.bucket": "method.request.path.folder"
    },
    "uri": "arn:aws:apigateway:us-west-2:s3:path/{bucket}/{object}",
    "passthroughBehavior": "when_no_match",
    "httpMethod": "GET",
    "type": "aws"
},
"head": {
    "produces": [
        "application/json"
    ],
    "parameters": [
        {
            "name": "item",
            "in": "path",
            "required": true,
            "type": "string"
        },
        {
            "name": "folder",
            "in": "path",
            "required": true,
            "type": "string"
        }
    ]
}
```

```
        "type": "string"
    },
],
"responses": {
    "200": {
        "description": "200 response",
        "schema": {
            "$ref": "#/definitions/Empty"
        },
        "headers": {
            "Content-Length": {
                "type": "string"
            },
            "Content-Type": {
                "type": "string"
            }
        }
    },
    "400": {
        "description": "400 response"
    },
    "500": {
        "description": "500 response"
    }
},
"security": [
    {
        "sigv4": []
    }
],
"x-amazon-apigateway-integration": {
    "credentials": "arn:aws:iam::123456789012:role/apigAwsProxyRole",
    "responses": {
        "4\\d{2)": {
            "statusCode": "400"
        },
        "default": {
            "statusCode": "200",
            "responseParameters": {
                "method.response.header.Content-Type": "integration.response.header.Content-Type",
                "method.response.header.Content-Length": "integration.response.header.Content-Length"
            }
        }
    }
}
```

```
        },
        "5\\d{2}": {
            "statusCode": "500"
        }
    },
    "requestParameters": {
        "integration.request.path.object": "method.request.path.item",
        "integration.request.path.bucket": "method.request.path.folder"
    },
    "uri": "arn:aws:apigateway:us-west-2:s3:path/{bucket}/{object}",
    "passthroughBehavior": "when_no_match",
    "httpMethod": "HEAD",
    "type": "aws"
}
},
"put": {
    "produces": [
        "application/json"
    ],
    "parameters": [
        {
            "name": "Content-Type",
            "in": "header",
            "required": false,
            "type": "string"
        },
        {
            "name": "item",
            "in": "path",
            "required": true,
            "type": "string"
        },
        {
            "name": "folder",
            "in": "path",
            "required": true,
            "type": "string"
        }
    ],
    "responses": {
        "200": {
            "description": "200 response",
            "schema": {
                "$ref": "#/definitions/Empty"
            }
        }
    }
}
```

```
        },
        "headers": {
            "Content-Length": {
                "type": "string"
            },
            "Content-Type": {
                "type": "string"
            }
        }
    },
    "400": {
        "description": "400 response"
    },
    "500": {
        "description": "500 response"
    }
},
"security": [
{
    "sigv4": []
}
],
"x-amazon-apigateway-integration": {
    "credentials": "arn:aws:iam::123456789012:role/apigAwsProxyRole",
    "responses": {
        "4\\d{2)": {
            "statusCode": "400"
        },
        "default": {
            "statusCode": "200",
            "responseParameters": {
                "method.response.header.Content-Type":
                    "integration.response.header.Content-Type",
                "method.response.header.Content-Length":
                    "integration.response.header.Content-Length"
            }
        },
        "5\\d{2)": {
            "statusCode": "500"
        }
    },
    "requestParameters": {
        "integration.request.path.object": "method.request.path.item",
        "integration.request.path.bucket": "method.request.path.folder",
    }
}
```

```
        "integration.request.header.Content-Type":  
    "method.request.header.Content-Type"  
    },  
    "uri": "arn:aws:apigateway:us-west-2:s3:path/{bucket}/{object}",  
    "passthroughBehavior": "when_no_match",  
    "httpMethod": "PUT",  
    "type": "aws"  
}  
,  
},  
"delete": {  
    "produces": [  
        "application/json"  
    ],  
    "parameters": [  
        {  
            "name": "item",  
            "in": "path",  
            "required": true,  
            "type": "string"  
        },  
        {  
            "name": "folder",  
            "in": "path",  
            "required": true,  
            "type": "string"  
        }  
    ],  
    "responses": {  
        "200": {  
            "description": "200 response",  
            "schema": {  
                "$ref": "#/definitions/Empty"  
            },  
            "headers": {  
                "Content-Length": {  
                    "type": "string"  
                },  
                "Content-Type": {  
                    "type": "string"  
                }  
            }  
        },  
        "400": {  
            "description": "400 response"
```

```
        },
        "500": {
            "description": "500 response"
        }
    },
    "security": [
        {
            "sigv4": []
        }
    ],
    "x-amazon-apigateway-integration": {
        "credentials": "arn:aws:iam::123456789012:role/apigAwsProxyRole",
        "responses": {
            "4\\d{2)": {
                "statusCode": "400"
            },
            "default": {
                "statusCode": "200"
            },
            "5\\d{2)": {
                "statusCode": "500"
            }
        },
        "requestParameters": {
            "integration.request.path.object": "method.request.path.item",
            "integration.request.path.bucket": "method.request.path.folder"
        },
        "uri": "arn:aws:apigateway:us-west-2:s3:path/{bucket}/{object}",
        "passthroughBehavior": "when_no_match",
        "httpMethod": "DELETE",
        "type": "aws"
    }
},
],
},
"securityDefinitions": {
    "sigv4": {
        "type": "apiKey",
        "name": "Authorization",
        "in": "header",
        "x-amazon-apigateway-authType": "awsSigv4"
    }
},
"definitions": {
```

```
"Empty": {  
    "type": "object",  
    "title": "Empty Schema"  
}  
}  
}
```

OpenAPI 3.0

```
{  
    "openapi" : "3.0.1",  
    "info" : {  
        "title" : "MyS3",  
        "version" : "2016-10-13T23:04:43Z"  
    },  
    "servers" : [ {  
        "url" : "https://9gn28ca086.execute-api.{region}.amazonaws.com/{basePath}",  
        "variables" : {  
            "basePath" : {  
                "default" : "S3"  
            }  
        }  
    } ],  
    "paths" : {  
        "/{folder}" : {  
            "get" : {  
                "parameters" : [ {  
                    "name" : "folder",  
                    "in" : "path",  
                    "required" : true,  
                    "schema" : {  
                        "type" : "string"  
                    }  
                } ],  
                "responses" : {  
                    "400" : {  
                        "description" : "400 response",  
                        "content" : { }  
                    },  
                    "500" : {  
                        "description" : "500 response",  
                        "content" : { }  
                    },  
                }  
            }  
        }  
    }  
}
```

```
"200" : {
    "description" : "200 response",
    "headers" : {
        "Content-Length" : {
            "schema" : {
                "type" : "string"
            }
        },
        "Date" : {
            "schema" : {
                "type" : "string"
            }
        },
        "Content-Type" : {
            "schema" : {
                "type" : "string"
            }
        }
    },
    "content" : {
        "application/json" : {
            "schema" : {
                "$ref" : "#/components/schemas/Empty"
            }
        }
    }
},
"x-amazon-apigateway-integration" : {
    "credentials" : "arn:aws:iam::123456789012:role/apigAwsProxyRole",
    "httpMethod" : "GET",
    "uri" : "arn:aws:apigateway:us-west-2:s3:path/{bucket}",
    "responses" : {
        "4\\d{2}" : {
            "statusCode" : "400"
        },
        "default" : {
            "statusCode" : "200",
            "responseParameters" : {
                "method.response.header.Content-Type" :
                    "integration.response.header.Content-Type",
                "method.response.header.Date" : "integration.response.header.Date",
                "method.response.header.Content-Length" :
                    "integration.response.header.content-length"
            }
        }
    }
}
```

```
        }
    },
    "5\\d{2}" : {
        "statusCode" : "500"
    }
},
"requestParameters" : {
    "integration.request.path.bucket" : "method.request.path.folder"
},
"passthroughBehavior" : "when_no_match",
"type" : "aws"
}
},
"put" : {
    "parameters" : [ {
        "name" : "Content-Type",
        "in" : "header",
        "schema" : {
            "type" : "string"
        }
    }, {
        "name" : "folder",
        "in" : "path",
        "required" : true,
        "schema" : {
            "type" : "string"
        }
    }
],
"responses" : {
    "400" : {
        "description" : "400 response",
        "content" : { }
    },
    "500" : {
        "description" : "500 response",
        "content" : { }
    },
    "200" : {
        "description" : "200 response",
        "headers" : {
            "Content-Length" : {
                "schema" : {
                    "type" : "string"
                }
            }
        }
    }
}
```

```
        },
        "Content-Type" : {
            "schema" : {
                "type" : "string"
            }
        }
    },
    "content" : {
        "application/json" : {
            "schema" : {
                "$ref" : "#/components/schemas/Empty"
            }
        }
    }
},
"x-amazon-apigateway-integration" : {
    "credentials" : "arn:aws:iam::123456789012:role/apigAwsProxyRole",
    "httpMethod" : "PUT",
    "uri" : "arn:aws:apigateway:us-west-2:s3:path/{bucket}",
    "responses" : {
        "4\d{2}" : {
            "statusCode" : "400"
        },
        "default" : {
            "statusCode" : "200",
            "responseParameters" : {
                "method.response.header.Content-Type" :
                    "integration.response.header.Content-Type",
                "method.response.header.Content-Length" :
                    "integration.response.header.Content-Length"
            }
        },
        "5\d{2}" : {
            "statusCode" : "500"
        }
    },
    "requestParameters" : {
        "integration.request.path.bucket" : "method.request.path.folder",
        "integration.request.header.Content-Type" :
            "method.request.header.Content-Type"
    },
    "passthroughBehavior" : "when_no_match",
    "type" : "aws"
}
```

```
        }
    },
    "delete" : {
        "parameters" : [ {
            "name" : "folder",
            "in" : "path",
            "required" : true,
            "schema" : {
                "type" : "string"
            }
        }],
        "responses" : {
            "400" : {
                "description" : "400 response",
                "content" : { }
            },
            "500" : {
                "description" : "500 response",
                "content" : { }
            },
            "200" : {
                "description" : "200 response",
                "headers" : {
                    "Date" : {
                        "schema" : {
                            "type" : "string"
                        }
                    },
                    "Content-Type" : {
                        "schema" : {
                            "type" : "string"
                        }
                    }
                },
                "content" : {
                    "application/json" : {
                        "schema" : {
                            "$ref" : "#/components/schemas/Empty"
                        }
                    }
                }
            }
        },
        "x-amazon-apigateway-integration" : {
```

```
"credentials" : "arn:aws:iam::123456789012:role/apigAwsProxyRole",
"httpMethod" : "DELETE",
"uri" : "arn:aws:apigateway:us-west-2:s3:path/{bucket}",
"responses" : {
    "4\d{2}" : {
        "statusCode" : "400"
    },
    "default" : {
        "statusCode" : "200",
        "responseParameters" : {
            "method.response.header.Content-Type" :
                "integration.response.header.Content-Type",
            "method.response.header.Date" : "integration.response.header.Date"
        }
    },
    "5\d{2}" : {
        "statusCode" : "500"
    }
},
"requestParameters" : {
    "integration.request.path.bucket" : "method.request.path.folder"
},
"passthroughBehavior" : "when_no_match",
"type" : "aws"
}
},
"/{folder}/{item}" : {
    "get" : {
        "parameters" : [ {
            "name" : "item",
            "in" : "path",
            "required" : true,
            "schema" : {
                "type" : "string"
            }
        }, {
            "name" : "folder",
            "in" : "path",
            "required" : true,
            "schema" : {
                "type" : "string"
            }
        }
    ]
},
```

```
"responses" : {
    "400" : {
        "description" : "400 response",
        "content" : { }
    },
    "500" : {
        "description" : "500 response",
        "content" : { }
    },
    "200" : {
        "description" : "200 response",
        "headers" : {
            "content-type" : {
                "schema" : {
                    "type" : "string"
                }
            },
            "Content-Type" : {
                "schema" : {
                    "type" : "string"
                }
            }
        },
        "content" : {
            "application/json" : {
                "schema" : {
                    "$ref" : "#/components/schemas/Empty"
                }
            }
        }
    },
    "x-amazon-apigateway-integration" : {
        "credentials" : "arn:aws:iam::123456789012:role/apigAwsProxyRole",
        "httpMethod" : "GET",
        "uri" : "arn:aws:apigateway:us-west-2:s3:path/{bucket}/{object}",
        "responses" : {
            "4\\d{2}" : {
                "statusCode" : "400"
            },
            "default" : {
                "statusCode" : "200",
                "responseParameters" : {

```

```
        "method.response.header.content-type" :
"integration.response.header.content-type",
        "method.response.header.Content-Type" :
"integration.response.header.Content-Type"
    }
},
"5\\d{2}" : {
    "statusCode" : "500"
}
},
"requestParameters" : {
    "integration.request.path.object" : "method.request.path.item",
    "integration.request.path.bucket" : "method.request.path.folder"
},
"passthroughBehavior" : "when_no_match",
"type" : "aws"
}
},
"put" : {
    "parameters" : [ {
        "name" : "Content-Type",
        "in" : "header",
        "schema" : {
            "type" : "string"
        }
    }, {
        "name" : "item",
        "in" : "path",
        "required" : true,
        "schema" : {
            "type" : "string"
        }
    }, {
        "name" : "folder",
        "in" : "path",
        "required" : true,
        "schema" : {
            "type" : "string"
        }
    }
],
"responses" : {
    "400" : {
        "description" : "400 response",
        "content" : { }
```

```
        },
        "500" : {
            "description" : "500 response",
            "content" : { }
        },
        "200" : {
            "description" : "200 response",
            "headers" : {
                "Content-Length" : {
                    "schema" : {
                        "type" : "string"
                    }
                },
                "Content-Type" : {
                    "schema" : {
                        "type" : "string"
                    }
                }
            },
            "content" : {
                "application/json" : {
                    "schema" : {
                        "$ref" : "#/components/schemas/Empty"
                    }
                }
            }
        }
    },
    "x-amazon-apigateway-integration" : {
        "credentials" : "arn:aws:iam::123456789012:role/apigAwsProxyRole",
        "httpMethod" : "PUT",
        "uri" : "arn:aws:apigateway:us-west-2:s3:path/{bucket}/{object}",
        "responses" : {
            "4\\d{2}" : {
                "statusCode" : "400"
            },
            "default" : {
                "statusCode" : "200",
                "responseParameters" : {
                    "method.response.header.Content-Type" :
                    "integration.response.header.Content-Type",
                    "method.response.header.Content-Length" :
                    "integration.response.header.Content-Length"
                }
            }
        }
    }
}
```

```
        },
        "5\\d{2}" : {
            "statusCode" : "500"
        }
    },
    "requestParameters" : {
        "integration.request.path.object" : "method.request.path.item",
        "integration.request.path.bucket" : "method.request.path.folder",
        "integration.request.header.Content-Type" :
"method.request.header.Content-Type"
    },
    "passthroughBehavior" : "when_no_match",
    "type" : "aws"
},
{
    "delete" : {
        "parameters" : [ {
            "name" : "item",
            "in" : "path",
            "required" : true,
            "schema" : {
                "type" : "string"
            }
        }, {
            "name" : "folder",
            "in" : "path",
            "required" : true,
            "schema" : {
                "type" : "string"
            }
        } ],
        "responses" : {
            "400" : {
                "description" : "400 response",
                "content" : { }
            },
            "500" : {
                "description" : "500 response",
                "content" : { }
            },
            "200" : {
                "description" : "200 response",
                "headers" : {
                    "Content-Length" : {

```

```
        "schema" : {
            "type" : "string"
        }
    },
    "Content-Type" : {
        "schema" : {
            "type" : "string"
        }
    }
},
"content" : {
    "application/json" : {
        "schema" : {
            "$ref" : "#/components/schemas/Empty"
        }
    }
}
},
"x-amazon-apigateway-integration" : {
    "credentials" : "arn:aws:iam::123456789012:role/apigAwsProxyRole",
    "httpMethod" : "DELETE",
    "uri" : "arn:aws:apigateway:us-west-2:s3:path/{bucket}/{object}",
    "responses" : {
        "4\d{2}" : {
            "statusCode" : "400"
        },
        "default" : {
            "statusCode" : "200"
        },
        "5\d{2}" : {
            "statusCode" : "500"
        }
    },
    "requestParameters" : {
        "integration.request.path.object" : "method.request.path.item",
        "integration.request.path.bucket" : "method.request.path.folder"
    },
    "passthroughBehavior" : "when_no_match",
    "type" : "aws"
},
},
"head" : {
    "parameters" : [ {
```

```
        "name" : "item",
        "in" : "path",
        "required" : true,
        "schema" : {
            "type" : "string"
        }
    },
    {
        "name" : "folder",
        "in" : "path",
        "required" : true,
        "schema" : {
            "type" : "string"
        }
    }
],
"responses" : {
    "400" : {
        "description" : "400 response",
        "content" : { }
    },
    "500" : {
        "description" : "500 response",
        "content" : { }
    },
    "200" : {
        "description" : "200 response",
        "headers" : {
            "Content-Length" : {
                "schema" : {
                    "type" : "string"
                }
            },
            "Content-Type" : {
                "schema" : {
                    "type" : "string"
                }
            }
        },
        "content" : {
            "application/json" : {
                "schema" : {
                    "$ref" : "#/components/schemas/Empty"
                }
            }
        }
    }
}
```

```
        }
    },
    "x-amazon-apigateway-integration" : {
        "credentials" : "arn:aws:iam::123456789012:role/apigAwsProxyRole",
        "httpMethod" : "HEAD",
        "uri" : "arn:aws:apigateway:us-west-2:s3:path/{bucket}/{object}",
        "responses" : {
            "4\\d{2}" : {
                "statusCode" : "400"
            },
            "default" : {
                "statusCode" : "200",
                "responseParameters" : {
                    "method.response.header.Content-Type" :
                        "integration.response.header.Content-Type",
                    "method.response.header.Content-Length" :
                        "integration.response.header.Content-Length"
                }
            },
            "5\\d{2}" : {
                "statusCode" : "500"
            }
        },
        "requestParameters" : {
            "integration.request.path.object" : "method.request.path.item",
            "integration.request.path.bucket" : "method.request.path.folder"
        },
        "passthroughBehavior" : "when_no_match",
        "type" : "aws"
    }
},
"/" : {
    "get" : {
        "responses" : {
            "400" : {
                "description" : "400 response",
                "content" : { }
            },
            "500" : {
                "description" : "500 response",
                "content" : { }
            },
            "200" : {

```

```
"description" : "200 response",
"headers" : {
    "Content-Length" : {
        "schema" : {
            "type" : "string"
        }
    },
    "Timestamp" : {
        "schema" : {
            "type" : "string"
        }
    },
    "Content-Type" : {
        "schema" : {
            "type" : "string"
        }
    }
},
"content" : {
    "application/json" : {
        "schema" : {
            "$ref" : "#/components/schemas/Empty"
        }
    }
},
"x-amazon-apigateway-integration" : {
    "credentials" : "arn:aws:iam::123456789012:role/apigAwsProxyRole",
    "httpMethod" : "GET",
    "uri" : "arn:aws:apigateway:us-west-2:s3:path//",
    "responses" : {
        "4\d{2}" : {
            "statusCode" : "400"
        },
        "default" : {
            "statusCode" : "200",
            "responseParameters" : {
                "method.response.header.Content-Type" :
"integration.response.header.Content-Type",
                "method.response.header.Content-Length" :
"integration.response.header.Content-Length",
                "method.response.header.Timestamp" :
"integration.response.header.Date"
```

```
        }
    },
    "5\\d{2}" : {
        "statusCode" : "500"
    }
},
"passthroughBehavior" : "when_no_match",
"type" : "aws"
}
}
}
},
"components" : {
    "schemas" : {
        "Empty" : {
            "title" : "Empty Schema",
            "type" : "object"
        }
    }
}
}
```

Call the API using a REST API client

To provide an end-to-end tutorial, we now show how to call the API using [Postman](#), which supports the AWS IAM authorization.

To call our Amazon S3 proxy API using Postman

1. Deploy or redeploy the API. Make a note of the base URL of the API that is displayed next to **Invoke URL** at the top of the **Stage Editor**.
2. Launch Postman.
3. Choose **Authorization** and then choose **AWS Signature**. Enter your IAM user's Access Key ID and Secret Access Key into the **AccessKey** and **SecretKey** input fields, respectively. Enter the AWS Region to which your API is deployed in the **AWS Region** text box. Enter **execute-api** in the **Service Name** input field.

You can create a pair of the keys from the **Security Credentials** tab from your IAM user account in the IAM Management Console.

4. To add a bucket named **amzn-s3-demo-bucket** to your Amazon S3 account in the **{region}** region:
 - a. Choose **PUT** from the drop-down method list and type the method URL (<https://api-id.execute-api.aws-region.amazonaws.com/stage/folder-name>)
 - b. Set the Content-Type header value as application/xml. You may need to delete any existing headers before setting the content type.
 - c. Choose **Body** menu item and type the following XML fragment as the request body:

```
<CreateBucketConfiguration>
  <LocationConstraint>{region}</LocationConstraint>
</CreateBucketConfiguration>
```

- d. Choose **Send** to submit the request. If successful, you should receive a 200 OK response with an empty payload.
5. To add a text file to a bucket, follow the instructions above. If you specify a bucket name of **amzn-s3-demo-bucket** for {folder} and a file name of **Readme.txt** for {item} in the URL and provide a text string of **Hello, World!** as the file contents (thereby making it the request payload), the request becomes

```
PUT /S3/amzn-s3-demo-bucket/Readme.txt HTTP/1.1
Host: 9gn28ca086.execute-api.{region}.amazonaws.com
Content-Type: application/xml
X-Amz-Date: 20161015T062647Z
Authorization: AWS4-HMAC-SHA256 Credential=access-key-id/20161015/{region}/execute-api/aws4_request, SignedHeaders=content-length;content-type;host;x-amz-date,
Signature=ccadb877bdb0d395ca38cc47e18a0d76bb5eaf17007d11e40bf6fb63d28c705b
Cache-Control: no-cache
Postman-Token: 6135d315-9cc4-8af8-1757-90871d00847e

Hello, World!
```

- If everything goes well, you should receive a 200 OK response with an empty payload.
6. To get the content of the **Readme.txt** file we just added to the **amzn-s3-demo-bucket** bucket, do a GET request like the following one:

```
GET /S3/amzn-s3-demo-bucket/Readme.txt HTTP/1.1
Host: 9gn28ca086.execute-api.{region}.amazonaws.com
Content-Type: application/xml
```

```
X-Amz-Date: 20161015T063759Z
Authorization: AWS4-HMAC-SHA256 Credential=access-key-id/20161015/{region}/
execute-api/aws4_request, SignedHeaders=content-type;host;x-amz-date,
Signature=ba09b72b585acf0e578e6ad02555c00e24b420b59025bc7bb8d3f7aed1471339
Cache-Control: no-cache
Postman-Token: d60fc59-d335-52f7-0025-5bd96928098a
```

If successful, you should receive a 200 OK response with the Hello, World! text string as the payload.

7. To list items in the amzn-s3-demo-bucket bucket, submit the following request:

```
GET /S3/amzn-s3-demo-bucket HTTP/1.1
Host: 9gn28ca086.execute-api.{region}.amazonaws.com
Content-Type: application/xml
X-Amz-Date: 20161015T064324Z
Authorization: AWS4-HMAC-SHA256 Credential=access-key-id/20161015/{region}/
execute-api/aws4_request, SignedHeaders=content-type;host;x-amz-date,
Signature=4ac9bd4574a14e01568134fd16814534d9951649d3a22b3b0db9f1f5cd4dd0ac
Cache-Control: no-cache
Postman-Token: 9c43020a-966f-61e1-81af-4c49ad8d1392
```

If successful, you should receive a 200 OK response with an XML payload showing a single item in the specified bucket, unless you added more files to the bucket before submitting this request.

```
<?xml version="1.0" encoding="UTF-8"?>
<ListBucketResult xmlns="http://s3.amazonaws.com/doc/2006-03-01/">
  <Name>apig-demo-5</Name>
  <Prefix></Prefix>
  <Marker></Marker>
  <MaxKeys>1000</MaxKeys>
  <IsTruncated>false</IsTruncated>
  <Contents>
    <Key>Readme.txt</Key>
    <LastModified>2016-10-15T06:26:48.000Z</LastModified>
    <ETag>"65a8e27d8879283831b664bd8b7f0ad4"</ETag>
    <Size>13</Size>
    <Owner>
      <ID>06e4b09e9d...603add12ee</ID>
      <DisplayName>user-name</DisplayName>
    </Owner>
```

```
<StorageClass>STANDARD</StorageClass>
</Contents>
</ListBucketResult>
```

 **Note**

To upload or download an image, you need to set content handling to CONVERT_TO_BINARY.

Tutorial: Create a REST API as an Amazon Kinesis proxy

This page describes how to create and configure a REST API with an integration of the AWS type to access Kinesis.

 **Note**

To integrate your API Gateway API with Kinesis, you must choose a region where both the API Gateway and Kinesis services are available. For region availability, see [Service Endpoints and Quotas](#).

For the purpose of illustration, we create an example API to enable a client to do the following:

1. List the user's available streams in Kinesis
2. Create, describe, or delete a specified stream
3. Read data records from or write data records into the specified stream

To accomplish the preceding tasks, the API exposes methods on various resources to invoke the following, respectively:

1. The `ListStreams` action in Kinesis
2. The `CreateStream`, `DescribeStream`, or `DeleteStream` action
3. The `GetRecords` or `PutRecords` (including `PutRecord`) action in Kinesis

Specifically, we build the API as follows:

- Expose an HTTP GET method on the API's /streams resource and integrate the method with the [ListStreams](#) action in Kinesis to list the streams in the caller's account.
- Expose an HTTP POST method on the API's /streams/{stream-name} resource and integrate the method with the [CreateStream](#) action in Kinesis to create a named stream in the caller's account.
- Expose an HTTP GET method on the API's /streams/{stream-name} resource and integrate the method with the [DescribeStream](#) action in Kinesis to describe a named stream in the caller's account.
- Expose an HTTP DELETE method on the API's /streams/{stream-name} resource and integrate the method with the [DeleteStream](#) action in Kinesis to delete a stream in the caller's account.
- Expose an HTTP PUT method on the API's /streams/{stream-name}/record resource and integrate the method with the [PutRecord](#) action in Kinesis. This enables the client to add a single data record to the named stream.
- Expose an HTTP PUT method on the API's /streams/{stream-name}/records resource and integrate the method with the [PutRecords](#) action in Kinesis. This enables the client to add a list of data records to the named stream.
- Expose an HTTP GET method on the API's /streams/{stream-name}/records resource and integrate the method with the [GetRecords](#) action in Kinesis. This enables the client to list data records in the named stream, with a specified shard iterator. A shard iterator specifies the shard position from which to start reading data records sequentially.
- Expose an HTTP GET method on the API's /streams/{stream-name}/sharditerator resource and integrate the method with the [GetShardIterator](#) action in Kinesis. This helper method must be supplied to the ListStreams action in Kinesis.

You can apply the instructions presented here to other Kinesis actions. For the complete list of the Kinesis actions, see [Amazon Kinesis API Reference](#).

Instead of using the API Gateway console to create the sample API, you can import the sample API into API Gateway using the API Gateway [Import API](#). For information on how to use the Import API, see [Develop REST APIs using OpenAPI in API Gateway](#).

Create an IAM role and policy for the API to access Kinesis

To allow the API to invoke Kinesis actions, you must have the appropriate IAM policies attached to an IAM role. In this step, you create a new IAM role.

To create the AWS service proxy execution role

1. Sign in to the AWS Management Console and open the IAM console at <https://console.aws.amazon.com/iam/>.
2. Choose **Roles**.
3. Choose **Create role**.
4. Choose **AWS service** under **Select type of trusted entity**, and then select **API Gateway** and select **Allows API Gateway to push logs to CloudWatch Logs**.
5. Choose **Next**, and then choose **Next**.
6. For **Role name**, enter **APIGatewayKinesisProxyPolicy**, and then choose **Create role**.
7. In the **Roles** list, choose the role you just created. You may need to scroll or use the search bar to find the role.
8. For the selected role, select the **Add permissions** tab.
9. Choose **Attach policies** from the dropdown list.
10. In the search bar, enter **AmazonKinesisFullAccess** and choose **Add permissions**.

 **Note**

This tutorial uses a managed policy for simplicity. As a best practice, you should create your own IAM policy to grant the minimum permissions required.

11. Note the newly created **Role ARN**, you will use it later.

Create an API as a Kinesis proxy

Use the following steps to create the API in the API Gateway console.

To create an API as an AWS service proxy for Kinesis

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. If this is your first time using API Gateway, you see a page that introduces you to the features of the service. Under **REST API**, choose **Build**. When the **Create Example API** popup appears, choose **OK**.

If this is not your first time using API Gateway, choose **Create API**. Under **REST API**, choose **Build**.

3. Choose **New API**.
4. In **API name**, enter **KinesisProxy**. Keep the default values for all other fields.
5. (Optional) For **Description**, enter a description.
6. For **IP address type**, select **IPv4**.
7. Choose **Create API**.

After the API is created, the API Gateway console displays the **Resources** page, which contains only the API's root (/) resource.

List streams in Kinesis

Kinesis supports the **ListStreams** action with the following REST API call:

```
POST /?Action=ListStreams HTTP/1.1
Host: kinesis.<region>.<domain>
Content-Length: <PayloadSizeBytes>
User-Agent: <UserAgentString>
Content-Type: application/x-amz-json-1.1
Authorization: <AuthParams>
X-Amz-Date: <Date>

{
  ...
}
```

In the above REST API request, the action is specified in the **Action** query parameter. Alternatively, you can specify the action in a **X-Amz-Target** header, instead:

```
POST / HTTP/1.1
Host: kinesis.<region>.<domain>
Content-Length: <PayloadSizeBytes>
User-Agent: <UserAgentString>
Content-Type: application/x-amz-json-1.1
Authorization: <AuthParams>
X-Amz-Date: <Date>
X-Amz-Target: Kinesis_20131202.ListStreams
{
  ...
}
```

In this tutorial, we use the query parameter to specify action.

To expose a Kinesis action in the API, add a `/streams` resource to the API's root. Then set a GET method on the resource and integrate the method with the `ListStreams` action of Kinesis.

The following procedure describes how to list Kinesis streams by using the API Gateway console.

To list Kinesis streams by using the API Gateway console

1. Select the `/` resource, and then choose **Create resource**.
2. For **Resource name**, enter `streams`.
3. Keep **CORS (Cross Origin Resource Sharing)** turned off.
4. Choose **Create resource**.
5. Choose the `/streams` resource, and then choose **Create method**, and then do the following:
 - a. For **Method type**, select **GET**.

 **Note**

The HTTP verb for a method invoked by a client may differ from the HTTP verb for an integration required by the backend. We select GET here, because listing streams is intuitively a READ operation.

- b. For **Integration type**, select **AWS service**.
- c. For **AWS Region**, select the AWS Region where you created your Kinesis stream.
- d. For **AWS service**, select **Kinesis**.
- e. Keep **AWS subdomain** blank.
- f. For **HTTP method**, choose **POST**.

 **Note**

We chose POST here because Kinesis requires that the `ListStreams` action be invoked with it.

- g. For **Action type**, choose **Use action name**.
- h. For **Action name**, enter **ListStreams**.
- i. For **Execution role**, enter the ARN for your execution role.

- j. Keep the default of **Passthrough for Content Handling**.
- k. Choose **Create method**.
6. On the **Integration request** tab, under **Integration request settings**, choose **Edit**.
7. For **Request body passthrough**, select **When there are no templates defined (recommended)**.
8. Choose **URL request headers parameters**, and then do the following:
 - a. Choose **Add request headers parameter**.
 - b. For **Name**, enter **Content-Type**.
 - c. For **Mapped from**, enter '**application/x-amz-json-1.1**'.

We use a request parameter mapping to set the Content-Type header to the static value of 'application/x-amz-json-1.1' to inform Kinesis that the input is of a specific version of JSON.

9. Choose **Mapping templates**, and then choose **Add mapping template**, and do the following:
 - a. For **Content-Type**, enter **application/json**.
 - b. For **Template body**, enter **{}**.
 - c. Choose **Save**.

The [ListStreams](#) request takes a payload of the following JSON format:

```
{  
    "ExclusiveStartStreamName": "string",  
    "Limit": number  
}
```

However, the properties are optional. To use the default values, we opted for an empty JSON payload here.

10. Test the GET method on the **/streams** resource to invoke the **ListStreams** action in Kinesis:

Choose the **Test** tab. You might need to choose the right arrow button to show the tab.

Choose **Test** to test your method.

If you already created two streams named "myStream" and "yourStream" in Kinesis, the successful test returns a 200 OK response containing the following payload:

```
{  
    "HasMoreStreams": false,  
    "StreamNames": [  
        "myStream",  
        "yourStream"  
    ]  
}
```

Create, describe, and delete a stream in Kinesis

Creating, describing, and deleting a stream in Kinesis involves making the following Kinesis REST API requests, respectively:

```
POST /?Action=CreateStream HTTP/1.1  
Host: kinesis.region.domain  
...  
Content-Type: application/x-amz-json-1.1  
Content-Length: PayloadSizeBytes  
  
{  
    "ShardCount": number,  
    "StreamName": "string"  
}
```

```
POST /?Action=DescribeStream HTTP/1.1  
Host: kinesis.region.domain  
...  
Content-Type: application/x-amz-json-1.1  
Content-Length: PayloadSizeBytes  
  
{  
    "StreamName": "string"
```

```
}
```

```
POST /?Action=DeleteStream HTTP/1.1
Host: kinesis.region.domain
...
Content-Type: application/x-amz-json-1.1
Content-Length: PayloadSizeBytes

{
    "StreamName": "string"
}
```

We can build the API to accept the required input as a JSON payload of the method request and pass the payload through to the integration request. However, to provide more examples of data mapping between method and integration requests, and method and integration responses, we create our API somewhat differently.

We expose the GET, POST, and Delete HTTP methods on a to-be-named Stream resource. We use the {stream-name} path variable as the placeholder of the stream resource and integrate these API methods with the Kinesis' DescribeStream, CreateStream, and DeleteStream actions, respectively. We require that the client pass other input data as headers, query parameters, or the payload of a method request. We provide mapping templates to transform the data to the required integration request payload.

To create the {stream-name} resource

1. Choose the **/streams** resource, and then choose **Create resource**.
2. Keep **Proxy resource** turned off.
3. For **Resource path**, select **/streams**.
4. For **Resource name**, enter **{stream-name}**.
5. Keep **CORS (Cross Origin Resource Sharing)** turned off.
6. Choose **Create resource**.

To configure and test the GET method on a stream resource

1. Choose the **{stream-name}** resource, and then choose **Create method**.
2. For **Method type**, select **GET**.
3. For **Integration type**, select **AWS service**.
4. For **AWS Region**, select the AWS Region where you created your Kinesis stream.
5. For **AWS service**, select **Kinesis**.
6. Keep **AWS subdomain** blank.
7. For **HTTP method**, choose **POST**.
8. For **Action type**, choose **Use action name**.
9. For **Action name**, enter **DescribeStream**.
10. For **Execution role**, enter the ARN for your execution role.
11. Keep the default of **Passthrough** for **Content Handling**.
12. Choose **Create method**.
13. In the **Integration request** section, add the following **URL request headers parameters**:

```
Content-Type: 'x-amz-json-1.1'
```

The task follows the same procedure to set up the request parameter mapping for the GET /streams method.

14. Add the following body mapping template to map data from the GET /streams/{stream-name} method request to the POST /?Action=DescribeStream integration request:

```
{  
    "StreamName": "$input.params('stream-name')"  
}
```

This mapping template generates the required integration request payload for the **DescribeStream** action of Kinesis from the method request's **stream-name** path parameter value.

15. To test the GET /stream/{stream-name} method to invoke the **DescribeStream** action in Kinesis, choose the **Test** tab.
16. For **Path**, under **stream-name**, enter the name of an existing Kinesis stream.

17. Choose **Test**. If the test is successful, a 200 OK response is returned with a payload similar to the following:

```
{  
    "StreamDescription": {  
        "HasMoreShards": false,  
        "RetentionPeriodHours": 24,  
        "Shards": [  
            {  
                "HashKeyRange": {  
                    "EndingHashKey": "68056473384187692692674921486353642290",  
                    "StartingHashKey": "0"  
                },  
                "SequenceNumberRange": {  
                    "StartingSequenceNumber":  
                        "49559266461454070523309915164834022007924120923395850242"  
                },  
                "ShardId": "shardId-000000000000"  
            },  
            ...  
            {  
                "HashKeyRange": {  
                    "EndingHashKey": "340282366920938463463374607431768211455",  
                    "StartingHashKey": "272225893536750770770699685945414569164"  
                },  
                "SequenceNumberRange": {  
                    "StartingSequenceNumber":  
                        "49559266461543273504104037657400164881014714369419771970"  
                },  
                "ShardId": "shardId-000000000004"  
            }  
        ],  
        "StreamARN": "arn:aws:kinesis:us-east-1:12345678901:stream/myStream",  
        "StreamName": "myStream",  
        "StreamStatus": "ACTIVE"  
    }  
}
```

After you deploy the API, you can make a REST request against this API method:

```
GET https://your-api-id.execute-api.region.amazonaws.com/stage/streams/myStream
HTTP/1.1
Host: your-api-id.execute-api.region.amazonaws.com
Content-Type: application/json
Authorization: ...
X-Amz-Date: 20160323T194451Z
```

To configure and test the POST method on a stream resource

1. Choose the **{stream-name}** resource, and then choose **Create method**.
2. For **Method type**, select **POST**.
3. For **Integration type**, select **AWS service**.
4. For **AWS Region**, select the AWS Region where you created your Kinesis stream.
5. For **AWS service**, select **Kinesis**.
6. Keep **AWS subdomain** blank.
7. For **HTTP method**, choose **POST**.
8. For **Action type**, choose **Use action name**.
9. For **Action name**, enter **CreateStream**.
10. For **Execution role**, enter the ARN for your execution role.
11. Keep the default of **Passthrough** for **Content Handling**.
12. Choose **Create method**.
13. In the **Integration request** section, add the following **URL request headers parameters**:

```
Content-Type: 'x-amz-json-1.1'
```

The task follows the same procedure to set up the request parameter mapping for the GET /streams method.

14. Add the following body mapping template to map data from the POST /streams/{stream-name} method request to the POST /?Action=CreateStream integration request:

```
{
  "ShardCount": #if($input.path('$.ShardCount') == '') 5 #else
$input.path('$.ShardCount') #end,
```

```
"StreamName": "$input.params('stream-name')"  
}
```

In the preceding mapping template, we set ShardCount to a fixed value of 5 if the client does not specify a value in the method request payload.

15. To test the POST /stream/{stream-name} method to invoke the CreateStream action in Kinesis, choose the **Test** tab.
16. For **Path**, under **stream-name**, enter the name of a new Kinesis stream.
17. Choose **Test**. If the test is successful, a 200 OK response is returned with no data.

After you deploy the API, you can also make a REST API request against the POST method on a Stream resource to invoke the CreateStream action in Kinesis:

```
POST https://your-api-id.execute-api.region.amazonaws.com/stage/streams/yourStream  
HTTP/1.1  
Host: your-api-id.execute-api.region.amazonaws.com  
Content-Type: application/json  
Authorization: ...  
X-Amz-Date: 20160323T194451Z  
  
{  
    "ShardCount": 5  
}
```

Configure and test the DELETE method on a stream resource

1. Choose the **/{stream-name}** resource, and then choose **Create method**.
2. For **Method type**, select **DELETE**.
3. For **Integration type**, select **AWS service**.
4. For **AWS Region**, select the AWS Region where you created your Kinesis stream.
5. For **AWS service**, select **Kinesis**.
6. Keep **AWS subdomain** blank.
7. For **HTTP method**, choose **POST**.
8. For **Action type**, choose **Use action name**.

9. For **Action name**, enter **DeleteStream**.
10. For **Execution role**, enter the ARN for your execution role.
11. Keep the default of **Passthrough** for **Content Handling**.
12. Choose **Create method**.
13. In the **Integration request** section, add the following **URL request headers parameters**:

```
Content-Type: 'x-amz-json-1.1'
```

The task follows the same procedure to set up the request parameter mapping for the GET /streams method.

14. Add the following body mapping template to map data from the DELETE /streams/{stream-name} method request to the corresponding integration request of POST /?Action=DeleteStream:

```
{  
    "StreamName": "$input.params('stream-name')"  
}
```

This mapping template generates the required input for the DELETE /streams/{stream-name} action from the client-supplied URL path name of stream-name.

15. To test the DELETE /stream/{stream-name} method to invoke the DeleteStream action in Kinesis, choose the **Test** tab.
16. For **Path**, under **stream-name**, enter the name of an existing Kinesis stream.
17. Choose **Test**. If the test is successful, a 200 OK response is returned with no data.

After you deploy the API, you can also make the following REST API request against the DELETE method on the Stream resource to call the DeleteStream action in Kinesis:

```
DELETE https://your-api-id.execute-api.region.amazonaws.com/stage/  
streams/yourStream HTTP/1.1  
Host: your-api-id.execute-api.region.amazonaws.com  
Content-Type: application/json  
Authorization: ...  
X-Amz-Date: 20160323T194451Z  
  
{}
```

Get records from and add records to a stream in Kinesis

After you create a stream in Kinesis, you can add data records to the stream and read the data from the stream. Adding data records involves calling the [PutRecords](#) or [PutRecord](#) action in Kinesis. The former adds multiple records whereas the latter adds a single record to the stream.

```
POST /?Action=PutRecords HTTP/1.1
Host: kinesis.region.domain
Authorization: AWS4-HMAC-SHA256 Credential=..., ...
...
Content-Type: application/x-amz-json-1.1
Content-Length: PayloadSizeBytes

{
    "Records": [
        {
            "Data": blob,
            "ExplicitHashKey": "string",
            "PartitionKey": "string"
        }
    ],
    "StreamName": "string"
}
```

or

```
POST /?Action=PutRecord HTTP/1.1
Host: kinesis.region.domain
Authorization: AWS4-HMAC-SHA256 Credential=..., ...
...
Content-Type: application/x-amz-json-1.1
Content-Length: PayloadSizeBytes

{
    "Data": blob,
    "ExplicitHashKey": "string",
```

```
"PartitionKey": "string",
"SequenceNumberForOrdering": "string",
"StreamName": "string"
}
```

Here, StreamName identifies the target stream to add records. StreamName, Data, and PartitionKey are required input data. In our example, we use the default values for all of the optional input data and will not explicitly specify values for them in the input to the method request.

Reading data in Kinesis amounts to calling the [GetRecords](#) action:

```
POST /?Action=GetRecords HTTP/1.1
Host: kinesis.region.domain
Authorization: AWS4-HMAC-SHA256 Credential=..., ...
...
Content-Type: application/x-amz-json-1.1
Content-Length: PayloadSizeBytes

{
    "ShardIterator": "string",
    "Limit": number
}
```

Here, the source stream from which we are getting records is specified in the required ShardIterator value, as is shown in the following Kinesis action to obtain a shard iterator:

```
POST /?Action=GetShardIterator HTTP/1.1
Host: kinesis.region.domain
Authorization: AWS4-HMAC-SHA256 Credential=..., ...
...
Content-Type: application/x-amz-json-1.1
Content-Length: PayloadSizeBytes


{
    "ShardId": "string",
    "ShardIteratorType": "string",
    "StartingSequenceNumber": "string",
    "StreamName": "string"
}
```

For the GetRecords and PutRecords actions, we expose the GET and PUT methods, respectively, on a /records resource that is appended to a named stream resource (/{{stream-name}}). Similarly, we expose the PutRecord action as a PUT method on a /record resource.

Because the GetRecords action takes as input a ShardIterator value, which is obtained by calling the GetShardIterator helper action, we expose a GET helper method on a ShardIterator resource (/sharditerator).

To create the /record, /records, and /sharditerator resources

1. Choose the /{{stream-name}} resource, and then choose **Create resource**.
2. Keep **Proxy resource** turned off.
3. For **Resource path**, select /{{stream-name}}.
4. For **Resource name**, enter **record**.
5. Keep **CORS (Cross Origin Resource Sharing)** turned off.
6. Choose **Create resource**.
7. Repeat the previous steps to create a /records and a /sharditerator resource. The final API should look like the following:



The following four procedures describe how to set up each of the methods, how to map data from the method requests to the integration requests, and how to test the methods.

To set up and test the `PUT /streams/{stream-name}/record` method to invoke PutRecord in Kinesis:

1. Choose the `/record`, and then choose **Create method**.
2. For **Method type**, select **PUT**.
3. For **Integration type**, select **AWS service**.
4. For **AWS Region**, select the AWS Region where you created your Kinesis stream.
5. For **AWS service**, select **Kinesis**.
6. Keep **AWS subdomain** blank.
7. For **HTTP method**, choose **POST**.
8. For **Action type**, choose **Use action name**.
9. For **Action name**, enter **PutRecord**.
10. For **Execution role**, enter the ARN for your execution role.
11. Keep the default of **Passthrough** for **Content Handling**.
12. Choose **Create method**.
13. In the **Integration request** section, add the following **URL request headers parameters**:

```
Content-Type: 'x-amz-json-1.1'
```

The task follows the same procedure to set up the request parameter mapping for the `GET /streams` method.

14. Add the following body mapping template to map data from the `PUT /streams/{stream-name}/record` method request to the corresponding integration request of `POST /?`
Action=PutRecord:

```
{  
    "StreamName": "$input.params('stream-name')",  
    "Data": "$util.base64Encode($input.json('$Data'))",  
    "PartitionKey": "$input.path('$PartitionKey')"  
}
```

This mapping template assumes that the method request payload is of the following format:

```
{
```

```
"Data": "some data",
"PartitionKey": "some key"
}
```

This data can be modeled by the following JSON schema:

```
{
  "$schema": "http://json-schema.org/draft-04/schema#",
  "title": "PutRecord proxy single-record payload",
  "type": "object",
  "properties": {
    "Data": { "type": "string" },
    "PartitionKey": { "type": "string" }
  }
}
```

You can create a model to include this schema and use the model to facilitate generating the mapping template. However, you can generate a mapping template without using any model.

15. To test the `PUT /streams/{stream-name}/record` method, set the `stream-name` path variable to the name of an existing stream, supply a payload of the required format, and then submit the method request. The successful result is a `200 OK` response with a payload of the following format:

```
{
  "SequenceNumber": "49559409944537880850133345460169886593573102115167928386",
  "ShardId": "shardId-000000000004"
}
```

To set up and test the `PUT /streams/{stream-name}/records` method to invoke PutRecords in Kinesis

1. Choose the `/records` resource, and then choose **Create method**.
2. For **Method type**, select **PUT**.
3. For **Integration type**, select **AWS service**.
4. For **AWS Region**, select the AWS Region where you created your Kinesis stream.
5. For **AWS service**, select **Kinesis**.

6. Keep **AWS subdomain** blank.
7. For **HTTP method**, choose **POST**.
8. For **Action type**, choose **Use action name**.
9. For **Action name**, enter **PutRecords**.
10. For **Execution role**, enter the ARN for your execution role.
11. Keep the default of **Passthrough** for **Content Handling**.
12. Choose **Create method**.
13. In the **Integration request** section, add the following **URL request headers parameters**:

```
Content-Type: 'x-amz-json-1.1'
```

The task follows the same procedure to set up the request parameter mapping for the GET /streams method.

14. Add the following mapping template to map data from the PUT /streams/{stream-name}/records method request to the corresponding integration request of POST /?Action=PutRecords :

```
{  
    "StreamName": "$input.params('stream-name')",  
    "Records": [  
        #foreach($elem in $input.path('$..records'))  
        {  
            "Data": "$util.base64Encode($elem.data)",  
            "PartitionKey": "$elem.partition-key"  
        }#if($foreach.hasNext),#end  
        #end  
    ]  
}
```

This mapping template assumes that the method request payload can be modelled by the following JSON schema:

```
{  
    "$schema": "http://json-schema.org/draft-04/schema#",  
    "title": "PutRecords proxy payload data",  
    "type": "object",  
    "properties": {  
        "records": {
```

```
"type": "array",
"items": {
    "type": "object",
    "properties": {
        "data": { "type": "string" },
        "partition-key": { "type": "string" }
    }
}
}
```

You can create a model to include this schema and use the model to facilitate generating the mapping template. However, you can generate a mapping template without using any model.

In this tutorial, we used two slightly different payload formats to illustrate that an API developer can choose to expose the backend data format to the client or hide it from the client. One format is for the `PUT /streams/{stream-name}/records` method (above). Another format is used for the `PUT /streams/{stream-name}/record` method (in the previous procedure). In production environment, you should keep both formats consistent.

15.

To test the `PUT /streams/{stream-name}/records` method, set the `stream-name` path variable to an existing stream, supply the following payload, and submit the method request.

```
{
    "records": [
        {
            "data": "some data",
            "partition-key": "some key"
        },
        {
            "data": "some other data",
            "partition-key": "some key"
        }
    ]
}
```

The successful result is a 200 OK response with a payload similar to the following output:

```
{  
    "FailedRecordCount": 0,  
    "Records": [  
        {  
            "SequenceNumber": "49559409944537880850133345460167468741933742152373764162",  
            "ShardId": "shardId-000000000004"  
        },  
        {  
            "SequenceNumber": "49559409944537880850133345460168677667753356781548470338",  
            "ShardId": "shardId-000000000004"  
        }  
    ]  
}
```

To set up and test the GET /streams/{stream-name}/sharditerator method invoke GetShardIterator in Kinesis

The GET /streams/{stream-name}/sharditerator method is a helper method to acquire a required shard iterator before calling the GET /streams/{stream-name}/records method.

1. Choose the **/sharditerator** resource, and then choose **Create method**.
2. For **Method type**, select **GET**.
3. For **Integration type**, select **AWS service**.
4. For **AWS Region**, select the AWS Region where you created your Kinesis stream.
5. For **AWS service**, select **Kinesis**.
6. Keep **AWS subdomain** blank.
7. For **HTTP method**, choose **POST**.
8. For **Action type**, choose **Use action name**.
9. For **Action name**, enter **GetShardIterator**.
10. For **Execution role**, enter the ARN for your execution role.
11. Keep the default of **Passthrough** for **Content Handling**.
12. Choose **URL query string parameters**.

The GetShardIterator action requires an input of a ShardId value. To pass a client-supplied ShardId value, we add a shard-id query parameter to the method request, as shown in the following step.

13. Choose **Add query string**.
14. For **Name**, enter **shard-id**.
15. Keep **Required** and **Caching** turned off.
16. Choose **Create method**.
17. In the **Integration request** section, add the following mapping template to generate the required input (ShardId and StreamName) to the GetShardIterator action from the shard-id and stream-name parameters of the method request. In addition, the mapping template also sets ShardIteratorType to TRIM_HORIZON as a default.

```
{  
    "ShardId": "$input.params('shard-id')",  
    "ShardIteratorType": "TRIM_HORIZON",  
    "StreamName": "$input.params('stream-name')"  
}
```

18. Using the **Test** option in the API Gateway console, enter an existing stream name as the **stream-name Path** variable value, set the **shard-id Query string** to an existing ShardId value (e.g., shard-000000000004), and choose **Test**.

The successful response payload is similar to the following output:

```
{  
    "ShardIterator": "AAAAAAAAAAFYVN3V1Fy..."  
}
```

Make note of the ShardIterator value. You need it to get records from a stream.

To configure and test the GET /streams/{stream-name}/records method to invoke the GetRecords action in Kinesis

1. Choose the **/records** resource, and then choose **Create method**.
2. For **Method type**, select **GET**.
3. For **Integration type**, select **AWS service**.
4. For **AWS Region**, select the AWS Region where you created your Kinesis stream.
5. For **AWS service**, select **Kinesis**.
6. Keep **AWS subdomain** blank.

7. For **HTTP method**, choose **POST**.
8. For **Action type**, choose **Use action name**.
9. For **Action name**, enter **GetRecords**.
10. For **Execution role**, enter the ARN for your execution role.
11. Keep the default of **Passthrough** for **Content Handling**.
12. Choose **HTTP request headers**.

The GetRecords action requires an input of a ShardIterator value. To pass a client-supplied ShardIterator value, we add a **Shard-Iterator** header parameter to the method request.

13. Choose **Add header**.
14. For **Name**, enter **Shard-Iterator**.
15. Keep **Required** and **Caching** turned off.
16. Choose **Create method**.
17. In the **Integration request** section, add the following body mapping template to map the **Shard-Iterator** header parameter value to the **ShardIterator** property value of the JSON payload for the GetRecords action in Kinesis.

```
{  
    "ShardIterator": "$input.params('Shard-Iterator')"  
}
```

18. Using the **Test** option in the API Gateway console, enter an existing stream name as the **stream-name** **Path** variable value, set the **Shard-Iterator Header** to the **ShardIterator** value obtained from the test run of the `GET /streams/{stream-name}/sharditerator` method (above), and choose **Test**.

The successful response payload is similar to the following output:

```
{  
    "MillisBehindLatest": 0,  
    "NextShardIterator": "AAAAAAAAAAF... ",  
    "Records": [ ... ]  
}
```

OpenAPI definitions of a sample API as a Kinesis proxy

Following are OpenAPI definitions for the sample API as a Kinesis proxy used in this tutorial.

OpenAPI 3.0

```
{  
  "openapi": "3.0.0",  
  "info": {  
    "title": "KinesisProxy",  
    "version": "2016-03-31T18:25:32Z"  
  },  
  "paths": {  
    "/streams/{stream-name}/sharditerator": {  
      "get": {  
        "parameters": [  
          {  
            "name": "stream-name",  
            "in": "path",  
            "required": true,  
            "schema": {  
              "type": "string"  
            }  
          },  
          {  
            "name": "shard-id",  
            "in": "query",  
            "schema": {  
              "type": "string"  
            }  
          }  
        ]  
      },  
      "responses": {  
        "200": {  
          "description": "200 response",  
          "content": {  
            "application/json": {  
              "schema": {  
                "$ref": "#/components/schemas/Empty"  
              }  
            }  
          }  
        }  
      }  
    },  
  },  
}
```

```
"x-amazon-apigateway-integration": {
    "type": "aws",
    "credentials": "arn:aws:iam::123456789012:role/apigAwsProxyRole",
    "uri": "arn:aws:apigateway:us-east-1:kinesis:action/GetShardIterator",
    "responses": {
        "default": {
            "statusCode": "200"
        }
    },
    "requestParameters": {
        "integration.request.header.Content-Type": "'application/x-amz-
json-1.1'"
    },
    "requestTemplates": {
        "application/json": "{\n            \"ShardId\": \"$input.params('shard-
id')\", \n            \"ShardIteratorType\": \"TRIM_HORIZON\", \n            \"StreamName\":
\"$input.params('stream-name')\"\n        }"
    },
    "passthroughBehavior": "when_no_match",
    "httpMethod": "POST"
}
},
"/streams/{stream-name}/records": {
    "get": {
        "parameters": [
            {
                "name": "stream-name",
                "in": "path",
                "required": true,
                "schema": {
                    "type": "string"
                }
            },
            {
                "name": "Shard-Iterator",
                "in": "header",
                "schema": {
                    "type": "string"
                }
            }
        ],
        "responses": {
            "200": {

```

```
        "description": "200 response",
        "content": {
            "application/json": {
                "schema": {
                    "$ref": "#/components/schemas/Empty"
                }
            }
        }
    },
    "x-amazon-apigateway-integration": {
        "type": "aws",
        "credentials": "arn:aws:iam::123456789012:role/apigAwsProxyRole",
        "uri": "arn:aws:apigateway:us-east-1:kinesis:action/GetRecords",
        "responses": {
            "default": {
                "statusCode": "200"
            }
        },
        "requestParameters": {
            "integration.request.header.Content-Type": "'application/x-amz-json-1.1'"
        },
        "requestTemplates": {
            "application/json": "{\n    \"ShardIterator\": \"$input.params('ShardIterator')\"\n}"
        },
        "passthroughBehavior": "when_no_match",
        "httpMethod": "POST"
    },
    "put": {
        "parameters": [
            {
                "name": "Content-Type",
                "in": "header",
                "schema": {
                    "type": "string"
                }
            },
            {
                "name": "stream-name",
                "in": "path",
                "required": true,
                "schema": {
                    "type": "string"
                }
            }
        ]
    }
}
```

```
        "schema": {
            "type": "string"
        }
    ],
    "requestBody": {
        "content": {
            "application/json": {
                "schema": {
                    "$ref": "#/components/schemas/PutRecordsMethodRequestPayload"
                }
            },
            "application/x-amz-json-1.1": {
                "schema": {
                    "$ref": "#/components/schemas/PutRecordsMethodRequestPayload"
                }
            }
        },
        "required": true
    },
    "responses": {
        "200": {
            "description": "200 response",
            "content": {
                "application/json": {
                    "schema": {
                        "$ref": "#/components/schemas/Empty"
                    }
                }
            }
        }
    },
    "x-amazon-apigateway-integration": {
        "type": "aws",
        "credentials": "arn:aws:iam::123456789012:role/apigAwsProxyRole",
        "uri": "arn:aws:apigateway:us-east-1:kinesis:action/PutRecords",
        "responses": {
            "default": {
                "statusCode": "200"
            }
        },
        "requestParameters": {
            "integration.request.header.Content-Type": "'application/x-amz-json-1.1'"
        }
    }
}
```

```
        },
        "requestTemplates": {
            "application/json": "{\n                \"StreamName\": \"$input.params('stream-\nname')\", \n                \"Records\": [\n                    {\n                        \"Data\": \"$util.base64Encode($elem.data)\",\n                        \"PartitionKey\": \"$elem.partition-key\"\n                    }#if($foreach.hasNext),#end\n                ]\n            },\n            \"application/x-amz-json-1.1\": \"{\\n    \"StreamName\": \"$input.params('stream-name')\",\\n    \"records\" : [\n        {\\n            \"Data\" : \"$elem.data\",\\n            \"PartitionKey\" : \"$elem.partition-key\"\n        }#if($foreach.hasNext),#end\\n    ]\\n}\",\n            \"passthroughBehavior\": \"when_no_match\",\n            \"httpMethod\": \"POST\"\n        }\n    }\n},\n\"/streams/{stream-name}\": {\n    \"get\": {\n        \"parameters\": [\n            {\n                \"name\": \"stream-name\",\n                \"in\": \"path\",\n                \"required\": true,\n                \"schema\": {\n                    \"type\": \"string\"\n                }\n            }\n        ],\n        \"responses\": {\n            \"200\": {\n                \"description\": \"200 response\",\n                \"content\": {\n                    \"application/json\": {\n                        \"schema\": {\n                            \"$ref\": \"#/components/schemas/Empty\"\n                        }\n                    }\n                }\n            }\n        },\n        \"x-amazon-apigateway-integration\": {\n            \"type\": \"aws\",\n            \"credentials\": \"arn:aws:iam::123456789012:role/apigAwsProxyRole\",\n            \"uri\": \"arn:aws:apigateway:us-east-1:kinesis:action/DescribeStream\",
```

```
"responses": {
    "default": {
        "statusCode": "200"
    }
},
"requestTemplates": {
    "application/json": "{\n      \"$StreamName\": \"$input.params('stream-name')\"\n    }"
},
"passthroughBehavior": "when_no_match",
"httpMethod": "POST"
},
"post": {
    "parameters": [
        {
            "name": "stream-name",
            "in": "path",
            "required": true,
            "schema": {
                "type": "string"
            }
        }
    ],
    "responses": {
        "200": {
            "description": "200 response",
            "content": {
                "application/json": {
                    "schema": {
                        "$ref": "#/components/schemas/Empty"
                    }
                }
            }
        }
    }
},
"x-amazon-apigateway-integration": {
    "type": "aws",
    "credentials": "arn:aws:iam::123456789012:role/apigAwsProxyRole",
    "uri": "arn:aws:apigateway:us-east-1:kinesis:action/CreateStream",
    "responses": {
        "default": {
            "statusCode": "200"
        }
    }
}
```

```
        },
        "requestParameters": {
            "integration.request.header.Content-Type": "'application/x-amz-
json-1.1'"
        },
        "requestTemplates": {
            "application/json": "{\n                \"ShardCount\": 5,\n                \"StreamName\": \"$input.params('stream-name')\"\n            }"
        },
        "passthroughBehavior": "when_no_match",
        "httpMethod": "POST"
    }
},
"delete": {
    "parameters": [
        {
            "name": "stream-name",
            "in": "path",
            "required": true,
            "schema": {
                "type": "string"
            }
        }
    ],
    "responses": {
        "200": {
            "description": "200 response",
            "headers": {
                "Content-Type": {
                    "schema": {
                        "type": "string"
                    }
                }
            },
            "content": {
                "application/json": {
                    "schema": {
                        "$ref": "#/components/schemas/Empty"
                    }
                }
            }
        },
        "400": {
            "description": "400 response",
            "headers": {
                "Content-Type": {
                    "schema": {
                        "type": "string"
                    }
                }
            }
        }
    }
}
```

```
"headers": {
    "Content-Type": {
        "schema": {
            "type": "string"
        }
    }
},
"content": {}
},
"500": {
    "description": "500 response",
    "headers": {
        "Content-Type": {
            "schema": {
                "type": "string"
            }
        }
    },
    "content": {}
}
},
"x-amazon-apigateway-integration": {
    "type": "aws",
    "credentials": "arn:aws:iam::123456789012:role/apigAwsProxyRole",
    "uri": "arn:aws:apigateway:us-east-1:kinesis:action/DeleteStream",
    "responses": {
        "4\d{2}": {
            "statusCode": "400",
            "responseParameters": {
                "method.response.header.Content-Type": "integration.response.header.Content-Type"
            }
        },
        "default": {
            "statusCode": "200",
            "responseParameters": {
                "method.response.header.Content-Type": "integration.response.header.Content-Type"
            }
        }
    },
    "5\d{2}": {
        "statusCode": "500",
        "responseParameters": {
            "method.response.header.Content-Type": "integration.response.header.Content-Type"
        }
    }
}
```

```
        "method.response.header.Content-Type":  
    "integration.response.header.Content-Type"  
    }  
}  
},  
"requestParameters": {  
    "integration.request.header.Content-Type": "'application/x-amz-  
json-1.1'"  
},  
"requestTemplates": {  
    "application/json": "{\n        \"StreamName\": \"$input.params('stream-  
name')\"\n    }",  
    "passthroughBehavior": "when_no_match",  
    "httpMethod": "POST"  
}  
}  
}  
},  
"/streams/{stream-name}/record": {  
    "put": {  
        "parameters": [  
            {  
                "name": "stream-name",  
                "in": "path",  
                "required": true,  
                "schema": {  
                    "type": "string"  
                }  
            }  
        ],  
        "responses": {  
            "200": {  
                "description": "200 response",  
                "content": {  
                    "application/json": {  
                        "schema": {  
                            "$ref": "#/components/schemas/Empty"  
                        }  
                    }  
                }  
            }  
        },  
        "x-amazon-apigateway-integration": {  
            "type": "aws",  
            "httpMethod": "PUT",  
            "uri": "https://kinesis.{region}.amazonaws.com:443/streams/{stream-name}/record",  
            "parameters": {  
                "X-Amz-Target": "KinesisStreamsPushStream.PutRecord",  
                "X-Amz-Region": "",  
                "X-Amz-SessionToken": "",  
                "X-Amz-Source": "",  
                "X-Amz-StreamName": {"from": "parameters.stream-name"},  
                "X-Amz-SequenceNumber": "",  
                "X-Amz-Data": {"from": "body"}  
            },  
            "methodResponses": {  
                "200": {  
                    "model": "Empty",  
                    "description": "Success response"  
                }  
            }  
        }  
    }  
}
```

```
"credentials": "arn:aws:iam::123456789012:role/apigAwsProxyRole",
"uri": "arn:aws:apigateway:us-east-1:kinesis:action/PutRecord",
"responses": {
    "default": {
        "statusCode": "200"
    }
},
"requestParameters": {
    "integration.request.header.Content-Type": "'application/x-amz-
json-1.1'"
},
"requestTemplates": {
    "application/json": "{\n      \"StreamName\": \"$input.params('stream-
name')\", \n      \"Data\": \"$util.base64Encode($input.json('$.Data'))\", \n
\"PartitionKey\": \"$input.path('$.PartitionKey')\"\n    }"
},
"passthroughBehavior": "when_no_match",
"httpMethod": "POST"
}
},
"/streams": {
    "get": {
        "responses": {
            "200": {
                "description": "200 response",
                "content": {
                    "application/json": {
                        "schema": {
                            "$ref": "#/components/schemas/Empty"
                        }
                    }
                }
            }
        }
    }
},
"x-amazon-apigateway-integration": {
    "type": "aws",
    "credentials": "arn:aws:iam::123456789012:role/apigAwsProxyRole",
    "uri": "arn:aws:apigateway:us-east-1:kinesis:action/ListStreams",
    "responses": {
        "default": {
            "statusCode": "200"
        }
    }
},
```

```
        "requestParameters": {
            "integration.request.header.Content-Type": "'application/x-amz-
json-1.1'"
        },
        "requestTemplates": {
            "application/json": "{\n}"
        },
        "passthroughBehavior": "when_no_match",
        "httpMethod": "POST"
    }
}
},
"components": {
    "schemas": {
        "Empty": {
            "type": "object"
        },
        "PutRecordsMethodRequestPayload": {
            "type": "object",
            "properties": {
                "records": {
                    "type": "array",
                    "items": {
                        "type": "object",
                        "properties": {
                            "data": {
                                "type": "string"
                            },
                            "partition-key": {
                                "type": "string"
                            }
                        }
                    }
                }
            }
        }
    }
}
```

OpenAPI 2.0

```
{  
  "swagger": "2.0",  
  "info": {  
    "version": "2016-03-31T18:25:32Z",  
    "title": "KinesisProxy"  
  },  
  "basePath": "/test",  
  "schemes": [  
    "https"  
  ],  
  "paths": {  
    "/streams": {  
      "get": {  
        "consumes": [  
          "application/json"  
        ],  
        "produces": [  
          "application/json"  
        ],  
        "responses": {  
          "200": {  
            "description": "200 response",  
            "schema": {  
              "$ref": "#/definitions/Empty"  
            }  
          }  
        }  
      },  
      "x-amazon-apigateway-integration": {  
        "type": "aws",  
        "credentials": "arn:aws:iam::123456789012:role/apigAwsProxyRole",  
        "uri": "arn:aws:apigateway:us-east-1:kinesis:action/ListStreams",  
        "responses": {  
          "default": {  
            "statusCode": "200"  
          }  
        },  
        "requestParameters": {  
          "integration.request.header.Content-Type": "'application/x-amz-  
json-1.1'"  
        }  
      },  
      "requestTemplates": {  
        "application/json": "{\n}"  
      }  
    }  
  }  
}
```

```
        },
        "passthroughBehavior": "when_no_match",
        "httpMethod": "POST"
    }
}
},
"/streams/{stream-name)": {
    "get": {
        "consumes": [
            "application/json"
        ],
        "produces": [
            "application/json"
        ],
        "parameters": [
            {
                "name": "stream-name",
                "in": "path",
                "required": true,
                "type": "string"
            }
        ],
        "responses": {
            "200": {
                "description": "200 response",
                "schema": {
                    "$ref": "#/definitions/Empty"
                }
            }
        }
    },
    "x-amazon-apigateway-integration": {
        "type": "aws",
        "credentials": "arn:aws:iam::123456789012:role/apigAwsProxyRole",
        "uri": "arn:aws:apigateway:us-east-1:kinesis:action/DescribeStream",
        "responses": {
            "default": {
                "statusCode": "200"
            }
        },
        "requestTemplates": {
            "application/json": "{\n              \"StreamName\": \"$input.params('stream-name')\"\n            }"
        },
        "passthroughBehavior": "when_no_match",
    }
}
```

```
        "httpMethod": "POST"
    }
},
"post": {
    "consumes": [
        "application/json"
    ],
    "produces": [
        "application/json"
    ],
    "parameters": [
        {
            "name": "stream-name",
            "in": "path",
            "required": true,
            "type": "string"
        }
    ],
    "responses": {
        "200": {
            "description": "200 response",
            "schema": {
                "$ref": "#/definitions/Empty"
            }
        }
    }
},
"x-amazon-apigateway-integration": {
    "type": "aws",
    "credentials": "arn:aws:iam::123456789012:role/apigAwsProxyRole",
    "uri": "arn:aws:apigateway:us-east-1:kinesis:action/CreateStream",
    "responses": {
        "default": {
            "statusCode": "200"
        }
    },
    "requestParameters": {
        "integration.request.header.Content-Type": "'application/x-amz-json-1.1'"
    },
    "requestTemplates": {
        "application/json": "{$input.params('stream-name')}"
    },
    "passthroughBehavior": "when_no_match",
```

```
        "httpMethod": "POST"
    }
},
"delete": {
    "consumes": [
        "application/json"
    ],
    "produces": [
        "application/json"
    ],
    "parameters": [
        {
            "name": "stream-name",
            "in": "path",
            "required": true,
            "type": "string"
        }
    ],
    "responses": {
        "200": {
            "description": "200 response",
            "schema": {
                "$ref": "#/definitions/Empty"
            },
            "headers": {
                "Content-Type": {
                    "type": "string"
                }
            }
        },
        "400": {
            "description": "400 response",
            "headers": {
                "Content-Type": {
                    "type": "string"
                }
            }
        },
        "500": {
            "description": "500 response",
            "headers": {
                "Content-Type": {
                    "type": "string"
                }
            }
        }
    }
}
```

```
        }
    },
},
"x-amazon-apigateway-integration": {
    "type": "aws",
    "credentials": "arn:aws:iam::123456789012:role/apigAwsProxyRole",
    "uri": "arn:aws:apigateway:us-east-1:kinesis:action/DeleteStream",
    "responses": {
        "4\d{2}": {
            "statusCode": "400",
            "responseParameters": {
                "method.response.header.Content-Type":
"integration.response.header.Content-Type"
            }
        },
        "default": {
            "statusCode": "200",
            "responseParameters": {
                "method.response.header.Content-Type":
"integration.response.header.Content-Type"
            }
        }
    },
    "5\d{2}": {
        "statusCode": "500",
        "responseParameters": {
            "method.response.header.Content-Type":
"integration.response.header.Content-Type"
        }
    }
},
"requestParameters": {
    "integration.request.header.Content-Type": "'application/x-amz-
json-1.1'"
},
"requestTemplates": {
    "application/json": "{\n      \"StreamName\": \"$input.params('stream-
name')\"\n    }"
},
"passthroughBehavior": "when_no_match",
"httpMethod": "POST"
}
},
"/streams/{stream-name}/record": {
```

```
"put": {
    "consumes": [
        "application/json"
    ],
    "produces": [
        "application/json"
    ],
    "parameters": [
        {
            "name": "stream-name",
            "in": "path",
            "required": true,
            "type": "string"
        }
    ],
    "responses": {
        "200": {
            "description": "200 response",
            "schema": {
                "$ref": "#/definitions/Empty"
            }
        }
    },
    "x-amazon-apigateway-integration": {
        "type": "aws",
        "credentials": "arn:aws:iam::123456789012:role/apigAwsProxyRole",
        "uri": "arn:aws:apigateway:us-east-1:kinesis:action/PutRecord",
        "responses": {
            "default": {
                "statusCode": "200"
            }
        },
        "requestParameters": {
            "integration.request.header.Content-Type": "'application/x-amz-json-1.1'"
        },
        "requestTemplates": {
            "application/json": "{\n                \"StreamName\": \"$input.params('stream-name')\", \n                \"Data\": \"$util.base64Encode($input.json('$.Data'))\", \n                \"PartitionKey\": \"$input.path('$.PartitionKey')\"\n            }",
            "passthroughBehavior": "when_no_match",
            "httpMethod": "POST"
        }
    }
}
```

```
        },
    },
    "/streams/{stream-name}/records": {
        "get": {
            "consumes": [
                "application/json"
            ],
            "produces": [
                "application/json"
            ],
            "parameters": [
                {
                    "name": "stream-name",
                    "in": "path",
                    "required": true,
                    "type": "string"
                },
                {
                    "name": "Shard-Iterator",
                    "in": "header",
                    "required": false,
                    "type": "string"
                }
            ],
            "responses": {
                "200": {
                    "description": "200 response",
                    "schema": {
                        "$ref": "#/definitions/Empty"
                    }
                }
            },
            "x-amazon-apigateway-integration": {
                "type": "aws",
                "credentials": "arn:aws:iam::123456789012:role/apigAwsProxyRole",
                "uri": "arn:aws:apigateway:us-east-1:kinesis:action/GetRecords",
                "responses": {
                    "default": {
                        "statusCode": "200"
                    }
                },
                "requestParameters": {
                    "integration.request.header.Content-Type": "'application/x-amz-json-1.1'"
                }
            }
        }
    }
}
```

```
        },
        "requestTemplates": {
            "application/json": "{\n              \"ShardIterator\": \"$input.params('Shard-\nIterator')\"\n            }\n          },
          "passthroughBehavior": "when_no_match",
          "httpMethod": "POST"
        }
      },
      "put": {
        "consumes": [
          "application/json",
          "application/x-amz-json-1.1"
        ],
        "produces": [
          "application/json"
        ],
        "parameters": [
          {
            "name": "Content-Type",
            "in": "header",
            "required": false,
            "type": "string"
          },
          {
            "name": "stream-name",
            "in": "path",
            "required": true,
            "type": "string"
          },
          {
            "in": "body",
            "name": "PutRecordsMethodRequestPayload",
            "required": true,
            "schema": {
              "$ref": "#/definitions/PutRecordsMethodRequestPayload"
            }
          },
          {
            "in": "body",
            "name": "PutRecordsMethodRequestPayload",
            "required": true,
            "schema": {
              "$ref": "#/definitions/PutRecordsMethodRequestPayload"
            }
          }
        ]
      }
    }
  }
}
```

```
        }
    ],
  },
  "responses": {
    "200": {
      "description": "200 response",
      "schema": {
        "$ref": "#/definitions/Empty"
      }
    }
  },
  "x-amazon-apigateway-integration": {
    "type": "aws",
    "credentials": "arn:aws:iam::123456789012:role/apigAwsProxyRole",
    "uri": "arn:aws:apigateway:us-east-1:kinesis:action/PutRecords",
    "responses": {
      "default": {
        "statusCode": "200"
      }
    },
    "requestParameters": {
      "integration.request.header.Content-Type": "'application/x-amz-json-1.1'"
    },
    "requestTemplates": {
      "application/json": "{\n        \"StreamName\": \"$input.params('stream-name')\", \n        \"Records\": [\n            {\n                \"Data\": \"$util.base64Encode($elem.data)\",\n                \"PartitionKey\": \"$elem.partition-key\"\n            }#if($foreach.hasNext),#end\n        ]\n    }",\n      "application/x-amz-json-1.1": "{\n        \"StreamName\": \"$input.params('stream-name')\", \n        \"records\" : [\n            {\n                \"Data\": \"$elem.data\", \n                \"PartitionKey\" : \"$elem.partition-key\"\n            }#if($foreach.hasNext),#end\n        ]\n    }"
    },
    "passthroughBehavior": "when_no_match",
    "httpMethod": "POST"
  }
},
"/streams/{stream-name}/sharditerator": {
  "get": {
    "consumes": [
      "application/json"
    ],
  }
},
```

```
"produces": [
    "application/json"
],
"parameters": [
    {
        "name": "stream-name",
        "in": "path",
        "required": true,
        "type": "string"
    },
    {
        "name": "shard-id",
        "in": "query",
        "required": false,
        "type": "string"
    }
],
"responses": {
    "200": {
        "description": "200 response",
        "schema": {
            "$ref": "#/definitions/Empty"
        }
    }
},
"x-amazon-apigateway-integration": {
    "type": "aws",
    "credentials": "arn:aws:iam::123456789012:role/apigAwsProxyRole",
    "uri": "arn:aws:apigateway:us-east-1:kinesis:action/GetShardIterator",
    "responses": {
        "default": {
            "statusCode": "200"
        }
    },
    "requestParameters": {
        "integration.request.header.Content-Type": "'application/x-amz-json-1.1'"
    },
    "requestTemplates": {
        "application/json": "{\n            \"ShardId\": \"$input.params('shard-id')\", \n            \"ShardIteratorType\": \"TRIM_HORIZON\", \n            \"StreamName\": \"$input.params('stream-name')\"\n        }"
    },
    "passthroughBehavior": "when_no_match",
}
```

```
        "httpMethod": "POST"
    }
}
},
"definitions": {
    "Empty": {
        "type": "object"
    },
    "PutRecordsMethodRequestPayload": {
        "type": "object",
        "properties": {
            "records": {
                "type": "array",
                "items": {
                    "type": "object",
                    "properties": {
                        "data": {
                            "type": "string"
                        },
                        "partition-key": {
                            "type": "string"
                        }
                    }
                }
            }
        }
    }
}
```

Tutorial: Create a REST API using AWS SDKs or the AWS CLI

Use the following tutorial to create a PetStore API supporting the GET /pets and GET /pets/{petId} methods. The methods are integrated with an HTTP endpoint. You can follow this tutorial using the AWS SDK for JavaScript, the SDK for Python (Boto3), or the AWS CLI. You use the following functions or commands to set up your API:

JavaScript v3

- [CreateRestApiCommand](#)

- [CreateResourceCommand](#)
- [PutMethodCommand](#)
- [PutMethodResponseCommand](#)
- [PutIntegrationCommand](#)
- [PutIntegrationResponseCommand](#)
- [CreateDeploymentCommand](#)

Python

- [create_rest_api](#)
- [create_resource](#)
- [put_method](#)
- [put_method_response](#)
- [put_integration](#)
- [put_integration_response](#)
- [create_deployment](#)

AWS CLI

- [create-rest-api](#)
- [create-resource](#)
- [put-method](#)
- [put-method-response](#)
- [put-integration](#)
- [put-integration-response](#)
- [create-deployment](#)

For more information about the AWS SDK for JavaScript v3, see [What's the AWS SDK for JavaScript?](#). For more information about the SDK for Python (Boto3), see [AWS SDK for Python \(Boto3\)](#). For more information about the AWS CLI, see [What is the AWS CLI?](#).

Set up an edge-optimized PetStore API

In this tutorial, example commands use placeholder values for value IDs such as API ID and resource ID. As you complete the tutorial, replace these values with your own.

To set up an edge-optimized PetStore API using AWS SDKs

1. Use the following example to create a RestApi entity:

JavaScript v3

```
import {APIGatewayClient, CreateRestApiCommand} from "@aws-sdk/client-api-gateway";
(async function (){
  const apig = new APIGatewayClient({region:"us-east-1"});
  const command = new CreateRestApiCommand({
    name: "Simple PetStore (JavaScript v3 SDK)",
    description: "Demo API created using the AWS SDK for JavaScript v3",
    version: "0.00.001",
    binaryMediaTypes: [
      '*'
    ]);
  try {
    const results = await apig.send(command)
    console.log(results)
  } catch (err) {
    console.error(Couldn't create API:\n, err)
  }
})();
```

A successful call returns your API ID and the root resource ID of your API in an output like the following:

```
{
  id: 'abc1234',
  name: 'PetStore (JavaScript v3 SDK)',
  description: 'Demo API created using the AWS SDK for node.js',
  createdDate: 2017-09-05T19:32:35.000Z,
  version: '0.00.001',
  rootResourceId: 'efg567'
  binaryMediaTypes: [ '*' ]
}
```

Python

```
import botocore
import boto3
import logging

logger = logging.getLogger()
apig = boto3.client('apigateway')

try:
    result = apig.create_rest_api(
        name='Simple PetStore (Python SDK)',
        description='Demo API created using the AWS SDK for Python',
        version='0.00.001',
        binaryMediaTypes=[
            '*'
        ]
    )
except botocore.exceptions.ClientError as error:
    logger.exception("Couldn't create REST API %s.", error)
    raise
attribute=["id","name","description","createdDate","version","binaryMediaTypes","apiKeySource"]
filtered_result ={key:result[key] for key in attribute}
print(filtered_result)
```

A successful call returns your API ID and the root resource ID of your API in an output like the following:

```
{'id': 'abc1234', 'name': 'Simple PetStore (Python SDK)', 'description': 'Demo API created using the AWS SDK for Python', 'createdDate': datetime.datetime(2024, 4, 3, 14, 31, 39, tzinfo=tzlocal()), 'version': '0.00.001', 'binaryMediaTypes': ['*'], 'apiKeySource': 'HEADER', 'endpointConfiguration': {'types': ['EDGE']}, 'disableExecuteApiEndpoint': False, 'rootResourceId': 'efg567'}
```

AWS CLI

```
aws apigateway create-rest-api --name 'Simple PetStore (AWS CLI)' --region us-west-2
```

The following is the output of this command:

```
{  
    "id": "abcd1234",  
    "name": "Simple PetStore (AWS CLI)",  
    "createdDate": "2022-12-15T08:07:04-08:00",  
    "apiKeySource": "HEADER",  
    "endpointConfiguration": {  
        "types": [  
            "EDGE"  
        ]  
    },  
    "disableExecuteApiEndpoint": false,  
    "rootResourceId": "efg567"  
}
```

The API you created has an API ID of abcd1234 and a root resource ID of efg567. You use these values in the set up of your API.

2. Next, you append a child resource under the root, you specify the RootResourceId as the parentId property value. Use the following example to create a /pets resource for your API:

JavaScript v3

```
import {APIGatewayClient, CreateResourceCommand } from "@aws-sdk/client-api-gateway";  
(async function (){  
const apig = new APIGatewayClient({region:"us-east-1"});  
const command = new CreateResourceCommand({  
    restApiId: 'abcd1234',  
    parentId: 'efg567',  
    pathPart: 'pets'  
});  
try {  
    const results = await apig.send(command)  
    console.log(results)  
} catch (err) {  
    console.log("The '/pets' resource setup failed:\n", err)  
}  
})();
```

A successful call returns information about your resource in an output like the following:

```
{  
    "path": "/pets",  
    "pathPart": "pets",  
    "id": "aaa111",  
    "parentId": "efg567'"  
}
```

Python

```
import botocore  
import boto3  
import logging  
  
logger = logging.getLogger()  
apig = boto3.client('apigateway')  
  
try:  
    result = apig.create_resource(  
        restApiId='abcd1234',  
        parentId='efg567',  
        pathPart='pets'  
    )  
except botocore.exceptions.ClientError as error:  
    logger.exception("The '/pets' resource setup failed: %s.", error)  
    raise  
attribute=["id", "parentId", "pathPart", "path",]  
filtered_result ={key:result[key] for key in attribute}  
print(filtered_result)
```

A successful call returns information about your resource in an output like the following:

```
{'id': 'aaa111', 'parentId': 'efg567', 'pathPart': 'pets', 'path': '/pets'}
```

AWS CLI

```
aws apigateway create-resource --rest-api-id abcd1234 \  
--region us-west-2 \  
--parent-id efg567 \  
--path-part pets
```

The following is the output of this command:

```
{  
  "id": "aaa111",  
  "parentId": "efg567",  
  "pathPart": "pets",  
  "path": "/pets"  
}
```

The /pets resource you created has a resource ID of aaa111. You use this value in the set up of your API.

3. Next, you append a child resource under the /pets resource. This resource, /{petId} has a path parameter for the {petId}. To make a path part a path parameter, enclose it in a pair of curly brackets, { }. Use the following example to create a /pets/{petId} resource for your API:

JavaScript v3

```
import {APIGatewayClient, CreateResourceCommand } from "@aws-sdk/client-api-gateway";  
(async function (){  
  const apig = new APIGatewayClient({region:"us-east-1"});  
  const command = new CreateResourceCommand({  
    restApiId: 'abcd1234',  
    parentId: 'aaa111',  
    pathPart: '{petId}'  
  });  
  try {  
    const results = await apig.send(command)  
    console.log(results)  
  } catch (err) {  
    console.log("The '/pets/{petId}' resource setup failed:\n", err)  
  }  
})();
```

A successful call returns information about your resource in an output like the following:

```
{  
  "path": "/pets/{petId}",
```

```
"pathPart": "{petId}",
"id": "bbb222",
"parentId": "aaa111"
}
```

Python

```
import botocore
import boto3
import logging

logger = logging.getLogger()
apig = boto3.client('apigateway')

try:
    result = apig.create_resource(
        restApiId='abcd1234',
        parentId='aaa111',
        pathPart='{petId}'
    )
except botocore.exceptions.ClientError as error:
    logger.exception("The '/pets/{petId}' resource setup failed: %s.", error)
    raise
attribute=["id","parentId", "pathPart", "path",]
filtered_result ={key:result[key] for key in attribute}
print(filtered_result)
```

A successful call returns information about your resource in an output like the following:

```
{'id': 'bbb222', 'parentId': 'aaa111', 'pathPart': '{petId}', 'path': '/pets/{petId}'}
```

AWS CLI

```
aws apigateway create-resource --rest-api-id abcd1234 \
--region us-west-2 \
--parent-id aaa111 \
--path-part '{petId}'
```

The following is the output of this command:

```
{  
  "id": "bbb222",  
  "parentId": "aaa111",  
  "path": "/pets/{petId}",  
  "pathPart": "{petId}"  
}
```

The `/pets/{petId}` resource you created has a resource ID of `bbb222`. You use this value in the set up of your API.

4. In the following two steps, you add HTTP methods to your resources. In this tutorial, you set the methods to have open access by setting the `authorization-type` to set to `NONE`. To permit only authenticated users to call the method, you can use IAM roles and policies, a Lambda authorizer (formerly known as a custom authorizer), or an Amazon Cognito user pool. For more information, see [the section called “Access control”](#).

Use the following example to add the GET HTTP method on the `/pets` resource:

JavaScript v3

```
import {APIGatewayClient, PutMethodCommand } from "@aws-sdk/client-api-gateway";  
  
(async function (){  
  const apig = new APIGatewayClient({region:"us-east-1"});  
  const command = new PutMethodCommand({  
    restApiId: 'abcd1234',  
    resourceId: 'aaa111',  
    httpMethod: 'GET',  
    authorizationType: 'NONE'  
  });  
  try {  
    const results = await apig.send(command)  
    console.log(results)  
  } catch (err) {  
    console.log("The 'GET /pets' method setup failed:\n", err)  
  }  
})();
```

A successful call returns the following output:

```
{  
    "apiKeyRequired": false,  
    "httpMethod": "GET",  
    "authorizationType": "NONE"  
}
```

Python

```
import botocore  
import boto3  
import logging  
  
logger = logging.getLogger()  
apig = boto3.client('apigateway')  
  
try:  
    result = apig.put_method(  
        restApiId='abcd1234',  
        resourceId='aaa111',  
        httpMethod='GET',  
        authorizationType='NONE'  
    )  
except botocore.exceptions.ClientError as error:  
    logger.exception("The 'GET /pets' method setup failed: %s", error)  
    raise  
attribute=["httpMethod","authorizationType","apiKeyRequired"]  
filtered_result ={key:result[key] for key in attribute}  
print(filtered_result)
```

A successful call returns the following output:

```
{'httpMethod': 'GET', 'authorizationType': 'NONE', 'apiKeyRequired': False}
```

AWS CLI

```
aws apigateway put-method --rest-api-id abcd1234 \  
--resource-id aaa111 \  
--http-method GET \  
--authorization-type "NONE" \  
--region us-west-2
```

The following is the output of this command:

```
{  
    "httpMethod": "GET",  
    "authorizationType": "NONE",  
    "apiKeyRequired": false  
}
```

5. Use the following example to add the GET HTTP method on the /pets/{petId} resource and to set the `requestParameters` property to pass the client-supplied `petId` value to the backend:

JavaScript v3

```
import {APIGatewayClient, PutMethodCommand } from "@aws-sdk/client-api-gateway";  
(async function (){  
const apig = new APIGatewayClient({region:"us-east-1"});  
const command = new PutMethodCommand({  
    restApiId: 'abcd1234',  
    resourceId: 'bbb222',  
    httpMethod: 'GET',  
    authorizationType: 'NONE'  
    requestParameters: {  
        "method.request.path.petId" : true  
    }  
});  
try {  
    const results = await apig.send(command)  
    console.log(results)  
} catch (err) {  
    console.log("The 'GET /pets/{petId}' method setup failed:\n", err)  
}  
})();
```

A successful call returns the following output:

```
{  
    "apiKeyRequired": false,  
    "httpMethod": "GET",  
    "authorizationType": "NONE",
```

```
    "requestParameters": {
        "method.request.path.petId": true
    }
}
```

Python

```
import botocore
import boto3
import logging

logger = logging.getLogger()
apig = boto3.client('apigateway')

try:
    result = apig.put_method(
        restApiId='abcd1234',
        resourceId='bbb222',
        httpMethod='GET',
        authorizationType='NONE',
        requestParameters={
            "method.request.path.petId": True
        }
)
except botocore.exceptions.ClientError as error:
    logger.exception("The 'GET /pets/{petId}' method setup failed: %s", error)
    raise
attribute=["httpMethod","authorizationType","apiKeyRequired",
"requestParameters"]
filtered_result ={key:result[key] for key in attribute}
print(filtered_result)
```

A successful call returns the following output:

```
{'httpMethod': 'GET', 'authorizationType': 'NONE', 'apiKeyRequired': False,
'requestParameters': {'method.request.path.petId': True}}
```

AWS CLI

```
aws apigateway put-method --rest-api-id abcd1234 \
--resource-id bbb222 --http-method GET \
--authorization-type "NONE" \
```

```
--region us-west-2 \
--request-parameters method.request.path.petId=true
```

The following is the output of this command:

```
{
    "httpMethod": "GET",
    "authorizationType": "NONE",
    "apiKeyRequired": false,
    "requestParameters": {
        "method.request.path.petId": true
    }
}
```

6. Use the following example to add the 200 OK method response for the GET /pets method:

JavaScript v3

```
import {APIGatewayClient, PutMethodResponseCommand } from "@aws-sdk/client-api-gateway";
(async function (){
const apig = new APIGatewayClient({region:"us-east-1"});
const command = new PutMethodResponseCommand({
    restApiId: 'abcd1234',
    resourceId: 'aaa111',
    httpMethod: 'GET',
    statusCode: '200'
});
try {
    const results = await apig.send(command)
    console.log(results)
} catch (err) {
    console.log("Set up the 200 OK response for the 'GET /pets' method failed:
\n", err)
}
})();
```

A successful call returns the following output:

```
{
    "statusCode": "200"
}
```

Python

```
import botocore
import boto3
import logging

logger = logging.getLogger()
apig = boto3.client('apigateway')

try:
    result = apig.put_method_response(
        restApiId='abcd1234',
        resourceId='aaa111',
        httpMethod='GET',
        statusCode='200'
    )
except botocore.exceptions.ClientError as error:
    logger.exception("Set up the 200 OK response for the 'GET /pets' method failed %s.", error)
    raise
attribute=["statusCode"]
filtered_result ={key:result[key] for key in attribute}
logger.info(filtered_result)
```

A successful call returns the following output:

```
{'statusCode': '200'}
```

AWS CLI

```
aws apigateway put-method-response --rest-api-id abcd1234 \
--resource-id aaa111 --http-method GET \
--status-code 200 --region us-west-2
```

The following is the output of this command:

```
{
    "statusCode": "200"
}
```

7. Use the following example to add the 200 OK method response for the GET /pets/{petId} method:

JavaScript v3

```
import {APIGatewayClient, PutMethodResponseCommand } from "@aws-sdk/client-api-gateway";
(async function (){
const apig = new APIGatewayClient({region:"us-east-1"});
const command = new PutMethodResponseCommand({
    restApiId: 'abcd1234',
    resourceId: 'bbb222',
    httpMethod: 'GET',
    statusCode: '200'
});
try {
    const results = await apig.send(command)
    console.log(results)
} catch (err) {
    console.log("Set up the 200 OK response for the 'GET /pets/{petId}' method failed:\n", err)
}
})();
```

A successful call returns the following output:

```
{  
  "statusCode": "200"  
}
```

Python

```
import botocore
import boto3
import logging

logger = logging.getLogger()
apig = boto3.client('apigateway')

try:
    result = apig.put_method_response(
        restApiId='abcd1234',
```

```
        resourceId='bbb222',
        httpMethod='GET',
        statusCode='200'
    )
except botocore.exceptions.ClientError as error:
    logger.exception("Set up the 200 OK response for the 'GET /pets/{petId}'"
method failed %s.", error)
    raise
attribute=["statusCode"]
filtered_result ={key:result[key] for key in attribute}
logger.info(filtered_result)
```

A successful call returns the following output:

```
{'statusCode': '200'}
```

AWS CLI

```
aws apigateway put-method-response --rest-api-id abcd1234 \
--resource-id bbb222 --http-method GET \
--status-code 200 --region us-west-2
```

The following is the output of this command:

```
{
    "statusCode": "200"
}
```

8. Use the following example to configure an integration for the GET /pets method with an HTTP endpoint. The HTTP endpoint is <http://petstore-demo-endpoint.execute-api.com/petstore/pets>.

JavaScript v3

```
import {APIGatewayClient, PutIntegrationCommand } from "@aws-sdk/client-api-gateway";
(async function (){
const apig = new APIGatewayClient({region:"us-east-1"});
const command = new PutIntegrationCommand({
    restApiId: 'abcd1234',
    resourceId: 'aaa111',
```

```
        httpMethod: 'GET',
        type: 'HTTP',
        integrationHttpMethod: 'GET',
        uri: 'http://petstore-demo-endpoint.execute-api.com/petstore/pets'
    );
    try {
        const results = await apig.send(command)
        console.log(results)
    } catch (err) {
        console.log("Set up the integration of the 'GET /pets' method of the API
failed:\n", err)
    }
})();
```

A successful call returns the following output:

```
{
    "httpMethod": "GET",
    "passThroughBehavior": "WHEN_NO_MATCH",
    "cacheKeyParameters": [],
    "type": "HTTP",
    "uri": "http://petstore-demo-endpoint.execute-api.com/petstore/pets",
    "cacheNamespace": "ccc333"
}
```

Python

```
import botocore
import boto3
import logging

logger = logging.getLogger()
apig = boto3.client('apigateway')

try:
    result = apig.put_integration(
        restApiId='abcd1234',
        resourceId='aaa111',
        httpMethod='GET',
        type='HTTP',
        integrationHttpMethod='GET',
        uri='http://petstore-demo-endpoint.execute-api.com/petstore/pets'
```

```
)  
except botocore.exceptions.ClientError as error:  
    logger.exception("Set up the integration of the 'GET /' method of the API  
failed %s.", error)  
    raise  
attribute=["httpMethod","passthroughBehavior","cacheKeyParameters", "type",  
"uri", "cacheNamespace"]  
filtered_result ={key:result[key] for key in attribute}  
print(filtered_result)
```

A successful call returns the following output:

```
{'httpMethod': 'GET', 'passthroughBehavior': 'WHEN_NO_MATCH',  
'cacheKeyParameters': [], 'type': 'HTTP', 'uri': 'http://petstore-demo-  
endpoint.execute-api.com/petstore/pets', 'cacheNamespace': 'ccc333'}
```

AWS CLI

```
aws apigateway put-integration --rest-api-id abcd1234 \  
--resource-id aaa111 --http-method GET --type HTTP \  
--integration-http-method GET \  
--uri 'http://petstore-demo-endpoint.execute-api.com/petstore/pets' \  
--region us-west-2
```

The following is the output of this command:

```
{  
    "type": "HTTP",  
    "httpMethod": "GET",  
    "uri": "http://petstore-demo-endpoint.execute-api.com/petstore/pets",  
    "connectionType": "INTERNET",  
    "passthroughBehavior": "WHEN_NO_MATCH",  
    "timeoutInMillis": 29000,  
    "cacheNamespace": "6sxz2j",  
    "cacheKeyParameters": []  
}
```

9. Use the following example to configure an integration for the GET /pets/{petId} method with an HTTP endpoint. The HTTP endpoint is http://petstore-demo-endpoint.execute-api.com/petstore/pets/{id}. In this step, you map the path parameter petId to the integration endpoint path parameter of id.

JavaScript v3

```
import {APIGatewayClient, PutIntegrationCommand } from "@aws-sdk/client-api-gateway";
(async function (){
const apig = new APIGatewayClient({region:"us-east-1"});
const command = new PutIntegrationCommand({
    restApiId: 'abcd1234',
    resourceId: 'bbb222',
    httpMethod: 'GET',
    type: 'HTTP',
    integrationHttpMethod: 'GET',
    uri: 'http://petstore-demo-endpoint.execute-api.com/petstore/pets/{id}'
    requestParameters: {
        "integration.request.path.id": "method.request.path.petId"
    }
});
try {
    const results = await apig.send(command)
    console.log(results)
} catch (err) {
    console.log("Set up the integration of the 'GET /pets/{petId}' method of the API failed:\n", err)
}
})();
```

A successful call returns the following output:

```
{
    "httpMethod": "GET",
    "passthroughBehavior": "WHEN_NO_MATCH",
    "cacheKeyParameters": [],
    "type": "HTTP",
    "uri": "http://petstore-demo-endpoint.execute-api.com/petstore/pets/{id}",
    "cacheNamespace": "ddd444",
    "requestParameters": {
        "integration.request.path.id": "method.request.path.petId"
    }
}
```

Python

```
import botocore
import boto3
import logging

logger = logging.getLogger()
apig = boto3.client('apigateway')

try:
    result = apig.put_integration(
        restApiId='ieps9b05sf',
        resourceId='t8zeb4',
        httpMethod='GET',
        type='HTTP',
        integrationHttpMethod='GET',
        uri='http://petstore-demo-endpoint.execute-api.com/petstore/pets/{id}',
        requestParameters={
            "integration.request.path.id": "method.request.path.petId"
        }
)
except botocore.exceptions.ClientError as error:
    logger.exception("Set up the integration of the 'GET /pets/{petId}' method of the API failed %s.", error)
    raise
attribute=["httpMethod","passthroughBehavior","cacheKeyParameters", "type",
"uri", "cacheNamespace", "requestParameters"]
filtered_result ={key:result[key] for key in attribute}
print(filtered_result)
```

A successful call returns the following output:

```
{'httpMethod': 'GET', 'passthroughBehavior': 'WHEN_NO_MATCH',
'cacheKeyParameters': [], 'type': 'HTTP', 'uri': 'http://petstore-
demo-endpoint.execute-api.com/petstore/pets/{id}', 'cacheNamespace':
'ddd444', 'requestParameters': {'integration.request.path.id':
'method.request.path.petId'}}}
```

AWS CLI

```
aws apigateway put-integration --rest-api-id abcd1234 \
```

```
--resource-id bbb222 --http-method GET --type HTTP \
--integration-http-method GET \
--uri 'http://petstore-demo-endpoint.execute-api.com/petstore/pets/{id}' \
--request-parameters
'{"integration.request.path.id":"method.request.path.petId"}' \
--region us-west-2
```

The following is the output of this command:

```
{
  "type": "HTTP",
  "httpMethod": "GET",
  "uri": "http://petstore-demo-endpoint.execute-api.com/petstore/pets/{id}",
  "connectionType": "INTERNET",
  "requestParameters": {
    "integration.request.path.id": "method.request.path.petId"
  },
  "passthroughBehavior": "WHEN_NO_MATCH",
  "timeoutInMillis": 29000,
  "cacheNamespace": "rjkmth",
  "cacheKeyParameters": []
}
```

10. Use the following example to add the integration response for the GET /pets integration:

JavaScript v3

```
import {APIGatewayClient, PutIntegrationResponseCommand } from "@aws-sdk/client-api-gateway";
(async function (){
const apig = new APIGatewayClient({region:"us-east-1"});
const command = new PutIntegrationResponseCommand({
  restApiId: 'abcd1234',
  resourceId: 'aaa111',
  httpMethod: 'GET',
  statusCode: '200',
  selectionPattern: ''
});
try {
  const results = await apig.send(command)
  console.log(results)
} catch (err) {
```

```
    console.log("The 'GET /pets' method integration response setup failed:\n",
    err)
}
})();
```

A successful call returns the following output:

```
{
  "selectionPattern": "",
  "statusCode": "200"
}
```

Python

```
import botocore
import boto3
import logging

logger = logging.getLogger()
apig = boto3.client('apigateway')

try:
    result = apig.put_integration_response(
        restApiId='abcd1234',
        resourceId='aaa111',
        httpMethod='GET',
        statusCode='200',
        selectionPattern='',
    )
except botocore.exceptions.ClientError as error:
    logger.exception("Set up the integration response of the 'GET /pets' method
of the API failed: %s", error)
    raise
attribute=["selectionPattern","statusCode"]
filtered_result ={key:result[key] for key in attribute}
print(filtered_result)
```

A successful call returns the following output:

```
{'selectionPattern': "", 'statusCode': '200'}
```

AWS CLI

```
aws apigateway put-integration-response --rest-api-id abcd1234 \
--resource-id aaa111 --http-method GET \
--status-code 200 --selection-pattern "" \
--region us-west-2
```

The following is the output of this command:

```
{  
  "statusCode": "200",  
  "selectionPattern": ""  
}
```

11. Use the following example to add the integration response for the GET /pets/{petId} integration:

JavaScript v3

```
import {APIGatewayClient, PutIntegrationResponseCommand } from "@aws-sdk/client-api-gateway";
(async function (){
  const apig = new APIGatewayClient({region:"us-east-1"});
  const command = new PutIntegrationResponseCommand({
    restApiId: 'abcd1234',
    resourceId: 'bbb222',
    httpMethod: 'GET',
    statusCode: '200',
    selectionPattern: ''
  });
  try {
    const results = await apig.send(command)
    console.log(results)
  } catch (err) {
    console.log("The 'GET /pets/{petId}' method integration response setup failed:\n", err)
  }
})();
```

A successful call returns the following output:

```
{  
    "selectionPattern": "",  
    "statusCode": "200"  
}
```

Python

```
import botocore  
import boto3  
import logging  
  
logger = logging.getLogger()  
apig = boto3.client('apigateway')  
  
try:  
    result = apig.put_integration_response(  
        restApiId='abcd1234',  
        resourceId='bbb222',  
        httpMethod='GET',  
        statusCode='200',  
        selectionPattern='',  
    )  
except botocore.exceptions.ClientError as error:  
    logger.exception("Set up the integration response of the 'GET /pets/{petId}'  
method of the API failed: %s", error)  
    raise  
attribute=["selectionPattern","statusCode"]  
filtered_result ={key:result[key] for key in attribute}  
print(filtered_result)
```

A successful call returns the following output:

```
{'selectionPattern': "", 'statusCode': '200'}
```

AWS CLI

```
aws apigateway put-integration-response --rest-api-id abcd1234 \  
--resource-id bbb222 --http-method GET  
--status-code 200 --selection-pattern ""  
--region us-west-2
```

The following is the output of this command:

```
{  
  "statusCode": "200",  
  "selectionPattern": ""  
}
```

After you create the integration response, your API can query available pets on the PetStore website and to view an individual pet of a specified identifier. Before your API is callable by your customers, you must deploy it. We recommend that before you deploy your API, you test it.

12. Use the following example to test the GET /pets method:

JavaScript v3

```
import {APIGatewayClient, TestInvokeMethodCommand } from "@aws-sdk/client-api-gateway";  
(async function (){  
  const apig = new APIGatewayClient({region:"us-east-1"});  
  const command = new TestInvokeMethodCommand({  
    restApiId: 'abcd1234',  
    resourceId: 'aaa111',  
    httpMethod: 'GET',  
    pathWithQueryString: '/',  
  });  
  try {  
    const results = await apig.send(command)  
    console.log(results)  
  } catch (err) {  
    console.log("The test on 'GET /pets' method failed:\n", err)  
  }  
})();
```

Python

```
import botocore  
import boto3  
import logging
```

```
logger = logging.getLogger()
apig = boto3.client('apigateaway')

try:
    result = apig.test_invoke_method(
        restApiId='abcd1234',
        resourceId='aaa111',
        httpMethod='GET',
        pathWithQueryString='/',
    )
except botocore.exceptions.ClientError as error:
    logger.exception("Test invoke method on 'GET /pets' failed: %s", error)
    raise
print(result)
```

AWS CLI

```
aws apigateway test-invoke-method --rest-api-id abcd1234 /
--resource-id aaa111 /
--http-method GET /
--path-with-query-string '/'
```

13. Use the following example to test the GET /pets/{petId} method with a petId of 3:

JavaScript v3

```
import {APIGatewayClient, TestInvokeMethodCommand } from "@aws-sdk/client-api-gateway";
(async function (){
const apig = new APIGatewayClient({region:"us-east-1"});
const command = new TestInvokeMethodCommand({
    restApiId: 'abcd1234',
    resourceId: 'bbb222',
    httpMethod: 'GET',
    pathWithQueryString: '/pets/3',
});
try {
    const results = await apig.send(command)
    console.log(results)
} catch (err) {
    console.log("The test on 'GET /pets/{petId}' method failed:\n", err)
}
```

```
})();
```

Python

```
import botocore
import boto3
import logging

logger = logging.getLogger()
apig = boto3.client('apigateway')

try:
    result = apig.test_invoke_method(
        restApiId='abcd1234',
        resourceId='bbb222',
        httpMethod='GET',
        pathWithQueryString='/pets/3',
    )
except botocore.exceptions.ClientError as error:
    logger.exception("Test invoke method on 'GET /pets/{petId}' failed: %s",
                      error)
    raise
print(result)
```

AWS CLI

```
aws apigateway test-invoke-method --rest-api-id abcd1234 /
--resource-id bbb222 /
--http-method GET /
--path-with-query-string '/pets/3'
```

After you successfully test your API, you can deploy it to a stage.

14. Use the following example to deploy your API to a stage named `test`. When you deploy your API to a stage, API callers can invoke your API.

JavaScript v3

```
import {APIGatewayClient, CreateDeploymentCommand } from "@aws-sdk/client-api-
gateway";
(async function (){
```

```
const apig = new APIGatewayClient({region:"us-east-1"});
const command = new CreateDeploymentCommand({
    restApiId: 'abcd1234',
    stageName: 'test',
    stageDescription: 'test deployment'
});
try {
    const results = await apig.send(command)
    console.log("Deploying API succeeded\n", results)
} catch (err) {
    console.log("Deploying API failed:\n", err)
}
})();
```

Python

```
import botocore
import boto3
import logging

logger = logging.getLogger()
apig = boto3.client('apigateway')

try:
    result = apig.create_deployment(
        restApiId='ieps9b05sf',
        stageName='test',
        stageDescription='my test stage',
    )
except botocore.exceptions.ClientError as error:
    logger.exception("Error deploying stage %s.", error)
    raise
print('Deploying API succeeded')
print(result)
```

AWS CLI

```
aws apigateway create-deployment --rest-api-id abcd1234 \
--region us-west-2 \
--stage-name test \
--stage-description 'Test stage' \
--description 'First deployment'
```

The following is the output of this command:

```
{  
    "id": "ab1c1d",  
    "description": "First deployment",  
    "createdDate": "2022-12-15T08:44:13-08:00"  
}
```

Your API is now callable by customers. You can test this API by entering the `https://abcd1234.execute-api.us-west-2.amazonaws.com/test/pets` URL in a browser, and substituting abcd1234 with the identifier of your API.

For more examples of how to create or update an API using AWS SDKs or the AWS CLI, see [Actions for API Gateway using AWS SDKs](#).

Automate the setup of your API

Instead of creating your API step-by-step, you can automate the creation and cleanup of AWS resources by using OpenAPI, CloudFormation, or Terraform to create your API.

OpenAPI 3.0 definition

You can import an OpenAPI defintion into API Gateway. For more information, see [the section called “OpenAPI”](#).

```
{  
    "openapi" : "3.0.1",  
    "info" : {  
        "title" : "Simple PetStore (OpenAPI)",  
        "description" : "Demo API created using OpenAPI",  
        "version" : "2024-05-24T20:39:34Z"  
    },  
    "servers" : [ {  
        "url" : "{basePath}",  
        "variables" : {  
            "basePath" : {  
                "default" : "Prod"  
            }  
        }  
    } ],
```

```
"paths" : {
    "/pets" : {
        "get" : {
            "responses" : {
                "200" : {
                    "description" : "200 response",
                    "content" : { }
                }
            },
            "x-amazon-apigateway-integration" : {
                "type" : "http",
                "httpMethod" : "GET",
                "uri" : "http://petstore-demo-endpoint.execute-api.com/petstore/pets",
                "responses" : {
                    "default" : {
                        "statusCode" : "200"
                    }
                },
                "passthroughBehavior" : "when_no_match",
                "timeoutInMillis" : 29000
            }
        }
    },
    "/pets/{petId}" : {
        "get" : {
            "parameters" : [ {
                "name" : "petId",
                "in" : "path",
                "required" : true,
                "schema" : {
                    "type" : "string"
                }
            } ],
            "responses" : {
                "200" : {
                    "description" : "200 response",
                    "content" : { }
                }
            },
            "x-amazon-apigateway-integration" : {
                "type" : "http",
                "httpMethod" : "GET",
                "uri" : "http://petstore-demo-endpoint.execute-api.com/petstore/pets/{id}",
                "responses" : {
```

```
        "default" : {
            "statusCode" : "200"
        },
        "requestParameters" : {
            "integration.request.path.id" : "method.request.path.petId"
        },
        "passthroughBehavior" : "when_no_match",
        "timeoutInMillis" : 29000
    }
}
},
"components" : { }
}
```

AWS CloudFormation template

To deploy your CloudFormation template, see [Creating a stack on the AWS CloudFormation console.](#)

```
AWSTemplateFormatVersion: 2010-09-09
Resources:
  Api:
    Type: 'AWS::ApiGateway::RestApi'
    Properties:
      Name: Simple PetStore (AWS CloudFormation)
  PetsResource:
    Type: 'AWS::ApiGateway::Resource'
    Properties:
      RestApiId: !Ref Api
      ParentId: !GetAtt Api.RootResourceId
      PathPart: 'pets'
  PetIdResource:
    Type: 'AWS::ApiGateway::Resource'
    Properties:
      RestApiId: !Ref Api
      ParentId: !Ref PetsResource
      PathPart: '{petId}'
  PetsMethodGet:
    Type: 'AWS::ApiGateway::Method'
    Properties:
      RestApiId: !Ref Api
```

```
ResourceId: !Ref PetsResource
HttpMethod: GET
AuthorizationType: NONE
Integration:
  Type: HTTP
  IntegrationHttpMethod: GET
  Uri: http://petstore-demo-endpoint.execute-api.com/petstore/pets/
  IntegrationResponses:
    - StatusCode: '200'
MethodResponses:
  - StatusCode: '200'
PetIdMethodGet:
  Type: 'AWS::ApiGateway::Method'
  Properties:
    RestApiId: !Ref Api
    ResourceId: !Ref PetIdResource
    HttpMethod: GET
    AuthorizationType: NONE
    RequestParameters:
      method.request.path.petId: true
  Integration:
    Type: HTTP
    IntegrationHttpMethod: GET
    Uri: http://petstore-demo-endpoint.execute-api.com/petstore/pets/{id}
    RequestParameters:
      integration.request.path.id: method.request.path.petId
  IntegrationResponses:
    - StatusCode: '200'
  MethodResponses:
    - StatusCode: '200'
ApiDeployment:
  Type: 'AWS::ApiGateway::Deployment'
  DependsOn:
    - PetsMethodGet
  Properties:
    RestApiId: !Ref Api
    StageName: Prod
Outputs:
  ApiRootUrl:
    Description: Root Url of the API
    Value: !Sub 'https://${Api}.execute-api.${AWS::Region}.amazonaws.com/Prod'
```

Terraform configuration

For more information about Terraform, see [Terraform](#).

```
provider "aws" {
    region = "us-east-1" # Update with your desired region
}

resource "aws_api_gateway_rest_api" "Api" {
    name      = "Simple PetStore (Terraform)"
    description = "Demo API created using Terraform"
}

resource "aws_api_gateway_resource" "petsResource"{
    rest_api_id = aws_api_gateway_rest_api.Api.id
    parent_id = aws_api_gateway_rest_api.Api.root_resource_id
    path_part = "pets"
}

resource "aws_api_gateway_resource" "petIdResource"{
    rest_api_id = aws_api_gateway_rest_api.Api.id
    parent_id = aws_api_gateway_resource.petsResource.id
    path_part = "{petId}"
}

resource "aws_api_gateway_method" "petsMethodGet" {
    rest_api_id     = aws_api_gateway_rest_api.Api.id
    resource_id     = aws_api_gateway_resource.petsResource.id
    http_method     = "GET"
    authorization   = "NONE"
}

resource "aws_api_gateway_method_response" "petsMethodResponseGet" {
    rest_api_id = aws_api_gateway_rest_api.Api.id
    resource_id = aws_api_gateway_resource.petsResource.id
    http_method = aws_api_gateway_method.petsMethodGet.http_method
    status_code = "200"
}

resource "aws_api_gateway_integration" "petsIntegration" {
    rest_api_id = aws_api_gateway_rest_api.Api.id
    resource_id = aws_api_gateway_resource.petsResource.id
    http_method = aws_api_gateway_method.petsMethodGet.http_method
    type        = "HTTP"
    uri          = "http://petstore-demo-endpoint.execute-api.com/petstore/
    pets"
}
```

```
integration_http_method = "GET"
depends_on              = [aws_api_gateway_method.petsMethodGet]
}

resource "aws_api_gateway_integration_response" "petsIntegrationResponse" {
  rest_api_id = aws_api_gateway_rest_api.Api.id
  resource_id = aws_api_gateway_resource.petsResource.id
  http_method = aws_api_gateway_method.petsMethodGet.http_method
  status_code = aws_api_gateway_method_response.petsMethodResponseGet.status_code
}

resource "aws_api_gateway_method" "petIdMethodGet" {
  rest_api_id   = aws_api_gateway_rest_api.Api.id
  resource_id   = aws_api_gateway_resource.petIdResource.id
  http_method   = "GET"
  authorization = "NONE"
  request_parameters = {"method.request.path.petId" = true}
}

resource "aws_api_gateway_method_response" "petIdMethodResponseGet" {
  rest_api_id = aws_api_gateway_rest_api.Api.id
  resource_id = aws_api_gateway_resource.petIdResource.id
  http_method = aws_api_gateway_method.petIdMethodGet.http_method
  status_code = "200"
}

resource "aws_api_gateway_integration" "petIdIntegration" {
  rest_api_id = aws_api_gateway_rest_api.Api.id
  resource_id = aws_api_gateway_resource.petIdResource.id
  http_method = aws_api_gateway_method.petIdMethodGet.http_method
  type        = "HTTP"
  uri          = "http://petstore-demo-endpoint.execute-api.com/petstore/
pets/{id}"
  integration_http_method = "GET"
  request_parameters = {"integration.request.path.id" = "method.request.path.petId"}
  depends_on      = [aws_api_gateway_method.petIdMethodGet]
}

resource "aws_api_gateway_integration_response" "petIdIntegrationResponse" {
  rest_api_id = aws_api_gateway_rest_api.Api.id
  resource_id = aws_api_gateway_resource.petIdResource.id
  http_method = aws_api_gateway_method.petIdMethodGet.http_method
  status_code = aws_api_gateway_method_response.petIdMethodResponseGet.status_code
}
```

```
}


resource "aws_api_gateway_deployment" "Deployment" {
  rest_api_id = aws_api_gateway_rest_api.Api.id
  depends_on  =
  [aws_api_gateway_integration.petsIntegration,aws_api_gateway_integration.petIdIntegration ]
}

resource "aws_api_gateway_stage" "Stage" {
  stage_name      = "Prod"
  rest_api_id    = aws_api_gateway_rest_api.Api.id
  deployment_id = aws_api_gateway_deployment.Deployment.id
}
```

Tutorial: Create a private REST API

In this tutorial, you create a private REST API. Clients can access the API only from within your Amazon VPC. The API is isolated from the public internet, which is a common security requirement.

This tutorial takes approximately 30 minutes to complete. First, you use an CloudFormation template to create an Amazon VPC, a VPC endpoint, an AWS Lambda function, and launch an Amazon EC2 instance that you'll use to test your API. Next, you use the AWS Management Console to create a private API and attach a resource policy that allows access only from your VPC endpoint. Lastly, you test your API.



To complete this tutorial, you need an AWS account and an AWS Identity and Access Management user with console access. For more information, see [Prerequisites](#).

In this tutorial, you use the AWS Management Console. For an CloudFormation template that creates this API and all related resources, see [template.yaml](#).

Topics

- [Step 1: Create dependencies](#)
- [Step 2: Create a private API](#)
- [Step 3: Create a method and integration](#)
- [Step 4: Attach a resource policy](#)
- [Step 5: Deploy your API](#)
- [Step 6: Verify that your API isn't publicly accessible](#)
- [Step 7: Connect to an instance in your VPC and invoke your API](#)
- [Step 8: Clean up](#)
- [Next steps: Automate with CloudFormation](#)

Step 1: Create dependencies

Download and unzip [this CloudFormation template](#). You use the template to create all of the dependencies for your private API, including an Amazon VPC, a VPC endpoint, and a Lambda function that serves as the backend of your API. You create the private API later.

To create an CloudFormation stack

1. Open the CloudFormation console at <https://console.aws.amazon.com/cloudformation>.
2. Choose **Create stack** and then choose **With new resources (standard)**.
3. For **Specify template**, choose **Upload a template file**.
4. Select the template that you downloaded.
5. Choose **Next**.
6. For **Stack name**, enter **private-api-tutorial** and then choose **Next**.
7. For **Configure stack options**, choose **Next**.
8. For **Capabilities**, acknowledge that CloudFormation can create IAM resources in your account.
9. Choose **Next**, and then choose **Submit**.

CloudFormation provisions the dependencies for your API, which can take a few minutes. When the status of your CloudFormation stack is **CREATE_COMPLETE**, choose **Outputs**. Note your VPC endpoint ID. You need it for later steps in this tutorial.

Step 2: Create a private API

You create a private API to allow only clients within your VPC to access it.

To create a private API

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose **Create API**, and then for **REST API**, choose **Build**.
3. For **API name**, enter **private-api-tutorial**.
4. For **API endpoint type**, select **Private**.
5. For **VPC endpoint IDs**, enter the VPC endpoint ID from the **Outputs** of your CloudFormation stack.
6. For **IP address type**, choose **Dualstack**.
7. Choose **Create API**.

Step 3: Create a method and integration

You create a GET method and Lambda integration to handle GET requests to your API. When a client invokes your API, API Gateway sends the request to the Lambda function that you created in Step 1, and then returns a response to the client.

To create a method and integration

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose your API.
3. Choose **Create method**.
4. For **Method type** select **GET**.
5. For **Integration type**, select **Lambda function**.
6. Turn on **Lambda proxy integration**. With a Lambda proxy integration, API Gateway sends an event to Lambda with a defined structure, and transforms the response from your Lambda function to an HTTP response.
7. For **Lambda function**, choose the function that you created with the CloudFormation template in Step 1. The function's name begins with **private-api-tutorial**.
8. Choose **Create method**.

Step 4: Attach a resource policy

You attach a [resource policy](#) to your API that allows clients to invoke your API only through your VPC endpoint. To further restrict access to your API, you can also configure a [VPC endpoint policy](#) for your VPC endpoint, but that's not necessary for this tutorial.

To attach a resource policy

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose your API.
3. Choose **Resource policy**, and then choose **Create policy**.
4. Enter the following policy. Replace *vpceID* with your VPC endpoint ID from the **Outputs** of your CloudFormation stack.

JSON

```
{  
    "Version": "2012-10-17",  
    "Statement": [  
        {  
            "Effect": "Deny",  
            "Principal": "*",  
            "Action": "execute-api:Invoke",  
            "Resource": "execute-api:/*",  
            "Condition": {  
                "StringNotEquals": {  
                    "aws:sourceVpce": "vpce-abcd1234"  
                }  
            }  
        },  
        {  
            "Effect": "Allow",  
            "Principal": "*",  
            "Action": "execute-api:Invoke",  
            "Resource": "execute-api:/*"  
        }  
    ]  
}
```

5. Choose **Save changes**.

Step 5: Deploy your API

Next, you deploy your API to make it available to clients in your Amazon VPC.

To deploy an API

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose your API.
3. Choose **Deploy API**.
4. For **Stage**, select **New stage**.
5. For **Stage name**, enter **test**.
6. (Optional) For **Description**, enter a description.
7. Choose **Deploy**.

Now you're ready to test your API.

Step 6: Verify that your API isn't publicly accessible

Use curl to verify that you can't invoke your API from outside of your Amazon VPC.

To test your API

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose your API.
3. In the main navigation pane, choose **Stages**, and then choose the **test** stage.
4. Under **Stage details**, choose the copy icon to copy your API's invoke URL. The URL looks like `https://abcdef123.execute-api.us-west-2.amazonaws.com/test`. The VPC endpoint that you created in Step 1 has private DNS enabled, so you can use the provided URL to invoke your API.
5. Use curl to attempt to invoke your API from outside of your VPC.

```
curl https://abcdef123.execute-api.us-west-2.amazonaws.com/test
```

Curl indicates that your API's endpoint can't be resolved. If you get a different response, go back to Step 2, and make sure that you choose **Private** for your API's endpoint type.

```
curl: (6) Could not resolve host: abcdef123.execute-api.us-west-2.amazonaws.com/
test
```

Next, you connect to an Amazon EC2 instance in your VPC to invoke your API.

Step 7: Connect to an instance in your VPC and invoke your API

Next, you test your API from within your Amazon VPC. To access your private API, you connect to an Amazon EC2 instance in your VPC and then use curl to invoke your API. You use Systems Manager Session Manager to connect to your instance in the browser.

To test your API

1. Open the Amazon EC2 console at <https://console.aws.amazon.com/ec2/>.
2. Choose **Instances**.
3. Choose the instance named **private-api-tutorial** that you created with the CloudFormation template in Step 1.
4. Choose **Connect** and then choose **Session Manager**.
5. Choose **Connect** to launch a browser-based session to your instance.
6. In your Session Manager session, use curl to invoke your API. You can invoke your API because you're using an instance in your Amazon VPC.

```
curl https://abcdef123.execute-api.us-west-2.amazonaws.com/test
```

Verify that you get the response Hello from Lambda!.

The screenshot shows the AWS Session Manager interface. At the top, there are two input fields: "Session ID: user-XXXXXX" and "Instance ID: i-XXXXXX". To the right of the instance ID field is an orange "Terminate" button. Below these fields is a terminal window with the following content:

```
sh-4.2$ curl https://abcdef123.execute-api.us-west-2.amazonaws.com/prod
"Hello from Lambda!"sh-4.2$
```

The terminal window has a black background and white text. The URL in the curl command is partially redacted with "abcdef123".

You successfully created an API that's accessible only from within your Amazon VPC and then verified that it works.

Step 8: Clean up

To prevent unnecessary costs, delete the resources that you created as part of this tutorial. The following steps delete your REST API and your CloudFormation stack.

To delete a REST API

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. On the **APIs** page, select an API. Choose **API actions**, choose **Delete API**, and then confirm your choice.

To delete an CloudFormation stack

1. Open the CloudFormation console at <https://console.aws.amazon.com/cloudformation>.
2. Select your CloudFormation stack.
3. Choose **Delete** and then confirm your choice.

Next steps: Automate with CloudFormation

You can automate the creation and cleanup of all AWS resources involved in this tutorial. For a full example CloudFormation template, see [template.yaml](#).

Amazon API Gateway HTTP API tutorials

The following tutorials provide hands-on exercises to help you learn about API Gateway HTTP APIs.

Topics

- [Tutorial: Create a CRUD HTTP API with Lambda and DynamoDB](#)
- [Tutorial: Create an HTTP API with a private integration to an Amazon ECS service](#)


Tutorial: Create a CRUD HTTP API with Lambda and DynamoDB

In this tutorial, you create a serverless API that creates, reads, updates, and deletes items from a DynamoDB table. DynamoDB is a fully managed NoSQL database service that provides fast and

predictable performance with seamless scalability. This tutorial takes approximately 30 minutes to complete, and you can do it within the [AWS Free Tier](#).

First, you create a [DynamoDB](#) table using the DynamoDB console. Then you create a [Lambda](#) function using the AWS Lambda console. Next, you create an HTTP API using the API Gateway console. Lastly, you test your API.

When you invoke your HTTP API, API Gateway routes the request to your Lambda function. The Lambda function interacts with DynamoDB, and returns a response to API Gateway. API Gateway then returns a response to you.



To complete this exercise, you need an AWS account and an AWS Identity and Access Management user with console access. For more information, see [Prerequisites](#).

In this tutorial, you use the AWS Management Console. For an AWS SAM template that creates this API and all related resources, see [template.yaml](#).

Topics

- [Step 1: Create a DynamoDB table](#)
- [Step 2: Create a Lambda function](#)
- [Step 3: Create an HTTP API](#)
- [Step 4: Create routes](#)
- [Step 5: Create an integration](#)
- [Step 6: Attach your integration to routes](#)
- [Step 7: Test your API](#)
- [Step 8: Clean up](#)
- [Next steps: Automate with AWS SAM or CloudFormation](#)

Step 1: Create a DynamoDB table

You use a [DynamoDB](#) table to store data for your API.

Each item has a unique ID, which we use as the [partition key](#) for the table.

To create a DynamoDB table

1. Open the DynamoDB console at <https://console.aws.amazon.com/dynamodb/>.
2. Choose **Create table**.
3. For **Table name**, enter **http-crud-tutorial-items**.
4. For **Partition key**, enter **id**.
5. Choose **Create table**.

Step 2: Create a Lambda function

You create a [Lambda](#) function for the backend of your API. This Lambda function creates, reads, updates, and deletes items from DynamoDB. The function uses [events from API Gateway](#) to determine how to interact with DynamoDB. For simplicity this tutorial uses a single Lambda function. As a best practice, you should create separate functions for each route. For more information, see [The Lambda monolith](#).

To create a Lambda function

1. Sign in to the Lambda console at <https://console.aws.amazon.com/lambda>.
2. Choose **Create function**.
3. For **Function name**, enter **http-crud-tutorial-function**.
4. For **Runtime**, choose either the latest supported **Node.js** or **Python** runtime.
5. Under **Permissions** choose **Change default execution role**.
6. Select **Create a new role from AWS policy templates**.
7. For **Role name**, enter **http-crud-tutorial-role**.
8. For **Policy templates**, choose **Simple microservice permissions**. This policy grants the Lambda function permission to interact with DynamoDB.

Note

This tutorial uses a managed policy for simplicity. As a best practice, you should create your own IAM policy to grant the minimum permissions required.

9. Choose **Create function**.

10. Open the Lambda function in the console's code editor, and replace its contents with the following code. Choose **Deploy** to update your function.

Node.js

```
import { DynamoDBClient } from "@aws-sdk/client-dynamodb";
import {
  DynamoDBDocumentClient,
  ScanCommand,
  PutCommand,
  GetCommand,
  DeleteCommand,
} from "@aws-sdk/lib-dynamodb";

const client = new DynamoDBClient({});

const dynamo = DynamoDBDocumentClient.from(client);

const tableName = "http-crud-tutorial-items";

export const handler = async (event, context) => {
  let body;
  let statusCode = 200;
  const headers = {
    "Content-Type": "application/json",
  };

  try {
    switch (event.routeKey) {
      case "DELETE /items/{id}":
        await dynamo.send(
          new DeleteCommand({
            TableName: tableName,
            Key: {
              id: event.pathParameters.id,
            },
          })
        );
        body = `Deleted item ${event.pathParameters.id}`;
        break;
      case "GET /items/{id}":
        body = await dynamo.send(
          new GetCommand({
```

```
        TableName: tableName,
        Key: {
            id: event.pathParameters.id,
        },
    })
);
body = body.Item;
break;
case "GET /items":
body = await dynamo.send(
    new ScanCommand({ TableName: tableName })
);
body = body.Items;
break;
case "PUT /items":
let requestJSON = JSON.parse(event.body);
await dynamo.send(
    new PutCommand({
        TableName: tableName,
        Item: {
            id: requestJSON.id,
            price: requestJSON.price,
            name: requestJSON.name,
        },
    })
);
body = `Put item ${requestJSON.id}`;
break;
default:
    throw new Error(`Unsupported route: "${event.routeKey}"`);
}
} catch (err) {
    statusCode = 400;
    body = err.message;
} finally {
    body = JSON.stringify(body);
}

return {
    statusCode,
    body,
    headers,
};
```

```
};
```

Python

```
import json
import boto3
from decimal import Decimal

client = boto3.client('dynamodb')
dynamodb = boto3.resource("dynamodb")
table = dynamodb.Table('http-crud-tutorial-items')
tableName = 'http-crud-tutorial-items'

def lambda_handler(event, context):
    print(event)
    body = {}
    statusCode = 200
    headers = {
        "Content-Type": "application/json"
    }

    try:
        if event['routeKey'] == "DELETE /items/{id}":
            table.delete_item(
                Key={'id': event['pathParameters']['id']})
            body = 'Deleted item ' + event['pathParameters']['id']
        elif event['routeKey'] == "GET /items/{id}":
            body = table.get_item(
                Key={'id': event['pathParameters']['id']})
            body = body["Item"]
            responseBody = [
                {'price': float(body['price']), 'id': body['id'], 'name':
body['name']}]
            body = responseBody
        elif event['routeKey'] == "GET /items":
            body = table.scan()
            body = body["Items"]
            print("ITEMS----")
            print(body)
            responseBody = []
            for items in body:
                responseItems = [
```

```
        {'price': float(items['price']), 'id': items['id'], 'name':  
         items['name']}]  
            responseBody.append(responseItems)  
        body = responseBody  
    elif event['routeKey'] == "PUT /items":  
        requestJSON = json.loads(event['body'])  
        table.put_item(  
            Item={  
                'id': requestJSON['id'],  
                'price': Decimal(str(requestJSON['price'])),  
                'name': requestJSON['name']  
            })  
        body = 'Put item ' + requestJSON['id']  
    except KeyError:  
        statusCode = 400  
        body = 'Unsupported route: ' + event['routeKey']  
    body = json.dumps(body)  
    res = {  
        "statusCode": statusCode,  
        "headers": {  
            "Content-Type": "application/json"  
        },  
        "body": body  
    }  
    return res
```

Step 3: Create an HTTP API

The HTTP API provides an HTTP endpoint for your Lambda function. In this step, you create an empty API. In the following steps, you configure routes and integrations to connect your API and your Lambda function.

To create an HTTP API

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose **Create API**, and then for **HTTP API**, choose **Build**.
3. For **API name**, enter **http-crud-tutorial-api**.
4. For **IP address type**, select **IPv4**.
5. Choose **Next**.

6. For **Configure routes**, choose **Next** to skip route creation. You create routes later.
7. Review the stage that API Gateway creates for you, and then choose **Next**.
8. Choose **Create**.

Step 4: Create routes

Routes are a way to send incoming API requests to backend resources. Routes consist of two parts: an HTTP method and a resource path, for example, GET /items. For this example API, we create four routes:

- GET /items/{id}
- GET /items
- PUT /items
- DELETE /items/{id}

To create routes

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose your API.
3. Choose **Routes**.
4. Choose **Create**.
5. For **Method**, choose **GET**.
6. For the path, enter **/items/{id}**. The {id} at the end of the path is a path parameter that API Gateway retrieves from the request path when a client makes a request.
7. Choose **Create**.
8. Repeat steps 4-7 for GET /items, DELETE /items/{id}, and PUT /items.

The screenshot shows the AWS API Gateway console. In the top navigation bar, there are links for 'API Gateway' and 'APIs', followed by 'Routes - http-crud-tutorial-api (acbd1234)'. On the far right, there are buttons for 'Stage: -' and 'Deploy'. Below the navigation, the word 'Routes' is displayed.

The main area is divided into two sections. The left section, titled 'Routes for http-crud-tutorial-api', contains a 'Create' button and a search bar. It lists two resource paths: '/items' and '/{id}'. Under '/items', there are three methods: 'GET', 'PUT' (which is highlighted with a blue background), and 'DELETE'. Under '/{id}', there are 'GET' and 'DELETE' methods. The right section, titled 'Route details', shows the route configuration for 'PUT /items (ID: bdlib4q)'. It includes fields for 'ARN' (arn:aws:apigateway:us-west-1::apis/abcd1234/routes/aaa111), 'Authorization' (with a note that no authorizer is attached and a 'Attach authorization' button), and 'Integration' (with a note that no integration is attached and a 'Attach integration' button). There are also 'Delete' and 'Edit' buttons at the top right of this section.

Step 5: Create an integration

You create an integration to connect a route to backend resources. For this example API, you create one Lambda integration that you use for all routes.

To create an integration

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose your API.
3. Choose **Integrations**.
4. Choose **Manage integrations** and then choose **Create**.
5. Skip **Attach this integration to a route**. You complete that in a later step.
6. For **Integration type**, choose **Lambda function**.
7. For **Lambda function**, enter **http-crud-tutorial-function**.
8. Choose **Create**.

Step 6: Attach your integration to routes

For this example API, you use the same Lambda integration for all routes. After you attach the integration to all of the API's routes, your Lambda function is invoked when a client calls any of your routes.

To attach integrations to routes

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose your API.
3. Choose **Integrations**.
4. Choose a route.
5. Under **Choose an existing integration**, choose **http-crud-tutorial-function**.
6. Choose **Attach integration**.
7. Repeat steps 4-6 for all routes.

All routes show that an AWS Lambda integration is attached.

The screenshot shows the 'Integrations' page for the 'http-crud-tutorial-api (abdc1234)' API. On the left, under 'Routes for http-crud-tutorial-api', there's a search bar and a list of routes: '/items' (with sub-routes GET, PUT, and DELETE all mapped to 'AWS Lambda') and '/{id}' (with sub-routes GET and DELETE both mapped to 'AWS Lambda'). On the right, the 'Integration details for route' section shows a PUT integration to '/items (aaa111)' using a 'Lambda function' named 'http-crud-tutorial-function (us-west-1)'. The 'Integration ID' is 'bbb222'. It includes sections for 'Description' (empty), 'Payload format version' (set to 2.0), 'Invoke permissions' (with a note about Lambda resource policy), 'Example policy statement' (link), 'Timeout' (set to 30000), and 'Request parameter mapping' (not configured). There are also tabs for 'Attach integrations to routes' and 'Manage integrations'.

Now that you have an HTTP API with routes and integrations, you can test your API.

Step 7: Test your API

To make sure that your API is working, you use [curl](#).

To get the URL to invoke your API

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose your API.
3. Note your API's invoke URL. It appears under **Invoke URL** on the **Details** page.

The screenshot shows the AWS API Gateway console. At the top, there's a navigation bar with 'API Gateway' > 'APIs' > 'http-crud-tutorial-api (abcd1234)'. Below this, the API name 'http-crud-tutorial-api' is displayed with a 'Stage: -' dropdown and a 'Deploy' button. The main section is titled 'API details' with an 'Edit' button. It contains fields for 'API ID' (abcd1234), 'Protocol' (HTTP), 'Created' (2024-05-02), 'Description' (My HTTP CRUD tutorial API), 'Default endpoint' (Enabled, https://abcd1234.execute-api.us-west-1.amazonaws.com), and 'ARN' (arn:aws:apigateway:us-west-1::apis/abcd1234). Below this is a table titled 'Stages for http-crud-tutorial-api (1)'. It has columns for 'Stage name', 'Invoke URL', 'Attached deployment', 'Auto deploy', and 'Last updated'. The single row shows '\$default' with 'https://abcd1234.execute-api.us-west-1.amazonaws.com' highlighted with a red border.

4. Copy your API's invoke URL.

The full URL looks like `https://abcdef123.execute-api.us-west-2.amazonaws.com`.

To create or update an item

- Use the following command to create or update an item. The command includes a request body with the item's ID, price, and name.

```
curl -X "PUT" -H "Content-Type: application/json" -d "{\"id\": \"123\", \"price\": 12345, \"name\": \"myitem\"}" https://abcdef123.execute-api.us-west-2.amazonaws.com/items
```

To get all items

- Use the following command to list all items.

```
curl https://abcdef123.execute-api.us-west-2.amazonaws.com/items
```

To get an item

- Use the following command to get an item by its ID.

```
curl https://abcdef123.execute-api.us-west-2.amazonaws.com/items/123
```

To delete an item

1. Use the following command to delete an item.

```
curl -X "DELETE" https://abcdef123.execute-api.us-west-2.amazonaws.com/items/123
```

2. Get all items to verify that the item was deleted.

```
curl https://abcdef123.execute-api.us-west-2.amazonaws.com/items
```

Step 8: Clean up

To prevent unnecessary costs, delete the resources that you created as part of this getting started exercise. The following steps delete your HTTP API, your Lambda function, and associated resources.

To delete a DynamoDB table

1. Open the DynamoDB console at <https://console.aws.amazon.com/dynamodb/>.
2. Select your table.
3. Choose **Delete table**.
4. Confirm your choice, and choose **Delete**.

To delete an HTTP API

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. On the **APIs** page, select an API. Choose **Actions**, and then choose **Delete**.
3. Choose **Delete**.

To delete a Lambda function

1. Sign in to the Lambda console at <https://console.aws.amazon.com/lambda>.
2. On the **Functions** page, select a function. Choose **Actions**, and then choose **Delete**.

3. Choose **Delete**.

To delete a Lambda function's log group

1. In the Amazon CloudWatch console, open the [Log groups page](#).
2. On the **Log groups** page, select the function's log group (/aws/lambda/http-crud-tutorial-function). Choose **Actions**, and then choose **Delete log group**.
3. Choose **Delete**.

To delete a Lambda function's execution role

1. In the AWS Identity and Access Management console, open the [Roles page](#).
2. Select the function's role, for example, http-crud-tutorial-role.
3. Choose **Delete role**.
4. Choose **Yes, delete**.

Next steps: Automate with AWS SAM or CloudFormation

You can automate the creation and cleanup of AWS resources by using CloudFormation or AWS SAM. For an example AWS SAM template for this tutorial, see [template.yaml](#).


For example CloudFormation templates, see [example CloudFormation templates](#).

Tutorial: Create an HTTP API with a private integration to an Amazon ECS service

In this tutorial, you create a serverless API that connects to an Amazon ECS service that runs in an Amazon VPC. Clients outside of your Amazon VPC can use the API to access your Amazon ECS service.

This tutorial takes approximately an hour to complete. First, you use a CloudFormation template to create an Amazon VPC and Amazon ECS service. Then you use the API Gateway console to create a VPC link. The VPC link allows API Gateway to access the Amazon ECS service that runs in your Amazon VPC. Next, you create an HTTP API that uses the VPC link to connect to your Amazon ECS service. Lastly, you test your API.

When you invoke your HTTP API, API Gateway routes the request to your Amazon ECS service through your VPC link, and then returns the response from the service.



To complete this tutorial, you need an AWS account and an AWS Identity and Access Management user with console access. For more information, see [Prerequisites](#).

In this tutorial, you use the AWS Management Console. For an CloudFormation template that creates this API and all related resources, see [template.yaml](#).

Topics

- [Step 1: Create an Amazon ECS service](#)
- [Step 2: Create a VPC link](#)
- [Step 3: Create an HTTP API](#)
- [Step 4: Create a route](#)
- [Step 5: Create an integration](#)
- [Step 6: Test your API](#)
- [Step 7: Clean up](#)
- [Next steps: Automate with CloudFormation](#)

Step 1: Create an Amazon ECS service

Amazon ECS is a container management service that makes it easy to run, stop, and manage Docker containers on a cluster. In this tutorial, you run your cluster on a serverless infrastructure that's managed by Amazon ECS.

Download and unzip [this CloudFormation template](#), which creates all of the dependencies for the service, including an Amazon VPC. You use the template to create an Amazon ECS service that uses an Application Load Balancer.

To create an CloudFormation stack

1. Open the CloudFormation console at <https://console.aws.amazon.com/cloudformation>.
2. Choose **Create stack** and then choose **With new resources (standard)**.
3. For **Specify template**, choose **Upload a template file**.
4. Select the template that you downloaded.
5. Choose **Next**.
6. For **Stack name**, enter **http-api-private-integrations-tutorial** and then choose **Next**.
7. For **Configure stack options**, choose **Next**.
8. For **Capabilities**, acknowledge that CloudFormation can create IAM resources in your account.
9. Choose **Next**, and then choose **Submit**.

CloudFormation provisions the ECS service, which can take a few minutes. When the status of your CloudFormation stack is **CREATE_COMPLETE**, you're ready to move on to the next step.

Step 2: Create a VPC link

A VPC link allows API Gateway to access private resources in an Amazon VPC. You use a VPC link to allow clients to access your Amazon ECS service through your HTTP API.

To create a VPC link

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. On the main navigation pane, choose **VPC links** and then choose **Create**.

You might need to choose the menu icon to open the main navigation pane.
3. For **Choose a VPC link version**, select **VPC link for HTTP APIs**.
4. For **Name**, enter **private-integrations-tutorial**.
5. For **VPC**, choose the VPC that you created in step 1. The name should start with **PrivateIntegrationsStack**.

6. For **Subnets**, select the two private subnets in your VPC. Their names end with `PrivateSubnet`.
7. For **Security groups**, select the Group ID that starts with `private-integrations-tutorial` and has the description of `PrivateIntegrationsStack/PrivateIntegrationsTutorialService/Service/SecurityGroup`.
8. Choose **Create**.

After you create your VPC link, API Gateway provisions Elastic Network Interfaces to access your VPC. The process can take a few minutes. In the meantime, you can create your API.

Step 3: Create an HTTP API

The HTTP API provides an HTTP endpoint for your Amazon ECS service. In this step, you create an empty API. In Steps 4 and 5, you configure a route and an integration to connect your API and your Amazon ECS service.

To create an HTTP API

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose **Create API**, and then for **HTTP API**, choose **Build**.
3. For **API name**, enter `http-private-integrations-tutorial`.
4. For **IP address type**, select **IPv4**.
5. Choose **Next**.
6. For **Configure routes**, choose **Next** to skip route creation. You create routes later.
7. Review the stage that API Gateway creates for you. API Gateway creates a `$default` stage with automatic deployments enabled, which is the best choice for this tutorial. Choose **Next**.
8. Choose **Create**.

Step 4: Create a route

Routes are a way to send incoming API requests to backend resources. Routes consist of two parts: an HTTP method and a resource path, for example, `GET /items`. For this example API, we create one route.

To create a route

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose your API.
3. Choose **Routes**.
4. Choose **Create**.
5. For **Method**, choose **ANY**.
6. For the path, enter **/{{proxy+}}**. The {{proxy+}} at the end of the path is a greedy path variable. API Gateway sends all requests to your API to this route.
7. Choose **Create**.

Step 5: Create an integration

You create an integration to connect a route to backend resources.

To create an integration

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose your API.
3. Choose **Integrations**.
4. Choose **Manage integrations** and then choose **Create**.
5. For **Attach this integration to a route**, select the **ANY /{{proxy+}}** route that you created earlier.
6. For **Integration type**, choose **Private resource**.
7. For **Integration details**, choose **Select manually**.
8. For **Target service**, choose **ALB/NLB**.
9. For **Load balancer**, choose the load balancer that you created with the CloudFormation template in Step 1. Its name should start with **http-Priva**.
10. For **Listener**, choose **HTTP 80**.
11. For **VPC link**, choose the VPC link that you created in Step 2. Its name should be **private-integrations-tutorial**.
12. Choose **Create**.

To verify that your route and integration are set up correctly, select **Attach integrations to routes**. The console shows that you have an ANY /{proxy+} route with an integration to a VPC Load Balancer.

Integrations

Stage: - ▾

Deploy

The screenshot shows the AWS API Gateway Integrations page. At the top, there are two tabs: "Attach integrations to routes" (which is selected) and "Manage integrations". Below the tabs, there's a search bar and a list of routes under the heading "Routes for private-integrations-tutorial". One route is listed: "ANY /{proxy+}" (abc123), which is integrated with a "VPC Load Balancer". On the right side, there's a detailed view for this route. It shows the "Integration details for route" section with options to "Detach integration" or "Manage integration". The route is associated with a "Load balancer listener" (ANY HTTP:80 - http-p-Priva-ABCD1234abc) and has an "Integration ID" (aaa111). There are fields for "Description" (empty), "VPC link" (efg456), and "Timeout" (30000 milliseconds).

Now you're ready to test your API.

Step 6: Test your API

Next, you test your API to make sure that it's working. For simplicity, use a web browser to invoke your API.

To test your API

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose your API.
3. Note your API's invoke URL.

my-http-api

Stage: -

API details

API ID
abcd1234

Protocol
HTTP

Created
2023-10-30

Description
My first HTTP API

Default endpoint
 Enabled
<https://abcd1234.execute-api.us-west-1.amazonaws.com>

ARN
 arn:aws:apigateway:us-west-1::apis/abcd1234

Stages for my-http-api (1)

Find resources

Stage name	Invoke URL	Attached deployment	Auto deploy	Last updated
\$default	https://abcd1234.execute-api.us-west-1.amazonaws.com	aaa111	enabled	2023-10-30

4. In a web browser, go to your API's invoke URL.

The full URL should look like <https://abcdef123.execute-api.us-east-2.amazonaws.com>.

Your browser sends a GET request to the API.

5. Verify that your API's response is a welcome message that tells you that your app is running on Amazon ECS.

If you see the welcome message, you successfully created an Amazon ECS service that runs in an Amazon VPC, and you used an API Gateway HTTP API with a VPC link to access the Amazon ECS service.

Step 7: Clean up

To prevent unnecessary costs, delete the resources that you created as part of this tutorial. The following steps delete your VPC link, CloudFormation stack, and HTTP API.

To delete an HTTP API

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. On the APIs page, select an API. Choose **Actions**, choose **Delete**, and then confirm your choice.

To delete a VPC link

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose **VPC link**.
3. Select your VPC link, choose **Delete**, and then confirm your choice.

To delete an CloudFormation stack

1. Open the CloudFormation console at <https://console.aws.amazon.com/cloudformation>.
2. Select your CloudFormation stack.
3. Choose **Delete** and then confirm your choice.

Next steps: Automate with CloudFormation

You can automate the creation and cleanup of all AWS resources involved in this tutorial. For a full example CloudFormation template, see [template.yaml](#).

Amazon API Gateway WebSocket API tutorials

The following tutorials provide a hands-on exercise to help you learn about API Gateway WebSocket APIs.

Topics


- [Tutorial: Create a WebSocket chat app with a WebSocket API, Lambda and DynamoDB](#)
- [Tutorial: Create a WebSocket API with an AWS integration](#)

Tutorial: Create a WebSocket chat app with a WebSocket API, Lambda and DynamoDB

In this tutorial, you'll create a serverless chat application with a WebSocket API. With a WebSocket API, you can support two-way communication between clients. Clients can receive messages without having to poll for updates.

This tutorial takes approximately 30 minutes to complete. First, you'll use an CloudFormation template to create Lambda functions that will handle API requests, as well as a DynamoDB table that stores your client IDs. Then, you'll use the API Gateway console to create a WebSocket API that

integrates with your Lambda functions. Lastly, you'll test your API to verify that messages are sent and received.



To complete this tutorial, you need an AWS account and an AWS Identity and Access Management user with console access. For more information, see [Prerequisites](#).

You also need wscat to connect to your API. For more information, see [the section called "Use wscat to connect to a WebSocket API and send messages to it"](#).

Topics

- [Step 1: Create Lambda functions and a DynamoDB table](#)
- [Step 2: Create a WebSocket API](#)
- [Step 3: Test your API](#)
- [Step 4: Clean up](#)
- [Next steps: Automate with CloudFormation](#)

Step 1: Create Lambda functions and a DynamoDB table

Download and unzip [the app creation template for CloudFormation](#). You'll use this template to create a Amazon DynamoDB table to store your app's client IDs. Each connected client has a unique

ID which we will use as the table's partition key. This template also creates Lambda functions that update your client connections in DynamoDB and handle sending messages to connected clients.

To create an CloudFormation stack

1. Open the CloudFormation console at <https://console.aws.amazon.com/cloudformation>.
2. Choose **Create stack** and then choose **With new resources (standard)**.
3. For **Specify template**, choose **Upload a template file**.
4. Select the template that you downloaded.
5. Choose **Next**.
6. For **Stack name**, enter **websocket-api-chat-app-tutorial** and then choose **Next**.
7. For **Configure stack options**, choose **Next**.
8. For **Capabilities**, acknowledge that CloudFormation can create IAM resources in your account.
9. Choose **Next**, and then choose **Submit**.

CloudFormation provisions the resources specified in the template. It can take a few minutes to finish provisioning your resources. When the status of your CloudFormation stack is **CREATE_COMPLETE**, you're ready to move on to the next step.

Step 2: Create a WebSocket API

You'll create a WebSocket API to handle client connections and route requests to the Lambda functions that you created in Step 1.

To create a WebSocket API

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose **Create API**. Then for **WebSocket API**, choose **Build**.
3. For **API name**, enter **websocket-chat-app-tutorial**.
4. For **IP address type**, select **IPv4**.
5. For **Route selection expression**, enter **request.body.action**. The route selection expression determines the route that API Gateway invokes when a client sends a message.
6. Choose **Next**.
7. For **Predefined routes**, choose **Add \$connect**, **Add \$disconnect**, and **Add \$default**. The **\$connect** and **\$disconnect** routes are special routes that API Gateway invokes automatically

- when a client connects to or disconnects from an API. API Gateway invokes the `$default` route when no other routes match a request.
8. For **Custom routes**, choose **Add custom route**. For **Route key**, enter `sendmessage`. This custom route handles messages that are sent to connected clients.
 9. Choose **Next**.
 10. Under **Attach integrations**, for each route and **Integration type**, choose Lambda.

For **Lambda**, choose the corresponding Lambda function that you created with CloudFormation in Step 1. Each function's name matches a route. For example, for the `$connect` route, choose the function named **websocket-chat-app-tutorial-ConnectHandler**.

11. Review the stage that API Gateway creates for you. By default, API Gateway creates a stage name `production` and automatically deploys your API to that stage. Choose **Next**.
12. Choose **Create and deploy**.

Step 3: Test your API

Next, you'll test your API to make sure that it works correctly. Use the `wscat` command to connect to the API.

To get the invoke URL for your API

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose your API.
3. Choose **Stages**, and then choose **production**.
4. Note your API's **WebSocket URL**. The URL should look like `wss://abcdef123.execute-api.us-east-2.amazonaws.com/production`.

To connect to your API

1. Use the following command to connect to your API. When you connect to your API, API Gateway invokes the `$connect` route. When this route is invoked, it calls a Lambda function that stores your connection ID in DynamoDB.

```
wscat -c wss://abcdef123.execute-api.us-west-2.amazonaws.com/production
```

Connected (press CTRL+C to quit)

2. Open a new terminal and run the **wscat** command again with the following parameters.

```
wscat -c wss://abcdef123.execute-api.us-west-2.amazonaws.com/production
```

Connected (press CTRL+C to quit)

This gives you two connected clients that can exchange messages.

To send a message

- API Gateway determines which route to invoke based on your API's route selection expression. Your API's route selection expression is `$request.body.action`. As a result, API Gateway invokes the `sendmessage` route when you send the following message:

```
{"action": "sendmessage", "message": "hello, everyone!"}
```

The Lambda function associated with the invoked route collects the client IDs from DynamoDB. Then, the function calls the API Gateway Management API and sends the message to those clients. All connected clients receive the following message:

```
< hello, everyone!
```

To invoke your API's `$default` route

- API Gateway invokes your API's default route when a client sends a message that doesn't match your defined routes. The Lambda function associated with the `$default` route uses the API Gateway Management API to send the client information about their connection.

```
test
```

Use the `sendmessage` route to send a message. Your info:

```
{"ConnectedAt": "2022-01-25T18:50:04.673Z", "Identity":  
 {"SourceIp": "192.0.2.1", "UserAgent": null}, "LastActiveAt": "2022-01-25T18:50:07.642Z", "connec
```

To disconnect from your API

- Press **CTRL+C** to disconnect from your API. When a client disconnects from your API, API Gateway invokes your API's \$disconnect route. The Lambda integration for your API's \$disconnect route removes the connection ID from DynamoDB.

Step 4: Clean up

To prevent unnecessary costs, delete the resources that you created as part of this tutorial. The following steps delete your CloudFormation stack and WebSocket API.

To delete a WebSocket API

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. On the APIs page, select your websocket-chat-app-tutorial API. Choose **Actions**, choose **Delete**, and then confirm your choice.

To delete an CloudFormation stack

1. Open the CloudFormation console at <https://console.aws.amazon.com/cloudformation>.
2. Select your CloudFormation stack.
3. Choose **Delete** and then confirm your choice.


Next steps: Automate with CloudFormation

You can automate the creation and cleanup of all of the AWS resources involved in this tutorial. For an CloudFormation template that creates this API and all related resources, see [ws-chat-app.yaml](#).

Tutorial: Create a WebSocket API with an AWS integration

In this tutorial, you create a serverless broadcast application with a WebSocket API. Clients can receive messages without having to poll for updates.

This tutorial shows how to broadcast messages to connected clients and includes an example of a Lambda authorizer, a mock integration, and a non-proxy integration to Step Functions.



After you create your resources using a CloudFormation template, you'll use the API Gateway console to create a WebSocket API that integrates with your AWS resources. You'll attach a Lambda authorizer to your API and create an AWS service integration with Step Functions to start a state machine execution. The Step Functions state machine will invoke a Lambda function that sends a message to all connected clients.

After you build your API, you'll test your connection to your API and verify that messages are sent and received. This tutorial takes approximately 45 minutes to complete.

Topics

- [Prerequisites](#)
- [Step 1: Create resources](#)
- [Step 2: Create a WebSocket API](#)
- [Step 3: Create a Lambda authorizer](#)
- [Step 4: Create a mock two-way integration](#)
- [Step 5: Create a non-proxy integration with Step Functions](#)
- [Step 6: Test your API](#)
- [Step 7: Clean up](#)
- [Next steps](#)

Prerequisites

You need the following prerequisites:

- An AWS account and an AWS Identity and Access Management user with console access. For more information, see [Prerequisites](#).
- wscat to connect to your API. For more information, see [the section called “Use wscat to connect to a WebSocket API and send messages to it”](#).

We recommend that you complete the WebSocket chat app tutorial before you start this tutorial. To complete the WebSocket chat app tutorial, see [the section called “Tutorial: Create a WebSocket chat app”](#).

Step 1: Create resources

Download and unzip [the app creation template for CloudFormation](#). You'll use this template to create the following:

- Lambda functions that handle API requests and authorize access to your API.
- A DynamoDB table to store client IDs and the principal user identification returned by the Lambda authorizer.
- A Step Functions state machine to send messages to connected clients.

To create an CloudFormation stack

1. Open the CloudFormation console at <https://console.aws.amazon.com/cloudformation>.
2. Choose **Create stack** and then choose **With new resources (standard)**.
3. For **Specify template**, choose **Upload a template file**.
4. Select the template that you downloaded.
5. Choose **Next**.
6. For **Stack name**, enter **websocket-step-functions-tutorial** and then choose **Next**.
7. For **Configure stack options**, choose **Next**.
8. For **Capabilities**, acknowledge that CloudFormation can create IAM resources in your account.
9. Choose **Next**, and then choose **Submit**.

CloudFormation provisions the resources specified in the template. It can take a few minutes to finish provisioning your resources. Choose the **Outputs** tab to see your created resources and their ARNs. When the status of your CloudFormation stack is **CREATE_COMPLETE**, you're ready to move on to the next step.

Step 2: Create a WebSocket API

You'll create a WebSocket API to handle client connections and route requests to the resources that you created in Step 1.

To create a WebSocket API

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose **Create API**. Then for **WebSocket API**, choose **Build**.
3. For **API name**, enter **websocket-step-functions-tutorial**.
4. For **IP address type**, select **IPv4**.
5. For **Route selection expression**, enter **request.body.action**.

The route selection expression determines the route that API Gateway invokes when a client sends a message.

6. Choose **Next**.
7. For **Predefined routes**, choose **Add \$connect**, **Add \$disconnect**, **Add \$default**.

The **\$connect** and **\$disconnect** routes are special routes that API Gateway invokes automatically when a client connects to or disconnects from an API. API Gateway invokes the **\$default** route when no other routes match a request. You will create a custom route to connect to Step Functions after you create your API.

8. Choose **Next**.
9. For **Integration for \$connect**, do the following:
 - a. For **Integration type**, choose **Lambda**.
 - b. For **Lambda function**, choose the corresponding **\$connect** Lambda function that you created with CloudFormation in Step 1. The Lambda function name should start with **websocket-step**.
10. For **Integration for \$disconnect**, do the following:
 - a. For **Integration type**, choose **Lambda**.

- b. For **Lambda function**, choose the corresponding **\$disconnect** Lambda function that you created with CloudFormation in Step 1. The Lambda function name should start with **websocket-step**.
11. For **Integration for \$default**, choose **mock**.

In a mock integration, API Gateway manages the route response without an integration backend.
12. Choose **Next**.
13. Review the stage that API Gateway creates for you. By default, API Gateway creates a stage named **production** and automatically deploys your API to that stage. Choose **Next**.
14. Choose **Create and deploy**.

Step 3: Create a Lambda authorizer

To control access to your WebSocket API, you create a Lambda authorizer. The CloudFormation template created the Lambda authorizer function for you. You can see the Lambda function in the Lambda console. The name should start with **websocket-step-functions-tutorial-AuthorizerHandler**. This Lambda function denies all calls to the WebSocket API unless the Authorization header is Allow. The Lambda function also passes the `$context.authorizer.principalId` variable to your API, which is later used in the DynamoDB table to identify API callers.

In this step, you configure the **\$connect** route to use the Lambda authorizer.

To create a Lambda authorizer

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. In the main navigation pane, choose **Authorizers**.
3. Choose **Create an authorizer**.
4. For **Authorizer name**, enter **LambdaAuthorizer**.
5. For **Authorizer ARN**, enter the name of the authorizer created by the CloudFormation template. The name should start with **websocket-step-functions-tutorial-AuthorizerHandler**.

Note

We recommend that you don't use this example authorizer for your production APIs.

6. For **Identity source type**, choose **Header**. For **Key**, enter **Authorization**.
7. Choose **Create authorizer**.

After you create your authorizer, you attach it to the **\$connect** route of your API.

To attach an authorizer to the \$connect route

1. In the main navigation pane, choose **Routes**.
2. Choose the **\$connect** route.
3. In the **Route request settings** section, choose **Edit**.
4. For **Authorization**, choose the dropdown menu, and then select your request authorizer.
5. Choose **Save changes**.

Step 4: Create a mock two-way integration

Next, you create the two-way mock integration for the **\$default** route. A mock integration lets you send a response to the client without using a backend. When you create an integration for the **\$default** route, you can show clients how to interact with your API.

You configure the **\$default** route to inform clients to use the **sendmessage** route.

To create a mock integration

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose the **\$default** route, and then choose the **Integration request** tab.
3. For **Request templates**, choose **Edit**.
4. For **Template selection expression**, enter **200**, and then choose **Edit**.
5. On the **Integration request** tab, for **Request templates**, choose **Create template**.
6. For **Template key**, enter **200**.
7. For **Generate template**, enter the following mapping template:

```
{"statusCode": 200}
```

Choose **Create template**.

The result should look like the following:

The screenshot shows the AWS Lambda integration configuration interface. At the top, there are tabs for "Route request", "Integration request" (which is selected), "Integration response", and "Route response".

Integration request settings:

- Integration type:** Info Mock
- Timeout:** 29000 ms
- Edit** button

Request templates (1):

- Template selection expression:** 200
- Edit** and **Create template** buttons

Template content (for key 200):

```
1 {"statusCode": 200}
```

Edit and **Delete** buttons for the template entry.

8. In the **\$default route** pane, choose **Enable two-way communication**.
9. Choose the **Integration response** tab, and then choose **Create integration response**.
10. For **Response key**, enter **\$default**.
11. For **Template selection expression**, enter **200**.
12. Choose **Create response**.
13. Under **Response templates**, choose **Create template**.
14. For **Template key**, enter **200**.
15. For **Response template**, enter the following mapping template:

```
{"Use the sendmessage route to send a message. Connection ID:  
$context.connectionId"}
```

16. Choose **Create template**.

The result should look like the following:

The screenshot shows the 'Integration response' tab selected in a navigation bar. Below it, a section titled 'Integration response settings' contains a 'Create integration response' button. A table lists a single entry for a 200 status code. The table has columns for 'Template selection expression' and 'Response templates'. The 'Template selection expression' column shows '200'. The 'Response templates' column shows a table for a 200 status code, which contains three numbered items: 1. {"Use the sendmessage route to send a message. Connection ID: \$context.connectionId"}, 2. , and 3. . Each item has 'Edit' and 'Delete' buttons.

Template selection expression	Response templates				
200	<table border="1"><thead><tr><th>200</th><th>Create template</th></tr></thead><tbody><tr><td>1 {"Use the sendmessage route to send a message. Connection ID: \$context.connectionId"} 2 3</td><td>Edit Delete</td></tr></tbody></table>	200	Create template	1 {"Use the sendmessage route to send a message. Connection ID: \$context.connectionId"} 2 3	Edit Delete
200	Create template				
1 {"Use the sendmessage route to send a message. Connection ID: \$context.connectionId"} 2 3	Edit Delete				

Step 5: Create a non-proxy integration with Step Functions

Next, you create a **sendmessage** route. Clients can invoke the **sendmessage** route to broadcast a message to all connected clients. The **sendmessage** route has a non-proxy AWS service integration with AWS Step Functions. The integration invokes the [StartExecution](#) command for the Step Functions state machine that the CloudFormation template created for you.

To create a non-proxy integration

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose **Create route**.
3. For **Route key**, enter **sendmessage**.
4. For **Integration type**, choose **AWS service**.
5. For **AWS Region**, enter the Region where you deployed your CloudFormation template.
6. For **AWS service**, choose **Step Functions**.
7. For **HTTP method**, choose **POST**.
8. For **Action name**, enter **StartExecution**.
9. For **Execution role**, enter the execution role created by the CloudFormation template. The name should be **WebSocketTutorialApiRole**.
10. Choose **Create route**.

Next, you create a mapping template to send request parameters to the Step Functions state machine.

To create a mapping template

1. Choose the **sendmessage** route, and then choose the **Integration request** tab.
2. In the **Request templates** section, choose **Edit**.
3. For **Template selection expression**, enter **\\$default**.
4. Choose **Edit**.
5. In the **Request templates** section, choose **Create template**.
6. For **Template key**, enter **\\$default**.
7. For **Generate template**, enter the following mapping template:

```
#set($domain = "$context.domainName")
#set($stage = "$context.stage")
#set($body = $input.json('$'))
#set($getMessage = $util.parseJson($body))
#set($mymessage = $getMessage.message)
{
  "input": "{\"domain\": \"$domain\", \"stage\": \"$stage\", \"message\": \"$mymessage\"}",
}
```

```
"stateMachineArn": "arn:aws:states:us-east-2:123456789012:stateMachine:WebSocket-Tutorial-StateMachine"  
}
```

Replace the *stateMachineArn* with the ARN of the state machine created by CloudFormation.

The mapping template does the following:

- Creates the variable \$domain using the context variable domainName.
- Creates the variable \$stage using the context variable stage.

The \$domain and \$stage variables are required to build a callback URL.

- Takes in the incoming sendmessage JSON message, and extracts the message property.
- Creates the input for the state machine. The input is the domain and stage of the WebSocket API and the message from the sendmessage route.

8. Choose **Create template**.

Request templates (1)

[Edit](#)[Create template](#)

Use request templates to transform the incoming message before sending it to the integration. API Gateway uses a template selection expression to determine which template to use. Name the template with a key that matches the result of the selection expression.

Template selection expression

\\$default

\\$default

[Edit](#)[Delete](#)

```
1 #set($domain = "$context.domainName")
2 #set($stage = "$context.stage")
3 #set($body = $input.json('$'))
4 #set($getMessage = $util.parseJson($body))
5 #set($mymessage = $getMessage.message)
6 {
7     "input": "{\"domain\": \"$domain\", \"stage\": \"$stage\",
8     \"message\": \"$mymessage\"}",
9     "stateMachineArn": "arn:aws:states:us-east-2:111222333:
stateMachine:WebSocket-Tutorial-StateMachine"
9 }
```

You can create a non-proxy integration on the **\$connect** or **\$disconnect** routes, to directly add or remove a connection ID from the DynamoDB table, without invoking a Lambda function.

Step 6: Test your API

Next, you'll deploy and test your API to make sure that it works correctly. You will use the `wscat` command to connect to the API and then, you will use a slash command to send a ping frame to check the connection to the WebSocket API.

To deploy your API

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.

2. In the main navigation pane, choose **Routes**.
3. Choose **Deploy API**.
4. For **Stage**, choose **production**.
5. (Optional) For **Deployment description**, enter a description.
6. Choose **Deploy**.

After you deploy your API, you can invoke it. Use the invoke URL to call your API.

To get the invoke URL for your API

1. Choose your API.
2. Choose **Stages**, and then choose **production**.
3. Note your API's **WebSocket URL**. The URL should look like `wss://abcdef123.execute-api.us-east-2.amazonaws.com/production`.

Now that you have your invoke URL, you can test the connection to your WebSocket API.

To test the connection to your API

1. Use the following command to connect to your API. First, you test the connection by invoking the `/ping` path.

```
wscat -c wss://abcdef123.execute-api.us-east-2.amazonaws.com/production -H  
"Authorization: Allow" --slash -P
```

```
Connected (press CTRL+C to quit)
```

2. Enter the following command to ping the control frame. You can use a control frame for keepalive purposes from the client side.

```
/ping
```

The result should look like the following:

```
< Received pong (data: "")
```

Now that you have tested the connection, you can test that your API works correctly. In this step, you open a new terminal window so the WebSocket API can send a message to all connected clients.

To test your API

1. Open a new terminal and run the wscat command again with the following parameters.

```
wscat -c wss://abcdef123.execute-api.us-east-2.amazonaws.com/production -H  
"Authorization: Allow"
```

Connected (press CTRL+C to quit)

2. API Gateway determines which route to invoke based on your API's route request selection expression. Your API's route select expression is \$request.body.action. As a result, API Gateway invokes the sendmessage route when you send the following message:

```
{"action": "sendmessage", "message": "hello, from Step Functions!"}
```

The Step Functions state machine associated with the route invokes a Lambda function with the message and the callback URL. The Lambda function calls the API Gateway Management API and sends the message to all connected clients. All clients receive the following message:

< hello, from Step Functions!

Now that you have tested your WebSocket API, you can disconnect from your API.

To disconnect from your API

- Press CTRL+C to disconnect from your API.

When a client disconnects from your API, API Gateway invokes your API's **\$disconnect** route. The Lambda integration for your API's **\$disconnect** route removes the connection ID from DynamoDB.

Step 7: Clean up

To prevent unnecessary costs, delete the resources that you created as part of this tutorial. The following steps delete your CloudFormation stack and WebSocket API.

To delete a WebSocket API

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. On the **APIs** page, select your **websocket-api**.
3. Choose **Actions**, choose **Delete**, and then confirm your choice.

To delete an CloudFormation stack

1. Open the CloudFormation console at <https://console.aws.amazon.com/cloudformation>.
2. Select your CloudFormation stack.
3. Choose **Delete** and then confirm your choice.

Next steps

You can automate the creation and cleanup of all the AWS resources involved in this tutorial. For an example of an CloudFormation template that automates these actions for this tutorial, see [ws-sfn.zip](#).

API Gateway REST APIs

A REST API in API Gateway is a collection of resources and methods that are integrated with backend HTTP endpoints, Lambda functions, or other AWS services. You can use API Gateway features to help you with all aspects of the API lifecycle, from creation through monitoring your production APIs.

API Gateway REST APIs use a request/response model where a client sends a request to a service and the service responds back synchronously. This kind of model is suitable for many different kinds of applications that depend on synchronous communication.

Topics

- [Develop REST APIs in API Gateway](#)
- [Publish REST APIs for customers to invoke](#)
- [Optimize performance of REST APIs](#)
- [Distribute your REST APIs to clients in API Gateway](#)
- [Protect your REST APIs in API Gateway](#)
- [Monitor REST APIs in API Gateway](#)

Develop REST APIs in API Gateway

In Amazon API Gateway, you build a REST API as a collection of programmable entities known as API Gateway [resources](#). For example, you use a [RestApi](#) resource to represent an API that can contain a collection of [Resource](#) entities.

Each Resource entity can have one or more [Method](#) resources. A Method is an incoming request submitted by the client and can contain the following request parameters: a path parameter, a header, or a query string parameter. In addition, depending on the HTTP method, the request can contain a body. Your method defines how the client accesses the exposed Resource. To integrate the Method with a backend endpoint, also known as the integration endpoint, you create an [Integration](#) resource. This forwards the incoming request to a specified integration endpoint URI. If necessary, you can transform request parameters or the request body to meet the backend requirements, or you can create a proxy integration, where API Gateway sends the entire request in a standardized format to the integration endpoint URI and then directly sends the response to the client.

For responses, you can create a [MethodResponse](#) resource to represent a response received by the client and you create an [IntegrationResponse](#) resource to represent the response that is returned by the backend. Use an integration response to transform the backend response data before returning the data to the client or to pass the backend response as-is to the client.

Example resource for a REST API


The following diagram shows how API Gateway implements this request/response model for an HTTP proxy and an HTTP non-proxy integration for the GET /pets resource. The client sends the x-version:beta header to API Gateway and API Gateway sends the 204 status code to the client.

In the non-proxy integration, API Gateway performs data transformations to meet the backend requirements, by modifying the integration request and integration response. In a non-proxy integration, you can access the body in the method request but you transform it in the integration request. When the integration endpoint returns a response with a body, you access and transform it in the integration response. You can't modify the body in the method response.


In the proxy integration, the integration endpoint modifies the request and response. API Gateway doesn't modify the integration request or integration response, and sends the incoming request to the backend as-is.

Regardless of the integration type, the client sent a request to API Gateway and API Gateway responded synchronously.

Non-proxy integration



Proxy integration



The following example execution logs show what API Gateway would log in the previous example. For clarity, some values and initial logs have been removed:

Non-proxy integration

```
Wed Feb 12 23:56:44 UTC 2025 : Starting execution for request: abcd-1234-5678
Wed Feb 12 23:56:44 UTC 2025 : HTTP Method: GET, Resource Path: /pets
Wed Feb 12 23:56:44 UTC 2025 : Method request path: {}
Wed Feb 12 23:56:44 UTC 2025 : Method request query string: {}
Wed Feb 12 23:56:44 UTC 2025 : Method request headers: {x-version=beta}
Wed Feb 12 23:56:44 UTC 2025 : Method request body before transformations:
Wed Feb 12 23:56:44 UTC 2025 : Endpoint request URI: http://petstore-demo-
endpoint.execute-api.com/petstore/pets
Wed Feb 12 23:56:44 UTC 2025 : Endpoint request headers: {app-version=beta}
Wed Feb 12 23:56:44 UTC 2025 : Endpoint request body after transformations:
Wed Feb 12 23:56:44 UTC 2025 : Sending request to http://petstore-demo-
endpoint.execute-api.com/petstore/pets
Wed Feb 12 23:56:45 UTC 2025 : Received response. Status: 200, Integration latency:
  123 ms
Wed Feb 12 23:56:45 UTC 2025 : Endpoint response headers: {Date=Wed, 12 Feb 2025
  23:56:45 GMT}
Wed Feb 12 23:56:45 UTC 2025 : Endpoint response body before transformations:
Wed Feb 12 23:56:45 UTC 2025 : Method response body after transformations: (null)
Wed Feb 12 23:56:45 UTC 2025 : Method response headers: {X-Amzn-Trace-Id=Root=1-
abcd-12345}
Wed Feb 12 23:56:45 UTC 2025 : Successfully completed execution
Wed Feb 12 23:56:45 UTC 2025 : Method completed with status: 204
```

Proxy integration

```
Wed Feb 12 23:59:42 UTC 2025 : Starting execution for request: abcd-1234-5678
Wed Feb 12 23:59:42 UTC 2025 : HTTP Method: GET, Resource Path: /pets
Wed Feb 12 23:59:42 UTC 2025 : Method request path: {}
Wed Feb 12 23:59:42 UTC 2025 : Method request query string: {}
Wed Feb 12 23:59:42 UTC 2025 : Method request headers: {x-version=beta}
Wed Feb 12 23:59:42 UTC 2025 : Method request body before transformations:
Wed Feb 12 23:59:42 UTC 2025 : Endpoint request URI: http://petstore-demo-
endpoint.execute-api.com/petstore/pets
Wed Feb 12 23:59:42 UTC 2025 : Endpoint request headers: { x-version=beta}
Wed Feb 12 23:59:42 UTC 2025 : Endpoint request body after transformations:
Wed Feb 12 23:59:42 UTC 2025 : Sending request to http://petstore-demo-
endpoint.execute-api.com/petstore/pets
```

```
Wed Feb 12 23:59:43 UTC 2025 : Received response. Status: 204, Integration latency:  
123 ms  
Wed Feb 12 23:59:43 UTC 2025 : Endpoint response headers: {Date=Wed, 12 Feb 2025  
23:59:43 GMT}  
Wed Feb 12 23:59:43 UTC 2025 : Endpoint response body before transformations:  
Wed Feb 12 23:59:43 UTC 2025 : Method response body after transformations:  
Wed Feb 12 23:59:43 UTC 2025 : Method response headers: {Date=Wed, 12 Feb 2025  
23:59:43 GMT}  
Wed Feb 12 23:59:43 UTC 2025 : Successfully completed execution  
Wed Feb 12 23:59:43 UTC 2025 : Method completed with status: 204
```


To import a similar API and test it in the AWS Management Console, see the [example API](#).

Additional REST API features for development

API Gateway supports additional features for the development of your REST API. For example, to help your customers understand your API, you can provide documentation for the API. To enable this, add a [DocumentationPart](#) resource for a supported API entity.

To control how clients call an API, use [IAM permissions](#), a [Lambda authorizer](#), or an [Amazon Cognito user pool](#). To meter the use of your API, set up [usage plans](#) to throttle API requests. You can enable these when creating or updating your API.

The following diagram shows the features available for REST API development and where in the request/response model these features are configured.



For an introduction on how to create an API, see [the section called “Tutorial: Create a REST API with a Lambda proxy integration”](#). To learn more information about the capabilities of API Gateway that you might use while developing a REST API, see the following topics. These topics contain conceptual information and procedures that you can perform using the API Gateway console, the API Gateway REST API, the AWS CLI, or one of the AWS SDKs.

Topics

- [API endpoint types for REST APIs in API Gateway](#)
- [Security policies for REST APIs in API Gateway](#)
- [IP address types for REST APIs in API Gateway](#)
- [Methods for REST APIs in API Gateway](#)
- [Control and manage access to REST APIs in API Gateway](#)
- [Integrations for REST APIs in API Gateway](#)
- [Request validation for REST APIs in API Gateway](#)
- [Data transformations for REST APIs in API Gateway](#)
- [Gateway responses for REST APIs in API Gateway](#)
- [CORS for REST APIs in API Gateway](#)

- [Binary media types for REST APIs in API Gateway](#)
- [Invoke REST APIs in API Gateway](#)
- [Develop REST APIs using OpenAPI in API Gateway](#)

API endpoint types for REST APIs in API Gateway

An [*API endpoint*](#) type refers to the hostname of the API. The API endpoint type can be *edge-optimized*, *Regional*, or *private*, depending on where the majority of your API traffic originates from.

Edge-optimized API endpoints

An [*edge-optimized API endpoint*](#) typically routes requests to the nearest CloudFront Point of Presence (POP), which could help in cases where your clients are geographically distributed. This is the default endpoint type for API Gateway REST APIs.

Edge-optimized APIs capitalize the names of [HTTP headers](#) (for example, `Cookie`).

CloudFront sorts HTTP cookies in natural order by cookie name before forwarding the request to your origin. For more information about the way CloudFront processes cookies, see [Caching Content Based on Cookies](#).

Any custom domain name that you use for an edge-optimized API applies across all regions.

Regional API endpoints

A [*Regional API endpoint*](#) is intended for clients in the same Region. When a client running on an EC2 instance calls an API in the same Region, or when an API is intended to serve a small number of clients with high demands, a Regional API reduces connection overhead.

For a Regional API, any custom domain name that you use is specific to the Region where the API is deployed. If you deploy a Regional API in multiple Regions, it can have the same custom domain name in all Regions. You can use custom domains together with Amazon Route 53 to perform tasks such as [latency-based routing](#). For more information, see [the section called “Set up a Regional custom domain name”](#) and [the section called “Set up an edge-optimized custom domain name in API Gateway”](#).

Regional API endpoints pass all header names through as-is.

Note

In cases where API clients are geographically dispersed, it may still make sense to use a Regional API endpoint, together with your own Amazon CloudFront distribution to ensure that API Gateway does not associate the API with service-controlled CloudFront distributions. For more information about this use case, see [How do I set up API Gateway with my own CloudFront distribution?](#).

Private API endpoints

A [*private API endpoint*](#) is an API endpoint that can only be accessed from your Amazon Virtual Private Cloud (VPC) using an interface VPC endpoint, which is an endpoint network interface (ENI) that you create in your VPC. For more information, see [the section called “Private REST APIs”](#).

Private API endpoints pass all header names through as-is.

Change a public or private API endpoint type in API Gateway

Changing an API endpoint type requires you to update the API's configuration. You can change an existing API type using the API Gateway console, the AWS CLI, or an AWS SDK for API Gateway. The endpoint type cannot be changed again until the current change is completed, but your API will be available.

The following endpoint type changes are supported:

- From edge-optimized to Regional or private
- From Regional to edge-optimized or private
- From private to Regional

You cannot change a private API into an edge-optimized API.

If you are changing a public API from edge-optimized to Regional or vice versa, note that an edge-optimized API may have different behaviors than a Regional API. For example, an edge-optimized API removes the Content-MD5 header. Any MD5 hash value passed to the backend can be expressed in a request string parameter or a body property. However, the Regional API passes this header through, although it may remap the header name to some other name. Understanding the differences helps you decide how to update an edge-optimized API to a Regional one or from a Regional API to an edge-optimized one.

Topics

- [Use the API Gateway console to change an API endpoint type](#)
- [Use the AWS CLI to change an API endpoint type](#)

Use the API Gateway console to change an API endpoint type

To change the API endpoint type of your API, perform one of the following sets of steps:

To convert a public endpoint from Regional or edge-optimized and vice versa

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose a REST API.
3. Choose **API settings**.
4. In the **API details** section, choose **Edit**.
5. For **API endpoint type**, select either **Edge-optimized** or **Regional**.
6. Choose **Save changes**.
7. Redeploy your API so that the changes will take effect.

To convert a private endpoint to a Regional endpoint

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose a REST API.
3. Edit the resource policy for your API to remove any mention of VPCs or VPC endpoints so that API calls from outside your VPC as well as inside your VPC will succeed.
4. Choose **API settings**.
5. In the **API details** section, choose **Edit**.
6. For **API endpoint type**, select **Regional**.
7. Choose **Save changes**.
8. Remove the resource policy from your API.
9. Redeploy your API so that the changes will take effect.

Because you're migrating the endpoint type from private to Regional, API Gateway changes the IP address type to IPv4. For more information, see [the section called "IP address types for REST APIs in API Gateway"](#).

To convert a Regional endpoint to a private endpoint

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose a REST API.
3. Create a resource policy that grants access to your VPC or VPC endpoint. For more information, see [???](#).
4. Choose **API settings**.
5. In the **API details** section, choose **Edit**.
6. For **API endpoint type**, select **Private**.
7. (Optional) For **VPC endpoint IDs**, select the VPC endpoint IDs that you want to associate with your private API.
8. Choose **Save changes**.
9. Redeploy your API so that the changes will take effect.

Because you're migrating the endpoint type from Regional to private, API Gateway changes the IP address type to dualstack. For more information, see [the section called "IP address types for REST APIs in API Gateway"](#).

Use the AWS CLI to change an API endpoint type

The following [update-rest-api](#) command updates an edge-optimized API to a Regional API:

```
aws apigateway update-rest-api \
  --rest-api-id a1b2c3 \
  --patch-operations op=replace,path=/endpointConfiguration/types/EDGE,value=REGIONAL
```

The successful response has a status code of 200 OK and a payload similar to the following:

```
{
  "createdDate": "2017-10-16T04:09:31Z",
  "description": "Your first API with Amazon API Gateway. This is a sample API that integrates via HTTP with our demo Pet Store endpoints",
  "endpointConfiguration": {
    "types": "REGIONAL"
  },
  "id": "a1b2c3",
  "name": "PetStore imported as edge-optimized"
```

}

The following [update-rest-api](#) command updates a Regional API to an edge-optimized API:

```
aws apigateway update-rest-api \
--rest-api-id a1b2c3 \
--patch-operations op=replace,path=/endpointConfiguration/types/REGIONAL,value=EDGE
```

Because [put-rest-api](#) is for updating API definitions, it is not applicable to updating an API endpoint type.

Security policies for REST APIs in API Gateway

A *security policy* is a predefined combination of minimum TLS version and cipher suites offered by API Gateway. When your clients establish a TLS handshake to your API or custom domain name, the security policy enforces the TLS version and cipher suite accepted by API Gateway. Security policies protect your APIs and custom domain names from network security problems such as tampering and eavesdropping between a client and server.

API Gateway supports legacy security policies and enhanced security policies. TLS_1_0 and TLS_1_2 are legacy security policies. Use these security policies for backwards compatibility. Any policy that starts with `SecurityPolicy_` is an enhanced security policy. Use these policies for regulated workloads, advanced governance, or to use post-quantum cryptography. When you use an enhanced security policy, you must also set the endpoint access mode for additional governance. For more information, see [the section called “Endpoint access mode”](#).

How API Gateway applies security policies

The following example shows how API Gateway applies security policies using the `SecurityPolicy_TLS13_1_3_2025_09` security policy as an example.

The `SecurityPolicy_TLS13_1_3_2025_09` security policy accepts TLS 1.3 traffic and rejects TLS 1.2 and TLS 1.0 traffic. For TLS 1.3 traffic, the security policy accepts the following cipher suites:

- `TLS_AES_128_GCM_SHA256`
- `TLS_AES_256_GCM_SHA384`
- `TLS_CHACHA20_POLY1305_SHA256`

API Gateway does not accept any other cipher suites. For instance, the security policy would reject any TLS 1.3 traffic that uses the AES128-SHA cipher suite. For more information about the supported TLS versions and ciphers, see [the section called “Supported security policies”](#).

To monitor which TLS protocol and ciphers clients used to access your API Gateway, you can use the `$context.tlsVersion` and `$context.cipherSuite` context variables in your access logs. For more information, see [the section called “Monitor”](#).

Endpoint access mode

Endpoint access mode is an additional parameter that you must specify for any REST API or custom domain name that uses an enhanced security policy that begins with `SecurityPolicy_`. You do this when you create your resource or if you change the security policy from a legacy policy to an enhanced policy.

When the endpoint access mode is set to `STRICT`, any requests to your REST API or custom domain name must pass the following checks:

- The request must originate from the same API Gateway endpoint type as your resource. This could be from a Regional, an edge-optimized, or a private endpoint.
- If you use a Regional or private endpoint, API Gateway uses SNI host matching. If you use an edge-optimized endpoint, API Gateway conforms to CloudFront's domain fronting protection. For more information, see [Domain fronting](#).

If either of these conditions are not met, API Gateway rejects the request. We recommend that you use `STRICT` endpoint access mode when possible.

To migrate an existing API or domain name to use strict endpoint access mode, first update your security policy to an enhanced security policy and keep the endpoint access mode set to `BASIC`. After you validate your traffic and access logs, set the endpoint access mode to `STRICT`. When you migrate the endpoint access mode from `STRICT` to `BASIC`, your endpoint will be unavailable for around 15 minutes as the changes propagate.

You should not set the endpoint access mode to `STRICT` for certain application architectures and instead set the endpoint access mode to `BASIC`. The following table shows some application architectures and a recommendation so your REST API or custom domain name can use `STRICT` endpoint access mode.

Architecture	Suggested migration
Using a VPC endpoint to access a public custom domain name.	This architecture uses cross-endpoint type traffic. We recommend that you migrate to the section called "Custom domain names for private APIs".
Using any method to invoke a private API that doesn't use a custom domain name or private DNS names.	This architecture creates a mismatch between the host header and the SNI used in the TLS handshake and does not pass CloudFront's domain fronting restrictions. We recommend you migrate your VPC to use private DNS.
Using domain sharding to distribute content across multiple domains or subdomains.	This architecture creates a mismatch between the host header and the SNI used in the TLS handshake and does not pass CloudFront's domain fronting restrictions. We recommend that you use HTTP/2 and migrate away from this anti-pattern.

The following are considerations for using endpoint access mode:

- If the endpoint access mode of an API or domain name is STRICT, you can't change the endpoint type. To change the endpoint type, first change the endpoint access mode to BASIC.
- After you change the endpoint access mode from BASIC to STRICT, there is a 15 minute delay for API Gateway to enforce the strict endpoint access mode.
- When you change a security policy from a policy that begins with `SecurityPolicy_` to a legacy policy, you must unset the endpoint access mode to "".

Considerations

The following are considerations for security policies for REST APIs in API Gateway:

- You can import the security policy in an OpenAPI definition file. For more information, see [x-amazon-apigateway-endpoint-access-mode](#).

- Your API can be mapped to a custom domain name with a different security policy than your API. When you invoke that custom domain name, API Gateway uses the security policy of the API to negotiate the TLS handshake. If you disable your default API endpoint, this might affect how callers can invoke your API.
- If you change your security policy, it takes about 15 minutes for the update to complete. You can monitor the `apiStatus` of your API. As your API updates, the `apiStatus` is `UPDATING` and when it completes, it will be `AVAILABLE`. When your API status is `UPDATING`, you can still invoke it.
- API Gateway supports security policies on all APIs. However, you can only choose a security policy for REST APIs. API Gateway only supports the `TLS_1_2` security policy for HTTP or WebSocket APIs.
- You can't update the security policy for an API from `TLS_1_0` to `TLS_1_2`.
- Some security policies support both ECDSA and RSA cipher suites. If you use this type of policy with a custom domain name, the cipher suites match the customer-provided certificate key type, either RSA or ECDSA. If you use this type of policy with a REST API, the cipher suites match the cipher suites compatible with RSA certificate types.

Supported security policies

The following tables describe the [security policies](#) that can be specified for each REST API endpoint type and custom domain name type. These policies allow you to control incoming connections. API Gateway only supports TLS 1.2 on egress. You can update the security policy for your API or custom domain name at any time.

Policies that contain FIPS in the title are compatible with the Federal Information Processing Standard (FIPS), which is a US and Canadian government standard that specifies the security requirements for cryptographic modules that protect sensitive information. To learn more, see [Federal Information Processing Standard \(FIPS\) 140](#) on the [AWS Cloud Security Compliance](#) page.

All FIPS policies leverage the AWS-LC FIPS validated cryptographic module. To learn more, see the [AWS-LC Cryptographic Module](#) page on the [NIST Cryptographic Module Validation Program](#) site.

Policies that contain PQ in the title use [Post-Quantum Cryptography \(PQC\)](#) to implement hybrid key exchange algorithms for TLS to ensure traffic confidentiality against future quantum computing threats.

Policies that contain PFS in the title use [Perfect Forward Secrecy \(PFS\)](#) to make sure session keys aren't compromised.

Policies that contain both FIPS and PQ in their title support both of these features.

Default security policies

When you create a new REST API or custom domain, the resource is assigned a default security policy. The following table shows the default security policy for these resources.

Resource	Default security policy name
Regional APIs	TLS_1_0
Edge-optimized APIs	TLS_1_0
Private APIs	TLS_1_2
Regional domain	TLS_1_2
Edge-optimized domain	TLS_1_2
Private domain	TLS_1_2

Supported security policies for Regional and private APIs and custom domain names

The following table describes the security policies that can be specified for Regional and private APIs and custom domain names:

Security policy	Supported TLS versions	Supported ciphers
SecurityPolicy_TLS13_1_3_20_25_09	TLS1.3	TLS1.3 <ul style="list-style-type: none">• TLS_AES_128_GCM_SH A256• TLS_AES_256_GCM_SH A384

Security policy	Supported TLS versions	Supported ciphers
		<ul style="list-style-type: none"> • TLS_CHACHA20_POLY1305_SHA256
SecurityPolicy_TLS13_1_3_FIPS_2025_09	TLS1.3	<p>TLS1.3</p> <ul style="list-style-type: none"> • TLS_AES_128_GCM_SHA256 • TLS_AES_256_GCM_SHA384
SecurityPolicy_TLS13_1_2_PF_S_PQ_2025_09	<p>TLS1.3</p> <p>TLS1.2</p>	<p>TLS1.3</p> <ul style="list-style-type: none"> • TLS_AES_128_GCM_SHA256 • TLS_AES_256_GCM_SHA384 • TLS_CHACHA20_POLY1305_SHA256 <p>TLS1.2</p> <ul style="list-style-type: none"> • TLS_AES_128_GCM_SHA256 • TLS_AES_256_GCM_SHA384 • ECDHE-ECDSA-AES128-GCM-SHA256 • ECDHE-RSA-AES128-GCM-SHA256 • ECDHE-ECDSA-AES256-GCM-SHA384 • ECDHE-RSA-AES256-GCM-SHA384

Security policy	Supported TLS versions	Supported ciphers
SecurityPolicy_TLS 13_1_2_PQ_2025_09	TLS1.3 TLS1.2	TLS1.3 <ul style="list-style-type: none"> • TLS_AES_128_GCM_SH_A256 • TLS_AES_256_GCM_SH_A384 • TLS_CHACHA20_POLY1305_SHA256 TLS1.2 <ul style="list-style-type: none"> • TLS_AES_128_GCM_SH_A256 • TLS_AES_256_GCM_SH_A384 • ECDHE-ECDSA-AES128-GCM-SHA256 • ECDHE-RSA-AES128-GCM-SHA256 • ECDHE-ECDSA-AES128-SHA256 • ECDHE-RSA-AES128-SHA256 • ECDHE-ECDSA-AES256-GCM-SHA384 • ECDHE-RSA-AES256-GCM-SHA384 • ECDHE-ECDSA-AES256-SHA384 • ECDHE-RSA-AES256-SHA384 • AES128-GCM-SHA256

Security policy	Supported TLS versions	Supported ciphers
		<ul style="list-style-type: none">• AES128-SHA256• AES256-GCM-SHA384• AES256-SHA256

Security policy	Supported TLS versions	Supported ciphers
TLS_1_2	TLS1.3	TLS1.3
	TLS1.2	<ul style="list-style-type: none">• TLS_AES_128_GCM_SHA256• TLS_AES_256_GCM_SHA384• TLS_CHACHA20_POLY1305_SHA256
		TLS1.2 <ul style="list-style-type: none">• ECDHE-ECDSA-AES128-GCM-SHA256• ECDHE-RSA-AES128-GCM-SHA256• ECDHE-ECDSA-AES128-SHA256• ECDHE-RSA-AES128-SHA256• ECDHE-ECDSA-AES256-GCM-SHA384• ECDHE-RSA-AES256-GCM-SHA384• ECDHE-ECDSA-AES256-SHA384• ECDHE-RSA-AES256-SHA384• AES128-GCM-SHA256• AES128-SHA256• AES256-GCM-SHA384• AES256-SHA256

Security policy	Supported TLS versions	Supported ciphers
TLS_1_0	TLS1.3 TLS1.2 TLS1.1 TLS1.0	TLS1.3 <ul style="list-style-type: none"> • TLS_AES_128_GCM_SHA256 • TLS_AES_256_GCM_SHA384 • TLS_CHACHA20_POLY1305_SHA256 TLS1.0-TLS1.2 <ul style="list-style-type: none"> • ECDHE-ECDSA-AES128-GCM-SHA256 • ECDHE-RSA-AES128-GCM-SHA256 • ECDHE-ECDSA-AES128-SHA256 • ECDHE-RSA-AES128-SHA256 • ECDHE-ECDSA-AES128-SHA • ECDHE-RSA-AES128-SHA • ECDHE-ECDSA-AES256-GCM-SHA384 • ECDHE-RSA-AES256-GCM-SHA384 • ECDHE-ECDSA-AES256-SHA384 • ECDHE-RSA-AES256-SHA384 • ECDHE-ECDSA-AES256-SHA

Security policy	Supported TLS versions	Supported ciphers
		<ul style="list-style-type: none"> • ECDHE-RSA-AES256-SHA • AES128-GCM-SHA256 • AES128-SHA256 • AES128-SHA • AES256-GCM-SHA384 • AES256-SHA256 • AES256-SHA

Supported security policies for edge-optimized APIs and custom domain names

The following table describes the security policies that can be specified for edge-optimized APIs and edge-optimized custom domain names:

Security policy name	Supported TLS versions	Supported ciphers
SecurityPolicy_TLS13_2025_E DGE	TLS1.3	TLS1.3
		<ul style="list-style-type: none"> • TLS_AES_128_GCM_SHA256 • TLS_AES_256_GCM_SHA384 • TLS_CHACHA20_POLY1305_SHA256
SecurityPolicy_TLS12_PFS_2025_EDGE	TLS1.3 TLS1.2	TLS1.3
		<ul style="list-style-type: none"> • TLS_AES_128_GCM_SHA256 • TLS_AES_256_GCM_SHA384 • TLS_CHACHA20_POLY1305_SHA256

Security policy name	Supported TLS versions	Supported ciphers
		<p>TLS1.2</p> <ul style="list-style-type: none">• ECDHE-ECDSA-AES128-GCM-SHA256• ECDHE-ECDSA-AES256-GCM-SHA384• ECDHE-ECDSA-CHACHA20-POLY1305• ECDHE-RSA-AES128-GCM-SHA256• ECDHE-RSA-AES256-GCM-SHA384• ECDHE-RSA-CHACHA20-POLY1305

Security policy name	Supported TLS versions	Supported ciphers
SecurityPolicy_TLS12_2018_E_DGE	TLS1.3 TLS1.2	TLS1.3 TLS1.2 <ul style="list-style-type: none">• TLS_AES_128_GCM_SHA256• TLS_AES_256_GCM_SHA384• TLS_CHACHA20_POLY1305_SHA256

Security policy name	Supported TLS versions	Supported ciphers
TLS_1_0	TLS1.3 TLS1.2 TLS1.1 TLS1.0	TLS1.3 <ul style="list-style-type: none"> • TLS_AES_128_GCM_SHA256 • TLS_AES_256_GCM_SHA384 • TLS_CHACHA20_POLY1305_SHA256 TLS1.0-TLS1.2 <ul style="list-style-type: none"> • ECDHE-ECDSA-AES128-GCM-SHA256 • ECDHE-RSA-AES128-GCM-SHA256 • ECDHE-ECDSA-AES128-SHA256 • ECDHE-RSA-AES128-SHA256 • ECDHE-ECDSA-AES128-SHA • ECDHE-RSA-AES128-SHA • ECDHE-ECDSA-AES256-GCM-SHA384 • ECDHE-RSA-AES256-GCM-SHA384 • ECDHE-ECDSA-AES256-SHA384 • ECDHE-RSA-AES256-SHA384 • ECDHE-ECDSA-AES256-SHA

Security policy name	Supported TLS versions	Supported ciphers
		<ul style="list-style-type: none"> • ECDHE-RSA-AES256-SHA • AES256-SHA256 • AES256-SHA

OpenSSL and RFC cipher names

OpenSSL and IETF RFC 5246 use different names for the same ciphers. The following table maps the OpenSSL name to the RFC name for each cipher. For more information, see [ciphers](#) in the OpenSSL Documentation.

OpenSSL cipher name	RFC cipher name
TLS_AES_128_GCM_SHA256	TLS_AES_128_GCM_SHA256
TLS_AES_256_GCM_SHA384	TLS_AES_256_GCM_SHA384
TLS_CHACHA20_POLY1305_SHA256	TLS_CHACHA20_POLY1305_SHA256
ECDHE-RSA-AES128-GCM-SHA256	TLS_ECDHE_RSA_WITH_AES_128_GCM_SHA256
ECDHE-RSA-AES128-SHA256	TLS_ECDHE_RSA_WITH_AES_128_CBC_SHA256
ECDHE-RSA-AES128-SHA	TLS_ECDHE_RSA_WITH_AES_128_CBC_SHA

OpenSSL cipher name	RFC cipher name
ECDHE-RSA-AES256-GCM-SHA384	TLS_ECDHE_RSA_WITH_AES_256_GCM_SHA384
ECDHE-RSA-AES256-SHA384	TLS_ECDHE_RSA_WITH_AES_256_CBC_SHA384
ECDHE-RSA-AES256-SHA	TLS_ECDHE_RSA_WITH_AES_256_CBC_SHA
AES128-GCM-SHA256	TLS_RSA_WITH_AES_128_GCM_SHA256
AES256-GCM-SHA384	TLS_RSA_WITH_AES_256_GCM_SHA384
AES128-SHA256	TLS_RSA_WITH_AES_128_CBC_SHA256
AES256-SHA	TLS_RSA_WITH_AES_256_CBC_SHA
AES128-SHA	TLS_RSA_WITH_AES_128_CBC_SHA
DES-CBC3-SHA	TLS_RSA_WITH_3DES_EDE_CBC_SHA

How to change a security policy

You can change the security policy for your API. If you are sending traffic to your APIs through your custom domain name, the API and the custom domain name don't need to have the same security policy. When you invoke that custom domain name, API Gateway uses the security policy of the API to negotiate the TLS handshake. However, for consistency, we recommend that you use the same security policy for your custom domain name and API.

If you change your security policy, it takes about 15 minutes for the update to complete. You can monitor the `apiStatus` of your API. As your API updates, the `apiStatus` is `UPDATING` and when it completes, it will be `AVAILABLE`. When your API is updating, you can still invoke it.

AWS Management Console

To change the security policy of an API

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose a REST API.
3. Choose **API settings**, and then choose **Edit**.
4. For **Security policy**, select a new policy that starts with **SecurityPolicy_**.
5. For **Endpoint access mode**, choose **Strict**.
6. Choose **Save changes**.

Redeploy your API for the changes to take effect. Because you changed the endpoint access mode to strict, it will take about 15 minutes for the changes to fully propagate.

AWS CLI

The following [update-rest-api](#) command updates an API to use the `SecurityPolicy_TLS13_1_3_2025_09` security policy:

```
aws apigateway update-rest-api \
--rest-api-id abcd1234 \
--patch-operations '[
    {
        "op": "replace",
        "path": "/securityPolicy",
        "value": "SecurityPolicy_TLS13_1_3_2025_09"
    },
    {
        "op": "replace",
        "path": "/endpointAccessMode",
        "value": "STRICT"
    }
]'
```

The output will look like the following:

```
{
    "id": "abcd1234",
    "name": "MyAPI",
    "description": "My API with a new security policy",
```

```
"createdDate": "2025-02-04T11:47:06-08:00",
"apiKeySource": "HEADER",
"endpointConfiguration": {
    "types": [
        "REGIONAL"
    ],
    "ipAddressType": "dualstack"
},
"tags": {},
"disableExecuteApiEndpoint": false,
"securityPolicy": "SecurityPolicy_TLS13_1_3_2025_09",
"endpointAccessMode": "STRICT"
"rootResourceId": "efg456"
}
```

The following [update-rest-api](#) command updates a API that was using an enhanced security policy to use the TLS_1_0 security policy.

```
aws apigateway update-rest-api \
--rest-api-id abcd1234 \
--patch-operations '[
{
    "op": "replace",
    "path": "/securityPolicy",
    "value": "TLS_1_0"
},
{
    "op": "replace",
    "path": "/endpointAccessMode",
    "value": ""
}
]'
```

The output will look like the following:

```
{
    "id": "abcd1234",
    "name": "MyAPI",
    "description": "My API with a new security policy",
    "createdDate": "2025-02-04T11:47:06-08:00",
    "apiKeySource": "HEADER",
    "endpointConfiguration": {
        "types": [

```

```
        "REGIONAL"
    ],
    "ipAddressType": "dualstack"
},
"tags": {},
"disableExecuteApiEndpoint": false,
"securityPolicy": "TLS_1_0",
"rootResourceId": "efg456"
}
```

IP address types for REST APIs in API Gateway

When you create an API, you specify the type of IP addresses that can invoke your API. You can choose IPv4 to resolve IPv4 addresses to invoke your API, or you can choose dualstack to allow both IPv4 and IPv6 addresses to invoke your API. We recommend that you set the IP address type to dualstack to alleviate IP space exhaustion or for your security posture. For more information about the benefits of a dualstack IP address type, see [IPv6 on AWS](#).

To restrict your API to only IPv6 traffic, you can create a resource policy and restrict the source IP addresses to only IPv6 ranges. You can change the IP address type by updating the API's configuration. This change will take effect immediately, and you don't need to redeploy your API. For more information, see [the section called “Example: Deny API traffic based on source IP address or range”](#)

Considerations for IP address types

The following considerations might impact your use of IP address types:

- The default IP address type for all Regional and edge-optimized APIs is IPv4.
- Private APIs can only have a dualstack IP address type.
- If you change the IP address type for an existing API from IPv4 to dualstack, confirm that any policies controlling access to your APIs have been updated to account for IPv6 calls. When you change the IP address type, the change takes effect immediately.
- If you migrate the endpoint type of an API from Regional or edge-optimized to private, API Gateway changes the IP address type to dualstack. For more information, see [the section called “Change a public or private API endpoint type”](#).
- If you migrate the endpoint type of an API from private to Regional, you must set the IP address type to dualstack. After the endpoint migration is complete, you can change the IP address type

to IPv4. For more information, see [the section called “Change a public or private API endpoint type”](#).

- Your API can be mapped to a custom domain name with a different IP address type than your API. If you disable your default API endpoint, this might affect how callers can invoke your API.
- You can't use an external definition file to configure your API's IP address type.

Change the IP address type of a REST API

You can change the IP address type by updating the API's configuration. You can update the API's configuration by using the AWS Management Console, the AWS CLI, CloudFormation, or an AWS SDK. If you change the API's IP address type, you don't redeploy your API for the changes to take effect. Before you change the IP address type, confirm that any policies controlling access to your APIs have been updated to account for IPv6 calls.

AWS Management Console

To change the IP address type of a REST API

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose a REST API.
3. Choose **API settings**, and then choose **Edit**.
4. For IP address type, select either **IPv4** or **Dualstack**.
5. Choose **Save changes**.

The change to your API's configuration will take effect immediately.

AWS CLI

The following [update-rest-api](#) command updates an API to have an IP address type of dualstack:

```
aws apigateway update-rest-api \
--rest-api-id abcd1234 \
--patch-operations "op='replace',path='/endpointConfiguration/
ipAddressType',value='dualstack'"
```

The output will look like the following:

```
{  
    "id": "abcd1234",  
    "name": "MyAPI",  
    "description": "My API with a dualstack IP address type",  
    "createdDate": "2025-02-04T11:47:06-08:00",  
    "apiKeySource": "HEADER",  
    "endpointConfiguration": {  
        "types": [  
            "REGIONAL"  
        ],  
        "ipAddressType": "dualstack"  
    },  
    "tags": {},  
    "disableExecuteApiEndpoint": false,  
    "rootResourceId": "efg456"  
}
```

Methods for REST APIs in API Gateway

In API Gateway, an API method embodies a [method request](#) and a [method response](#). You set up an API method to define what a client should or must do to submit a request to access the service at the backend and to define the responses that the client receives in return. For input, you can choose method request parameters, or an applicable payload, for the client to provide the required or optional data at run time. For output, you determine the method response status code, headers, and applicable body as targets to map the backend response data into, before they are returned to the client. To help the client developer understand the behaviors and the input and output formats of your API, you can [document your API](#) and [provide proper error messages](#) for [invalid requests](#).

An API method request is an HTTP request. To set up the method request, you configure an HTTP method (or verb), the path to an API [resource](#), headers, applicable query string parameters. You also configure a payload when the HTTP method is POST, PUT, or PATCH. For example, to retrieve a pet using the [PetStore sample API](#), you define the API method request of GET /pets/{petId}, where {petId} is a path parameter that can take a number at run time.

```
GET /pets/1  
Host: apigateway.us-east-1.amazonaws.com  
...  
...
```

If the client specifies an incorrect path, for example, /pet/1 or /pets/one instead of /pets/1, an exception is thrown.

An API method response is an HTTP response with a given status code. For a non-proxy integration, you must set up method responses to specify the required or optional targets of mappings. These transform integration response headers or body to associated method response headers or body. The mapping can be as simple as an [identity transform](#) that passes the headers or body through the integration as-is. For example, the following 200 method response shows an example of passthrough of a successful integration response as-is.

```
200 OK
Content-Type: application/json
...
{
    "id": "1",
    "type": "dog",
    "price": "$249.99"
}
```

In principle, you can define a method response corresponding to a specific response from the backend. Typically, this involves any 2XX, 4XX, and 5XX responses. However, this may not be practical, because often you may not know in advance all the responses that a backend may return. In practice, you can designate one method response as the default to handle the unknown or unmapped responses from the backend. It is good practice to designate the 500 response as the default. In any case, you must set up at least one method response for non-proxy integrations. Otherwise, API Gateway returns a 500 error response to the client even when the request succeeds at the backend.

To support a strongly typed SDK, such as a Java SDK, for your API, you should define the data model for input for the method request, and define the data model for output of the method response.

Prerequisites

Before setting up an API method, verify the following:

- You must have the method available in API Gateway. Follow the instructions in [Tutorial: Create a REST API with an HTTP non-proxy integration](#).

- If you want the method to communicate with a Lambda function, you must have already created the Lambda invocation role and Lambda execution role in IAM. You must also have created the Lambda function with which your method will communicate in AWS Lambda. To create the roles and function, use the instructions in [Create a Lambda function for Lambda non-proxy integration](#) of the [Choose an AWS Lambda integration tutorial](#).
- If you want the method to communicate with an HTTP or HTTP proxy integration, you must have already created, and have access to, the HTTP endpoint URL with which your method will communicate.
- Verify that your certificates for HTTP and HTTP proxy endpoints are supported by API Gateway. For details see [API Gateway-supported certificate authorities for HTTP and HTTP proxy integrations in API Gateway](#).

Topics

- [Set up a method request in API Gateway](#)
- [Set up a method response in API Gateway](#)
- [Set up a method using the API Gateway console](#)

Set up a method request in API Gateway

Setting up a method request involves performing the following tasks, after creating a [RestApi](#) resource:

1. Creating a new API or choosing an existing API [Resource](#) entity.
2. Creating an API [Method](#) resource that is a specific HTTP verb on the new or chosen API Resource. This task can be further divided into the following sub tasks:
 - Adding an HTTP method to the method request
 - Configuring request parameters
 - Defining a model for the request body
 - Enacting an authorization scheme
 - Enabling request validation

You can perform these tasks using the following methods:

- [API Gateway console](#)

- AWS CLI commands ([create-resource](#) and [put-method](#))
- AWS SDK functions (for example, in Node.js, [createResource](#) and [putMethod](#))
- API Gateway REST API ([resource:create](#) and [method:put](#)).

Topics

- [Set up API resources](#)
- [Set up an HTTP method](#)
- [Set up method request parameters](#)
- [Set up a method request model](#)
- [Set up method request authorization](#)
- [Set up method request validation](#)

Set up API resources

In an API Gateway API, you expose addressable resources as a tree of API [Resources](#) entities, with the root resource (/) at the top of the hierarchy. The root resource is relative to the API's base URL, which consists of the API endpoint and a stage name. In the API Gateway console, this base URI is referred to as the **Invoke URI** and is displayed in the API's stage editor after the API is deployed.

The API endpoint can be a default host name or a custom domain name. The default host name is of the following format:

`{api-id}.execute-api.{region}.amazonaws.com`

In this format, the `{api-id}` represents the API identifier that is generated by API Gateway. The `{region}` variable represents the AWS Region (for example, us-east-1) that you chose when creating the API. A custom domain name is any user-friendly name under a valid internet domain. For example, if you have registered an internet domain of example.com, any of *.example.com is a valid custom domain name. For more information, see [create a custom domain name](#).

For the [PetStore sample API](#), the root resource (/) exposes the pet store. The /pets resource represents the collection of pets available in the pet store. The /pets/{petId} exposes an individual pet of a given identifier (petId). The path parameter of {petId} is part of the request parameters.

To set up an API resource, you choose an existing resource as its parent and then create the child resource under this parent resource. You start with the root resource as a parent, add a resource to this parent, add another resource to this child resource as the new parent, and so on, to its parent identifier. Then you add the named resource to the parent.

The following [get-resources](#) command retrieves all the resources of an API:

```
aws apigateway get-resources --rest-api-id apiId
```

For the PetStore sample API, the output looks like the following:

```
{
  "items": [
    {
      "path": "/pets",
      "resourceMethods": {
        "GET": {}
      },
      "id": "6sxz2j",
      "pathPart": "pets",
      "parentId": "svzr2028x8"
    },
    {
      "path": "/pets/{petId}",
      "resourceMethods": {
        "GET": {}
      },
      "id": "rjkmth",
      "pathPart": "{petId}",
      "parentId": "6sxz2j"
    },
    {
      "path": "/",
      "id": "svzr2028x8"
    }
  ]
}
```

Each item lists the identifiers of the resource (`id`) and, except for the root resource, its immediate parent (`parentId`), as well as the resource name (`pathPart`). The root resource is special in that it does not have any parent. After choosing a resource as the parent, use the following command to add a child resource:

```
aws apigateway create-resource --rest-api-id apiId \  
  --parent-id parentId \  
  --path-part resourceName
```

For example, to add pet food for sale on the PetStore website, use the following command:

```
aws apigateway create-resource --rest-api-id a1b2c3 \  
  --parent-id svzr2028x8 \  
  --path-part food
```

The output will look like the following:

```
{  
  "path": "/food",  
  "pathPart": "food",  
  "id": "xdsvhp",  
  "parentId": "svzr2028x8"  
}
```

Use a proxy resource to streamline API setup

As business grows, the PetStore owner may decide to add food, toys, and other pet-related items for sale. To support this, you can add /food, /toys, and other resources under the root resource. Under each sale category, you may also want to add more resources, such as /food/{type}/{item}, /toys/{type}/{item}, etc. This can get tedious. If you decide to add a middle layer {subtype} to the resource paths to change the path hierarchy into /food/{type}/{subtype}/{item}, /toys/{type}/{subtype}/{item}, etc., the changes will break the existing API set up. To avoid this, you can use an API Gateway [proxy resource](#) to expose a set of API resources all at once.

API Gateway defines a proxy resource as a placeholder for a resource to be specified when the request is submitted. A proxy resource is expressed by a special path parameter of {proxy+}, often referred to as a greedy path parameter. The + sign indicates whichever child resources are appended to it. The /parent/{proxy+} placeholder stands for any resource matching the path pattern of /parent/*. You can use any string for the greedy path parameter name.

The following [create-resource](#) command creates a proxy resource under the root (/{{proxy}}):

```
aws apigateway create-resource --rest-api-id apiId \  
  --parent-id / \  
  --path-part {{proxy}}
```

```
--parent-id rootResourceId \
--path-part {proxy+}
```

The output will look like the following:

```
{
  "path": "/{proxy+}",
  "pathPart": "{proxy+}",
  "id": "234jdr",
  "parentId": "svzr2028x8"
}
```

For the PetStore API example, you can use `/{{proxy+}}` to represent both the `/pets` and `/pets/{petId}`. This proxy resource can also reference any other (existing or to-be-added) resources, such as `/food/{type}/{item}`, `/toys/{type}/{item}`, etc., or `/food/{type}/{subtype}/{item}`, `/toys/{type}/{subtype}/{item}`, etc. The backend developer determines the resource hierarchy and the client developer is responsible for understanding it. API Gateway simply passes whatever the client submitted to the backend.

An API can have more than one proxy resource. For example, the following proxy resources are allowed within an API, assuming `/parent/{{proxy+}}` is not the same parent as `/parent/{child}/{proxy+}`.

```
/{proxy+}
/parent/{proxy+}
/parent/{child}/{proxy+}
```

When a proxy resource has non-proxy siblings, the sibling resources are excluded from the representation of the proxy resource. For the preceding examples, `/{proxy+}` refers to any resources under the root resource except for the `/parent/*` resources. In other words, a method request against a specific resource takes precedence over a method request against a generic resource at the same level of the resource hierarchy.

The following table shows how API Gateway routes requests to the following resources for the prod stage of an API.

Method	URI Pattern
ANY	<code>/{proxy+}</code>
GET	<code>/pets/{proxy+}</code>
GET	<code>/pets/dog</code>

Request	Selected route	Explanation
GET https:// <i>api-id</i> .execute-api. <i>region</i> .amazonaws.com/prod/pets/dog	GET /pets/dog	The request fully matches this resource.
GET https:// <i>api-id</i> .execute-api. <i>region</i> .amazonaws.com/prod/pets/cats	GET /pets/{proxy+}	The /pets/{proxy+} greedy path variable catches this request.
GET https:// <i>api-id</i> .execute-api. <i>region</i> .amazonaws.com/prod/animals	GET /{proxy+}	The /{proxy+} greedy path variable catches this request.

A proxy resource cannot have any child resource. Any API resource after {proxy+} is redundant and ambiguous. The following proxy resources are not allowed within an API.

```
{proxy+}/child
/parent/{proxy+}/{child}
/parent/{child}/{proxy+}/{grandchild+}
```

Set up an HTTP method

An API method request is encapsulated by the API Gateway [Method](#) resource. To set up the method request, you must first instantiate the Method resource, setting at least an HTTP method and an authorization type on the method.

Closely associated with the proxy resource, API Gateway supports an HTTP method of ANY. This ANY method represents any HTTP method that is to be supplied at run time. It allows you to use a single API method setup for all of the supported HTTP methods of DELETE, GET, HEAD, OPTIONS, PATCH, POST, and PUT.

You can set up the ANY method on a non-proxy resource as well. Combining the ANY method with a proxy resource, you get a single API method setup for all of the supported HTTP methods against

any resources of an API. Furthermore, the backend can evolve without breaking the existing API setup.

Before setting up an API method, consider who can call the method. Set the authorization type according to your plan. For open access, set it to NONE. To use IAM permissions, set the authorization type to AWS_IAM. To use a Lambda authorizer function, set this property to CUSTOM. To use an Amazon Cognito user pool, set the authorization type to COGNITO_USER_POOLS.

The following [put-method](#) command creates a method request for the ANY verb using IAM permissions to control its access.

```
aws apigateway put-method --rest-api-id vaz7da96z6 \
    --resource-id 6sxz2j \
    --http-method ANY \
    --authorization-type AWS_IAM
```

To create an API method request with a different authorization type, see [the section called “Set up method request authorization”](#).

Set up method request parameters

Method request parameters are a way for a client to provide input data or execution context necessary to complete the method request. A method parameter can be a path parameter, a header, or a query string parameter. As part of method request setup, you must declare required request parameters to make them available for the client. For non-proxy integration, you can translate these request parameters to a form that is compatible with the backend requirement.

For example, for the GET /pets/{petId} method request, the {petId} path variable is a required request parameter. You can declare this path parameter when calling the put-method command of the AWS CLI. The following [put-method](#) command creates a method with a required path parameter:

```
aws apigateway put-method --rest-api-id vaz7da96z6 \
    --resource-id rjkmth \
    --http-method GET \
    --authorization-type "NONE" \
    --request-parameters method.request.path.petId=true
```

If a parameter is not required, you can set it to false in `request-parameters`. For example, if the GET /pets method uses an optional query string parameter of type, and an optional header parameter of age, you can declare them using the following [put-method](#) command:

```
aws apigateway put-method --rest-api-id vaz7da96z6 \
    --resource-id 6sxz2j \
    --http-method GET \
    --authorization-type "NONE" \
    --request-parameters
method.request.querystring.type=false,method.request.header.age=false
```

Instead of this abbreviated form, you can use a JSON string to set the `request-parameters` value:

```
'{"method.request.querystring.type":false,"method.request.header.age":false}'
```

With this setup, the client can query pets by type:

```
GET /pets?type=dog
```

And the client can query dogs who are puppies as follows:

```
GET /pets?type=dog
age:puppy
```

For information on how to map method request parameters to integration request parameters, see [the section called “Integrations”](#).

Set up a method request model

For an API method that can take input data in a payload, you can use a model. A model is expressed in a [JSON schema draft 4](#) and describes the data structure of the request body. With a model, a client can determine how to construct a method request payload as input. More importantly, API Gateway uses the model to [validate a request](#), [generate an SDK](#), and initialize a mapping template for setting up the integration in the API Gateway console. For information about how to create a [model](#), see [Understanding data models](#).

Depending on the content types, a method payload can have different formats. A model is indexed against the media type of the applied payload. API Gateway uses the Content-Type request

header to determine the content type. To set up method request models, add key-value pairs of the "*media-type*": "*model-name*" format to the `requestModels` map when calling the AWS CLI `put-method` command.

To use the same model regardless of the content type, specify `$default` as the key.

For example, to set a model on the JSON payload of the `POST /pets` method request of the PetStore example API, you can use the following [put-method](#) command:

```
aws apigateway put-method \
--rest-api-id vaz7da96z6 \
--resource-id 6szz2j \
--http-method POST \
--authorization-type "NONE" \
--request-models '{"application/json":"petModel"}'
```

Here, `petModel` is the name property value of a [Model](#) resource describing a pet. The actual schema definition is expressed as a JSON string value of the [schema](#) property of the Model resource.

In a Java, or other strongly typed SDK, of the API, the input data is cast as the `petModel` class derived from the schema definition. With the request model, the input data in the generated SDK is cast into the `Empty` class, which is derived from the default `Empty` model. In this case, the client cannot instantiate the correct data class to provide the required input.

Set up method request authorization

To control who can call the API method, you can configure the [authorization type](#) on the method. You can use this type to enact one of the supported authorizers, including IAM roles and policies (`AWS_IAM`), an Amazon Cognito user pool (`COGNITO_USER_POOLS`), or a Lambda authorizer (`CUSTOM`).

To use IAM permissions to authorize access to the API method, set the `authorization-type` input property to `AWS_IAM`. When you set this option, API Gateway verifies the caller's signature on the request based on the caller's credentials. If the verified user has permission to call the method, it accepts the request. Otherwise, it rejects the request and the caller receives an unauthorized error response. The call to the method doesn't succeed unless the caller has permission to invoke the API method. The following IAM policy grants permission to the caller to call any API methods created within the same AWS account:

JSON

```
{  
    "Version": "2012-10-17",  
    "Statement": [  
        {  
            "Effect": "Allow",  
            "Action": [  
                "execute-api:Invoke"  
            ],  
            "Resource": "arn:aws:execute-api:*:*:  
        }  
    ]  
}
```

For more information, see [the section called “Use IAM permissions”](#).

Currently, you can only grant this policy to the users, groups, and roles within the API owner's AWS account. Users from a different AWS account can call the API methods only if allowed to assume a role within the API owner's AWS account with the necessary permissions to call the execute-api:Invoke action. For information on cross-account permissions, see [Using IAM Roles](#).

You can use AWS CLI, an AWS SDK, or a REST API client, such as [Postman](#), which implements [Signature Version 4 \(SigV4\) signing](#).

To use a Lambda authorizer to authorize access to the API method, set the authorization-type input property to CUST0M and set the [authorizer-id](#) input property to the [id](#) property value of a Lambda authorizer that already exists. The referenced Lambda authorizer can be of the TOKEN or REQUEST type. For information about creating a Lambda authorizer, see [the section called “Use Lambda authorizers”](#).

To use an Amazon Cognito user pool to authorize access to the API method, set the authorization-type input property to COGNITO_USER_POOLS and set the [authorizer-id](#) input property to the [id](#) property value of the COGNITO_USER_POOLS authorizer that was already created. For information about creating an Amazon Cognito user pool authorizer, see [the section called “Use Amazon Cognito user pool as authorizer for a REST API”](#).

Set up method request validation

You can enable request validation when setting up an API method request. You need to first create a [request validator](#). The following [create-request-validator](#) command creates a body-only request validator.

```
aws apigateway create-request-validator \
--rest-api-id 7zw9uyk9kl \
--name bodyOnlyValidator \
--validate-request-body \
--no-validate-request-parameters
```

The output will look like the following:

```
{
  "validateRequestParameters": false,
  "validateRequestBody": true,
  "id": "jgpyy6",
  "name": "bodyOnlyValidator"
}
```

You can use this request validator, to use request validation as part of the method request setup. The following [put-method](#) command creates a method request that requires the incoming request body to match the PetModel and has two request parameter that aren't required:

```
aws apigateway put-method \
--rest-api-id 7zw9uyk9kl \
--resource-id xdsvhp \
--http-method PUT \
--authorization-type "NONE" \
--request-parameters '{"method.request.querystring.type": false,
"method.request.querystring.page":false}' \
--request-models '{"application/json":"petModel"}' \
--request-validator-id jgpyy6
```

To include a request parameter in the request validation, you must set `validateRequestParameters` to `true` for the request validator, and set the specific request parameter to `true` in the `put-method` command.

Set up a method response in API Gateway

An API method response encapsulates the output of an API method request that the client will receive. The output data includes an HTTP status code, some headers, and possibly a body.

With non-proxy integrations, the specified response parameters and body can be mapped from the associated integration response data or can be assigned certain static values according to mappings. These mappings are specified in the integration response. The mapping can be an identical transformation that passes the integration response through as-is.

With a proxy integration, API Gateway passes the backend response through to the method response automatically. There is no need for you to set up the API method response. However, with the Lambda proxy integration, the Lambda function must return a result of [this output format](#) for API Gateway to successfully map the integration response to a method response.

Programmatically, the method response setup amounts to creating a [MethodResponse](#) resource of API Gateway and setting the properties of [statusCode](#), [responseParameters](#), and [responseModels](#).

When setting status codes for an API method, you should choose one as the default to handle any integration response of an unanticipated status code. It is reasonable to set 500 as the default because this amounts to casting otherwise unmapped responses as a server-side error. For instructional reasons, the API Gateway console sets the 200 response as the default. But you can reset it to the 500 response.

To set up a method response, you must have created the method request.

Set up method response status code

The status code of a method response defines a type of response. For example, responses of 200, 400, and 500 indicate successful, client-side error and server-side error responses, respectively.

To set up a method response status code, set the [statusCode](#) property to an HTTP status code. The following [put-method-response](#) command creates 200 method response.

```
aws apigateway put-method-response \
--rest-api-id vaz7da96z6 \
--resource-id 6sxz2j \
--http-method GET \
--status-code 200
```

Set up method response parameters

Method response parameters define which headers the client receives in response to the associated method request. Response parameters also specify a target to which API Gateway maps an integration response parameter, according to mappings prescribed in the API method's integration response.

To set up the method response parameters, add to the [responseParameters](#) map of MethodResponse key-value pairs of the "{parameter-name}": "{boolean}" format. The following [put-method-response](#) command sets the my-header header.

```
aws apigateway put-method-response \
--rest-api-id vaz7da96z6 \
--resource-id 6sxz2j \
--http-method GET \
--status-code 200 \
--response-parameters method.response.header.my-header=false
```

Set up method response models

A method response model defines a format of the method response body. Setting up a method response model is necessary when you generate a strongly typed SDK for the API. It ensures that the output is cast into an appropriate class in Java or Objective-C. In other cases, setting a model is optional.

Before setting up the response model, you must first create the model in API Gateway. To do so, you can call the [create-model](#) command. The following [create-model](#) command creates PetStorePet model to describe the body of the response to the GET /pets/{petId} method request.

```
aws apigateway create-model \
--rest-api-id vaz7da96z6 \
--content-type application/json \
--name PetStorePet \
--schema '{ \
    "$schema": "http://json-schema.org/draft-04/schema#", \
    "title": "PetStorePet", \
    "type": "object", \
    "properties": { \
        "id": { "type": "number" }, \
        "name": { "type": "string" }, \
        "category": { "type": "string" }, \
        "tags": [ { "type": "string" } ], \
        "photoUrl": { "type": "string" } \
    } \
}'
```

```
"type": { "type": "string" }, \
"price": { "type": "number" } \
} \
}'
```

The result is created as an API Gateway [Model](#) resource.

To set up the method response models to define the payload format, add the "application/json":"PetStorePet" key-value pair to the [requestModels](#) map of [MethodResponse](#) resource. The following [put-method-response](#) command creates a method response that uses a response model to define the payload format:

```
aws apigateway put-method-response \
--rest-api-id vaz7da96z6 \
--resource-id 6sxz2j \
--http-method GET \
--status-code 200 \
--response-parameters method.response.header.my-header=false \
--response-models '{"application/json":"PetStorePet"}'
```

Set up a method using the API Gateway console

When you create a method using the REST API console, you configure both the integration request and the method request. By default, API Gateway creates the 200 method response for your method.

The following instructions show how to edit the method request settings and how to create additional method responses for your method.

Topics

- [Edit an API Gateway method request in the API Gateway console](#)
- [Set up an API Gateway method response using the API Gateway console](#)

Edit an API Gateway method request in the API Gateway console

These instructions assume you have already created your method request. For more information on how to create a method, see [the section called “ Set up integration request using the console”](#).

1. In the **Resources** pane, choose your method, and then choose the **Method request** tab.

2. In the **Method request settings** section, choose **Edit**.
3. For **Authorization**, select an available authorizer.
 - a. To enable open access to the method for any user, select **None**. This step can be skipped if the default setting has not been changed.
 - b. To use IAM permissions to control the client access to the method, select **AWS_IAM**. With this choice, only users of the IAM roles with the correct IAM policy attached are allowed to call this method.

To create the IAM role, specify an access policy with a format like the following:

JSON

```
{  
    "Version": "2012-10-17",  
    "Statement": [  
        {  
            "Effect": "Allow",  
            "Action": [  
                "execute-api:Invoke"  
            ],  
            "Resource": [  
                "arn:aws:execute-api:us-east-1:111111111111:aaabbb/*/GET/"  
            ]  
        }  
    ]  
}
```

In this access policy, `arn:aws:execute-api:us-east-1:111111111111:aaabbb/*/GET/` is the ARN of your method. You can find the ARN of your method by selecting the method on the **Resources** page. For more information about setting the IAM permissions, see [Control access to a REST API with IAM permissions](#).

To create the IAM role, you can adapt the instructions in the following tutorial, [???](#).

- c. To use a Lambda authorizer, select a token or a request authorizer. Create the Lambda authorizer to have this choice displayed in the dropdown menu. For information on how to create a Lambda authorizer, see [Use API Gateway Lambda authorizers](#).

- d. To use an Amazon Cognito user pool, choose an available user pool under **Cognito user pool authorizers**. Create a user pool in Amazon Cognito and an Amazon Cognito user pool authorizer in API Gateway to have this choice displayed in the dropdown menu. For information on how to create an Amazon Cognito user pool authorizer, see [Control access to REST APIs using Amazon Cognito user pools as an authorizer](#).
4. To specify request validation, select a value from the **Request Validator** dropdown menu. To turn off request validation, select **None**. For more information about each option, see [Request validation for REST APIs in API Gateway](#).
5. Select **API key required** to require an API key. When enabled, API keys are used in [usage plans](#) to throttle client traffic.
6. (Optional) To assign an operation name in a Java SDK of this API, generated by API Gateway, for **Operation name**, enter a name. For example, for the method request of GET /pets/{petId}, the corresponding Java SDK operation name is, by default, GetPetsPetId. This name is constructed from the method's HTTP verb (GET) and the resource path variable names (Pets and PetId). If you set the operation name as getPetById, the SDK operation name becomes GetPetById.
7. To add a query string parameter to the method, do the following:
 - a. Choose **URL Query string parameters**, and then choose **Add query string**.
 - b. For **Name**, enter the name of the query string parameter.
 - c. Select **Required** if the newly created query string parameter is to be used for request validation. For more information about the request validation, see [Request validation for REST APIs in API Gateway](#).
 - d. Select **Caching** if the newly created query string parameter is to be used as part of a caching key. For more information about caching, see [Use method or integration parameters as cache keys to index cached responses](#).

To remove the query string parameter, choose **Remove**.

8. To add a header parameter to the method, do the following:
 - a. Choose **HTTP request headers**, and then choose **Add header**.
 - b. For **Name**, enter the name of the header.
 - c. Select **Required** if the newly created header is to be used for request validation. For more information about the request validation, see [Request validation for REST APIs in API Gateway](#).

- d. Select **Caching** if the newly created header is to be used as part of a caching key. For more information about caching, see [Use method or integration parameters as cache keys to index cached responses](#).

To remove the header, choose **Remove**.

9. To declare the payload format of a method request with the POST, PUT, or PATCH HTTP verb, choose **Request body**, and do the following:
 - a. Choose **Add model**.
 - b. For **Content-type**, enter a MIME-type (for example, application/json).
 - c. For **Model**, select a model from the dropdown menu. The currently available models for the API include the default Empty and Error models as well as any models you have created and added to the [Models](#) collection of the API. For more information about creating a model, see [Data models for REST APIs](#).

 **Note**

The model is useful to inform the client of the expected data format of a payload. It is helpful to generate a skeletal mapping template. It is important to generate a strongly typed SDK of the API in such languages as Java, C#, Objective-C, and Swift. It is only required if request validation is enabled against the payload.

10. Choose **Save**.

Set up an API Gateway method response using the API Gateway console

An API method can have one or more responses. Each response is indexed by its HTTP status code. By default, the API Gateway console adds 200 response to the method responses. You can modify it, for example, to have the method return 201 instead. You can add other responses, for example, 409 for access denial and 500 for uninitialized stage variables used.

To use the API Gateway console to modify, delete, or add a response to an API method, follow these instructions.

1. In the **Resources** pane, choose your method, and then choose the **Method response** tab. You might need to choose the right arrow button to show the tab.
2. In the **Method response settings** section, choose **Create response**.

3. For **HTTP status code**, enter an HTTP status code such as 200, 400, or 500.

When a backend-returned response does not have a corresponding method response defined, API Gateway fails to return the response to the client. Instead, it returns a 500 Internal server error error response.

4. Choose **Add header**.
5. For **Header name**, enter a name.

To return a header from the backend to the client, add the header in the method response.

6. Choose **Add model** to define a format of the method response body.

Enter the media type of the response payload for **Content type** and choose a model from the **Models** dropdown menu.

7. Choose **Save**.

To modify an existing response, navigate to your method response, and then choose **Edit**. To change the **HTTP status code**, choose **Delete** and create a new method response.

For every response returned from the backend, you must have a compatible response configured as the method response. However, the configuring method response headers and payload model are optional unless you map the result from the backend to the method response before returning to the client. Also, a method response payload model is important if you are generating a strongly typed SDK for your API.

Control and manage access to REST APIs in API Gateway

API Gateway supports multiple mechanisms for controlling and managing access to your API.

You can use the following mechanisms for authentication and authorization:

- **Resource policies** let you create resource-based policies to allow or deny access to your APIs and methods from specified source IP addresses or VPC endpoints. For more information, see [the section called "Use API Gateway resource policies"](#).
- **Standard AWS IAM roles and policies** offer flexible and robust access controls that can be applied to an entire API or individual methods. IAM roles and policies can be used for controlling who can create and manage your APIs, as well as who can invoke them. For more information, see [the section called "Use IAM permissions"](#).

- **IAM tags** can be used together with IAM policies to control access. For more information, see [the section called “Attribute-based access control”](#).
- **Endpoint policies for interface VPC endpoints** allow you to attach IAM resource policies to interface VPC endpoints to improve the security of your [private APIs](#). For more information, see [the section called “Use VPC endpoint policies for private APIs”](#).
- **Lambda authorizers** are Lambda functions that control access to REST API methods using bearer token authentication—as well as information described by headers, paths, query strings, stage variables, or context variables request parameters. Lambda authorizers are used to control who can invoke REST API methods. For more information, see [the section called “Use Lambda authorizers”](#).
- **Amazon Cognito user pools** let you create customizable authentication and authorization solutions for your REST APIs. Amazon Cognito user pools are used to control who can invoke REST API methods. For more information, see [the section called “Use Amazon Cognito user pool as authorizer for a REST API”](#).

You can use the following mechanisms for performing other tasks related to access control:

- **Cross-origin resource sharing (CORS)** lets you control how your REST API responds to cross-domain resource requests. For more information, see [the section called “CORS”](#).
- **Client-side SSL certificates** can be used to verify that HTTP requests to your backend system are from API Gateway. For more information, see [the section called “Client certificates”](#).
- **AWS WAF** can be used to protect your API Gateway API from common web exploits. For more information, see [the section called “AWS WAF”](#).

You can use the following mechanisms for tracking and limiting the access that you have granted to authorized clients:

- **Usage plans** let you provide **API keys** to your customers—and then track and limit usage of your API stages and methods for each API key. For more information, see [the section called “Usage plans”](#).

Control access to a REST API with API Gateway resource policies

Amazon API Gateway *resource policies* are JSON policy documents that you attach to an API to control whether a specified principal (typically an IAM role or group) can invoke the API. You can use API Gateway resource policies to allow your API to be securely invoked by:

- Users from a specified AWS account.
- Specified source IP address ranges or CIDR blocks.
- Specified virtual private clouds (VPCs) or VPC endpoints (in any account).

You can attach a resource policy for any API endpoint type in API Gateway by using the AWS Management Console, AWS CLI, or AWS SDKs. For [private APIs](#), you can use resource policies together with VPC endpoint policies to control which principals have access to which resources and actions. For more information, see [the section called “Use VPC endpoint policies for private APIs”](#).

API Gateway resource policies are different from IAM identity-based policies. IAM identity-based policies are attached to IAM users, groups, or roles and define what actions those identities are capable of doing on which resources. API Gateway resource policies are attached to resources. You can use API Gateway resource policies together with IAM policies. For more information, see [Identity-Based Policies and Resource-Based Policies](#).

Topics

- [Access policy language overview for Amazon API Gateway](#)
- [How API Gateway resource policies affect authorization workflow](#)
- [API Gateway resource policy examples](#)
- [Create and attach an API Gateway resource policy to an API](#)
- [AWS condition keys that can be used in API Gateway resource policies](#)

Access policy language overview for Amazon API Gateway

This page describes the basic elements used in Amazon API Gateway resource policies.

Resource policies are specified using the same syntax as IAM policies. For complete policy language information, see [Overview of IAM Policies](#) and [AWS Identity and Access Management Policy Reference](#) in the *IAM User Guide*.

For information about how an AWS service decides whether a given request should be allowed or denied, see [Determining Whether a Request is Allowed or Denied](#).

Common elements in an access policy

In its most basic sense, a resource policy contains the following elements:

- **Resources** – APIs are the Amazon API Gateway resources for which you can allow or deny permissions. In a policy, you use the Amazon Resource Name (ARN) to identify the resource. You can also use abbreviated syntax, which API Gateway automatically expands to the full ARN when you save a resource policy. To learn more, see [API Gateway resource policy examples](#).

For the format of the full Resource element, see [Resource format of permissions for executing API in API Gateway](#).

- **Actions** – For each resource, Amazon API Gateway supports a set of operations. You identify resource operations that you will allow (or deny) by using action keywords.

For example, the `execute-api:Invoke` permission will allow the user permission to invoke an API upon a client request.

For the format of the Action element, see [Action format of permissions for executing API in API Gateway](#).

- **Effect** – What the effect is when the user requests the specific action—this can be either Allow or Deny. You can also explicitly deny access to a resource, which you might do in order to make sure that a user cannot access it, even if a different policy grants access.

 **Note**

"Implicit deny" is the same thing as "deny by default".

An "implicit deny" is different from an "explicit deny". For more information, see [The Difference Between Denying by Default and Explicit Deny](#).

- **Principal** – The account or user allowed access to the actions and resources in the statement. In a resource policy, the principal is the user or account who receives this permission.

The following example resource policy shows the previous common policy elements. The policy grants access to the API under the specified `account-id` in the specified `region` to any user

whose source IP address is in the address block **123.4.5.6/24**. The policy denies all access to the API if the user's source IP is not within the range.

JSON

```
{  
    "Version": "2012-10-17",  
    "Statement": [  
        {  
            "Effect": "Allow",  
            "Principal": "*",  
            "Action": "execute-api:Invoke",  
            "Resource": "arn:aws:execute-api:us-east-1:111111111111:*"  
        },  
        {  
            "Effect": "Deny",  
            "Principal": "*",  
            "Action": "execute-api:Invoke",  
            "Resource": "arn:aws:execute-api:us-east-1:111111111111:*",  
            "Condition": {  
                "NotIpAddress": {  
                    "aws:SourceIp": "123.4.5.6/24"  
                }  
            }  
        }  
    ]  
}
```

How API Gateway resource policies affect authorization workflow

When API Gateway evaluates the resource policy attached to your API, the result is affected by the authentication type that you have defined for the API, as illustrated in the flowcharts in the following sections.


Topics

- [API Gateway resource policy only](#)
- [Lambda authorizer and resource policy](#)
- [IAM authentication and resource policy](#)
- [Amazon Cognito authentication and resource policy](#)

- [Policy evaluation outcome tables](#)

API Gateway resource policy only

In this workflow, an API Gateway resource policy is attached to the API, but no authentication type is defined for the API. Evaluation of the policy involves seeking an explicit allow based on the inbound criteria of the caller. An implicit denial or any explicit denial results in denying the caller.



The following is an example of such a resource policy.

JSON


```
{
```

```
"Version": "2012-10-17",
"Statement": [
    {
        "Effect": "Allow",
        "Principal": "*",
        "Action": "execute-api:Invoke",
        "Resource": "arn:aws:execute-api:us-east-1:111111111111:api-id/",
        "Condition": {
            "IpAddress": {
                "aws:SourceIp": ["192.0.2.0/24", "198.51.100.0/24"]
            }
        }
    }
]
```

Lambda authorizer and resource policy

In this workflow, a Lambda authorizer is configured for the API in addition to a resource policy. The resource policy is evaluated in two phases. Before calling the Lambda authorizer, API Gateway first evaluates the policy and checks for any explicit denials. If found, the caller is denied access immediately. Otherwise, the Lambda authorizer is called, and it returns a [policy document](#), which is evaluated in conjunction with the resource policy. If your authorizer uses caching, API Gateway might return the cached policy document. The result is determined based on [Table A](#).

The following example resource policy allows calls only from the VPC endpoint whose VPC endpoint ID is *vpc-e-1a2b3c4d*. During the "pre-auth" evaluation, only the calls coming from the VPC endpoint indicated in the example are allowed to move forward and evaluate the Lambda authorizer. All remaining calls are blocked. This authorization workflow is the same if you use a custom domain name for a private API.



JSON


```
{  
    "Version": "2012-10-17",  
    "Statement": [  
        {  
            "Effect": "Deny",  
            "Principal": "*",  
            "Action": "execute-api:Invoke",  
            "Resource": [  
                "arn:aws:execute-api:us-east-1:111111111111:api-id/"  
            ],  
            "Condition" : {  
                "StringNotEquals": {  
                    "aws:SourceVpce": "vpce-1a2b3c4d"  
                }  
            }  
        }  
    ]  
}
```

IAM authentication and resource policy

In this workflow, you configure IAM authentication for the API in addition to a resource policy. After you authenticate the user with the IAM service, the API evaluates both the policies attached to the user and the resource policy. The outcome varies based on whether the caller is in the same AWS account or a separate AWS account, from the API owner.

If the caller and API owner are from separate accounts, both the IAM policies and the resource policy explicitly allow the caller to proceed. For more information, see [Table B](#).

However, if the caller and the API owner are in the same AWS account, then either the IAM user policies or the resource policy must explicitly allow the caller to proceed. For more information, see [Table A](#).



The following is an example of a cross-account resource policy. Assuming the IAM policy contains an allow effect, this resource policy allows calls only from the VPC whose VPC ID is [vpc-2f09a348](#). For more information, see [Table B](#).


JSON

```
{
  "Version": "2012-10-17",
  "Statement": [
    {
      "Effect": "Allow",
      "Principal": "*",
      "Action": "execute-api:Invoke",
      "Resource": "arn:aws:execute-api:::///"
    }
  ]
}
```

```
        "Effect": "Allow",
        "Principal": "*",
        "Action": "execute-api:Invoke",
        "Resource": [
            "arn:aws:execute-api:us-east-1:111111111111:api-id/"
        ],
        "Condition" : {
            "StringEquals": {
                "aws:SourceVpc": "vpc-2f09a348"
            }
        }
    ]
}
```

Amazon Cognito authentication and resource policy

In this workflow, an [Amazon Cognito user pool](#) is configured for the API in addition to a resource policy. API Gateway first attempts to authenticate the caller through Amazon Cognito. This is typically performed through a [JWT token](#) that is provided by the caller. If authentication is successful, the resource policy is evaluated independently, and an explicit allow is required. A deny or "neither allow or deny" results in a deny. The following is an example of a resource policy that might be used together with Amazon Cognito user pools.



The following is an example of a resource policy that allows calls only from specified source IPs, assuming that the Amazon Cognito authentication token contains an allow. For more information, see [Table B](#).

JSON

```
{  
    "Version": "2012-10-17",  
    "Statement": [  
        {  
            "Effect": "Allow",  
            "Principal": "*",  
            "Action": "execute-api:Invoke",  
            "Resource": "arn:aws:execute-api:us-east-1:111111111111:api-id/",  
            "Condition": {  
                "IpAddress": {  
                    "aws:SourceIp": ["192.0.2.0/24", "198.51.100.0/24"]  
                }  
            }  
        }  
    ]  
}
```

Policy evaluation outcome tables

Table A lists the resulting behavior when access to an API Gateway API is controlled by an IAM policy or a Lambda authorizer and an API Gateway resource policy, both of which are in the same AWS account.

IAM policy (or Lambda authorizer)	API Gateway resource policy	Resulting behavior
Allow	Allow	Allow
Allow	Neither Allow nor Deny	Allow
Allow	Deny	Explicit Deny
Neither Allow nor Deny	Allow	Allow

IAM policy (or Lambda authorizer)	API Gateway resource policy	Resulting behavior
Neither Allow nor Deny	Neither Allow nor Deny	Implicit Deny
Neither Allow nor Deny	Deny	Explicit Deny
Deny	Allow	Explicit Deny
Deny	Neither Allow nor Deny	Explicit Deny
Deny	Deny	Explicit Deny

Table B lists the resulting behavior when access to an API Gateway API is controlled by an IAM policy or a Amazon Cognito user pools authorizer and an API Gateway resource policy, which are in different AWS accounts. If either is silent (neither allow nor deny), cross-account access is denied. This is because cross-account access requires that both the resource policy and the IAM policy or Amazon Cognito user pools authorizer explicitly grant access.

IAM policy (or Amazon Cognito user pools authorizer)	API Gateway resource policy	Resulting behavior
Allow	Allow	Allow
Allow	Neither Allow nor Deny	Implicit Deny
Allow	Deny	Explicit Deny
Neither Allow nor Deny	Allow	Implicit Deny
Neither Allow nor Deny	Neither Allow nor Deny	Implicit Deny
Neither Allow nor Deny	Deny	Explicit Deny
Deny	Allow	Explicit Deny
Deny	Neither Allow nor Deny	Explicit Deny

IAM policy (or Amazon Cognito user pools authorizer)	API Gateway resource policy	Resulting behavior
Deny	Deny	Explicit Deny

API Gateway resource policy examples

This page presents a few examples of typical use cases for API Gateway resource policies.

The following example policies use a simplified syntax to specify the API resource. This simplified syntax is an abbreviated way that you can refer to an API resource, instead of specifying the full Amazon Resource Name (ARN). API Gateway converts the abbreviated syntax to the full ARN when you save the policy. For example, you can specify the resource `execute-api:/stage-name/GET/pets` in a resource policy. API Gateway converts the resource to `arn:aws:execute-api:us-east-2:123456789012:aabbccdde/stage-name/GET/pets` when you save the resource policy. API Gateway builds the full ARN by using the current Region, your AWS account ID, and the ID of the REST API that the resource policy is associated with. You can use `execute-api:/*` to represent all stages, methods, and paths in the current API. For information about access policy language, see [Access policy language overview for Amazon API Gateway](#).

Topics

- [Example: Allow roles in another AWS account to use an API](#)
- [Example: Deny API traffic based on source IP address or range](#)
- [Example: Deny API traffic based on source IP address or range when using a private API](#)
- [Example: Allow private API traffic based on source VPC or VPC endpoint](#)

Example: Allow roles in another AWS account to use an API

The following example resource policy grants API access in one AWS account to two roles in a different AWS account via [Signature Version 4](#) (SigV4) or [Signature Version 4a](#) (SigV4a) protocols. Specifically, the developer and the administrator role for the AWS account identified by `account-id-2` are granted the `execute-api:Invoke` action to execute the `GET` action on the `pets` resource (API) in your AWS account.

JSON

```
{  
    "Version": "2012-10-17",  
    "Statement": [  
        {  
            "Effect": "Allow",  
            "Principal": {  
                "AWS": [  
                    "arn:aws:iam::1112222333:role/developer",  
                    "arn:aws:iam::1112222333:role/Admin"  
                ]  
            },  
            "Action": "execute-api:Invoke",  
            "Resource": [  
                "execute-api:/stage/GET/pets"  
            ]  
        }  
    ]  
}
```

Example: Deny API traffic based on source IP address or range

The following example resource policy denies (blocks) incoming traffic to an API from two specified source IP address blocks.

JSON

```
{  
    "Version": "2012-10-17",  
    "Statement": [  
        {  
            "Effect": "Allow",  
            "Principal": "*",  
            "Action": "execute-api:Invoke",  
            "Resource": [  
                "execute-api:/*"  
            ]  
        },  
        {  
            "Effect": "Deny",  
            "Principal": "*",  
            "Action": "execute-api:Invoke",  
            "Resource": [  
                "execute-api:/*"  
            ]  
        }  
    ]  
}
```

```
        "Principal": "*",
        "Action": "execute-api:Invoke",
        "Resource": [
            "execute-api:/*"
        ],
        "Condition" : {
            "IpAddress": {
                "aws:SourceIp": ["192.0.2.0/24", "198.51.100.0/24"]
            }
        }
    ]
}
```

If you use any IAM user policies or API Gateway resource policies to control access to API Gateway or any API Gateway APIs, confirm that your policies are updated to include IPv6 address ranges. Policies that aren't updated to handle IPv6 addresses might impact client's access to API Gateway when they start using the dualstack endpoint. For more information, see [the section called "Using IPv6 addresses in IAM policies"](#).

Example: Deny API traffic based on source IP address or range when using a private API

The following example resource policy denies (blocks) incoming traffic to a private API from two specified source IP address blocks. When using private APIs, the VPC endpoint for execute-api re-writes the original source IP address. The aws:VpcSourceIp condition filters the request against the original requester IP address.

JSON

```
{
    "Version":"2012-10-17",
    "Statement": [
        {
            "Effect": "Allow",
            "Principal": "*",
            "Action": "execute-api:Invoke",
            "Resource": [
                "execute-api:/*"
            ]
        },
        {
            "Effect": "Deny",
            "Principal": "*",
            "Action": "execute-api:Invoke",
            "Resource": [
                "execute-api:/*"
            ],
            "Condition": {
                "aws:VpcSourceIp": ["192.0.2.0/24", "198.51.100.0/24"]
            }
        }
    ]
}
```

```
        "Effect": "Deny",
        "Principal": "*",
        "Action": "execute-api:Invoke",
        "Resource": [
            "execute-api:/*"
        ],
        "Condition" : {
            "IpAddress": {
                "aws:VpcSourceIp": ["192.0.2.0/24", "198.51.100.0/24"]
            }
        }
    }
]
```

Example: Allow private API traffic based on source VPC or VPC endpoint

The following example resource policies allow incoming traffic to a private API only from a specified virtual private cloud (VPC) or VPC endpoint.

This example resource policy specifies a source VPC:

JSON

```
{
    "Version":"2012-10-17",
    "Statement": [
        {
            "Effect": "Allow",
            "Principal": "*",
            "Action": "execute-api:Invoke",
            "Resource": [
                "execute-api:/*"
            ]
        },
        {
            "Effect": "Deny",
            "Principal": "*",
            "Action": "execute-api:Invoke",
            "Resource": [
                "execute-api:/*"
            ],

```

```
        "Condition" : {
            "StringNotEquals": {
                "aws:SourceVpc": "vpc-1a2b3c4d"
            }
        }
    }
}
```

This example resource policy specifies a source VPC endpoint:

JSON

```
{
    "Version": "2012-10-17",
    "Statement": [
        {
            "Effect": "Allow",
            "Principal": "*",
            "Action": "execute-api:Invoke",
            "Resource": [
                "execute-api:/*"
            ]
        },
        {
            "Effect": "Deny",
            "Principal": "*",
            "Action": "execute-api:Invoke",
            "Resource": [
                "execute-api:/*"
            ],
            "Condition": {
                "StringNotEquals": {
                    "aws:SourceVpc": "vpce-1a2b3c4d"
                }
            }
        }
    ]
}
```

Create and attach an API Gateway resource policy to an API

To allow a user to access your API by calling the API execution service, you must create an API Gateway resource policy and attach the policy to the API. When you attach a policy to your API, it applies the permissions in the policy to the methods in the API. If you update the resource policy, you'll need to deploy the API.

Topics

- [Prerequisites](#)
- [Attach a resource policy to an API Gateway API](#)
- [Troubleshoot your resource policy](#)

Prerequisites

To update an API Gateway resource policy, you'll need the `apigateway:UpdateRestApiPolicy` permission and the `apigateway:PATCH` permission.

For an edge-optimized or Regional API, you can attach your resource policy to your API as you create it, or after it has been deployed. For a private API, you can't deploy your API without a resource policy. For more information, see [the section called “Private REST APIs”](#).

Attach a resource policy to an API Gateway API

The following procedure shows you how to attach a resource policy to an API Gateway API.

AWS Management Console

To attach a resource policy to an API Gateway API

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose a REST API.
3. In the main navigation pane, choose **Resource policy**.
4. Choose **Create policy**.
5. (Optional) Choose **Select a template** to generate an example policy.

In the example policies, placeholders are enclosed in double curly braces ("{{*placeholder*}}"). Replace each of the placeholders, including the curly braces, with the necessary information.

6. If you don't use one of the template examples, enter your resource policy.
7. Choose **Save changes**.

If the API has been deployed previously in the API Gateway console, you'll need to redeploy it for the resource policy to take effect.

AWS CLI

To use the AWS CLI to create a new API and attach a resource policy to it, use the following [create-rest-api](#) command:

```
aws apigateway create-rest-api \
--name "api-name" \
--policy "{\"jsonEscapedPolicyDocument}\""
```

To use the AWS CLI to attach a resource policy to an existing API, use the following [update-rest-api](#) command:

```
aws apigateway update-rest-api \
--rest-api-id api-id \
--patch-operations op=replace,path=/ \
policy,value='\"{\"jsonEscapedPolicyDocument}\"'"
```

You can also attach your resource policy as a separate `policy.json` file and including it in your [create-rest-api](#) command. The following [create-rest-api](#) command creates a new API with a resource policy:

```
aws apigateway create-rest-api \
--name "api-name" \
--policy file://policy.json
```

`policy.json` is an API Gateway resource policy, such as [the section called “Example: Deny API traffic based on source IP address or range”](#).

AWS CloudFormation

You can use CloudFormation to create an API with a resource policy. The following example creates a REST API with the example resource policy, [the section called “Example: Deny API traffic based on source IP address or range”](#).

```
AWSTemplateFormatVersion: 2010-09-09
```

```
Resources:  
  Api:  
    Type: 'AWS::ApiGateway::RestApi'  
    Properties:  
      Name: testapi  
      Policy:  
        Statement:  
          - Action: 'execute-api:Invoke'  
            Effect: Allow  
            Principal: '*'  
            Resource: 'execute-api:/'*'  
          - Action: 'execute-api:Invoke'  
            Effect: Deny  
            Principal: '*'  
            Resource: 'execute-api:/'*'  
        Condition:  
          IpAddress:  
            'aws:SourceIp': ["192.0.2.0/24", "198.51.100.0/24" ]  
      Version: 2012-10-17  
  Resource:  
    Type: 'AWS::ApiGateway::Resource'  
    Properties:  
      RestApiId: !Ref Api  
      ParentId: !GetAtt Api.RootResourceId  
      PathPart: 'helloworld'  
  MethodGet:  
    Type: 'AWS::ApiGateway::Method'  
    Properties:  
      RestApiId: !Ref Api  
      ResourceId: !Ref Resource  
      HttpMethod: GET  
      ApiKeyRequired: false  
      AuthorizationType: NONE  
      Integration:  
        Type: MOCK  
        RequestTemplates:  
          application/json: '{"statusCode": 200}'  
        IntegrationResponses:  
          - StatusCode: 200  
            ResponseTemplates:  
              application/json: '{}'  
      MethodResponses:  
        - StatusCode: 200  
          ResponseModels:
```

```
application/json: 'Empty'  
ApiDeployment:  
  Type: 'AWS::ApiGateway::Deployment'  
  DependsOn:  
    - MethodGet  
  Properties:  
    RestApiId: !Ref Api  
    StageName: test
```

Troubleshoot your resource policy

The following troubleshooting guidance might help resolve issues with your resource policy.

My API returns {"Message":"User: anonymous is not authorized to perform: execute-api:Invoke on resource: arn:aws:execute-api:us-east-1:***/***/****/*"}**

In your resource policy, if you set the Principal to an AWS principal, such as the following:

JSON

```
{  
  "Version": "2012-10-17",  
  "Statement": [  
    {  
      "Effect": "Allow",  
      "Principal": {  
        "AWS": [  
          "arn:aws:iam::111111111111:role/developer",  
          "arn:aws:iam::111111111111:role/Admin"  
        ]  
      },  
      "Action": "execute-api:Invoke",  
      "Resource": [  
        "execute-api:/stage/GET/pets"  
      ]  
    }  
  ]  
}
```

You must use AWS_IAM authorization for every method in your API, or else your API returns the previous error message. For more instructions on how to turn on AWS_IAM authorization for a method, see [the section called “Methods”](#).

My resource policy is not updating

If you update the resource policy after the API is created, you'll need to deploy the API to propagate the changes after you've attached the updated policy. Updating or saving the policy alone won't change the runtime behavior of the API. For more information about deploying your API, see [the section called “Deploy REST APIs”](#).

My resource policy returns the following error: Invalid policy document. Please check the policy syntax and ensure that Principals are valid.

To troubleshoot this error, we first recommend that you check the policy syntax. For more information, see [the section called “Access policy language overview for Amazon API Gateway”](#). We also recommend that you check that all the principals specified are valid and haven't been deleted.

In addition, if your API is in an [opt-in Region](#), verify that all accounts in the resource policy have the Region enabled.

AWS condition keys that can be used in API Gateway resource policies

The following table contains AWS condition keys that can be used in resource policies for APIs in API Gateway for each authorization type.

For more information about AWS condition keys, see [AWS Global Condition Context Keys](#).

Condition keys	Criteria	Needs AuthN?	Authorization type
aws:CurrentTime	None	No	All
aws:EpochTime	None	No	All
aws:TokenIssueTime	Key is present only in requests that are signed using temporary security credentials.	Yes	IAM

Condition keys	Criteria	Needs AuthN?	Authorization type
aws:MultiFactorAuthPresent	Key is present only in requests that are signed using temporary security credentials.	Yes	IAM
aws:MultiFactorAuthAge	Key is present only if MFA is present in the requests.	Yes	IAM
aws:PrincipalAccount	None	Yes	IAM
aws:PrincipalArn	None	Yes	IAM
aws:PrincipalOrgID	This key is included in the request context only if the principal is a member of an organization.	Yes	IAM
aws:PrincipalOrgPaths	This key is included in the request context only if the principal is a member of an organization.	Yes	IAM

Condition keys	Criteria	Needs AuthN?	Authorization type
aws:PrincipalTag	This key is included in the request context if the principal is using an IAM user with attached tags. It is included for a principal using an IAM role with attached tags or session tags.	Yes	IAM
aws:PrincipalType	None	Yes	IAM
aws:Referer	Key is present only if the value is provided by the caller in the HTTP header.	No	All
aws:SecureTransport	None	No	All
aws:SourceArn	None	No	All
aws:SourceIp	None	No	All
aws:SourceVpc	This key can be used only for private APIs.	No	All
aws:SourceVpce	This key can be used only for private APIs.	No	All
aws:VpcSourceIp	This key can be used only for private APIs.	No	All

Condition keys	Criteria	Needs AuthN?	Authorization type
aws:UserAgent	Key is present only if the value is provided by the caller in the HTTP header.	No	All
aws:userid	None	Yes	IAM
aws:username	None	Yes	IAM

Control access to a REST API with IAM permissions

You control access to your Amazon API Gateway API with [IAM permissions](#) by controlling access to the following two API Gateway component processes:

- To create, deploy, and manage an API in API Gateway, you must grant the API developer permissions to perform the required actions supported by the API management component of API Gateway.
- To call a deployed API or to refresh the API caching, you must grant the API caller permissions to perform required IAM actions supported by the API execution component of API Gateway.

The access control for the two processes involves different permissions models, explained next.

API Gateway permissions model for creating and managing an API

To allow an API developer to create and manage an API in API Gateway, you must [create IAM permissions policies](#) that allow a specified API developer to create, update, deploy, view, or delete required [API entities](#). You attach the permissions policy to a user, role, or group.

To provide access, add permissions to your users, groups, or roles:

- Users and groups in AWS IAM Identity Center:

Create a permission set. Follow the instructions in [Create a permission set](#) in the *AWS IAM Identity Center User Guide*.

- Users managed in IAM through an identity provider:

Create a role for identity federation. Follow the instructions in [Create a role for a third-party identity provider \(federation\)](#) in the *IAM User Guide*.

- IAM users:

- Create a role that your user can assume. Follow the instructions in [Create a role for an IAM user](#) in the *IAM User Guide*.
- (Not recommended) Attach a policy directly to a user or add a user to a user group. Follow the instructions in [Adding permissions to a user \(console\)](#) in the *IAM User Guide*.

For more information on how to use this permissions model, see [the section called "API Gateway identity-based policies"](#).

API Gateway permissions model for invoking an API

To allow an API caller to invoke the API or refresh its caching, you must create IAM policies that permit a specified API caller to invoke the API method for which user authentication is enabled. The API developer sets the method's `authorizationType` property to `AWS_IAM` to require that the caller submit the user's credentials to be authenticated. API Gateway supports Signature Version 4a (SigV4a) and Signature Version 4 (SigV4) to authenticate the user's credentials. For more information, see [AWS Signature Version 4](#). Then, you attach the policy to a user, role, or group.

In this IAM permissions policy statement, the `IAM Resource` element contains a list of deployed API methods identified by given HTTP verbs and API Gateway [resource paths](#). The `IAM Action` element contains the required API Gateway API executing actions. These actions include `execute-api:Invoke` or `execute-api:ExecuteApi:InvalidateCache`, where `execute-api` designates the underlying API execution component of API Gateway.

For more information on how to use this permissions model, see [Control access for invoking an API](#).

When an API is integrated with an AWS service (for example, AWS Lambda) in the back end, API Gateway must also have permissions to access integrated AWS resources (for example, invoking a Lambda function) on behalf of the API caller. To grant these permissions, create an IAM role of the **AWS service for API Gateway** type. When you create this role in the IAM Management console, this resulting role contains the following IAM trust policy that declares API Gateway as a trusted entity permitted to assume the role:

JSON

```
{  
    "Version": "2012-10-17",  
    "Statement": [  
        {  
            "Sid": "",  
            "Effect": "Allow",  
            "Principal": {  
                "Service": "apigateway.amazonaws.com"  
            },  
            "Action": "sts:AssumeRole"  
        }  
    ]  
}
```

If you create the IAM role by calling the [create-role](#) command of CLI or a corresponding SDK method, you must supply the above trust policy as the input parameter of `assume-role-policy-document`. Do not attempt to create such a policy directly in the IAM Management console or calling AWS CLI [create-policy](#) command or a corresponding SDK method.

For API Gateway to call the integrated AWS service, you must also attach to this role appropriate IAM permissions policies for calling integrated AWS services. For example, to call a Lambda function, you must include the following IAM permissions policy in the IAM role:

JSON

```
{  
    "Version": "2012-10-17",  
    "Statement": [  
        {  
            "Effect": "Allow",  

```

Note that Lambda supports resource-based access policy, which combines both trust and permissions policies. When integrating an API with a Lambda function using the API Gateway console, you are not asked to set this IAM role explicitly, because the console sets the resource-based permissions on the Lambda function for you, with your consent.

Note

To enact access control to an AWS service, you can use either the caller-based permissions model, where a permissions policy is directly attached to the caller's user or group, or the role-based permission model, where a permissions policy is attached to an IAM role that API Gateway can assume. The permissions policies may differ in the two models. For example, the caller-based policy blocks the access while the role-based policy allows it. You can take advantage of this to require that a user access an AWS service through an API Gateway API only.

Control access for invoking an API

In this section, you learn about the permissions model for controlling access to your API using IAM permissions. When IAM authorization is enabled, clients must use Signature Version 4a (SigV4a) and Signature Version 4 (SigV4) to sign their requests with AWS credentials. For more information, see [AWS Signature Version 4](#).

In this section, we show a template IAM policy statement and the policy statement reference. The policy statement reference includes the formats of Action and Resource fields related to the API execution service. Use these references to create your IAM policy statement. When you create your IAM policy statement, you might need to consider the how API Gateway resource policies affect the authorization workflow. For more information, see [the section called “How resource policies affect authorization workflow”](#).

For private APIs, you should use a combination of an API Gateway resource policy and a VPC endpoint policy. For more information, see the following topics:

- [the section called “Use API Gateway resource policies”](#)
- [the section called “Use VPC endpoint policies for private APIs”](#)

Control who can call an API Gateway API method with IAM policies

To control who can or cannot call a deployed API with IAM permissions, create an IAM policy document with required permissions. A template for such a policy document is shown as follows.

JSON

```
{  
    "Version": "2012-10-17",  
    "Statement": [  
        {  
            "Effect": "Permission",  
            "Action": [  
                "execute-api:Execution-operation"  
            ],  
            "Resource": [  
                "arn:aws:execute-api:region:account-id:api-  
                id/stage/METHOD_HTTP_VERB/Resource-path"  
            ]  
        }  
    ]  
}
```

Here, *Permission* is to be replaced by Allow or Deny depending on whether you want to grant or revoke the included permissions. *Execution-operation* is to be replaced by the operations supported by the API execution service. *METHOD_HTTP_VERB* stands for a HTTP verb supported by the specified resources. *Resource-path* is the placeholder for the URL path of a deployed API [Resource](#) instance supporting the said *METHOD_HTTP_VERB*. For more information, see [Statement reference of IAM policies for executing API in API Gateway](#).

 **Note**

For IAM policies to be effective, you must have enabled IAM authentication on API methods by setting AWS_IAM for the methods' [authorizationType](#) property. Failing to do so will make these API methods publicly accessible.

For example, to grant a user permission to view a list of pets exposed by a specified API, but to deny the user permission to add a pet to the list, you could include the following statement in the IAM policy:

JSON

```
{  
    "Version": "2012-10-17",  
    "Statement": [  
        {  
            "Effect": "Allow",  
            "Action": [  
                "execute-api:Invoke"  
            ],  
            "Resource": [  
                "arn:aws:execute-api:us-east-1:11111111111:api-id/*/GET/pets"  
            ]  
        },  
        {  
            "Effect": "Deny",  
            "Action": [  
                "execute-api:Invoke"  
            ],  
            "Resource": [  
                "arn:aws:execute-api:us-east-1:11111111111:api-id/*/POST/pets"  
            ]  
        }  
    ]  
}
```

To grant a user permission to view a specific pet exposed by an API that is configured as GET /pets/{*petId*}, you could include the following statement in the IAM policy:

JSON

```
{  
    "Version": "2012-10-17",  
    "Statement": [  
        {  
            "Effect": "Allow",  
            "Action": [  
                "execute-api:Invoke"  
            ],  
            "Resource": [  
                "arn:aws:execute-api:us-east-1:11111111111:api-id/*/{petId}/GET/pets"  
            ]  
        }  
    ]  
}
```

```
        "Action": [
            "execute-api:Invoke"
        ],
        "Resource": [
            "arn:aws:execute-api:us-east-1:111122223333:api-id/*",
            "GET/pets/a1b2"
        ]
    }
}
```

Statement reference of IAM policies for executing API in API Gateway

The following information describes the Action and Resource format of IAM policy statements of access permissions for executing an API.

Action format of permissions for executing API in API Gateway

The API-executing Action expression has the following general format:

```
execute-api:action
```

where *action* is an available API-executing action:

- *, which represents all of the following actions.
- Invoke**, used to invoke an API upon a client request.
- InvalidateCache**, used to invalidate API cache upon a client request.

Resource format of permissions for executing API in API Gateway

The API-executing Resource expression has the following general format:

```
arn:aws:execute-api:region:account-id:api-id/stage-name/HTTP-VERB/resource-path-specifier
```

where:

- region* is the AWS region (such as **us-east-1** or * for all AWS regions) that corresponds to the deployed API for the method.
- account-id* is the 12-digit AWS account Id of the REST API owner.

- *api-id* is the identifier API Gateway has assigned to the API for the method.
- *stage-name* is the name of the stage associated with the method.
- *HTTP-VERB* is the HTTP verb for the method. It can be one of the following: GET, POST, PUT, DELETE, PATCH.
- *resource-path-specifier* is the path to the desired method.

 **Note**

If you specify a wildcard (*), the Resource expression applies the wildcard to the rest of the expression.

Some example resource expressions include:

- **arn:aws:execute-api:*:*:*** for any resource path in any stage, for any API in any AWS region.
- **arn:aws:execute-api:us-east-1:*:*** for any resource path in any stage, for any API in the AWS region of us-east-1.
- **arn:aws:execute-api:us-east-1:*:*api-id*/*** for any resource path in any stage, for the API with the identifier of *api-id* in the AWS region of us-east-1.
- **arn:aws:execute-api:us-east-1:*:*api-id*/test/*** for any resource path in the stage of test, for the API with the identifier of *api-id* in the AWS region of us-east-1.

To learn more, see [API Gateway Amazon Resource Name \(ARN\) reference](#).

IAM policy examples for API execution permissions

For permissions model and other background information, see [Control access for invoking an API](#).

The following policy statement gives the user permission to call any POST method along the path of mydemoresource, in the stage of test, for the API with the identifier of a123456789, assuming the corresponding API has been deployed to the AWS region of us-east-1:

JSON

```
{
```

```
"Version":"2012-10-17",
"Statement": [
    {
        "Effect": "Allow",
        "Action": [
            "execute-api:Invoke"
        ],
        "Resource": [
            "arn:aws:execute-api:us-east-1:*:a123456789/test/POST/my-demo-resource-
path/*"
        ]
    }
]
```

The following example policy statement gives the user permission to call any method on the resource path of petstorewalkthrough/pets, in any stage, for the API with the identifier of a123456789, in any AWS region where the corresponding API has been deployed:

JSON

```
{
    "Version":"2012-10-17",
    "Statement": [
        {
            "Effect": "Allow",
            "Action": [
                "execute-api:Invoke"
            ],
            "Resource": [
                "arn:aws:execute-api:*:*:a123456789/*/*/petstorewalkthrough/pets"
            ]
        }
    ]
}
```

Use VPC endpoint policies for private APIs in API Gateway

To improve the security of your private API, you can create a VPC endpoint policy. A VPC endpoint policy is an IAM resource policy that you attach to a VPC endpoint. For more information, see [Controlling Access to Services with VPC Endpoints](#).

You might want to create a VPC endpoint policy to do the following tasks.

- Allow only certain organizations or resources to access your VPC endpoint and invoke your API.
- Use a single policy and avoid session-based or role-based policies to control traffic to your API.
- Tighten the security perimeter of your application while migrating from on premises to AWS.

VPC endpoint policy considerations

The following are considerations for your VPC endpoint policy:

- The identity of the invoker is evaluated based on the Authorization header value. The VPC endpoint policy is evaluated first, and then API Gateway evaluates the request, based on the type of authorization configured on the method request. The following table shows how the VPC endpoint policy is evaluated based on the content of the Authorization header value.

Content of the Authorization header value	How the VPC endpoint policy is evaluated
No content	The invoker is evaluated as an anonymous user
Valid SigV4 or SigV4a signature	The invoker is evaluated as the authenticated IAM identity from the signature
Invalid SigV4 or SigV4a signature	API Gateway denies access
Non-SigV4 authorization information such as a bearer token	The invoker is evaluated as an anonymous user

- If your access control depends on using a bearer token, such as a Lambda or Amazon Cognito authorizer, you can control your security perimeter by using [properties of the resource](#).
- If your authorization controls use IAM authorization, you can control your security perimeter by using [properties of the resource](#) and [properties of the principal](#).

- VPC endpoint policies can be used together with API Gateway resource policies. The API Gateway resource policy specifies which principals can access the API. The endpoint policy specifies who can access the VPC and which APIs can be called from the VPC endpoint. Your private API needs a resource policy but you don't need to create a custom VPC endpoint policy.

VPC endpoint policy examples

You can create policies for Amazon Virtual Private Cloud endpoints for Amazon API Gateway in which you can specify the following.

- The principal that can perform actions.
- The actions that can be performed.
- The resources that can have actions performed on them.

This might depend on the contents of your authorization header. For more information, see [the section called "VPC endpoint policy considerations"](#). For additional example policies, see [Data perimeter policy examples](#) on the GitHub website.

To attach the policy to the VPC endpoint, you'll need to use the VPC console. For more information, see [Controlling Access to Services with VPC Endpoints](#).

Example 1: VPC endpoint policy granting access to two APIs

The following example policy grants access to only two specific APIs via the VPC endpoint that the policy is attached to.

JSON

```
{  
    "Version": "2012-10-17",  
    "Statement": [  
        {  
            "Principal": "*",  
            "Action": [  
                "execute-api:Invoke"  
            ],  
            "Effect": "Allow",  
            "Resource": [  
                "arn:aws:execute-api:us-east-1:123412341234:a1b2c3d4e5/*",  
                "arn:aws:execute-api:us-east-1:123412341234:b1c2d3e4f5/*"  
            ]  
        }  
    ]  
}
```

```
        "arn:aws:execute-api:us-east-1:123412341234:aaaaa11111/*"
    ]
}
]
```

Example 2: VPC endpoint policy granting access to GET methods

The following example policy grants users access to GET methods for a specific API via the VPC endpoint that the policy is attached to.

JSON

```
{
  "Version": "2012-10-17",
  "Statement": [
    {
      "Principal": "*",
      "Action": [
        "execute-api:Invoke"
      ],
      "Effect": "Allow",
      "Resource": [
        "arn:aws:execute-api:us-east-1:123412341234:a1b2c3d4e5/stageName/
GET/*"
      ]
    }
  ]
}
```

Example 3: VPC endpoint policy granting a specific user access to a specific API

The following example policy grants a specific user access to a specific API via the VPC endpoint that the policy is attached to.

In this case, because the policy restricts access to specific IAM principals, you must set the `authorizationType` of the method to `AWS_IAM` or `NONE`.

JSON

```
{  
    "Version": "2012-10-17",  
    "Statement": [  
        {  
            "Principal": {  
                "AWS": [  
                    "arn:aws:iam::123412341234:user/MyUser"  
                ]  
            },  
            "Action": [  
                "execute-api:Invoke"  
            ],  
            "Effect": "Allow",  
            "Resource": [  
                "arn:aws:execute-api:us-east-1:123412341234:a1b2c3d4e5/*"  
            ]  
        }  
    ]  
}
```

Example 4: VPC endpoint policy granting users access to a specific custom domain name and every API mapped to the domain

The following example policy grants users access to a specific custom domain name for private APIs via the VPC endpoint that the policy is attached to. With this policy, as long as a user has created a domain name access association between the VPC endpoint and the custom domain name and is granted access to invoke the custom domain name and any private API's mapped to the custom domain name, the user can invoke any APIs mapped to this custom domain name. For more information, see [the section called “Custom domain names for private APIs”](#).

JSON

```
{  
    "Version": "2012-10-17",  
    "Statement": [  
        {  
            "Effect": "Allow",  
            "Principal": {  
                "AWS": [  
                    "arn:aws:iam::123412341234:user/MyUser"  
                ]  
            },  
            "Action": [  
                "execute-api:Invoke"  
            ],  
            "Resource": [  
                "arn:aws:execute-api:us-east-1:123412341234:a1b2c3d4e5/*"  
            ]  
        }  
    ]  
}
```

```
        "AWS": "*"
    },
    "Action": "execute-api:Invoke",
    "Resource": [
        "*"
    ],
    "Condition": {
        "ArnEquals": {
            "execute-api:viaDomainArn": "arn:aws:execute-api:us-
west-2:111122223333:/domainnames/private.test.com+f4g5h6",
        }
    }
}
```

Example 5: VPC endpoint policy granting or denying access to specific APIs and domain resources

The following example policy grants users access to specific APIs and domain resources. With this policy, as long as a user has created a domain name access association between the VPC endpoint and the custom domain name and is granted access to invoke the custom domain name and any private API's mapped to the custom domain name, the user can invoke allowed private APIs and domain resources. For more information, see [the section called “Custom domain names for private APIs”](#).

JSON

```
{
    "Version": "2012-10-17",
    "Statement": [
        {
            "Effect": "Allow",
            "Principal": {
                "AWS": "*"
            },
            "Action": "execute-api:Invoke",
            "Resource": [
                "arn:aws:execute-api:us-west-2:111122223333:/domainnames/private.test.com
+f4g5h6",
                "arn:aws:execute-api:us-west-2:111122223333:a1b2c3d4e5/*"
            ]
        }
    ]
}
```

```
        ],
      },
      {
        "Effect": "Deny",
        "Principal": {
          "AWS": "*"
        },
        "Action": "execute-api:Invoke",
        "Resource": [
          "arn:aws:execute-api:us-west-2:111122223333:a1b2c3d4e5/admin/*",
          "arn:aws:execute-api:us-west-2:111122223333:bcd123455/*"
        ]
      }
    ]
  }
```

Example 6: VPC endpoint policy granting or denying access by principals and resources belonging to an organization

The following example policy grants access to principals and resources that belong to an organization.

JSON

```
{
  "Version": "2012-10-17",
  "Statement": [
    {
      "Condition": {
        "StringEquals": {
          "aws:ResourceOrgID": "o-abcd1234",
          "aws:PrincipalOrgID": "o-abcd1234"
        }
      },
      "Action": "*",
      "Resource": "*",
      "Effect": "Allow",
      "Principal": {
        "AWS": "*"
      },
      "Sid": "AllowRequestsByOrgsIdentitiesToOrgsResources"
    }
  ]
}
```

```
}
```

Use tags to control access to REST APIs in API Gateway

Permission to access REST APIs can be fine-tuned using attribute-based access control in IAM policies.

For more information, see [the section called “Attribute-based access control”](#).


Use API Gateway Lambda authorizers

Use a *Lambda authorizer* (formerly known as a *custom authorizer*) to control access to your API. When a client makes a request to your API's method, API Gateway calls your Lambda authorizer. The Lambda authorizer takes the caller's identity as the input and returns an IAM policy as the output.

Use a Lambda authorizer to implement a custom authorization scheme. Your scheme can use request parameters to determine the caller's identity or use a bearer token authentication strategy such as OAuth or SAML. Create a Lambda authorizer in the API Gateway REST API console, using the AWS CLI, or an AWS SDK.

Lambda authorizer authorization workflow

The following diagram shows the authorization workflow for a Lambda authorizer.



API Gateway Lambda authorization workflow

1. The client calls a method on an API Gateway API, passing a bearer token or request parameters.
2. API Gateway checks if the method request is configured with a Lambda authorizer. If it is, API Gateway calls the Lambda function.
3. The Lambda function authenticates the caller. The function can authenticate in the following ways:
 - By calling out to an OAuth provider to get an OAuth access token.
 - By calling out to a SAML provider to get a SAML assertion.
 - By generating an IAM policy based on the request parameter values.
 - By retrieving credentials from a database.
4. The Lambda function returns an IAM policy and a principal identifier. If the Lambda function does not return that information, the call fails.
5. API Gateway evaluates the IAM policy.

- If access is denied, API Gateway returns a suitable HTTP status code, such as 403 ACCESS_DENIED.
- If access is allowed, API Gateway invokes the method.

If you enable authorization caching, API Gateway caches the policy so that the Lambda authorizer function isn't invoked again. Ensure that your policy is applicable to all resources and methods across your API.

You can customize the 403 ACCESS_DENIED or the 401 UNAUTHORIZED gateway responses. To learn more, see [the section called "Gateway responses"](#).

Choosing a type of Lambda authorizer

There are two types of Lambda authorizers:

Request parameter-based Lambda authorizer (REQUEST authorizer)

A REQUEST authorizer receives the caller's identity in a combination of headers, query string parameters, [stageVariables](#), and [\\$context](#) variables. You can use a REQUEST authorizer to create fine-grained policies based on the information from multiple identity sources, such as the `$context.path` and `$context.httpMethod` context variables.

If you turn on authorization caching for a REQUEST authorizer, API Gateway verifies that all specified identity sources are present in the request. If a specified identify source is missing, null, or empty, API Gateway returns a 401 Unauthorized HTTP response without calling the Lambda authorizer function. When multiple identity sources are defined, they are all used to derive the authorizer's cache key, with the order preserved. You can define a fine-grained cache key by using multiple identity sources.

If you change any of the cache key parts, and redeploy your API, the authorizer discards the cached policy document and generates a new one.

If you turn off authorization caching for a REQUEST authorizer, API Gateway directly passes the request to the Lambda function.

Token-based Lambda authorizer (TOKEN authorizer)

A TOKEN authorizer receives the caller's identity in a bearer token, such as a JSON Web Token (JWT) or an OAuth token.

If you turn on authorization caching for a TOKEN authorizer, the header name specified in the token source becomes the cache key.

Additionally, you can use token validation to enter a RegEx statement. API Gateway performs initial validation of the input token against this expression and invokes the Lambda authorizer function upon successful validation. This helps reduce calls to your API.

The IdentityValidationExpression property is supported for TOKEN authorizers only. For more information, see [the section called “x-amazon-apigateway-authorizer”](#).

Note

We recommend that you use a REQUEST authorizer to control access to your API. You can control access to your API based on multiple identity sources when using a REQUEST authorizer, compared to a single identity source when using a TOKEN authorizer. In addition, you can separate cache keys using multiple identity sources for a REQUEST authorizer.

Example REQUEST authorizer Lambda function

The following example code creates a Lambda authorizer function that allows a request if the client-supplied HeaderAuth1 header, QueryString1 query parameter, and stage variable of StageVar1 all match the specified values of headerValue1, queryValue1, and stageValue1, respectively.

Node.js

```
// A simple request-based authorizer example to demonstrate how to use request
// parameters to allow or deny a request. In this example, a request is
// authorized if the client-supplied HeaderAuth1 header, QueryString1
// query parameter, and stage variable of StageVar1 all match
// specified values of 'headerValue1', 'queryValue1', and 'stageValue1',
// respectively.

export const handler = function(event, context, callback) {
    console.log('Received event:', JSON.stringify(event, null, 2));

    // Retrieve request parameters from the Lambda function input:
    var headers = event.headers;
```

```
var queryStringParameters = event.queryStringParameters;
var pathParameters = event.pathParameters;
var stageVariables = event.stageVariables;

// Parse the input for the parameter values
var tmp = event.methodArn.split(':');
var apiGatewayArnTmp = tmp[5].split('/');
var awsAccountId = tmp[4];
var region = tmp[3];
var restApiId = apiGatewayArnTmp[0];
var stage = apiGatewayArnTmp[1];
var method = apiGatewayArnTmp[2];
var resource = '/'; // root resource
if (apiGatewayArnTmp[3]) {
    resource += apiGatewayArnTmp[3];
}

// Perform authorization to return the Allow policy for correct parameters and
// the 'Unauthorized' error, otherwise.

if (headers.HeaderAuth1 === "headerValue1"
    && queryStringParameters.QueryString1 === "queryValue1"
    && stageVariables.StageVar1 === "stageValue1") {
    callback(null, generateAllow('me', event.methodArn));
} else {
    callback(null, generateDeny('me', event.methodArn));
}
}

// Help function to generate an IAM policy
var generatePolicy = function(principalId, effect, resource) {
    // Required output:
    var authResponse = {};
    authResponse.principalId = principalId;
    if (effect && resource) {
        var policyDocument = {};
        policyDocument.Version = '2012-10-17'; // default version
        policyDocument.Statement = [];
        var statementOne = {};
        statementOne.Action = 'execute-api:Invoke'; // default action
        statementOne.Effect = effect;
        statementOne.Resource = resource;
        policyDocument.Statement[0] = statementOne;
```

```
        authResponse.policyDocument = policyDocument;
    }
    // Optional output with custom properties of the String, Number or Boolean type.
    authResponse.context = {
        "stringKey": "stringval",
        "numberKey": 123,
        "booleanKey": true
    };
    return authResponse;
}

var generateAllow = function(principalId, resource) {
    return generatePolicy(principalId, 'Allow', resource);
}

var generateDeny = function(principalId, resource) {
    return generatePolicy(principalId, 'Deny', resource);
}
```

Python

```
# A simple request-based authorizer example to demonstrate how to use request
# parameters to allow or deny a request. In this example, a request is
# authorized if the client-supplied headerauth1 header, QueryString1
# query parameter, and stage variable of StageVar1 all match
# specified values of 'headerValue1', 'queryValue1', and 'stageValue1',
# respectively.

def lambda_handler(event, context):
    print(event)

    # Retrieve request parameters from the Lambda function input:
    headers = event['headers']
    queryStringParameters = event['queryStringParameters']
    pathParameters = event['pathParameters']
    stageVariables = event['stageVariables']

    # Parse the input for the parameter values
    tmp = event['methodArn'].split(':')
    apiGatewayArnTmp = tmp[5].split('/')
    awsAccountId = tmp[4]
    region = tmp[3]
    restApiId = apiGatewayArnTmp[0]
```

```
stage = apiGatewayArnTmp[1]
method = apiGatewayArnTmp[2]
resource = '/'

if (apiGatewayArnTmp[3]):
    resource += apiGatewayArnTmp[3]

# Perform authorization to return the Allow policy for correct parameters
# and the 'Unauthorized' error, otherwise.

if (headers['HeaderAuth1'] == "headerValue1" and
queryStringParameters['QueryString1'] == "queryValue1" and
stageVariables['StageVar1'] == "stageValue1"):
    response = generateAllow('me', event['methodArn'])
    print('authorized')
    return response
else:
    print('unauthorized')
    response = generateDeny('me', event['methodArn'])
    return response

# Help function to generate IAM policy

def generatePolicy(principalId, effect, resource):
    authResponse = {}
    authResponse['principalId'] = principalId
    if (effect and resource):
        policyDocument = {}
        policyDocument['Version'] = '2012-10-17'
        policyDocument['Statement'] = []
        statementOne = {}
        statementOne['Action'] = 'execute-api:Invoke'
        statementOne['Effect'] = effect
        statementOne['Resource'] = resource
        policyDocument['Statement'] = [statementOne]
        authResponse['policyDocument'] = policyDocument

        authResponse['context'] = {
            "stringKey": "stringval",
            "numberKey": 123,
            "booleanKey": True
        }

    return authResponse
```

```
def generateAllow(principalId, resource):
    return generatePolicy(principalId, 'Allow', resource)

def generateDeny(principalId, resource):
    return generatePolicy(principalId, 'Deny', resource)
```

In this example, the Lambda authorizer function checks the input parameters and acts as follows:

- If all the required parameter values match the expected values, the authorizer function returns a 200 OK HTTP response and an IAM policy that looks like the following, and the method request succeeds:

JSON

```
{
  "Version": "2012-10-17",
  "Statement": [
    {
      "Action": "execute-api:Invoke",
      "Effect": "Allow",
      "Resource": "arn:aws:execute-api:us-east-1:123456789012:ivtdh7b5/
ESTestInvoke-stage/GET/"
    }
  ]
}
```

- Otherwise, the authorizer function returns a 401 Unauthorized HTTP response, and the method request fails.

In addition to returning an IAM policy, the Lambda authorizer function must also return the caller's principal identifier. Optionally, it can return a context object containing additional information that can be passed into the integration backend. For more information, see [Output from an API Gateway Lambda authorizer](#).

In production code, you might need to authenticate the user before granting authorization. You can add authentication logic in the Lambda function by calling an authentication provider as directed in the documentation for that provider.

Example TOKEN authorizer Lambda function

The following example code creates a TOKEN Lambda authorizer function that allows a caller to invoke a method if the client-supplied token value is allow. The caller is not allowed to invoke the request if the token value is deny. If the token value is unauthorized or an empty string, the authorizer function returns an 401 UNAUTHORIZED response.

Node.js

```
// A simple token-based authorizer example to demonstrate how to use an
// authorization token
// to allow or deny a request. In this example, the caller named 'user' is allowed
// to invoke
// a request if the client-supplied token value is 'allow'. The caller is not
// allowed to invoke
// the request if the token value is 'deny'. If the token value is 'unauthorized' or
// an empty
// string, the authorizer function returns an HTTP 401 status code. For any other
// token value,
// the authorizer returns an HTTP 500 status code.
// Note that token values are case-sensitive.

export const handler = function(event, context, callback) {
    var token = event.authorizationToken;
    switch (token) {
        case 'allow':
            callback(null, generatePolicy('user', 'Allow', event.methodArn));
            break;
        case 'deny':
            callback(null, generatePolicy('user', 'Deny', event.methodArn));
            break;
        case 'unauthorized':
            callback("Unauthorized"); // Return a 401 Unauthorized response
            break;
        default:
            callback("Error: Invalid token"); // Return a 500 Invalid token response
    }
};

// Help function to generate an IAM policy
var generatePolicy = function(principalId, effect, resource) {
    var authResponse = {};
```

```
authResponse.principalId = principalId;
if (effect && resource) {
    var policyDocument = {};
    policyDocument.Version = '2012-10-17';
    policyDocument.Statement = [];
    var statementOne = {};
    statementOne.Action = 'execute-api:Invoke';
    statementOne.Effect = effect;
    statementOne.Resource = resource;
    policyDocument.Statement[0] = statementOne;
    authResponse.policyDocument = policyDocument;
}

// Optional output with custom properties of the String, Number or Boolean type.
authResponse.context = {
    "stringKey": "stringval",
    "numberKey": 123,
    "booleanKey": true
};
return authResponse;
}
```

Python

```
# A simple token-based authorizer example to demonstrate how to use an authorization
# token
# to allow or deny a request. In this example, the caller named 'user' is allowed to
# invoke
# a request if the client-supplied token value is 'allow'. The caller is not allowed
# to invoke
# the request if the token value is 'deny'. If the token value is 'unauthorized' or
# an empty
# string, the authorizer function returns an HTTP 401 status code. For any other
# token value,
# the authorizer returns an HTTP 500 status code.
# Note that token values are case-sensitive.

import json


def lambda_handler(event, context):
    token = event['authorizationToken']
    if token == 'allow':
```

```
        print('authorized')
        response = generatePolicy('user', 'Allow', event['methodArn'])
    elif token == 'deny':
        print('unauthorized')
        response = generatePolicy('user', 'Deny', event['methodArn'])
    elif token == 'unauthorized':
        print('unauthorized')
        raise Exception('Unauthorized') # Return a 401 Unauthorized response
        return 'unauthorized'
try:
    return json.loads(response)
except BaseException:
    print('unauthorized')
    return 'unauthorized' # Return a 500 error

def generatePolicy(principalId, effect, resource):
    authResponse = {}
    authResponse['principalId'] = principalId
    if (effect and resource):
        policyDocument = {}
        policyDocument['Version'] = '2012-10-17'
        policyDocument['Statement'] = []
        statementOne = {}
        statementOne['Action'] = 'execute-api:Invoke'
        statementOne['Effect'] = effect
        statementOne['Resource'] = resource
        policyDocument['Statement'] = [statementOne]
        authResponse['policyDocument'] = policyDocument
    authResponse['context'] = {
        "stringKey": "stringval",
        "numberKey": 123,
        "booleanKey": True
    }
    authResponse_JSON = json.dumps(authResponse)
    return authResponse_JSON
```

In this example, when the API receives a method request, API Gateway passes the source token to this Lambda authorizer function in the event.authorizationToken attribute. The Lambda authorizer function reads the token and acts as follows:

- If the token value is allow, the authorizer function returns a 200 OK HTTP response and an IAM policy that looks like the following, and the method request succeeds:

JSON

```
{  
    "Version": "2012-10-17",  
    "Statement": [  
        {  
            "Action": "execute-api:Invoke",  
            "Effect": "Allow",  
            "Resource": "arn:aws:execute-api:us-east-1:123456789012:ivtdh7b5/  
ESTestInvoke-stage/GET/"  
        }  
    ]  
}
```

- If the token value is deny, the authorizer function returns a 200 OK HTTP response and a Deny IAM policy that looks like the following, and the method request fails:

JSON

```
{  
    "Version": "2012-10-17",  
    "Statement": [  
        {  
            "Action": "execute-api:Invoke",  
            "Effect": "Deny",  
            "Resource": "arn:aws:execute-api:us-east-1:123456789012:ivtdh7b5/  
ESTestInvoke-stage/GET/"  
        }  
    ]  
}
```

 **Note**

Outside of the test environment, API Gateway returns a 403 Forbidden HTTP response and the method request fails.

- If the token value is unauthorized or an empty string, the authorizer function returns a 401 Unauthorized HTTP response, and the method call fails.

- If the token is anything else, the client receives a 500 Invalid token response, and the method call fails.

In addition to returning an IAM policy, the Lambda authorizer function must also return the caller's principal identifier. Optionally, it can return a context object containing additional information that can be passed into the integration backend. For more information, see [Output from an API Gateway Lambda authorizer](#).

In production code, you might need to authenticate the user before granting authorization. You can add authentication logic in the Lambda function by calling an authentication provider as directed in the documentation for that provider.

Additional examples of Lambda authorizer functions

The following list shows additional examples of Lambda authorizer functions. You can create a Lambda function in the same account, or a different account, from where you created your API.

For the previous example Lambda functions, you can use the built-in [AWSLambdaBasicExecutionRole](#), as these functions don't call other AWS services. If your Lambda function calls other AWS services, you'll need to assign an IAM execution role to the Lambda function. To create the role, follow the instructions in [AWS Lambda Execution Role](#).

Additional examples of Lambda authorizer functions

- For an example application, see [Open Banking Brazil - Authorization Samples](#) on GitHub.
- For more example Lambda functions, see [aws-apigateway-lambda-authorizer-blueprints](#) on GitHub.
- You can create a Lambda authorizer that authenticates users using Amazon Cognito user pools and authorizes callers based on a policy store using Verified Permissions. For more information, see [the section called "Control access based on an identity's attributes with Verified Permissions"](#).
- The Lambda console provides a Python blueprint, which you can use by choosing **Use a blueprint** and choosing the **api-gateway-authorizer-python** blueprint.

Configure an API Gateway Lambda authorizer

After you create a Lambda function, you configure the Lambda function as an authorizer for your API. You then configure your method to invoke your Lambda authorizer to determine if a caller can

invoke your method. You can create a Lambda function in the same account, or a different account, from where you created your API.

You can test your Lambda authorizer using built-in tools in the API Gateway console or by using [Postman](#). For instructions for how to use Postman to test your Lambda authorizer function, see [the section called “Call an API with Lambda authorizers”](#).

Configure a Lambda authorizer (console)

The following procedure shows how to create a Lambda authorizer in the API Gateway REST API console. To learn more about the different types of Lambda authorizers, see [the section called “Choosing a type of Lambda authorizer”](#).

REQUEST authorizer

To configure a REQUEST Lambda authorizer

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Select an API, and then choose **Authorizers**.
3. Choose **Create authorizer**.
4. For **Authorizer name**, enter a name for the authorizer.
5. For **Authorizer type**, select **Lambda**.
6. For **Lambda function**, select the AWS Region where you created your Lambda authorizer function, and then enter the function name.
7. Keep **Lambda invoke role** blank to let the API Gateway REST API console set a resource-based policy. The policy grants API Gateway permissions to invoke the Lambda authorizer function. You can also choose to enter the name of an IAM role to allow API Gateway to invoke the Lambda authorizer function. For an example role, see [Create an assumable IAM role](#).
8. For **Lambda event payload**, select **Request**.
9. For **Identity source type**, select a parameter type. Supported parameter types are Header, Query string, Stage variable, and Context. To add more identity sources, choose **Add parameter**.
10. To cache the authorization policy generated by the authorizer, keep **Authorization caching** turned on. When policy caching is enabled, you can modify the **TTL** value. Setting the **TTL** to zero disables policy caching.

If you enable caching, your authorizer must return a policy that is applicable to all methods across an API. To enforce a method-specific policy, use the context variables `$context.path` and `$context.httpMethod`.

11. Choose **Create authorizer**.

TOKEN authorizer

To configure a TOKEN Lambda authorizer

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Select an API, and then choose **Authorizers**.
3. Choose **Create authorizer**.
4. For **Authorizer name**, enter a name for the authorizer.
5. For **Authorizer type**, select **Lambda**.
6. For **Lambda function**, select the AWS Region where you created your Lambda authorizer function, and then enter the function name.
7. Keep **Lambda invoke role** blank to let the API Gateway REST API console set a resource-based policy. The policy grants API Gateway permissions to invoke the Lambda authorizer function. You can also choose to enter the name of an IAM role to allow API Gateway to invoke the Lambda authorizer function. For an example role, see [Create an assumable IAM role](#).
8. For **Lambda event payload**, select **Token**.
9. For **Token source**, enter the header name that contains the authorization token. The caller must include a header of this name to send the authorization token to the Lambda authorizer.
10. (Optional) For **Token validation**, enter a RegEx statement. API Gateway performs initial validation of the input token against this expression and invokes the authorizer upon successful validation.
11. To cache the authorization policy generated by the authorizer, keep **Authorization caching** turned on. When policy caching is enabled, the header name specified in **Token source** becomes the cache key. When policy caching is enabled, you can modify the **TTL** value. Setting the **TTL** to zero disables policy caching.

If you enable caching, your authorizer must return a policy that is applicable to all methods across an API. To enforce a method-specific policy, you can turn off **Authorization caching**.

12. Choose **Create authorizer**.

After you create your Lambda authorizer, you can test it. The following procedure shows how to test your Lambda authorizer.

REQUEST authorizer

To test a REQUEST Lambda authorizer

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Select the name of your authorizer.
3. Under **Test authorizer**, enter a value for your identity source.

If you are using the [the section called “Example REQUEST authorizer Lambda function”](#), do the following:

- a. Select **Header** and enter **headerValue1**, and then choose **Add parameter**.
- b. Under **Identity source type**, select **Query string** and enter **queryValue1**, and then choose **Add parameter**.
- c. Under **Identity source type**, select **Stage variable** and enter **stageValue1**.

You can't modify the context variables for the test invocation, but you can modify the **API Gateway Authorizer** test event template for your Lambda function. Then, you can test your Lambda authorizer function with modified context variables. For more information, see [Testing Lambda functions in the console](#) in the *AWS Lambda Developer Guide*.

4. Choose **Test authorizer**.

TOKEN authorizer

To test a TOKEN Lambda authorizer

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Select the name of your authorizer.

3. Under **Test authorizer**, enter a value for your token.

If you are using the [the section called “Example TOKEN authorizer Lambda function”](#), do the following:

- For the **authorizationToken**, enter **allow**.

4. Choose **Test authorizer**.

If your Lambda authorizer successfully denies a request in the test environment, the test responds with a `200 OK` HTTP response. However, outside of the test environment, API Gateway returns a `403 Forbidden` HTTP response and the method request fails.

Configure a Lambda authorizer (AWS CLI)

The following [create-authorizer](#) command shows to create a Lambda authorizer using the AWS CLI.

REQUEST authorizer

The following [create-authorizer](#) command creates a REQUEST authorizer and uses the **Authorizer** header and **accountId** context variable as identity sources:

```
aws apigateway create-authorizer \
--rest-api-id 1234123412 \
--name 'First_Request_Custom_Authorizer' \
--type REQUEST \
--authorizer-uri 'arn:aws:apigateway:us-west-2:lambda:path/2015-03-31/functions/
arn:aws:lambda:us-west-2:123412341234:function:customAuthFunction/invocations' \
--identity-source 'method.request.header.Authorization,context.accountId' \
--authorizer-result-ttl-in-seconds 300
```

TOKEN authorizer

The following [create-authorizer](#) command creates a TOKEN authorizer and uses the **Authorization** header as the identity source:

```
aws apigateway create-authorizer \
--rest-api-id 1234123412 \
--name 'First_Token_Custom_Authorizer' \
--type TOKEN \
--authorizer-uri 'arn:aws:apigateway:us-west-2:lambda:path/2015-03-31/functions/
arn:aws:lambda:us-west-2:123412341234:function:customAuthFunction/invocations' \
```

```
--identity-source 'method.request.header.Authorization' \
--authorizer-result-ttl-in-seconds 300
```

After you create your Lambda authorizer, you can test it. The following [test-invoker-authorizer](#) command tests a Lambda authorizer:

```
aws apigateway test-invoker-authorizer --rest-api-id 1234123412 \
--authorizer-id efg1234 \
--headers Authorization='Value'
```

Configure a method to use a Lambda authorizer (console)

After you configure your Lambda authorizer, you must attach it to a method for your API. If your authorizer uses authorization caching, make sure you update the policy to control access for the additional method.

To configure an API method to use a Lambda authorizer

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Select an API.
3. Choose **Resources**, and then choose a new method or choose an existing method.
4. On the **Method request** tab, under **Method request settings**, choose **Edit**.
5. For **Authorizer**, from the dropdown menu, select the Lambda authorizer you just created.
6. (Optional) If you want to pass the authorization token to the backend, choose **HTTP request headers**. Choose **Add header**, and then add the name of the authorization header. For **Name**, enter the header name that matches the **Token source** name you specified when you created the Lambda authorizer for the API. This step does not apply to REQUEST authorizers.
7. Choose **Save**.
8. Choose **Deploy API** to deploy the API to a stage. For a REQUEST authorizer using stage variables, you must also define the required stage variables and specify their values while on the **Stages** page.

Configure a method to use a Lambda authorizer (AWS CLI)

After you configure your Lambda authorizer, you must attach it to a method for your API. You can create a new method or use a patch operation to attach an authorizer to an existing method. If

your authorizer uses authorization caching, make sure you update the policy to control access for the additional method.

The following [put-method](#) command creates a new method that uses an Lambda authorizer:

```
aws apigateway put-method --rest-api-id 1234123412 \
--resource-id a1b2c3 \
--http-method PUT \
--authorization-type CUSTOM \
--authorizer-id efg1234
```

The following [update-method](#) command update an existing method to use a Lambda authorizer:

```
aws apigateway update-method \
--rest-api-id 1234123412 \
--resource-id a1b2c3 \
--http-method PUT \
--patch-operations op="replace",path="/authorizationType",value="CUSTOM"
op="replace",path="/authorizerId",value="efg1234"
```

Input to an API Gateway Lambda authorizer

The following section explains the format of the input from API Gateway to a Lambda authorizer.

TOKEN input format

For a Lambda authorizer (formerly known as a custom authorizer) of the TOKEN type, you must specify a custom header as the **Token Source** when you configure the authorizer for your API. The API client must pass the required authorization token in that header in the incoming request. Upon receiving the incoming method request, API Gateway extracts the token from the custom header. It then passes the token as the `authorizationToken` property of the event object of the Lambda function, in addition to the method ARN as the `methodArn` property:

```
{
  "type": "TOKEN",
  "authorizationToken": "{caller-supplied-token}",
  "methodArn": "arn:aws:execute-api:{regionId}:{accountId}:{apiId}/{stage}/{httpVerb}/
  [{resource}][{child-resources}]"
}
```

In this example, the type property specifies the authorizer type, which is a TOKEN authorizer. The *{caller-supplied-token}* originates from the authorization header in a client request, and can be any string value. The methodArn is the ARN of the incoming method request and is populated by API Gateway in accordance with the Lambda authorizer configuration.

REQUEST input format

For a Lambda authorizer of the REQUEST type, API Gateway passes request parameters to the authorizer Lambda function as part of the event object. The request parameters include headers, path parameters, query string parameters, stage variables, and some of request context variables. The API caller can set the path parameters, headers, and query string parameters. The API developer must set the stage variables during the API deployment and API Gateway provides the request context at run time.

Note

Path parameters can be passed as request parameters to the Lambda authorizer function, but they cannot be used as identity sources.

The following example shows an input to a REQUEST authorizer for an API method (GET /request) with a proxy integration:

```
{
  "type": "REQUEST",
  "methodArn": "arn:aws:execute-api:us-east-1:123456789012:abcdef123/test/GET/request",
  "resource": "/request",
  "path": "/request",
  "httpMethod": "GET",
  "headers": {
    "X-AMZ-Date": "20170718T062915Z",
    "Accept": "*/*",
    "HeaderAuth1": "headerValue1",
    "CloudFront-Viewer-Country": "US",
    "CloudFront-Forwarded-Proto": "https",
    "CloudFront-Is-Tablet-Viewer": "false",
    "CloudFront-Is-Mobile-Viewer": "false",
    "User-Agent": "..."
  },
  "queryStringParameters": {
    "QueryString1": "queryValue1"
  }
}
```

The `requestContext` is a map of key-value pairs and corresponds to the [\\$context](#) variable. Its outcome is API-dependent.

API Gateway might add new keys to the map. For more information about Lambda function input in Lambda proxy integration, see [Input format of a Lambda function for proxy integration](#).

Output from an API Gateway Lambda authorizer

A Lambda authorizer function's output is a dictionary-like object, which must include the principal identifier (`principalId`) and a policy document (`policyDocument`) containing a list of policy statements. The output can also include a context map containing key-value pairs. If the API uses

a usage plan (the [apiKeySource](#) is set to AUTHORIZER), the Lambda authorizer function must return one of the usage plan's API keys as the `usageIdentifierKey` property value.

The following shows an example of this output.

JSON

```
{  
    "principalId": "yyyyyyyy",  
    "policyDocument": {  
        "Version": "2012-10-17",  
        "Statement": [  
            {  
                "Action": "execute-api:Invoke",  
                "Effect": "Allow|Deny",  
                "Resource": "arn:aws:execute-  
api:{regionId}:{accountId}:{apiId}/{stage}/{httpVerb}/[{resource}]/[{child-  
resources}]]"  
            }  
        ]  
    },  
    "context": {  
        "stringKey": "value",  
        "numberKey": "1",  
        "booleanKey": "true"  
    },  
    "usageIdentifierKey": "{api-key}"  
}
```

Here, a policy statement specifies whether to allow or deny (Effect) the API Gateway execution service to invoke (Action) the specified API method (Resource). You might need to control access to multiple resources based on your authorizer. You can use a wild card (*) to specify a resource type (method). For information about setting valid policies for calling an API, see [Statement reference of IAM policies for executing API in API Gateway](#).

For an authorization-enabled method ARN, e.g., `arn:aws:execute-api:{regionId}:{accountId}:{apiId}/{stage}/{httpVerb}/[{resource}]/[{child-resources}]]`, the maximum length is 1600 bytes. The path parameter values, the size of which are determined at run time, can cause the ARN length to exceed the limit. When this happens, the API client will receive a 414 Request URI too long response.

In addition, the Resource ARN, as shown in the policy statement output by the authorizer, is currently limited to 512 characters long. For this reason, you must not use URI with a JWT token of a significant length in a request URI. You can safely pass the JWT token in a request header, instead.

You can access the `principalId` value in a mapping template using the `$context.authorizer.principalId` variable. This is useful if you want to pass the value to the backend. For more information, see [Context variables for data transformations](#).

You can access the `stringKey`, `numberKey`, or `booleanKey` value (for example, "value", "1", or "true") of the context map in a mapping template by calling `$context.authorizer.stringKey`, `$context.authorizer.numberKey`, or `$context.authorizer.booleanKey`, respectively. The returned values are all stringified. Notice that you cannot set a JSON object or array as a valid value of any key in the context map.

You can use the context map to return cached credentials from the authorizer to the backend, using an integration request mapping template. This enables the backend to provide an improved user experience by using the cached credentials to reduce the need to access the secret keys and open the authorization tokens for every request.

For the Lambda proxy integration, API Gateway passes the `context` object from a Lambda authorizer directly to the backend Lambda function as part of the input event. You can retrieve the context key-value pairs in the Lambda function by calling `$event.requestContext.authorizer.key`.

{api-key} stands for an API key in the API stage's usage plan. For more information, see [the section called "Usage plans"](#).

The following shows example output from the example Lambda authorizer. The example output contains a policy statement to block (Deny) calls to the GET method for the dev stage of an API (ymy8tbxw7b) of an AWS account (123456789012).

JSON

```
{  
  "principalId": "user",  
  "policyDocument": {  
    "Version": "2012-10-17",  
    "Statement": [
```

```
{  
    "Action": "execute-api:Invoke",  
    "Effect": "Deny",  
    "Resource": "arn:aws:execute-api:us-west-2:123456789012:ymy8tbxw7b/dev/  
    GET/*"  
}  
]  
}  
}
```

Call an API with an API Gateway Lambda authorizer

Having configured the Lambda authorizer (formerly known as the custom authorizer) and deployed the API, you should test the API with the Lambda authorizer enabled. For this, you need a REST client, such as [cURL](#) or [Postman](#). For the following examples, we use Postman.

Note


When calling an authorizer-enabled method, API Gateway does not log the call to CloudWatch if the required token for the TOKEN authorizer is not set, is null, or is invalidated by the specified **Token validation expression**. Similarly, API Gateway does not log the call to CloudWatch if any of the required identity sources for the REQUEST authorizer are not set, are null, or are empty.

In the following, we show how to use Postman to call or test an API with a Lambda TOKEN authorizer. The method can be applied to calling an API with a Lambda REQUEST authorizer, if you specify the required path, header, or query string parameters explicitly.

To call an API with the custom TOKEN authorizer

1. Open **Postman**, choose the **GET** method, and paste the API's **Invoke URL** into the adjacent URL field.

Add the Lambda authorization token header and set the value to **allow**. Choose **Send**.



The response shows that the API Gateway Lambda authorizer returns a **200 OK** response and successfully authorizes the call to access the HTTP endpoint (<http://httpbin.org/get>) integrated with the method.

2. Still in Postman, change the Lambda authorization token header value to deny. Choose **Send**.

The screenshot shows the Postman interface for testing an API endpoint. The URL is set to `https://<api-id>.execute-api.<region>.amazonaws.com/test`. In the 'Headers' tab, there is one entry: 'Authorization' with the value 'deny'. The 'Body' tab is selected. The response status is 403 Forbidden, and the response body is a JSON object with a single key 'Message': "User is not authorized to access this resource".

Path variable key Value
URL Parameter Key Value
Authorization Headers (1) Body Pre-request script Tests
Auth Header Value Presets
Body Cookies Headers (9) Tests (0/0) Status 403 Forbidden Time 868 ms
Pretty Raw Preview JSON

```
1 "Message": "User is not authorized to access this resource"
```

The response shows that the API Gateway Lambda authorizer returns a **403 Forbidden** response without authorizing the call to access the HTTP endpoint.

3. In Postman, change the Lambda authorization token header value to unauthorized and choose **Send**.

The screenshot shows the Postman interface with a GET request to `https://<api-id>.execute-api.<region>.amazonaws.com/test`. The 'Headers (1)' tab is selected, showing an 'Auth' entry with the value 'unauthorized'. The 'Body' tab is selected, displaying a JSON response with the message "Unauthorized". The status bar at the bottom shows "Status 401 Unauthorized".

```
1 {
2   "message": "Unauthorized"
3 }
```

The response shows that API Gateway returns a **401 Unauthorized** response without authorizing the call to access the HTTP endpoint.

4. Now, change the Lambda authorization token header value to fail. Choose **Send**.

The screenshot shows the Postman interface with the same GET request. The 'Headers (1)' tab is selected, showing an 'Auth' entry with the value 'fail'. The 'Body' tab is selected, displaying a JSON response with the message "null". The status bar at the bottom shows "Status 500 Internal Server Error".

```
1 {
2   "message": null
3 }
```

The response shows that API Gateway returns a **500 Internal Server Error** response without authorizing the call to access the HTTP endpoint.

Configure a cross-account API Gateway Lambda authorizer

You can now also use an AWS Lambda function from a different AWS account as your API authorizer function. Each account can be in any region where Amazon API Gateway is available. The Lambda authorizer function can use bearer token authentication strategies such as OAuth or SAML. This makes it easy to centrally manage and share a central Lambda authorizer function across multiple API Gateway APIs.

In this section, we show how to configure a cross-account Lambda authorizer function using the Amazon API Gateway console.

These instructions assume that you already have an API Gateway API in one AWS account and a Lambda authorizer function in another account.

Configure a cross-account Lambda authorizer using the API Gateway console

Log in to the Amazon API Gateway console in the account that has your API in it, and then do the following:

1. Choose your API, and then in the main navigation pane, choose **Authorizers**.
2. Choose **Create authorizer**.
3. For **Authorizer name**, enter a name for the authorizer.
4. For **Authorizer type**, select **Lambda**.
5. For **Lambda Function**, enter the full ARN for the Lambda authorizer function that you have in your second account.

 **Note**

In the Lambda console, you can find the ARN for your function in the upper right corner of the console window.

6. A warning with an `aws lambda add-permission` command string will appear. This policy grants API Gateway permission to invoke the authorizer Lambda function. Copy the command and save it for later. You run the command after you create the authorizer.

7. For **Lambda event payload**, select either **Token** for a TOKEN authorizer or **Request** for a REQUEST authorizer.
8. Depending on the choice of the previous step, do one of the following:
 - a. For the **Token** option, do the following:
 - For **Token source**, enter the header name that contains the authorization token. The API client must include a header of this name to send the authorization token to the Lambda authorizer.
 - Optionally, for **Token validation**, enter a RegEx statement. API Gateway performs initial validation of the input token against this expression and invokes the authorizer upon successful validation. This helps reduce calls to your API.
 - To cache the authorization policy generated by the authorizer, keep **Authorization caching** turned on. When policy caching is enabled, you can choose to modify the **TTL** value. Setting the **TTL** to zero disables policy caching. When policy caching is enabled, the header name specified in **Token source** becomes the cache key. If multiple values are passed to this header in the request, all values will become the cache key, with the order preserved.

 **Note**

The default **TTL** value is 300 seconds. The maximum value is 3600 seconds; this limit cannot be increased.

- b. For the **Request** option, do the following:

- For **Identity source type**, select a parameter type. Supported parameter types are Header, Query string, Stage variable, and Context. To add more identity sources, choose **Add parameter**.
- To cache the authorization policy generated by the authorizer, keep **Authorization caching** turned on. When policy caching is enabled, you can choose to modify the **TTL** value. Setting the **TTL** to zero disables policy caching.

API Gateway uses the specified identity sources as the request authorizer caching key. When caching is enabled, API Gateway calls the authorizer's Lambda function only after successfully verifying that all the specified identity sources are present at runtime.

If a specified identity source is missing, null, or empty, API Gateway returns a 401 Unauthorized response without calling the authorizer Lambda function.

When multiple identity sources are defined, they are all used to derive the authorizer's cache key. Changing any of the cache key parts causes the authorizer to discard the cached policy document and generate a new one. If a header with multiple values is passed in the request, then all values will be part of the cache key, with the order preserved.

- When caching is turned off, it is not necessary to specify an identity source.

 **Note**

To enable caching, your authorizer must return a policy that is applicable to all methods across an API. To enforce method-specific policy, you can turn off **Authorization caching**.

9. Choose **Create authorizer**.
10. Paste the `aws lambda add-permission` command string that you copied in a previous step into an AWS CLI window that is configured for your second account. Replace `AUTHORIZER_ID` with your authorizer's ID. This will grant your first account access to your second account's Lambda authorizer function.

Control access based on an identity's attributes with Verified Permissions

Use Amazon Verified Permissions to control access to your API Gateway API. When you use API Gateway with Verified Permissions, Verified Permissions creates a Lambda authorizer that uses fine-grained authorization decisions to control access to your API. Verified Permissions authorizes callers based on a policy store schema and policies using the Cedar policy language to define fine-grained permissions for application users. For more information, see [Create a policy store with a connected API and identity provider](#) in the *Amazon Verified Permissions User Guide*.

Verified Permissions supports Amazon Cognito user pools or OpenID Connect (OIDC) identity providers as identity sources. Verified Permissions presumes that the principal has been previously identified and authenticated. Verified Permissions is only supported for Regional and edge-optimized REST APIs.

Create a Lambda authorizer using Verified Permissions

Verified Permissions creates a Lambda authorizer to determine if a principal is allowed to perform an action on your API. You create the Cedar policy that Verified Permissions uses to perform its authorization tasks.

The following is an example Cedar policy that allows access to invoke an API based on the Amazon Cognito user pool, us-east-1_ABC1234 for the developer group on the GET /users resource of an API. Verified Permissions determines group membership by parsing the bearer token for the caller's identity.

```
permit(  
    principal in MyAPI::UserGroup::"us-east-1_ABC1234|developer",  
    action in [ MyAPI::Action::"get /users" ],  
    resource  
)
```

Optionally, Verified Permissions can attach the authorizer to the methods of your API. On production stages for your API, we recommend that you don't allow Verified Permissions to attach the authorizer for you.

The following list show how to configure Verified Permissions to attach or not to attach the Lambda authorizer to the method request of your API's methods.

Attach the authorizer for you (AWS Management Console)

When you choose **Create policy store** in the Verified Permissions console, on the **Deploy app integration** page, choose **Now**.

Don't attach the authorizer for you (AWS Management Console)

When you choose **Create policy store** in the Verified Permissions console, on the **Deploy app integration** page, choose **Later**.

Verified Permissions still creates a Lambda authorizer for you. The Lambda authorizer starts with AVPAuthorizerLambda-. For more instructions on how to attach your authorizer on a method, see [the section called "Configure a method to use a Lambda authorizer \(console\)"](#).

Attach the authorizer for you (CloudFormation)

In the Verified Permissions-generated CloudFormation template, in the Conditions section, set "Ref": "shouldAttachAuthorizer" to true.

Don't attach the authorizer for you (CloudFormation)

In the Verified Permissions-generated CloudFormation template, in the Conditions section, set "Ref": "shouldAttachAuthorizer" to false.

Verified Permissions still creates a Lambda authorizer for you. The Lambda authorizer starts with AVPAuthorizerLambda-. For more instructions on how to attach your authorizer on a method, see [the section called “Configure a method to use a Lambda authorizer \(AWS CLI\)”](#).

Call a Lambda authorizer using Verified Permissions

You can call your Lambda authorizer by providing an identity or access token in the Authorization header. For more information, see [the section called “Call an API with Lambda authorizers”](#).

API Gateway caches the policy that your Lambda authorizer returns for 120 seconds. You can modify the TTL in the API Gateway console or by using the AWS CLI.

Control access to REST APIs using Amazon Cognito user pools as an authorizer

As an alternative to using [IAM roles and policies](#) or [Lambda authorizers](#) (formerly known as custom authorizers), you can use an [Amazon Cognito user pool](#) to control who can access your API in Amazon API Gateway.

To use an Amazon Cognito user pool with your API, you must first create an authorizer of the COGNITO_USER_POOLS type and then configure an API method to use that authorizer. After the API is deployed, the client must first sign the user in to the user pool, obtain an [identity or access token](#) for the user, and then call the API method with one of the tokens, which are typically set to the request's Authorization header. The API call succeeds only if the required token is supplied and the supplied token is valid, otherwise, the client isn't authorized to make the call because the client did not have credentials that could be authorized.

The identity token is used to authorize API calls based on identity claims of the signed-in user. The access token is used to authorize API calls based on the custom scopes of specified access-protected resources. For more information, see [Using Tokens with User Pools](#) and [Resource Server and Custom Scopes](#).

To create and configure an Amazon Cognito user pool for your API, you perform the following tasks:

- Use the Amazon Cognito console, CLI/SDK, or API to create a user pool—or use one that's owned by another AWS account.
- Use the API Gateway console, CLI/SDK, or API to create an API Gateway authorizer with the chosen user pool.
- Use the API Gateway console, CLI/SDK, or API to enable the authorizer on selected API methods.

To call any API methods with a user pool enabled, your API clients perform the following tasks:

- Use the Amazon Cognito CLI/SDK or API to sign a user in to the chosen user pool, and obtain an identity token or access token. To learn more about using the SDKs, see [Code examples for Amazon Cognito using AWS SDKs](#).
- Use a client-specific framework to call the deployed API Gateway API and supply the appropriate token in the Authorization header.

As the API developer, you must provide your client developers with the user pool ID, a client ID, and possibly the associated client secrets that are defined as part of the user pool.

 **Note**

To let a user sign in using Amazon Cognito credentials and also obtain temporary credentials to use with the permissions of an IAM role, use [Amazon Cognito Federated Identities](#). For each API resource endpoint HTTP method, set the authorization type, category Method Execution, to AWS_IAM.

In this section, we describe how to create a user pool, how to integrate an API Gateway API with the user pool, and how to invoke an API that's integrated with the user pool.

Topics

- [Create an Amazon Cognito user pool for a REST API](#)
- [Integrate a REST API with an Amazon Cognito user pool](#)
- [Call a REST API integrated with an Amazon Cognito user pool](#)
- [Configure cross-account Amazon Cognito authorizer for a REST API using the API Gateway console](#)
- [Create an Amazon Cognito authorizer for a REST API using CloudFormation](#)

Create an Amazon Cognito user pool for a REST API

Before integrating your API with a user pool, you must create the user pool in Amazon Cognito. Your user pool configuration must follow all [resource quotas for Amazon Cognito](#). All user-defined Amazon Cognito variables such as groups, users, and roles should use only alphanumeric characters. For instructions on how to create a user pool, see [Tutorial: Creating a user pool](#) in the *Amazon Cognito Developer Guide*.

Note the user pool ID, client ID, and any client secret. The client must provide them to Amazon Cognito for the user to register with the user pool, to sign in to the user pool, and to obtain an identity or access token to be included in requests to call API methods that are configured with the user pool. Also, you must specify the user pool name when you configure the user pool as an authorizer in API Gateway, as described next.

If you're using access tokens to authorize API method calls, be sure to configure the app integration with the user pool to set up the custom scopes that you want on a given resource server. For more information about using tokens with Amazon Cognito user pools, see [Using Tokens with User Pools](#). For more information about resource servers, see [Defining Resource Servers for Your User Pool](#).

Note the configured resource server identifiers and custom scope names. You need them to construct the access scope full names for **OAuth Scopes**, which is used by the COGNITO_USER_POOLS authorizer.

The screenshot shows the AWS Cognito console interface. The left sidebar has a navigation menu with sections like User management, Authentication, Security, Branding, and Identity pools. The main content area is titled 'Domain' under 'User pools'. It shows two tabs: 'Cognito domain' (selected) and 'Custom domain'. Under 'Cognito domain', there's a 'Domain' field with a value of '-' and a 'Branding version' field with a value of '-'. Under 'Custom domain', there's also a 'Domain' field with a value of '-' and a 'Branding version' field with a value of '-'. Below this is a section titled 'Resource servers (1)' with a 'Create resource server' button. A table lists one resource server named 'PetStore' with the URL 'https://my-petstore-api.example.com'. The 'Custom scopes' column for this row shows '2 custom scopes'. The entire 'Resource servers' section is highlighted with a red border.

Integrate a REST API with an Amazon Cognito user pool

After creating an Amazon Cognito user pool, in API Gateway, you must then create a COGNITO_USER_POOLS authorizer that uses the user pool. The following procedure shows you how to do this using the API Gateway console.

Note

You can use the [CreateAuthorizer](#) action to create a COGNITO_USER_POOLS authorizer that uses multiple user pools. You can use up to 1,000 user pools for one COGNITO_USER_POOLS authorizer. This limit cannot be increased.

Important

After performing any of the procedures below, you'll need to deploy or redeploy your API to propagate the changes. For more information about deploying your API, see [Deploy REST APIs in API Gateway](#).

To create a COGNITO_USER_POOLS authorizer by using the API Gateway console

1. Create a new API, or select an existing API in API Gateway.
2. In the main navigation pane, choose **Authorizers**.
3. Choose **Create authorizer**.
4. To configure the new authorizer to use a user pool, do the following:
 - a. For **Authorizer name**, enter a name.
 - b. For **Authorizer type**, select **Cognito**.
 - c. For **Cognito user pool**, choose the AWS Region where you created your Amazon Cognito and select an available user pool.

You can use a stage variable to define your user pool. Use the following format for your user pool: `arn:aws:cognito-idp:us-east-2:111122223333:userpool/${stageVariables.MyUserPool}`.

- d. For **Token source**, enter **Authorization** as the header name to pass the identity or access token that's returned by Amazon Cognito when a user signs in successfully.

- e. (Optional) Enter a regular expression in the **Token validation** field to validate the aud (audience) field of the identity token before the request is authorized with Amazon Cognito. Note that when using an access token this validation rejects the request due to the access token not containing the aud field.
 - f. Choose **Create authorizer**.
5. After creating the COGNITO_USER_POOLS authorizer, you can test invoke it by supplying an identity token that's provisioned from the user pool. You can't use an access token to test invoke your authorizer.

You can obtain this identity token by calling the [Amazon Cognito Identity SDK](#) to perform user sign-in. You can also use the [InitiateAuth](#) action. If you do not configure any **Authorization scopes**, API Gateway treats the supplied token as an identity token.

The preceding procedure creates a COGNITO_USER_POOLS authorizer that uses the newly created Amazon Cognito user pool. Depending on how you enable the authorizer on an API method, you can use either an identity token or an access token that's provisioned from the integrated user pool.

To configure a COGNITO_USER_POOLS authorizer on methods

1. Choose **Resources**. Choose a new method or choose an existing method. If necessary, create a resource.
2. On the **Method request** tab, under **Method request settings**, choose **Edit**.
3. For **Authorizer**, from the dropdown menu, select the **Amazon Cognito user pool authorizers** you just created.
4. To use an identity token, do the following:
 - a. Keep **Authorization Scopes** empty.
 - b. If needed, in the **Integration request**, add the
`$context.authorizer.claims['property-name']` or
`$context.authorizer.claims.property-name` expressions in a body-mapping template to pass the specified identity claims property from the user pool to the backend. For simple property names, such as sub or custom-sub, the two notations are identical. For complex property names, such as custom:role, you can't use the dot notation. For example, the following mapping expressions pass the claim's [standard fields](#) of sub and email to the backend:

```
{  
  "context" : {  
    "sub" : "$context.authorizer.claims.sub",  
    "email" : "$context.authorizer.claims.email"  
  }  
}
```

If you declared a custom claim field when you configured a user pool, you can follow the same pattern to access the custom fields. The following example gets a custom `role` field of a claim:

```
{  
  "context" : {  
    "role" : "$context.authorizer.claims.role"  
  }  
}
```

If the custom claim field is declared as `custom:role`, use the following example to get the claim's property:

```
{  
  "context" : {  
    "role" : "$context.authorizer.claims['custom:role']"  
  }  
}
```

5. To use an access token, do the following:

- For **Authorization Scopes**, enter one or more full names of a scope that has been configured when the Amazon Cognito user pool was created. For example, following the example given in [Create an Amazon Cognito user pool for a REST API](#), one of the scopes is <https://my-petstore-api.example.com/cats.read>.

At runtime, the method call succeeds if any scope that's specified on the method in this step matches a scope that's claimed in the incoming token. Otherwise, the call fails with a `401 Unauthorized` response.

- Choose **Save**.

6. Repeat these steps for other methods that you choose.

With the COGNITO_USER_POOLS authorizer, if the **OAuth Scopes** option isn't specified, API Gateway treats the supplied token as an identity token and verifies the claimed identity against the one from the user pool. Otherwise, API Gateway treats the supplied token as an access token and verifies the access scopes that are claimed in the token against the authorization scopes declared on the method.

Instead of using the API Gateway console, you can also enable an Amazon Cognito user pool on a method by specifying an OpenAPI definition file and importing the API definition into API Gateway.

To import a COGNITO_USER_POOLS authorizer with an OpenAPI definition file

1. Create (or export) an OpenAPI definition file for your API.
2. Specify the COGNITO_USER_POOLS authorizer (MyUserPool) JSON definition as part of the securitySchemes section in OpenAPI 3.0 or the securityDefinitions section in Open API 2.0 as follows:

OpenAPI 3.0

```
"securitySchemes": {  
    "MyUserPool": {  
        "type": "apiKey",  
        "name": "Authorization",  
        "in": "header",  
        "x-amazon-apigateway-authType": "cognito_user_pools",  
        "x-amazon-apigateway-authorizer": {  
            "type": "cognito_user_pools",  
            "providerARNs": [  
                "arn:aws:cognito-idp:{region}:{account_id}:userpool/{user_pool_id}"  
            ]  
        }  
    }  
}
```

OpenAPI 2.0

```
"securityDefinitions": {  
    "MyUserPool": {  
        "type": "apiKey",  
        "name": "Authorization",  
        "in": "header",  
        "x-amazon-apigateway-authType": "cognito_user_pools",  
        "x-amazon-apigateway-authorizer": {  
            "type": "cognito_user_pools",  
            "providerARNs": [  
                "arn:aws:cognito-idp:{region}:{account_id}:userpool/{user_pool_id}"  
            ]  
        }  
    }  
}
```

```
        "type": "cognito_user_pools",
        "providerARNs": [
            "arn:aws:cognito-idp:{region}:{account_id}:userpool/{user_pool_id}"
        ]
    }
}
```

3. To use the identity token for method authorization, add { "MyUserPool": [] } to the security definition of the method, as shown in the following GET method on the root resource.

```
"paths": {
    "/": {
        "get": {
            "consumes": [
                "application/json"
            ],
            "produces": [
                "text/html"
            ],
            "responses": {
                "200": {
                    "description": "200 response",
                    "headers": {
                        "Content-Type": {
                            "type": "string"
                        }
                    }
                }
            },
            "security": [
                {
                    "MyUserPool": []
                }
            ],
            "x-amazon-apigateway-integration": {
                "type": "mock",
                "responses": {
                    "default": {
                        "statusCode": "200",
                        "responseParameters": {
                            "method.response.header.Content-Type": "'text/html'"
                        }
                    }
                }
            }
        }
    }
}
```

```
        },
      },
      "requestTemplates": {
        "application/json": "{\"statusCode\": 200}"
      },
      "passthroughBehavior": "when_no_match"
    }
  },
  ...
}
```

4. To use the access token for method authorization, change the above security definition to { "MyUserPool": [resource-server/scope, ...] }:

```
"paths": {
  "/": {
    "get": {
      "consumes": [
        "application/json"
      ],
      "produces": [
        "text/html"
      ],
      "responses": {
        "200": {
          "description": "200 response",
          "headers": {
            "Content-Type": {
              "type": "string"
            }
          }
        }
      }
    },
    "security": [
      {
        "MyUserPool": ["https://my-petstore-api.example.com/cats.read",
                      "http://my.resource.com/file.read"]
      }
    ],
    "x-amazon-apigateway-integration": {
      "type": "mock",
      "responses": {
        "default": {

```

```
        "statusCode": "200",
        "responseParameters": {
            "method.response.header.Content-Type": "'text/html'"
        },
    },
},
"requestTemplates": {
    "application/json": "{\"statusCode\": 200}"
},
"passthroughBehavior": "when_no_match"
}
},
...
}
```

5. If needed, you can set other API configuration settings by using the appropriate OpenAPI definitions or extensions. For more information, see [OpenAPI extensions for API Gateway](#).

Call a REST API integrated with an Amazon Cognito user pool

To call a method with a user pool authorizer configured, the client must do the following:

- Enable the user to sign up with the user pool.
- Enable the user to sign in to the user pool.
- Obtain an [identity or access token](#) of the signed-in user from the user pool.
- Include the token in the Authorization header (or another header you specified when you created the authorizer).

You can use [AWS Amplify](#) to perform these tasks. See [Integrating Amazon Cognito With Web and Mobile Apps](#) for more information.

- For Android, see [Getting Started with Amplify for Android](#).
- To use iOS see [Getting started with Amplify for iOS](#).
- To use JavaScript, see [Getting Started with Amplify for Javascript](#).

Configure cross-account Amazon Cognito authorizer for a REST API using the API Gateway console

You can now also use a Amazon Cognito user pool from a different AWS account as your API authorizer. The Amazon Cognito user pool can use bearer token authentication strategies such as OAuth or SAML. This makes it easy to centrally manage and share a central Amazon Cognito user pool authorizer across multiple API Gateway APIs.

In this section, we show how to configure a cross-account Amazon Cognito user pool using the Amazon API Gateway console.

These instructions assume that you already have an API Gateway API in one AWS account and a Amazon Cognito user pool in another account.

Create a cross-account Amazon Cognito authorizer for a REST API

Log in to the Amazon API Gateway console in the account that has your API in it, and then do the following:

1. Create a new API, or select an existing API in API Gateway.
2. In the main navigation pane, choose **Authorizers**.
3. Choose **Create authorizer**.
4. To configure the new authorizer to use a user pool, do the following:
 - a. For **Authorizer name**, enter a name.
 - b. For **Authorizer type**, select **Cognito**.
 - c. For **Cognito user pool**, enter the full ARN for the user pool that you have in your second account.

 **Note**

In the Amazon Cognito console, you can find the ARN for your user pool in the **Pool ARN** field of the **General Settings** pane.

- d. For **Token source**, enter **Authorization** as the header name to pass the identity or access token that's returned by Amazon Cognito when a user signs in successfully.
- e. (Optional) Enter a regular expression in the **Token validation** field to validate the aud (audience) field of the identity token before the request is authorized with Amazon

Cognito. Note that when using an access token this validation rejects the request due to the access token not containing the aud field.

- f. Choose **Create authorizer**.

Create an Amazon Cognito authorizer for a REST API using CloudFormation

You can use CloudFormation to create an Amazon Cognito user pool and an Amazon Cognito authorizer. The example CloudFormation template does the following:

- Create an Amazon Cognito user pool. The client must first sign the user in to the user pool and obtain an [identity or access token](#). If you're using access tokens to authorize API method calls, be sure to configure the app integration with the user pool to set up the custom scopes that you want on a given resource server.
- Creates an API Gateway API with a GET method.
- Creates an Amazon Cognito authorizer that uses the Authorization header as the token source.

```
AWSTemplateFormatVersion: 2010-09-09
Resources:
  UserPool:
    Type: AWS::Cognito::UserPool
    Properties:
      AccountRecoverySetting:
        RecoveryMechanisms:
          - Name: verified_phone_number
            Priority: 1
          - Name: verified_email
            Priority: 2
      AdminCreateUserConfig:
        AllowAdminCreateUserOnly: true
      EmailVerificationMessage: The verification code to your new account is #####
      EmailVerificationSubject: Verify your new account
      SmsVerificationMessage: The verification code to your new account is #####
      VerificationMessageTemplate:
        DefaultEmailOption: CONFIRM_WITH_CODE
        EmailMessage: The verification code to your new account is #####
        EmailSubject: Verify your new account
        SmsMessage: The verification code to your new account is #####
  UpdateReplacePolicy: Retain
```

```
DeletionPolicy: Retain
CogAuthorizer:
  Type: AWS::ApiGateway::Authorizer
  Properties:
    Name: CognitoAuthorizer
    RestApiId:
      Ref: Api
    Type: COGNITO_USER_POOLS
    IdentitySource: method.request.header.Authorization
    ProviderARNs:
      - Fn::GetAtt:
          - UserPool
          - Arn
Api:
  Type: AWS::ApiGateway::RestApi
  Properties:
    Name: MyCogAuthApi
ApiDeployment:
  Type: AWS::ApiGateway::Deployment
  Properties:
    RestApiId:
      Ref: Api
    DependsOn:
      - CogAuthorizer
      - ApiGET
ApiDeploymentStageprod:
  Type: AWS::ApiGateway::Stage
  Properties:
    RestApiId:
      Ref: Api
    DeploymentId:
      Ref: ApiDeployment
    StageName: prod
ApiGET:
  Type: AWS::ApiGateway::Method
  Properties:
    HttpMethod: GET
    ResourceId:
      Fn::GetAtt:
        - Api
        - RootResourceId
    RestApiId:
      Ref: Api
    AuthorizationType: COGNITO_USER_POOLS
```

```
AuthorizerId:  
  Ref: CogAuthorizer  
Integration:  
  IntegrationHttpMethod: GET  
  Type: HTTP_PROXY  
  Uri: http://petstore-demo-endpoint.execute-api.com/petstore/pets  
Outputs:  
  ApiEndpoint:  
    Value:  
      Fn::Join:  
        - ""  
        - - https://  
        - Ref: Api  
        - .execute-api.  
        - Ref: AWS::Region  
        - ."  
        - Ref: AWS::URLSuffix  
        - /  
        - Ref: ApiDeploymentStageprod  
        - /
```

Integrations for REST APIs in API Gateway

After setting up an API method, you must integrate it with an endpoint in the backend. A backend endpoint is also referred to as an integration endpoint and can be a Lambda function, an HTTP webpage, or an AWS service action.

As with the API method, the API integration has an integration request and an integration response. An integration request encapsulates an HTTP request received by the backend. It might or might not differ from the method request submitted by the client. An integration response is an HTTP response encapsulating the output returned by the backend.

Setting up an integration request involves the following: configuring how to pass client-submitted method requests to the backend; configuring how to transform the request data, if necessary, to the integration request data; and specifying which Lambda function to call, specifying which HTTP server to forward the incoming request to, or specifying the AWS service action to invoke.

Setting up an integration response (applicable to non-proxy integrations only) involves the following: configuring how to pass the backend-returned result to a method response of a given status code, configuring how to transform specified integration response parameters to

preconfigured method response parameters, and configuring how to map the integration response body to the method response body according to the specified body-mapping templates.

Programmatically, an integration request is encapsulated by the [Integration](#) resource and an integration response by the [IntegrationResponse](#) resource of API Gateway.

To set up an integration request, you create an [Integration](#) resource and use it to configure the integration endpoint URL. You then set the IAM permissions to access the backend, and specify mappings to transform the incoming request data before passing it to the backend. To set up an integration response for non-proxy integration, you create an [IntegrationResponse](#) resource and use it to set its target method response. You then configure how to map backend output to the method response.

Topics

- [Set up an integration request in API Gateway](#)
- [Set up an integration response in API Gateway](#)
- [Lambda integrations for REST APIs in API Gateway](#)
- [HTTP integrations for REST APIs in API Gateway](#)
- [Stream the integration response for your proxy integrations in API Gateway](#)
- [Private integrations for REST APIs in API Gateway](#)
- [Mock integrations for REST APIs in API Gateway](#)

Set up an integration request in API Gateway

To set up an integration request, you perform the following required and optional tasks:

1. Choose an integration type that determines how method request data is passed to the backend.
2. For non-mock integrations, specify an HTTP method and the URI of the targeted integration endpoint, except for the MOCK integration.
3. For integrations with Lambda functions and other AWS service actions, set an IAM role with required permissions for API Gateway to call the backend on your behalf.
4. For non-proxy integrations, set necessary parameter mappings to map predefined method request parameters to appropriate integration request parameters.
5. For non-proxy integrations, set necessary body mappings to map the incoming method request body of a given content type according to the specified mapping template.

6. For non-proxy integrations, specify the condition under which the incoming method request data is passed through to the backend as-is.
7. Optionally, specify how to handle type conversion for a binary payload.
8. Optionally, declare a cache namespace name and cache key parameters to enable API caching.

Performing these tasks involves creating an [Integration](#) resource of API Gateway and setting appropriate property values. You can do so using the API Gateway console, AWS CLI commands, an AWS SDK, or the API Gateway REST API.

Topics

- [Basic tasks of an API integration request](#)
- [Choose an API Gateway API integration type](#)
- [Set up a proxy integration with a proxy resource](#)
- [Set up an API integration request using the API Gateway console](#)

Basic tasks of an API integration request

An integration request is an HTTP request that API Gateway submits to the backend, passing along the client-submitted request data, and transforming the data, if necessary. The HTTP method (or verb) and URI of the integration request are dictated by the backend (that is, the integration endpoint). They can be the same as or different from the method request's HTTP method and URI, respectively.

For example, when a Lambda function returns a file that is fetched from Amazon S3, you can expose this operation intuitively as a GET method request to the client even though the corresponding integration request requires that a POST request be used to invoke the Lambda function. For an HTTP endpoint, it is likely that the method request and the corresponding integration request both use the same HTTP verb. However, this is not required. You can integrate the following method request:

```
GET /{var}?query=value
Host: api.domain.net
```

With the following integration request:

```
POST /
Host: service.domain.com
```

```
Content-Type: application/json  
Content-Length: ...  
  
{  
    path: "{var}'s value",  
    type: "value"  
}
```

As an API developer, you can use whatever HTTP verb and URI for a method request suit your requirements. But you must follow the requirements of the integration endpoint. When the method request data differs from the integration request data, you can reconcile the difference by providing mappings from the method request data to the integration request data.

In the preceding examples, the mapping translates the path variable ({var}) and the query parameter (query) values of the GET method request to the values of the integration request's payload properties of path and type. Other mappable request data includes request headers and body. These are described in [the section called “Parameter mapping”](#).

When setting up the HTTP or HTTP proxy integration request, you assign the backend HTTP endpoint URL as the integration request URI value. For example, in the PetStore API, the method request to get a page of pets has the following integration request URI:

```
http://petstore-demo-endpoint.execute-api.com/petstore/pets
```

When setting up the Lambda or Lambda proxy integration, you assign the Amazon Resource Name (ARN) for invoking the Lambda function as the integration request URI value. This ARN has the following format:

```
arn:aws:apigateway:api-region:lambda:path//2015-03-31/functions/arn:aws:lambda:Lambda-region:account-id:function:Lambda-function-name/invocations
```

The part after arn:aws:apigateway:*api-region*:lambda:path/, namely, /2015-03-31/functions/arn:aws:lambda:*Lambda-region:account-id*:function:*Lambda-function-name*/invocations, is the REST API URI path of the Lambda [Invoke](#) action. If you use the API Gateway console to set up the Lambda integration, API Gateway creates the ARN and assigns it to the integration URI after prompting you to choose the *Lambda-function-name* from a region.

When setting up the integration request with another AWS service action, the integration request URI is also an ARN, similar to the integration with the Lambda Invoke action. For example, for the

integration with the [GetBucket](#) action of Amazon S3, the integration request URI is an ARN of the following format:

```
arn:aws:apigateway:api-region:s3:path/{bucket}
```

The integration request URI is of the path convention to specify the action, where *{bucket}* is the placeholder of a bucket name. Alternatively, an AWS service action can be referenced by its name. Using the action name, the integration request URI for the GetBucket action of Amazon S3 becomes the following:

```
arn:aws:apigateway:api-region:s3:action/GetBucket
```

With the action-based integration request URI, the bucket name (*{bucket}*) must be specified in the integration request body ({ Bucket: "*{bucket}*" }), following the input format of GetBucket action.

For AWS integrations, you must also configure [credentials](#) to allow API Gateway to call the integrated actions. You can create a new or choose an existing IAM role for API Gateway to call the action and then specify the role using its ARN. The following shows an example of this ARN:

```
arn:aws:iam::account-id:role/iam-role-name
```

This IAM role must contain a policy to allow the action to be executed. It must also have API Gateway declared (in the role's trust relationship) as a trusted entity to assume the role. Such permissions can be granted on the action itself. They are known as resource-based permissions. For the Lambda integration, you can call the Lambda's [addPermission](#) action to set the resource-based permissions and then set credentials to null in the API Gateway integration request.

We discussed the basic integration setup. Advanced settings involve mapping method request data to the integration request data. For more information, see [the section called “Data transformations”](#).

Choose an API Gateway API integration type

You choose an API integration type according to the types of integration endpoint you work with and how you want data to pass to and from the integration endpoint. For a Lambda function, you can have the Lambda proxy integration, or the Lambda custom integration. For an HTTP endpoint,

you can have the HTTP proxy integration or the HTTP custom integration. For an AWS service action, you have the AWS integration of the non-proxy type only. API Gateway also supports the mock integration, where API Gateway serves as an integration endpoint to respond to a method request.

The Lambda custom integration is a special case of the AWS integration, where the integration endpoint corresponds to the [function-invoking action](#) of the Lambda service.

Programmatically, you choose an integration type by setting the [type](#) property on the [Integration](#) resource. For the Lambda proxy integration, the value is AWS_PROXY. For the Lambda custom integration and all other AWS integrations, it is AWS. For the HTTP proxy integration and HTTP integration, the value is HTTP_PROXY and HTTP, respectively. For the mock integration, the type value is MOCK.

The Lambda proxy integration supports a streamlined integration setup with a single Lambda function. The setup is simple and can evolve with the backend without having to tear down the existing setup. For these reasons, it is highly recommended for integration with a Lambda function.

In contrast, the Lambda custom integration allows for reuse of configured mapping templates for various integration endpoints that have similar requirements of the input and output data formats. The setup is more involved and is recommended for more advanced application scenarios.

Similarly, the HTTP proxy integration has a streamlined integration setup and can evolve with the backend without having to tear down the existing setup. The HTTP custom integration is more involved to set up, but allows for reuse of configured mapping templates for other integration endpoints.

The following list summarizes the supported integration types:

- AWS: This type of integration lets an API expose AWS service actions. In AWS integration, you must configure both the integration request and integration response and set up necessary data mappings from the method request to the integration request, and from the integration response to the method response.
- AWS_PROXY: This type of integration lets an API method be integrated with the Lambda function invocation action with a flexible, versatile, and streamlined integration setup. This integration relies on direct interactions between the client and the integrated Lambda function.

With this type of integration, also known as the Lambda proxy integration, you do not set the integration request or the integration response. API Gateway passes the incoming request

from the client as the input to the backend Lambda function. The integrated Lambda function takes the [input of this format](#) and parses the input from all available sources, including request headers, URL path variables, query string parameters, and applicable body. The function returns the result following this [output format](#).

This is the preferred integration type to call a Lambda function through API Gateway and is not applicable to any other AWS service actions, including Lambda actions other than the function-invoking action.

- **HTTP:** This type of integration lets an API expose HTTP endpoints in the backend. With the HTTP integration, also known as the HTTP custom integration, you must configure both the integration request and integration response. You must set up necessary data mappings from the method request to the integration request, and from the integration response to the method response.
- **HTTP_PROXY:** The HTTP proxy integration allows a client to access the backend HTTP endpoints with a streamlined integration setup on single API method. You do not set the integration request or the integration response. API Gateway passes the incoming request from the client to the HTTP endpoint and passes the outgoing response from the HTTP endpoint to the client.
- **MOCK:** This type of integration lets API Gateway return a response without sending the request further to the backend. This is useful for API testing because it can be used to test the integration set up without incurring charges for using the backend and to enable collaborative development of an API.

In collaborative development, a team can isolate their development effort by setting up simulations of API components owned by other teams by using the MOCK integrations. It is also used to return CORS-related headers to ensure that the API method permits CORS access. In fact, the API Gateway console integrates the OPTIONS method to support CORS with a mock integration. [Gateway responses](#) are other examples of mock integrations.

Set up a proxy integration with a proxy resource

To set up a proxy integration in an API Gateway API with a [proxy resource](#), you perform the following tasks:

- Create a proxy resource with a greedy path variable of `{proxy+}`.
- Set the ANY method on the proxy resource.
- Integrate the resource and method with a backend using the HTTP or Lambda integration type.

Note

Greedy path variables, ANY methods, and proxy integration types are independent features, although they are commonly used together. You can configure a specific HTTP method on a greedy resource or apply non-proxy integration types to a proxy resource.

API Gateway enacts certain restrictions and limitations when handling methods with either a Lambda proxy integration or an HTTP proxy integration. For details, see [the section called "Important notes"](#).

Note

When using proxy integration with a passthrough, API Gateway returns the default Content-Type:application/json header if the content type of a payload is unspecified.

A proxy resource is most powerful when it is integrated with a backend using either HTTP proxy integration or Lambda proxy [integration](#).

HTTP proxy integration with a proxy resource

The HTTP proxy integration, designated by HTTP_PROXY in the API Gateway REST API, is for integrating a method request with a backend HTTP endpoint. With this integration type, API Gateway simply passes the entire request and response between the frontend and the backend, subject to certain [restrictions and limitations](#).

Note

HTTP proxy integration supports multi-valued headers and query strings.

When applying the HTTP proxy integration to a proxy resource, you can set up your API to expose a portion or an entire endpoint hierarchy of the HTTP backend with a single integration setup. For example, suppose the backend of the website is organized into multiple branches of tree nodes off the root node (/site) as: /site/a₀/a₁/.../a_N, /site/b₀/b₁/.../b_M, etc. If you integrate the ANY method on a proxy resource of /api/{proxy+} with the backend endpoints with URL paths

of `/site/{proxy}`, a single integration request can support any HTTP operations (GET, POST, etc.) on any of $[a_0, a_1, \dots, a_N, b_0, b_1, \dots, b_M, \dots]$. If you apply a proxy integration to a specific HTTP method, for example, GET, instead, the resulting integration request works with the specified (that is, GET) operations on any of those backend nodes.

Lambda proxy integration with a proxy resource

The Lambda proxy integration, designated by `AWS_PROXY` in the API Gateway REST API, is for integrating a method request with a Lambda function in the backend. With this integration type, API Gateway applies a default mapping template to send the entire request to the Lambda function and transforms the output from the Lambda function to HTTP responses.

Similarly, you can apply the Lambda proxy integration to a proxy resource of `/api/{proxy+}` to set up a single integration to have a backend Lambda function react individually to changes in any of the API resources under `/api`.

Set up an API integration request using the API Gateway console

An API method setup defines the method and describes its behaviors. To set up a method, you must specify a resource, including the root ("`/`"), on which the method is exposed, an HTTP method (GET, POST, etc.), and how it will be integrated with the targeted backend. The method request and response specify the contract with the calling app, stipulating which parameters the API can receive and what the response looks like.

The following procedures describe how to use the API Gateway console to create an integration request.

Topics

- [Set up a Lambda integration](#)
- [Set up an HTTP integration](#)
- [Set up an AWS service integration](#)
- [Set up a mock integration](#)

Set up a Lambda integration

Use a Lambda function integration to integrate your API with a Lambda function. At the API level, this is an AWS integration type if you create a non-proxy integration, or an `AWS_PROXY` integration type if you create a proxy integration.

To set up a Lambda integration

1. In the **Resources** pane, choose **Create method**.
2. For **Method type**, select an HTTP method.
3. For **Integration type**, choose **Lambda function**.
4. To use a Lambda proxy integration, turn on **Lambda proxy integration**. To learn more about Lambda proxy integrations, see [the section called “Understand Lambda proxy integration”](#).
5. For **Lambda function**, enter the name of the Lambda function.

If you are using a Lambda function in a different Region than your API, select the Region from the dropdown menu and enter the name of the Lambda function. If you are using a cross-account Lambda function, enter the function ARN.

6. To use the default timeout value of 29 seconds, keep **Default timeout** turned on. To set a custom timeout, choose **Default timeout** and enter a timeout value between 50 and 29000 milliseconds.
7. (Optional) You can configure the method request settings using the following dropdown menus. Choose **Method request settings** and configure your method request. For more information, see step 3 of [the section called “Edit a method request in the console”](#).

You can also configure your method request settings after you create your method.

8. Choose **Create method**.

Set up an HTTP integration

Use an HTTP integration to integrate your API with an HTTP endpoint. At the API level, this is the HTTP integration type.

To set up an HTTP integration

1. In the **Resources** pane, choose **Create method**.
2. For **Method type**, select an HTTP method.
3. For **Integration type**, choose **HTTP**.
4. To use an HTTP proxy integration, turn on **HTTP proxy integration**. To learn more about HTTP proxy integrations, see [the section called “Set up HTTP proxy integrations in API Gateway”](#).
5. For **HTTP method**, choose the HTTP method type that most closely matches the method in the HTTP backend.

6. For **Endpoint URL**, enter the URL of the HTTP backend you want this method to use.
7. For **Content handling**, select a content handling behavior.
8. To use the default timeout value of 29 seconds, keep **Default timeout** turned on. To set a custom timeout, choose **Default timeout** and enter a timeout value between 50 and 29000 milliseconds.
9. (Optional) You can configure the method request settings using the following dropdown menus. Choose **Method request settings** and configure your method request. For more information, see step 3 of [the section called “Edit a method request in the console”](#).

You can also configure your method request settings after you create your method.

10. Choose **Create method**.

Set up an AWS service integration

Use an AWS service integration to integrate your API directly with an AWS service. At the API level, this is the AWS integration type.

To set up an API Gateway API to do any of the following:

- Create a new Lambda function.
- Set a resource permission on the Lambda function.
- Perform any other Lambda service actions.

You must choose **AWS service**.

To set up an AWS service integration

1. In the **Resources** pane, choose **Create method**.
2. For **Method type**, select an HTTP method.
3. For **Integration type**, choose **AWS service**.
4. For **AWS Region**, choose the AWS Region you want this method to use to call the action.
5. For **AWS service**, choose the AWS service you want this method to call.
6. For **AWS subdomain**, enter the subdomain used by the AWS service. Typically, you would leave this blank. Some AWS services can support subdomains as part of the hosts. Consult the service documentation for the availability and, if available, details.

7. For **HTTP method**, choose the HTTP method type that corresponds to the action. For HTTP method type, see the API reference documentation for the AWS service you chose for **AWS service**.
8. For **Action type**, select to either **Use action name** to use an API action or **Use path override** to use a custom resource path. For available actions and custom resource paths, see the API reference documentation for the AWS service you chose for **AWS service**.
9. Enter either an **Action name** or **Path override**.
10. For **Execution role**, enter the ARN of the IAM role that the method will use to call the action.

To create the IAM role, you can adapt the instructions in [the section called “Step 1: Create the AWS service proxy execution role”](#). Specify an access policy with the desired number of action and resource statements. For more information, see [the section called “How Amazon API Gateway works with IAM”](#).

For the action and resource statement syntax, see the documentation for the AWS service you chose for **AWS service**.

For the IAM role's trust relationship, specify the following, which enables API Gateway to take action on behalf of your AWS account:

JSON

```
{  
    "Version": "2012-10-17",  
    "Statement": [  
        {  
            "Sid": "",  
            "Effect": "Allow",  
            "Principal": {  
                "Service": "apigateway.amazonaws.com"  
            },  
            "Action": "sts:AssumeRole"  
        }  
    ]  
}
```

11. To use the default timeout value of 29 seconds, keep **Default timeout** turned on. To set a custom timeout, choose **Default timeout** and enter a timeout value between 50 and 29000 milliseconds.

12. (Optional) You can configure the method request settings using the following dropdown menus. Choose **Method request settings** and configure your method request. For more information, see step 3 of [the section called “Edit a method request in the console”](#).

You can also configure your method request settings after you create your method.

13. Choose **Create method**.

Set up a mock integration

Use a mock integration if you want API Gateway to act as your backend to return static responses. At the API level, this is the MOCK integration type. Typically, you can use the MOCK integration when your API is not yet final, but you want to generate API responses to unblock dependent teams for testing. For the OPTION method, API Gateway sets the MOCK integration as default to return CORS-enabling headers for the applied API resource.

To set up a mock integration

1. In the **Resources** pane, choose **Create method**.
2. For **Method type**, select an HTTP method.
3. For **Integration type**, choose **Mock**.
4. (Optional) You can configure the method request settings using the following dropdown menus. Choose **Method request settings** and configure your method request. For more information, see step 3 of [the section called “Edit a method request in the console”](#).

You can also configure your method request settings after you create your method.

5. Choose **Create method**.

Set up an integration response in API Gateway

For a non-proxy integration, you must set up at least one integration response, and make it the default response, to pass the result returned from the backend to the client. You can choose to pass through the result as-is or to transform the integration response data to the method response data if the two have different formats.

For a proxy integration, API Gateway automatically passes the backend output to the client as an HTTP response. You do not set either an integration response or a method response.

To set up an integration response, you perform the following required and optional tasks:

1. Specify an HTTP status code of a method response to which the integration response data is mapped. This is required.
2. Define a regular expression to select backend output to be represented by this integration response. If you leave this empty, the response is the default response that is used to catch any response not yet configured.
3. If needed, declare mappings consisting of key-value pairs to map specified integration response parameters to given method response parameters.
4. If needed, add body-mapping templates to transform given integration response payloads into specified method response payloads.
5. If needed, specify how to handle type conversion for a binary payload.

An integration response is an HTTP response encapsulating the backend response. For an HTTP endpoint, the backend response is an HTTP response. The integration response status code can take the backend-returned status code, and the integration response body is the backend-returned payload. For a Lambda endpoint, the backend response is the output returned from the Lambda function. With the Lambda integration, the Lambda function output is returned as a 200 OK response. The payload can contain the result as JSON data, including a JSON string or a JSON object, or an error message as a JSON object. You can assign a regular expression to the [selectionPattern](#) property to map an error response to an appropriate HTTP error response. For more information about the Lambda function error response, see [Handle Lambda errors in API Gateway](#). With the Lambda proxy integration, the Lambda function must return output of the following format:

```
{  
    statusCode: "...",           // a valid HTTP status code  
    headers: {  
        custom-header: "..."    // any API-specific custom header  
    },  
    body: "...",                // a JSON string.  
    isBase64Encoded: true|false // for binary support  
}
```

There is no need to map the Lambda function response to its proper HTTP response.

To return the result to the client, set up the integration response to pass the endpoint response through as-is to the corresponding method response. Or you can map the endpoint response data to the method response data. The response data that can be mapped includes the response status

code, response header parameters, and response body. If no method response is defined for the returned status code, API Gateway returns a 500 error. For more information, see [Override your API's request and response parameters and status codes for REST APIs in API Gateway](#).

Lambda integrations for REST APIs in API Gateway

You can integrate an API method with a Lambda function using Lambda proxy integration or Lambda non-proxy (custom) integration.

In Lambda proxy integration, the required setup is simple. Set the integration's HTTP method to POST, the integration endpoint URI to the ARN of the Lambda function invocation action of a specific Lambda function, and grant API Gateway permission to call the Lambda function on your behalf.

In Lambda non-proxy integration, in addition to the proxy integration setup steps, you also specify how the incoming request data is mapped to the integration request and how the resulting integration response data is mapped to the method response.

Topics

- [Lambda proxy integrations in API Gateway](#)
- [Set up Lambda custom integrations in API Gateway](#)
- [Set up asynchronous invocation of the backend Lambda function](#)
- [Handle Lambda errors in API Gateway](#)

Lambda proxy integrations in API Gateway

The following section shows how to use a Lambda proxy integration.

Topics

- [Understand API Gateway Lambda proxy integration](#)
- [Support for multi-value headers and query string parameters](#)
- [Input format of a Lambda function for proxy integration](#)
- [Output format of a Lambda function for proxy integration](#)
- [Set up Lambda proxy integration for API Gateway using the AWS CLI](#)
- [Set up a proxy resource with Lambda proxy integration with an OpenAPI definition](#)

Understand API Gateway Lambda proxy integration

Amazon API Gateway Lambda proxy integration is a simple, powerful, and nimble mechanism to build an API with a setup of a single API method. The Lambda proxy integration allows the client to call a single Lambda function in the backend. The function accesses many resources or features of other AWS services, including calling other Lambda functions.

In Lambda proxy integration, when a client submits an API request, API Gateway passes to the integrated Lambda function an [event object](#), except that the order of the request parameters is not preserved. This [request data](#) includes the request headers, query string parameters, URL path variables, payload, and API configuration data. The configuration data can include current deployment stage name, stage variables, user identity, or authorization context (if any). The backend Lambda function parses the incoming request data to determine the response that it returns. For API Gateway to pass the Lambda output as the API response to the client, the Lambda function must return the result in [this format](#).

Because API Gateway doesn't intervene very much between the client and the backend Lambda function for the Lambda proxy integration, the client and the integrated Lambda function can adapt to changes in each other without breaking the existing integration setup of the API. To enable this, the client must follow application protocols enacted by the backend Lambda function.

You can set up a Lambda proxy integration for any API method. But a Lambda proxy integration is more potent when it is configured for an API method involving a generic proxy resource. The generic proxy resource can be denoted by a special templated path variable of `{proxy+}`, the catch-all ANY method placeholder, or both. The client can pass the input to the backend Lambda function in the incoming request as request parameters or applicable payload. The request parameters include headers, URL path variables, query string parameters, and the applicable payload. The integrated Lambda function verifies all of the input sources before processing the request and responding to the client with meaningful error messages if any of the required input is missing.

When calling an API method integrated with the generic HTTP method of ANY and the generic resource of `{proxy+}`, the client submits a request with a particular HTTP method in place of ANY. The client also specifies a particular URL path instead of `{proxy+}`, and includes any required headers, query string parameters, or an applicable payload.

The following list summarizes runtime behaviors of different API methods with the Lambda proxy integration:

- ANY /{proxy+}: The client must choose a particular HTTP method, must set a particular resource path hierarchy, and can set any headers, query string parameters, and applicable payload to pass the data as input to the integrated Lambda function.
- ANY /res: The client must choose a particular HTTP method and can set any headers, query string parameters, and applicable payload to pass the data as input to the integrated Lambda function.
- GET | POST | PUT | ... /{proxy+}: The client can set a particular resource path hierarchy, any headers, query string parameters, and applicable payload to pass the data as input to the integrated Lambda function.
- GET | POST | PUT | ... /res/{path}/...: The client must choose a particular path segment (for the {path} variable) and can set any request headers, query string parameters, and applicable payload to pass input data to the integrated Lambda function.
- GET | POST | PUT | ... /res: The client can choose any request headers, query string parameters, and applicable payload to pass input data to the integrated Lambda function.

Both the proxy resource of {proxy+} and the custom resource of {custom} are expressed as templated path variables. However {proxy+} can refer to any resource along a path hierarchy, while {custom} refers to a particular path segment only. For example, a grocery store might organize its online product inventory by department names, produce categories, and product types. The grocery store's website can then represent available products by the following templated path variables of custom resources: /{department}/{produce-category}/{product-type}. For example, apples are represented by /produce/fruit/apple and carrots by /produce/vegetables/carrot. It can also use /{proxy+} to represent any department, any produce category, or any product type that a customer can search for while shopping in the online store. For example, /{proxy+} can refer to any of the following items:

- /produce
- /produce/fruit
- /produce/vegetables/carrot

To let customers search for any available product, its produce category, and the associated store department, you can expose a single method of GET /{proxy+} with read-only permissions. Similarly, to allow a supervisor to update the produce department's inventory, you can set up another single method of PUT /produce/{proxy+} with read/write permissions. To allow a cashier to update the running total of a vegetable, you can set up a POST /produce/

vegetables/{proxy+} method with read/write permissions. To let a store manager perform any possible action on any available product, the online store developer can expose the ANY / {proxy+} method with read/write permissions. In any case, at run time, the customer or the employee must select a particular product of a given type in a chosen department, a specific produce category in a chosen department, or a specific department.

For more information about setting up API Gateway proxy integrations, see [Set up a proxy integration with a proxy resource](#).

Proxy integration requires that the client have more detailed knowledge of the backend requirements. Therefore, to ensure optimal app performance and user experience, the backend developer must communicate clearly to the client developer the requirements of the backend, and provide a robust error feedback mechanism when the requirements are not met.

Support for multi-value headers and query string parameters

API Gateway supports multiple headers and query string parameters that have the same name. Multi-value headers as well as single-value headers and parameters can be combined in the same requests and responses. For more information, see [Input format of a Lambda function for proxy integration](#) and [Output format of a Lambda function for proxy integration](#).

Input format of a Lambda function for proxy integration

In Lambda proxy integration, API Gateway maps the entire client request to the input event parameter of the backend Lambda function. The following example shows the structure of an event that API Gateway sends to a Lambda proxy integration.

In this example, we assume that the invocation to API Gateway was the following:

```
curl 'https://a1b2c3.execute-api.us-east-1.amazonaws.com/my/path?  
parameter1=value1&parameter2=value1&parameter2=value2&parameter3=value1,value2'  
-H 'header1: value1' -H 'header2: value1' -H 'header2: value2' -H 'header3:  
value1,value2'
```

The output looks like the following:

```
{  
  "resource": "/my/path",  
  "path": "/my/path",  
  "httpMethod": "GET",  
  "headers": {
```

```
"header1": "value1",
"header2": "value2",
"header3": "value1,value2"
},
"multiValueHeaders": {
  "header1": ["value1"],
  "header2": ["value1","value2"],
  "header3": ["value1,value2"]
},
"queryStringParameters": {
  "parameter1": "value1",
  "parameter2": "value2",
  "parameter3": "value1,value2"
},
"multiValueQueryStringParameters": {
  "parameter1": ["value1"],
  "parameter2": ["value1","value2"],
  "parameter3": ["value1,value2"]
},
"requestContext": {
  "accountId": "123456789012",
  "apiId": "id",
  "authorizer": {
    "claims": null,
    "scopes": null
  },
  "domainName": "id.execute-api.us-east-1.amazonaws.com",
  "domainPrefix": "id",
  "extendedRequestId": "request-id",
  "httpMethod": "GET",
  "identity": {
    "accessKey": null,
    "accountId": null,
    "caller": null,
    "cognitoAuthenticationProvider": null,
    "cognitoAuthenticationType": null,
    "cognitoIdentityId": null,
    "cognitoIdentityPoolId": null,
    "principalOrgId": null,
    "sourceIp": "IP",
    "user": null,
    "userAgent": "user-agent",
    "userArn": null,
    "clientCert": {
      "cert": "-----BEGIN CERTIFICATE-----\n-----END CERTIFICATE-----"
    }
  }
}
```

```
        "clientCertPem": "CERT_CONTENT",
        "subjectDN": "www.example.com",
        "issuerDN": "Example issuer",
        "serialNumber": "a1:a1:a1:a1:a1:a1:a1:a1:a1:a1:a1:a1:a1:a1:a1:a1",
        "validity": {
            "notBefore": "May 28 12:30:02 2019 GMT",
            "notAfter": "Aug 5 09:36:04 2021 GMT"
        }
    },
    "path": "/my/path",
    "protocol": "HTTP/1.1",
    "requestId": "id",
    "requestTime": "04/Mar/2020:19:15:17 +0000",
    "requestTimeEpoch": 1583349317135,
    "resourceId": null,
    "resourcePath": "/my/path",
    "stage": "$default"
},
"pathParameters": null,
"stageVariables": null,
"body": "Hello from Lambda!",
"isBase64Encoded": false
}
```

Note

In the input:

- The `headers` key can only contain single-value headers.
- The `multiValueHeaders` key can contain multi-value headers as well as single-value headers.
- If you specify values for both `headers` and `multiValueHeaders`, API Gateway merges them into a single list. If the same key-value pair is specified in both, only the values from `multiValueHeaders` will appear in the merged list.

In the input to the backend Lambda function, the `requestContext` object is a map of key-value pairs. In each pair, the key is the name of a [\\$context](#) variable property, and the value is the value of that property. API Gateway might add new keys to the map.

Depending on the features that are enabled, the `requestContext` map may vary from API to API. For example, in the preceding example, no authorization type is specified, so no `$context.authorizer.*` or `$context.identity.*` properties are present. When an authorization type is specified, this causes API Gateway to pass authorized user information to the integration endpoint in a `requestContext.identity` object as follows:

- When the authorization type is `AWS_IAM`, the authorized user information includes `$context.identity.*` properties.
- When the authorization type is `COGNITO_USER_POOLS` (Amazon Cognito authorizer), the authorized user information includes `$context.identity.cognito*` and `$context.authorizer.claims.*` properties.
- When the authorization type is `CUSTOM` (Lambda authorizer), the authorized user information includes `$context.authorizer.principalId` and other applicable `$context.authorizer.*` properties.

Output format of a Lambda function for proxy integration

In Lambda proxy integration, API Gateway requires the backend Lambda function to return output according to the following JSON format:

```
{  
  "isBase64Encoded": true|false,  
  "statusCode": httpStatusCode,  
  "headers": { "headerName": "headerValue", ... },  
  "multiValueHeaders": { "headerName": ["headerValue", "headerValue2", ...], ... },  
  "body": "..."  
}
```

In the output:

- The `headers` and `multiValueHeaders` keys can be unspecified if no extra response headers are to be returned.
- The `headers` key can only contain single-value headers.
- The `multiValueHeaders` key can contain multi-value headers as well as single-value headers. You can use the `multiValueHeaders` key to specify all of your extra headers, including any single-value ones.

- If you specify values for both headers and multiValueHeaders, API Gateway merges them into a single list. If the same key-value pair is specified in both, only the values from multiValueHeaders will appear in the merged list.

To enable CORS for the Lambda proxy integration, you must add Access-Control-Allow-Origin:*domain-name* to the output headers. *domain-name* can be * for any domain name. The output body is marshalled to the frontend as the method response payload. If body is a binary blob, you can encode it as a Base64-encoded string by setting isBase64Encoded to true and configuring */* as a **Binary Media Type**. Otherwise, you can set it to false or leave it unspecified.

 **Note**

For more information about enabling binary support, see [Enabling binary support using the API Gateway console](#). For an example Lambda function, see [Return binary media from a Lambda proxy integration in API Gateway](#).

If the function output is of a different format, API Gateway returns a 502 Bad Gateway error response.

To return a response in a Lambda function in Node.js, you can use commands such as the following:

- To return a successful result, call `callback(null, {"statusCode": 200, "body": "results"})`.
- To throw an exception, call `callback(new Error('internal server error'))`.
- For a client-side error (if, for example, a required parameter is missing), you can call `callback(null, {"statusCode": 400, "body": "Missing parameters of ..."})` to return the error without throwing an exception.

In a Lambda async function in Node.js, the equivalent syntax would be:

- To return a successful result, call `return {"statusCode": 200, "body": "results"}`.
- To throw an exception, call `throw new Error("internal server error")`.
- For a client-side error (if, for example, a required parameter is missing), you can call `return {"statusCode": 400, "body": "Missing parameters of ..."}` to return the error without throwing an exception.

Set up Lambda proxy integration for API Gateway using the AWS CLI

In this section, we show how to set up an API with the Lambda proxy integration using the AWS CLI. For detailed instructions for using the API Gateway console to configure a proxy resource with the Lambda proxy integration, see [Tutorial: Create a REST API with a Lambda proxy integration](#).

As an example, we use the following sample Lambda function as the backend of the API:

```
export const handler = async(event, context) => {
    console.log('Received event:', JSON.stringify(event, null, 2));
    var res ={
        "statusCode": 200,
        "headers": {
            "Content-Type": "*/*"
        }
    };
    var greeter = 'World';
    if (event.greeter && event.greeter!="") {
        greeter = event.greeter;
    } else if (event.body && event.body != "") {
        var body = JSON.parse(event.body);
        if (body.greeter && body.greeter != "") {
            greeter = body.greeter;
        }
    } else if (event.queryStringParameters && event.queryStringParameters.greeter && event.queryStringParameters.greeter != "") {
        greeter = event.queryStringParameters.greeter;
    } else if (event.multiValueHeaders && event.multiValueHeaders.greeter && event.multiValueHeaders.greeter != "") {
        greeter = event.multiValueHeaders.greeter.join(" and ");
    } else if (event.headers && event.headers.greeter && event.headers.greeter != "") {
        greeter = event.headers.greeter;
    }
    res.body = "Hello, " + greeter + "!";
    return res
};
```

Comparing this to the Lambda custom integration setup in [the section called “Set up Lambda custom integrations”](#), the input to this Lambda function can be expressed in the request parameters and body. You have more latitude to allow the client to pass the same input data. Here, the client can pass the greeter's name in as a query string parameter, a header, or a body property.

The function can also support the Lambda custom integration. The API setup is simpler. You do not configure the method response or integration response at all.

To set up a Lambda proxy integration using the AWS CLI

1. Use the following [create-rest-api](#) command to create an API:

```
aws apigateway create-rest-api --name 'HelloWorld (AWS CLI)'
```

The output will look like the following:

```
{  
  "name": "HelloWorldProxy (AWS CLI)",  
  "id": "te6si5ach7",  
  "rootResourceId" : "krznpq9xpg",  
  "createdDate": 1508461860  
}
```

You use the API id (`te6si5ach7`) and the `rootResourceId` (`krznpq9xpg`) throughout this example.

2. Use the following [create-resource](#) command to create an API Gateway [Resource](#) of /greeting:

```
aws apigateway create-resource \  
  --rest-api-id te6si5ach7 \  
  --parent-id krznpq9xpg \  
  --path-part {proxy+}
```

The output will look like the following:

```
{  
  "path": "/{proxy+}",  
  "pathPart": "{proxy+}",  
  "id": "2jf6xt",  
  "parentId": "krznpq9xpg"  
}
```

You use the `{proxy+}` resource's id value (`2jf6xt`) to create a method on the `/{proxy+}` resource in the next step.

3. Use the following [put-method](#) to create an ANY /{proxy+}:

```
aws apigateway put-method --rest-api-id te6si5ach7 \
    --resource-id 2jf6xt \
    --http-method ANY \
    --authorization-type "NONE"
```

The output will look like the following:

```
{  
    "apiKeyRequired": false,  
    "httpMethod": "ANY",  
    "authorizationType": "NONE"  
}
```

This API method allows the client to receive or send greetings from the Lambda function at the backend.

4. Use the following [put-integration](#) command to set up the integration of the ANY /{proxy+} method with a Lambda function, named HelloWorld. This function responds to the request with a message of "Hello, {name}!", if the greeter parameter is provided, or "Hello, World!", if the query string parameter is not set.

```
aws apigateway put-integration \
    --rest-api-id te6si5ach7 \
    --resource-id 2jf6xt \
    --http-method ANY \
    --type AWS_PROXY \
    --integration-http-method POST \
    --uri arn:aws:apigateway:us-west-2:lambda:path/2015-03-31/functions/
arn:aws:lambda:us-west-2:123456789012:function:HelloWorld/invocations \
    --credentials arn:aws:iam::123456789012:role/apigAwsProxyRole
```

Important

For Lambda integrations, you must use the HTTP method of POST for the integration request, according to the [specification of the Lambda service action for function invocations](#). The IAM role of apigAwsProxyRole must have policies allowing the apigateway service to invoke Lambda functions. For more information about IAM

permissions, see [the section called “ API Gateway permissions model for invoking an API”.](#)

The output will look like the following:

```
{  
    "passthroughBehavior": "WHEN_NO_MATCH",  
    "cacheKeyParameters": [],  
    "uri": "arn:aws:apigateway:us-west-2:lambda:path/2015-03-31/functions/  
arn:aws:lambda:us-west-2:1234567890:function:HelloWorld/invocations",  
    "httpMethod": "POST",  
    "cacheNamespace": "vvom7n",  
    "credentials": "arn:aws:iam::1234567890:role/apigAwsProxyRole",  
    "type": "AWS_PROXY"  
}
```

Instead of supplying an IAM role for `credentials`, you can use the [add-permission](#) command to add resource-based permissions. This is what the API Gateway console does.

5. Use the following [create-deployment](#) command to deploy the API to a test stage:

```
aws apigateway create-deployment \  
    --rest-api-id te6si5ach7 \  
    --stage-name test
```

6. Test the API using the following cURL commands in a terminal.

Calling the API with the query string parameter of `?greeter=jane`:

```
curl -X GET 'https://te6si5ach7.execute-api.us-west-2.amazonaws.com/test/greeting?  
greeter=jane'
```

Calling the API with a header parameter of `greeter:jane`:

```
curl -X GET https://te6si5ach7.execute-api.us-west-2.amazonaws.com/test/hi \  
-H 'content-type: application/json' \  
-H 'greeter: jane'
```

Calling the API with a body of `{"greeter": "jane"}`:

```
curl -X POST https://te6si5ach7.execute-api.us-west-2.amazonaws.com/test/hi \
-H 'content-type: application/json' \
-d '{ "greeter": "jane" }'
```

In all the cases, the output is a 200 response with the following response body:

```
Hello, jane!
```

Set up a proxy resource with Lambda proxy integration with an OpenAPI definition

To set up a proxy resource with the Lambda proxy integration type, create an API resource with a greedy path parameter (for example, /parent/{proxy+}) and integrate this resource with a Lambda function backend (for example, arn:aws:lambda:us-west-2:123456789012:function:SimpleLambda4ProxyResource) on the ANY method. The greedy path parameter must be at the end of the API resource path. As with a non-proxy resource, you can set up the proxy resource by using the API Gateway console, importing an OpenAPI definition file, or calling the API Gateway REST API directly.

The following OpenAPI API definition file shows an example of an API with a proxy resource that is integrated with a Lambda function named SimpleLambda4ProxyResource.

OpenAPI 3.0

```
{
  "openapi": "3.0.0",
  "info": {
    "version": "2016-09-12T17:50:37Z",
    "title": "ProxyIntegrationWithLambda"
  },
  "paths": {
    "/{proxy+}": {
      "x-amazon-apigateway-any-method": {
        "parameters": [
          {
            "name": "proxy",
            "in": "path",
            "required": true,
            "schema": {
              "type": "string"
            }
          }
        ]
      }
    }
  }
}
```

```
        }
    ],
    "responses": {},
    "x-amazon-apigateway-integration": {
        "responses": {
            "default": {
                "statusCode": "200"
            }
        },
        "uri": "arn:aws:apigateway:us-east-1:lambda:path/2015-03-31/functions/arn:aws:lambda:us-east-1:123456789012:function:SimpleLambda4ProxyResource/invocations",
        "passthroughBehavior": "when_no_match",
        "httpMethod": "POST",
        "cacheNamespace": "roq9wj",
        "cacheKeyParameters": [
            "method.request.path.proxy"
        ],
        "type": "aws_proxy"
    }
}
},
"servers": [
{
    "url": "https://gy415nuibc.execute-api.us-east-1.amazonaws.com/{basePath}",
    "variables": {
        "basePath": {
            "default": "/testStage"
        }
    }
}
]
```

OpenAPI 2.0

```
{
  "swagger": "2.0",
  "info": {
    "version": "2016-09-12T17:50:37Z",
    "title": "ProxyIntegrationWithLambda"
```

```
},
  "host": "gy415nuibc.execute-api.us-east-1.amazonaws.com",
  "basePath": "/testStage",
  "schemes": [
    "https"
],
  "paths": {
    "/{proxy+}": {
      "x-amazon-apigateway-any-method": {
        "produces": [
          "application/json"
        ],
        "parameters": [
          {
            "name": "proxy",
            "in": "path",
            "required": true,
            "type": "string"
          }
        ],
        "responses": {}
      },
      "x-amazon-apigateway-integration": {
        "responses": {
          "default": {
            "statusCode": "200"
          }
        },
        "uri": "arn:aws:apigateway:us-east-1:lambda:path/2015-03-31/functions/
arn:aws:lambda:us-east-1:123456789012:function:SimpleLambda4ProxyResource/
invocations",
          "passthroughBehavior": "when_no_match",
          "httpMethod": "POST",
          "cacheNamespace": "roq9wj",
          "cacheKeyParameters": [
            "method.request.path.proxy"
          ],
          "type": "aws_proxy"
        }
      }
    }
  }
}
```

In Lambda proxy integration, at run time, API Gateway maps an incoming request into the input event parameter of the Lambda function. The input includes the request method, path, headers, any query string parameters, any payload, associated context, and any defined stage variables. The input format is explained in [Input format of a Lambda function for proxy integration](#). For API Gateway to map the Lambda output to HTTP responses successfully, the Lambda function must output the result in the format described in [Output format of a Lambda function for proxy integration](#).

In Lambda proxy integration of a proxy resource through the ANY method, the single backend Lambda function serves as the event handler for all requests through the proxy resource. For example, to log traffic patterns, you can have a mobile device send its location information of state, city, street, and building by submitting a request with /state/city/street/house in the URL path for the proxy resource. The backend Lambda function can then parse the URL path and insert the location tuples into a DynamoDB table.

Set up Lambda custom integrations in API Gateway

To show how to set up the Lambda custom, or non-proxy,integration, we create an API Gateway API to expose the GET /greeting?greeter={name} method to invoke a Lambda function. Use one of the following example Lambda functions for your API.

Use one of the following example Lambda functions:

Node.js

```
'use strict';
var days = ['Sunday', 'Monday', 'Tuesday', 'Wednesday', 'Thursday', 'Friday',
'Saturday'];
var times = ['morning', 'afternoon', 'evening', 'night', 'day'];

export const handler = async(event) => {
  console.log(event);
  // Parse the input for the name, city, time and day property values
  let name = event.name === null || event.name === undefined || event.name === "" ?
  'you' : event.name;
  let city = event.city === undefined ? 'World' : event.city;
  let time = times.indexOf(event.time)<0 ? 'day' : event.time;
  let day = days.indexOf(event.day)<0 ? null : event.day;

  // Generate a greeting
  let greeting = 'Good ' + time + ', ' + name + ' of ' + city + '. ';
  if (day) greeting += 'Happy ' + day + '!';
}
```

```
// Log the greeting to CloudWatch
console.log('Hello: ', greeting);

// Return a greeting to the caller
return greeting;
};
```

Python

```
import json

def lambda_handler(event, context):
    print(event)
    res = {
        "statusCode": 200,
        "headers": {
            "Content-Type": "*/*"
        }
    }

    if event['greeter'] == "":
        res['body'] = "Hello, World"
    elif (event['greeter']):
        res['body'] = "Hello, " + event['greeter'] + "!"
    else:
        raise Exception('Missing the required greeter parameter.')

    return res
```

The function responds with a message of "Hello, {name}!" if the greeter parameter value is a non-empty string. It returns a message of "Hello, World!" if the greeter value is an empty string. The function returns an error message of "Missing the required greeter parameter." if the greeter parameter is not set in the incoming request. We name the function `HelloWorld`.

You can create it in the Lambda console or by using the AWS CLI. In this section, we reference this function using the following ARN:

```
arn:aws:lambda:us-east-1:123456789012:function:HelloWorld
```

With the Lambda function set in the backend, proceed to set up the API.

To set up the Lambda custom integration using the AWS CLI

1. Use the following [create-rest-api](#) command to create an API:

```
aws apigateway create-rest-api --name 'HelloWorld (AWS CLI)'
```

The output will look like the following:

```
{  
    "name": "HelloWorld (AWS CLI)",  
    "id": "te6si5ach7",  
    "rootResourceId": "krznpq9xpg",  
    "createdDate": 1508461860  
}
```

You use the API id (`te6si5ach7`) and the `rootResourceId` (`krznpq9xpg`) throughout this example.

2. Use the following [create-resource](#) command to create an API Gateway [Resource](#) of `/greeting`:

```
aws apigateway create-resource \  
    --rest-api-id te6si5ach7 \  
    --parent-id krznpq9xpg \  
    --path-part greeting
```

The output will look like the following:

```
{  
    "path": "/greeting",  
    "pathPart": "greeting",  
    "id": "2jf6xt",  
    "parentId": "krznpq9xpg"  
}
```

You use the `greeting` resource's `id` value (`2jf6xt`) to create a method on the `/greeting` resource in the next step.

3. Use the following [put-method](#) command to create an API method request of GET /greeting?greeter={name}:

```
aws apigateway put-method --rest-api-id te6si5ach7 \
    --resource-id 2jf6xt \
    --http-method GET \
    --authorization-type "NONE" \
    --request-parameters method.request.querystring.greeter=false
```

The output will look like the following:

```
{  
    "apiKeyRequired": false,  
    "httpMethod": "GET",  
    "authorizationType": "NONE",  
    "requestParameters": {  
        "method.request.querystring.greeter": false  
    }  
}
```

This API method allows the client to receive a greeting from the Lambda function at the backend. The greeter parameter is optional because the backend should handle either an anonymous caller or a self-identified caller.

4. Use the following [put-method-response](#) command to set up the 200 OK response to the method request of GET /greeting?greeter={name}:

```
aws apigateway put-method-response \
    --rest-api-id te6si5ach7 \
    --resource-id 2jf6xt \
    --http-method GET \
    --status-code 200
```

5. Use the following [put-integration](#) command to set up the integration of the GET /greeting?greeter={name} method with a Lambda function, named HelloWorld. The function responds to the request with a message of "Hello, {name}!", if the greeter parameter is provided, or "Hello, World!", if the query string parameter is not set.

```
aws apigateway put-integration \
    --rest-api-id te6si5ach7 \
```

```
--resource-id 2jf6xt \
--http-method GET \
--type AWS \
--integration-http-method POST \
--uri arn:aws:apigateway:us-east-1:lambda:path/2015-03-31/functions/
arn:aws:lambda:us-east-1:123456789012:function:HelloWorld/invocations \
--request-templates '{"application/json":"{\\"greeter\\":"
\"$input.params('greeter')\\\"}"}' \
--credentials arn:aws:iam::123456789012:role/apigAwsProxyRole
```

The mapping template supplied here translates the `greeter` query string parameter to the `greeter` property of the JSON payload. This is necessary because the input to a Lambda function must be expressed in the body.

⚠ Important

For Lambda integrations, you must use the HTTP method of POST for the integration request, according to the [specification of the Lambda service action for function invocations](#). The `uri` parameter is the ARN of the function-invoking action.

The output will look like the following:

```
{
    "passthroughBehavior": "WHEN_NO_MATCH",
    "cacheKeyParameters": [],
    "uri": "arn:aws:apigateway:us-east-1:lambda:path/2015-03-31/functions/
arn:aws:lambda:us-east-1:123456789012:function:HelloWorld/invocations",
    "httpMethod": "POST",
    "requestTemplates": {
        "application/json": "{\"greeter\": \"$input.params('greeter')\"}"
    },
    "cacheNamespace": "krznpq9xpg",
    "credentials": "arn:aws:iam::123456789012:role/apigAwsProxyRole",
    "type": "AWS"
}
```

The IAM role of `apigAwsProxyRole` must have policies that allow the `apigateway` service to invoke Lambda functions. Instead of supplying an IAM role for `credentials`, you can call the [add-permission](#) command to add resource-based permissions. This is how the API Gateway console adds these permissions.

6. Use the following [put-integration-response](#) command to set up the integration response to pass the Lambda function output to the client as the 200 OK method response:

```
aws apigateway put-integration-response \
    --rest-api-id te6si5ach7 \
    --resource-id 2jf6xt \
    --http-method GET \
    --status-code 200 \
    --selection-pattern ""
```

By setting the selection-pattern to an empty string, the 200 OK response is the default.

The output will look like the following:

```
{  
    "selectionPattern": "",  
    "statusCode": "200"  
}
```

7. Use the following [create-deployment](#) command to deploy the API to a test stage:

```
aws apigateway create-deployment \
    --rest-api-id te6si5ach7 \
    --stage-name test
```

8. Test the API using the following cURL command in a terminal:

```
curl -X GET 'https://te6si5ach7.execute-api.us-west-2.amazonaws.com/test/greeting?  
greeter=me' \
-H 'authorization: AWS4-HMAC-SHA256 Credential=[access_key]/20171020/us-  
west-2/execute-api/aws4_request, SignedHeaders=content-type;host;x-amz-date,  
Signature=f327...5751'
```

Set up asynchronous invocation of the backend Lambda function

In Lambda non-proxy (custom) integration, the backend Lambda function is invoked synchronously by default. This is the desired behavior for most REST API operations. Some applications, however, require work to be performed asynchronously (as a batch operation or a long-latency operation),

typically by a separate backend component. In this case, the backend Lambda function is invoked asynchronously, and the front-end REST API method doesn't return the result.

You can configure the Lambda function for a Lambda non-proxy integration to be invoked asynchronously by specifying 'Event' as the [Lambda invocation type](#). This is done as follows:

Configure Lambda asynchronous invocation in the API Gateway console

For all invocations to be asynchronous:

- In **Integration request**, add an X-Amz-Invocation-Type header with a static value of 'Event'.

For clients to decide if invocations are asynchronous or synchronous:

1. In **Method request**, add an InvocationType header.
2. In **Integration request** add an X-Amz-Invocation-Type header with a mapping expression of `method.request.header.InvocationType`.
3. Clients can include the `InvocationType: Event` header in API requests for asynchronous invocations or `InvocationType: RequestResponse` for synchronous invocations.

Configure Lambda asynchronous invocation using OpenAPI

For all invocations to be asynchronous:

- Add the X-Amz-Invocation-Type header to the **x-amazon-apigateway-integration** section.

```
"x-amazon-apigateway-integration" : {  
    "type" : "aws",  
    "httpMethod" : "POST",  
    "uri" : "arn:aws:apigateway:us-east-2:lambda:path/2015-03-31/functions/  
arn:aws:lambda:us-east-2:123456789012:function:my-function/invocations",  
    "responses" : {  
        "default" : {  
            "statusCode" : "200"  
        }  
    },  
    "requestParameters" : {  
        "integration.request.header.X-Amz-Invocation-Type" : "'Event'"  
    },
```

```
        "passthroughBehavior" : "when_no_match",
        "contentHandling" : "CONVERT_TO_TEXT"
    }
```

For clients to decide if invocations are asynchronous or synchronous:

1. Add the following header on any [OpenAPI Path Item Object](#).

```
"parameters" : [ {
  "name" : "InvocationType",
  "in" : "header",
  "schema" : {
    "type" : "string"
  }
} ]
```

2. Add the X-Amz-Invocation-Type header to **x-amazon-apigateway-integration** section.

```
"x-amazon-apigateway-integration" : {
  "type" : "aws",
  "httpMethod" : "POST",
  "uri" : "arn:aws:apigateway:us-east-2:lambda:path/2015-03-31/functions/
arn:aws:lambda:us-east-2:123456789012:function:my-function/invocations",
  "responses" : {
    "default" : {
      "statusCode" : "200"
    }
  },
  "requestParameters" : {
    "integration.request.header.X-Amz-Invocation-Type" :
"method.request.header.InvocationType"
  },
  "passthroughBehavior" : "when_no_match",
  "contentHandling" : "CONVERT_TO_TEXT"
}
```

3. Clients can include the InvocationType: Event header in API requests for asynchronous invocations or InvocationType: RequestResponse for synchronous invocations.

Configure Lambda asynchronous invocation using CloudFormation

The following CloudFormation templates show how to configure the AWS::ApiGateway::Method for asynchronous invocations.

For all invocations to be asynchronous:

```
AsyncMethodGet:  
  Type: 'AWS::ApiGateway::Method'  
  Properties:  
    RestApiId: !Ref Api  
    ResourceId: !Ref AsyncResource  
    HttpMethod: GET  
    ApiKeyRequired: false  
    AuthorizationType: NONE  
    Integration:  
      Type: AWS  
      RequestParameters:  
        integration.request.header.X-Amz-Invocation-Type: "'Event'"  
      IntegrationResponses:  
        - StatusCode: '200'  
      IntegrationHttpMethod: POST  
      Uri: !Sub arn:aws:apigateway:${AWS::Region}:lambda:path/2015-03-31/functions/ ${myfunction}.Arn}/invocations  
      MethodResponses:  
        - StatusCode: '200'
```

For clients to decide if invocations are asynchronous or synchronous:

```
AsyncMethodGet:  
  Type: 'AWS::ApiGateway::Method'  
  Properties:  
    RestApiId: !Ref Api  
    ResourceId: !Ref AsyncResource  
    HttpMethod: GET  
    ApiKeyRequired: false  
    AuthorizationType: NONE  
    RequestParameters:  
      method.request.header.InvocationType: false  
    Integration:  
      Type: AWS  
      RequestParameters:
```

```
integration.request.header.X-Amz-Invocation-Type:  
method.request.header.InvocationType  
IntegrationResponses:  
  - StatusCode: '200'  
IntegrationHttpMethod: POST  
Uri: !Sub arn:aws:apigateway:${AWS::Region}:lambda:path/2015-03-31/functions/  
${myfunction}.Arn}/invocations  
MethodResponses:  
  - StatusCode: '200'
```

Clients can include the `InvocationType`: `Event` header in API requests for asynchronous invocations or `InvocationType`: `RequestResponse` for synchronous invocations.

Handle Lambda errors in API Gateway

For Lambda custom integrations, you must map errors returned by Lambda in the integration response to standard HTTP error responses for your clients. Otherwise, Lambda errors are returned as `200 OK` responses by default and the result is not intuitive for your API users.

There are two types of errors that Lambda can return: standard errors and custom errors. In your API, you must handle these differently.

With the Lambda proxy integration, Lambda is required to return an output of the following format:

```
{  
  "isBase64Encoded" : "boolean",  
  "statusCode": "number",  
  "headers": { ... },  
  "body": "JSON string"  
}
```

In this output, `statusCode` is typically `4XX` for a client error and `5XX` for a server error. API Gateway handles these errors by mapping the Lambda error to an HTTP error response, according to the specified `statusCode`. For API Gateway to pass the error type (for example, `InvalidParameterException`), as part of the response to the client, the Lambda function must include a header (for example, `"X-Amzn-ErrorType": "InvalidParameterException"`) in the `headers` property.

Topics

- [Handle standard Lambda errors in API Gateway](#)
- [Handle custom Lambda errors in API Gateway](#)

Handle standard Lambda errors in API Gateway

A standard AWS Lambda error has the following format:

```
{  
  "errorMessage": "<replaceable>string</replaceable>",  
  "errorType": "<replaceable>string</replaceable>",  
  "stackTrace": [  
    "<replaceable>string</replaceable>,  
    ...  
  ]  
}
```

Here, `errorMessage` is a string expression of the error. The `errorType` is a language-dependent error or exception type. The `stackTrace` is a list of string expressions showing the stack trace leading to the occurrence of the error.

For example, consider the following JavaScript (Node.js) Lambda function.

```
export const handler = function(event, context, callback) {  
  callback(new Error("Malformed input ..."));  
};
```

This function returns the following standard Lambda error, containing `Malformed input ...` as the error message:

```
{  
  "errorMessage": "Malformed input ...",  
  "errorType": "Error",  
  "stackTrace": [  
    "export const handler (/var/task/index.js:3:14)"  
  ]  
}
```

Similarly, consider the following Python Lambda function, which raises an `Exception` with the same `Malformed input ...` error message.

```
def lambda_handler(event, context):
    raise Exception('Malformed input ...')
```

This function returns the following standard Lambda error:

```
{
  "stackTrace": [
    [
      "/var/task/lambda_function.py",
      3,
      "lambda_handler",
      "raise Exception('Malformed input ...')"
    ],
    {
      "errorType": "Exception",
      "errorMessage": "Malformed input ..."
    }
}
```

Note that the `errorType` and `stackTrace` property values are language-dependent. The standard error also applies to any error object that is an extension of the `Error` object or a subclass of the `Exception` class.

To map the standard Lambda error to a method response, you must first decide on an HTTP status code for a given Lambda error. You then set a regular expression pattern on the [selectionPattern](#) property of the [IntegrationResponse](#) associated with the given HTTP status code. In the API Gateway console, this `selectionPattern` is denoted as **Lambda error regex** in the **Integration response** section, under each integration response.

 **Note**

API Gateway uses Java pattern-style regexes for response mapping. For more information, see [Pattern](#) in the Oracle documentation.

For example, use the following [put-integration-response](#) to set up a new `selectionPattern` expression:

```
aws apigateway put-integration-response --rest-api-id z0vprf0mdh --resource-id x3o5ih
--http-method GET --status-code 400 --selection-pattern "Malformed.*" --region us-
west-2
```

Make sure that you also set up the corresponding error code (400) on the [method response](#). Otherwise, API Gateway throws an invalid configuration error response at runtime.

Note

At runtime, API Gateway matches the Lambda error's `errorMessage` against the pattern of the regular expression on the `selectionPattern` property. If there is a match, API Gateway returns the Lambda error as an HTTP response of the corresponding HTTP status code. If there is no match, API Gateway returns the error as a default response or throws an invalid configuration exception if no default response is configured.

Setting the `selectionPattern` value to `. *` for a given response amounts to resetting this response as the default response. This is because such a selection pattern will match all error messages, including null, i.e., any unspecified error message. The resulting mapping overrides the default mapping. If you use `. +` as the selection pattern to filter responses, it might not match a response containing be aware that it may not match a response containing a newline ('\n) character.

To update an existing `selectionPattern` value using the AWS CLI, call the [update-integration-response](#) operation to replace the `/selectionPattern` path value with the specified regex expression of the `Malformed*` pattern.

To set the `selectionPattern` expression using the API Gateway console, enter the expression in the **Lambda error regex** text box when setting up or updating an integration response of a specified HTTP status code.

Handle custom Lambda errors in API Gateway

Instead of the standard error described in the preceding section, AWS Lambda allows you to return a custom error object as JSON string. The error can be any valid JSON object. For example, the following JavaScript (Node.js) Lambda function returns a custom error:

```
export const handler = (event, context, callback) => {
  ...
  // Error caught here:
  var myErrorObj = {
    errorType : "InternalServerError",
    httpStatus : 500,
    requestId : context.awsRequestId,
```

```
    trace : {
        "function": "abc()",  
        "line": 123,  
        "file": "abc.js"  
    }  
}  
callback(JSON.stringify(myErrorObj));  
};
```

You must turn the `myErrorObj` object into a JSON string before calling `callback` to exit the function. Otherwise, the `myErrorObj` is returned as a string of "[object Object]". When a method of your API is integrated with the preceding Lambda function, API Gateway receives an integration response with the following payload:

```
{  
    "errorMessage": "{\"errorType\":\"InternalServerError\",\"httpStatus\":500,  
    \"requestId\":\"e5849002-39a0-11e7-a419-5bb5807c9fb2\",\"trace\":{\"function\"::  
    \"abc()\", \"line\":123, \"file\":\"abc.js\"}}"  
}
```

As with any integration response, you can pass through this error response as-is to the method response. Or you can have a mapping template to transform the payload into a different format. For example, consider the following body-mapping template for a method response of 500 status code:

```
{  
    errorMessage: $input.path('$.errorMessage');  
}
```

This template translates the integration response body that contains the custom error JSON string to the following method response body. This method response body contains the custom error JSON object:

```
{  
    "errorMessage" : {  
        "errorType" : "InternalServerError",  
        "httpStatus" : 500,  
        "requestId" : context.awsRequestId,  
        "trace" : {  
            "function": "abc()",  
            "line": 123,  
            "file": "abc.js"  
        }  
    }  
}
```

```
        "line": 123,
        "file": "abc.js"
    }
};

};
```

Depending on your API requirements, you may need to pass some or all of the custom error properties as method response header parameters. You can achieve this by applying the custom error mappings from the integration response body to the method response headers.

For example, the following OpenAPI extension defines a mapping from the `errorMessage.errorType`, `errorMessage.HttpStatus`, `errorMessage.trace.function`, and `errorMessage.trace` properties to the `error_type`, `error_status`, `error_trace_function`, and `error_trace` headers, respectively.

```
"x-amazon-apigateway-integration": {
    "responses": {
        "default": {
            "statusCode": "200",
            "responseParameters": {
                "method.response.header.error_trace_function": "integration.response.body.errorMessage.trace.function",
                "method.response.header.error_status": "integration.response.body.errorMessage.HttpStatus",
                "method.response.header.error_type": "integration.response.body.errorMessage.errorType",
                "method.response.header.error_trace": "integration.response.body.errorMessage.trace"
            },
            ...
        }
    }
}
```

At runtime, API Gateway deserializes the `integration.response.body` parameter when performing header mappings. However, this deserialization applies only to body-to-header mappings for Lambda custom error responses and does not apply to body-to-body mappings using `$input.body`. With these custom-error-body-to-header mappings, the client receives the following headers as part of the method response, provided that the `error_status`, `error_trace`, `error_trace_function`, and `error_type` headers are declared in the method request.

```
"error_status": "500",
"error_trace": "{\"function\": \"abc()\", \"line\": 123, \"file\": \"abc.js\"}",
"error_trace_function": "abc()",
"error_type": "InternalServerError"
```

The `errorMessage.trace` property of the integration response body is a complex property. It is mapped to the `error_trace` header as a JSON string.

HTTP integrations for REST APIs in API Gateway

You can integrate an API method with an HTTP endpoint using the HTTP proxy integration or the HTTP custom integration.

API Gateway supports the following endpoint ports: 80, 443 and 1024-65535.

With proxy integration, setup is simple. You only need to set the HTTP method and the HTTP endpoint URI, according to the backend requirements, if you are not concerned with content encoding or caching.

With custom integration, setup is more involved. In addition to the proxy integration setup steps, you need to specify how the incoming request data is mapped to the integration request and how the resulting integration response data is mapped to the method response.

Topics

- [Set up HTTP proxy integrations in API Gateway](#)
- [Set up HTTP custom integrations in API Gateway](#)

Set up HTTP proxy integrations in API Gateway

To set up a proxy resource with the HTTP proxy integration type, create an API resource with a greedy path parameter (for example, `/parent/{proxy+}`) and integrate this resource with an HTTP backend endpoint (for example, `https://petstore-demo-endpoint.execute-api.com/petstore/{proxy}`) on the ANY method. The greedy path parameter must be at the end of the resource path.

As with a non-proxy resource, you can set up a proxy resource with the HTTP proxy integration by using the API Gateway console, importing an OpenAPI definition file, or calling the API Gateway REST API directly. For detailed instructions about using the API Gateway console to configure a

proxy resource with the HTTP integration, see [Tutorial: Create a REST API with an HTTP proxy integration](#).

The following OpenAPI definition file shows an example of an API with a proxy resource that is integrated with the [PetStore](#) website.

OpenAPI 3.0

```
{  
  "openapi": "3.0.0",  
  "info": {  
    "version": "2016-09-12T23:19:28Z",  
    "title": "PetStoreWithProxyResource"  
  },  
  "paths": {  
    "/{proxy}": {  
      "x-amazon-apigateway-any-method": {  
        "parameters": [  
          {  
            "name": "proxy",  
            "in": "path",  
            "required": true,  
            "schema": {  
              "type": "string"  
            }  
          }  
        ],  
        "responses": {},  
        "x-amazon-apigateway-integration": {  
          "responses": {  
            "default": {  
              "statusCode": "200"  
            }  
          },  
          "requestParameters": {  
            "integration.request.path.proxy": "method.request.path.proxy"  
          },  
          "uri": "http://petstore-demo-endpoint.execute-api.com/petstore/  
{proxy}",  
          "passthroughBehavior": "when_no_match",  
          "httpMethod": "ANY",  
          "cacheNamespace": "rbftud",  
          "cacheKeyParameters": [  
        }  
      }  
    }  
  }  
}
```

```
        "method.request.path.proxy"
    ],
    "type": "http_proxy"
}
}
},
"servers": [
{
    "url": "https://4z9giyi2c1.execute-api.us-east-1.amazonaws.com/{basePath}",
    "variables": {
        "basePath": {
            "default": "/test"
        }
    }
}
]
}
```

OpenAPI 2.0

```
{
  "swagger": "2.0",
  "info": {
    "version": "2016-09-12T23:19:28Z",
    "title": "PetStoreWithProxyResource"
  },
  "host": "4z9giyi2c1.execute-api.us-east-1.amazonaws.com",
  "basePath": "/test",
  "schemes": [
    "https"
  ],
  "paths": {
    "/{proxy+}": {
      "x-amazon-apigateway-any-method": {
        "produces": [
          "application/json"
        ],
        "parameters": [
          {
            "name": "proxy",
            "in": "path",
            "required": true,
            "type": "string"
          }
        ]
      }
    }
  }
}
```

```
        "type": "string"
    },
],
"responses": {},
"x-amazon-apigateway-integration": {
    "responses": {
        "default": {
            "statusCode": "200"
        }
    },
    "requestParameters": {
        "integration.request.path.proxy": "method.request.path.proxy"
    },
    "uri": "http://petstore-demo-endpoint.execute-api.com/petstore/{proxy}",
    "passthroughBehavior": "when_no_match",
    "httpMethod": "ANY",
    "cacheNamespace": "rbftud",
    "cacheKeyParameters": [
        "method.request.path.proxy"
    ],
    "type": "http_proxy"
}
}
}
}
}
```

In this example, a cache key is declared on the `method.request.path.proxy` path parameter of the proxy resource. This is the default setting when you create the API using the API Gateway console. The API's base path (/test, corresponding to a stage) is mapped to the website's PetStore page (/petstore). The single integration request mirrors the entire PetStore website using the API's greedy path variable and the catch-all ANY method. The following examples illustrate this mirroring.

- **Set ANY as GET and {proxy+} as pets**

Method request initiated from the frontend:

```
GET https://4z9giyi2c1.execute-api.us-west-2.amazonaws.com/test/pets HTTP/1.1
```

Integration request sent to the backend:

```
GET http://petstore-demo-endpoint.execute-api.com/petstore/pets HTTP/1.1
```

The run-time instances of the ANY method and proxy resource are both valid. The call returns a 200 OK response with the payload containing the first batch of pets, as returned from the backend.

- **Set ANY as GET and {proxy+} as pets?type=dog**

```
GET https://4z9giyi2c1.execute-api.us-west-2.amazonaws.com/test/pets?type=dog  
HTTP/1.1
```

Integration request sent to the backend:

```
GET http://petstore-demo-endpoint.execute-api.com/petstore/pets?type=dog HTTP/1.1
```

The run-time instances of the ANY method and proxy resource are both valid. The call returns a 200 OK response with the payload containing the first batch of specified dogs, as returned from the backend.

- **Set ANY as GET and {proxy+} as pets/{petId}**

Method request initiated from the frontend:

```
GET https://4z9giyi2c1.execute-api.us-west-2.amazonaws.com/test/pets/1 HTTP/1.1
```

Integration request sent to the backend:

```
GET http://petstore-demo-endpoint.execute-api.com/petstore/pets/1 HTTP/1.1
```

The run-time instances of the ANY method and proxy resource are both valid. The call returns a 200 OK response with the payload containing the specified pet, as returned from the backend.

- **Set ANY as POST and {proxy+} as pets**

Method request initiated from the frontend:

```
POST https://4z9giyi2c1.execute-api.us-west-2.amazonaws.com/test/pets HTTP/1.1  
Content-Type: application/json  
Content-Length: ...
```

```
{  
  "type" : "dog",  
  "price" : 1001.00  
}
```

Integration request sent to the backend:

```
POST http://petstore-demo-endpoint.execute-api.com/petstore/pets HTTP/1.1  
Content-Type: application/json  
Content-Length: ...  
  
{  
  "type" : "dog",  
  "price" : 1001.00  
}
```

The run-time instances of the ANY method and proxy resource are both valid. The call returns a 200 OK response with the payload containing the newly created pet, as returned from the backend.

- **Set ANY as GET and {proxy+} as pets/cat**

Method request initiated from the frontend:

```
GET https://4z9giyi2c1.execute-api.us-west-2.amazonaws.com/test/pets/cat
```

Integration request sent to the backend:

```
GET http://petstore-demo-endpoint.execute-api.com/petstore/pets/cat
```

The run-time instance of the proxy resource path does not correspond to a backend endpoint and the resulting request is invalid. As a result, a 400 Bad Request response is returned with the following error message.

```
{  
  "errors": [  
    {  
      "key": "Pet2.type",  
      "message": "Missing required field"  
    }  
  ]  
}
```

```
    },
    {
        "key": "Pet2.price",
        "message": "Missing required field"
    }
]
```

- **Set ANY as GET and {proxy+} as null**

Method request initiated from the frontend:

```
GET https://4z9giyi2c1.execute-api.us-west-2.amazonaws.com/test
```

Integration request sent to the backend:

```
GET http://petstore-demo-endpoint.execute-api.com/petstore/pets
```

The targeted resource is the parent of the proxy resource, but the run-time instance of the ANY method is not defined in the API on that resource. As a result, this GET request returns a 403 Forbidden response with the Missing Authentication Token error message as returned by API Gateway. If the API exposes the ANY or GET method on the parent resource (/), the call returns a 404 Not Found response with the Cannot GET /petstore message as returned from the backend.

For any client request, if the targeted endpoint URL is invalid or the HTTP verb is valid but not supported, the backend returns a 404 Not Found response. For an unsupported HTTP method, a 403 Forbidden response is returned.

Set up HTTP custom integrations in API Gateway

With the HTTP custom integration, also known as the non-proxy integration, you have more control of which data to pass between an API method and an API integration and how to pass the data. You do this using data mappings.

As part of the method request setup, you set the [requestParameters](#) property on a [Method](#) resource. This declares which method request parameters, which are provisioned from the client, are to be mapped to integration request parameters or applicable body properties before being dispatched to the backend. Then, as part of the integration request setup, you set the

[requestParameters](#) property on the corresponding [Integration](#) resource to specify the parameter-to-parameter mappings. You also set the [requestTemplates](#) property to specify mapping templates, one for each supported content type. The mapping templates map method request parameters, or body, to the integration request body.

Similarly, as part of the method response setup, you set the [responseParameters](#) property on the [MethodResponse](#) resource. This declares which method response parameters, to be dispatched to the client, are to be mapped from integration response parameters or certain applicable body properties that were returned from the backend. You then set up the [selectionPattern](#) to choose an integration response based on the response from the backend. For a non-proxy HTTP integration, this is a regular expression. For example, to map all 2xx HTTP response status codes from an HTTP endpoint to this output mapping, use `2\d{2}`.

 **Note**

API Gateway uses Java pattern-style regexes for response mapping. For more information, see [Pattern](#) in the Oracle documentation.

Then, as part of the integration response setup, you set the [responseParameters](#) property on the corresponding [IntegrationResponse](#) resource to specify the parameter-to-parameter mappings. You also set the [responseTemplates](#) map to specify mapping templates, one for each supported content type. The mapping templates map integration response parameters, or integration response body properties, to the method response body.

For more information about setting up mapping templates, see [Data transformations for REST APIs in API Gateway](#).

Stream the integration response for your proxy integrations in API Gateway

You can configure your proxy integration to control how API Gateway returns your integration response. By default, API Gateway waits to receive the complete response before beginning transmission. However, if you set your integration's response transfer mode to STREAM, API Gateway doesn't wait for a response to be completely computed before sending it to the client. Response streaming works for all REST API endpoint types.

Use response streaming for the following use cases:

- Lower the time-to-first-byte (TTFB) for generative AI applications like chatbots.
- Stream large image, video, or music files without using an S3 pre-signed URL.
- Perform long-running operations while reporting incremental progress like server-sent events (SSE).
- Exceed API Gateway's 10 MB response payload limit.
- Exceed API Gateway's 29 second timeout limit without requesting an integration timeout limit increase.
- Receive a binary payload without configuring the binary media types.

Considerations for response payload streaming

The following considerations might impact your use of response payload streaming:

- You can only use response payload streaming for HTTP_PROXY or AWS_PROXY integration types. This includes Lambda proxy integrations and private integrations that use HTTP_PROXY integrations.
- The default transfer mode setting is BUFFERED. To use response streaming you must change the response transfer mode to STREAM.
- Response streaming is only supported for REST APIs.
- Request streaming isn't supported.
- You can stream your response for up to 15 minutes.
- Your streams are subject to idle timeouts. For Regional or private endpoints, the timeout is 5 minutes. For edge-optimized endpoints, the timeout is 30 seconds.
- If you use response streaming for a Regional REST API with your own CloudFront distribution, you can achieve an idle time out greater than 30 seconds by increasing the response timeout of your CloudFront distribution. For more information, see [Response timeout](#).

- When the response transfer mode is set to STREAM, API Gateway can't support features that require buffering the entire integration response. Because of this, the following features aren't supported with response streaming:
 - Endpoint caching
 - Content encoding. If you want to compress your integration response, do this in your integration.
 - Response transformation with VTL
- Within each streaming response, the first 10MB of response payload is not subject to any bandwidth restrictions. Response payload data exceeding 10MB is restricted to 2MB/s.
- When the connection between the client and API Gateway or between API Gateway and Lambda is closed due to timeout, the Lambda function might continue to execute. For more information, see [Configure Lambda function timeout](#).
- Response streaming incurs a cost. For more information, see [API Gateway Pricing](#).

Set up an HTTP proxy integration with payload response streaming in API Gateway

When you set up response payload streaming, you specify the response transfer mode in the integration request of your method. You configure these settings in the integration request to control how API Gateway behaves before and during the integration response. When you use response streaming, you can configure the integration timeout up to 15 minutes.

When you use payload response streaming with an HTTP_PROXY integration, API Gateway won't send the HTTP response status code or any HTTP response headers until it fully receives all headers.

Create an HTTP proxy integration with payload response streaming

The following procedure shows you how to import a new API with the `responseTransferMode` set to STREAM. If you have an existing integration API and want to modify the `responseTransferMode`, see [the section called “Update the response transfer mode for an HTTP proxy integration”](#).

AWS Management Console

To create an HTTP proxy integration with payload response streaming

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose a REST API.

3. Choose **Create resource**.
4. For **Resource name**, enter **streaming**.
5. Choose **Create resource**.
6. With the **/streaming** resource selected, choose **Create method**.
7. For **Method type**, choose **ANY**.
8. For **Integration type**, choose **HTTP**.
9. Choose **HTTP proxy integration**.
10. For **Response transfer mode**, choose **Stream**.
11. For **HTTP method**, choose a method.
12. For **Endpoint URL**, enter an integration endpoint. Make sure that you choose an endpoint that produces a large payload to be streamed back to you.
13. Choose **Create method**.

After you create your method, deploy your API.

To deploy your API

1. Choose **Deploy API**.
2. For **Stage**, select **New stage**.
3. For **Stage name**, enter **prod**.
4. (Optional) For **Description**, enter a description.
5. Choose **Deploy**.

AWS CLI

To create a new API with payload response streaming

1. Copy the following Open API file, and then save it as `ResponseStreamDemoSwagger.yaml`. In this file, `responseTransferMode` is set to `STREAM`. The integration endpoint is set to `https://example.com`, but we recommend that you modify it to an endpoint that produces a large payload to be streamed back to you.

```
openapi: "3.0.1"
info:
```

```
title: "ResponseStreamingDemo"
version: "2025-04-28T17:28:25Z"
servers:
- url: "{basePath}"
variables:
  basePath:
    default: "prod"
paths:
  /streaming:
    get:
      x-amazon-apigateway-integration:
        httpMethod: "GET"
        uri: "https://example.com"
        type: "http_proxy"
        timeoutInMillis: 900000
        responseTransferMode: "STREAM"
```

2. Use the following `import-rest-api` command to import your OpenAPI definition:

```
aws apigateway import-rest-api \
--body 'fileb://~/ResponseStreamDemoSwagger.yaml' \
--parameters endpointConfigurationTypes=REGIONAL \
--region us-west-1
```

3. Use the following `create-deployment` command to deploy your new API to a stage:

```
aws apigateway create-deployment \
--rest-api-id a1b2c3 \
--stage-name prod \
--region us-west-1
```

Update the response transfer mode for an HTTP proxy integration

The following procedure shows how to update the response transfer mode for an HTTP proxy integration.

AWS Management Console

To update the response transfer mode for an HTTP proxy integration

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose a REST API.

3. Choose a method.
4. On the **Integration request** tab, under **Integration request settings**, choose **Edit**.
5. For **Response transfer mode**, choose **Stream**.
6. Choose **Save**.

After you update your method, deploy your API.

To deploy your API

1. Choose **Deploy API**.
2. For **Stage**, select **New stage**.
3. For **Stage name**, enter **prod**.
4. (Optional) For **Description**, enter a description.
5. Choose **Deploy**.

AWS CLI

The following `update-integration` command updates the transfer mode of an integration from **BUFFERED** to **STREAM**. For any existing APIs, the response transfer mode for all integrations is set to **BUFFERED**.

```
aws apigateway update-integration \
--rest-api-id a1b2c3 \
--resource-id aaa111 \
--http-method GET \
--patch-operations "op='replace',path='/responseTransferMode',value=STREAM" \
--region us-west-1
```

You need to redeploy your API for the changes to take effect. If you customized the integration timeout, this timeout value is removed, as API Gateway streams your response for up to 5 minutes.

The following `update-integration` command updates the transfer mode of an integration from **STREAM** to **BUFFERED**:

```
aws apigateway update-integration \
```

```
--rest-api-id a1b2c3 \
--resource-id aaa111 \
--http-method GET \
--patch-operations "op='replace',path='/responseTransferMode',value=BUFFERED" \
--region us-west-1
```

You need to redeploy your API for the changes to take effect.

Set up a Lambda proxy integration with payload response streaming in API Gateway

You can stream the response of a Lambda function to improve time to first byte (TTFB) performance and send partial responses back to the client as they become available. API Gateway requires you to use the [InvokeWithResponseStream](#) Lambda API to invoke your Lambda function. API Gateway passes an event object to the Lambda function. The backend Lambda function parses the incoming request data to determine the response that it returns. In order for API Gateway to stream the Lambda output, the Lambda function must output the [format](#) required by API Gateway.

Differences in Lambda proxy integrations between stream and buffered response transfer mode

The following list describes the differences between a Lambda proxy integration and a Lambda proxy integration for response streaming:

- API Gateway uses the [InvokeWithResponseStream](#) API to invoke the Lambda proxy integration for response streaming. This results in a different URI, which is the following:

```
arn:aws:apigateway:us-west-1:lambda:path/2021-11-15/functions/arn:aws:lambda:us-west-1:111122223333:function:my-function-name/response-streaming-invocations
```

This ARN uses a different date for the API version and a different service action compared to Lambda proxy integration.

If you use the API Gateway console for response streaming, the console uses the correct URI for you.

- In a Lambda proxy integration, API Gateway sends the response to client only after it receives the full response from Lambda. In a Lambda proxy integration for response streaming, API Gateway begins the payload stream after it receives the valid metadata and delimiter from Lambda.
- Lambda proxy integration for response streaming uses the same input format as the proxy integration, but it requires a different output format.

Lambda proxy integration format for response streaming

When API Gateway invokes a Lambda function with response streaming, the input format is the same as the input format of a Lambda function for proxy integration. For more information, see [the section called “Input format of a Lambda function for proxy integration”](#).

When Lambda streams a response to API Gateway, the response must adhere to the following format. This format uses a delimiter to separate the metadata JSON and the raw payload. In this case, the payload data is streamed as it is transmitted by your streaming Lambda function:

```
{  
  "headers": {"headerName": "headerValue", ...},  
  "multiValueHeaders": { "headerName": ["headerValue", "headerValue2", ...], ... },  
  "cookies" : ["cookie1", "cookie2"],  
  "statusCode": httpStatusCode  
}<DELIMITER>PAYLOAD1 | PAYLOAD2 | PAYLOAD3
```

In the output:

- The `headers`, `multiValueHeaders`, `cookies`, and `statusCode` keys can be unspecified if no extra response headers are to be returned.
- The `headers` key can only contain single-value headers.
- The output expects the headers to contain either `Transfer-Encoding: chunked` or `Content-length: number`. If your function doesn't return either of these headers, API Gateway appends `Transfer-Encoding: chunked` to the response header.
- The `multiValueHeaders` key can contain multi-value headers as well as single-value headers. You can use the `multiValueHeaders` key to specify all of your extra headers, including any single-value ones.
- If you specify values for both `headers` and `multiValueHeaders`, API Gateway merges them into a single list. If the same key-value pair is specified in both, only the values from `multiValueHeaders` will appear in the merged list.
- The metadata must be valid JSON. Only `headers`, `multiValueHeaders`, `cookies` and the `statusCode` keys are supported.
- You must provide a delimiter after the metadata JSON. The delimiter must be 8 null bytes and it must appear within the first 16KB of stream data.
- API Gateway doesn't require a specific format for the method response payload.

If you're using a function URL to stream your Lambda function, you must modify the input and the output of your Lambda function to satisfy these requirements.

If your Lambda function output doesn't adhere to the requirements of this format, API Gateway might still invoke your Lambda function. The following table shows the combinations of API integration request settings and Lambda function code that is supported by API Gateway. This includes supported combinations for response transfer mode of buffered.

Response transfer mode	Function code adheres to the required format	Lambda invoke API	Supported by API Gateway
Stream	Yes	InvokeWithResponse Stream	Yes. API Gateway streams your response.
Stream	No	InvokeWithResponse Stream	No. API Gateway invokes your Lambda function and return a 500 error response.
Stream	Yes	Invoke	No. API Gateway doesn't support this integration configuration.
Stream	No	Invoke	No. API Gateway doesn't support this integration configuration.
Buffered	Yes	InvokeWithResponse Stream	No. API Gateway doesn't support this integration configuration.
Buffered	No	InvokeWithResponse Stream	No. API Gateway doesn't support this

Response transfer mode	Function code adheres to the required format	Lambda invoke API	Supported by API Gateway
			integration configuration.
Buffered	Yes	Invoke	API Gateway returns the HTTP headers and status code but not the response body.
Buffered	No	Invoke	Yes. This is a Lambda proxy integration. For more information, see Lambda proxy integration .

Configure a Lambda proxy integration with payload response streaming in API Gateway

When you set up response payload streaming, you specify the transfer mode in the integration request of your resource. You configure these settings in the integration request to control how API Gateway behaves before and during the integration response.

Example Lambda functions for response streaming

Your Lambda function must adhere to the [the section called “Lambda proxy integration format for response streaming”](#). We recommend you use one of the three example Lambda functions to test out response streaming. When you create your Lambda function, make sure to do the following:

- Provide an adequate timeout for your function. We recommend you configure a timeout of at least 1 minute to learn about response streaming. When you create your production resources, make sure your Lambda function timeout covers the full request cycle. For more information, see [Configure Lambda function timeout](#).
- Use the latest Node.js runtime.
- Use a Region where Lambda response streaming is available.

Using `HttpResponseStream.from`

The following code example streams the JSON metadata objects and payloads back to the client using the `awslambda.HttpResponseStream()` method without using the `pipeline` method. You don't need to create the delimiter. For more information, see [Writing response streaming-enabled Lambda functions](#).

```
export const handler = awslambda.streamifyResponse(  
  async (event, responseStream, context) => {  
    const httpResponseMetadata = {  
      "statusCode": 200,  
      "headers": {  
        "x-foo": "bar"  
      },  
      "multiValueHeaders": {  
        "x-mv1": ["hello", "world"],  
        "Set-Cookie": ["c1=blue", "c2=red"]  
      }  
    };  
  
    responseStream = awslambda.HttpResponseStream.from(responseStream,  
    httpResponseMetadata);  
    await new Promise(r => setTimeout(r, 1000)); // synthetic delay  
  
    responseStream.write("First payload ");  
    await new Promise(r => setTimeout(r, 1000)); // synthetic delay  
  
    responseStream.write("Final payload");  
    responseStream.end();  
  });
```

Using the `pipeline` method

Lambda recommends that when you write response streaming-enabled functions, you use the `awslambda.streamifyResponse()` decorator that the native Node.js runtimes provide, and the `pipeline()` method. When you use the `pipeline` method, you don't need to create the delimiter, Lambda does this for you. For more information, see [Writing response streaming-enabled Lambda functions](#).

The following code example streams the JSON metadata objects and three payloads back to the client.

```
import { pipeline } from 'node:stream/promises';
import { Readable } from 'node:stream';

export const handler = awslambda.streamifyResponse(
  async (event, responseStream, context) => {
    const httpResponseMetadata = {
      statusCode: 200,
      headers: {
        "Content-Type": "text/plain",
        "X-Custom-Header": "Example-Custom-Header"
      }
    };

    responseStream = awslambda.HttpResponseStream.from(responseStream,
    httpResponseMetadata);

    const dataStream = Readable.from(async function* () {
      yield "FIRST payload\n";
      await new Promise(r => setTimeout(r, 1000));
      yield "SECOND payload\n";
      await new Promise(r => setTimeout(r, 1000));
      yield "THIRD payload\n";
      await new Promise(r => setTimeout(r, 1000));
    })();

    await pipeline(dataStream, responseStream);
  }
);
```

Without using the pipeline method

The following code example streams the JSON metadata objects and three payloads back to the client without using the `awslambda.HttpResponseStream()` method. Without the `awslambda.HttpResponseStream()` method, you must include a delimiter of 8 null bytes between the metadata and the payload.

```
export const handler = awslambda.streamifyResponse(async (event, response, ctx) => {
  response.write('{"statusCode": 200, "headers": {"hdr-x": "val-x"} }');
  response.write("\x00".repeat(8)); // DELIMITER
  await new Promise(r => setTimeout(r, 1000));

  response.write("FIRST payload");
```

```
await new Promise(r => setTimeout(r, 1000));  
  
response.write("SECOND payload");  
await new Promise(r => setTimeout(r, 1000));  
  
response.write("FINAL payload");  
response.end();  
});
```

Create a Lambda proxy integration with payload response streaming

The following procedure shows how to create a Lambda proxy integration with payload response streaming. Use the example Lambda function or create your own.

AWS Management Console

To create a Lambda proxy integration with payload response streaming

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose a REST API.
3. Choose **Create resource**.
4. For **Resource name**, enter **streaming**.
5. Choose **Create resource**.
6. With the **/streaming** resource selected, choose **Create method**.
7. For **Method type**, choose **ANY**.
8. For **Integration type**, choose **Lambda**.
9. Choose **Lambda proxy integration**.
10. For **Response transfer mode**, choose **Stream**.
11. For **Lambda function**, choose the name of your Lambda function.

The API Gateway console automatically uses [InvokeWithResponseStream](#) API to invoke the Lambda function. You are responsible for writing a response streaming-enabled Lambda function. For an example, see [the section called “Example Lambda functions for response streaming”](#).

12. Choose **Create method**.

After you create your method, deploy your API.

To deploy your API

1. Choose **Deploy API**.
2. For **Stage**, select **New stage**.
3. For **Stage name**, enter **prod**.
4. (Optional) For **Description**, enter a description.
5. Choose **Deploy**.

AWS CLI

The following procedure shows you how to import a new API with the `responseTransferMode` set to STREAM. If you have an existing integration API and want to modify the `responseTransferMode`, see [the section called “Update the response transfer mode for a Lambda proxy integration”](#).

To create a new API with payload response streaming

1. Copy the following Open API file, and then save it as `ResponseStreamDemoSwagger.yaml`. In this file, `responseTransferMode` is set to STREAM, and the integration URI is set to `arn:aws:apigateway:us-west-1:lambda:path/2021-11-15/functions/arn:aws:lambda:us-west-1:111122223333:function:my-function-name/response-streaming-invocations`.

Replace the function name from `my-function` with a streaming-enabled function and replace the credentials with an IAM role that has policies allowing the apigateway service to invoke Lambda functions.

```
openapi: "3.0.1"
info:
  title: "ResponseStreamingDemo"
  version: "2025-04-28T17:28:25Z"
servers:
- url: "{basePath}"
variables:
  basePath:
    default: "prod"
```

```
paths:  
  /lambda:  
    get:  
      x-amazon-apigateway-integration:  
        httpMethod: "POST"  
        uri: "arn:aws:apigateway:us-west-1:lambda:path/2021-11-15/functions/  
arn:aws:lambda:us-west-1:111122223333:function:my-function-name/response-  
streaming-invocations"  
        type: "aws_proxy"  
        timeoutInMillis: 90000  
        responseTransferMode: "STREAM"  
        credentials: "arn:aws:iam::111122223333:role/apigateway-lambda-role"
```

Instead of supplying an IAM role for credentials, you can use the `add-permission` command for Lambda to add resource-based permissions.

2. Use the following `import-rest-api` command to import your OpenAPI definition:

```
aws apigateway import-rest-api \  
--body 'fileb://~/ResponseStreamDemoSwagger.yaml' \  
--parameters endpointConfigurationTypes=REGIONAL \  
--region us-west-1
```

3. Use the following `create-deployment` command to deploy your new API to a stage:

```
aws apigateway create-deployment \  
--rest-api-id a1b2c2 \  
--stage-name prod \  
--region us-west-1
```

Update the response transfer mode for a Lambda proxy integration

The following procedure shows how to update the response transfer mode for a Lambda proxy integration. When you change the response transfer mode to streaming, update your Lambda function so it adheres to the requirements for response streaming. Use the example Lambda function or create your own.

AWS Management Console

To update the response transfer mode for a Lambda proxy integration

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose a REST API.
3. Choose a method.
4. On the **Integration request** tab, under **Integration request settings**, choose **Edit**.
5. For **Response transfer mode**, choose **Stream**.
6. For **Lambda function**, choose the name of your Lambda function.
7. Choose **Save**.

After you update your method, deploy your API.

To deploy your API

1. Choose **Deploy API**.
2. For **Stage**, select **New stage**.
3. For **Stage name**, enter **prod**.
4. (Optional) For **Description**, enter a description.
5. Choose **Deploy**.

AWS CLI

1. Update your Lambda function to be streaming-enabled.
2. Use the following AWS CLI command to update the integration URI and response transfer mode of your integration:

```
aws apigateway update-integration \
--rest-api-id a1b2c3 \
--resource-id aaa111 \
--http-method ANY \
--patch-operations "[{\\"op\\\":\\"replace\\",\\"path\\\":\\"/uri\\",\\"value\\":\\"arn:aws:apigateway:us-west-1:lambda:path/2021-11-15/functions/
arn:aws:lambda:us-west-1:111122223333:function:my-function-name/response-
streaming-invocations\\"}, {\\"op\\\":\\"replace\\",\\"path\\\":\\"/responseTransferMode\\",
\\"value\\\":\\"STREAM\\"}]" \
```

```
--region us-west-1
```

3. Redeploy your API for the changes to take effect.

Troubleshoot issues with response streaming in API Gateway

The following troubleshooting guidance might help resolve issues with your APIs that use response streaming.

General troubleshooting

You can use the [TestInvokeMethod](#) or the console's test tab to test your stream response. The following considerations might impact your use of test invoke for response streaming:

- When you test your method, API Gateway buffers your streamed response payload. Once any of the following conditions have been met, API Gateway returns a one-time response containing the buffered payload:
 - The request is complete
 - 35 seconds have elapsed
 - More than 1 MB of response payload has been buffered
- If more than 35 seconds elapse before your method returns an HTTP response status and all headers, then the response status returned in TestInvokeMethod is 0.
- API Gateway doesn't produce any execution logs.

After you've deployed your API, you can test your stream response by using a curl command. We recommend that you use the `-i` option to include protocol response headers in the output. To see the response data as it arrives, use the curl option `--no-buffer`

Troubleshoot cURL errors

If you're testing an integration and you receive the error `curl: (18) transfer closed with outstanding read data remaining`, make sure the timeout of your integration is long enough. If you're using a Lambda function, you need to update the response timeout of the Lambda function. For more information, see [Configure Lambda function timeout](#).

Troubleshoot using access logging

You can use access logs for your REST API stage to log and troubleshoot your response stream. In addition to the existing variables, you can use the following access log variables:

`$context.integration.responseTransferMode`

The response transfer mode of your integration. This can be either **BUFFERED** or **STREAMED**.

`$context.integration.timeToAllHeaders`

The time between when API Gateway establishes the integration connection to when it receives all integration response headers from the client.


`$context.integration.timeToFirstContent`

The time between when API Gateway establishes the integration connection to when it receives the first content bytes.

`$context.integration.latency` or `$context.integrationLatency`

The time when API Gateway establishes the integration connection to when the integration response stream is complete.

The following figure shows how these access log variables represent different components of a response stream.



For more information about access logs, see [the section called “CloudWatch logs”](#). You can also use X-Ray to monitor your response stream. For more information, see [the section called “X-Ray”](#).

Private integrations for REST APIs in API Gateway

Use a private integration to expose your HTTP/HTTPS resources within an Amazon VPC for access by clients outside of the VPC. This extends access to your private VPC resources beyond the VPC boundaries. You can control access to your API by using any of the [authorization methods](#) that API Gateway supports.

To create a private integration, you must first create a VPC link. API Gateway supports VPC links V2 for REST APIs. VPC links V2 let you create private integrations that connect your REST API to Application Load Balancers without using a Network Load Balancer. Using an Application Load Balancer allows you to connect to Amazon ECSs container-based applications and many other backends. VPC links V1 are considered a legacy integration type. While they are supported by API Gateway, we recommend that you don't create new VPC links V1.

Considerations

The following considerations might impact your use of private integrations:

- All resources must be owned by the same AWS account. This includes the load balancer, VPC link and REST API.
- By default, private integration traffic uses the HTTP protocol. To use HTTPS, specify an [uri](#) that contains a secure server name, such as `https://example.com:443/test`.
- In a private integration, API Gateway includes the [stage](#) portion of the API endpoint in the request to your backend resources. For example, if you request the test stage of an API, API Gateway includes `test/path` in the request to your private integration. To remove the stage name from the request to your backend resources, use [parameter mapping](#) to create an override for the `$context.requestOverride.path` variable.
- Private integrations with AWS Cloud Map aren't supported.

Topics

- [Set up VPC links V2 in API Gateway](#)
- [Set up a private integration](#)
- [Private integration using VPC links V1 \(legacy\)](#)

Set up VPC links V2 in API Gateway

VPC links enable you to create private integrations that connect your API routes to private resources in a VPC, such as Application Load Balancers or Amazon ECS container-based applications. A private integration uses a VPC link V2 to encapsulate connections between API Gateway and targeted VPC resources. You can reuse VPC links across different resources and APIs.

When you create a VPC link, API Gateway creates and manages [elastic network interfaces](#) for the VPC link V2 in your account. This process can take a few minutes. When a VPC link V2 is ready to use, its state transitions from PENDING to AVAILABLE.

Note

If no traffic is sent over the VPC link for 60 days, it becomes INACTIVE. When a VPC link is in an INACTIVE state, API Gateway deletes all of the VPC link's network interfaces. This causes API requests that depend on the VPC link to fail. If API requests resume, API Gateway reprovisions network interfaces. It can take a few minutes to create the network interfaces and reactivate the VPC link. You can use the VPC link status to monitor the state of your VPC link.

Create a VPC link V2 by using the AWS CLI

To create a VPC link V2, all resources involved must be owned by the same AWS account. The following [create-vpc-link](#) command creates a VPC link:

```
aws apigatewayv2 create-vpc-link --name MyVpcLink \
--subnet-ids subnet-aaaa subnet-bbbb \
--security-group-ids sg1234 sg5678
```

Note

VPC links V2 are immutable. After you create a VPC link V2, you can't change its subnets or security groups.

Delete a VPC link V2 by using the AWS CLI

The following [delete-vpc-link](#) command deletes a VPC link.

```
aws apigatewayv2 delete-vpc-link --vpc-link-id abcd123
```

Availability by Region

VPC links V2 are supported in the following Regions and Availability Zones:

Region name	Region	Supported Availability Zones
US East (Ohio)	us-east-2	use2-az1, use2-az2, use2-az3

Region name	Region	Supported Availability Zones
US East (N. Virginia)	us-east-1	use1-az1, use1-az2, use1-az4, use1-az5, use1-az6
US West (N. California)	us-west-1	usw1-az1, usw1-az3
US West (Oregon)	us-west-2	usw2-az1, usw2-az2, usw2-az3, usw2-az4
Asia Pacific (Hong Kong)	ap-east-1	ape1-az2, ape1-az3
Asia Pacific (Mumbai)	ap-south-1	aps1-az1, aps1-az2, aps1-az3
Asia Pacific (Seoul)	ap-northeast-2	apne2-az1, apne2-az2, apne2-az3
Asia Pacific (Singapore)	ap-southeast-1	apse1-az1, apse1-az2, apse1-az3
Asia Pacific (Sydney)	ap-southeast-2	apse2-az1, apse2-az2, apse2-az3
Asia Pacific (Tokyo)	ap-northeast-1	apne1-az1, apne1-az2, apne1-az4
Canada (Central)	ca-central-1	cac1-az1, cac1-az2
Europe (Frankfurt)	eu-central-1	euc1-az1, euc1-az2, euc1-az3
Europe (Ireland)	eu-west-1	euw1-az1, euw1-az2, euw1-az3
Europe (London)	eu-west-2	euw2-az1, euw2-az2, euw2-az3

Region name	Region	Supported Availability Zones
Europe (Paris)	eu-west-3	euw3-az1, euw3-az3
Europe (Spain)	eu-south-2	eus2-az1, eus2-az2, eus2-az3
Europe (Stockholm)	eu-north-1	eun1-az1, eun1-az2, eun1-az3
Middle East (Bahrain)	me-south-1	mes1-az1, mes1-az2, mes1-az3
South America (São Paulo)	sa-east-1	sae1-az1, sae1-az2, sae1-az3
AWS GovCloud (US-West)	us-gov-we st-1	usgw1-az1, usgw1-az2, usgw1-az3

Set up a private integration

To create a private integration with an Application Load Balancer or Network Load Balancer, you create an HTTP proxy integration, specify the [VPC link V2](#) to use, and provide the ARN of an Network Load Balancer or an Application Load Balancer. By default, private integration traffic uses the HTTP protocol. To use HTTPS, specify an [uri](#) that contains a secure server name, such as `https://example.com:443/test`. For a complete tutorial on how to create a REST API with a private integration, see [the section called “Tutorial: Create a REST API with a private integration”](#).

Create a private integration

The following procedure shows how to create a private integration that connects to a load balancer by using a VPC link V2.

AWS Management Console

For a tutorial on how to create a private integration see, [the section called “Tutorial: Create a REST API with a private integration”](#).

AWS CLI

The following [put-integration](#) command creates a private integration that connects to a load balancer by using a VPC link V2:

```
aws apigateway put-integration \
--rest-api-id abcdef123 \
--resource-id aaa000 \
--integration-target 'arn:aws:elasticloadbalancing:us-
east-2:111122223333:loadbalancer/app/myLoadBalancerName/1234567891011' \
--uri 'https://example.com:443/path' \
--http-method GET \
--type HTTP_PROXY \
--integration-http-method GET \
--connection-type VPC_LINK \
--connection-id bbb111
```

Instead of directly providing the connection ID, you can use a stage variable instead. When you deploy your API to a stage, you set the VPC link V2 ID. The following [put-integration](#) command creates a private integration using a stage variable for the VPC link V2 ID:

```
aws apigateway put-integration \
--rest-api-id abcdef123 \
--resource-id aaa000 \
--integration-target 'arn:aws:elasticloadbalancing:us-
east-2:111122223333:loadbalancer/app/myLoadBalancerName/1234567891011' \
--uri 'https://example.com:443/path' \
--http-method GET \
--type HTTP_PROXY \
--integration-http-method GET \
--connection-type VPC_LINK \
--connection-id "\${stageVariables.vpcLinkV2Id}"
```

Make sure to double-quote the stage variable expression (`\${stageVariables.vpcLinkV2Id}`) and escape the `$` character.

OpenAPI

You can set up an API with the private integration by importing the API's OpenAPI file. The settings are similar to the OpenAPI definitions of an API with HTTP integrations, with the following exceptions:

- You must explicitly set `connectionType` to `VPC_LINK`.
- You must explicitly set `connectionId` to the ID of a `VpcLinkV2` or to a stage variable referencing the ID of a `VpcLinkV2`.
- The `uri` parameter in the private integration points to an HTTP/HTTPS endpoint in the VPC, but is used instead to set up the integration request's Host header.
- The `uri` parameter in the private integration with an HTTPS endpoint in the VPC is used to verify the stated domain name against the one in the certificate installed on the VPC endpoint.

You can use a stage variable to reference the `VpcLinkV2` ID. Or you can assign the ID value directly to `connectionId`.

The following JSON-formatted OpenAPI file shows an example of an API with a VPC link as referenced by a stage variable (`#{stageVariables.vpcLinkIdV2}`):

```
{
  "swagger": "2.0",
  "info": {
    "version": "2017-11-17T04:40:23Z",
    "title": "MyApiWithVpcLinkV2"
  },
  "host": "abcdef123.execute-api.us-west-2.amazonaws.com",
  "basePath": "/test",
  "schemes": [
    "https"
  ],
  "paths": {
    "/": {
      "get": {
        "produces": [
          "application/json"
        ],
        "responses": {
          "200": {
            "description": "Success"
          }
        }
      }
    }
  }
}
```

```
        "description": "200 response",
        "schema": {
            "$ref": "#/definitions/Empty"
        }
    },
    "x-amazon-apigateway-integration": {
        "responses": {
            "default": {
                "statusCode": "200"
            }
        },
        "uri": "https://example.com:443/path",
        "passthroughBehavior": "when_no_match",
        "connectionType": "VPC_LINK",
        "connectionId": "${stageVariables.vpcLinkV2Id}",
        "integration-target": "arn:aws:elasticloadbalancing:us-
east-2:111122223333:loadbalancer/app/myLoadBalancerName/1234567891011",
        "httpMethod": "GET",
        "type": "http_proxy"
    }
}
},
"definitions": {
    "Empty": {
        "type": "object",
        "title": "Empty Schema"
    }
}
}
```

Update a private integration

The following example updates the VPC link V2 for a private integration.

AWS Management Console

To update a private integration

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose a REST API with a private integration.

3. Choose the resource and method that uses a private integration.
4. On the **Integration request tab**, under the **Integration request settings**, choose **Edit**.
5. You can edit the setting of your private integration. If you are currently using a VPC link V1, you can change your VPC link to a VPC link V2.
6. Choose **Save**.
7. Redeploy your API for the changes to take effect.

AWS CLI

The following [update-integration](#) command updates a private integration to use a VPC link V2:

```
aws apigateway update-integration \
--rest-api-id a1b2c3d4e5 \
--resource-id a1b2c3 \
--http-method GET \
--patch-operations "[{\\"op\\":\\"replace\\",\\"path\\":\\"/connectionId\\",\\"value\\":\\"pk0000\\"}, {\\"op\\":\\"replace\\",\\"path\\":\\"/uri\\",\\"value\\":\\"http://example.com\\"}, {\\"op\\":\\"replace\\",\\"path\\":\\"/integrationTarget\\",\\"value\\":\\"arn:aws:elasticloadbalancing:us-east-2:111122223333:loadbalancer/app/myLoadBalancerName/1234567891011\\"}]"
```

Private integration using VPC links V1 (legacy)

Note

The following implementation of private integrations uses VPC links V1. VPC links V1 are legacy resources. We recommend that you use [VPC links V2 for REST APIs](#).

To create a private integration, you must first create a Network Load Balancer. Your Network Load Balancer must have a [listener](#) that routes requests to resources in your VPC. To improve the availability of your API, ensure that your Network Load Balancer routes traffic to resources in more than one Availability Zone in the AWS Region. Then, you create a VPC link that you use to connect your API and your Network Load Balancer. After you create a VPC link, you create private integrations to route traffic from your API to resources in your VPC through your VPC link and Network Load Balancer. The Network Load Balancer and API must be owned by the same AWS account.

Topics

- [Set up a Network Load Balancer for API Gateway private integrations \(legacy\)](#)
- [Grant permissions for API Gateway to create a VPC link \(legacy\)](#)
- [Set up an API Gateway API with private integrations using the AWS CLI \(legacy\)](#)
- [API Gateway accounts used for private integrations \(legacy\)](#)

Set up a Network Load Balancer for API Gateway private integrations (legacy)

 **Note**

The following implementation of private integrations uses VPC links V1. VPC links V1 are legacy resources. We recommend that you use [VPC links V2 for REST APIs](#).

The following procedure outlines the steps to set up a Network Load Balancer (NLB) for API Gateway private integrations using the Amazon EC2 console and provides references for detailed instructions for each step.

For each VPC you have resources in, you only need to configure one NLB and one VPCLink. The NLB supports multiple [listeners](#) and [target groups](#) per NLB. You can configure each service as a specific listener on the NLB and use a single VPCLink to connect to the NLB. When creating the private integration in API Gateway you then define each service using the specific port that is assigned for each service. For more information, see [the section called “Tutorial: Create a REST API with a private integration”](#). The Network Load Balancer and API must be owned by the same AWS account.

To create a Network Load Balancer for private integration using the API Gateway console

1. Sign in to the AWS Management Console and open the Amazon EC2 console at <https://console.aws.amazon.com/ec2/>.
2. Set up a web server on an Amazon EC2 instance. For an example setup, see [Installing a LAMP Web Server on Amazon Linux 2](#).
3. Create a Network Load Balancer, register the EC2 instance with a target group, and add the target group to a listener of the Network Load Balancer. For details, follow the instructions in [Getting Started with Network Load Balancers](#).
4. After the Network Load Balancer is created, do the following:

- a. Note the ARN of the Network Load Balancer. You will need it to create a VPC link in API Gateway for integrating the API with the VPC resources behind the Network Load Balancer.
- b. Turn off security group evaluation for PrivateLink.
 - To turn off security group evaluation for PrivateLink traffic using the console, you can choose the **Security** tab, and then **Edit**. In the **Security settings**, clear **Enforce inbound rules on PrivateLink traffic**.
 - Use the following [set-security-groups](#) command to turn off security group evaluation for PrivateLink traffic:

```
aws elbv2 set-security-groups --load-balancer-  
arn arn:aws:elasticloadbalancing:us-east-2:111122223333:loadbalancer/net/  
my-loadbalancer/abc12345 \  
--security-groups sg-123345a --enforce-security-group-inbound-rules-on-  
private-link-traffic off
```

Note

Do not add any dependencies to API Gateway CIDRs as they are bound to change without notice.

Grant permissions for API Gateway to create a VPC link (legacy)

Note

The following implementation of private integrations uses VPC links V1. VPC links V1 are legacy resources. We recommend that you use [VPC links V2 for REST APIs](#).

For you or a user in your account to create and maintain a VPC link, you or the user must have permissions to create, delete, and view VPC endpoint service configurations, change VPC endpoint service permissions, and examine load balancers. To grant such permissions, use the following steps.

To grant permissions to create, update, and delete a VPC link

1. Create an IAM policy similar to the following:

JSON

```
{  
    "Version": "2012-10-17",  
    "Statement": [  
        {  
            "Effect": "Allow",  
            "Action": [  
                "apigateway:POST",  
                "apigateway:GET",  
                "apigateway:PATCH",  
                "apigateway:DELETE"  
            ],  
            "Resource": [  
                "arn:aws:apigateway:us-east-1:::vpclinks",  
                "arn:aws:apigateway:us-east-1:::vpclinks/*"  
            ]  
        },  
        {  
            "Effect": "Allow",  
            "Action": [  
                "elasticloadbalancing:DescribeLoadBalancers"  
            ],  
            "Resource": "*"  
        },  
        {  
            "Effect": "Allow",  
            "Action": [  
                "ec2:CreateVpcEndpointServiceConfiguration",  
                "ec2:DeleteVpcEndpointServiceConfigurations",  
                "ec2:DescribeVpcEndpointServiceConfigurations",  
                "ec2:ModifyVpcEndpointServicePermissions"  
            ],  
            "Resource": "*"  
        }  
    ]  
}
```

- If you want to enable tagging for your VPC link, make sure to allow tagging operations. For more information, see [the section called “Allow tagging operations”](#).
2. Create or choose an IAM role and attach the preceding policy to the role.
 3. Assign the IAM role to you or a user in your account who is creating VPC links.

Set up an API Gateway API with private integrations using the AWS CLI (legacy)

 **Note**

The following implementation of private integrations uses VPC links V1. VPC links V1 are legacy resources. We recommend that you use [VPC links V2 for REST APIs](#).

The following tutorial shows how to use the AWS CLI to create a VPC link and a private integration. The following prerequisites are required:

- You need an Network Load Balancer created and configured with your VPC source as the target. For more information, see [Set up a Network Load Balancer for API Gateway private integrations \(legacy\)](#). This must be in the same AWS account as your API. You need the Network Load Balancer ARN to create your VPC link.
- To create and manage a VpcLink, you need the permissions to create a VpcLink in your API. You don't need the permissions to use the VpcLink. For more information, see [Grant permissions for API Gateway to create a VPC link \(legacy\)](#).

To set up an API with the private integration using AWS CLI

1. Use the following [create-vpc-link](#) command to create a VpcLink targeting the specified Network Load Balancer:

```
aws apigateway create-vpc-link \
--name my-test-vpc-link \
--target-arns arn:aws:elasticloadbalancing:us-east-2:123456789012:loadbalancer/
net/my-vpclink-test-nlb/1234567890abcdef
```

The output of this command acknowledges the receipt of the request and shows the PENDING status for the VpcLink being created.

```
{  
    "status": "PENDING",  
    "targetArns": [  
        "arn:aws:elasticloadbalancing:us-east-2:123456789012:loadbalancer/net/my-vpc-link-test-nlb/1234567890abcdef"  
    ],  
    "id": "gim7c3",  
    "name": "my-test-vpc-link"  
}
```

It takes 2-4 minutes for API Gateway to finish creating the VpcLink. When the operation finishes successfully, the status is AVAILABLE. You can verify this by using the following [get-vpc-link](#) command:

```
aws apigateway get-vpc-link --vpc-link-id gim7c3
```

If the operation fails, you get a FAILED status, with the statusMessage containing the error message. For example, if you attempt to create a VpcLink with a Network Load Balancer that is already associated with a VPC endpoint, you get the following on the statusMessage property:

```
"NLB is already associated with another VPC Endpoint Service"
```

After the VpcLink is created successfully, you can create an API and integrate it with the VPC resource through the VpcLink.

Note the id value of the newly created VpcLink. In this example output, it's gim7c3. You need it to set up the private integration.

2. Use the following [create-rest-api](#) command to create an API Gateway [RestApi](#) resource:

```
aws apigateway create-rest-api --name 'My VPC Link Test'
```

Note the RestApi's id value and the RestApi's rootResourceId value in the returned result. You need this value to perform further operations on the API.

Next, you create an API with only a GET method on the root resource (/) and integrate the method with the VpcLink.

3. Use the following [put-method](#) command to create the GET / method:

```
aws apigateway put-method \
  --rest-api-id abcdef123 \
  --resource-id skpp60rab7 \
  --http-method GET \
  --authorization-type "NONE"
```

If you don't use the proxy integration with the VpcLink, you must also set up at least a method response of the 200 status code. You use the proxy integration here.

4. After you create the GET / method, you set up the integration. For a private integration, you use the connection-id parameter to provide the VpcLink ID. You can use either a stage variable or directly enter the VpcLink ID. The uri parameter is not used for routing requests to your endpoint, but is used for setting the Host header and for certificate validation.

Use the VPC link ID

Use the following [put-integration](#) command to use the VpcLink ID directly in the integration:

```
aws apigateway put-integration \
  --rest-api-id abcdef123 \
  --resource-id skpp60rab7 \
  --uri 'http://my-vpclink-test-nlb-1234567890abcdef.us-east-2.amazonaws.com' \
  \
  --http-method GET \
  --type HTTP_PROXY \
  --integration-http-method GET \
  --connection-type VPC_LINK \
  --connection-id gim7c3
```

Use a stage variable

Use the following [put-integration](#) command to use a stage variable to reference the VPC link ID. When you deploy your API to a stage, you set the VPC link ID.

```
aws apigateway put-integration \
  --rest-api-id abcdef123 \
  --resource-id skpp60rab7 \
```

```
--uri 'http://my-vpcLink-test-nlb-1234567890abcdef.us-east-2.amazonaws.com'  
\  
--http-method GET \  
--type HTTP_PROXY \  
--integration-http-method GET \  
--connection-type VPC_LINK \  
--connection-id "\${stageVariables.vpcLinkId}"
```

Make sure to double-quote the stage variable expression
(\\${stageVariables.vpcLinkId}) and escape the \$ character.

At any point, you can also update the integration to change the connection-id. Use the following [update-integration](#) command to update your integration:

```
aws apigateway update-integration \  
--rest-api-id abcdef123 \  
--resource-id skpp60rab7 \  
--http-method GET \  
--patch-operations '[{"op":"replace","path":"/  
connectionId","value":\${stageVariables.vpcLinkId}}]'
```

Make sure to use a stringified JSON list as the patch-operations parameter value.

Because you used the private proxy integration, your API is now ready for deployment and for test runs.

5. If you used the stage variable to define your connection-id, you need to deploy your API to test it. Use the following [create-deployment](#) command to deploy your API with a stage variable:

```
aws apigateway create-deployment \  
--rest-api-id abcdef123 \  
--stage-name test \  
--variables vpcLinkId=gim7c3
```

To update the stage variable with a different VpcLink ID, such as *asf9d7*, use the following [update-stage](#) command:

```
aws apigateway update-stage \  
--rest-api-id abcdef123 \  
--stage-name test
```

```
--stage-name test \
--patch-operations op=replace,path='/variables/vpcLinkId',value='asf9d7'
```

When you hardcode the connection-id property with the VpcLink ID literal, you don't need to deploy your API to test it. Use the [test-invoke-method](#) command to test your API before it is deployed.

6. Use the following command to invoke your API:

```
curl -X GET https://abcdef123.execute-api.us-east-2.amazonaws.com/test
```

Alternatively, you can enter your API's invoke-URL in a web browser to view the result.

API Gateway accounts used for private integrations (legacy)

The following region-specific API Gateway account IDs are automatically added to your VPC endpoint service as `AllowedPrincipals` when you create a VpcLink.

Region	Account ID
us-east-1	392220576650
us-east-2	718770453195
us-west-1	968246515281
us-west-2	109351309407
ca-central-1	796887884028
eu-west-1	631144002099
eu-west-2	544388816663
eu-west-3	061510835048
eu-central-1	474240146802
eu-central-2	166639821150

Region	Account ID
eu-north-1	394634713161
eu-south-1	753362059629
eu-south-2	359345898052
ap-northeast-1	969236854626
ap-northeast-2	020402002396
ap-northeast-3	360671645888
ap-southeast-1	195145609632
ap-southeast-2	798376113853
ap-southeast-3	652364314486
ap-southeast-4	849137399833
ap-south-1	507069717855
ap-south-2	644042651268
ap-east-1	174803364771
sa-east-1	287228555773
me-south-1	855739686837
me-central-1	614065512851

Mock integrations for REST APIs in API Gateway

Amazon API Gateway supports mock integrations for API methods. This feature enables API developers to generate API responses from API Gateway directly, without the need for an integration backend. As an API developer, you can use this feature to unblock dependent teams that need to work with an API before the project development is complete. You can also use this feature to provision a landing page for your API, which can provide an overview of and navigation

to your API. For an example of such a landing page, see the integration request and response of the GET method on the root resource of the example API discussed in [Tutorial: Create a REST API by importing an example](#).

As an API developer, you decide how API Gateway responds to a mock integration request. For this, you configure the method's integration request and integration response to associate a response with a given status code. For a method with the mock integration to return a 200 response, configure the integration request body mapping template to return the following.

```
{"statusCode": 200}
```

Configure a 200 integration response to have the following body mapping template, for example:

```
{
  "statusCode": 200,
  "message": "Go ahead without me."
}
```

Similarly, for the method to return, for example, a 500 error response, set up the integration request body mapping template to return the following.

```
{"statusCode": 500}
```

Set up a 500 integration response with, for example, the following mapping template:

```
{
  "statusCode": 500,
  "message": "The invoked method is not supported on the API resource."
}
```

Alternatively, you can have a method of the mock integration return the default integration response without defining the integration request mapping template. The default integration response is the one with an undefined **HTTP status regex**. Make sure appropriate passthrough behaviors are set.

Note

Mock integrations aren't intended to support large response templates. If you need them for your use case, you should consider using a Lambda integration instead.

Using an integration request mapping template, you can inject application logic to decide which mock integration response to return based on certain conditions. For example, you could use a scope query parameter on the incoming request to determine whether to return a successful response or an error response:

```
{  
  #if( $input.params('scope') == "internal" )  
  "statusCode": 200  
  #else  
  "statusCode": 500  
  #end  
}
```

This way, the method of the mock integration lets internal calls to go through while rejecting other types of calls with an error response.

In this section, we describe how to use the API Gateway console to enable the mock integration for an API method.

Topics

- [Enable mock integration using the API Gateway console](#)

Enable mock integration using the API Gateway console

You must have a method available in API Gateway. Follow the instructions in [Tutorial: Create a REST API with an HTTP non-proxy integration](#).

1. Choose an API resource and choose **Create method**.

To create the method, do the following:

- For **Method type**, select a method.
- For **Integration type**, select **Mock**.
- Choose **Create method**.
- On the **Method request** tab, for **Method request settings**, choose **Edit**.
- Choose **URL query string parameters**. Choose **Add query string** and for **Name**, enter **scope**. This query parameter determines if the caller is internal or otherwise.
- Choose **Save**.

2. On the **Method response** tab, choose **Create response**, and then do the following:
 - a. For **HTTP Status**, enter **500**.
 - b. Choose **Save**.
3. On the **Integration request** tab, for **Integration request settings**, choose **Edit**.
4. Choose **Mapping templates**, and then do the following:
 - a. Choose **Add mapping template**.
 - b. For **Content type**, enter **application/json**.
 - c. For **Template body**, enter the following:

```
{  
    #if( $input.params('scope') == "internal" )  
        "statusCode": 200  
    #else  
        "statusCode": 500  
    #end  
}
```

- d. Choose **Save**.
5. On the **Integration response** tab, for the **Default - Response** choose **Edit**.
6. Choose **Mapping templates**, and then do the following:
 - a. For **Content type**, enter **application/json**.
 - b. For **Template body**, enter the following:

```
{  
    "statusCode": 200,  
    "message": "Go ahead without me"  
}
```

- c. Choose **Save**.
7. Choose **Create response**.

To create a 500 response, do the following:

- a. For **HTTP status regex**, enter **5\d{2}**.
- b. For **Method response status**, select **500**.

- c. Choose **Save**.
- d. For **5\d{2} - Response**, choose **Edit**.
- e. Choose **Mapping templates**, and then choose **Add mapping template**.
- f. For **Content type**, enter **application/json**.
- g. For **Template body**, enter the following:

```
{  
    "statusCode": 500,  
    "message": "The invoked method is not supported on the API resource."  
}
```

- h. Choose **Save**.
8. Choose the **Test** tab. You might need to choose the right arrow button to show the tab. To test your mock integration, do the following:

- a. Enter scope=internal under **Query strings**. Choose **Test**. The test result shows:

Request: /?scope=internal
Status: 200
Latency: 26 ms
Response Body

```
{  
    "statusCode": 200,  
    "message": "Go ahead without me"  
}
```

Response Headers

```
{"Content-Type": "application/json"}
```

- b. Enter scope=public under **Query strings** or leave it blank. Choose **Test**. The test result shows:

Request: /
Status: 500
Latency: 16 ms

Response Body

```
{  
  "statusCode": 500,  
  "message": "The invoked method is not supported on the API resource."  
}
```

Response Headers

```
{"Content-Type": "application/json"}
```

You can also return headers in a mock integration response by first adding a header to the method response and then setting up a header mapping in the integration response. In fact, this is how the API Gateway console enables CORS support by returning CORS required headers.

Request validation for REST APIs in API Gateway

You can configure API Gateway to perform basic validation of an API request before proceeding with the integration request. When the validation fails, API Gateway immediately fails the request, returns a 400 error response to the caller, and publishes the validation results in CloudWatch Logs. This reduces unnecessary calls to the backend. More importantly, it lets you focus on the validation efforts specific to your application. You can validate a request body by verifying that required request parameters are valid and non-null or by specifying a model schema for more complicated data validation.

Topics

- [Overview of basic request validation in API Gateway](#)
- [Data models for REST APIs](#)
- [Set up basic request validation in API Gateway](#)
- [AWS CloudFormation template of a sample API with basic request validation](#)

Overview of basic request validation in API Gateway

API Gateway can perform the basic request validation, so that you can focus on app-specific validation in the backend. For validation, API Gateway verifies either or both of the following conditions:

- The required request parameters in the URI, query string, and headers of an incoming request are included and not blank. API Gateway only checks the existence of a parameter and doesn't check the type or format.
- The applicable request payload adheres to the configured [JSON schema](#) request of the method for a given content type. If no matching content type is found, request validation is not performed. To use the same model regardless of the content type, set the content type for your data model to \$default.

To turn on validation, you specify validation rules in a [request validator](#), add the validator to the API's [map of request validators](#), and assign the validator to individual API methods.

 **Note**

Request body validation and [Method request behavior for payloads without mapping templates for REST APIs in API Gateway](#) are two separate topics. When a request payload does not have a matching model schema, you can choose to passthrough or block the original payload. For more information, see [Method request behavior for payloads without mapping templates for REST APIs in API Gateway](#).

Data models for REST APIs

In API Gateway, a model defines the data structure of a payload. In API Gateway, models are defined using the [JSON schema draft 4](#). The following JSON object is sample data in the Pet Store example.

```
{  
  "id": 1,  
  "type": "dog",  
  "price": 249.99  
}
```

The data contains the id, type, and price of the pet. A model of this data allows you to:

- Use basic request validation.
- Create mapping templates for data transformation.
- Create a user-defined data type (UDT) when you generate an SDK.

```
1 {
2 "$schema": "http://json-schema.org/draft-04/
schema#",
3 "title": "PetStoreModel", ← 1
4 "type" : "object", ← 2
5 "required" : [ "price", "type" ], ←
6 "properties" : {
7   "id" : { ← 3
8     "type" : "integer" ←
9   },
10  "type" : { ← 4
11    "type" : "string",
12    "enum" : [ "dog", "cat", "fish" ] ← 5
13  },
14  "price" : { ← 6
15    "type" : "number",
16    "minimum" : 25.0,
17    "maximum" : 500.0
18  }
19 }
20 }
```

In this model:

1. The `$schema` object represents a valid JSON Schema version identifier. This schema is the JSON Schema draft v4.
2. The `title` object is a human-readable identifier for the model. This title is `PetStoreModel`.
3. The `required` validation keyword requires `type`, and `price` for basic request validation.
4. The `properties` of the model are `id`, `type`, and `price`. Each object has properties that are described in the model.
5. The object `type` can have only the values `dog`, `cat`, or `fish`.
6. The object `price` is a number and is constrained with a `minimum` of 25 and a `maximum` of 500.

PetStore model

```
1 {
2 "$schema": "http://json-schema.org/draft-04/schema#",
3 "title": "PetStoreModel",
4 "type" : "object",
5 "required" : [ "price", "type" ],
6 "properties" : {
7     "id" : {
8         "type" : "integer"
9     },
10    "type" : {
11        "type" : "string",
12        "enum" : [ "dog", "cat", "fish" ]
13    },
14    "price" : {
15        "type" : "number",
16        "minimum" : 25.0,
17        "maximum" : 500.0
18    }
19 }
20 }
```

In this model:

1. On line 2, the `$schema` object represents a valid JSON Schema version identifier. This schema is the JSON Schema draft v4.
2. On line 3, the `title` object is a human-readable identifier for the model. This title is `PetStoreModel`.
3. On line 5, the `required` validation keyword requires `type`, and `price` for basic request validation.
4. On lines 6 -- 17, the `properties` of the model are `id`, `type`, and `price`. Each object has properties that are described in the model.
5. On line 12, the object `type` can have only the values `dog`, `cat`, or `fish`.
6. On lines 14 -- 17, the object `price` is a number and is constrained with a `minimum` of 25 and a `maximum` of 500.

Creating more complex models

You can use the `$ref` primitive to create reusable definitions for longer models. For example, you can create a definition called `Price` in the `definitions` section describing the `price` object. The value of `$ref` is the `Price` definition.

```
{  
  "$schema" : "http://json-schema.org/draft-04/schema#",  
  "title" : "PetStoreModelReusableRef",  
  "required" : ["price", "type" ],  
  "type" : "object",  
  "properties" : {  
    "id" : {  
      "type" : "integer"  
    },  
    "type" : {  
      "type" : "string",  
      "enum" : [ "dog", "cat", "fish" ]  
    },  
    "price" : {  
      "$ref": "#/definitions/Price"  
    }  
  },  
  "definitions" : {  
    "Price": {  
      "type" : "number",  
      "minimum" : 25.0,  
      "maximum" : 500.0  
    }  
  }  
}
```

You can also reference another model schema defined in an external model file. Set the value of the `$ref` property to the location of the model. In the following example, the `Price` model is defined in the `PetStorePrice` model in API `a1234`.

```
{  
  "$schema" : "http://json-schema.org/draft-04/schema#",  
  "title" : "PetStorePrice",  
  "type": "number",  
  "minimum": 25,  
  "maximum": 500
```

```
}
```

The longer model can reference the PetStorePrice model.

```
{
  "$schema" : "http://json-schema.org/draft-04/schema#",
  "title" : "PetStoreModelReusableRefAPI",
  "required" : [ "price", "type" ],
  "type" : "object",
  "properties" : {
    "id" : {
      "type" : "integer"
    },
    "type" : {
      "type" : "string",
      "enum" : [ "dog", "cat", "fish" ]
    },
    "price" : {
      "$ref": "https://apigateway.amazonaws.com/restapis/a1234/models/PetStorePrice"
    }
  }
}
```

Using output data models

If you transform your data, you can define a payload model in the integration response. A payload model can be used when you generate an SDK. For strongly typed languages, such as Java, Objective-C, or Swift, the object corresponds to a user-defined data type (UDT). API Gateway creates a UDT if you provide it with a data model when you generate an SDK. For more information about data transformations, see [Mapping template transformations for REST APIs in API Gateway](#).

The following example is output data from an integration response.

```
{
[
  {
    "description" : "Item 1 is a dog.",
    "askingPrice" : 249.99
  },
  {
    "description" : "Item 2 is a cat.",
    "askingPrice" : 124.99
  }
]
```

```
},
{
  "description" : "Item 3 is a fish.",
  "askingPrice" : 0.99
}
]
}
```

The following example is a payload model that describes the output data.

```
{
"$schema": "http://json-schema.org/draft-04/schema#",
"title": "PetStoreOutputModel",
"type" : "object",
"required" : [ "description", "askingPrice" ],
"properties" : {
  "description" : {
    "type" : "string"
  },
  "askingPrice" : {
    "type" : "number",
    "minimum" : 25.0,
    "maximum" : 500.0
  }
}
}
```

With this model, you can call an SDK to retrieve the `description` and `askingPrice` property values by reading the `PetStoreOutputModel[i].description` and `PetStoreOutputModel[i].askingPrice` properties. If no model is provided, API Gateway uses the empty model to create a default UDT.

Next steps

- This section provides resources that you can use to gain more knowledge about the concepts presented in this topic.

You can follow the request validation tutorials:

- [Set up request validation using the API Gateway console](#)
- [Set up basic request validation using the AWS CLI](#)
- [Set up basic request validation using an OpenAPI definition](#)

- For more information about data transformation and mapping templates, [Mapping template transformations for REST APIs in API Gateway](#).

Set up basic request validation in API Gateway

This section shows how to set up request validation for API Gateway using the console, AWS CLI, and an OpenAPI definition.

Topics

- [Set up request validation using the API Gateway console](#)
- [Set up basic request validation using the AWS CLI](#)
- [Set up basic request validation using an OpenAPI definition](#)

Set up request validation using the API Gateway console

You can use the API Gateway console to validate a request by selecting one of three validators for an API request:

- **Validate body.**
- **Validate query string parameters and headers.**
- **Validate body, query string parameters, and headers.**

When you apply one of the validators on an API method, the API Gateway console adds the validator to the API's [RequestValidators](#) map.

To follow this tutorial, you'll use an CloudFormation template to create an incomplete API Gateway API. This API has a /validator resource with GET and POST methods. Both methods are integrated with the `http://petstore-demo-endpoint.execute-api.com/petstore/pets` HTTP endpoint. You will configure two kinds of request validation:

- In the GET method, you will configure request validation for URL query string parameters.
- In the POST method, you will configure request validation for the request body.

This will allow only certain API calls to pass through to the API.

Download and unzip [the app creation template for CloudFormation](#). You'll use this template to create an incomplete API. You will finish the rest of the steps in the API Gateway console.

To create an CloudFormation stack

1. Open the CloudFormation console at <https://console.aws.amazon.com/cloudformation>.
2. Choose **Create stack** and then choose **With new resources (standard)**.
3. For **Specify template**, choose **Upload a template file**.
4. Select the template that you downloaded.
5. Choose **Next**.
6. For **Stack name**, enter **request-validation-tutorial-console** and then choose **Next**.
7. For **Configure stack options**, choose **Next**.
8. For **Capabilities**, acknowledge that CloudFormation can create IAM resources in your account.
9. Choose **Next**, and then choose **Submit**.

CloudFormation provisions the resources specified in the template. It can take a few minutes to finish provisioning your resources. When the status of your CloudFormation stack is **CREATE_COMPLETE**, you're ready to move on to the next step.

To select your newly created API

1. Select the newly created **request-validation-tutorial-console** stack.
2. Choose **Resources**.
3. Under **Physical ID**, choose your API. This link will direct you to the API Gateway console.

Before you modify the GET and POST methods, you must create a model.

To create a model

1. A model is required to use request validation on the body of an incoming request. To create a model, in the main navigation pane, choose **Models**.
2. Choose **Create model**.
3. For **Name**, enter **PetStoreModel**.
4. For **Content Type**, enter **application/json**. If no matching content type is found, request validation is not performed. To use the same model regardless of the content type, enter **\$default**.
5. For **Description**, enter **My PetStore Model** as the model description.

6. For **Model schema**, paste the following model into the code editor, and choose **Create**.

```
{  
    "type" : "object",  
    "required" : [ "name", "price", "type" ],  
    "properties" : {  
        "id" : {  
            "type" : "integer"  
        },  
        "type" : {  
            "type" : "string",  
            "enum" : [ "dog", "cat", "fish" ]  
        },  
        "name" : {  
            "type" : "string"  
        },  
        "price" : {  
            "type" : "number",  
            "minimum" : 25.0,  
            "maximum" : 500.0  
        }  
    }  
}
```

For more information about the model, see [Data models for REST APIs](#).

To configure request validation for a GET method

1. In the main navigation pane, choose **Resources**, and then select the **GET** method.
2. On the **Method request** tab, under **Method request settings**, choose **Edit**.
3. For **Request validator**, select **Validate query string parameters and headers**.
4. Under **URL query string parameters**, do the following:
 - a. Choose **Add query string**.
 - b. For **Name**, enter **petType**.
 - c. Turn on **Required**.
 - d. Keep **Caching** turned off.
5. Choose **Save**.
6. On the **Integration request** tab, under **Integration request settings**, choose **Edit**.

7. Under **URL query string parameters**, do the following:

- a. Choose **Add query string**.
- b. For **Name**, enter **petType**.
- c. For **Mapped from**, enter **method.request.querystring.petType**. This maps the **petType** to the pet's type.

For more information about data mapping, see [the data mapping tutorial](#).

- d. Keep **Caching** turned off.

8. Choose **Save**.

To test request validation for the GET method

1. Choose the **Test** tab. You might need to choose the right arrow button to show the tab.
2. For **Query strings**, enter **petType=dog**, and then choose **Test**.
3. The method test will return **200 OK** and a list of dogs.

For information about how to transform this output data, see the [data mapping tutorial](#).

4. Remove **petType=dog** and choose **Test**.
5. The method test will return a **400** error with the following error message:

```
{  
  "message": "Missing required request parameters: [petType]"  
}
```

To configure request validation for the POST method

1. In the main navigation pane, choose **Resources**, and then select the **POST** method.
2. On the **Method request** tab, under **Method request settings**, choose **Edit**.
3. For **Request validator**, select **Validate body**.
4. Under **Request body**, choose **Add model**.
5. For **Content type**, enter **application/json**. If no matching content type is found, request validation is not performed. To use the same model regardless of the content type, enter **\$default**.

For Model, select **PetStoreModel**.

6. Choose **Save**.

To test request validation for a POST method

1. Choose the **Test** tab. You might need to choose the right arrow button to show the tab.
2. For **Request body** paste the following into the code editor:

```
{  
    "id": 2,  
    "name": "Bella",  
    "type": "dog",  
    "price": 400  
}
```

Choose **Test**.

3. The method test will return 200 OK and a success message.
4. For **Request body** paste the following into the code editor:

```
{  
    "id": 2,  
    "name": "Bella",  
    "type": "dog",  
    "price": 4000  
}
```

Choose **Test**.

5. The method test will return a 400 error with the following error message:

```
{  
    "message": "Invalid request body"  
}
```

At the bottom of the test logs, the reason for the invalid request body is returned. In this case, the price of the pet was outside the maximum specified in the model.

To delete an CloudFormation stack

1. Open the CloudFormation console at <https://console.aws.amazon.com/cloudformation>.
2. Select your CloudFormation stack.
3. Choose **Delete** and then confirm your choice.

Next steps

- For information about how to transform output data and perform more data mapping, see the [data mapping tutorial](#).
- Follow the [Set up basic request validation using the AWS CLI](#) tutorial, to do similar steps using the AWS CLI.

Set up basic request validation using the AWS CLI

You can create a validator to set up request validation using the AWS CLI. To follow this tutorial, you'll use an CloudFormation template to create an incomplete API Gateway API.

 **Note**

This is not the same CloudFormation template as the console tutorial.

Using a pre-exposed `/validatorresource`, you will create GET and POST methods. Both methods will be integrated with the `http://petstore-demo-endpoint.execute-api.com/petstore/pets` HTTP endpoint. You will configure the following two request validations:

- On the GET method, you will create a `params-only` validator to validate URL query string parameters.
- On the POST method, you will create a `body-only` validator to validate the request body.

This will allow only certain API calls to pass through to the API.

To create an CloudFormation stack

Download and unzip [the app creation template for CloudFormation](#).

To complete the following tutorial, you need the [AWS Command Line Interface \(AWS CLI\) version 2](#).

For long commands, an escape character (\) is used to split a command over multiple lines.

 **Note**

In Windows, some Bash CLI commands that you commonly use (such as zip) are not supported by the operating system's built-in terminals. To get a Windows-integrated version of Ubuntu and Bash, [install the Windows Subsystem for Linux](#). Example CLI commands in this guide use Linux formatting. Commands which include inline JSON documents must be reformatted if you are using the Windows CLI.

1. Use the following command to create the CloudFormation stack.

```
aws cloudformation create-stack --stack-name request-validation-tutorial-cli  
--template-body file://request-validation-tutorial-cli.zip --capabilities  
CAPABILITY_NAMED_IAM
```

2. CloudFormation provisions the resources specified in the template. It can take a few minutes to finish provisioning your resources. Use the following command to see the status of your CloudFormation stack.

```
aws cloudformation describe-stacks --stack-name request-validation-tutorial-cli
```

3. When the status of your CloudFormation stack is StackStatus: "CREATE_COMPLETE", use the following command to retrieve relevant output values for future steps.

```
aws cloudformation describe-stacks --stack-name request-validation-tutorial-cli  
--query "Stacks[*].Outputs[*].{OutputKey: OutputKey, OutputValue: OutputValue,  
Description: Description}"
```

The output values are the following:

- Apild, which is the ID for the API. For this tutorial, the API ID is abc123.
- Resourceld, which is the ID for the validator resource where the GET and POST methods are exposed. For this tutorial, the Resource ID is efg456

To create the request validators and import a model

1. A validator is required to use request validation with the AWS CLI. Use the following command to create a validator that validates only request parameters.

```
aws apigateway create-request-validator --rest-api-id abc123 \
--no-validate-request-body \
--validate-request-parameters \
--name params-only
```

Note the ID of the params-only validator.

2. Use the following command to create a validator that validates only the request body.

```
aws apigateway create-request-validator --rest-api-id abc123 \
--validate-request-body \
--no-validate-request-parameters \
--name body-only
```

Note the ID of the body-only validator.

3. A model is required to use request validation on the body of an incoming request. Use the following command to import a model.

```
aws apigateway create-model --rest-api-id abc123 --name PetStoreModel --description
'My PetStore Model' --content-type 'application/json' --schema '{"type": "object", "required": [ "name", "price", "type" ], "properties": { "id" : {"type" : "integer"}, "type" : {"type" : "string", "enum" : [ "dog", "cat", "fish" ]}, "name" : { "type" : "string"}, "price" : {"type" : "number", "minimum" : 25.0, "maximum" : 500.0}}}'
```

If no matching content type is found, request validation is not performed. To use the same model regardless of the content type, specify \$default as the key.

To create the GET and POST methods

1. Use the following command to add the GET HTTP method on the /validate resource. This command creates the GETmethod, adds the params-only validator, and sets the query string petType as required.

```
aws apigateway put-method --rest-api-id abc123 \
    --resource-id efg456 \
    --http-method GET \
    --authorization-type "NONE" \
    --request-validator-id aaa111 \
    --request-parameters "method.request.querystring.petType=true"
```

Use the following command to add the POST HTTP method on the /validate resource. This command creates the POSTmethod, adds the body-only validator, and attaches the model to the body-only validator.

```
aws apigateway put-method --rest-api-id abc123 \
    --resource-id efg456 \
    --http-method POST \
    --authorization-type "NONE" \
    --request-validator-id bbb222 \
    --request-models 'application/json'=PetStoreModel
```

2. Use the following command to set up the 200 OK response of the GET /validate method.

```
aws apigateway put-method-response --rest-api-id abc123 \
    --resource-id efg456 \
    --http-method GET \
    --status-code 200
```

Use the following command to set up the 200 OK response of the POST /validate method.

```
aws apigateway put-method-response --rest-api-id abc123 \
    --resource-id efg456 \
    --http-method POST \
    --status-code 200
```

3. Use the following command to set up an Integration with a specified HTTP endpoint for the GET /validation method.

```
aws apigateway put-integration --rest-api-id abc123 \
    --resource-id efg456 \
    --http-method GET \
    --type HTTP \
    --integration-http-method GET \
```

```
--request-parameters '{"integration.request.querystring.type" :  
"method.request.querystring.petType"}'  
--uri 'http://petstore-demo-endpoint.execute-api.com/petstore/pets'
```

Use the following command to set up an Integration with a specified HTTP endpoint for the POST /validation method.

```
aws apigateway put-integration --rest-api-id abc123 \  
    --resource-id efg456 \  
    --http-method POST \  
    --type HTTP \  
    --integration-http-method GET \  
    --uri 'http://petstore-demo-endpoint.execute-api.com/petstore/pets'
```

4. Use the following command to set up an integration response for the GET /validation method.

```
aws apigateway put-integration-response --rest-api-id abc123 \  
    --resource-id efg456 \  
    --http-method GET \  
    --status-code 200 \  
    --selection-pattern ""
```

Use the following command to set up an integration response for the POST /validation method.

```
aws apigateway put-integration-response --rest-api-id abc123 \  
    --resource-id efg456 \  
    --http-method POST \  
    --status-code 200 \  
    --selection-pattern ""
```

To test the API

1. To test the GET method, which will perform request validation for the query strings, use the following command:

```
aws apigateway test-invoke-method --rest-api-id abc123 \  
    --resource-id efg456 \  
    --http-method GET \  
    --querystring-type petType
```

```
--path-with-query-string '/validate?petType=dog'
```

The result will return a 200 OK and list of dogs.

2. Use the following command to test without including the query string petType

```
aws apigateway testInvokeMethod --rest-api-id abc123 \
--resource-id efg456 \
--http-method GET
```

The result will return a 400 error.

3. To test the POST method, which will perform request validation for the request body, use the following command:

```
aws apigateway testInvokeMethod --rest-api-id abc123 \
--resource-id efg456 \
--http-method POST \
--body '{"id": 1, "name": "bella", "type": "dog", "price" : 400 }'
```

The result will return a 200 OK and a success message.

4. Use the following command to test using an invalid body.

```
aws apigateway testInvokeMethod --rest-api-id abc123 \
--resource-id efg456 \
--http-method POST \
--body '{"id": 1, "name": "bella", "type": "dog", "price" : 1000 }'
```

The result will return a 400 error, as the price of the dog is over the maximum price defined by the model.

To delete an CloudFormation stack

- Use the following command to delete your CloudFormation resources.

```
aws cloudformation delete-stack --stack-name request-validation-tutorial-cli
```

Set up basic request validation using an OpenAPI definition

You can declare a request validator at the API level by specifying a set of the [x-amazon-apigateway-request-validation object](#) objects in the [x-amazon-apigateway-request-validation object](#) map to select what part of the request will be validated. In the example OpenAPI definition, there are two validators:

- `all` validator which validates both the body, using the `RequestBodyModel` data model, and the parameters.

The `RequestBodyModel` data model requires that the input JSON object contains the `name`, `type`, and `price` properties. The `name` property can be any string, `type` must be one of the specified enumeration fields (`["dog", "cat", "fish"]`), and `price` must range between 25 and 500. The `id` parameter is not required.

- `param-only` which validates only the parameters.

To turn a request validator on all methods of an API, specify an [x-amazon-apigateway-request-validator property](#) property at the API level of the OpenAPI definition. In the example OpenAPI definition, the `all` validator is used on all API methods, unless otherwise overridden. When using a model to validate the body, if no matching content type is found, request validation is not performed. To use the same model regardless of the content type, specify `$default` as the key.

To turn on a request validator on an individual method, specify the `x-amazon-apigateway-request-validator` property at the method level. In the example, OpenAPI definition, the `param-only` validator overwrites the `all` validator on the GET method.

To import the OpenAPI example into API Gateway, see the following instructions to [Import a Regional API into API Gateway](#) or to [Import an edge-optimized API into API Gateway](#).

OpenAPI 3.0

```
{  
  "openapi" : "3.0.1",  
  "info" : {  
    "title" : "ReqValidators Sample",  
    "version" : "1.0.0"  
  },  
  "servers" : [ {  
    "url" : "/{basePath}"  
  }  
]
```

```
"variables" : {
    "basePath" : {
        "default" : "/v1"
    }
},
} ],
"paths" : {
    "/validation" : {
        "get" : {
            "parameters" : [ {
                "name" : "q1",
                "in" : "query",
                "required" : true,
                "schema" : {
                    "type" : "string"
                }
            }],
            "responses" : {
                "200" : {
                    "description" : "200 response",
                    "headers" : {
                        "test-method-response-header" : {
                            "schema" : {
                                "type" : "string"
                            }
                        }
                    },
                    "content" : {
                        "application/json" : {
                            "schema" : {
                                "$ref" : "#/components/schemas/ArrayOfError"
                            }
                        }
                    }
                }
            }
        },
        "x-amazon-apigateway-request-validator" : "params-only",
        "x-amazon-apigateway-integration" : {
            "httpMethod" : "GET",
            "uri" : "http://petstore-demo-endpoint.execute-api.com/petstore/pets",
            "responses" : {
                "default" : {
                    "statusCode" : "400",
                    "responseParameters" : {

```

```
        "method.response.header.test-method-response-header" : "'static
value'"
    },
    "responseTemplates" : {
        "application/xml" : "xml 400 response template",
        "application/json" : "json 400 response template"
    }
},
"2\\d{2}" : {
    "statusCode" : "200"
}
},
"requestParameters" : {
    "integration.request.querystring.type" : "method.request.querystring.q1"
},
"passthroughBehavior" : "when_no_match",
"type" : "http"
},
},
"post" : {
    "parameters" : [ {
        "name" : "h1",
        "in" : "header",
        "required" : true,
        "schema" : {
            "type" : "string"
        }
    }],
    "requestBody" : {
        "content" : {
            "application/json" : {
                "schema" : {
                    "$ref" : "#/components/schemas/RequestBodyModel"
                }
            }
        },
        "required" : true
    },
    "responses" : {
        "200" : {
            "description" : "200 response",
            "headers" : {
                "test-method-response-header" : {
                    "schema" : {
```

```
        "type" : "string"
    }
}
},
"content" : {
    "application/json" : {
        "schema" : {
            "$ref" : "#/components/schemas/ArrayOfError"
        }
    }
}
},
"x-amazon-apigateway-request-validator" : "all",
"x-amazon-apigateway-integration" : {
    "httpMethod" : "POST",
    "uri" : "http://petstore-demo-endpoint.execute-api.com/petstore/pets",
    "responses" : {
        "default" : {
            "statusCode" : "400",
            "responseParameters" : {
                "method.response.header.test-method-response-header" : "'static
value'"
            },
            "responseTemplates" : {
                "application/xml" : "xml 400 response template",
                "application/json" : "json 400 response template"
            }
        },
        "2\\d{2}" : {
            "statusCode" : "200"
        }
    },
    "requestParameters" : {
        "integration.request.header.custom_h1" : "method.request.header.h1"
    },
    "passthroughBehavior" : "when_no_match",
    "type" : "http"
}
}
},
"components" : {
    "schemas" : {
```

```
"RequestBodyModel" : {
    "required" : [ "name", "price", "type" ],
    "type" : "object",
    "properties" : {
        "id" : {
            "type" : "integer"
        },
        "type" : {
            "type" : "string",
            "enum" : [ "dog", "cat", "fish" ]
        },
        "name" : {
            "type" : "string"
        },
        "price" : {
            "maximum" : 500.0,
            "minimum" : 25.0,
            "type" : "number"
        }
    }
},
"ArrayOfError" : {
    "type" : "array",
    "items" : {
        "$ref" : "#/components/schemas/Error"
    }
},
"Error" : {
    "type" : "object"
}
},
"x-amazon-apigateway-requestValidators" : {
    "all" : {
        "validateRequestParameters" : true,
        "validateRequestBody" : true
    },
    "params-only" : {
        "validateRequestParameters" : true,
        "validateRequestBody" : false
    }
}
```

OpenAPI 2.0

```
{  
  "swagger" : "2.0",  
  "info" : {  
    "version" : "1.0.0",  
    "title" : "ReqValidators Sample"  
  },  
  "basePath" : "/v1",  
  "schemes" : [ "https" ],  
  "paths" : {  
    "/validation" : {  
      "get" : {  
        "produces" : [ "application/json", "application/xml" ],  
        "parameters" : [ {  
          "name" : "q1",  
          "in" : "query",  
          "required" : true,  
          "type" : "string"  
        } ],  
        "responses" : {  
          "200" : {  
            "description" : "200 response",  
            "schema" : {  
              "$ref" : "#/definitions/ArrayOfError"  
            },  
            "headers" : {  
              "test-method-response-header" : {  
                "type" : "string"  
              }  
            }  
          }  
        },  
        "x-amazon-apigateway-request-validator" : "params-only",  
        "x-amazon-apigateway-integration" : {  
          "httpMethod" : "GET",  
          "uri" : "http://petstore-demo-endpoint.execute-api.com/petstore/pets",  
          "responses" : {  
            "default" : {  
              "statusCode" : "400",  
              "responseParameters" : {  
                "method.response.header.test-method-response-header" : "'static  
value'"  
              }  
            }  
          }  
        }  
      }  
    }  
  }  
}
```

```
        "responseTemplates" : {
            "application/xml" : "xml 400 response template",
            "application/json" : "json 400 response template"
        }
    },
    "2\\d{2}" : {
        "statusCode" : "200"
    }
},
"requestParameters" : {
    "integration.request.querystring.type" : "method.request.querystring.q1"
},
"passthroughBehavior" : "when_no_match",
"type" : "http"
},
},
"post" : {
    "consumes" : [ "application/json" ],
    "produces" : [ "application/json", "application/xml" ],
    "parameters" : [ {
        "name" : "h1",
        "in" : "header",
        "required" : true,
        "type" : "string"
    }, {
        "in" : "body",
        "name" : "RequestBodyModel",
        "required" : true,
        "schema" : {
            "$ref" : "#/definitions/RequestBodyModel"
        }
    } ],
    "responses" : {
        "200" : {
            "description" : "200 response",
            "schema" : {
                "$ref" : "#/definitions/ArrayOfError"
            },
            "headers" : {
                "test-method-response-header" : {
                    "type" : "string"
                }
            }
        }
    }
}
```

```
        },
        "x-amazon-apigateway-request-validator" : "all",
        "x-amazon-apigateway-integration" : {
            "httpMethod" : "POST",
            "uri" : "http://petstore-demo-endpoint.execute-api.com/petstore/pets",
            "responses" : {
                "default" : {
                    "statusCode" : "400",
                    "responseParameters" : {
                        "method.response.header.test-method-response-header" : "'static
value'"
                    },
                    "responseTemplates" : {
                        "application/xml" : "xml 400 response template",
                        "application/json" : "json 400 response template"
                    }
                },
                "2\\d{2}" : {
                    "statusCode" : "200"
                }
            },
            "requestParameters" : {
                "integration.request.header.custom_h1" : "method.request.header.h1"
            },
            "passthroughBehavior" : "when_no_match",
            "type" : "http"
        }
    }
},
"definitions" : {
    "RequestBodyModel" : {
        "type" : "object",
        "required" : [ "name", "price", "type" ],
        "properties" : {
            "id" : {
                "type" : "integer"
            },
            "type" : {
                "type" : "string",
                "enum" : [ "dog", "cat", "fish" ]
            },
            "name" : {
                "type" : "string"
            }
        }
    }
}
```

```
        },
        "price" : {
            "type" : "number",
            "minimum" : 25.0,
            "maximum" : 500.0
        }
    },
},
"ArrayOfError" : {
    "type" : "array",
    "items" : {
        "$ref" : "#/definitions/Error"
    }
},
"Error" : {
    "type" : "object"
}
},
"x-amazon-apigateway-requestValidators" : {
    "all" : {
        "validateRequestParameters" : true,
        "validateRequestBody" : true
    },
    "params-only" : {
        "validateRequestParameters" : true,
        "validateRequestBody" : false
    }
}
}
```

AWS CloudFormation template of a sample API with basic request validation

The following CloudFormation example template definition defines a sample API with request validation enabled. The API is a subset of the [PetStore API](#). It exposes a POST method to add a pet to the pets collection and a GET method to query pets by a specified type.

There are two request validators declared:

GETValidator

This validator is enabled on the GET method. It allows API Gateway to verify that the required query parameter (q1) is included and not blank in the incoming request.

POSTValidator

This validator is enabled on the POST method. It allows API Gateway to verify that payload request format adheres to the specified RequestBodyModel when the content type is application/json if no matching content type is found, request validation is not performed. To use the same model regardless of the content type, specify \$default. RequestBodyModel contains an additional model, RequestBodyModelId, to define the pet ID.

```
AWSTemplateFormatVersion: 2010-09-09
Parameters:
  StageName:
    Type: String
    Default: v1
    Description: Name of API stage.
Resources:
  Api:
    Type: 'AWS::ApiGateway::RestApi'
    Properties:
      Name: ReqValidatorsSample
  RequestBodyModelId:
    Type: 'AWS::ApiGateway::Model'
    Properties:
      RestApiId: !Ref Api
      ContentType: application/json
      Description: Request body model for Pet ID.
      Schema:
        $schema: 'http://json-schema.org/draft-04/schema#'
        title: RequestBodyModelId
        properties:
          id:
            type: integer
  RequestBodyModel:
    Type: 'AWS::ApiGateway::Model'
    Properties:
      RestApiId: !Ref Api
      ContentType: application/json
      Description: Request body model for Pet type, name, price, and ID.
      Schema:
        $schema: 'http://json-schema.org/draft-04/schema#'
        title: RequestBodyModel
        required:
          - price
```

```
- name
- type
type: object
properties:
  id:
    "$ref": !Sub
      - 'https://apigateway.amazonaws.com/restapis/${Api}/models/
${RequestBodyModelId}'
      - Api: !Ref Api
        RequestBodyModelId: !Ref RequestBodyModelId
  price:
    type: number
    minimum: 25
    maximum: 500
  name:
    type: string
  type:
    type: string
    enum:
      - "dog"
      - "cat"
      - "fish"
GETValidator:
Type: AWS::ApiGateway::RequestValidator
Properties:
  Name: params-only
  RestApiId: !Ref Api
  ValidateRequestBody: False
  ValidateRequestParameters: True
POSTValidator:
Type: AWS::ApiGateway::RequestValidator
Properties:
  Name: body-only
  RestApiId: !Ref Api
  ValidateRequestBody: True
  ValidateRequestParameters: False
ValidationResource:
Type: 'AWS::ApiGateway::Resource'
Properties:
  RestApiId: !Ref Api
  ParentId: !GetAtt Api.RootResourceId
  PathPart: 'validation'
ValidationMethodGet:
Type: 'AWS::ApiGateway::Method'
```

```
Properties:  
  RestApiId: !Ref Api  
  ResourceId: !Ref ValidationResource  
  HttpMethod: GET  
  AuthorizationType: NONE  
  RequestValidatorId: !Ref GETValidator  
RequestParameters:  
  method.request.querystring.q1: true  
Integration:  
  Type: HTTP_PROXY  
  IntegrationHttpMethod: GET  
  Uri: http://petstore-demo-endpoint.execute-api.com/petstore/pets/  
ValidationMethodPost:  
  Type: 'AWS::ApiGateway::Method'  
Properties:  
  RestApiId: !Ref Api  
  ResourceId: !Ref ValidationResource  
  HttpMethod: POST  
  AuthorizationType: NONE  
  RequestValidatorId: !Ref POSTValidator  
RequestModels:  
  application/json : !Ref RequestBodyModel  
Integration:  
  Type: HTTP_PROXY  
  IntegrationHttpMethod: POST  
  Uri: http://petstore-demo-endpoint.execute-api.com/petstore/pets/  
ApiDeployment:  
  Type: 'AWS::ApiGateway::Deployment'  
DependsOn:  
  - ValidationMethodGet  
  - RequestBodyModel  
Properties:  
  RestApiId: !Ref Api  
  StageName: !Sub '${StageName}'  
Outputs:  
  ApiRootUrl:  
    Description: Root Url of the API  
    Value: !Sub 'https://${Api}.execute-api.${AWS::Region}.amazonaws.com/${StageName}'
```


Data transformations for REST APIs in API Gateway

Note

This section explains features that you use with a non-proxy integration. However, we recommend that when possible, you use a proxy integration for your REST API. A proxy integration has a streamlined integration setup and can evolve with the backend without having to tear down the existing setup. For more information, see [the section called "Choose an API integration type".](#)

If you use a non-proxy integration, you can use two features of API Gateway to transform your method request and your integration response. You might transform your method request if it takes a different payload format than the integration request payload. You might transform your integration response if it returns a different payload format than the format you need to return in the method response. For more information about the request lifecycle, see [the section called "Example resource for a REST API".](#)

The following example shows a data transformation where for the header "x-version:beta", the x-version header parameter is transformed into the app-version header parameter. The data transformation from x-version to app-version occurs in the integration request. That way, the integration endpoint receives the transformed header parameter value. When the integration endpoint returns a status code, the status code is transformed from 200 to 204 before the method response.



To create a data transformation, you can use the following features:

Parameter mapping

In parameter mapping, you can modify integration request URL path parameters, URL query string parameters, or HTTP header values, but you can't modify the integration request payload. You can also modify HTTP response header values. Use parameter mapping to create static header values for cross origin resource sharing (CORS).

You can use parameter mapping in your integration request for proxy and non-proxy integrations, but to use parameter mapping for an integration response, you need a non-proxy integration. Parameter mapping doesn't require any scripting in [Velocity Template Language \(VTL\)](#). For more information, see [the section called “Parameter mapping”](#).

Mapping template transformations

In mapping template transformations, you use a mapping template to map URL path parameters, URL query string parameters, HTTP headers, and the integration request or integration response body. A *mapping template* is a script expressed in [Velocity Template Language \(VTL\)](#) using [JSONPath expressions](#) and applied to the payload based on the Content-type header.

With a mapping template, you can do the following:

- Select which data to send using integration with AWS services, such as Amazon DynamoDB or Lambda functions, or HTTP endpoints. For more information, see [the section called "Tutorial: Modify the integration request and response for integrations to AWS services"](#).
- Conditionally override an API's integration request and integration response parameters, create new header values, and override status codes. For more information, see [the section called "Override your API's request and response parameters and status codes"](#).

You can also specify the behavior of your API when an integration request body has Content-type header with no matching mapping templates. This is called integration passthrough behavior. For more information, see [the section called "Method request behavior for payloads without mapping templates"](#).

Choose between parameter mapping and mapping template transformations

We recommend that you use parameter mapping to transform your data when possible. If your API requires you to change the body, or requires you to perform conditional overrides and modifications based on the incoming integration request or integration response, and you can't use a proxy integration, use mapping template transformations.


Parameter mapping for REST APIs in API Gateway

Note

If you are using an HTTP API, see [the section called "Parameter mapping"](#).


In parameter mapping, you map request or response parameters. You can map parameters using parameter mapping expressions or static values. For a list of mapping expressions, see [the section called "Parameter mapping source reference"](#). You can use parameter mapping in your integration request for proxy and non-proxy integrations, but to use parameter mapping for an integration response, you need a non-proxy integration.

For example, you can map the method request header parameter `puppies` to the integration request header parameter `DogsAge0`. Then, if a client sends the header `puppies:true` to your API, the integration request sends the request header `DogsAge0:true` to the integration endpoint. The following diagram shows the request lifecycle of this example.



To create this example using API Gateway, see [the section called “Example 1: Map a method request parameter to an integration request parameter”](#).

As another example, you can also map the integration response header parameter `kittens` to the method response header parameter `CatsAge0`. Then, if the integration endpoint returns `kittens:false`, the client receives the header `CatsAge0:false`. The following diagram shows the request lifecycle of this example.



Topics

- [Parameter mapping examples for REST APIs in API Gateway](#)
- [Parameter mapping source reference for REST APIs in API Gateway](#)

Parameter mapping examples for REST APIs in API Gateway

The following examples show how to create parameter mapping expressions using the API Gateway console, OpenAPI, and CloudFormation templates. For an example of how to use parameter mapping to create the required CORS headers, see [the section called “CORS”](#).

Example 1: Map a method request parameter to an integration request parameter

The following example maps the method request header parameter puppies to the integration request header parameter DogsAge0.

AWS Management Console

To map the method request parameter

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.

2. Choose a REST API.
3. Choose a method.

Your method must have a non-proxy integration.

4. For **Method request settings**, choose **Edit**.
5. Choose **HTTP request headers**.
6. Choose **Add header**.
7. For **Name**, enter **puppies**.
8. Choose **Save**.
9. Choose the **Integration request** tab, and then for **Integration request settings**, choose **Edit**.

The AWS Management Console automatically adds a parameter mapping from `method.request.header.puppies` to puppies for you, but you need to change the **Name** to match the request header parameter that is expected by your integration endpoint.

10. For **Name**, enter **DogsAge0**.
11. Choose **Save**.
12. Redeploy your API for the changes to take effect.

The following steps show you how to verify that your parameter mapping was successful.

(Optional) Test your parameter mapping

1. Choose the **Test** tab. You might need to choose the right arrow button to show the tab.
2. For headers, enter **puppies:true**.
3. Choose **Test**.
4. In the **Logs**, the result should look like the following:

```
Tue Feb 04 00:28:36 UTC 2025 : Method request headers: {puppies=true}
Tue Feb 04 00:28:36 UTC 2025 : Method request body before transformations:
Tue Feb 04 00:28:36 UTC 2025 : Endpoint request URI: http://petstore-demo-
endpoint.execute-api.com/petstore/pets
Tue Feb 04 00:28:36 UTC 2025 : Endpoint request headers: {DogsAge0=true,
  x-amzn-apigateway-api-id=abcd1234, Accept=application/json, User-
  Agent=AmazonAPIGateway_aaaaaaa, X-Amzn-Trace-Id=Root=1-abcd-12344}
```

The request header parameter has changed from puppies to DogsAge0.

CloudFormation

In this example, you use the [body](#) property to import an OpenAPI definition file into API Gateway.

```
AWSTemplateFormatVersion: 2010-09-09
Resources:
  Api:
    Type: 'AWS::ApiGateway::RestApi'
    Properties:
      Body:
        openapi: 3.0.1
        info:
          title: ParameterMappingExample
          version: "2025-02-04T00:30:41Z"
        paths:
          /pets:
            get:
              parameters:
                - name: puppies
                  in: header
                  schema:
                    type: string
              responses:
                "200":
                  description: 200 response
            x-amazon-apigateway-integration:
              httpMethod: GET
              uri: http://petstore-demo-endpoint.execute-api.com/petstore/pets
              responses:
                default:
                  statusCode: "200"
              requestParameters:
                integration.request.header.DogsAge0: method.request.header.puppies
                passthroughBehavior: when_no_match
                type: http
  ApiGatewayDeployment:
    Type: 'AWS::ApiGateway::Deployment'
    DependsOn: Api
    Properties:
```

```
RestApiId: !Ref Api
ApiGatewayDeployment20250219:
  Type: 'AWS::ApiGateway::Deployment'
  DependsOn: Api
  Properties:
    RestApiId: !Ref Api
Stage:
  Type: 'AWS::ApiGateway::Stage'
  Properties:
    DeploymentId: !Ref ApiGatewayDeployment20250219
    RestApiId: !Ref Api
    StageName: prod
```

OpenAPI

```
{
  "openapi" : "3.0.1",
  "info" : {
    "title" : "ParameterMappingExample",
    "version" : "2025-02-04T00:30:41Z"
  },
  "paths" : {
    "/pets" : {
      "get" : {
        "parameters" : [ {
          "name" : "puppies",
          "in" : "header",
          "schema" : {
            "type" : "string"
          }
        }],
        "responses" : {
          "200" : {
            "description" : "200 response"
          }
        },
        "x-amazon-apigateway-integration" : {
          "httpMethod" : "GET",
          "uri" : "http://petstore-demo-endpoint.execute-api.com/petstore/pets",
          "responses" : {
            "default" : {
              "statusCode" : "200"
            }
          }
        }
      }
    }
  }
}
```

```
        },
        "requestParameters" : {
            "integration.request.header.DogsAge0" : "method.request.header.puppies"
        },
        "passthroughBehavior" : "when_no_match",
        "type" : "http"
    }
}
}
}
}
```

Example 2: Map multiple method request parameters to different integration request parameters

The following example maps the multi-value method request query string parameter `methodRequestQueryParam` to the integration request query string parameter `integrationQueryParam` and maps the method request header parameter `methodRequestHeaderParam` to the integration request path parameter `integrationPathParam`.

AWS Management Console

To map the method request parameters

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose a REST API.
3. Choose a method.

Your method must have a non-proxy integration.
4. For **Method request settings**, choose **Edit**.
5. Choose **URL query string parameters**.
6. Choose **Add query string**.
7. For **Name**, enter `methodRequestQueryParam`.
8. Choose **HTTP request headers**.
9. Choose **Add header**.
10. For **Name**, enter `methodRequestHeaderParam`.

11. Choose **Save**.
12. Choose the **Integration request** tab, and then for **Integration request settings**, choose **Edit**.
13. Choose **URL path parameters**.
14. Choose **Add path parameter**.
15. For **Name**, enter **integrationPathParam**.
16. For **Mapped from**, enter **method.request.header.methodRequestHeaderParam**.

This maps the method request header you specified in the method request to a new integration request path parameter.

17. Choose **URL query string parameters**.
18. Choose **Add query string**.
19. For **Name**, enter **integrationQueryParam**.
20. For **Mapped from**, enter
method.request.multivaluequerystring.methodRequestQueryParam.

This maps the multivalue query string parameter to a new single valued integration request query string parameter.

21. Choose **Save**.
22. Redeploy your API for the changes to take effect.

CloudFormation

In this example, you use the [body](#) property to import an OpenAPI definition file into API Gateway.

The following OpenAPI definition creates the following parameter mappings for an HTTP integration:

- The method request's header, named **methodRequestHeaderParam**, into the integration request path parameter, named **integrationPathParam**
- The multi-value method request query string, named **methodRequestQueryParam**, into the integration request query string, named **integrationQueryParam**

AWSTemplateFormatVersion: 2010-09-09

```
Resources:  
  Api:  
    Type: 'AWS::ApiGateway::RestApi'  
    Properties:  
      Body:  
        openapi: 3.0.1  
        info:  
          title: Parameter mapping example 2  
          version: "2025-01-15T19:12:31Z"  
        paths:  
          /:  
            post:  
              parameters:  
                - name: methodRequestQueryParam  
                  in: query  
                  schema:  
                    type: string  
                - name: methodRequestHeaderParam  
                  in: header  
                  schema:  
                    type: string  
              responses:  
                "200":  
                  description: 200 response  
              x-amazon-apigateway-integration:  
                httpMethod: GET  
                uri: http://petstore-demo-endpoint.execute-api.com/petstore/pets  
                responses:  
                  default:  
                    statusCode: "200"  
                requestParameters:  
                  integration.request.querystring.integrationQueryParam:  
method.request.multivaluequerystring.methodRequestQueryParam  
                  integration.request.path.integrationPathParam:  
method.request.header.methodRequestHeaderParam  
                  requestTemplates:  
                    application/json: '{"statusCode": 200}'  
                    passthroughBehavior: when_no_templates  
                    timeoutInMillis: 29000  
                    type: http  
  ApiGatewayDeployment:  
    Type: 'AWS::ApiGateway::Deployment'  
    DependsOn: Api  
    Properties:
```

```
RestApiId: !Ref Api
ApiGatewayDeployment20250219:
  Type: 'AWS::ApiGateway::Deployment'
  DependsOn: Api
  Properties:
    RestApiId: !Ref Api
Stage:
  Type: 'AWS::ApiGateway::Stage'
  Properties:
    DeploymentId: !Ref ApiGatewayDeployment20250219
    RestApiId: !Ref Api
    StageName: prod
```

OpenAPI

The following OpenAPI definition creates the following parameter mappings for an HTTP integration:

- The method request's header, named `methodRequestHeaderParam`, into the integration request path parameter, named `integrationPathParam`
- The multi-value method request query string, named `methodRequestQueryParam`, into the integration request query string, named `integrationQueryParam`

```
{
  "openapi" : "3.0.1",
  "info" : {
    "title" : "Parameter mapping example 2",
    "version" : "2025-01-15T19:12:31Z"
  },
  "paths" : {
    "/" : {
      "post" : {
        "parameters" : [ {
          "name" : "methodRequestQueryParam",
          "in" : "query",
          "schema" : {
            "type" : "string"
          }
        }, {
          "name" : "methodRequestHeaderParam",
          "in" : "header",
          "schema" : {
            "type" : "string"
          }
        } ]
      }
    }
  }
}
```

```
        "schema" : {
            "type" : "string"
        }
    },
    "responses" : {
        "200" : {
            "description" : "200 response"
        }
    },
    "x-amazon-apigateway-integration" : {
        "httpMethod" : "GET",
        "uri" : "http://petstore-demo-endpoint.execute-api.com/petstore/pets",
        "responses" : {
            "default" : {
                "statusCode" : "200"
            }
        },
        "requestParameters" : {
            "integration.request.querystring.integrationQueryParam" :
"method.request.multivaluequerystring.methodRequestQueryParam",
            "integration.request.path.integrationPathParam" :
"method.request.header.methodRequestHeaderParam"
        },
        "requestTemplates" : {
            "application/json" : "{\"statusCode\": 200}"
        },
        "passthroughBehavior" : "when_no_templates",
        "timeoutInMillis" : 29000,
        "type" : "http"
    }
}
}
```

Example 3: Map fields from the JSON request body to integration request parameters

You can also map integration request parameters from fields in the JSON request body using a [JSONPath expression](#). The following example maps the method request body to an integration request header named `body-header` and maps part of the request body, as expressed by a JSON expression to an integration request header named `pet-price`.

To test this example, provide an input that contains a price category, such as the following:

```
[  
 {  
   "id": 1,  
   "type": "dog",  
   "price": 249.99  
 }  
]
```

AWS Management Console

To map the method request parameters

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose a REST API.
3. Choose a POST, PUT, PATCH, or ANY method.

Your method must have a non-proxy integration.

4. For **Integration request settings**, choose **Edit**.
5. Choose **URL request headers parameters**.
6. Choose **Add request header parameter**.
7. For **Name**, enter **body-header**.
8. For **Mapped from**, enter **method.request.body**.

This maps the method request body to a new integration request header parameter.

9. Choose **Add request header parameter**.
10. For **Name**, enter **pet-price**.
11. For **Mapped from**, enter **method.request.body[0].price**.

This maps a part of the method request body to a new integration request header parameter.

12. Choose **Save**.
13. Redeploy your API for the changes to take effect.

CloudFormation

In this example, you use the [body](#) property to import an OpenAPI definition file into API Gateway.

```
AWSTemplateFormatVersion: 2010-09-09
Resources:
  Api:
    Type: 'AWS::ApiGateway::RestApi'
    Properties:
      Body:
        openapi: 3.0.1
        info:
          title: Parameter mapping example 3
          version: "2025-01-15T19:19:14Z"
        paths:
          /:
            post:
              responses:
                "200":
                  description: 200 response
                  x-amazon-apigateway-integration:
                    httpMethod: GET
                    uri: http://petstore-demo-endpoint.execute-api.com/petstore/pets
                    responses:
                      default:
                        statusCode: "200"
                    requestParameters:
                      integration.request.header.pet-price: method.request.body[0].price
                      integration.request.header.body-header: method.request.body
                    requestTemplates:
                      application/json: '{"statusCode": 200}'
                    passthroughBehavior: when_no_templates
                    timeoutInMillis: 29000
                    type: http
      ApiGatewayDeployment:
        Type: 'AWS::ApiGateway::Deployment'
        DependsOn: Api
        Properties:
          RestApiId: !Ref Api
  ApiGatewayDeployment20250219:
    Type: 'AWS::ApiGateway::Deployment'
    DependsOn: Api
    Properties:
```

```
RestApiId: !Ref Api
Stage:
Type: 'AWS::ApiGateway::Stage'
Properties:
DeploymentId: !Ref ApiGatewayDeployment20250219
RestApiId: !Ref Api
StageName: prod
```

OpenAPI

The following OpenAPI definition map integration request parameters from fields in the JSON request body.

```
{
  "openapi" : "3.0.1",
  "info" : {
    "title" : "Parameter mapping example 3",
    "version" : "2025-01-15T19:19:14Z"
  },
  "paths" : {
    "/" : {
      "post" : {
        "responses" : {
          "200" : {
            "description" : "200 response"
          }
        },
        "x-amazon-apigateway-integration" : {
          "httpMethod" : "GET",
          "uri" : "http://petstore-demo-endpoint.execute-api.com/petstore/pets",
          "responses" : {
            "default" : {
              "statusCode" : "200"
            }
          },
          "requestParameters" : {
            "integration.request.header.pet-price" : "method.request.body[0].price",
            "integration.request.header.body-header" : "method.request.body"
          },
          "requestTemplates" : {
            "application/json" : "{\"statusCode\": 200}"
          },
          "passthroughBehavior" : "when_no_templates",
        }
      }
    }
  }
}
```

```
        "timeoutInMillis" : 29000,
        "type" : "http"
    }
}
}
}
}
```

Example 4: Map the integration response to the method response

You can also map the integration response to the method response. The following example maps the integration response body to a method response header named `location`, maps the integration response header `x-app-id` to the method response header `id`, and maps the multi-valued integration response header `item` to the method response header `items`.

AWS Management Console

To map the integration response

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose a REST API.
3. Choose a method.

Your method must have a non-proxy integration.

4. Choose the **Method response** tab, and then for **Response 200**, choose **Edit**.
5. For **Header name**, choose **Add header**.
6. Create three headers named **id**, **item**, and **location**.
7. Choose **Save**.
8. Choose the **Integration response** tab, and then for **Default - Response**, choose **Edit**.
9. Under **Header mappings**, enter the following.
 - a. For **id**, enter `integration.response.header.x-app-id`
 - b. For **item**, enter `integration.response.multivalueheader.item`
 - c. For **location**, enter `integration.response.body.redirect.url`
10. Choose **Save**.
11. Redeploy your API for the changes to take effect.

CloudFormation

In this example, you use the [body](#) property to import an OpenAPI definition file into API Gateway.

```
AWSTemplateFormatVersion: 2010-09-09
Resources:
  Api:
    Type: 'AWS::ApiGateway::RestApi'
    Properties:
      Body:
        openapi: 3.0.1
        info:
          title: Parameter mapping example
          version: "2025-01-15T19:21:35Z"
        paths:
          /:
            post:
              responses:
                "200":
                  description: 200 response
                  headers:
                    item:
                      schema:
                        type: string
                    location:
                      schema:
                        type: string
                    id:
                      schema:
                        type: string
              x-amazon-apigateway-integration:
                type: http
                httpMethod: GET
                uri: http://petstore-demo-endpoint.execute-api.com/petstore/pets
                responses:
                  default:
                    statusCode: "200"
                    responseParameters:
                      method.response.header.id: integration.response.header.x-app-
id
                      method.response.header.location:
integration.response.body.redirect.url
```

```
        method.response.header.item:  
integration.response.multivalueheader.item  
        requestTemplates:  
            application/json: '{"statusCode": 200}'  
            passthroughBehavior: when_no_templates  
            timeoutInMillis: 29000  
ApiGatewayDeployment:  
    Type: 'AWS::ApiGateway::Deployment'  
    DependsOn: Api  
    Properties:  
        RestApiId: !Ref Api  
ApiGatewayDeployment20250219:  
    Type: 'AWS::ApiGateway::Deployment'  
    DependsOn: Api  
    Properties:  
        RestApiId: !Ref Api  
Stage:  
    Type: 'AWS::ApiGateway::Stage'  
    Properties:  
        DeploymentId: !Ref ApiGatewayDeployment20250219  
        RestApiId: !Ref Api  
        StageName: prod
```

OpenAPI

The following OpenAPI definition maps the integration response to the method response.

```
{  
  "openapi" : "3.0.1",  
  "info" : {  
    "title" : "Parameter mapping example",  
    "version" : "2025-01-15T19:21:35Z"  
  },  
  "paths" : {  
    "/" : {  
      "post" : {  
        "responses" : {  
          "200" : {  
            "description" : "200 response",  
            "headers" : {  
              "item" : {  
                "schema" : {  
                  "type" : "string"  
                }  
              }  
            }  
          }  
        }  
      }  
    }  
  }  
}
```

```
        },
        "location" : {
            "schema" : {
                "type" : "string"
            }
        },
        "id" : {
            "schema" : {
                "type" : "string"
            }
        }
    }
},
"x-amazon-apigateway-integration" : {
    "type" : "http",
    "httpMethod" : "GET",
    "uri" : "http://petstore-demo-endpoint.execute-api.com/petstore/pets",
    "responses" : {
        "default" : {
            "statusCode" : "200",
            "responseParameters" : {
                "method.response.header.id" : "integration.response.header.x-app-id",
                "method.response.header.location" :
                "integration.response.body.redirect.url",
                "method.response.header.item" :
                "integration.response.multivalueheader.item"
            }
        }
    },
    "requestTemplates" : {
        "application/json" : "{\"statusCode\": 200}"
    },
    "passthroughBehavior" : "when_no_templates",
    "timeoutInMillis" : 29000
}
}
}
```

Parameter mapping source reference for REST APIs in API Gateway

When you create a parameter mapping, you specify the method request or integration response parameters to modify and you specify how to modify those parameters.

The following table shows the method request parameters that you can map, and the expression to create the mapping. In these expressions, *name* is the name of a method request parameter. For example, to map the request header parameter `puppies`, use the expression `method.request.header.puppies`. Your expression must match the regular expression '`^[a-zA-Z0-9._$-]+$`'. You can use parameter mapping in your integration request for proxy and non-proxy integrations.

Mapped data source	Mapping expression
Method request path	<code>method.request.path. <i>name</i></code>
Method request query string	<code>method.request.querystring. <i>name</i></code>
Multi-value method request query string	<code>method.request.multivaluequerystring. <i>name</i></code>
Method request header	<code>method.request.header. <i>name</i></code>
Multi-value method request header	<code>method.request.multivalueheader. <i>name</i></code>
Method request body	<code>method.request.body</code>
Method request body (JsonPath)	<code>method.request.body. <i>JSONPath_EXPRESSION</i> .</code> <i>JSONPath_EXPRESSION</i> is a JSONPath expression for a JSON field of the body of a request. For more information, see JSONPath expression .
Stage variables	<code>stageVariables. <i>name</i></code>
Context variables	<code>context.<i>name</i></code>

Mapped data source	Mapping expression
	The name must be one of the supported context variables .
Static value	' <i>static_value</i> ' . The <i>static_value</i> is a string literal and must be enclosed within a pair of single quotes. For example, 'https://www.example.com' .

The following table shows the integration response parameters that you can map and the expression to create the mapping. In these expressions, *name* is the name of an integration response parameter. You can map method response headers from any integration response header or integration response body, \$context variables, or static values. To use parameter mapping for an integration response, you need a non-proxy integration.


Mapped data source	Mapping expression
Integration response header	integration.response.header. <i>name</i>
Integration response header	integration.response.multivalueheader. <i>name</i>
Integration response body	integration.response.body
Integration response body (JsonPath)	integration.response.body. <i>JSONPath_EXPRESSION</i> <i>JSONPath_EXPRESSION</i> is a JSONPath expression for a JSON field of the body of a response. For more information, see JSONPath expression .
Stage variable	stageVariables. <i>name</i>
Context variable	context. <i>name</i>

Mapped data source	Mapping expression
	The name must be one of the supported context variables .
Static value	<p>'<i>static_value</i>'</p> <p>The <i>static_value</i> is a string literal and must be enclosed within a pair of single quotes. For example, 'https://www.example.com' .</p>

Mapping template transformations for REST APIs in API Gateway

A mapping template transformation uses a mapping template to modify your integration request or integration response. A *mapping template* is a script expressed in [Velocity Template Language \(VTL\)](#) and applied to a payload using [JSONPath](#) based on the Content-type header. You use mapping templates when you use mapping template transformations. This section describes conceptual information related to mapping templates.

The following diagram shows the request lifecycle for a POST /pets resource that has an integration with a PetStore integration endpoint. In this API, a user sends data about a pet and the integration endpoint returns the adoption fee associated with a pet. In this request lifecycle, mapping template transformations filter the request body to the integration endpoint and filter the response body from the integration endpoint.



The following sections explain the request and response lifecycle.

Method request and integration request

In the previous example, if this is the request body sent to the method request:

```

POST /pets
HTTP/1.1
Host:abcd1234.us-west-2.amazonaws.com
Content-type: application/json

{
  "id": 1,
  "type": "dog",
  "Age": 11,
}
  
```

This request body is not in the correct format to be used by the integration endpoint, so API Gateway performs a mapping template transformation. API Gateway only performs a mapping template transformation because there is a mapping template defined for the Content-Type application/json. If you don't define a mapping template for the Content-Type, by default, API

Gateway passes the body through the integration request to the integration endpoint. To modify this behavior, see [the section called “Method request behavior for payloads without mapping templates”](#).

The following mapping template transforms the method request data in the integration request before it's sent to the integration endpoint:

```
#set($inputRoot = $input.path('$'))  
{  
    "dogId" : "dog_"$elem.id,  
    "Age": $inputRoot.Age  
}
```

1. The `$inputRoot` variable represents the root object in the original JSON data from the previous section. Directives begin with the `#` symbol.
2. The dog is a concatenation of the user's `id` and a string value.
3. Age is from the method request body.

Then, the following output is forwarded to the integration endpoint:

```
{  
    "dogId" : "dog_1",  
    "Age": 11  
}
```

Integration response and method response

After the successful request to the integration endpoint, the endpoint sends a response to API Gateway's integration response. The following is the example output data from the integration endpoint:

```
{  
    "dogId" : "dog_1",  
    "adoptionFee": 19.95,  
}
```

The method response expects a different payload than what is returned by the integration response. API Gateway performs a mapping template transformation. API Gateway only performs

a mapping template transformation because there is a mapping template defined for the Content-Type application/json. If you don't define a mapping template for the Content-Type, by default, API Gateway passes the body through the integration response to the method response. To modify this behavior, see [the section called "Method request behavior for payloads without mapping templates".](#)

```
#set($inputRoot = $input.path('$'))  
{  
    "adoptionFee" : $inputRoot.adoptionFee,  
}
```

The following output is sent to the method response:

```
{"adoptionFee": 19.95}
```

This completes the example mapping template transformation. We recommend that when possible, instead of using mapping template transformations, you use a proxy integration to transform your data. For more information, see [the section called "Choose an API integration type".](#)

Method request behavior for payloads without mapping templates for REST APIs in API Gateway

If your method request has a payload and you don't have a mapping template defined for the Content-Type header, you can choose to pass the client-supplied request payload through the integration request to the backend without transformation. The process is known as integration passthrough.

The actual passthrough behavior of an incoming request is determined by this setting. There are three options:

When no template matches the request Content-Type header

Choose this option if you want the method request body to pass through the integration request to the backend without transformation when the method request content type does not match any content types associated with the mapping templates.

When calling the API Gateway API, you choose this option by setting WHEN_NO_MATCH as the passthroughBehavior property value on the [Integration](#).

When there are no templates defined (recommended)

Choose this option if you want the method request body to pass through the integration request to the backend without transformation when no mapping template is defined in the integration request. If a template is defined when this option is selected, the method request with a payload and content type that doesn't match any defined mapping template will be rejected with an HTTP 415 Unsupported Media Type response.

When calling the API Gateway API, you choose this option by setting `WHEN_NO_TEMPLATES` as the `passthroughBehavior` property value on the [Integration](#).

Never

Choose this option if you do not want the method request body to pass through the integration request to the backend without transformation when no mapping template is defined in the integration request. If a template is defined when this option is selected, the method request of an unmapped content type will be rejected with an HTTP 415 Unsupported Media Type response.

When calling the API Gateway API, you choose this option by setting `NEVER` as the `passthroughBehavior` property value on the [Integration](#).

The following examples show the possible passthrough behaviors.

Example 1: One mapping template is defined in the integration request for the `application/json` content type.

Content-type	Passthrough option	Behavior
None	<code>WHEN_NO_MATCH</code>	The request payload is transformed using the template.
API Gateway defaults to <code>application/json</code>		
None	<code>WHEN_NO_TEMPLATES</code>	The request payload is transformed using the template.
API Gateway defaults to <code>application/json</code>		

Content-type	Passthrough option	Behavior
None API Gateway defaults to application/json	NEVER	The request payload is transformed using the template.
application/json	WHEN_NO_MATCH	The request payload is transformed using the template.
application/json	WHEN_NO_TEMPLATES	The request payload is transformed using the template.
application/json	NEVER	The request payload is transformed using the template.
application/xml	WHEN_NO_MATCH	The request payload is not transformed and is sent to the backend as-is.
application/xml	WHEN_NO_TEMPLATES	The request is rejected with an HTTP 415 Unsupported Media Type response.
application/xml	NEVER	The request is rejected with an HTTP 415 Unsupported Media Type response.

Example 2: One mapping template is defined in the integration request for the application/xml content type.

Content-type	Passthrough option	Behavior
None API Gateway defaults to application/json	WHEN_NO_MATCH	The request payload is not transformed and is sent to the backend as-is.
None API Gateway defaults to application/json	WHEN_NO_TEMPLATES	The request is rejected with an HTTP 415 Unsupported Media Type response.
None API Gateway defaults to application/json	NEVER	The request is rejected with an HTTP 415 Unsupported Media Type response.
application/json	WHEN_NO_MATCH	The request payload is not transformed and is sent to the backend as-is.
application/json	WHEN_NO_TEMPLATES	The request is rejected with an HTTP 415 Unsupported Media Type response.
application/json	NEVER	The request is rejected with an HTTP 415 Unsupported Media Type response.
application/xml	WHEN_NO_MATCH	The request payload is transformed using the template.
application/xml	WHEN_NO_TEMPLATES	The request payload is transformed using the template.

Content-type	Passthrough option	Behavior
application/xml	NEVER	The request payload is transformed using the template.

Example 3: No mapping templates are defined in the integration request.

Content-type	Passthrough option	Behavior
None API Gateway defaults to application/json	WHEN_NO_MATCH	The request payload is not transformed and is sent to the backend as-is.
None API Gateway defaults to application/json	WHEN_NO_TEMPLATES	The request payload is not transformed and is sent to the backend as-is.
None API Gateway defaults to application/json	NEVER	The request is rejected with an HTTP 415 Unsupported Media Type response.
application/json	WHEN_NO_MATCH	The request payload is not transformed and is sent to the backend as-is.
application/json	WHEN_NO_TEMPLATES	The request payload is not transformed and is sent to the backend as-is.
application/json	NEVER	The request is rejected with an HTTP 415 Unsupported Media Type response.

Content-type	Passthrough option	Behavior
application/xml	WHEN_NO_MATCH	The request payload is not transformed and is sent to the backend as-is.
application/xml	WHEN_NO_TEMPLATES	The request payload is not transformed and is sent to the backend as-is.
application/xml	NEVER	The request is rejected with an HTTP 415 Unsupported Media Type response.

Additional mapping template example for REST APIs in API Gateway

The following example shows a photo album API in API Gateway that uses mapping templates to transform integration request and integration response data. It also uses data models to define method request and integration response payloads. For more information about data models, see [Data models for REST APIs](#).

Method request and integration request

The following is a model that defines the method request body. This input model requires that the caller upload one photo page, and requires a minimum of 10 photos for each page. You can use this input model to generate an SDK or to use request validation for your API. While using request validation, if the method request body doesn't adhere to the data structure of the model, API Gateway fails the request.

```
{
  "$schema": "http://json-schema.org/draft-04/schema#",
  "title": "PhotosInputModel",
  "type": "object",
  "properties": {
    "photos": {
      "type": "object",
      "required": [
        "photo"
      ],
      "properties": {
        "photo": {
          "type": "string"
        }
      }
    }
  }
}
```

```
"page": { "type": "integer" },
"pages": { "type": "string" },
"perpage": { "type": "integer", "minimum" : 10 },
"total": { "type": "string" },
"photo": {
    "type": "array",
    "items": {
        "type": "object",
        "properties": {
            "id": { "type": "string" },
            "owner": { "type": "string" },
            "photographer_first_name" : {"type" : "string"},
            "photographer_last_name" : {"type" : "string"},
            "secret": { "type": "string" },
            "server": { "type": "string" },
            "farm": { "type": "integer" },
            "title": { "type": "string" },
            "ispublic": { "type": "boolean" },
            "isfriend": { "type": "boolean" },
            "isfamily": { "type": "boolean" }
        }
    }
}
}
}
}
}
```

The following is an example method request body that adheres to the data structure of the previous data model.

```
{
"photos": {
    "page": 1,
    "pages": "1234",
    "perpage": 100,
    "total": "123398",
    "photo": [
        {
            "id": "12345678901",
            "owner": "23456789@A12",
            "photographer_first_name" : "Saanvi",
            "photographer_last_name" : "Sarkar",
        }
    ]
}
```

```
        "secret": "abc123d456",
        "server": "1234",
        "farm": 1,
        "title": "Sample photo 1",
        "ispublic": true,
        "isfriend": false,
        "isfamily": false
    },
    {
        "id": "23456789012",
        "owner": "34567890@B23",
        "photographer_first_name" : "Richard",
        "photographer_last_name" : "Roe",
        "secret": "bcd234e567",
        "server": "2345",
        "farm": 2,
        "title": "Sample photo 2",
        "ispublic": true,
        "isfriend": false,
        "isfamily": false
    }
]
}
```

In this example, if the previous method request body was submitted by the client, then this mapping template transforms the payload to match the format required by the integration endpoint.

```
#set($inputRoot = $input.path('$'))
{
    "photos": [
#foreach($elem in $inputRoot.photos.photo)
{
    "id": "$elem.id",
    "photographedBy": "$elem.photographer_first_name $elem.photographer_last_name",
    "title": "$elem.title",
    "ispublic": $elem.ispublic,
    "isfriend": $elem.isfriend,
    "isfamily": $elem.isfamily
}#if($foreach.hasNext),#end

#end
```

```
]  
}
```

The following example is output data from the transformation:

```
{  
  "photos": [  
    {  
      "id": "12345678901",  
      "photographedBy": "Saanvi Sarkar",  
      "title": "Sample photo 1",  
      "ispublic": true,  
      "isfriend": false,  
      "isfamily": false  
    },  
    {  
      "id": "23456789012",  
      "photographedBy": "Richard Roe",  
      "title": "Sample photo 2",  
      "ispublic": true,  
      "isfriend": false,  
      "isfamily": false  
    }  
  ]  
}
```

This data is sent to the integration request, and then to the integration endpoint.

Integration response and method response

The following is an example output model for the photo data from the integration endpoint. You can use this model for a method response model, which is necessary when you generate a strongly typed SDK for the API. This causes the output to be cast into an appropriate class in Java or Objective-C.

```
{  
  "$schema": "http://json-schema.org/draft-04/schema#",  
  "title": "PhotosOutputModel",  
  "type": "object",  
  "properties": {  
    "photos": {  
      "type": "array",  
      "items": {
```

```
"type": "object",
"properties": {
    "id": { "type": "string" },
    "photographedBy": { "type": "string" },
    "title": { "type": "string" },
    "ispublic": { "type": "boolean" },
    "isfriend": { "type": "boolean" },
    "isfamily": { "type": "boolean" }
}
}
```

The integration endpoint might not respond with a response that adheres to the data structure of this model. For instance, the integration response might look like the following:

```
"photos": [
{
    "id": "12345678901",
    "photographedBy": "Saanvi Sarkar",
    "title": "Sample photo 1",
    "description": "My sample photo 1",
    "public": true,
    "friend": false,
    "family": false
},
{
    "id": "23456789012",
    "photographedBy": "Richard Roe",
    "title": "Sample photo 2",
    "description": "My sample photo 1",
    "public": true,
    "friend": false,
    "family": false
}
]
```

The following example mapping template transforms the integration response data into the format expected by the method response:

```
#set($inputRoot = $input.path('$'))  
{  
    "photos": [  
        #foreach($elem in $inputRoot.photos.photo)  
        {  
            "id": "$elem.id",  
            "photographedBy": "$elem.photographer_first_name $elem.photographer_last_name",  
            "title": "$elem.title",  
            "ispublic": $elem.public,  
            "isfriend": $elem.friend,  
            "isfamily": $elem.family  
        }#if($foreach.hasNext),#end  
  
    #end  
]  
}
```

The following example is output data from the transformation:

```
{  
    "photos": [  
        {  
            "id": "12345678901",  
            "photographedBy": "Saanvi Sarkar",  
            "title": "Sample photo 1",  
            "ispublic": true,  
            "isfriend": false,  
            "isfamily": false  
        },  
        {  
            "id": "23456789012",  
            "photographedBy": "Richard Roe",  
            "title": "Sample photo 2",  
            "ispublic": true,  
            "isfriend": false,  
            "isfamily": false  
        }  
    ]  
}
```

This data is sent to the method response and then back to the client.

Override your API's request and response parameters and status codes for REST APIs in API Gateway

You can use mapping template transformations to override any type of request parameter, response header, or response status code. You use a mapping template to do the following:

- Perform many-to-one parameter mappings
- Override parameters after standard API Gateway mappings have been applied
- Conditionally map parameters based on body content or other parameter values
- Programmatically create new parameters
- Override status codes returned by your integration endpoint

Overrides are final. An override may only be applied to each parameter once. If you try to override the same parameter multiple times, API Gateway returns a 5XX response. If you must override the same parameter multiple times throughout the template, we recommend creating a variable and applying the override at the end of the template. The template is applied only after the entire template is parsed.

Example 1: Override the status code based on the integration body

The following example use the [example API](#) to override the status code based on the integration response body.

AWS Management Console

To override a status code based on the integration response body

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose **Create API**.
3. For **REST API**, choose **Build**.
4. For **API details**, choose **Example API**.
5. Choose **Create API**.

API Gateway creates an example pet store API. To retrieve information about a pet, you use the API method request of GET /pets/{petId}, where {petId} is a path parameter corresponding to an ID number for a pet.

In this example, you override the GET method's response code to 400 when an error condition is detected.

6. In the **Resources** tree, choose the GET method under /{petId}.
7. First, you test the current implementation of the API.

Choose the **Test** tab. You might need to choose the right arrow button to show the tab.

8. For **petId**, enter **-1**, and then choose **Test**.

The **Response body** indicates an out-of-range error:

```
{  
  "errors": [  
    {  
      "key": "GetPetRequest.petId",  
      "message": "The value is out of range."  
    }  
  ]  
}
```

In addition, the last line under **Logs** ends with: Method completed with status: 200.

The integration was completed successfully, but there was an error. Now you'll override the status code based on the integration response.

9. On the **Integration response** tab, for the **Default - Response**, choose **Edit**.
10. Choose **Mapping templates**.
11. Choose **Add mapping template**.
12. For **Content type**, enter **application/json**.
13. For **Template body**, enter the following:

```
#set($inputRoot = $input.path('$'))  
$input.json("")  
#if($inputRoot.toString().contains("error"))  
#set($context.responseOverride.status = 400)  
#end
```

This mapping template uses the `$context.responseOverride.status` variable to override the status code to 400 if the integration response contains the string `error`.

14. Choose **Save**.
15. Choose the **Test** tab.
16. For **petId**, enter **-1**.
17. In the results, the **Response Body** indicates an out-of-range error:

```
{  
  "errors": [  
    {  
      "key": "GetPetRequest.petId",  
      "message": "The value is out of range."  
    }  
  ]  
}
```

However, the last line under **Logs** now ends with: Method completed with status: 400.

CloudFormation

In this example, you use the [body](#) property to import an OpenAPI definition file into API Gateway.

```
AWSTemplateFormatVersion: 2010-09-09  
Resources:  
  Api:  
    Type: 'AWS::ApiGateway::RestApi'  
    Properties:  
      Body:  
        openapi: 3.0.1  
        info:  
          title: PetStore Example 1  
          description: Example pet store API.  
          version: "2025-01-14T00:13:18Z"  
      paths:  
        /pets/{petId}:  
          get:  
            parameters:  
              - name: petId  
                in: path  
                required: true
```

```
        schema:
            type: string
        responses:
            "200":
                description: 200 response
        x-amazon-apigateway-integration:
            httpMethod: GET
            uri: http://petstore.execute-api.us-east-1.amazonaws.com/petstore/
pets/{petId}
        responses:
            default:
                statusCode: "200"
            responseTemplates:
                application/json: |-
                    #set($inputRoot = $input.path('$'))
                    $input.json("$")
                    #if($inputRoot.toString().contains("error"))
                    #set($context.responseOverride.status = 400)
                    #end
            requestParameters:
                integration.request.path.petId: method.request.path.petId
            passthroughBehavior: when_no_match
            type: http
        components:
            schemas:
                Pet:
                    type: object
                    properties:
                        id:
                            type: integer
                        type:
                            type: string
                        price:
                            type: number
        ApiGatewayDeployment:
            Type: 'AWS::ApiGateway::Deployment'
            DependsOn: Api
            Properties:
                RestApiId: !Ref Api
        ApiGatewayDeployment20250219:
            Type: 'AWS::ApiGateway::Deployment'
            DependsOn: Api
            Properties:
                RestApiId: !Ref Api
```

```
Stage:  
  Type: 'AWS::ApiGateway::Stage'  
  Properties:  
    DeploymentId: !Ref ApiGatewayDeployment20250219  
    RestApiId: !Ref Api  
    StageName: prod
```

OpenAPI

The following OpenAPI definition creates the GET `pets/{petId}` resource and overrides the status code based on the integration body.

```
{  
  "openapi" : "3.0.1",  
  "info" : {  
    "title" : "PetStore Example 1",  
    "description" : "Example pet store API.",  
    "version" : "2025-01-14T00:13:18Z"  
  },  
  "paths" : {  
    "/pets/{petId}" : {  
      "get" : {  
        "parameters" : [ {  
          "name" : "petId",  
          "in" : "path",  
          "required" : true,  
          "schema" : {  
            "type" : "string"  
          }  
        } ],  
        "responses" : {  
          "200" : {  
            "description" : "200 response"  
          }  
        },  
        "x-amazon-apigateway-integration" : {  
          "httpMethod" : "GET",  
          "uri" : "http://petstore.execute-api.us-east-1.amazonaws.com/petstore/  
pets/{petId}",  
          "responses" : {  
            "default" : {  
              "statusCode" : "200",  
              "responseTemplates" : {
```

```
        "application/json" : "#set($inputRoot = $input.path(''))\n$input.json(\"$\")\n#if($inputRoot.toString().contains(\"error\"))\n#set($context.responseOverride.status = 400)\n#end"
    }
}
},
"requestParameters" : {
    "integration.request.path.petId" : "method.request.path.petId"
},
"passthroughBehavior" : "when_no_match",
"type" : "http"
}
}
}
},
"components" : {
    "schemas" : {
        "Pet" : {
            "type" : "object",
            "properties" : {
                "id" : {
                    "type" : "integer"
                },
                "type" : {
                    "type" : "string"
                },
                "price" : {
                    "type" : "number"
                }
            }
        }
    }
}
}
```

Example 2: Override the request header and create new headers

The following example uses the [example API](#) to override the request header and create new headers.

AWS Management Console

To override a method's request header by creating a new header

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose the example API you created in the previous tutorial. The name of the API should be **PetStore**.
3. In the **Resources** tree, choose the GET method under /pet.
4. On the **Method request** tab, for **Method request settings**, choose **Edit**.
5. Choose **HTTP request headers**, and then choose **Add header**.
6. For **Name**, enter **header1**.
7. Choose **Add header**, and then create a second header called **header2**.
8. Choose **Save**.

Now, you combine these headers into one header value using a mapping template.

9. On the **Integration request** tab, for **Integration request settings**, choose **Edit**.
10. For **Request body passthrough**, select **When there are no templates defined (recommended)**.
11. Choose **Mapping templates**, and then do the following:
 - a. Choose **Add mapping template**.
 - b. For **Content type**, enter **application/json**.
 - c. For **Template body**, enter the following:

```
#set($header1Override = "pets")
#set($header3Value = "$input.params('header1')$input.params('header2')")
$input.json("$")
#set($context.requestOverride.header.header3 = $header3Value)
#set($context.requestOverride.header.header1 = $header1Override)
#set($context.requestOverride.header.multivalueheader=[$header1Override,
$header3Value])
```

This mapping template overrides header1 with the string pets and creates a multi-value header called \$header3Value that combines header1 and header2.

12. Choose **Save**.
13. Choose the **Test** tab.

14. Under **Headers**, copy the following code:

```
header1:header1Val  
header2:header2Val
```

15. Choose **Test**.

In the **Logs**, you should see an entry that includes this text:

```
Endpoint request headers: {header3=header1Valheader2Val,  
header2=header2Val, header1=pets, x-amzn-apigateway-api-id=api-id,  
Accept=application/json, multivalueheader=pets,header1Valheader2Val}
```

CloudFormation

In this example, you use the [body](#) property to import an OpenAPI definition file into API Gateway.

```
AWSTemplateFormatVersion: 2010-09-09
Resources:
  Api:
    Type: 'AWS::ApiGateway::RestApi'
    Properties:
      Body:
        openapi: 3.0.1
        info:
          title: PetStore Example 2
          description: Example pet store API.
          version: "2025-01-14T00:36:18Z"
        paths:
          /pets:
            get:
              parameters:
                - name: header2
                  in: header
                  schema:
                    type: string
                - name: page
                  in: query
                  schema:
                    type: string
                - name: type
```

```
        in: query
        schema:
          type: string
      - name: header1
        in: header
        schema:
          type: string
    responses:
      "200":
        description: 200 response
    x-amazon-apigateway-integration:
      httpMethod: GET
      uri: http://petstore.execute-api.us-east-1.amazonaws.com/petstore/
pets
  responses:
    default:
      statusCode: "200"
    requestParameters:
      integration.request.header.header1: method.request.header.header1
      integration.request.header.header2: method.request.header.header2
      integration.request.querystring.page:
method.request.querystring.page
      integration.request.querystring.type:
method.request.querystring.type
      requestTemplates:
        application/json: |-
          #set($header1Override = "pets")
          #set($header3Value =
"$input.params('header1')$input.params('header2')")
          $input.json("$")
          #set($context.requestOverride.header.header3 = $header3Value)
          #set($context.requestOverride.header.header1 = $header1Override)

#set($context.requestOverride.header.multivalueheader=[$header1Override,
$header3Value])
      passthroughBehavior: when_no_match
      type: http
components:
  schemas:
    Pet:
      type: object
      properties:
        id:
          type: integer
```

```
    type:  
      type: string  
    price:  
      type: number  
  ApiGatewayDeployment:  
    Type: 'AWS::ApiGateway::Deployment'  
    DependsOn: Api  
    Properties:  
      RestApiId: !Ref Api  
  ApiGatewayDeployment20250219:  
    Type: 'AWS::ApiGateway::Deployment'  
    DependsOn: Api  
    Properties:  
      RestApiId: !Ref Api  
  Stage:  
    Type: 'AWS::ApiGateway::Stage'  
    Properties:  
      DeploymentId: !Ref ApiGatewayDeployment20250219  
      RestApiId: !Ref Api  
      StageName: prod
```

OpenAPI

The following OpenAPI definition creates the GET `/pets` resource and overrides the request header and create new headers.

```
{  
  "openapi" : "3.0.1",  
  "info" : {  
    "title" : "PetStore Example 2",  
    "description" : "Example pet store API.",  
    "version" : "2025-01-14T00:36:18Z"  
  },  
  "paths" : {  
    "/pets" : {  
      "get" : {  
        "parameters" : [ {  
          "name" : "header2",  
          "in" : "header",  
          "schema" : {  
            "type" : "string"  
          }  
        }, {  
          "name" : "header3",  
          "in" : "header",  
          "schema" : {  
            "type" : "string"  
          }  
        }  
      }  
    }  
  }  
}
```

```
        "name" : "page",
        "in" : "query",
        "schema" : {
            "type" : "string"
        }
    }, {
        "name" : "type",
        "in" : "query",
        "schema" : {
            "type" : "string"
        }
    }, {
        "name" : "header1",
        "in" : "header",
        "schema" : {
            "type" : "string"
        }
    }
],
"responses" : {
    "200" : {
        "description" : "200 response"
    }
},
"x-amazon-apigateway-integration" : {
    "httpMethod" : "GET",
    "uri" : "http://petstore.execute-api.us-east-1.amazonaws.com/petstore/
pets",
    "responses" : {
        "default" : {
            "statusCode" : "200"
        }
    },
    "requestParameters" : {
        "integration.request.header.header1" : "method.request.header.header1",
        "integration.request.header.header2" : "method.request.header.header2",
        "integration.request.querystring.page" :
"method.request.querystring.page",
        "integration.request.querystring.type" :
"method.request.querystring.type"
    },
    "requestTemplates" : {
        "application/json" : "#set($header1Override = \"pets
\")\n#set($header3Value = \"$input.params('header1')$input.params('header2')\")\n$input.json(\"$\")\n#set($context.requestOverride.header.header3
"
    }
}
```

```
= $header3Value)\n#set($context.requestOverride.header.header1 =  
$header1Override)\n#set($context.requestOverride.header.multivalueheader=[$header1Override,  
$header3Value])"  
},  
"passthroughBehavior" : "when_no_match",  
"type" : "http"  
}  
}  
}  
}  
}  
}
```

To use a mapping template override, add one or more of the following `$context` variables. For a list of `$context` variables, see [the section called “Context variables for data transformations”](#).

Tutorial: Modify the integration request and response for integrations to AWS services

The following tutorial shows how to use mapping template transformations to set up mapping templates to transform integration requests and responses using the console and AWS CLI.

Topics

- [Set up data transformation using the API Gateway console](#)
- [Set up data transformation using the AWS CLI](#)
- [Completed data transformation CloudFormation template](#)

Set up data transformation using the API Gateway console

In this tutorial, you will create an incomplete API and DynamoDB table using the following .zip file [data-transformation-tutorial-console.zip](#). This incomplete API has a /pets resource with GET and POST methods.

- The GET method will get data from the `http://petstore-demo-endpoint.execute-api.com/petstore/pets` HTTP endpoint. The output data will be transformed according to the mapping template in [the section called “Mapping template transformations”](#).
- The POST method will allow the user to POST pet information to a Amazon DynamoDB table using a mapping template.

Download and unzip [the app creation template for CloudFormation](#). You'll use this template to create a DynamoDB table to post pet information and an incomplete API. You will finish the rest of the steps in the API Gateway console.

To create an CloudFormation stack

1. Open the CloudFormation console at <https://console.aws.amazon.com/cloudformation>.
2. Choose **Create stack** and then choose **With new resources (standard)**.
3. For **Specify template**, choose **Upload a template file**.
4. Select the template that you downloaded.
5. Choose **Next**.
6. For **Stack name**, enter **data-transformation-tutorial-console** and then choose **Next**.
7. For **Configure stack options**, choose **Next**.
8. For **Capabilities**, acknowledge that CloudFormation can create IAM resources in your account.
9. Choose **Next**, and then choose **Submit**.

CloudFormation provisions the resources specified in the template. It can take a few minutes to finish provisioning your resources. When the status of your CloudFormation stack is **CREATE_COMPLETE**, you're ready to move on to the next step.

To test the GET integration response

1. On the **Resources** tab of the CloudFormation stack for **data-transformation-tutorial-console**, select the physical ID of your API.
2. In the main navigation pane, choose **Resources**, and then select the **GET** method.
3. Choose the **Test** tab. You might need to choose the right arrow button to show the tab.

The output of the test will show the following:

```
[  
 {  
   "id": 1,  
   "type": "dog",  
   "price": 249.99  
 },  
 {  
   "id": 2,
```

```
    "type": "cat",
    "price": 124.99
},
{
    "id": 3,
    "type": "fish",
    "price": 0.99
}
]
```

You will transform this output according to the mapping template in [the section called “Mapping template transformations”](#).

To transform the GET integration response

1. Choose the **Integration response** tab.

Currently, there are no mapping templates defined, so the integration response will not be transformed.

2. For **Default - Response**, choose **Edit**.
3. Choose **Mapping templates**, and then do the following:
 - a. Choose **Add mapping template**.
 - b. For **Content type**, enter **application/json**.
 - c. For **Template body**, enter the following:

```
#set($inputRoot = $input.path('$'))
[
#foreach($elem in $inputRoot)
{
    "description" : "Item $elem.id is a $elem.type.",
    "askingPrice" : $elem.price
}#if($foreach.hasNext),#end

#end
]
```

Choose **Save**.

To test the GET integration response

- Choose the **Test** tab, and then choose **Test**.

The output of the test will show the transformed response.

```
[  
  {  
    "description" : "Item 1 is a dog.",  
    "askingPrice" : 249.99  
  },  
  {  
    "description" : "Item 2 is a cat.",  
    "askingPrice" : 124.99  
  },  
  {  
    "description" : "Item 3 is a fish.",  
    "askingPrice" : 0.99  
  }  
]
```

To transform input data from the POST method

- Choose the **POST** method.
- Choose the **Integration request** tab, and then for **Integration request settings**, choose **Edit**.

The CloudFormation template has populated some of the integration request fields.

- The integration type is AWS service.
- The AWS service is DynamoDB.
- The HTTP method is POST.
- The Action is PutItem.
- The Execution role allowing API Gateway to put an item into the DynamoDB table is data-transformation-tutorial-console-APIGatewayRole. CloudFormation created this role to allow API Gateway to have the minimal permissions for interacting with DynamoDB.

The name of the DynamoDB table has not been specified. You will specify the name in the following steps.

3. For **Request body passthrough**, select **Never**.

This means that the API will reject data with Content-Types that do not have a mapping template.

4. Choose **Mapping templates**.

5. The **Content type** is set to `application/json`. This means a content types that are not `application/json` will be rejected by the API. For more information about the integration passthrough behaviors, see [Method request behavior for payloads without mapping templates for REST APIs in API Gateway](#)

6. Enter the following code into the text editor.

```
{  
    "TableName": "data-transformation-tutorial-console-ddb",  
    "Item": {  
        "id": {  
            "N": $input.json("$.id")  
        },  
        "type": {  
            "S": $input.json("$.type")  
        },  
        "price": {  
            "N": $input.json("$.price")  
        }  
    }  
}
```

This template specifies the table as `data-transformation-tutorial-console-ddb` and sets the items as `id`, `type`, and `price`. The items will come from the body of the POST method. You also can use a data model to help create a mapping template. For more information, see [Request validation for REST APIs in API Gateway](#).

7. Choose **Save** to save your mapping template.

To add a method and integration response from the POST method

The CloudFormation created a blank method and integration response. You will edit this response to provide more information. For more information about how to edit responses, see [Parameter mapping examples for REST APIs in API Gateway](#).

1. On the **Integration response** tab, for **Default - Response**, choose **Edit**.

2. Choose **Mapping templates**, and then choose **Add mapping template**.
3. For **Content-type**, enter **application/json**.
4. In the code editor, enter the following output mapping template to send an output message:

```
{ "message" : "Your response was recorded at $context.requestTime" }
```

For more information about context variables, see [Context variables for data transformations](#).

5. Choose **Save** to save your mapping template.

Test the POST method

Choose the **Test** tab. You might need to choose the right arrow button to show the tab.

1. In the request body, enter the following example.

```
{
  "id": "4",
  "type" : "dog",
  "price": "321"
}
```

2. Choose **Test**.

The output should show your success message.

You can open the DynamoDB console at <https://console.aws.amazon.com/dynamodb/> to verify that the example item is in your table.

To delete an CloudFormation stack

1. Open the CloudFormation console at <https://console.aws.amazon.com/cloudformation>.
2. Select your CloudFormation stack.
3. Choose **Delete** and then confirm your choice.

Set up data transformation using the AWS CLI

In this tutorial, you will create an incomplete API and DynamoDB table using the following .zip file [data-transformation-tutorial-cli.zip](#). This incomplete API has a /pets resource with a GET method

integrated with the `http://petstore-demo-endpoint.execute-api.com/petstore/pets` HTTP endpoint. You will create a POST method to connect to a DynamoDB table and use mapping templates to input data into a DynamoDB table.

- You will transform the output data according to the mapping template in [the section called "Mapping template transformations".](#)
- You will create a POST method to allow the user to POST pet information to a Amazon DynamoDB table using a mapping template.

To create an CloudFormation stack

Download and unzip [the app creation template for CloudFormation.](#)

To complete the following tutorial, you need the [AWS Command Line Interface \(AWS CLI\) version 2.](#)

For long commands, an escape character (\) is used to split a command over multiple lines.

Note

In Windows, some Bash CLI commands that you commonly use (such as zip) are not supported by the operating system's built-in terminals. To get a Windows-integrated version of Ubuntu and Bash, [install the Windows Subsystem for Linux](#). Example CLI commands in this guide use Linux formatting. Commands which include inline JSON documents must be reformatted if you are using the Windows CLI.

1. Use the following command to create the CloudFormation stack.

```
aws cloudformation create-stack --stack-name data-transformation-tutorial-cli  
--template-body file://data-transformation-tutorial-cli.zip --capabilities  
CAPABILITY_NAMED_IAM
```

2. CloudFormation provisions the resources specified in the template. It can take a few minutes to finish provisioning your resources. Use the following command to see the status of your CloudFormation stack.

```
aws cloudformation describe-stacks --stack-name data-transformation-tutorial-cli
```

3. When the status of your CloudFormation stack is StackStatus: "CREATE_COMPLETE", use the following command to retrieve relevant output values for future steps.

```
aws cloudformation describe-stacks --stack-name data-transformation-tutorial-cli  
--query "Stacks[*].Outputs[*].{OutputKey: OutputKey, OutputValue: OutputValue,  
Description: Description}"
```

The output values are the following:

- ApiRole, which is the role name that allows API Gateway to put items in the DynamoDB table. For this tutorial, the role name is data-transformation-tutorial-cli-APIGatewayRole-ABCDEFG.
- DDBTableName, which is the name of the DynamoDB table. For this tutorial, the table name is data-transformation-tutorial-cli-ddb
- ResourceId, which is the ID for the pets resource where the GET and POST methods are exposed. For this tutorial, the Resource ID is efg456
- Apild, which is the ID for the API. For this tutorial, the API ID is abc123.

To test the GET method before data transformation

- Use the following command to test the GET method.

```
aws apigateway test-invoke-method --rest-api-id abc123 \  
--resource-id efg456 \  
--http-method GET
```

The output of the test will show the following.

```
[  
 {  
   "id": 1,  
   "type": "dog",  
   "price": 249.99  
 },  
 {  
   "id": 2,  
   "type": "cat",  
   "price": 124.99  
 },  
 {  
   "id": 3,
```

```
    "type": "fish",
    "price": 0.99
}
]
```

You will transform this output according to the mapping template in [the section called “Mapping template transformations”](#).

To transform the GET integration response

- Use the following command to update the integration response for the GET method. Replace the *rest-api-id* and *resource-id* with your values.

Use the following command to create the integration response.

```
aws apigateway put-integration-response --rest-api-id abc123 \
--resource-id efg456 \
--http-method GET \
--status-code 200 \
--selection-pattern "" \
--response-templates '{"application/json": "#set($inputRoot = $input.path(\"$\"))\n[\n#foreach($elem in $inputRoot)\n {\n \\"description\\": \"Item $elem.id is a\n$elem.type\", \n \\"askingPrice\\": \"$elem.price\"\n }#if($foreach.hasNext),#end\n\n#end\n]"}'
```

To test the GET method

- Use the following command to test the GET method.

```
aws apigateway test-invoke-method --rest-api-id abc123 \
--resource-id efg456 \
--http-method GET \
```

The output of the test will show the transformed response.

```
[

{
    "description" : "Item 1 is a dog.",
    "askingPrice" : 249.99
```

```
},
{
  "description" : "Item 2 is a cat.",
  "askingPrice" : 124.99
},
{
  "description" : "Item 3 is a fish.",
  "askingPrice" : 0.99
}
]
```

To create a POST method

1. Use the following command to create a new method on the /pets resource.

```
aws apigateway put-method --rest-api-id abc123 \
  --resource-id efg456 \
  --http-method POST \
  --authorization-type "NONE" \
```

This method will allow you to send pet information to the DynamoDB table that you created in the CloudFormation stack.

2. Use the following command to create an AWS service integration on the POST method.

```
aws apigateway put-integration --rest-api-id abc123 \
  --resource-id efg456 \
  --http-method POST \
  --type AWS \
  --integration-http-method POST \
  --uri "arn:aws:apigateway:us-east-2:dynamodb:action/PutItem" \
  --credentials arn:aws:iam::111122223333:role/data-transformation-tutorial-
  APIGatewayRole-ABCDEFG \
  --request-templates '{"application/json":"{\\"TableName\\":\\"data-transformation-
  tutorial-cli-ddb\\",\\"Item\\":{\\"id\\":{\\"N\\":$input.json(\"$.id\")},\\"type\\":{\\"S\\":$input.json(\"$.type\")},\\"price\\":{\\"N\\":$input.json(\"$.price\")} }}"}'
```

3. Use the following command to create a method response for a successful call of the POST method.

```
aws apigateway put-method-response --rest-api-id abc123 \
```

```
--resource-id efg456 \
--http-method POST \
--status-code 200
```

4. Use the following command to create an integration response for the successful call of the POST method.

```
aws apigateway put-integration-response --rest-api-id abc123 \
--resource-id efg456 \
--http-method POST \
--status-code 200 \
--selection-pattern "" \
--response-templates '{"application/json": "{\"message\": \"Your response was recorded at $context.requestTime\"}"}'
```

To test the POST method

- Use the following command to test the POST method.

```
aws apigateway test-invoke-method --rest-api-id abc123 \
--resource-id efg456 \
--http-method POST \
--body '{\"id\": \"4\", \"type\": \"dog\", \"price\": \"321\"}'
```

The output will show the successful message.

To delete an CloudFormation stack

- Use the following command to delete your CloudFormation resources.

```
aws cloudformation delete-stack --stack-name data-transformation-tutorial-cli
```

Completed data transformation CloudFormation template

The following example is a completed CloudFormation template, which creates an API and a DynamoDB table with a /pets resource with GET and POST methods.

- The GET method will get data from the `http://petstore-demo-endpoint.execute-api.com/petstore/pets` HTTP endpoint. The output data will be transformed according to the mapping template in [the section called “Mapping template transformations”](#).
- The POST method will allow the user to POST pet information to a DynamoDB table using a mapping template.

Example CloudFormation template

```
AWSTemplateFormatVersion: 2010-09-09
Description: A completed Amazon API Gateway REST API that uses non-proxy integration
to POST to an Amazon DynamoDB table and non-proxy integration to GET transformed pets
data.

Parameters:
  StageName:
    Type: String
    Default: v1
    Description: Name of API stage.

Resources:
  DynamoDBTable:
    Type: 'AWS::DynamoDB::Table'
    Properties:
      TableName: !Sub data-transformation-tutorial-complete
      AttributeDefinitions:
        - AttributeName: id
          AttributeType: N
      KeySchema:
        - AttributeName: id
         KeyType: HASH
      ProvisionedThroughput:
        ReadCapacityUnits: 5
        WriteCapacityUnits: 5
  APIGatewayRole:
    Type: 'AWS::IAM::Role'
    Properties:
      AssumeRolePolicyDocument:
        Version: 2012-10-17
        Statement:
          - Action:
              - 'sts:AssumeRole'
            Effect: Allow
      Principal:
        Service:
```

```
- apigateway.amazonaws.com
```

Policies:

```
- PolicyName: APIGatewayDynamoDBPolicy
```

PolicyDocument:

```
Version: 2012-10-17
```

Statement:

```
- Effect: Allow
```

Action:

```
- 'dynamodb:PutItem'
```

```
Resource: !GetAtt DynamoDBTable.Arn
```

Api:

```
Type: 'AWS::ApiGateway::RestApi'
```

Properties:

```
Name: data-transformation-complete-api
```

```
ApiKeySourceType: HEADER
```

PetsResource:

```
Type: 'AWS::ApiGateway::Resource'
```

Properties:

```
RestApiId: !Ref Api
```

```
ParentId: !GetAtt Api.RootResourceId
```

```
PathPart: 'pets'
```

PetsMethodGet:

```
Type: 'AWS::ApiGateway::Method'
```

Properties:

```
RestApiId: !Ref Api
```

```
ResourceId: !Ref PetsResource
```

```
HttpMethod: GET
```

```
ApiKeyRequired: false
```

```
AuthorizationType: NONE
```

Integration:

```
Type: HTTP
```

```
Credentials: !GetAtt APIGatewayRole.Arn
```

```
IntegrationHttpMethod: GET
```

```
Uri: http://petstore-demo-endpoint.execute-api.com/petstore/pets/
```

```
PassthroughBehavior: WHEN_NO_TEMPLATES
```

IntegrationResponses:

```
- StatusCode: '200'
```

ResponseTemplates:

```
application/json: "#set($inputRoot = $input.path(\"$
```

```
\"))\n[\n#foreach($elem in $inputRoot)\n {\n   \"description\": \"$elem.id is a\n$elem.type\", \n   \"askingPrice\": \"$elem.price\"\n }#if($foreach.hasNext),#end\n\n]\"
```

MethodResponses:

```
- StatusCode: '200'
```

```
PetsMethodPost:
  Type: 'AWS::ApiGateway::Method'
  Properties:
    RestApiId: !Ref Api
    ResourceId: !Ref PetsResource
    HttpMethod: POST
    ApiKeyRequired: false
    AuthorizationType: NONE
  Integration:
    Type: AWS
    Credentials: !GetAtt APIGatewayRole.Arn
    IntegrationHttpMethod: POST
    Uri: arn:aws:apigateway:us-west-1:dynamodb:action/PutItem
    PassthroughBehavior: NEVER
    RequestTemplates:
      application/json: "{\"TableName\":\"data-transformation-tutorial-complete\",
\", \"Item\":{\"id\":{$input.json(\"$.id\")}, \"type\":{$input.json(\"$.type\")}}, \"price\":{$input.json(\"$.price\")} }"
    IntegrationResponses:
      - StatusCode: 200
        ResponseTemplates:
          application/json: "{\"message\": \"Your response was recorded at
\$context.requestTime\"]"
    MethodResponses:
      - StatusCode: '200'

  ApiDeployment:
    Type: 'AWS::ApiGateway::Deployment'
    DependsOn:
      - PetsMethodGet
    Properties:
      RestApiId: !Ref Api
      StageName: !Sub '${StageName}'
  Outputs:
    ApiId:
      Description: API ID for CLI commands
      Value: !Ref Api
    ResourceId:
      Description: /pets resource ID for CLI commands
      Value: !Ref PetsResource
    ApiRole:
      Description: Role ID to allow API Gateway to put and scan items in DynamoDB table
      Value: !Ref APIGatewayRole
    DDBTableName:
```

```
Description: DynamoDB table name  
Value: !Ref DynamoDBTable
```

Examples using variables for mapping template transformations for API Gateway

The following examples show how to use \$context, input, and util variables in mapping templates. You can use a mock integration or a Lambda non-proxy integration that returns the input event back to API Gateway. For a list of all supported variables for data transformations, see [the section called "Variables for data transformations".](#)

Example 1: Pass multiple \$context variables to the integration endpoint

The following example shows a mapping template that maps incoming \$context variables to backend variables with slightly different names in an integration request payload:

```
{  
  "stage" : "$context.stage",  
  "request_id" : "$context.requestId",  
  "api_id" : "$context.apiId",  
  "resource_path" : "$context.resourcePath",  
  "resource_id" : "$context.resourceId",  
  "http_method" : "$context.httpMethod",  
  "source_ip" : "$context.identity.sourceIp",  
  "user-agent" : "$context.identity.userAgent",  
  "account_id" : "$context.identity.accountId",  
  "api_key" : "$context.identity.apiKey",  
  "caller" : "$context.identity.caller",  
  "user" : "$context.identity.user",  
  "user_arn" : "$context.identity.userArn"  
}
```

The output of this mapping template should look like the following:

```
{  
  stage: 'prod',  
  request_id: 'abcdefg-000-000-0000-abcdefg',  
  api_id: 'abcd1234',  
  resource_path: '/',  
  resource_id: 'efg567',  
  http_method: 'GET',  
  source_ip: '192.0.2.1',  
  user-agent: 'curl/7.84.0',
```

```
account_id: '111122223333',
api_key: 'MyTestKey',
caller: 'ABCD-0000-12345',
user: 'ABCD-0000-12345',
user_arn: 'arn:aws:sts::111122223333:assumed-role/Admin/carlos-salazar'
}
```

One of the variables is an API key. This example assumes that the method requires an API key.

Example 2: Pass all request parameters to the integration endpoint via a JSON payload

The following example passes all request parameters, including path, querystring, and header parameters, through to the integration endpoint via a JSON payload:

```
#set($allParams = $input.params())
{
    "params" : {
        #foreach($type in $allParams.keySet())
        #set($params = $allParams.get($type))
        "$type" : {
            #foreach($paramName in $params.keySet())
            "$paramName" : "$util.escapeJavaScript($params.get($paramName))"
            #if($foreach.hasNext),#end
            #end
        }
        #if($foreach.hasNext),#end
        #end
    }
}
```

If a request has the following input parameters:

- A path parameter named myparam
- Query string parameters querystring1=value1,value2
- Headers "header1" : "value1".

The output of this mapping template should look like the following:

```
{"params": {"path": {"example2": "myparamm"}, "querystring": {"querystring1": "value1,value2"}, "header": {"header1": "value1"}}}
```

Example 3: Pass a subsection of a method request to the integration endpoint

The following example uses the input parameter name to retrieve only the name parameter and the input parameter `input.json('$')` to retrieve the entire body of the method request:

```
{  
    "name" : "$input.params('name')",  
    "body" : $input.json('$')  
}
```

For a request that includes the query string parameters `name=Bella&type=dog` and the following body:

```
{  
    "Price" : "249.99",  
    "Age": "6"  
}
```

The output of this mapping template should look like the following:

```
{  
    "name" : "Bella",  
    "body" : {"Price":"249.99", "Age":"6"}  
}
```

This mapping template removes the query string parameter `type=dog`.

If the JSON input contains unescaped characters that cannot be parsed by JavaScript, API Gateway might return a 400 response. Apply `$util.escapeJavaScript($input.json('$'))` to ensure the JSON input can be parsed properly.

The previous example with `$util.escapeJavaScript($input.json('$'))` applied is as follows:

```
{  
    "name" : "$input.params('name')",  
    "body" : "$util.escapeJavaScript($input.json('$'))"  
}
```

In this case, the output of this mapping template should look like the following:

```
{  
    "name" : "Bella",  
    "body": {"Price":"249.99", "Age":"6"}  
}
```

Example 4: Use JSONPath expression to pass a subsection of a method request to the integration endpoint

The following example uses the JSONPath expressions to retrieve only the input parameter name and the Age from the request body:

```
{  
    "name" : "$input.params('name')",  
    "body" : $input.json('$Age')  
}
```

For a request that includes the query string parameters name=Bella&type=dog and the following body:

```
{  
    "Price" : "249.99",  
    "Age": "6"  
}
```

The output of this mapping template should look like the following:

```
{  
    "name" : "Bella",  
    "body" : "6"  
}
```

This mapping template removes the query string parameter type=dog and the Price field from the body.

If a method request payload contains unescaped characters that cannot be parsed by JavaScript, API Gateway might return a 400 response. Apply `$util.escapeJavaScript()` to ensure the JSON input can be parsed properly.

The previous example with `$util.escapeJavaScript($input.json('$Age'))` applied is as follows:

```
{  
    "name" : "$input.params('name')",  
    "body" : "$util.escapeJavaScript($input.json('$Age'))"  
}
```

In this case, the output of this mapping template should look like the following:

```
{  
    "name" : "Bella",  
    "body": "\"6\""  
}
```

Example 5: Use a JSONPath expression to pass information about a method request to the integration endpoint

The following example uses `$input.params()`, `$input.path()`, and `$input.json()` to send information about a method request to the integration endpoint. This mapping template uses the `size()` method to provide the number of elements in a list.

```
{  
    "id" : "$input.params('id')",  
    "count" : "$input.path('$things').size()",  
    "things" : $input.json('$things')  
}
```

For a request that includes the path parameter `123` and the following body:

```
{  
    "things": {  
        "1": {},  
        "2": {},  
        "3": {}  
    }  
}
```

The output of this mapping template should look like the following:

```
{"id":"123","count":"3","things":{"1":{},"2":{},"3":{}}}
```

If a method request payload contains unescaped characters that cannot be parsed by JavaScript, API Gateway might return a `400` response. Apply `$util.escapeJavaScript()` to ensure the JSON input can be parsed properly.

The previous example with `$util.escapeJavaScript($input.json('$.things'))` applied is as follows:

```
{  
    "id" : "$input.params('id')",  
    "count" : "$input.path('$.things').size()",  
    "things" : "$util.escapeJavaScript($input.json('$.things'))"  
}
```

The output of this mapping template should look like the following:

```
{"id":"123","count":"3","things":"{\"1\":{},\"2\":{},\"3\":{}}"}
```

Variables for data transformations for API Gateway

When you create a parameter mapping, you can use context variables as your data source. When you create mapping template transformations, you can use context variables, input, and util variables in scripts you write in [Velocity Template Language \(VTL\)](#). For example mapping templates that use these reference variables, see [the section called “Examples using variables for mapping template transformations”](#).

For a list of reference variables for access logging, see [the section called “Variables for access logging for API Gateway”](#).

Context variables for data transformations

You can use the following case-sensitive `$context` variables for data transformations.

Parameter	Description
<code>\$context.accountId</code>	The API owner's AWS account ID.
<code>\$context.apiId</code>	The identifier API Gateway assigns to your API.
<code>\$context.authorizer.claims. property</code>	A property of the claims returned from the Amazon Cognito user pool after the method

Parameter	Description
	<p>caller is successfully authenticated. For more information, see the section called “Use Amazon Cognito user pool as authorizer for a REST API”.</p>
\$context.authorizer.principalId	<p>The principal user identification associated with the token sent by the client and returned from an API Gateway Lambda authorizer (formerly known as a custom authorizer). For more information, see the section called “Use Lambda authorizers”.</p>

Parameter	Description
<code>\$context.authorizer.</code> <i>property</i>	<p>The stringified value of the specified key-value pair of the context map returned from an API Gateway Lambda authorizer function. For example, if the authorizer returns the following context map:</p> <pre data-bbox="856 517 1134 707"> "context" : { "key": "value", "numKey": 1, "boolKey": true } </pre> <p>Calling <code>\$context.authorizer.key</code> returns the "value" string, calling <code>\$context.authorizer.numKey</code> returns the "1" string, and calling <code>\$context.authorizer.boolKey</code> returns the "true" string.</p> <p>For <i>property</i>, the only supported special character is the underscore (_) character.</p> <p>For more information, see the section called "Use Lambda authorizers".</p>
<code>\$context.awsEndpointRequestId</code>	The AWS endpoint's request ID.
<code>\$context.deploymentId</code>	The ID of the API deployment.
<code>\$context.domainName</code>	The full domain name used to invoke the API. This should be the same as the incoming Host header.
<code>\$context.domainPrefix</code>	The first label of the <code>\$context.domainName</code> .

Parameter	Description
\$context.error.message	A string containing an API Gateway error message. This variable can only be used for simple variable substitution in a GatewayResponse body-mapping template, which is not processed by the Velocity Template Language engine, and in access logging. For more information, see the section called “Metrics” and the section called “Setting up gateway responses to customize error responses” .
\$context.error.messageString	The quoted value of \$context.error.message , namely "\$context.error.message" .
\$context.error.responseType	A type of GatewayResponse . This variable can only be used for simple variable substitution in a GatewayResponse body-mapping template, which is not processed by the Velocity Template Language engine, and in access logging. For more information, see the section called “Metrics” and the section called “Setting up gateway responses to customize error responses” .
\$context.error.validationErrorMessage	A string containing a detailed validation error message.
\$context.extendedRequestId	The extended ID that API Gateway generates and assigns to the API request. The extended request ID contains useful information for debugging and troubleshooting.
\$context.httpMethod	The HTTP method used. Valid values include: DELETE, GET, HEAD, OPTIONS, PATCH, POST, and PUT.

Parameter	Description
\$context.identity.accountId	The AWS account ID associated with the request.
\$context.identity.apiKey	For API methods that require an API key, this variable is the API key associated with the method request. For methods that don't require an API key, this variable is null. For more information, see the section called "Usage plans" .
\$context.identity.apiKeyId	The API key ID associated with an API request that requires an API key.
\$context.identity.caller	The principal identifier of the caller that signed the request. Supported for resources that use IAM authorization.
\$context.identity.cognitoAuthenticationProvider	<p>A comma-separated list of all the Amazon Cognito authentication providers used by the caller making the request. Available only if the request was signed with Amazon Cognito credentials.</p> <p>For example, for an identity from an Amazon Cognito user pool, cognito-idp.<i>region</i>.amazonaws.com/ <i>user_pool_id</i>, cognito-idp. <i>region</i>.amazonaws.com/ <i>user_pool_id</i> :CognitoSignIn: <i>token subject claim</i></p> <p>For information about the available Amazon Cognito authentication providers, see Using Federated Identities in the Amazon Cognito Developer Guide.</p>

Parameter	Description
\$context.identity.cognitoAuthenticationType	The Amazon Cognito authentication type of the caller making the request. Available only if the request was signed with Amazon Cognito credentials. Possible values include authenticated for authenticated identities and unauthenticated for unauthenticated identities.
\$context.identity.cognitoIdentityId	The Amazon Cognito identity ID of the caller making the request. Available only if the request was signed with Amazon Cognito credentials.
\$context.identity.cognitoIdentityPoolId	The Amazon Cognito identity pool ID of the caller making the request. Available only if the request was signed with Amazon Cognito credentials.
\$context.identity.principalOrgId	The AWS organization ID .
\$context.identity.sourceIp	The source IP address of the immediate TCP connection making the request to the API Gateway endpoint.
\$context.identity.clientCertificate.clientCertPem	The PEM-encoded client certificate that the client presented during mutual TLS authentication. Present when a client accesses an API by using a custom domain name that has mutual TLS enabled. Present only in access logs if mutual TLS authentication fails.

Parameter	Description
\$context.identity.clientCertificate.subjectDN	The distinguished name of the subject of the certificate that a client presents. Present when a client accesses an API by using a custom domain name that has mutual TLS enabled. Present only in access logs if mutual TLS authentication fails.
\$context.identity.clientCertificate.issuerDN	The distinguished name of the issuer of the certificate that a client presents. Present when a client accesses an API by using a custom domain name that has mutual TLS enabled. Present only in access logs if mutual TLS authentication fails.
\$context.identity.clientCertificate.serialNumber	The serial number of the certificate. Present when a client accesses an API by using a custom domain name that has mutual TLS enabled. Present only in access logs if mutual TLS authentication fails.
\$context.identity.clientCertificate.validity.notBefore	The date before which the certificate is invalid. Present when a client accesses an API by using a custom domain name that has mutual TLS enabled. Present only in access logs if mutual TLS authentication fails.
\$context.identity.clientCertificate.validity.notAfter	The date after which the certificate is invalid. Present when a client accesses an API by using a custom domain name that has mutual TLS enabled. Present only in access logs if mutual TLS authentication fails.
\$context.identity.vpcId	The VPC ID of the VPC making the request to the API Gateway endpoint.

Parameter	Description
\$context.identity.vpceId	The VPC endpoint ID of the VPC endpoint making the request to the API Gateway endpoint. Present only when you have a private API.
\$context.identity.user	The principal identifier of the user that will be authorized against resource access. Supported for resources that use IAM authorization.
\$context.identity.userAgent	The User-Agent header of the API caller.
\$context.identity.userArn	The Amazon Resource Name (ARN) of the effective user identified after authentication. For more information, see https://docs.aws.amazon.com/IAM/latest/UserGuide/id_users.html .
\$context.isCanaryRequest	Returns <code>true</code> if the request was directed to the canary and <code>false</code> if the request was not directed to the canary. Present only when you have a canary enabled.
\$context.path	The request path. For example, for a non-proxy request URL of <code>https://{{rest-api-id}}.execute-api.{{region}}.amazonaws.com/{{stage}}/root/child</code> , the <code>\$context.path</code> value is <code>/{{stage}}/root/child</code> .

Parameter	Description
\$context.protocol	<p>The request protocol, for example, HTTP/1.1.</p> <div data-bbox="845 312 1519 762" style="border: 1px solid #ccc; padding: 10px;"><p> Note</p><p>API Gateway APIs can accept HTTP/2 requests, but API Gateway sends requests to backend integrations using HTTP/1.1. As a result, the request protocol is logged as HTTP/1.1 even if a client sends a request that uses HTTP/2.</p></div>
\$context.requestId	An ID for the request. Clients can override this request ID. Use \$context.extendedRequestId for a unique request ID that API Gateway generates.
\$context.requestOverride.header. <i>header_name</i>	The request header override. If this parameter is defined, it contains the headers to be used instead of the HTTP Headers that are defined in the Integration Request pane. For more information, see Override your API's request and response parameters and status codes for REST APIs in API Gateway .
\$context.requestOverride.path. <i>path_name</i>	The request path override. If this parameter is defined, it contains the request path to be used instead of the URL Path Parameters that are defined in the Integration Request pane. For more information, see Override your API's request and response parameters and status codes for REST APIs in API Gateway .

Parameter	Description
\$context.requestOverride.querystring. <i>querystring_name</i>	The request query string override. If this parameter is defined, it contains the request query strings to be used instead of the URL Query String Parameters that are defined in the Integration Request pane. For more information, see Override your API's request and response parameters and status codes for REST APIs in API Gateway .
\$context.responseOverride.header. <i>header_name</i>	The response header override. If this parameter is defined, it contains the header to be returned instead of the Response header that is defined as the Default mapping in the Integration Response pane. For more information, see Override your API's request and response parameters and status codes for REST APIs in API Gateway .
\$context.responseOverride.status	The response status code override. If this parameter is defined, it contains the status code to be returned instead of the Method response status that is defined as the Default mapping in the Integration Response pane. For more information, see Override your API's request and response parameters and status codes for REST APIs in API Gateway .
\$context.requestTime	The CLF -formatted request time (dd/MMM/yy yy:HH:mm:ss +-hhmm).
\$context.requestTimeEpoch	The Epoch -formatted request time, in milliseconds.
\$context.resourceId	The identifier that API Gateway assigns to your resource.

Parameter	Description
\$context.resourcePath	The path to your resource. For example, for the non-proxy request URI of <code>https://[rest-api-id].execute-api.[region].amazonaws.com/{stage}/root/child</code> , the <code>\$context.resourcePath</code> value is <code>/root/child</code> . For more information, see Tutorial: Create a REST API with an HTTP non-proxy integration .
\$context.stage	The deployment stage of the API request (for example, Beta or Prod).
\$context.wafResponseCode	The response received from AWS WAF : <code>WAF_ALLOW</code> or <code>WAF_BLOCK</code> . Will not be set if the stage is not associated with a web ACL. For more information, see the section called "AWS WAF" .
\$context.webaclArn	The complete ARN of the web ACL that is used to decide whether to allow or block the request. Will not be set if the stage is not associated with a web ACL. For more information, see the section called "AWS WAF" .

Input variables

You can use the following case-sensitive `$input` variables to refer to the method request payload and method request parameters. The following functions are available:

Variable and function	Description
<code>\$input.body</code>	Returns the raw request payload as a string. You can use <code>\$input.body</code> to preserve entire floating point numbers, such as <code>10.00</code> .

Variable and function	Description
\$input.json(x)	<p>This function evaluates a JSONPath expression and returns the results as a JSON string.</p> <p>For example, <code>\$input.json('\$.pets')</code> returns a JSON string representing the pets structure.</p> <p>For more information about JSONPath, see JSONPath or JSONPath for Java.</p>
\$input.params()	Returns a map of all the request parameters. We recommend that you use <code>\$util.escapeJavaScript</code> to sanitize the result to avoid a potential injection attack. For full control of request sanitization, use a proxy integration without a template and handle request sanitization in your integration.
\$input.params(x)	Returns the value of a method request parameter from the path, query string, or header value (searched in that order), given a parameter name string x. We recommend that you use <code>\$util.escapeJavaScript</code> to sanitize the parameter to avoid a potential injection attack. For full control of parameter sanitization, use a proxy integration without a template and handle request sanitization in your integration.

Variable and function	Description
\$input.path(x)	<p>Takes a JSONPath expression string (x) and returns a JSON object representation of the result. This allows you to access and manipulate elements of the payload natively in Apache Velocity Template Language (VTL).</p> <p>For example, if the expression \$input.path('\$.pets') returns an object like this:</p> <pre>[{ "id": 1, "type": "dog", "price": 249.99 }, { "id": 2, "type": "cat", "price": 124.99 }, { "id": 3, "type": "fish", "price": 0.99 }]</pre> <p>\$input.path('\$.pets').size() would return "3".</p> <p>For more information about JSONPath, see JSONPath or JSONPath for Java.</p>

Stage variables

You can use the following stage variables as placeholders for ARNs and URLs in method integrations. For more information, see [the section called “Use stage variables”](#).

Syntax	Description
<pre>\$stageVariables. <i>variable_name</i> , \$stageVariables[' <i>variable_name</i> '], or \${stageVariables[' <i>variable_name</i> ']}</pre>	<i>variable_name</i> represents a stage variable name.

Util variables

You can use the following case-sensitive `$util` variables to use utility functions for mapping templates. Unless otherwise specified, the default character set is UTF-8.

Function	Description
<code>\$util.escapeJavaScript()</code>	<p>Escapes the characters in a string using JavaScript string rules.</p> <p>Note</p> <p>This function will turn any regular single quotes ('') into escaped ones (\'). However, the escaped single quotes are not valid in JSON. Thus, when the output from this function is used in a JSON property, you must turn any escaped single quotes (\') back to regular single quotes (''). This is shown in the following example:</p> <pre>"input" : "\$util.escapeJavaScript(<i>data</i>).replaceAll("\\\"", "")"</pre>
<code>\$util.parseJson()</code>	Takes "stringified" JSON and returns an object representation of the result. You can use the result from this function to access and

Function	Description
	<p>manipulate elements of the payload natively in Apache Velocity Template Language (VTL). For example, if you have the following payload:</p> <pre data-bbox="848 443 1419 517">{ "errorMessage": "{\"key1\": \"var1\", \"key2\": {\"arr\": [1, 2, 3]}}"}</pre> <p>and use the following mapping template</p> <pre data-bbox="848 675 1387 950">#set (\$errorMessageObj = \$util.parseJson(\$input.path('\$.errorMessage'))) { "errorMessageObjKey2ArrVal" : \$errorMessageObj.key2.arr[0] }</pre> <p>You will get the following output:</p> <pre data-bbox="848 1108 1387 1214">{ "errorMessageObjKey2ArrVal" : 1 }</pre>
\$util.urlEncode()	Converts a string into "application/x-www-form-urlencoded" format.
\$util.urlDecode()	Decodes an "application/x-www-form-urlencoded" string.
\$util.base64Encode()	Encodes the data into a base64-encoded string.
\$util.base64Decode()	Decodes the data from a base64-encoded string.

Gateway responses for REST APIs in API Gateway

A gateway response is identified by a response type that is defined by API Gateway. The response consists of an HTTP status code, a set of additional headers that are specified by parameter mappings, and a payload that is generated by a non-[VTL](#) mapping template.

In the API Gateway REST API, a gateway response is represented by the [GatewayResponse](#). In OpenAPI, a `GatewayResponse` instance is described by the [x-amazon-apigateway-gateway-responses.gatewayResponse](#) extension.

To enable a gateway response, you set up a gateway response for a [supported response type](#) at the API level. Whenever API Gateway returns a response of this type, the header mappings and payload mapping templates defined in the gateway response are applied to return the mapped results to the API caller.

In the following section, we show how to set up gateway responses by using the API Gateway console and the API Gateway REST API.

Setting up gateway responses to customize error responses

If API Gateway fails to process an incoming request, it returns to the client an error response without forwarding the request to the integration backend. By default, the error response contains a short descriptive error message. For example, if you attempt to call an operation on an undefined API resource, you receive an error response with the `{ "message": "Missing Authentication Token" }` message. If you are new to API Gateway, you may find it difficult to understand what actually went wrong.

For some of the error responses, API Gateway allows customization by API developers to return the responses in different formats. For the Missing Authentication Token example, you can add a hint to the original response payload with the possible cause, as in this example: `{"message": "Missing Authentication Token", "hint": "The HTTP method or resources may not be supported."}`.

When your API mediates between an external exchange and the AWS Cloud, you use VTL mapping templates for integration request or integration response to map the payload from one format to another. However, the VTL mapping templates work only for valid requests with successful responses.

For invalid requests, API Gateway bypasses the integration altogether and returns an error response. You must use the customization to render the error responses in an exchange-compliant

format. Here, the customization is rendered in a non-VTL mapping template supporting only simple variable substitutions.

Generalizing the API Gateway-generated error response to any responses generated by API Gateway, we refer to them as *gateway responses*. This distinguishes API Gateway-generated responses from the integration responses. A gateway response mapping template can access \$context variable values and \$stageVariables property values, as well as method request parameters, in the form of `method.request.param-position.param-name`.

For more information about \$context variables, see [Context variables for data transformations](#). For more information about \$stageVariables, see [Stage variables](#). For more information about method request parameters, see [the section called “Input variables”](#).

Topics

- [Set up a gateway response for a REST API using the API Gateway console](#)
- [Set up a gateway response using the API Gateway REST API](#)
- [Set up gateway response customization in OpenAPI](#)
- [Gateway response types for API Gateway](#)

Set up a gateway response for a REST API using the API Gateway console

The following example shows how to set up a gateway response for a REST API using the API Gateway console

To customize a gateway response using the API Gateway console

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose a REST API.
3. In the main navigation pane, choose **Gateway responses**.
4. Choose a response type, and then choose **Edit**. In this walkthrough, we use **Missing authentication token** as an example.
5. You can change the API Gateway-generated **Status code** to return a different status code that meets your API's requirements. In this example, the customization changes the status code from the default (403) to 404 because this error message occurs when a client calls an unsupported or invalid resource that can be thought of as not found.
6. To return custom headers, choose **Add response header** under **Response headers**. For illustration purposes, we add the following custom headers:

```
Access-Control-Allow-Origin:'a.b.c'  
x-request-id:method.request.header.x-amzn-RequestId  
x-request-path:method.request.path.petId  
x-request-query:method.request.querystring.q
```

In the preceding header mappings, a static domain name ('a.b.c') is mapped to the Allow-Control-Allow-Origin header to allow CORS access to the API; the input request header of x-amzn-RequestId is mapped to request-id in the response; the petId path variable of the incoming request is mapped to the request-path header in the response; and the q query parameter of the original request is mapped to the request-query header of the response.

7. Under **Response templates**, keep application/json for **Content Type** and enter the following body mapping template in the **Template body** editor:

```
{  
    "message": "$context.error.messageString",  
    "type": "$context.error.responseType",  
    "statusCode": "'404'",  
    "stage": "$context.stage",  
    "resourcePath": "$context.resourcePath",  
    "stageVariables.a": "$stageVariables.a"  
}
```

This example shows how to map \$context and \$stageVariables properties to properties of the gateway response body.

8. Choose **Save changes**.
9. Deploy the API to a new or existing stage.

Test your gateway response by calling the following CURL command, assuming the corresponding API method's invoke URL is <https://o81lxisefl.execute-api.us-east-1.amazonaws.com/custErr/pets/{petId}>:

```
curl -v -H 'x-amzn-RequestId:123344566' https://o81lxisefl.execute-api.us-east-1.amazonaws.com/custErr/pets/5/type?q=1
```

Because the extra query string parameter q=1 isn't compatible with the API, an error is returned from the specified gateway response. You should get a gateway response similar to the following:

```
> GET /custErr/pets/5?q=1 HTTP/1.1
Host: o81lxisefl.execute-api.us-east-1.amazonaws.com
User-Agent: curl/7.51.0
Accept: */*

HTTP/1.1 404 Not Found
Content-Type: application/json
Content-Length: 334
Connection: keep-alive
Date: Tue, 02 May 2017 03:15:47 GMT
x-amzn-RequestId: 123344566
Access-Control-Allow-Origin: a.b.c
x-amzn-ErrorType: MissingAuthenticationTokenException
header-1: static
x-request-query: 1
x-request-path: 5
X-Cache: Error from cloudfront
Via: 1.1 441811a054e8d055b893175754efd0c3.cloudfront.net (CloudFront)
X-Amz-Cf-Id: nNDR-fX4csbRoAgtQJ16u0rTDz9FZWT-Mk93Kgoxnfd1TUh3f1mzA==

{
    "message": "Missing Authentication Token",
    "type": "MISSING_AUTHENTICATION_TOKEN",
    "statusCode": '404',
    "stage": "custErr",
    "resourcePath": "/pets/{petId}",
    "stageVariables.a": a
}
```

The preceding example assumes that the API backend is [Pet Store](#) and the API has a stage variable, a, defined.

Set up a gateway response using the API Gateway REST API

Before customizing a gateway response using the API Gateway REST API, you must have already created an API and have obtained its identifier. To retrieve the API identifier, you can follow [restapi:gateway-responses](#) link relation and examine the result.

To customize a gateway response using the API Gateway REST API

1. To overwrite an entire [GatewayResponse](#) instance, call the [gatewayresponse:put](#) action. Specify a desired [responseType](#) in the URL path parameter, and supply in the request payload the [statusCode](#), [responseParameters](#), and [responseTemplates](#) mappings.
2. To update part of a [GatewayResponse](#) instance, call the [gatewayresponse:update](#) action. Specify a desired [responseType](#) in the URL path parameter, and supply in the request payload the individual [GatewayResponse](#) properties you want—for example, the [responseParameters](#) or the [responseTemplates](#) mapping.

Set up gateway response customization in OpenAPI

You can use the `x-amazon-apigateway-gateway-responses` extension at the API root level to customize gateway responses in OpenAPI. The following OpenAPI definition shows an example for customizing the [GatewayResponse](#) of the `MISSING_AUTHENTICATION_TOKEN` type.

```
"x-amazon-apigateway-gateway-responses": {
    "MISSING_AUTHENTICATION_TOKEN": {
        "statusCode": 404,
        "responseParameters": {
            "gatewayresponse.header.x-request-path": "method.input.params.petId",
            "gatewayresponse.header.x-request-query": "method.input.params.q",
            "gatewayresponse.header.Access-Control-Allow-Origin": "'a.b.c'",
            "gatewayresponse.header.x-request-header": "method.input.params.Accept"
        },
        "responseTemplates": {
            "application/json": "{\n                \"message\": $context.error.messageString,\n                \"type\": \"$context.error.responseType\",\n                \"stage\": \"$context.stage\"\n            },\n            \"resourcePath\": \"$context.resourcePath\",\n            \"stageVariables.a\": \"$stageVariables.a\",\n            \"statusCode\": \"404\"\n        }"
        }
    }
}
```

In this example, the customization changes the status code from the default (403) to 404. It also adds to the gateway response four header parameters and one body mapping template for the application/json media type.

Gateway response types for API Gateway

API Gateway exposes the following gateway responses for customization by API developers.

Gateway response type	Default status code	Description
ACCESS_DENIED	403	The gateway response for authorization failure—for example, when access is denied by a custom or Amazon Cognito authorizer. If the response type is unspecified, this response defaults to the DEFAULT_4XX type.
API_CONFIGURATION_ERROR	500	The gateway response for an invalid API configuration—including when an invalid endpoint address is submitted, when base64 decoding fails on binary data when binary support is enacted, or when integration response mapping can't match any template and no default template is configured. If the response type is unspecified, this response defaults to the DEFAULT_5XX type.
AUTHORIZER_CONFIGURATION_ERROR	500	The gateway response for failing to connect to a custom or Amazon Cognito authorizer. If the response type is unspecified, this response defaults to the DEFAULT_5XX type.
AUTHORIZER_FAILURE	500	The gateway response when a custom or Amazon Cognito authorizer failed to authenticate.

Gateway response type	Default status code	Description
		ate the caller. If the response type is unspecified, this response defaults to the DEFAULT_5XX type.
BAD_REQUEST_PARAMETERS	400	The gateway response when the request parameter cannot be validated according to an enabled request validator. If the response type is unspecified, this response defaults to the DEFAULT_4XX type.
BAD_REQUEST_BODY	400	The gateway response when the request body cannot be validated according to an enabled request validator. If the response type is unspecified, this response defaults to the DEFAULT_4XX type.

Gateway response type	Default status code	Description
DEFAULT_4XX	Null	<p>The default gateway response for an unspecified response type with the status code of 4XX. Changing the status code of this fallback gateway response changes the status codes of all other 4XX responses to the new value. Resetting this status code to null reverts the status codes of all other 4XX responses to their original values.</p> <div data-bbox="1073 840 1530 1199" style="border: 1px solid #ccc; padding: 10px;"><p> Note AWS WAF custom responses take precedence over custom gateway responses.</p></div>
DEFAULT_5XX	Null	<p>The default gateway response for an unspecified response type with a status code of 5XX. Changing the status code of this fallback gateway response changes the status codes of all other 5XX responses to the new value. Resetting this status code to null reverts the status codes of all other 5XX responses to their original values.</p>

Gateway response type	Default status code	Description
EXPIRED_TOKEN	403	The gateway response for an AWS authentication token expired error. If the response type is unspecified, this response defaults to the DEFAULT_4XX type.
INTEGRATION_FAILURE	504	The gateway response for an integration failed error. If the response type is unspecified, this response defaults to the DEFAULT_5XX type.
INTEGRATION_TIMEOUT	504	The gateway response for an integration timed out error. If the response type is unspecified, this response defaults to the DEFAULT_5XX type.
INVALID_API_KEY	403	The gateway response for an invalid API key submitted for a method requiring an API key. If the response type is unspecified, this response defaults to the DEFAULT_4XX type.
INVALID_SIGNATURE	403	The gateway response for an invalid AWS signature error. If the response type is unspecified, this response defaults to the DEFAULT_4XX type.

Gateway response type	Default status code	Description
MISSING_AUTHENTICATION_TOKEN	403	The gateway response for a missing authentication token error, including the cases when the client attempts to invoke an unsupported API method or resource. If the response type is unspecified, this response defaults to the DEFAULT_4XX type.
QUOTA_EXCEEDED	429	The gateway response for the usage plan quota exceeded error. If the response type is unspecified, this response defaults to the DEFAULT_4XX type.
REQUEST_TOO_LARGE	413	The gateway response for the request too large error. If the response type is unspecified, this response defaults to: HTTP content length exceeded 10485760 bytes.
RESOURCE_NOT_FOUND	404	The gateway response when API Gateway cannot find the specified resource after an API request passes authentication and authorization, except for API key authentication and authorization. If the response type is unspecified, this response defaults to the DEFAULT_4XX type.

Gateway response type	Default status code	Description
THROTTLED	429	The gateway response when usage plan-, method-, stage-, or account-level throttling limits exceeded. If the response type is unspecified, this response defaults to the DEFAULT_4XX type.
UNAUTHORIZED	401	The gateway response when the custom or Amazon Cognito authorizer failed to authenticate the caller.
UNSUPPORTED_MEDIA_TYPE	415	The gateway response when a payload is of an unsupported media type, if strict passthrough behavior is enabled. If the response type is unspecified, this response defaults to the DEFAULT_4XX type.
WAF_FILTERED	403	The gateway response when a request is blocked by AWS WAF. If the response type is unspecified, this response defaults to the DEFAULT_4XX type.

 **Note**

[AWS WAF custom responses](#) take precedence over custom gateway responses.

CORS for REST APIs in API Gateway

[Cross-origin resource sharing \(CORS\)](#) is a browser security feature that restricts cross-origin HTTP requests that are initiated from scripts running in the browser. For more information, see [What is CORS?](#).

Determining whether to enable CORS support

A *cross-origin* HTTP request is one that is made to:

- A different *domain* (for example, from example.com to amazondomains.com)
- A different *subdomain* (for example, from example.com to petstore.example.com)
- A different *port* (for example, from example.com to example.com:10777)
- A different *protocol* (for example, from https://example.com to http://example.com)

If you cannot access your API and receive an error message that contains Cross-Origin Request Blocked, you might need to enable CORS.

Cross-origin HTTP requests can be divided into two types: *simple* requests and *non-simple* requests.

Enabling CORS for a simple request

An HTTP request is *simple* if all of the following conditions are true:

- It is issued against an API resource that allows only GET, HEAD, and POST requests.
- If it is a POST method request, it must include an Origin header.
- The request payload content type is text/plain, multipart/form-data, or application/x-www-form-urlencoded.
- The request does not contain custom headers.
- Any additional requirements that are listed in the [Mozilla CORS documentation for simple requests](#).

For simple cross-origin POST method requests, the response from your resource needs to include the header Access-Control-Allow-Origin: '*' or Access-Control-Allow-Origin: '*origin*'.

All other cross-origin HTTP requests are *non-simple* requests.

Enabling CORS for a non-simple request

If your API's resources receive non-simple requests, you must enable additional CORS support depending on your integration type.

Enabling CORS for non-proxy integrations

For these integrations, the [CORS protocol](#) requires the browser to send a preflight request to the server and wait for approval (or a request for credentials) from the server before sending the actual request. You must configure your API to send an appropriate response to the preflight request.

To create a preflight response:

1. Create an OPTIONS method with a mock integration.
2. Add the following response headers to the 200 method response:
 - Access-Control-Allow-Headers
 - Access-Control-Allow-Methods
 - Access-Control-Allow-Origin
3. Set the integration passthrough behavior to NEVER. In this case, the method request of an unmapped content type will be rejected with an HTTP 415 Unsupported Media Type response. For more information, see [Method request behavior for payloads without mapping templates for REST APIs in API Gateway](#).
4. Enter values for the response headers. To allow all origins, all methods, and common headers, use the following header values:
 - Access-Control-Allow-Headers: 'Content-Type, X-Amz-Date, Authorization, X-Api-Key, X-Amz-Security-Token'
 - Access-Control-Allow-Methods: 'DELETE, GET, HEAD, OPTIONS, PUT, POST, PATCH'
 - Access-Control-Allow-Origin: '*'

After creating the preflight request, you must return the Access-Control-Allow-Origin: '*' or Access-Control-Allow-Origin: '*origin*' header for all CORS-enabled methods for at least all 200 responses.

Enabling CORS for non-proxy integrations using the AWS Management Console

You can use the AWS Management Console to enable CORS. API Gateway creates an OPTIONS method and adds the Access-Control-Allow-Origin header to your existing method integration responses. This doesn't always work, and sometimes you need to manually modify the integration response to return the Access-Control-Allow-Origin header for all CORS-enabled methods for at least all 200 responses.

If you have binary media types set to `/*` for your API, when API Gateway creates an OPTIONS method, change the contentHandling to `CONVERT_TO_TEXT`.

The following [update-integration](#) command changes the contentHandling to `CONVERT_TO_TEXT` for an integration request:

```
aws apigateway update-integration \
--rest-api-id abc123 \
--resource-id aaa111 \
--http-method OPTIONS \
--patch-operations op='replace',path='/contentHandling',value='CONVERT_TO_TEXT'
```

The following [update-integration-response](#) command changes the contentHandling to `CONVERT_TO_TEXT` for an integration response:

```
aws apigateway update-integration-response \
--rest-api-id abc123 \
--resource-id aaa111 \
--http-method OPTIONS \
--status-code 200 \
--patch-operations op='replace',path='/contentHandling',value='CONVERT_TO_TEXT'
```

Enabling CORS support for proxy integrations

For a Lambda proxy integration or HTTP proxy integration, your backend is responsible for returning the `Access-Control-Allow-Origin`, `Access-Control-Allow-Methods`, and `Access-Control-Allow-Headers` headers, because a proxy integration doesn't return an integration response.

The following example Lambda functions return the required CORS headers:

Node.js

```
export const handler = async (event) => {
  const response = {
    statusCode: 200,
    headers: {
      "Access-Control-Allow-Headers" : "Content-Type",
      "Access-Control-Allow-Origin": "https://www.example.com",
      "Access-Control-Allow-Methods": "OPTIONS,POST,GET"
    },
    body: JSON.stringify('Hello from Lambda!'),
  };
  return response;
};
```

Python 3

```
import json

def lambda_handler(event, context):
    return {
        'statusCode': 200,
        'headers': {
            'Access-Control-Allow-Headers': 'Content-Type',
            'Access-Control-Allow-Origin': 'https://www.example.com',
            'Access-Control-Allow-Methods': 'OPTIONS,POST,GET'
        },
        'body': json.dumps('Hello from Lambda!')
    }
```

Topics

- [Enable CORS on a resource using the API Gateway console](#)
- [Enable CORS on a resource using the API Gateway import API](#)
- [Test CORS for an API Gateway API](#)

Enable CORS on a resource using the API Gateway console

You can use the API Gateway console to enable CORS support for one or all methods on a REST API resource that you have created. After you enable COR support, set the integration passthrough

behavior to NEVER. In this case, the method request of an unmapped content type will be rejected with an HTTP 415 Unsupported Media Type response. For more information, see [Method request behavior for payloads without mapping templates for REST APIs in API Gateway](#)

⚠ Important

Resources can contain child resources. Enabling CORS support for a resource and its methods does not recursively enable it for child resources and their methods.

To enable CORS support on a REST API resource

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose an API.
3. Choose a resource under **Resources**.
4. In the **Resource details** section, choose **Enable CORS**.

The screenshot shows the AWS API Gateway Resources page. At the top, there's a navigation bar with 'API Gateway' and 'APIs'. Below that, the main title is 'Resources - PetStore (abcd1234)'. On the left, there's a sidebar with a 'Create resource' button and a list of resources: '/', '/pets', '/{petId}', and '/{petId}' again. The '/{petId}' item has 'GET' and 'OPTIONS' methods listed under it. On the right, the 'Resource details' section shows the path '/'. It includes buttons for 'Update documentation' and 'Enable CORS' (which is highlighted with a red box). Below this is the 'Methods (1)' section, which lists a single GET method with 'Mock' integration type, 'None' authorization, and 'Not required' API key requirement. There are 'Delete' and 'Create method' buttons at the bottom of the methods list.

5. In the **Enable CORS** box, do the following:

- a. (Optional) If you created a custom gateway response and want to enable CORS support for a response, select a gateway response.
 - b. Select each method to enable CORS support. The OPTION method must have CORS enabled.
- If you enable CORS support for an ANY method, CORS is enabled for all methods.
- c. In the **Access-Control-Allow-Headers** input field, enter a static string of a comma-separated list of headers that the client must submit in the actual request of the resource. Use the console-provided header list of 'Content-Type, X-Amz-Date, Authorization, X-Api-Key, X-Amz-Security-Token' or specify your own headers.
 - d. Use the console-provided value of '*' as the **Access-Control-Allow-Origin** header value to allow access requests from all origins, or specify an origin to be permitted to access the resource.
 - e. Choose **Save**.

 API Gateway > APIs > Resources - PetStore (abcd1234) > Enable CORS

Enable CORS

CORS settings Info

To allow requests from scripts running in the browser, configure cross-origin resource sharing (CORS) for your API. When you save your configuration, API Gateway replaces any existing CORS settings with your new configuration.

Gateway responses

API Gateway will configure CORS for the selected gateway responses.

- Default 4XX
 Default 5XX

Access-Control-Allow-Methods

API Gateway will configure CORS for the selected gateway responses.

Access-Control-Allow-Headers

API Gateway will configure CORS for the selected gateway responses.

Content-Type,X-Amz-Date,Authorization,X-Api-Key,X-Amz-Security-Token

Access-Control-Allow-Origin

Enter an origin that can access the resource. Use a wildcard '*' to allow any origin to access the resource.

*

► Additional settings

Cancel

Save

⚠ Important

When applying the above instructions to the ANY method in a proxy integration, any applicable CORS headers will not be set. Instead, your backend must return the applicable CORS headers, such as Access-Control-Allow-Origin.

After CORS is enabled on the GET method, an OPTIONS method is added to the resource, if it is not already there. The 200 response of the OPTIONS method is automatically configured to return the three Access-Control-Allow-* headers to fulfill preflight handshakes. In addition, the actual (GET) method is also configured by default to return the Access-Control-Allow-Origin header in its 200 response as well. For other types of responses, you will need to manually configure them to return Access-Control-Allow-Origin' header with '*' or specific origins, if you do not want to return the Cross-origin access error.

After you enable CORS support on your resource, you must deploy or redeploy the API for the new settings to take effect. For more information, see [the section called “Create a deployment”](#).

ℹ Note

If you cannot enable CORS support on your resource after following the procedure, we recommend that you compare your CORS configuration to the example API /pets resource. To learn how to create the example API, see [the section called “Tutorial: Create a REST API by importing an example”](#).

Enable CORS on a resource using the API Gateway import API

If you are using the [API Gateway Import API](#), you can set up CORS support using an OpenAPI file. You must first define an OPTIONS method in your resource that returns the required headers.

ℹ Note

Web browsers expect Access-Control-Allow-Headers, and Access-Control-Allow-Origin headers to be set up in each API method that accepts CORS requests. In addition, some browsers first make an HTTP request to an OPTIONS method in the same resource, and then expect to receive the same headers.

Example Options method

The following example creates an OPTIONS method for a mock integration.

OpenAPI 3.0

```
/users:
  options:
    summary: CORS support
    description: |
      Enable CORS by returning correct headers
    tags:
      - CORS
    responses:
      200:
        description: Default response for CORS method
        headers:
          Access-Control-Allow-Origin:
            schema:
              type: "string"
          Access-Control-Allow-Methods:
            schema:
              type: "string"
          Access-Control-Allow-Headers:
            schema:
              type: "string"
            content: {}
      x-amazon-apigateway-integration:
        type: mock
        requestTemplates:
          application/json: "{\"statusCode\": 200}"
        passthroughBehavior: "never"
        responses:
          default:
            statusCode: "200"
            responseParameters:
              method.response.header.Access-Control-Allow-Headers: "'Content-Type,X-Amz-Date,Authorization,X-Api-Key'"
              method.response.header.Access-Control-Allow-Methods: "'*'"
              method.response.header.Access-Control-Allow-Origin: "'*'"
```

OpenAPI 2.0

```
/users:
  options:
    summary: CORS support
    description: |
      Enable CORS by returning correct headers
    consumes:
      - "application/json"
    produces:
      - "application/json"
    tags:
      - CORS
    x-amazon-apigateway-integration:
      type: mock
      requestTemplates: "{\"statusCode\": 200}"
      passthroughBehavior: "never"
      responses:
        "default":
          statusCode: "200"
          responseParameters:
            method.response.header.Access-Control-Allow-Headers : "'Content-Type,X-Amz-Date,Authorization,X-Api-Key'"
            method.response.header.Access-Control-Allow-Methods : "'*'"
            method.response.header.Access-Control-Allow-Origin : "'*'"
      responses:
        200:
          description: Default response for CORS method
          headers:
            Access-Control-Allow-Headers:
              type: "string"
            Access-Control-Allow-Methods:
              type: "string"
            Access-Control-Allow-Origin:
              type: "string"
```

Once you have configured the OPTIONS method for your resource, you can add the required headers to the other methods in the same resource that need to accept CORS requests.

1. Declare the **Access-Control-Allow-Origin** and **Headers** to the response types.

OpenAPI 3.0

```
responses:
  200:
    description: Default response for CORS method
    headers:
      Access-Control-Allow-Origin:
        schema:
          type: "string"
      Access-Control-Allow-Methods:
        schema:
          type: "string"
      Access-Control-Allow-Headers:
        schema:
          type: "string"
    content: {}
```

OpenAPI 2.0

```
responses:
  200:
    description: Default response for CORS method
    headers:
      Access-Control-Allow-Headers:
        type: "string"
      Access-Control-Allow-Methods:
        type: "string"
      Access-Control-Allow-Origin:
        type: "string"
```

2. In the `x-amazon-apigateway-integration` tag, set up the mapping for those headers to your static values:

OpenAPI 3.0

```
responses:
  default:
    statusCode: "200"
    responseParameters:
      method.response.header.Access-Control-Allow-Headers: "'Content-Type,X-Amz-Date,Authorization,X-Api-Key'"
      method.response.header.Access-Control-Allow-Methods: "'*'"
```

```
        method.response.header.Access-Control-Allow-Origin: "*"
responses:
    application/json: |
        {}
```

OpenAPI 2.0

```
responses:
    "default":
        statusCode: "200"
        responseParameters:
            method.response.header.Access-Control-Allow-Headers : "'Content-Type,X-Amz-Date,Authorization,X-Api-Key'"
            method.response.header.Access-Control-Allow-Methods : "*"
            method.response.header.Access-Control-Allow-Origin : "*"
```

Example API

The following example creates a complete API with an OPTIONS method and a GET method with an HTTP integration.

OpenAPI 3.0

```
openapi: "3.0.1"
info:
    title: "cors-api"
    description: "cors-api"
    version: "2024-01-16T18:36:01Z"
servers:
- url: "/{basePath}"
variables:
    basePath:
        default: "/test"
paths:
    /:
        get:
            operationId: "GetPet"
            responses:
                "200":
                    description: "200 response"
                    headers:
                        Access-Control-Allow-Origin:
```

```
    schema:
      type: "string"
    content: {}
x-amazon-apigateway-integration:
  httpMethod: "GET"
  uri: "http://petstore.execute-api.us-east-1.amazonaws.com/petstore/pets"
  responses:
    default:
      statusCode: "200"
      responseParameters:
        method.response.header.Access-Control-Allow-Origin: "'*'"
      passthroughBehavior: "never"
      type: "http"
options:
  responses:
    "200":
      description: "200 response"
      headers:
        Access-Control-Allow-Origin:
          schema:
            type: "string"
        Access-Control-Allow-Methods:
          schema:
            type: "string"
        Access-Control-Allow-Headers:
          schema:
            type: "string"
      content:
        application/json:
          schema:
            $ref: "#/components/schemas/Empty"
x-amazon-apigateway-integration:
  responses:
    default:
      statusCode: "200"
      responseParameters:
        method.response.header.Access-Control-Allow-Methods: "'GET,OPTIONS'"
        method.response.header.Access-Control-Allow-Headers: "'Content-Type,X-Amz-Date,Authorization,X-Api-Key'"
        method.response.header.Access-Control-Allow-Origin: "'*'"
      requestTemplates:
        application/json: "{\"statusCode\": 200}"
      passthroughBehavior: "never"
      type: "mock"
```

```
components:  
  schemas:  
    Empty:  
      type: "object"
```

OpenAPI 2.0

```
swagger: "2.0"  
info:  
  description: "cors-api"  
  version: "2024-01-16T18:36:01Z"  
  title: "cors-api"  
basePath: "/test"  
schemes:  
- "https"  
paths:  
  /:  
    get:  
      operationId: "GetPet"  
      produces:  
      - "application/json"  
      responses:  
        "200":  
          description: "200 response"  
          headers:  
            Access-Control-Allow-Origin:  
              type: "string"  
          x-amazon-apigateway-integration:  
            httpMethod: "GET"  
            uri: "http://petstore.execute-api.us-east-1.amazonaws.com/petstore/pets"  
            responses:  
              default:  
                statusCode: "200"  
                responseParameters:  
                  method.response.header.Access-Control-Allow-Origin: "'*'"  
              passthroughBehavior: "never"  
              type: "http"  
            options:  
              consumes:  
              - "application/json"  
              produces:  
              - "application/json"  
              responses:
```

```
"200":  
    description: "200 response"  
    schema:  
        $ref: "#/definitions/Empty"  
    headers:  
        Access-Control-Allow-Origin:  
            type: "string"  
        Access-Control-Allow-Methods:  
            type: "string"  
        Access-Control-Allow-Headers:  
            type: "string"  
    x-amazon-apigateway-integration:  
        responses:  
            default:  
                statusCode: "200"  
                responseParameters:  
                    method.response.header.Access-Control-Allow-Methods: "'GET,OPTIONS'"  
                    method.response.header.Access-Control-Allow-Headers: "'Content-Type,X-Amz-Date,Authorization,X-Api-Key'"  
                    method.response.header.Access-Control-Allow-Origin: "'*'"  
                requestTemplates:  
                    application/json: "{\"statusCode\": 200}"  
                passthroughBehavior: "never"  
                type: "mock"  
    definitions:  
        Empty:  
            type: "object"
```

Test CORS for an API Gateway API

You can test your API's CORS configuration by invoking your API, and checking the CORS headers in the response. The following curl command sends an OPTIONS request to a deployed API.

```
curl -v -X OPTIONS https://{restapi_id}.execute-api.{region}.amazonaws.com/{stage_name}
```

```
< HTTP/1.1 200 OK  
< Date: Tue, 19 May 2020 00:55:22 GMT  
< Content-Type: application/json  
< Content-Length: 0  
< Connection: keep-alive  
< x-amzn-RequestId: a1b2c3d4-5678-90ab-cdef-abc123  
< Access-Control-Allow-Origin: *
```

```
< Access-Control-Allow-Headers: Content-Type,Authorization,X-Amz-Date,X-Api-Key,X-Amz-Security-Token  
< x-amz-apigw-id: Abcd=  
< Access-Control-Allow-Methods: DELETE,GET,HEAD,OPTIONS,PATCH,POST,PUT
```

The `Access-Control-Allow-Origin`, `Access-Control-Allow-Headers`, and `Access-Control-Allow-Methods` headers in the response show that the API supports CORS. For more information, see [CORS for REST APIs in API Gateway](#).

Binary media types for REST APIs in API Gateway

In API Gateway, the API request and response have a text or binary payload. A text payload is a UTF-8-encoded JSON string. A binary payload is anything other than a text payload. The binary payload can be, for example, a JPEG file, a GZip file, or an XML file. The API configuration required to support binary media depends on whether your API uses proxy or non-proxy integrations.

If you use a proxy integration with payload response streaming, you don't need to configure your binary media types. For more information, see [the section called "Stream the integration response for your proxy integrations"](#).

AWS Lambda proxy integrations

To handle binary payloads for AWS Lambda proxy integrations, you must base64-encode your function's response. You must also configure the [binaryMediaTypes](#) for your API. Your API's `binaryMediaTypes` configuration is a list of content types that your API treats as binary data. Example binary media types include `image/png` or `application/octet-stream`. You can use the wildcard character (*) to cover multiple media types.

API Gateway uses the first `Accept` header from clients to determine if a response should return binary media. To return binary media when you can't control the order of `Accept` header values, such as requests from a browser, set your API's binary media types to `*/*`.

For example code, see [the section called "Return binary media from a Lambda proxy integration in API Gateway"](#).

If you use a Lambda proxy integration with payload response streaming, you don't need to configure your binary media types. For more information, see [the section called "Set up a Lambda proxy integration with payload response streaming"](#).

Non-proxy integrations

To handle binary payloads for non-proxy integrations, you add the media types to the [binaryMediaTypes](#) list of the [RestApi](#) resource. Your API's `binaryMediaTypes` configuration is a list of content types that your API treats as binary data. Alternatively, you can set the `contentHandling` properties on the [Integration](#) and the [IntegrationResponse](#) resources. The `contentHandling` value can be `CONVERT_TO_BINARY`, `CONVERT_TO_TEXT`, or `undefined`.

 **Note**

For MOCK or private integrations, setting the `contentHandling` properties isn't supported in the AWS Management Console. You must use the AWS CLI, CloudFormation, or an SDK to set the `contentHandling` properties.

Depending on the `contentHandling` value, and whether the `Content-Type` header of the response or the `Accept` header of the incoming request matches an entry in the `binaryMediaTypes` list, API Gateway can encode the raw binary bytes as a base64-encoded string, decode a base64-encoded string back to its raw bytes, or pass the body through without modification.

You must configure the API as follows to support binary payloads for your API in API Gateway:

- Add the desired binary media types to the `binaryMediaTypes` list on the [RestApi](#) resource. If this property and the `contentHandling` property are not defined, the payloads are handled as UTF-8 encoded JSON strings.
- Address the `contentHandling` property of the [Integration](#) resource.
 - To have the request payload converted from a base64-encoded string to its binary blob, set the property to `CONVERT_TO_BINARY`.
 - To have the request payload converted from a binary blob to a base64-encoded string, set the property to `CONVERT_TO_TEXT`.
 - To pass the payload through without modification, leave the property `undefined`. To pass a binary payload through without modification, you must also ensure that the `Content-Type` matches one of the `binaryMediaTypes` entries, and that [passthrough behaviors](#) are enabled for the API.
- Set the `contentHandling` property of the [IntegrationResponse](#) resource. The `contentHandling` property, `Accept` header in client requests, and your API's

`binaryMediaTypes` combined determine how API Gateway handles content type conversions. For details, see [the section called “Content type conversions in API Gateway”](#).

Important

When a request contains multiple media types in its `Accept` header, API Gateway honors only the first `Accept` media type. If you can't control the order of the `Accept` media types and the media type of your binary content isn't the first in the list, add the first `Accept` media type in the `binaryMediaTypes` list of your API. API Gateway handles all content types in this list as binary.

For example, to send a JPEG file using an `` element in a browser, the browser might send `Accept: image/webp, image/*, */*; q=0.8` in a request. By adding `image/webp` to the `binaryMediaTypes` list, the endpoint receives the JPEG file as binary.

For detailed information about how API Gateway handles the text and binary payloads, see [Content type conversions in API Gateway](#).

Content type conversions in API Gateway

The combination of your API's `binaryMediaTypes`, the headers in client requests, and the `integration contentHandling` property determine how API Gateway encodes payloads.

The following table shows how API Gateway converts the request payload for specific configurations of a request's `Content-Type` header, the `binaryMediaTypes` list of a [RestApi](#) resource, and the `contentHandling` property value of the [Integration](#) resource.

Method request payload	Request Content-Type header	<code>binaryMediaTypes</code>	<code>contentHandling</code>	Integration request payload
Text data	Any data type	Undefined	Undefined	UTF8-encoded string
Text data	Any data type	Undefined	CONVERT_TO_BINARY	Base64-decoded binary blob

Method request payload	Request Content-Type header	binaryMediaTypes	contentHandling	Integration request payload
Text data	Any data type	Undefined	CONVERT_TO_TEXT	UTF8-encoded string
Text data	A text data type	Set with matching media types	Undefined	Text data
Text data	A text data type	Set with matching media types	CONVERT_TO_BINARY	Base64-decoded binary blob
Text data	A text data type	Set with matching media types	CONVERT_TO_TEXT	Text data
Binary data	A binary data type	Set with matching media types	Undefined	Binary data
Binary data	A binary data type	Set with matching media types	CONVERT_TO_BINARY	Binary data
Binary data	A binary data type	Set with matching media types	CONVERT_TO_TEXT	Base64-encoded string

The following table shows how API Gateway converts the response payload for specific configurations of a request's Accept header, the binaryMediaTypes list of a [RestApi](#) resource, and the contentHandling property value of the [IntegrationResponse](#) resource.

⚠️ Important

When a request contains multiple media types in its Accept header, API Gateway honors only the first Accept media type. If you can't control the order of the Accept media types and the media type of your binary content isn't the first in the list, add the first Accept media type in the `binaryMediaTypes` list of your API. API Gateway handles all content types in this list as binary.

For example, to send a JPEG file using an `` element in a browser, the browser might send `Accept:image/webp,image/*,*/*;q=0.8` in a request. By adding `image/webp` to the `binaryMediaTypes` list, the endpoint receives the JPEG file as binary.

Integration response payload	Request Accept header	binaryMediaTypes	contentHandling	Method response payload
Text or binary data	A text type	Undefined	Undefined	UTF8-encoded string
Text or binary data	A text type	Undefined	CONVERT_TO_BINARY	Base64-decoded blob
Text or binary data	A text type	Undefined	CONVERT_TO_TEXT	UTF8-encoded string
Text data	A text type	Set with matching media types	Undefined	Text data
Text data	A text type	Set with matching media types	CONVERT_TO_BINARY	Base64-decoded blob
Text data	A text type	Set with matching media types	CONVERT_TO_TEXT	UTF8-encoded string

Integration response payload	Request Accept header	binaryMediaTypes	contentHandling	Method response payload
Text data	A binary type	Set with matching media types	Undefined	Base64-decoded blob
Text data	A binary type	Set with matching media types	CONVERT_TO_BINARY	Base64-decoded blob
Text data	A binary type	Set with matching media types	CONVERT_TO_TEXT	UTF8-encoded string
Binary data	A text type	Set with matching media types	Undefined	Base64-encoded string
Binary data	A text type	Set with matching media types	CONVERT_TO_BINARY	Binary data
Binary data	A text type	Set with matching media types	CONVERT_TO_TEXT	Base64-encoded string
Binary data	A binary type	Set with matching media types	Undefined	Binary data
Binary data	A binary type	Set with matching media types	CONVERT_TO_BINARY	Binary data
Binary data	A binary type	Set with matching media types	CONVERT_TO_TEXT	Base64-encoded string

When converting a text payload to a binary blob, API Gateway assumes that the text data is a base64-encoded string and outputs the binary data as a base64-decoded blob. If the conversion fails, it returns a 500 response, which indicates an API configuration error. You don't provide a mapping template for such a conversion, although you must enable the [passthrough behaviors](#) on the API.

When converting a binary payload to a text string, API Gateway always applies a base64 encoding on the binary data. You can define a mapping template for such a payload, but can only access the base64-encoded string in the mapping template through `$input.body`, as shown in the following excerpt of an example mapping template.

```
{  
  "data": "$input.body"  
}
```

To have the binary payload passed through without modification, you must enable the [passthrough behaviors](#) on the API.


Enabling binary support using the API Gateway console

The section explains how to enable binary support using the API Gateway console. As an example, we use an API that is integrated with Amazon S3. We focus on the tasks to set the supported media types and to specify how the payload should be handled. For detailed information on how to create an API integrated with Amazon S3, see [Tutorial: Create a REST API as an Amazon S3 proxy](#).

To enable binary support by using the API Gateway console

1. Set binary media types for the API:
 - a. Create a new API or choose an existing API. For this example, we name the API **FileMan**.
 - b. Under the selected API in the primary navigation panel, choose **API settings**.
 - c. In the **API settings** pane, choose **Manage media types** in the **Binary Media Types** section.
 - d. Choose **Add binary media type**.
 - e. Enter a required media type, for example, **image/png**, in the input text field. If needed, repeat this step to add more media types. To support all binary media types, specify ***/***.
 - f. Choose **Save changes**.
2. Set how message payloads are handled for the API method:

- a. Create a new or choose an existing resource in the API. For this example, we use the /{folder}/{item} resource.
- b. Create a new or choose an existing method on the resource. As an example, we use the GET /{folder}/{item} method integrated with the Object GET action in Amazon S3.
- c. For **Content handling**, choose an option.



Choose **Passthrough** if you don't want to convert the body when the client and backend accepts the same binary format. Choose **Convert to text** to convert the binary body to a base64-encoded string when, for example, the backend requires that a binary request payload is passed in as a JSON property. And choose **Convert to binary** when the client submits a base64-encoded string and the backend requires the original binary format, or when the endpoint returns a base64-encoded string and the client accepts only the binary output.

- d. For **Request body passthrough**, choose **When there are no templates defined (recommended)** to enable the passthrough behavior on the request body.

You could also choose **Never**. This means that the API will reject data with content-types that do not have a mapping template.

- e. Preserve the incoming request's Accept header in the integration request. You should do this if you've set contentHandling to passthrough and want to override that setting at runtime.

HTTP headers (2)		<	1	>
Name	Mapped from	Caching		
Accept	method.request.header.Accept	<input type="checkbox"/>	Inactive	
Content-Type	method.request.header.Content-Type	<input type="checkbox"/>	Inactive	

- f. For conversion to text, define a mapping template to put the base64-encoded binary data into the required format.

An example of a mapping template to convert to text is the following:

```
{  
  "operation": "thumbnail",  
  "base64Image": "$input.body"  
}
```

The format of this mapping template depends on the endpoint requirements of the input.

- g. Choose **Save**.

Enabling binary support using the API Gateway REST API

The following tasks show how to enable binary support using the API Gateway REST API calls.

Topics

- [Add and update supported binary media types to an API](#)
- [Configure request payload conversions](#)
- [Configure response payload conversions](#)
- [Convert binary data to text data](#)
- [Convert text data to a binary payload](#)
- [Pass through a binary payload](#)

Add and update supported binary media types to an API

To enable API Gateway to support a new binary media type, you must add the binary media type to the `binaryMediaTypes` list of the `RestApi` resource. For example, to have API Gateway handle JPEG images, submit a PATCH request to the `RestApi` resource:

```
PATCH /restapis/<restapi_id>

{
  "patchOperations" : [ {
    "op" : "add",
    "path" : "/binaryMediaTypes/image~1jpeg"
  }
]
}
```

The MIME type specification of `image/jpeg` that is part of the `path` property value is escaped as `image~1jpeg`.

To update the supported binary media types, replace or remove the media type from the `binaryMediaTypes` list of the `RestApi` resource. For example, to change binary support from JPEG files to raw bytes, submit a PATCH request to the `RestApi` resource, as follows:

```
PATCH /restapis/<restapi_id>

{
  "patchOperations" : [ {
    "op" : "replace",
    "path" : "/binaryMediaTypes/image~1jpeg",
    "value" : "application/octet-stream"
  },
  {
    "op" : "remove",
    "path" : "/binaryMediaTypes/image~1jpeg"
  ]
}
```

Configure request payload conversions

If the endpoint requires a binary input, set the `contentHandling` property of the `Integration` resource to `CONVERT_TO_BINARY`. To do so, submit a PATCH request, as follows:

```
PATCH /restapis/<restapi_id>/resources/<resource_id>/methods/<http_method>/integration
```

```
{  
    "patchOperations" : [ {  
        "op" : "replace",  
        "path" : "/contentHandling",  
        "value" : "CONVERT_TO_BINARY"  
    }]  
}
```

Configure response payload conversions

If the client accepts the result as a binary blob instead of a base64-encoded payload returned from the endpoint, set the `contentHandling` property of the `IntegrationResponse` resource to `CONVERT_TO_BINARY`. To do this, submit a PATCH request, as follows:

```
PATCH /restapis/<restapi_id>/resources/<resource_id>/methods/<http_method>/integration/  
responses/<status_code>
```

```
{  
    "patchOperations" : [ {  
        "op" : "replace",  
        "path" : "/contentHandling",  
        "value" : "CONVERT_TO_BINARY"  
    }]  
}
```

Convert binary data to text data

To send binary data as a JSON property of the input to AWS Lambda or Kinesis through API Gateway, do the following:

1. Enable the binary payload support of the API by adding the new binary media type of `application/octet-stream` to the API's `binaryMediaTypes` list.

```
PATCH /restapis/<restapi_id>  
  
{  
    "patchOperations" : [ {  
        "op" : "add",  
        "path" : "/binaryMediaTypes/application~1octet-stream"
```

```
}
```

```
]
```

```
}
```

- Set CONVERT_TO_TEXT on the contentHandling property of the Integration resource and provide a mapping template to assign the base64-encoded string of the binary data to a JSON property. In the following example, the JSON property is body and \$input.body holds the base64-encoded string.

```
PATCH /restapis/<restapi_id>/resources/<resource_id>/methods/<http_method>/integration
```

```
{
```

```
    "patchOperations" : [
```

```
        {
```

```
            "op" : "replace",
```

```
            "path" : "/contentHandling",
```

```
            "value" : "CONVERT_TO_TEXT"
```

```
        },
```

```
        {
```

```
            "op" : "add",
```

```
            "path" : "/requestTemplates/application~1octet-stream",
```

```
            "value" : "{\"body\": \"$input.body\"}"
```

```
        }
```

```
    ]
```

```
}
```

Convert text data to a binary payload

Suppose a Lambda function returns an image file as a base64-encoded string. To pass this binary output to the client through API Gateway, do the following:

- Update the API's binaryMediaTypes list by adding the binary media type of application/octet-stream, if it is not already in the list.

```
PATCH /restapis/<restapi_id>
```

```
{
```

```
    "patchOperations" : [ {
```

```
        "op" : "add",
```

```
        "path" : "/binaryMediaTypes/application~1octet-stream",
```

```
  }]
}
```

2. Set the contentHandling property on the Integration resource to CONVERT_TO_BINARY.

Do not define a mapping template. If you don't define a mapping template, API Gateway invokes the passthrough template to return the base64-decoded binary blob as the image file to the client.

```
PATCH /restapis/<restapi_id>/resources/<resource_id>/methods/<http_method>/
integration/responses/<status_code>
```

```
{
  "patchOperations" : [
    {
      "op" : "replace",
      "path" : "/contentHandling",
      "value" : "CONVERT_TO_BINARY"
    }
  ]
}
```

Pass through a binary payload

To store an image in an Amazon S3 bucket using API Gateway, do the following:

1. Update the API's binaryMediaTypes list by adding the binary media type of application/octet-stream, if it isn't already in the list.

```
PATCH /restapis/<restapi_id>

{
  "patchOperations" : [ {
    "op" : "add",
    "path" : "/binaryMediaTypes/application~1octet-stream"
  }
]
```

2. On the contentHandling property of the Integration resource, set CONVERT_TO_BINARY.

Set WHEN_NO_MATCH as the passthroughBehavior property value without defining a mapping template. This enables API Gateway to invoke the passthrough template.

```
PATCH /restapis/<restapi_id>/resources/<resource_id>/methods/<http_method>/  
integration  
  
{  
    "patchOperations" : [  
        {  
            "op" : "replace",  
            "path" : "/contentHandling",  
            "value" : "CONVERT_TO_BINARY"  
        },  
        {  
            "op" : "replace",  
            "path" : "/passthroughBehaviors",  
            "value" : "WHEN_NO_MATCH"  
        }  
    ]  
}
```

Import and export content encodings for API Gateway

To import the `binaryMediaTypes` list on a [RestApi](#), use the following API Gateway extension to the API's OpenAPI definition file. The extension is also used to export the API settings.

- [x-amazon-apigateway-binary-media-types property](#)

To import and export the `contentHandling` property value on an `Integration` or `IntegrationResponse` resource, use the following API Gateway extensions to the OpenAPI definitions:

- [x-amazon-apigateway-integration object](#)
- [x-amazon-apigateway-integration.response object](#)

Return binary media from a Lambda proxy integration in API Gateway

To return binary media from an [AWS Lambda proxy integration](#), base64 encode the response from your Lambda function. You must also [configure your API's binary media types](#). When you configure your API's binary media types, your API treats that content type as binary data. The payload size limit is 10 MB.

Note

To use a web browser to invoke an API with this example integration, set your API's binary media types to `*/*`. API Gateway uses the first Accept header from clients to determine if a response should return binary media. To return binary media when you can't control the order of Accept header values, such as requests from a browser, set your API's binary media types to `*/*` (for all content types).

The following example Lambda function can return a binary image from Amazon S3 or text to clients. The function's response includes a Content-Type header to indicate to the client the type of data that it returns. The function conditionally sets the `isBase64Encoded` property in its response, depending on the type of data that it returns.

Node.js

```
import { S3Client, GetObjectCommand } from "@aws-sdk/client-s3"

const client = new S3Client({region: 'us-east-2'});

export const handler = async (event) => {

    var randomint = function(max) {
        return Math.floor(Math.random() * max);
    }

    var number = randomint(2);
    if (number == 1){
        const input = {
            "Bucket" : "bucket-name",
            "Key" : "image.png"
        }
        try {
            const command = new GetObjectCommand(input)
            const response = await client.send(command);
            var str = await response.Body.transformToByteArray();
        } catch (err) {
            console.error(err);
        }
        const base64body = Buffer.from(str).toString('base64');
        return {
            'headers': { "Content-Type": "image/png" },
            'body': base64body
        }
    }
}
```

```
'statusCode': 200,
'body': base64body,
'isBase64Encoded': true
}
} else {
    return {
        'headers': { "Content-Type": "text/html" },
        'statusCode': 200,
        'body': "<h1>This is text</h1>",
    }
}
}
```

Python

```
import base64
import boto3
import json
import random

s3 = boto3.client('s3')

def lambda_handler(event, context):
    number = random.randint(0,1)
    if number == 1:
        response = s3.get_object(
            Bucket='bucket-name',
            Key='image.png',
        )
        image = response['Body'].read()
        return {
            'headers': { "Content-Type": "image/png" },
            'statusCode': 200,
            'body': base64.b64encode(image).decode('utf-8'),
            'isBase64Encoded': True
        }
    else:
        return {
            'headers': { "Content-type": "text/html" },
            'statusCode': 200,
            'body': "<h1>This is text</h1>",
        }
```

To learn more about binary media types, see [Binary media types for REST APIs in API Gateway](#).

Access binary files in Amazon S3 through an API Gateway API

The following examples show the OpenAPI file used to access images in Amazon S3, how to download an image from Amazon S3, and how to upload an image to Amazon S3.

Topics

- [OpenAPI file of a sample API to access images in Amazon S3](#)
- [Download an image from Amazon S3](#)
- [Upload an image to Amazon S3](#)

OpenAPI file of a sample API to access images in Amazon S3

The following OpenAPI file shows a sample API that illustrates downloading an image file from Amazon S3 and uploading an image file to Amazon S3. This API exposes the GET /s3?key={file-name} and PUT /s3?key={file-name} methods for downloading and uploading a specified image file. The GET method returns the image file as a base64-encoded string as part of a JSON output, following the supplied mapping template, in a 200 OK response. The PUT method takes a raw binary blob as input and returns a 200 OK response with an empty payload.

OpenAPI 3.0

```
{  
  "openapi": "3.0.0",  
  "info": {  
    "version": "2016-10-21T17:26:28Z",  
    "title": "ApiName"  
  },  
  "paths": {  
    "/s3": {  
      "get": {  
        "parameters": [  
          {  
            "name": "key",  
            "in": "query",  
            "required": false,  
            "schema": {  
              "type": "string"  
            }  
          }  
        ]  
      }  
    }  
  }  
}
```

```
        }
    ],
    "responses": {
        "200": {
            "description": "200 response",
            "content": {
                "application/json": {
                    "schema": {
                        "$ref": "#/components/schemas/Empty"
                    }
                }
            }
        },
        "500": {
            "description": "500 response"
        }
    },
    "x-amazon-apigateway-integration": {
        "credentials": "arn:aws:iam::123456789012:role/binarySupportRole",
        "responses": {
            "default": {
                "statusCode": "500"
            },
            "2\d{2}": {
                "statusCode": "200"
            }
        },
        "requestParameters": {
            "integration.request.path.key": "method.request.querystring.key"
        },
        "uri": "arn:aws:apigateway:us-west-2:s3:path/{key}",
        "passthroughBehavior": "when_no_match",
        "httpMethod": "GET",
        "type": "aws"
    }
},
"put": {
    "parameters": [
        {
            "name": "key",
            "in": "query",
            "required": false,
            "schema": {
                "type": "string"
            }
        }
    ]
}
```

```
        }
    ],
    "responses": {
        "200": {
            "description": "200 response",
            "content": {
                "application/json": {
                    "schema": {
                        "$ref": "#/components/schemas/Empty"
                    }
                },
                "application/octet-stream": {
                    "schema": {
                        "$ref": "#/components/schemas/Empty"
                    }
                }
            }
        },
        "500": {
            "description": "500 response"
        }
    },
    "x-amazon-apigateway-integration": {
        "credentials": "arn:aws:iam::123456789012:role/binarySupportRole",
        "responses": {
            "default": {
                "statusCode": "500"
            },
            "2\d{2}": {
                "statusCode": "200"
            }
        },
        "requestParameters": {
            "integration.request.path.key": "method.request.querystring.key"
        },
        "uri": "arn:aws:apigateway:us-west-2:s3:path/{key}",
        "passthroughBehavior": "when_no_match",
        "httpMethod": "PUT",
        "type": "aws",
        "contentHandling": "CONVERT_TO_BINARY"
    }
}
}
```

```
},
"x-amazon-apigateway-binary-media-types": [
    "application/octet-stream",
    "image/jpeg"
],
"servers": [
    {
        "url": "https://abcdefghi.execute-api.us-east-1.amazonaws.com/{basePath}",
        "variables": {
            "basePath": {
                "default": "/v1"
            }
        }
    }
],
"components": {
    "schemas": {
        "Empty": {
            "type": "object",
            "title": "Empty Schema"
        }
    }
}
}
```

OpenAPI 2.0

```
{
    "swagger": "2.0",
    "info": {
        "version": "2016-10-21T17:26:28Z",
        "title": "ApiName"
    },
    "host": "abcdefghi.execute-api.us-east-1.amazonaws.com",
    "basePath": "/v1",
    "schemes": [
        "https"
    ],
    "paths": {
        "/s3": {
            "get": {
                "produces": [
                    "application/json"

```

```
],
  "parameters": [
    {
      "name": "key",
      "in": "query",
      "required": false,
      "type": "string"
    }
  ],
  "responses": {
    "200": {
      "description": "200 response",
      "schema": {
        "$ref": "#/definitions/Empty"
      }
    },
    "500": {
      "description": "500 response"
    }
  },
  "x-amazon-apigateway-integration": {
    "credentials": "arn:aws:iam::123456789012:role/binarySupportRole",
    "responses": {
      "default": {
        "statusCode": "500"
      },
      "2\\d{2)": {
        "statusCode": "200"
      }
    },
    "requestParameters": {
      "integration.request.path.key": "method.request.querystring.key"
    },
    "uri": "arn:aws:apigateway:us-west-2:s3:path/{key}",
    "passthroughBehavior": "when_no_match",
    "httpMethod": "GET",
    "type": "aws"
  }
},
"put": {
  "produces": [
    "application/json", "application/octet-stream"
  ],
  "parameters": [
    {

```

```
        "name": "key",
        "in": "query",
        "required": false,
        "type": "string"
    }
],
"responses": {
    "200": {
        "description": "200 response",
        "schema": {
            "$ref": "#/definitions/Empty"
        }
    },
    "500": {
        "description": "500 response"
    }
},
"x-amazon-apigateway-integration": {
    "credentials": "arn:aws:iam::123456789012:role/binarySupportRole",
    "responses": {
        "default": {
            "statusCode": "500"
        },
        "2\d{2}": {
            "statusCode": "200"
        }
    },
    "requestParameters": {
        "integration.request.path.key": "method.request.querystring.key"
    },
    "uri": "arn:aws:apigateway:us-west-2:s3:path/{key}",
    "passthroughBehavior": "when_no_match",
    "httpMethod": "PUT",
    "type": "aws",
    "contentHandling" : "CONVERT_TO_BINARY"
}
}
},
"x-amazon-apigateway-binary-media-types" : ["application/octet-stream", "image/jpeg"],
"definitions": {
    "Empty": {
        "type": "object",

```

```
        "title": "Empty Schema"
    }
}
```

Download an image from Amazon S3

To download an image file (`image.jpg`) as a binary blob from Amazon S3:

```
GET /v1/s3?key=image.jpg HTTP/1.1
Host: abcdefghi.execute-api.us-east-1.amazonaws.com
Content-Type: application/json
Accept: application/octet-stream
```

The successful response looks like this:

```
200 OK HTTP/1.1
```

```
[raw bytes]
```

The raw bytes are returned because the `Accept` header is set to a binary media type of `application/octet-stream` and binary support is enabled for the API.

Alternatively, to download an image file (`image.jpg`) as a base64-encoded string (formatted as a JSON property) from Amazon S3, add a response template to the 200 integration response, as shown in the following bold-faced OpenAPI definition block:

```
"x-amazon-apigateway-integration": {
    "credentials": "arn:aws:iam::123456789012:role/binarySupportRole",
    "responses": {
        "default": {
            "statusCode": "500"
        },
        "2\\d{2)": {
            "statusCode": "200",
            "responseTemplates": {
                "application/json": "{\n        \"image\": \"$input.body\"\n    }"
            }
        }
    },
},
```

The request to download the image file looks like the following:

```
GET /v1/s3?key=image.jpg HTTP/1.1
Host: abcdefghi.execute-api.us-east-1.amazonaws.com
Content-Type: application/json
Accept: application/json
```

The successful response looks like the following:

```
200 OK HTTP/1.1

{
  "image": "W3JhdYBieXRlc10="
}
```

Upload an image to Amazon S3

To upload an image file (`image.jpg`) as a binary blob to Amazon S3:

```
PUT /v1/s3?key=image.jpg HTTP/1.1
Host: abcdefghi.execute-api.us-east-1.amazonaws.com
Content-Type: application/octet-stream
Accept: application/json

[raw bytes]
```

The successful response looks like the following:

```
200 OK HTTP/1.1
```

To upload an image file (`image.jpg`) as a base64-encoded string to Amazon S3:

```
PUT /v1/s3?key=image.jpg HTTP/1.1
Host: abcdefghi.execute-api.us-east-1.amazonaws.com
Content-Type: application/json
Accept: application/json

W3JhdYBieXRlc10=
```

The input payload must be a base64-encoded string because the Content-Type header value is set to `application/json`. The successful response looks like the following:

200 OK HTTP/1.1

Access binary files in Lambda using an API Gateway API

The following OpenAPI example demonstrates how to access a binary file in AWS Lambda through an API Gateway API. This API exposes the GET /lambda?key={file-name} and the PUT /lambda?key={file-name} methods for downloading and uploading a specified image file. The GET method returns the image file as a base64-encoded string as part of a JSON output, following the supplied mapping template, in a 200 OK response. The PUT method takes a raw binary blob as input and returns a 200 OK response with an empty payload.

You create the Lambda function that your API calls, and it must return a base64-encoded string with the Content-Type header of application/json.

Topics

- [OpenAPI file of a sample API to access images in Lambda](#)
- [Download an image from Lambda](#)
- [Upload an image to Lambda](#)

OpenAPI file of a sample API to access images in Lambda

The following OpenAPI file shows an example API that illustrates downloading an image file from Lambda and uploading an image file to Lambda.

OpenAPI 3.0

```
{  
  "openapi": "3.0.0",  
  "info": {  
    "version": "2016-10-21T17:26:28Z",  
    "title": "ApiName"  
  },  
  "paths": {  
    "/lambda": {  
      "get": {  
        "parameters": [  
          {  
            "name": "key",  
            "in": "query",  
            "required": false,  
            "type": "string"  
          }  
        ]  
      }  
    }  
  }  
}
```

```
        "schema": {
            "type": "string"
        }
    ],
    "responses": {
        "200": {
            "description": "200 response",
            "content": {
                "application/json": {
                    "schema": {
                        "$ref": "#/components/schemas/Empty"
                    }
                }
            }
        },
        "500": {
            "description": "500 response"
        }
    },
    "x-amazon-apigateway-integration": {
        "uri": "arn:aws:apigateway:us-east-1:lambda:path/2015-03-31/functions/arn:aws:lambda:us-east-1:123456789012:function:image/invocations",
        "type": "AWS",
        "credentials": "arn:aws:iam::123456789012:role/Lambda",
        "httpMethod": "POST",
        "requestTemplates": {
            "application/json": "{\n    \"imageKey\": \"$input.params('key')\"\n}"
        },
        "responses": {
            "default": {
                "statusCode": "500"
            },
            "2\d{2)": {
                "statusCode": "200",
                "responseTemplates": {
                    "application/json": "{\n    \"image\": \"$input.body\"\n}"
                }
            }
        }
    },
    "put": {
```

```
"parameters": [
    {
        "name": "key",
        "in": "query",
        "required": false,
        "schema": {
            "type": "string"
        }
    }
],
"responses": {
    "200": {
        "description": "200 response",
        "content": {
            "application/json": {
                "schema": {
                    "$ref": "#/components/schemas/Empty"
                }
            },
            "application/octet-stream": {
                "schema": {
                    "$ref": "#/components/schemas/Empty"
                }
            }
        }
    },
    "500": {
        "description": "500 response"
    }
},
"x-amazon-apigateway-integration": {
    "uri": "arn:aws:apigateway:us-east-1:lambda:path/2015-03-31/functions/arn:aws:lambda:us-east-1:123456789012:function:image/invocations",
    "type": "AWS",
    "credentials": "arn:aws:iam::123456789012:role/Lambda",
    "httpMethod": "POST",
    "contentHandling": "CONVERT_TO_TEXT",
    "requestTemplates": {
        "application/json": "{\n          \"imageKey\": \"$input.params('key')\",\n          \"image\": \"$input.body\"\n        }"
    },
    "responses": {
        "default": {
            "statusCode": "500"
        }
    }
}
```

```
        },
        "2\\d{2}": {
            "statusCode": "200"
        }
    }
}
},
"x-amazon-apigateway-binary-media-types": [
    "application/octet-stream",
    "image/jpeg"
],
"servers": [
{
    "url": "https://abcdefghi.execute-api.us-east-1.amazonaws.com/{basePath}",
    "variables": {
        "basePath": {
            "default": "/v1"
        }
    }
}
],
"components": {
    "schemas": {
        "Empty": {
            "type": "object",
            "title": "Empty Schema"
        }
    }
}
}
```

OpenAPI 2.0

```
{
    "swagger": "2.0",
    "info": {
        "version": "2016-10-21T17:26:28Z",
        "title": "ApiName"
    },
    "host": "abcdefghi.execute-api.us-east-1.amazonaws.com",
    "basePath": "/v1",
```

```
"schemes": [
    "https"
],
"paths": {
    "/lambda": {
        "get": {
            "produces": [
                "application/json"
            ],
            "parameters": [
                {
                    "name": "key",
                    "in": "query",
                    "required": false,
                    "type": "string"
                }
            ],
            "responses": {
                "200": {
                    "description": "200 response",
                    "schema": {
                        "$ref": "#/definitions/Empty"
                    }
                },
                "500": {
                    "description": "500 response"
                }
            },
            "x-amazon-apigateway-integration": {
                "uri": "arn:aws:apigateway:us-east-1:lambda:path/2015-03-31/functions/arn:aws:lambda:us-east-1:123456789012:function:image/invocations",
                "type": "AWS",
                "credentials": "arn:aws:iam::123456789012:role/Lambda",
                "httpMethod": "POST",
                "requestTemplates": {
                    "application/json": "{\n          \"imageKey\": \"$input.params('key')\"\n        }"
                },
                "responses": {
                    "default": {
                        "statusCode": "500"
                    },
                    "2\d{2}": {
                        "statusCode": "200",
                        "responseTemplates": {
                            "application/json": "{\n          \"imageKey\": \"$input.params('key')\"\n        }"
                        }
                    }
                }
            }
        }
    }
}
```

```
        "application/json": "{\n          \"image\": \"$input.body\"\n        }\n      }\n    }\n  },\n  \"put\": {\n    \"produces\": [\n      \"application/json\", \"application/octet-stream\"\n    ],\n    \"parameters\": [\n      {\n        \"name\": \"key\",\n        \"in\": \"query\",\n        \"required\": false,\n        \"type\": \"string\"\n      }\n    ],\n    \"responses\": {\n      \"200\": {\n        \"description\": \"200 response\",\n        \"schema\": {\n          \"$ref\": \"#/definitions/Empty\"\n        }\n      },\n      \"500\": {\n        \"description\": \"500 response\"\n      }\n    },\n    \"x-amazon-apigateway-integration\": {\n      \"uri\": \"arn:aws:apigateway:us-east-1:lambda:path/2015-03-31/functions/\narn:aws:lambda:us-east-1:123456789012:function:image/invocations\",\n      \"type\": \"AWS\",\n      \"credentials\": \"arn:aws:iam::123456789012:role/Lambda\",\n      \"httpMethod\": \"POST\",\n      \"contentHandling\" : \"CONVERT_TO_TEXT\",\n      \"requestTemplates\": {\n        \"application/json\": \"{\\n          \"imageKey\": \"$input.params('key')\",\\n          \"image\": \"$input.body\"\n        }\",\n        \"responses\": {\n          \"default\": {\n            \"statusCode\": \"500\"\n          }\n        }\n      }\n    }\n  }
```

```
        "2\\d{2}": {
            "statusCode": "200"
        }
    }
}
},
"x-amazon-apigateway-binary-media-types" : ["application/octet-stream", "image/jpeg"],
"definitions": {
    "Empty": {
        "type": "object",
        "title": "Empty Schema"
    }
}
}
```

Download an image from Lambda

To download an image file (`image.jpg`) as a binary blob from Lambda:

```
GET /v1/lambda?key=image.jpg HTTP/1.1
Host: abcdefghi.execute-api.us-east-1.amazonaws.com
Content-Type: application/json
Accept: application/octet-stream
```

The successful response looks like the following:

```
200 OK HTTP/1.1
```

```
[raw bytes]
```

To download an image file (`image.jpg`) as a base64-encoded string (formatted as a JSON property) from Lambda:

```
GET /v1/lambda?key=image.jpg HTTP/1.1
Host: abcdefghi.execute-api.us-east-1.amazonaws.com
Content-Type: application/json
Accept: application/json
```

The successful response looks like the following:

```
200 OK HTTP/1.1

{
  "image": "W3JhdBieXRlc10="
}
```

Upload an image to Lambda

To upload an image file (`image.jpg`) as a binary blob to Lambda:

```
PUT /v1/lambda?key=image.jpg HTTP/1.1
Host: abcdefghi.execute-api.us-east-1.amazonaws.com
Content-Type: application/octet-stream
Accept: application/json

[raw bytes]
```

The successful response looks like the following:

```
200 OK
```

To upload an image file (`image.jpg`) as a base64-encoded string to Lambda:

```
PUT /v1/lambda?key=image.jpg HTTP/1.1
Host: abcdefghi.execute-api.us-east-1.amazonaws.com
Content-Type: application/json
Accept: application/json

W3JhdBieXRlc10=
```

The successful response looks like the following:

```
200 OK
```

Invoke REST APIs in API Gateway

To call a deployed API, clients submit requests to the URL for the API Gateway component service for API execution, known as `execute-api`.

The base URL for REST APIs is in the following format:

`https://api-id.execute-api.region.amazonaws.com/stage/`

where *api-id* is the API identifier, *region* is the AWS Region, and *stage* is the stage name of the API deployment.

 **Important**

Before you can invoke an API, you must deploy it in API Gateway. For instructions on deploying an API, see [Deploy REST APIs in API Gateway](#).

Topics

- [Obtaining an API's invoke URL](#)
- [Invoking an API](#)
- [Use the API Gateway console to test a REST API method](#)
- [Use a Java SDK generated by API Gateway for a REST API](#)
- [Use an Android SDK generated by API Gateway for a REST API](#)
- [Use a JavaScript SDK generated by API Gateway for a REST API](#)
- [Use a Ruby SDK generated by API Gateway for a REST API](#)
- [Use an iOS SDK generated by API Gateway for a REST API in Objective-C or Swift](#)

Obtaining an API's invoke URL

You can use the console, the AWS CLI, or an exported OpenAPI definition to obtain an API's invoke URL.

Obtaining an API's invoke URL using the console

The following procedure shows how to obtain an API's invoke URL in the REST API console.

To obtain an API's invoke URL using the REST API console

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.

2. Choose a deployed API.
3. From the main navigation pane, choose **Stage**.
4. Under **Stage details**, choose the copy icon to copy your API's invoke URL.

This URL is for the root resource of your API.

Stage details [Info](#) [Edit](#)

Stage name Prod	Rate Info 10000	Web ACL -
Cache cluster Info <input type="radio"/> Inactive	Burst Info 5000	Client certificate -
Default method-level caching <input type="radio"/> Inactive		

Invoke URL [!\[\]\(bccf923fb0903560cc666f55840aeeef_img.jpg\) https://abcd1234.execute-api.us-east-1.amazonaws.com/Prod](https://abcd1234.execute-api.us-east-1.amazonaws.com/Prod)

Active deployment
efg456 on June 01, 2023, 15:00 (UTC-07:00)

5. To obtain an API's invoke URL for another resource in your API, expand the stage under the secondary navigation pane, and then choose a method.
6. Choose the copy icon to copy your API's resource-level invoke URL.

Stages

[Stage actions ▾](#)[Create stage](#)

The screenshot shows the 'prod' stage configuration for the '/pets' endpoint. The left sidebar lists methods: GET, /pets, GET, OPTIONS, POST, /{petId}, GET, and OPTIONS. The 'POST' method is selected. The right panel shows 'Method overrides' with a note that this method inherits settings from the 'prod' stage. It also displays the 'Invoke URL' as <https://abcd1234.execute-api.us-west-1.amazonaws.com/prod/pets>.

Obtaining an API's invoke URL using the AWS CLI

The following procedure shows how to obtain an API's invoke URL using the AWS CLI.

To obtain an API's invoke URL using the AWS CLI

1. Use the following command to obtain the `rest-api-id`. This command returns all `rest-api-id` values in your Region. For more information, see [get-rest-apis](#).

```
aws apigateway get-rest-apis
```

2. Replace the example `rest-api-id` with your `rest-api-id`, replace the example `{stage-name}` with your `{stage-name}`, and replace the `{region}`, with your Region.

```
https://{restapi_id}.execute-api.{region}.amazonaws.com/{stage_name}/
```

Obtaining an API's invoke URL using the exported OpenAPI definition file of the API

You can also construct the root URL by combining the host and basePath fields of an exported OpenAPI definition file of the API. For instructions on how to export your API, see [the section called “Export a REST API”](#).

Invoking an API

You can call your deployed API using the browser, curl, or other applications, like [Postman](#).

Additionally, you can use the API Gateway console to test an API call. Test uses the API Gateway's TestInvoke feature, which allows API testing before the API is deployed. For more information, see [the section called “Use the console to test a REST API method”](#).

 **Note**

Query string parameter values in an invocation URL cannot contain %%.

Invoking an API using a web browser

If your API permits anonymous access, you can use any web browser to invoke any GET method. Enter the complete invocation URL in the browser's address bar.

For other methods or any authentication-required calls, you must specify a payload or sign the requests. You can handle these in a script behind an HTML page or in a client application using one of the AWS SDKs.

Invoking an API using curl

You can use a tool like [curl](#) in your terminal to call your API. The following example curl command invokes the GET method on the `getUsers` resource of the `prod` stage of an API.

Linux or Macintosh

```
curl -X GET 'https://b123abcde4.execute-api.us-west-2.amazonaws.com/prod/getUsers'
```

Windows

```
curl -X GET "https://b123abcde4.execute-api.us-west-2.amazonaws.com/prod/getUsers"
```

Use the API Gateway console to test a REST API method

Use the API Gateway console to test a REST API method.

Topics

- [Prerequisites](#)
- [Test a method with the API Gateway console](#)

Prerequisites

- You must specify the settings for the methods you want to test. Follow the instructions in [Methods for REST APIs in API Gateway](#).

Test a method with the API Gateway console

Important

Testing methods with the API Gateway console might result in changes to resources that cannot be undone. Testing a method with the API Gateway console is the same as calling the method outside of the API Gateway console. For example, if you use the API Gateway console to call a method that deletes an API's resources, if the method call is successful, the API's resources will be deleted.

To test a method

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose a REST API.
3. In the **Resources** pane, choose the method you want to test.

4. Choose the **Test** tab. You might need to choose the right arrow button to show the tab.

The screenshot shows the 'Test' tab selected in a navigation bar. Below it is a 'Test method' section with instructions: 'Make a test call to your method. When you make a test call, API Gateway skips authorization and directly invokes your method.' Under 'Query strings', there is a box containing 'dog=2'. Under 'Headers', there is a box containing 'header1:value1' and 'header2:value2'. Under 'Client certificate', there is a box stating 'No client certificates have been generated.' At the bottom is a prominent orange 'Test' button.

Enter values in any of the displayed boxes (such as **Query strings**, **Headers**, and **Request body**). The console includes these values in the method request in default application/json form.

For additional options you might need to specify, contact the API owner.

5. Choose **Test**. The following information will be displayed:

- **Request** is the resource's path that was called for the method.
- **Status** is the response's HTTP status code.
- **Latency (ms)** is the time between the receipt of the request from the caller and the returned response.
- **Response body** is the HTTP response body.
- **Response headers** are the HTTP response headers.

Tip

Depending on the mapping, the HTTP status code, response body, and response headers might be different from those sent from the Lambda function, HTTP proxy, or AWS service proxy.

- **Logs** are the simulated Amazon CloudWatch Logs entries that would have been written if this method were called outside of the API Gateway console.

 **Note**

Although the CloudWatch Logs entries are simulated, the results of the method call are real.

In addition to using the API Gateway console, you can use AWS CLI or an AWS SDK for API Gateway to test invoking a method. To do so using AWS CLI, see [test-invoke-method](#).

Use a Java SDK generated by API Gateway for a REST API

In this section, we outline the steps to use a Java SDK generated by API Gateway for a REST API, by using the [Simple Calculator](#) API as an example. Before proceeding, you must complete the steps in [Generate SDKs for REST APIs in API Gateway](#).

To install and use a Java SDK generated by API Gateway

1. Extract the contents of the API Gateway-generated .zip file that you downloaded earlier.
2. Download and install [Apache Maven](#) (must be version 3.5 or later).
3. Download and install [JDK 8](#).
4. Set the JAVA_HOME environment variable.
5. Go to the unzipped SDK folder where the pom.xml file is located. This folder is generated-code by default. Run the **mvn install** command to install the compiled artifact files to your local Maven repository. This creates a target folder containing the compiled SDK library.
6. Type the following command in an empty directory to create a client project stub to call the API using the installed SDK library.

```
mvn -B archetype:generate \
-DarchetypeGroupId=org.apache.maven.archetypes \
-DgroupId=examples.aws.apig.simpleCalc.sdk.app \
-DartifactId=SimpleCalc-sdkClient
```

Note

The separator \ in the preceding command is included for readability. The whole command should be on a single line without the separator.

This command creates an application stub. The application stub contains a pom.xml file and an src folder under the project's root directory (*SimpleCalc-sdkClient* in the preceding command). Initially, there are two source files: src/main/java/{package-path}/App.java and src/test/java/{package-path}/AppTest.java. In this example, {package-path} is examples/aws/apig/simpleCalc/sdk/app. This package path is derived from the DarchetypeGroupId value. You can use the App.java file as a template for your client application, and you can add others in the same folder if needed. You can use the AppTest.java file as a unit test template for your application, and you can add other test code files to the same test folder as needed.

7. Update the package dependencies in the generated pom.xml file to the following, substituting your project's groupId, artifactId, version, and name properties, if necessary:

```
<project xmlns="http://maven.apache.org/POM/4.0.0" xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance" xsi:schemaLocation="http://maven.apache.org/POM/4.0.0 http://maven.apache.org/maven-v4_0_0.xsd">
    <modelVersion>4.0.0</modelVersion>
    <groupId>examples.aws.apig.simpleCalc.sdk.app</groupId>
    <artifactId>SimpleCalc-sdkClient</artifactId>
    <packaging>jar</packaging>
    <version>1.0-SNAPSHOT</version>
    <name>SimpleCalc-sdkClient</name>
    <url>http://maven.apache.org</url>

    <dependencies>
        <dependency>
            <groupId>com.amazonaws</groupId>
            <artifactId>aws-java-sdk-core</artifactId>
            <version>1.11.94</version>
        </dependency>
        <dependency>
            <groupId>my-apig-api-examples</groupId>
            <artifactId>simple-calc-sdk</artifactId>
            <version>1.0.0</version>
        </dependency>
    </dependencies>

```

```
</dependency>

<dependency>
    <groupId>junit</groupId>
    <artifactId>junit</artifactId>
    <version>4.12</version>
    <scope>test</scope>
</dependency>

<dependency>
    <groupId>commons-io</groupId>
    <artifactId>commons-io</artifactId>
    <version>2.5</version>
</dependency>
</dependencies>

<build>
    <plugins>
        <plugin>
            <groupId>org.apache.maven.plugins</groupId>
            <artifactId>maven-compiler-plugin</artifactId>
            <version>3.5.1</version>
            <configuration>
                <source>1.8</source>
                <target>1.8</target>
            </configuration>
        </plugin>
    </plugins>
</build>
</project>
```

 **Note**

When a newer version of dependent artifact of `aws-java-sdk-core` is incompatible with the version specified above (1.11.94), you must update the `<version>` tag to the new version.

8. Next, we show how to call the API using the SDK by calling the `getABOp(GetABOpRequest req)`, `getApiRoot(GetApiRootRequest req)`, and `postApiRoot(PostApiRootRequest req)` methods of the SDK. These methods correspond to the `GET /{a}/{b}/{op}`, `GET /?a={x}&b={y}&op={operator}`, and

POST / methods, with a payload of {"a": x, "b": y, "op": "operator"} API requests, respectively.

Update the App.java file as follows:

```
package examples.aws.apig.simpleCalc.sdk.app;

import java.io.IOException;

import com.amazonaws.opensdk.config.ConnectionConfiguration;
import com.amazonaws.opensdk.config.TimeoutConfiguration;

import examples.aws.apig.simpleCalc.sdk.*;
import examples.aws.apig.simpleCalc.sdk.model.*;
import examples.aws.apig.simpleCalc.sdk.SimpleCalcSdk.*;

public class App
{
    SimpleCalcSdk sdkClient;

    public App() {
        initSdk();
    }

    // The configuration settings are for illustration purposes and may not be a
    recommended best practice.
    private void initSdk() {
        sdkClient = SimpleCalcSdk.builder()
            .connectionConfiguration(
                new ConnectionConfiguration()
                    .maxConnections(100)
                    .connectionMaxIdleMillis(1000))
            .timeoutConfiguration(
                new TimeoutConfiguration()
                    .httpRequestTimeout(3000)
                    .totalExecutionTimeout(10000)
                    .socketTimeout(2000))
            .build();

    }
    // Calling shutdown is not necessary unless you want to exert explicit control
    of this resource.
    public void shutdown() {
```

```
        sdkClient.shutdown();
    }

    // GetABOpResult getABOp(GetABOpRequest getABOpRequest)
    public Output getResultWithPathParameters(String x, String y, String operator)
    {
        operator = operator.equals"+" ? "add" : operator;
        operator = operator.equals"/" ? "div" : operator;

        GetABOpResult abopResult = sdkClient.getABOp(new
GetABOpRequest().a(x).b(y).op(operator));
        return abopResult.getResult().getOutput();
    }

    public Output getResultWithQueryParameters(String a, String b, String op) {
        GetApiRootResult rootResult = sdkClient.getApiRoot(new
GetApiRootRequest().a(a).b(b).op(op));
        return rootResult.getResult().getOutput();
    }

    public Output getResultByPostInputBody(Double x, Double y, String o) {
        PostApiRootResult postResult = sdkClient.postApiRoot(
            new PostApiRootRequest().input(new Input().a(x).b(y).op(o)));
        return postResult.getResult().getOutput();
    }

    public static void main( String[] args )
    {
        System.out.println( "Simple calc" );
        // to begin
        App calc = new App();

        // call the SimpleCalc API
        Output res = calc.getResultWithPathParameters("1", "2", "-");
        System.out.printf("GET /1/2/-: %s\n", res.getc());

        // Use the type query parameter
        res = calc.getResultWithQueryParameters("1", "2", "+");
        System.out.printf("GET /?a=1&b=2&op=+: %s\n", res.getc());

        // Call POST with an Input body.
        res = calc.getResultByPostInputBody(1.0, 2.0, "*");
        System.out.printf("PUT /\n\n{\"a\":1, \"b\":2,\"op\":\"*\")\n %s\n",
res.getc());
    }
}
```

```
    }  
}
```

In the preceding example, the configuration settings used to instantiate the SDK client are for illustration purposes and are not necessarily recommended best practice. Also, calling `sdkClient.shutdown()` is optional, especially if you need precise control on when to free up resources.

We have shown the essential patterns to call an API using a Java SDK. You can extend the instructions to calling other API methods.

Use an Android SDK generated by API Gateway for a REST API

In this section, we will outline the steps to use an Android SDK generated by API Gateway for a REST API. Before proceeding further, you must have already completed the steps in [Generate SDKs for REST APIs in API Gateway](#).

Note

The generated SDK is not compatible with Android 4.4 and earlier. For more information, see [the section called “Important notes”](#).

To install and use an Android SDK generated by API Gateway

1. Extract the contents of the API Gateway-generated .zip file that you downloaded earlier.
2. Download and install [Apache Maven](#) (preferably version 3.x).
3. Download and install [JDK 8](#).
4. Set the JAVA_HOME environment variable.
5. Run the **mvn install** command to install the compiled artifact files to your local Maven repository. This creates a target folder containing the compiled SDK library.
6. Copy the SDK file (the name of which is derived from the **Artifact Id** and **Artifact Version** you specified when generating the SDK, e.g., `simple-calcsdk-1.0.0.jar`) from the target folder, along with all of the other libraries from the target/lib folder, into your project's lib folder.

If you use Android Studio, create a `libs` folder under your client app module and copy the required `.jar` file into this folder. Verify that the dependencies section in the module's gradle file contains the following.

```
compile fileTree(include: ['*.jar'], dir: 'libs')
compile fileTree(include: ['*.jar'], dir: 'app/libs')
```

Make sure no duplicated `.jar` files are declared.

7. Use the `ApiClientFactory` class to initialize the API Gateway-generated SDK. For example:

```
ApiClientFactory factory = new ApiClientFactory();

// Create an instance of your SDK. Here, 'SimpleCalcClient.java' is the compiled
// java class for the SDK generated by API Gateway.
final SimpleCalcClient client = factory.build(SimpleCalcClient.class);

// Invoke a method:
//   For the 'GET /?a=1&b=2&op=+' method exposed by the API, you can invoke it by
//   calling the following SDK method:

Result output = client.rootGet("1", "2", "+");

//   where the Result class of the SDK corresponds to the Result model of the
//   API.
//

//   For the 'GET /{a}/{b}/{op}' method exposed by the API, you can call the
//   following SDK method to invoke the request,

Result output = client.aB0pGet(a, b, c);

//   where a, b, c can be "1", "2", "add", respectively.

//   For the following API method:
//     POST /
//     host: ...
//     Content-Type: application/json
//
//     { "a": 1, "b": 2, "op": "+" }
// you can call invoke it by calling the rootPost method of the SDK as follows:
Input body = new Input();
```

```
input.a=1;
input.b=2;
input.op="+";
Result output = client.rootPost(body);

//      where the Input class of the SDK corresponds to the Input model of the API.

// Parse the result:
//      If the 'Result' object is { "a": 1, "b": 2, "op": "add", "c":3}, you
// retrieve the result 'c') as

String result=output.c;
```

8. To use an Amazon Cognito credentials provider to authorize calls to your API, use the `ApiClientFactory` class to pass a set of AWS credentials by using the SDK generated by API Gateway, as shown in the following example.

```
// Use CognitoCachingCredentialsProvider to provide AWS credentials
// for the ApiClientFactory
AWSCredentialsProvider credentialsProvider = new CognitoCachingCredentialsProvider(
    context,           // activity context
    "identityPoolId", // Cognito identity pool id
    Regions.US_EAST_1 // region of Cognito identity pool
);

ApiClientFactory factory = new ApiClientFactory()
    .credentialsProvider(credentialsProvider);
```

9. To set an API key by using the API Gateway- generated SDK, use code similar to the following.

```
ApiClientFactory factory = new ApiClientFactory()
    .apiKey("YOUR_API_KEY");
```

Use a JavaScript SDK generated by API Gateway for a REST API

The following procedure shows how to use a JavaScript SDK generated by API Gateway.

Note

These instructions assume you have already completed the instructions in [Generate SDKs for REST APIs in API Gateway](#).

Important

If your API only has ANY methods defined, the generated SDK package will not contain an `apigClient.js` file, and you will need to define the ANY methods yourself.

To install, initiate and call a JavaScript SDK generated by API Gateway for a REST API

1. Extract the contents of the API Gateway-generated .zip file you downloaded earlier.
2. Enable cross-origin resource sharing (CORS) for all of the methods the SDK generated by API Gateway will call. For instructions, see [CORS for REST APIs in API Gateway](#).
3. In your web page, include references to the following scripts.

```
<script type="text/javascript" src="lib/axios/dist/axios.standalone.js"></script>
<script type="text/javascript" src="lib/CryptoJS/rollups/hmac-sha256.js"></script>
<script type="text/javascript" src="lib/CryptoJS/rollups/sha256.js"></script>
<script type="text/javascript" src="lib/CryptoJS/components/hmac.js"></script>
<script type="text/javascript" src="lib/CryptoJS/components/enc-base64.js"></script>
<script type="text/javascript" src="lib/url-template/url-template.js"></script>
<script type="text/javascript" src="lib/apiGatewayCore/sigV4Client.js"></script>
<script type="text/javascript" src="lib/apiGatewayCore/apiGatewayClient.js"></script>
<script type="text/javascript" src="lib/apiGatewayCore/simpleHttpClient.js"></script>
<script type="text/javascript" src="lib/apiGatewayCore/utils.js"></script>
<script type="text/javascript" src="apigClient.js"></script>
```

4. In your code, initialize the SDK generated by API Gateway by using code similar to the following.

```
var apigClient = apigClientFactory.newClient();
```

To initialize the SDK generated by API Gateway with AWS credentials, use code similar to the following. If you use AWS credentials, all requests to the API will be signed.

```
var apigClient = apigClientFactory.newClient({  
    accessKey: 'ACCESS_KEY',  
    secretKey: 'SECRET_KEY',  
});
```

To use an API key with the SDK generated by API Gateway, pass the API key as a parameter to the Factory object by using code similar to the following. If you use an API key, it is specified as part of the x-api-key header and all requests to the API will be signed. This means you must set the appropriate CORS Accept headers for each request.

```
var apigClient = apigClientFactory.newClient({  
    apiKey: 'API_KEY'  
});
```

5. Call the API methods in API Gateway by using code similar to the following. Each call returns a promise with a success and failure callbacks.

```
var params = {  
    // This is where any modeled request parameters should be added.  
    // The key is the parameter name, as it is defined in the API in API Gateway.  
    param0: '',  
    param1: ''  
};  
  
var body = {  
    // This is where you define the body of the request,  
};  
  
var additionalParams = {  
    // If there are any unmodeled query parameters or headers that must be  
    // sent with the request, add them here.  
    headers: {  
        param0: '',  
        param1: ''  
    }  
};
```

```
},
queryParams: {
  param0: '',
  param1: ''
}
};

apigClient.methodName(params, body, additionalParams)
  .then(function(result){
    // Add success callback code here.
  }).catch( function(result){
    // Add error callback code here.
  });

```

Here, the *methodName* is constructed from the method request's resource path and the HTTP verb. For the SimpleCalc API, the SDK methods for the API methods of

1. GET /?a=...&b=...&op=...
2. POST /
 { "a": ..., "b": ..., "op": ... }
3. GET /{a}/{b}/{op}

the corresponding SDK methods are as follows:

1. rootGet(params); // where params={"a": ..., "b": ..., "op": ...} is resolved to the query parameters
2. rootPost(null, body); // where body={"a": ..., "b": ..., "op": ...}
3. aB0pGet(params); // where params={"a": ..., "b": ..., "op": ...} is resolved to the path parameters

Use a Ruby SDK generated by API Gateway for a REST API


The following procedure shows how to use a Ruby SDK generated by API Gateway.

Note

These instructions assume you already completed the instructions in [Generate SDKs for REST APIs in API Gateway](#).

To install, instantiate, and call a Ruby SDK generated by API Gateway for a REST API

1. Unzip the downloaded Ruby SDK file. The generated SDK source is shown as follows.



2. Build a Ruby Gem from the generated SDK source, using the following shell commands in a terminal window:

```
# change to /simplecalc-sdk directory
cd simplecalc-sdk

# build the generated gem
gem build simplecalc-sdk.gemspec
```

After this, **simplecalc-sdk-1.0.0.gem** becomes available.

3. Install the gem:

```
gem install simplecalc-sdk-1.0.0.gem
```

4. Create a client application. Instantiate and initialize the Ruby SDK client in the app:

```
require 'simplecalc-sdk'
client = SimpleCalc::Client.new()
```

```
    http_wire_trace: true,  
    retry_limit: 5,  
    http_read_timeout: 50  
)
```

If the API has authorization of the AWS_IAM type is configured, you can include the caller's AWS credentials by supplying `accessKey` and `secretKey` during the initialization:

```
require 'pet-sdk'  
client = Pet::Client.new(  
    http_wire_trace: true,  
    retry_limit: 5,  
    http_read_timeout: 50,  
    access_key_id: 'ACCESS_KEY',  
    secret_access_key: 'SECRET_KEY'  
)
```

5. Make API calls through the SDK in the app.

Tip

If you are not familiar with the SDK method call conventions, you can review the `client.rb` file in the generated SDK `lib` folder. The folder contains documentation of each supported API method call.

To discover supported operations:

```
# to show supported operations:  
puts client.operation_names
```

This results in the following display, corresponding to the API methods of GET `/?` `a={.}&b={.}&op={.}`, GET `/{{a}}/{{b}}/{{op}}`, and POST `/`, plus a payload of the `{a:"...", b:"...", op:"..."}` format, respectively:

```
[:get_api_root, :get_ab_op, :post_api_root]
```

To invoke the GET `/?a=1&b=2&op=+` API method, call the following the Ruby SDK method:

```
resp = client.get_api_root({a:"1", b:"2", op:"+"})
```

To invoke the POST / API method with a payload of {a: "1", b: "2", "op": "+"}, call the following Ruby SDK method:

```
resp = client.post_api_root(input: {a:"1", b:"2", op:"+"})
```

To invoke the GET /1/2/+ API method, call the following Ruby SDK method:

```
resp = client.get_ab_op({a:"1", b:"2", op:"+"})
```

The successful SDK method calls return the following response:

```
resp : {
    result: {
        input: {
            a: 1,
            b: 2,
            op: "+"
        },
        output: {
            c: 3
        }
    }
}
```

Use iOS SDK generated by API Gateway for a REST API in Objective-C or Swift

In this tutorial, we will show how to use an iOS SDK generated by API Gateway for a REST API in an Objective-C or Swift app to call the underlying API. We will use the [SimpleCalc API](#) as an example to illustrate the following topics:

- How to install the required AWS Mobile SDK components into your Xcode project
- How to create the API client object before calling the API's methods
- How to call the API methods through the corresponding SDK methods on the API client object
- How to prepare a method input and parse its result using the corresponding model classes of the SDK

Topics

- [Use generated iOS SDK \(Objective-C\) to call API](#)
- [Use generated iOS SDK \(Swift\) to call API](#)

Use generated iOS SDK (Objective-C) to call API


Before beginning the following procedure, you must complete the steps in [Generate SDKs for REST APIs in API Gateway](#) for iOS in Objective-C and download the .zip file of the generated SDK.

Install the AWS mobile SDK and an iOS SDK generated by API Gateway in an Objective-C project

The following procedure describes how to install the SDK.

To install and use an iOS SDK generated by API Gateway in Objective-C

1. Extract the contents of the API Gateway-generated .zip file you downloaded earlier. Using the [SimpleCalc API](#), you may want to rename the unzipped SDK folder to something like **sdk_objc_simple_calc**. In this SDK folder there is a README.md file and a Podfile file. The README.md file contains the instructions to install and use the SDK. This tutorial provides details about these instructions. The installation leverages [CocoaPods](#) to import required API Gateway libraries and other dependent AWS Mobile SDK components. You must update the Podfile to import the SDKs into your app's Xcode project. The unarchived SDK folder also contains a generated-src folder that contains the source code of the generated SDK of your API.
2. Launch Xcode and create a new iOS Objective-C project. Make a note of the project's target. You will need to set it in the Podfile.



3. To import the AWS Mobile SDK for iOS into the Xcode project by using CocoaPods, do the following:

- a. Install CocoaPods by running the following command in a terminal window:

```
sudo gem install cocoapods  
pod setup
```

- b. Copy the Podfile file from the extracted SDK folder into the same directory containing your Xcode project file. Replace the following block:

```
target '<YourXcodeTarget>' do  
    pod 'AWSAPIGateway', '~> 2.4.7'  
end
```

with your project's target name:

```
target 'app_objc_simple_calc' do  
    pod 'AWSAPIGateway', '~> 2.4.7'  
end
```

If your Xcode project already contains a file named Podfile, add the following line of code to it:

```
pod 'AWSAPIGateway', '~> 2.4.7'
```

- c. Open a terminal window and run the following command:

```
pod install
```

This installs the API Gateway component and other dependent AWS Mobile SDK components.

- d. Close the Xcode project and then open the .xcworkspace file to relaunch Xcode.
 - e. Add all of the .h and .m files from the extracted SDK's generated-src directory into your Xcode project.

The screenshot shows the Xcode interface with the project navigation bar at the top. Below it, the project structure is displayed in a tree view. A red circle highlights the 'app_objc_simple_calc' folder, which contains several Objective-C files: SIMPLE_CALCInput.h, SIMPLE_CALCInput.m, SIMPLE_CALCOutput.h, SIMPLE_CALCOutput.m, SIMPLE_CALCResult.h, SIMPLE_CALCResult.m, SIMPLE_CALCSimpleCalcClient.h, and SIMPLE_CALCSimpleCalcClient.m. The SIMPLE_CALCSimpleCalcClient.m file is selected and its code is shown in the main editor area. The code is a standard Objective-C class definition for an AWS API gateway client, including imports for various AWS headers and an interface for the AWSAPIGatewayClient.

```

1 /*
2 Copyright 2010-2016 Amazon.com, Inc. or its affiliates. All Rights
3 Reserved.
4
5 Licensed under the Apache License, Version 2.0 (the "License").
6 You may not use this file except in compliance with the License.
7 A copy of the License is located at
8
9 http://aws.amazon.com/apache2.0
10
11 or in the "license" file accompanying this file. This file is distributed
12 on an "AS IS" BASIS, WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either
13 express or implied. See the License for the specific language governing
14 permissions and limitations under the License.
15 */
16
17 #import "SIMPLE_CALCSimpleCalcClient.h"
18 #import <AWSCore/AWSCore.h>
19 #import <AWSCore/AWSSignature.h>
20 #import <AWSCore/AWSynchronizedMutableDictionary.h>
21
22 #import "SIMPLE_CALCResult.h"
23 #import "SIMPLE_CALCInput.h"
24
25 @interface AWSAPIGatewayClient()
26
27 // Networking
28 @property (nonatomic, strong) NSURLSession *session;
29
30 // For requests
31 @property (nonatomic, strong) NSURL *baseURL;
32
33 // For responses
34 @property (nonatomic, strong) NSDictionary *HTTPHeaderFields;
35 @property (nonatomic, assign) NSInteger HTTPStatusCode;
36
37 - (AWSTask *)invokeHTTPRequest:(NSString *)HTTPMethod

```

To import the AWS Mobile SDK for iOS Objective-C into your project by explicitly downloading AWS Mobile SDK or using [Carthage](#), follow the instructions in the *README.md* file. Be sure to use only one of these options to import the AWS Mobile SDK.

Call API methods using the iOS SDK generated by API Gateway in an Objective-C project

When you generated the SDK with the prefix of SIMPLE_CALC for this [SimpleCalc API](#) with two models for input (Input) and output (Result) of the methods, in the SDK, the resulting API client class becomes SIMPLE_CALCSimpleCalcClient and the corresponding data classes are SIMPLE_CALCInput and SIMPLE_CALCResult, respectively. The API requests and responses are mapped to the SDK methods as follows:

- The API request of

```
GET /?a=...&b=...&op=...
```

becomes the SDK method of

```
(AWSTask *)rootGet:(NSString *)op a:(NSString *)a b:(NSString *)b
```

The AWSTask.result property is of the SIMPLE_CALCResult type if the Result model was added to the method response. Otherwise, the property is of the NSDictionary type.

- This API request of

```
POST /  
  
{  
    "a": "Number",  
    "b": "Number",  
    "op": "String"  
}
```

becomes the SDK method of

```
(AWSTask *)rootPost:(SIMPLE_CALCInput *)body
```

- The API request of

```
GET /{a}/{b}/{op}
```

becomes the SDK method of

```
(AWSTask *)aB0pGet:(NSString *)a b:(NSString *)b op:(NSString *)op
```

The following procedure describes how to call the API methods in Objective-C app source code; for example, as part of the viewDidLoad delegate in a ViewController.m file.

To call the API through the iOS SDK generated by API Gateway

1. Import the API client class header file to make the API client class callable in the app:

```
#import "SIMPLE_CALCSimpleCalc.h"
```

The #import statement also imports SIMPLE_CALCInput.h and SIMPLE_CALCResult.h for the two model classes.

2. Instantiate the API client class:

```
SIMPLE_CALCSimpleCalcClient *apiInstance = [SIMPLE_CALCSimpleCalcClient  
defaultClient];
```

To use Amazon Cognito with the API, set the `defaultServiceConfiguration` property on the `defaultAWSServiceManager` object, as shown in the following, before calling the `defaultClient` method to create the API client object (shown in the preceding example):

```
AWSCognitoCredentialsProvider *creds = [[AWSCognitoCredentialsProvider alloc]  
initWithRegionType:AWSRegionUSEast1 identityPoolId:your_cognito_pool_id];  
AWSServiceConfiguration *configuration = [[AWSServiceConfiguration alloc]  
initWithRegion:AWSRegionUSEast1 credentialsProvider:creds];  
AWSServiceManager.defaultServiceManager.defaultServiceConfiguration =  
configuration;
```

3. Call the GET /?a=1&b=2&op=+ method to perform 1+2:

```
[[apiInstance rootGet: @"" a:@"1" b:@"2"] continueWithBlock:^id _Nullable(AWSTask  
* _Nonnull task) {  
    _textField1.text = [self handleApiResponse:task];  
    return nil;  
}];
```

where the helper function `handleApiResponse:task` formats the result as a string to be displayed in a text field (`_textField1`).

```
- (NSString *)handleApiResponse:(AWSTask *)task {  
    if (task.error != nil) {  
        return [NSString stringWithFormat: @"Error: %@", task.error.description];  
    } else if (task.result != nil && [task.result isKindOfClass:[SIMPLE_CALCResult  
class]]) {  
        return [NSString stringWithFormat:@"%@ %@ %@ = %@", task.result.input.a,  
task.result.input.op, task.result.input.b, task.result.output.c];  
    }  
    return nil;  
}
```

The resulting display is 1 + 2 = 3.

4. Call the POST / with a payload to perform 1-2:

```
SIMPLE_CALCInput *input = [[SIMPLE_CALCInput alloc] init];
    input.a = [NSNumber numberWithInt:1];
    input.b = [NSNumber numberWithInt:2];
    input.op = @"-";
    [[apiInstance rootPost:input] continueWithBlock:^id _Nullable(AWSTask *
_Nonnull task) {
        _textField2.text = [self handleApiResponse:task];
        return nil;
    }];
}
```

The resulting display is $1 - 2 = -1$.

5. Call the GET `/{a}/{b}/{op}` to perform 1/2:

```
[[apiInstance aB0pGet:@"1" b:@"2" op:@"div"] continueWithBlock:^id
_Nullable(AWSTask * _Nonnull task) {
    _textField3.text = [self handleApiResponse:task];
    return nil;
}];
```

The resulting display is $1 \text{ div } 2 = 0.5$. Here, `div` is used in place of `/` because the [simple Lambda function](#) in the backend does not handle URL encoded path variables.

Use generated iOS SDK (Swift) to call API

Before beginning the following procedure, you must complete the steps in [Generate SDKs for REST APIs in API Gateway](#) for iOS in Swift and download the .zip file of the generated SDK.

Topics


- [Install AWS mobile SDK and API Gateway-generated SDK in a Swift project](#)
- [Call API methods through the iOS SDK generated by API Gateway in a Swift project](#)

Install AWS mobile SDK and API Gateway-generated SDK in a Swift project

The following procedure describes how to install the SDK.

To install and use an iOS SDK generated by API Gateway in Swift

1. Extract the contents of the API Gateway-generated .zip file you downloaded earlier. Using the [SimpleCalc API](#), you may want to rename the unzipped SDK folder to something like **sdk_swift_simple_calc**. In this SDK folder there is a README.md file and a Podfile file. The README.md file contains the instructions to install and use the SDK. This tutorial provides details about these instructions. The installation leverages [CocoaPods](#) to import required AWS Mobile SDK components. You must update the Podfile to import the SDKs into your Swift app's Xcode project. The unarchived SDK folder also contains a generated-src folder that contains the source code of the generated SDK of your API.
2. Launch Xcode and create a new iOS Swift project. Make a note of the project's target. You will need to set it in the Podfile.



3. To import the required AWS Mobile SDK components into the Xcode project by using CocoaPods, do the following:
 - a. If it is not installed, install CocoaPods by running the following command in a terminal window:

```
sudo gem install cocoapods
pod setup
```
 - b. Copy the Podfile file from the extracted SDK folder into the same directory containing your Xcode project file. Replace the following block:

```
target '<YourXcodeTarget>' do
```

```
pod 'AWSAPIGateway', '~> 2.4.7'  
end
```

with your project's target name as shown:

```
target 'app_swift_simple_calc' do  
    pod 'AWSAPIGateway', '~> 2.4.7'  
end
```

If your Xcode project already contains a Podfile with the correct target, you can simply add the following line of code to the do ... end loop:


```
pod 'AWSAPIGateway', '~> 2.4.7'
```

- c. Open a terminal window and run the following command in the app directory:

```
pod install
```

This installs the API Gateway component and any dependent AWS Mobile SDK components into the app's project.

- d. Close the Xcode project and then open the *.xcworkspace file to relaunch Xcode.
- e. Add all of the SDK's header files (.h) and Swift source code files (.swift) from the extracted generated-src directory to your Xcode project.




The screenshot shows the Xcode interface with the project 'app_swift_simple_calc' open. On the left, the file structure is visible, including files like AWSApiGatewayBridge.h, Bridging_Header.h, SIMPLE_CALCInput.swift, SIMPLE_CALCOutput.swift, SIMPLE_CALCResult.swift, and SIMPLE_CAL...alcClient.swift. A red circle highlights the 'Bridging_Header.h' file. On the right, the code editor displays the contents of the SIMPLE_CALCSimpleCalcClient.swift file, which includes imports for AWSCore and AWSAPIGateway, and defines a class SIMPLE_CALCSimpleCalcClient that inherits from AWSAPIGatewayClient. The code also includes comments about service clients and default tokens.

```

/*
Copyright 2010-2016 Amazon.com, Inc. or its affiliates. All Rights Reserved.
Licensed under the Apache License, Version 2.0 (the "License").
You may not use this file except in compliance with the License.
A copy of the License is located at
http://aws.amazon.com/apache2.0
or in the "license" file accompanying this file. This file is distributed
on an "AS IS" BASIS, WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either
express or implied. See the License for the specific language governing
permissions and limitations under the License.
*/
import AWSCore
import AWSAPIGateway
public class SIMPLE_CALCSimpleCalcClient: AWSAPIGatewayClient {
    private static let _serviceClients = AWSSynchronizedMutableDictionary()
    private static var token: dispatch_once_t = 0
    private static var _defaultClient:SIMPLE_CALCSimpleCalcClient?
    /**
     Returns the singleton service client. If the singleton object does not exist, the SDK
     instantiates the default service client with 'defaultServiceConfiguration' from
     'AWSServiceManager.defaultServiceManager()'. The reference to this object is
     maintained by the SDK, and you do not need to retain it manually.
     If you want to enable AWS Signature, set the default service configuration in 'func
     application(application: UIApplication, didFinishLaunchingWithOptions'

```

- To enable calling the Objective-C libraries of the AWS Mobile SDK from your Swift code project, set the **Bridging_Header.h** file path on the **Objective-C Bridging Header** property under the **Swift Compiler - General** setting of your Xcode project configuration:




Tip

You can type **bridging** in the search box of Xcode to locate the **Objective-C Bridging Header** property.

- Build the Xcode project to verify that it is properly configured before proceeding further. If your Xcode uses a more recent version of Swift than the one supported for the AWS

Mobile SDK, you will get Swift compiler errors. In this case, set the **Use Legacy Swift Language Version** property to **Yes** under the **Swift Compiler - Version** setting:



To import the AWS Mobile SDK for iOS in Swift into your project by explicitly downloading the AWS Mobile SDK or using [Carthage](#), follow the instructions in the README.md file that comes with the SDK package. Be sure to use only one of these options to import the AWS Mobile SDK.

Call API methods through the iOS SDK generated by API Gateway in a Swift project

When you generated the SDK with the prefix of SIMPLE_CALC for this [SimpleCalc API](#) with two models to describe the input (Input) and output (Result) of the API's requests and responses, in the SDK, the resulting API client class becomes SIMPLE_CALCSimpleCalcClient and the corresponding data classes are SIMPLE_CALCInput and SIMPLE_CALCResult, respectively. The API requests and responses are mapped to the SDK methods as follows:

- The API request of

```
GET /?a=...&b=...&op=...
```

becomes the SDK method of

```
public func rootGet(op: String?, a: String?, b: String?) -> AWSTask
```

The AWSTask.result property is of the SIMPLE_CALCResult type if the Result model was added to the method response. Otherwise, it is of the NSDictionary type.

- This API request of

```
POST /  
  
{  
  "a": "Number",  
  "b": "Number",  
  "op": "String"  
}
```

becomes the SDK method of

```
public func rootPost(body: SIMPLE_CALCInput) -> AWSTask
```

- The API request of

```
GET /{a}/{b}/{op}
```

becomes the SDK method of

```
public func aB0pGet(a: String, b: String, op: String) -> AWSTask
```

The following procedure describes how to call the API methods in Swift app source code; for example, as part of the `viewDidLoad()` delegate in a `ViewController.m` file.

To call the API through the iOS SDK generated by API Gateway

1. Instantiate the API client class:

```
let client = SIMPLE_CALCSimpleCalcClient.default()
```

To use Amazon Cognito with the API, set a default AWS service configuration (shown following) before getting the default method (shown previously):

```
let credentialsProvider =  
  AWS Cognito Credentials Provider(regionType: AWSRegionType.USEast1, identityPoolId:  
  "my_pool_id")  
let configuration = AWS Service Configuration(region: AWSRegionType.USEast1,  
  credentialsProvider: credentialsProvider)
```

```
AWSServiceManager.defaultServiceManager().defaultServiceConfiguration =  
configuration
```

2. Call the GET /?a=1&b=2&op=+ method to perform 1+2:

```
client.rootGet("+", a: "1", b:"2").continueWithBlock {(task: AWSTask) -> AnyObject?  
in  
    self.showResult(task)  
    return nil  
}
```

where the helper function `self.showResult(task)` prints the result or error to the console; for example:

```
func showResult(task: AWSTask) {  
    if let error = task.error {  
        print("Error: \(error)")  
    } else if let result = task.result {  
        if result is SIMPLE_CALCResult {  
            let res = result as! SIMPLE_CALCResult  
            print(String(format:@"%@ %@ %@ = %@", res.input!.a!, res.input!.op!,  
res.input!.b!, res.output!.c!))  
        } else if result is NSDictionary {  
            let res = result as! NSDictionary  
            print("NSDictionary: \(res)")  
        }  
    }  
}
```

In a production app, you can display the result or error in a text field. The resulting display is $1 + 2 = 3$.

3. Call the POST / with a payload to perform 1-2:

```
let body = SIMPLE_CALCInput()  
body.a=1  
body.b=2  
body.op="-"  
client.rootPost(body).continueWithBlock {(task: AWSTask) -> AnyObject? in  
    self.showResult(task)  
    return nil  
}
```

The resultant display is $1 - 2 = -1$.

4. Call the GET `/{a}/{b}/{op}` to perform $1/2$:

```
client.aB0pGet("1", b:"2", op:"div").continueWithBlock {(task: AWSTask) ->
    AnyObject? in
    self.showResult(task)
    return nil
}
```

The resulting display is $1 \text{ div } 2 = 0.5$. Here, `div` is used in place of `/` because the [simple Lambda function](#) in the backend does not handle URL encoded path variables.

Develop REST APIs using OpenAPI in API Gateway

You can use API Gateway to import a REST API from an external definition file into API Gateway. Currently, API Gateway supports [OpenAPI v2.0](#) and [OpenAPI v3.0](#) definition files, with exceptions listed in [Amazon API Gateway important notes for REST APIs](#). You can update an API by overwriting it with a new definition, or you can merge a definition with an existing API. You specify the options by using a mode query parameter in the request URL.

For a tutorial on using the Import API feature from the API Gateway console, see [Tutorial: Create a REST API by importing an example](#).

Topics

- [Import an edge-optimized API into API Gateway](#)
- [Import a Regional API into API Gateway](#)
- [Import an OpenAPI file to update an existing API definition](#)
- [Set the OpenAPI basePath property](#)
- [AWS variables for OpenAPI import](#)
- [Errors and warnings from importing your API into API Gateway](#)
- [Export a REST API from API Gateway](#)

Import an edge-optimized API into API Gateway

You can import an API's OpenAPI definition file to create a new edge-optimized API by specifying the EDGE endpoint type as an additional input, besides the OpenAPI file, to the import operation. You can do so using the API Gateway console, AWS CLI, or an AWS SDK.

For a tutorial on using the Import API feature from the API Gateway console, see [Tutorial: Create a REST API by importing an example](#).

Topics

- [Import an edge-optimized API using the API Gateway console](#)
- [Import an edge-optimized API using the AWS CLI](#)

Import an edge-optimized API using the API Gateway console

To import an edge-optimized API using the API Gateway console, do the following:

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose **Create API**.
3. Under **REST API**, choose **Import**.
4. Copy an API's OpenAPI definition and paste it into the code editor, or choose **Choose file** to load an OpenAPI file from a local drive.
5. For **API endpoint type**, select **Edge-optimized**.
6. Choose **Create API** to start importing the OpenAPI definitions.

Import an edge-optimized API using the AWS CLI

The following [import-rest-api](#) command imports an API from an OpenAPI definition file to create a new edge-optimized API:

```
aws apigateway import-rest-api \
  --fail-on-warnings \
  --body 'file://path/to/API_OpenAPI_template.json'
```

or with an explicit specification of the endpointConfigurationTypes query string parameter to EDGE:

```
aws apigateway import-rest-api \
```

```
--parameters endpointConfigurationTypes=EDGE \
--fail-on-warnings \
--body 'file://path/to/API_OpenAPI_template.json'
```

Import a Regional API into API Gateway

When importing an API, you can choose the regional endpoint configuration for the API. You can use the API Gateway console, the AWS CLI, or an AWS SDK.

When you export an API, the API endpoint configuration is not included in the exported API definitions.

For a tutorial on using the Import API feature from the API Gateway console, see [Tutorial: Create a REST API by importing an example](#).

Topics

- [Import a regional API using the API Gateway console](#)
- [Import a regional API using the AWS CLI](#)

Import a regional API using the API Gateway console

To import an API of a regional endpoint using the API Gateway console, do the following:

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose **Create API**.
3. Under **REST API**, choose **Import**.
4. Copy an API's OpenAPI definition and paste it into the code editor, or choose **Choose file** to load an OpenAPI file from a local drive.
5. For **API endpoint type**, select **Regional**.
6. Choose **Create API** to start importing the OpenAPI definitions.

Import a regional API using the AWS CLI

The following [import-rest-api](#) command imports an OpenAPI definition file and sets the endpoint type to Regional:

```
aws apigateway import-rest-api \
```

```
--parameters endpointConfigurationTypes=REGIONAL \
--fail-on-warnings \
--body 'file://path/to/API_OpenAPI_template.json'
```

Import an OpenAPI file to update an existing API definition

You can import API definitions only to update an existing API, without changing its endpoint configuration, as well as stages and stage variables, or references to API keys.

The import-to-update operation can occur in two modes: merge or overwrite.

When an API (A) is merged into another (B), the resulting API retains the definitions of both A and B if the two APIs do not share any conflicting definitions. When conflicts arise, the method definitions of the merging API (A) overrides the corresponding method definitions of the merged API (B). For example, suppose B has declared the following methods to return 200 and 206 responses:

```
GET /a
POST /a
```

and A declares the following method to return 200 and 400 responses:

```
GET /a
```

When A is merged into B, the resulting API yields the following methods:

```
GET /a
```

which returns 200 and 400 responses, and

```
POST /a
```

which returns 200 and 206 responses.

Merging an API is useful when you have decomposed your external API definitions into multiple, smaller parts and only want to apply changes from one of those parts at a time. For example, this might occur if multiple teams are responsible for different parts of an API and have changes available at different rates. In this mode, items from the existing API that aren't specifically defined in the imported definition are left alone.

When an API (A) overwrites another API (B), the resulting API takes the definitions of the overwriting API (A). Overwriting an API is useful when an external API definition contains the complete definition of an API. In this mode, items from an existing API that aren't specifically defined in the imported definition are deleted.

To merge an API, submit a PUT request to `https://apigateway.<region>.amazonaws.com/restapis/<restapi_id>?mode=merge`. The `restapi_id` path parameter value specifies the API to which the supplied API definition will be merged.

The following code snippet shows an example of the PUT request to merge an OpenAPI API definition in JSON, as the payload, with the specified API already in API Gateway.

```
PUT /restapis/<restapi_id>?mode=merge
Host:apigateway.<region>.amazonaws.com
Content-Type: application/json
Content-Length: ...
```

[An OpenAPI API definition in JSON](#)

The merging update operation takes two complete API definitions and merges them together. For a small and incremental change, you can use the [resource update](#) operation.

To overwrite an API, submit a PUT request to `https://apigateway.<region>.amazonaws.com/restapis/<restapi_id>?mode=overwrite`. The `restapi_id` path parameter specifies the API that will be overwritten with the supplied API definitions.

The following code snippet shows an example of an overwriting request with the payload of a JSON-formatted OpenAPI definition:

```
PUT /restapis/<restapi_id>?mode=overwrite
Host:apigateway.<region>.amazonaws.com
Content-Type: application/json
Content-Length: ...
```

[An OpenAPI API definition in JSON](#)

When the mode query parameter isn't specified, merge is assumed.

Note

The PUT operations are idempotent, but not atomic. That means if a system error occurs part way through processing, the API can end up in a bad state. However, repeating the operation successfully puts the API into the same final state as if the first operation had succeeded.

Set the OpenAPI basePath property

In [OpenAPI 2.0](#), you can use the basePath property to provide one or more path parts that precede each path defined in the paths property. Because API Gateway has several ways to express a resource's path, the Import API feature provides the following options for interpreting the basePath property during import: ignore, prepend, and split.

In [OpenAPI 3.0](#), basePath is no longer a top-level property. Instead, API Gateway uses a [server variable](#) as a convention. The Import API feature provides the same options for interpreting the base path during import. The base path is identified as follows:

- If the API doesn't contain any basePath variables, the Import API feature checks the server.url string to see if it contains a path beyond "/". If it does, that path is used as the base path.
- If the API contains only one basePath variable, the Import API feature uses it as the base path, even if it's not referenced in the server.url.
- If the API contains multiple basePath variables, the Import API feature uses only the first one as the base path.

Ignore

If the OpenAPI file has a basePath value of /a/b/c and the paths property contains /e and /f, the following POST or PUT request:

```
POST /restapis?mode=import&basepath=ignore
```

```
PUT /restapis/api_id?basepath=ignore
```

results in the following resources in the API:

- /
- /e
- /f

The effect is to treat the basePath as if it was not present, and all of the declared API resources are served relative to the host. This can be used, for example, when you have a custom domain name with an API mapping that doesn't include a *Base Path* and a *Stage* value that refers to your production stage.

 **Note**

API Gateway automatically creates a root resource for you, even if it isn't explicitly declared in your definition file.

When unspecified, basePath takes ignore by default.

Prepend

If the OpenAPI file has a basePath value of /a/b/c and the paths property contains /e and /f, the following POST or PUT request:

```
POST /restapis?mode=import&basepath=prepend
```

```
PUT /restapis/api_id?basepath=prepend
```

results in the following resources in the API:

- /
- /a
- /a/b

- /a/b/c
- /a/b/c/e
- /a/b/c/f

The effect is to treat the `basePath` as specifying additional resources (without methods) and to add them to the declared resource set. This can be used, for example, when different teams are responsible for different parts of an API and the `basePath` could reference the path location for each team's API part.

 **Note**

API Gateway automatically creates intermediate resources for you, even if they aren't explicitly declared in your definition.

Split

If the OpenAPI file has a `basePath` value of `/a/b/c` and the `paths` property contains `/e` and `/f`, the following POST or PUT request:

```
POST /restapis?mode=import&basepath=split
```

```
PUT /restapis/api_id?basepath=split
```

results in the following resources in the API:

- /
- /b
- /b/c
- /b/c/e
- /b/c/f

The effect is to treat top-most path part, `/a`, as the beginning of each resource's path, and to create additional (no method) resources within the API itself. This could, for example, be used when `a` is a stage name that you want to expose as part of your API.

AWS variables for OpenAPI import

You can use the following AWS variables in OpenAPI definitions. API Gateway resolves the variables when the API is imported. To specify a variable, use `$(variable-name)`. The following table describes the available AWS variables.

Variable name	Description
<code>AWS::AccountId</code>	The AWS account ID that imports the API. For example, 123456789012.
<code>AWS::Partition</code>	The AWS partition in which the API is imported. For standard AWS Regions, the partition is aws.
<code>AWS::Region</code>	The AWS Region in which the API is imported. For example, us-east-2 .

AWS variables example

The following example uses AWS variables to specify an AWS Lambda function for an integration.

OpenAPI 3.0

```
openapi: "3.0.1"
info:
  title: "tasks-api"
  version: "v1.0"
paths:
  /:
    get:
      summary: List tasks
      description: Returns a list of tasks
      responses:
        200:
          description: "OK"
          content:
```

```
application/json:  
  schema:  
    type: array  
    items:  
      $ref: "#/components/schemas/Task"  
  500:  
    description: "Internal Server Error"  
    content: {}  
  x-amazon-apigateway-integration:  
    uri:  
      arn:${AWS::Partition}:apigateway:${AWS::Region}:lambda:path/2015-03-31/  
functions/arn:${AWS::Partition}:lambda:${AWS::Region}:  
${AWS::AccountId}:function:LambdaFunctionName/invocations  
    responses:  
      default:  
        statusCode: "200"  
        passthroughBehavior: "when_no_match"  
        httpMethod: "POST"  
        contentHandling: "CONVERT_TO_TEXT"  
        type: "aws_proxy"  
  components:  
    schemas:  
      Task:  
        type: object  
        properties:  
          id:  
            type: integer  
          name:  
            type: string  
          description:  
            type: string
```

Errors and warnings from importing your API into API Gateway

When you import your external definition file into API Gateway, API Gateway might generate warnings and errors. The following sections discuss the errors and warnings that might occur during import.

Errors during import

During the import, errors can be generated for major issues like an invalid OpenAPI document. Errors are returned as exceptions (for example, `BadRequestException`) in an unsuccessful

response. When an error occurs, the new API definition is discarded and no change is made to the existing API.

Warnings during import

During the import, warnings can be generated for minor issues like a missing model reference. If a warning occurs, the operation will continue if the failonwarnings=false query expression is appended to the request URL. Otherwise, the updates will be rolled back. By default, failonwarnings is set to false. In such cases, warnings are returned as a field in the resulting [RestApi](#) resource. Otherwise, warnings are returned as a message in the exception.

Export a REST API from API Gateway

Once you created and configured a REST API in API Gateway, using the API Gateway console or otherwise, you can export it to an OpenAPI file using the API Gateway Export API, which is part of the Amazon API Gateway Control Service. To use the API Gateway Export API, you need to sign your API requests. For more information about signing requests, see [Signing AWS API requests](#) in the *IAM User Guide*. You have options to include the API Gateway integration extensions, as well as the [Postman](#) extensions, in the exported OpenAPI definition file.

Note

When exporting the API using the AWS CLI, be sure to include the extensions parameter as shown in the following example, to ensure that the x-amazon-apigateway-request-validator extension is included:

```
aws apigateway get-export --parameters extensions='apigateway' --rest-api-id abcdefg123 --stage-name dev --export-type swagger latestswagger2.json
```

You cannot export an API if its payloads are not of the application/json type. If you try, you will get an error response stating that JSON body models are not found.

Request to export a REST API

With the Export API, you export an existing REST API by submitting a GET request, specifying the to-be-exported API as part of URL paths. The request URL is of the following format:

OpenAPI 3.0

```
https://<host>/restapis/<restapi_id>/stages/<stage_name>/exports/oas30
```

OpenAPI 2.0

```
https://<host>/restapis/<restapi_id>/stages/<stage_name>/exports/swagger
```

You can append the `extensions` query string to specify whether to include API Gateway extensions (with the `integration` value) or Postman extensions (with the `postman` value).

In addition, you can set the `Accept` header to `application/json` or `application/yaml` to receive the API definition output in JSON or YAML format, respectively.

For more information about submitting GET requests using the API Gateway Export API, see [GetExport](#).

Note

If you define models in your API, they must be for the content type of "application/json" for API Gateway to export the model. Otherwise, API Gateway throws an exception with the "Only found non-JSON body models for ..." error message.

Models must contain properties or be defined as a particular JSONSchema type.

Download REST API OpenAPI definition in JSON

To export and download a REST API in OpenAPI definitions in JSON format:

OpenAPI 3.0

```
GET /restapis/<restapi_id>/stages/<stage_name>/exports/oas30
Host: apigateway.<region>.amazonaws.com
Accept: application/json
```

OpenAPI 2.0

```
GET /restapis/<restapi_id>/stages/<stage_name>/exports/swagger  
Host: apigateway.<region>.amazonaws.com  
Accept: application/json
```

Here, `<region>` could be, for example, `us-east-1`. For all the regions where API Gateway is available, see [Regions and Endpoints](#).

Download REST API OpenAPI definition in YAML

To export and download a REST API in OpenAPI definitions in YAML format:

OpenAPI 3.0

```
GET /restapis/<restapi_id>/stages/<stage_name>/exports/oas30  
Host: apigateway.<region>.amazonaws.com  
Accept: application/yaml
```

OpenAPI 2.0

```
GET /restapis/<restapi_id>/stages/<stage_name>/exports/swagger  
Host: apigateway.<region>.amazonaws.com  
Accept: application/yaml
```

Download REST API OpenAPI definition with Postman extensions in JSON

To export and download a REST API in OpenAPI definitions with Postman in JSON format:

OpenAPI 3.0

```
GET /restapis/<restapi_id>/stages/<stage_name>/exports/oas30?extensions=postman
Host: apigateway.<region>.amazonaws.com
Accept: application/json
```

OpenAPI 2.0

```
GET /restapis/<restapi_id>/stages/<stage_name>/exports/swagger?extensions=postman
Host: apigateway.<region>.amazonaws.com
Accept: application/json
```

Download REST API OpenAPI definition with API Gateway integration in YAML

To export and download a REST API in OpenAPI definitions with API Gateway integration in YAML format:

OpenAPI 3.0

```
GET /restapis/<restapi_id>/stages/<stage_name>/exports/oas30?extensions=integrations
Host: apigateway.<region>.amazonaws.com
Accept: application/yaml
```


OpenAPI 2.0

```
GET /restapis/<restapi_id>/stages/<stage_name>/exports/swagger?
extensions=integrations
Host: apigateway.<region>.amazonaws.com
Accept: application/yaml
```

Export REST API using the API Gateway console

After [deploying your REST API to a stage](#), you can proceed to export the API in the stage to an OpenAPI file using the API Gateway console.

In the **Stages** pane in the API Gateway console, choose **Stage actions**, **Export**.



Specify an **API specification type**, **Format**, and **Extensions** to download your API's OpenAPI definition.

Publish REST APIs for customers to invoke

Simply creating and developing an API Gateway API doesn't automatically make it callable by your users. To make it callable, you must deploy your API to a stage. In addition, you might want to customize the URL that your users will use to access your API. You can give it a domain that is consistent with your brand or is more memorable than the default URL for your API.

In this section, you can learn how to deploy your API and customize the URL that you provide to users to access it.

Note

To augment the security of your API Gateway APIs, the `execute-api`.

{`region`}.`.amazonaws.com` domain is registered in the [Public Suffix List \(PSL\)](#). For further security, we recommend that you use cookies with a `__Host-` prefix if you ever need to set sensitive cookies in the default domain name for your API Gateway APIs. This practice will help to defend your domain against cross-site request forgery attempts (CSRF). For more information see the [Set-Cookie](#) page in the Mozilla Developer Network.

Topics

- [Deploy REST APIs in API Gateway](#)
- [Custom domain name for public REST APIs in API Gateway](#)

Deploy REST APIs in API Gateway

After creating your API, you must deploy it to make it callable by your users.

To deploy an API, you create an API deployment and associate it with a stage. A stage is a logical reference to a lifecycle state of your API (for example, dev, prod, beta, v2). API stages are identified by the API ID and stage name. They're included in the URL that you use to invoke the API. Each stage is a named reference to a deployment of the API and is made available for client applications to call.

 **Important**

Every time you update an API, you must redeploy the API to an existing stage or to a new stage. Updating an API includes modifying routes, methods, integrations, authorizers, resource policies, and anything else other than stage settings.

As your API evolves, you can continue to deploy it to different stages as different versions of the API. You can also deploy your API updates as a [canary release deployment](#). This enables your API clients to access, on the same stage, the production version through the production release, and the updated version through the canary release.

To call a deployed API, the client submits a request against an API's URL. The URL is determined by an API's protocol (HTTP(S) or (WSS)), hostname, stage name, and (for REST APIs) resource path. The hostname and the stage name determine the API's base URL.

Using the API's default domain name, the base URL of a REST API (for example) in a given stage (`{stageName}`) is in the following format:

```
https://{restapi-id}.execute-api.{region}.amazonaws.com/{stageName}
```

To make the API's default base URL more user-friendly, you can create a custom domain name (for example, `api.example.com`) to replace the default hostname of the API. To support multiple APIs under the custom domain name, you must map an API stage to a base path.

With a custom domain name of `{api.example.com}` and the API stage mapped to a base path of `{basePath}` under the custom domain name, the base URL of a REST API becomes the following:

`https://{api.example.com}/{basePath}`

For each stage, you can optimize API performance by adjusting the default account-level request throttling limits and enabling API caching. You can also enable logging for API calls to CloudTrail or CloudWatch, and can select a client certificate for the backend to authenticate the API requests. In addition, you can override stage-level settings for individual methods and define stage variables to pass stage-specific environment contexts to the API integration at runtime.

Stages enable robust version control of your API. For example, you can deploy an API to a test stage and a prod stage, and use the test stage as a test build and use the prod stage as a stable build. After the updates pass the test, you can promote the test stage to the prod stage. The promotion can be done by redeploying the API to the prod stage or updating a stage variable value from the stage name of test to that of prod.

In this section, we discuss how to deploy an API by using the [API Gateway console](#) or calling the [API Gateway REST API](#). To use other tools, see the documentation of the [AWS CLI](#) or an [AWS SDK](#).

Topics

- [Create a deployment for a REST API in API Gateway](#)
- [Set up a stage for a REST API in API Gateway](#)
- [Set up an API Gateway canary release deployment](#)
- [Updates to REST APIs that require redeployment](#)

Create a deployment for a REST API in API Gateway

In API Gateway, a REST API deployment is represented by a [Deployment](#) resource. It's similar to an executable of an API that is represented by a [RestApi](#) resource.

For the client to call your API, you must create a deployment and associate a stage with it. A stage is represented by a [Stage](#) resource. It represents a snapshot of the API, including methods, integrations, models, mapping templates, and Lambda authorizers (formerly known as custom authorizers). When you update the API, you can redeploy the API by associating a new stage with the existing deployment. We discuss creating a stage in [the section called "Set up a stage"](#).

Topics

- [Create a deployment](#)
- [Next steps for your API deployment](#)

Create a deployment

The following procedures show how to create a deployment for a REST API.

AWS Management Console

You must have created a REST API before deploying it for the first time. For more information, see [Develop REST APIs in API Gateway](#).

The API Gateway console lets you deploy an API by creating a deployment and associating it with a new or existing stage.

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. In the **APIs** navigation pane, choose the API you want to deploy.
3. In the **Resources** pane, choose **Deploy API**.
4. For **Stage**, select from the following:
 - a. To create a new stage, select **New stage**, and then enter a name in **Stage name**. Optionally, you can provide a description for the deployment in **Deployment description**.
 - b. To choose an existing stage, select the stage name from the dropdown menu. You might want to provide a description of the new deployment in **Deployment description**.
 - c. To create a deployment that is not associated with a stage, select **No stage**. Later, you can associate this deployment with a stage.
5. Choose **Deploy**.

AWS CLI

When you create a deployment, you instantiate the [Deployment](#) resource.

The following [create-deployment](#) command creates a new deployment:

```
aws apigateway create-deployment --rest-api-id rest-api-id
```

You can't call the API until you associate this deployment with a stage. With an existing stage, you can do this by updating the stage's [deploymentId](#) property with the newly created deployment ID. The following [update-stage](#) command updates the stage with a new deployment. In the console, this is called the **Active deployment**.

```
aws apigateway update-stage \  
  --rest-api-id rest-api-id \  
  --stage-name 'stage-name' \  
  --patch-operations op='replace',path='/deploymentId',value='deployment-id'
```

When you create your deployment, you can also associate it with a new stage at the same time. The following [create-deployment](#) command creates a new deployment and associates it with a new stage called beta:

```
aws apigateway create-deployment \  
  --rest-api-id rest-api-id \  
  --stage-name beta
```

To redeploy an API, perform the same steps. You can reuse the same stage.

Next steps for your API deployment

The following are next steps for your API deployment.

Modify stage settings

After an API is deployed, you can modify the stage settings to enable or disable the API cache, logging, or request throttling. You can also choose a client certificate for the backend to authenticate API Gateway and set stage variables to pass deployment context to the API integration at runtime. For more information, see [Modify stage settings](#)

After modifying stage settings, you must redeploy the API for the changes to take effect.

Note

If the updated settings, such as enabling logging, requires a new IAM role, you can add the required IAM role without redeploying the API. However, it might take a few minutes

before the new IAM role takes effect. Before that happens, traces of your API calls are not logged even if you have enabled the logging option.

Choose different deployment-stage combinations

Because a deployment represents an API snapshot and a stage defines a path into a snapshot, you can choose different deployment-stage combinations to control how users call into different versions of the API. This is useful, for example, when you want to roll back API state to a previous deployment or to merge a 'private branch' of the API into the public one.

The following procedure shows how to do this using the **Stage Editor** in the API Gateway console. It is assumed that you must have deployed an API more than once.

1. If you're not already on the **Stages** pane, in the main navigation pane, choose **Stages**.
2. Select the stage you want to update.
3. On the **Deployment history** tab, select the deployment you want the stage to use.
4. Choose **Change active deployment**.
5. Confirm you want to change the active deployment and choose **Change active deployment** in the **Make active deployment** dialog box.

Pass deployment-specific data to your API.

For a deployment, you can set or modify stage variables to pass deployment-specific data to the API integration at runtime. You can do this on the **Stage Variables** tab in the **Stage Editor**. For more information, see instructions in [Use stage variables for a REST API in API Gateway](#).

Set up a stage for a REST API in API Gateway

A stage is a named reference to a deployment, which is a snapshot of the API. You use a [Stage](#) to manage and optimize a particular deployment. For example, you can configure stage settings to enable caching, customize request throttling, configure logging, define stage variables, or attach a canary release for testing. The following section shows how to create and configure your stage.

Create a new stage

After the initial deployment, you can add more stages and associate them with existing deployments. You can use the API Gateway console to create a new stage, or you can choose an

existing stage while deploying an API. In general, you can add a new stage to an API deployment before redeploying the API. To create a new stage using the API Gateway console, follow these steps:

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose a REST API.
3. In the main navigation pane, choose **Stages** under an API.
4. From the **Stages** navigation pane, choose **Create stage**.
5. For **Stage name**, enter a name, for example, **prod**.

 **Note**

Stage names can only contain alphanumeric characters, hyphens, and underscores. Maximum length is 128 characters.

6. (Optional). For **Description**, enter a stage description.
7. For **Deployment**, select the date and time of the existing API deployment you want to associate with this stage.
8. Under **Additional settings**, you can specify additional settings for your stage.
9. Choose **Create stage**.

Modify stage settings

After a successful deployment of an API, the stage is populated with default settings. You can use the console or the API Gateway REST API to change the stage settings, including API caching and logging. If you've modified the default endpoint of your REST API, when you update a stage, the modification is propagated to all stages of your API. The following steps show you how to do so using the **Stage editor** of the API Gateway console.

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose a REST API.
3. In the main navigation pane, choose **Stages** under an API.
4. In the **Stages** pane, choose the name of the stage.
5. In the **Stage details** section, choose **Edit**.
6. (Optional) For **Stage description**, edit the description.

7. For Additional settings, you modify the following settings:

Cache settings

To enable API caching for the stage, turn on **Provision API cache**. Then configure the **Default method-level caching**, **Cache capacity**, **Encrypt cache data**, **Cache time-to-live (TTL)**, as well as any requirements for per-key cache invalidation.

Caching is not active until you turn on the default method-level caching or turn on the method-level cache for a specific method.

For more information about cache settings, see [Cache settings for REST APIs in API Gateway](#).

 **Note**

If you enable API caching for an API stage, your AWS account might be charged for API caching. Caching isn't eligible for the AWS Free Tier.

Throttling settings

To set stage-level throttling targets for all of the methods associated with this API, turn on **Throttling**.

For **Rate**, enter a target rate. This is the rate, in requests per second, that tokens are added to the token bucket. The stage-level rate must not be more than the [account-level](#) rate as specified in [Quotas for configuring and running a REST API in API Gateway](#).

For **Burst**, enter a target burst rate. The burst rate, is the capacity of the token bucket. This allows more requests through for a period of time than the target rate. This stage-level burst rate must not be more than the [account-level](#) burst rate as specified in [Quotas for configuring and running a REST API in API Gateway](#).

 **Note**

Throttling rates are not hard limits, and are applied on a best-effort basis. In some cases, clients can exceed the targets that you set. Don't rely on throttling to control

costs or block access to an API. Consider using [AWS Budgets](#) to monitor costs and [AWS WAF](#) to manage API requests.

Firewall and certificate settings

To associate an AWS WAF web ACL with the stage, select a web ACL from the **Web ACL** dropdown list. If desired, choose **Block API Request if WebACL cannot be evaluated (Fail-Close)**.

To select a client certificate for your stage, select a certificate from the **Client certificate** dropdown menu.

8. Choose **Continue**.
9. Review your changes and choose **Save changes**.
10. To enable Amazon CloudWatch Logs for all of the methods associated with this stage of this API Gateway API, in the **Logs and tracing** section, choose **Edit**.

Note

To enable CloudWatch Logs, you must also specify the ARN of an IAM role that enables API Gateway to write information to CloudWatch Logs on behalf of your user. To do so, choose **Settings** from the **APIs** main navigation pane. Then, for **CloudWatch log role**, enter the ARN of an IAM role.

For common application scenarios, the IAM role could attach the managed policy of [AmazonAPIGatewayPushToCloudWatchLogs](#).

The IAM role must also contain the following trust relationship statement:

JSON

```
{  
    "Version": "2012-10-17",  
    "Statement": [  
        {  
            "Sid": "",  
            "Effect": "Allow",  
            "Principal": {  
                "Service": "apigateway.amazonaws.com"  
            },  
            "Action": "logs:PutLogEvents",  
            "Resource": "arn:aws:logs:  
                <region>:  
                <account>/log-group:  
                    <log_group_name>  
            "Condition": {}  
        }  
    ]  
}
```

```
        "Action": "sts:AssumeRole"
    }
}
```

For more information about CloudWatch, see the [Amazon CloudWatch User Guide](#).

11. Select a logging level from the **CloudWatch Logs** dropdown menu. The logging levels are the following:
 - **Off** – Logging is not turned on for this stage.
 - **Errors only** – Logging is enabled for errors only.
 - **Errors and info logs** – Logging is enabled for all events.
12. Select **Data tracing** to have API Gateway report to CloudWatch the data trace logging for your stage. This can be useful to troubleshoot APIs, but can result in logging sensitive data.

 **Note**

We recommend that you don't use **Data tracing** for production APIs.

13. Select **Detailed metrics** to have API Gateway report to CloudWatch the API metrics of API calls, Latency, Integration latency, 400 errors, and 500 errors. For more information about CloudWatch, see the [Basic monitoring and detailed monitoring](#) in the Amazon CloudWatch User Guide.

 **Important**

Your account is charged for accessing method-level CloudWatch metrics, but not the API-level or stage-level metrics.

14. To enable access logging to a destination, turn on **Custom access logging**.
15. For **Access log destination ARN**, enter the ARN of a log group or a Firehose stream.

The ARN format for Firehose is `arn:aws:firehose:{region}:{account-id}:deliverystream/amazon-apigateway-{your-stream-name}`. The name of your Firehose stream must be `amazon-apigateway-{your-stream-name}`.

16. In **Log format**, enter a log format. To learn more about example log formats, see [the section called "CloudWatch log formats for API Gateway"](#).
17. To enable [AWS X-Ray](#) tracing for the API stage, select **X-Ray tracing**. For more information, see [Trace user requests to REST APIs using X-Ray in API Gateway](#).
18. Choose **Save changes**. Redeploy your API for the new settings to take effect.

Override stage-level settings

After you customize the stage-level settings, you can override them for each API method. Some of these options might result in additional charges to your AWS account.

1. To configure method overrides, expand the stage under the secondary navigation pane, and then choose a method.

Stages

[Stage actions ▾](#)[Create stage](#)

The screenshot shows the 'prod' stage configuration for the '/pets' endpoint. The left sidebar lists methods: GET, /pets, GET, OPTIONS, POST, and /{petId}, GET, OPTIONS. The right panel shows 'Method overrides' with a note that the method inherits settings from the 'prod' stage. It also displays the 'Invoke URL' as <https://abcd1234.execute-api.us-west-1.amazonaws.com/prod/pets>.

2. For **Method overrides**, choose **Edit**.
3. To turn on method-level CloudWatch settings, for **CloudWatch Logs**, select a logging level.
4. To turn on data trace logging for your method, select **Data tracing**.

Note

We recommend that you don't use **Data tracing** for production APIs.

5. To turn on method-level detailed metrics, select **Detailed metrics**. Your account is charged for accessing method-level CloudWatch metrics, but not the API-level or stage-level metrics.

6. To turn on method-level throttling, select **Throttling**. Enter the appropriate method-level options. To learn more about throttling, see [the section called "Throttling"](#).
7. To configure the method-level cache, select **Enable method cache**. If you change the default method-level caching setting in the **Stage details**, it doesn't affect this setting.
8. Choose **Save**.

Add an API Gateway REST API as a target for Amazon Bedrock AgentCore Gateway

An Amazon Bedrock AgentCore Gateway provides AI agent developers a secure way to expose your API Gateway REST APIs as Model Context Protocol (MCP)-compatible tools. AgentCore Gateway uses targets to define tools. When you add your stage as a target, your Gateway becomes a single MCP URL that enables access to the tools for an agent. For more information, see [API Gateway REST API stages as targets](#) in the *Amazon Bedrock AgentCore Gateway Developer Guide*.

API Gateway targets connect your AgentCore Gateway to stages of your REST APIs. You can include the entire stage as a target, or select resources. After you create the API Gateway target, AgentCore Gateway translates incoming MCP requests into HTTP requests and handles the response formatting. MCP clients can retrieve API documentation using the tools/list method and invoke APIs using the tools/call method.

Considerations

The following considerations might impact your use adding a stage as a target to a AgentCore Gateway:

- You must already have a AgentCore Gateway.
- Only public REST APIs are supported.
- The default endpoint of your API cannot be disabled.
- Every method of your API must either have an [operation name](#) defined for it, or you need to create a name override when you add your stage as a target. This name is used as the tool name that agents use to interact with your method.
- You can use API_KEY, NO_AUTH, or GATEWAY_IAM_ROLE credential provider types for Outbound Auth to allow your Gateway to access your API. The API_KEY credential provider is defined by AgentCore Gateway. You can use your existing API Gateway API key. For more information, see [Setting up Outbound Auth](#).
- If you use a Amazon Cognito user pool or Lambda authorizer to control access to your API, MCP clients cannot access it.

- Your API must be in the same account and Region as your AgentCore Gateway.

Add a stage of an API as a target for a AgentCore Gateway

The following procedure shows how to add a stage of an API as a target for a AgentCore Gateway.

To add a stage of an API as a target for a AgentCore Gateway

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose a REST API that's deployed to a stage.
3. In the main navigation pane, choose **Stages**.
4. Choose **Stage actions**, and then choose **Create MCP target**.
5. For **AgentCore Gateway**, select an AgentCore Gateway.
6. For **Target name**, enter a target name.
7. For **Target description**, enter a description.
8. Keep the provided API and stage.
9. For **Select API resources**, select the resources of your API that agents using your AgentCore Gateway can access.

If you don't select a resource, an agent cannot view the documentation or invoke the endpoint.

10. The combination of the resource and the method are the operations for the tool. If your operation does not have a name, create a name override.

You can also define an operation name for a method when you create it.

11. For **Outbound Auth configuration**, choose either **IAM Role**, **No authorization** or **API key**.
12. Choose **Create target**.

To view all the AgentCore Gateways that have access to your APIs, choose the **MCP targets** section in the main navigation pane. In this section, you can create a MCP target for any API in your Region deployed to a stage. Choose **Create MCP target** and follow the previous steps.

You can also view the available tools for your target and edit your target in the AgentCore Gateway console. For more information, see [Add targets to an existing AgentCore Gateway](#).

Delete a stage

When you no longer need a stage, you can delete it to avoid paying for unused resources. The following steps show you how to use the API Gateway console to delete a stage.

Warning

Deleting a stage might cause part or all of the corresponding API to be unusable by API callers. Deleting a stage cannot be undone, but you can recreate the stage and associate it with the same deployment.

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose a REST API.
3. In the main navigation pane, choose **Stages**.
4. In the **Stages** pane, choose the stage you want to delete, and then choose **Stage actions**, **Delete stage**.
5. When you're prompted, enter **confirm**, and then choose **Delete**.

Set up tags for an API stage in API Gateway

In API Gateway, you can add a tag to an API stage, remove the tag from the stage, or view the tag. To do this, you can use the API Gateway console, the AWS CLI/SDK, or the API Gateway REST API.

A stage can also inherit tags from its parent REST API. For more information, see [the section called "Tag inheritance in the Amazon API Gateway V1 API"](#).

For more information about tagging API Gateway resources, see [Tagging](#).

Topics

- [Set up tags for an API stage using the API Gateway console](#)
- [Set up tags for an API stage using the AWS CLI](#)
- [Set up tags for an API stage using the API Gateway REST API](#)

Set up tags for an API stage using the API Gateway console

The following procedure describes how to set up tags for an API stage.

To set up tags for an API stage by using the API Gateway console

1. Sign in to the API Gateway console.
2. Choose an existing API, or create a new API that includes resources, methods, and the corresponding integrations.
3. Choose a stage or deploy the API to a new stage.
4. In the main navigation pane, choose **Stages**.
5. Choose the **Tags** tab. You might need to choose the right arrow button to show the tab.
6. Choose **Manage tags**.
7. In the **Tag Editor**, choose **Add tag**. Enter a tag key (for example, Department) in the **Key** field, and enter a tag value (for example, Sales) in the **Value** field. Choose **Save** to save the tag.
8. If needed, repeat step 5 to add more tags to the API stage. The maximum number of tags per stage is 50.
9. To remove an existing tag from the stage, choose **Remove**.
10. If the API has been deployed previously in the API Gateway console, you need to redeploy it for the changes to take effect.

Set up tags for an API stage using the AWS CLI

You can set up tags for an API stage using the [create-stage](#) command or the [tag-resource](#) command. You can delete one or more tags from an API stage using the [untag-resource](#) command.

The following [create-stage](#) command adds a tag when creating a test stage:

```
aws apigateway create-stage --rest-api-id abc1234 --stage-name test --description  
'Testing stage' --deployment-id efg456 --tag Department=Sales
```

The following [tag-resource](#) command adds a tag to a prod stage:

```
aws apigateway tag-resource --resource-arn arn:aws:apigateway:us-east-2::/  
restapis/abc123/stages/prod --tags Department=Sales
```

The following [untag-resource](#) command removes the Department=Sales tag from the test stage:

```
aws apigateway untag-resource --resource-arn arn:aws:apigateway:us-east-2::/  
restapis/abc123/stages/test --tag-keys Department
```

Set up tags for an API stage using the API Gateway REST API

You can set up tags for an API stage using the API Gateway REST API by doing one of the following:

- Call [tags:tag](#) to tag an API stage.
- Call [tags:untag](#) to delete one or more tags from an API stage.
- Call [stage:create](#) to add one or more tags to an API stage that you're creating.

You can also call [tags:get](#) to describe tags in an API stage.

Tag an API stage

After you deploy an API (m5zr3vnks7) to a stage (test), tag the stage by calling [tags:tag](#).

The required stage Amazon Resource Name (ARN) (arn:aws:apigateway:us-east-1::/
restapis/m5zr3vnks7/stages/test) must be URL encoded (arn%3Aaws%3Aapigateway
%3Aus-east-1%3A%3A%2Frestapis%2Fm5zr3vnks7%2Fstages%2Ftest).

```
PUT /tags/arn%3Aaws%3Aapigateway%3Aus-east-1%3A%3A%2Frestapis%2Fm5zr3vnks7%2Fstages  
%2Ftest
```

```
{  
  "tags" : {  
    "Department" : "Sales"  
  }  
}
```

You can also use the previous request to update an existing tag to a new value.

You can add tags to a stage when calling [stage:create](#) to create the stage:

```
POST /restapis/<restapi_id>/stages  
  
{  
  "stageName" : "test",  
  "deploymentId" : "adr134",  
  "description" : "test deployment",  
  "cacheClusterEnabled" : "true",  
  "cacheClusterSize" : "500",
```

```
"variables" : {  
    "sv1" : "val1"  
,  
    "documentationVersion" : "test",  
  
    "tags" : {  
        "Department" : "Sales",  
        "Division" : "Retail"  
    }  
}
```

Untag an API stage

To remove the Department tag from the stage, call [tags:untag](#):

```
DELETE /tags/arn%3Aaws%3Apigateway%3Aus-east-1%3A%3A%2Frestapis%2Fm5zr3vnks7%2Fstages  
%2Ftest?tagKeys=Department  
Host: apigateway.us-east-1.amazonaws.com  
Authorization: ...
```

To remove more than one tag, use a comma-separated list of tag keys in the query expression—for example, ?tagKeys=Department,Division,....

Describe tags for an API stage

To describe existing tags on a given stage, call [tags:get](#):

```
GET /tags/arn%3Aaws%3Apigateway%3Aus-east-1%3A%3A%2Frestapis%2Fm5zr3vnks7%2Fstages  
%2Ftags  
Host: apigateway.us-east-1.amazonaws.com  
Authorization: ...
```

The successful response is similar to the following:

200 OK

```
{  
    "_links": {  
        "curies": {  
            "href": "http://docs.aws.amazon.com/apigateway/latest/developerguide/  
restapi-tags-{rel}.html",  
            "name": "tags",  
            "templated": true
```

```
        },
        "tags:tag": {
            "href": "/tags/arn%3Aaws%3Aapigateway%3Aus-east-1%3A%3A%2Frestapis
%2Fm5zr3vnks7%2Fstages%2Ftags"
        },
        "tags:untag": {
            "href": "/tags/arn%3Aaws%3Aapigateway%3Aus-east-1%3A%3A%2Frestapis
%2Fm5zr3vnks7%2Fstages%2Ftags{?tagKeys}",
            "templated": true
        }
    },
    "tags": {
        "Department": "Sales"
    }
}
```

Use stage variables for a REST API in API Gateway

Stage variables are key-value pairs that you can define as configuration attributes associated with a deployment stage of a REST API. They act like environment variables and can be used in your API setup and mapping templates. With deployment stages in API Gateway, you can manage multiple release stages for each API and use stage variables you can configure an API deployment stage to interact with different backend endpoints.

Stage variables are not intended to be used for sensitive data, such as credentials. To pass sensitive data to integrations, use an AWS Lambda authorizer. You can pass sensitive data to integrations in the output of the Lambda authorizer. To learn more, see [the section called “Output from an API Gateway Lambda authorizer”](#).

Use cases for stage variables

The following are use cases for your stage variables.

Specify a different backend endpoint

Your API can pass a GET request as an HTTP proxy to the backend web host. You can use a stage variable so that when API callers invoke your production endpoint, API Gateway calls example.com. Then, when API callers invoke the beta stage, API Gateway calls a different web host, such as beta.example.com. Similarly, stage variables can be used to specify a different AWS Lambda function name for each stage in your API. You can't use a stage variable to set a different integration endpoint, such as pointing the GET request to an HTTP proxy integration in one stage and a Lambda proxy integration in another stage.

When specifying a Lambda function name as a stage variable value, you must configure the permissions on the Lambda function manually. When you specify a Lambda function in the API Gateway console, a AWS CLI command will pop-up to configure the proper permissions. You can also use the following AWS CLI command to do this.

```
aws lambda add-permission --function-name "arn:aws:lambda:us-east-2:123456789012:function:my-function" --source-arn "arn:aws:execute-api:us-east-2:123456789012:api_id/*/HTTP_METHOD/resource" --principal apigateway.amazonaws.com --statement-id apigateway-access --action lambda:InvokeFunction
```

Pass information using mapping templates

You can access stage variables in the mapping templates, or pass configuration parameters to your AWS Lambda or HTTP backend. For example, you might want to reuse the same Lambda function for multiple stages in your API, but the function should read data from a different Amazon DynamoDB table depending on the stage. In the mapping templates that generate the request for the Lambda function, you can use stage variables to pass the table name to Lambda.

To use a stage variable, you first configure a stage variable, and then you assign it a value. For example, to customize the HTTP integration endpoint, first create the `url` stage variable, and then in your API's integration request, enter the stage variable value, `http://${stageVariables.url}`. This value tells API Gateway to substitute your stage variable `{}$` at runtime, depending on which stage your API is running. For more information, see [the section called “Set up stage variables for REST APIs in API Gateway”](#).

Set up stage variables for REST APIs in API Gateway

This section shows how to set up various stage variables for two deployment stages of a sample API by using the Amazon API Gateway console. To understand how to use stage variables in API Gateway, we recommend that you follow all procedures in this section.

Prerequisites

Before you begin, make sure the following prerequisites are met:

- You must have an API available in API Gateway. Follow the instructions in [Develop REST APIs in API Gateway](#).

- You must have deployed the API at least once. Follow the instructions in [Deploy REST APIs in API Gateway](#).
- You must have created the first stage for a deployed API. Follow the instructions in [Create a new stage](#).

Invoke an HTTP endpoint through an API with a stage variable

This procedure describes how to create a stage variable for an HTTP endpoint and two stages for your API. In addition, you create the stage variables, `url`, `stageName`, and `function` that are used in the following procedures in this section.

To invoke an HTTP endpoint through an API with a stage variable

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Create an API, and then create a GET method on the API's root resource. Set the integration type to **HTTP** and set the **Endpoint URL** to `http://${stageVariables.url}`.
3. Deploy the API to a new stage named **beta**.
4. In the main navigation pane, choose **Stages**, and then select the **beta** stage.
5. On the **Stage variables** tab, choose **Edit**.
6. Choose **Add stage variable**.
7. For **Name**, enter `url`. For **value**, enter `httpbin.org/get`.
8. Choose **Add stage variable**, and then do the following:

For **Name**, enter `stageName`. For **value**, enter **beta**.
9. Choose **Add stage variable**, and then do the following:

For **Name**, enter `function`. For **value**, enter `HelloWorld`.
10. Choose **Save**.
11. Now create a second stage. From the **Stages** navigation pane, choose **Create stage**. For **Stage name**, enter **prod**. Select a recent deployment from **Deployment**, and then choose **Create stage**.
12. As with the **beta** stage, set the same three stage variables (`url`, `stageName`, and `function`) to different values (`petstore-demo-endpoint.execute-api.com/petstore/pets`, `prod`, and `HelloEveryone`), respectively.

13. In the **Stages** navigation pane, choose **beta**. Under **Stage details**, choose the copy icon to copy your API's invoke URL, and then enter your API's invoke URL in a web browser. This starts the **beta** stage GET request on the root resource of the API.

 **Note**

The **Invoke URL** link points to the root resource of the API in its **beta** stage. Entering the URL in a web browser calls the **beta** stage GET method on the root resource. If methods are defined on child resources and not on the root resource itself, entering the URL in a web browser returns a `{"message": "Missing Authentication Token"}` error response. In this case, you must append the name of a specific child resource to the **Invoke URL** link.

14. The response you get from the **beta** stage GET request is shown next. You can also verify the result by using a browser to navigate to <http://httpbin.org/get>. This value was assigned to the `url` variable in the **beta** stage. The two responses are identical.
15. In the **Stages** navigation pane, choose the **prod** stage. Under **Stage details**, choose the copy icon to copy your API's invoke URL, and then enter your API's invoke URL in a web browser. This starts the **prod** stage GET request on the root resource of the API.
16. The response you get from the **prod** stage GET request is shown next. You can verify the result by using a browser to navigate to <http://petstore-demo-endpoint.execute-api.com/petstore/pets>. This value was assigned to the `url` variable in the **prod** stage. The two responses are identical.

Pass stage-specific metadata into an HTTP backend

This procedure describes how to use a stage variable value in a query parameter expression to pass stage-specific metadata into an HTTP backend. We will use the `stageName` stage variable declared in the previous procedure.

To pass stage-specific metadata into an HTTP backend

1. In the **Resource** navigation pane, choose the **GET** method.

To add a query string parameter to the method's URL, choose the **Method request** tab, and then in the **Method request settings** section, choose **Edit**.

2. Choose **URL query string parameters** and do the following:

- a. Choose **Add query string**.
 - b. For **Name**, enter **stageName**.
 - c. Keep **Required** and **Caching** turned off.
3. Choose **Save**.
4. Choose the **Integration request** tab, and then in the **Integration request settings** section, choose **Edit**.
5. For **Endpoint URL**, append `?stageName=${stageVariables.stageName}` to the previously defined URL value, so the entire **Endpoint URL** is `http://${stageVariables.url}?stageName=${stageVariables.stageName}`.
6. Choose **Deploy API** and select the **beta** stage.
7. In the main navigation pane, choose **Stages**. In the **Stages** navigation pane, choose **beta**. Under **Stage details**, choose the copy icon to copy your API's invoke URL, and then enter your API's invoke URL in a web browser.

 **Note**

We use the beta stage here because the HTTP endpoint (as specified by the `url` variable "http://httpbin.org/get") accepts query parameter expressions and returns them as the `args` object in its response.

8. You get the following response. Notice that `beta`, assigned to the `stageName` stage variable, is passed in the backend as the `stageName` argument.

```
{  
  "args": {  
    "stageName": "beta"  
  },  
  "headers": {  
    "Accept": "application/json",  
    "Host": "httpbin.org",  
    "User-Agent": "AmazonAPIGateway_abcd1234",  
    "X-Amzn-Apigateway-Api-Id": "abcd1234",  
    "X-Amzn-Trace-Id": "Self=1-abcd-1111111111111111;Root=1-11111111-1111111111111111"  
  },  
  "origin": "192.0.2.9",  
  "url": "http://httpbin.org/get?stageName=beta"  
}
```

Invoke a Lambda function through an API with a stage variable

This procedure describes how to use a stage variable to call a Lambda function as a backend of your API. You use the function stage variable declared in [Invoke an HTTP endpoint through an API with a stage variable](#).

When setting a Lambda function as the value of a stage variable, use the function's local name, possibly including its alias or version specification, as in **HelloWorld**, **HelloWorld:1** or **HelloWorld:alpha**. Do not use the function's ARN (for example, **arn:aws:lambda:us-east-1:123456789012:function:HelloWorld**). The API Gateway console assumes the stage variable value for a Lambda function as the unqualified function name and expands the given stage variable into an ARN.

To invoke a Lambda function through an API with a stage variable

1. Create a Lambda function named **HelloWorld** using the default Node.js runtime. The code must contain the following:

```
export const handler = function(event, context, callback) {
    if (event.stageName)
        callback(null, 'Hello, World! I\'m calling from the ' + event.stageName + ' stage.');
    else
        callback(null, 'Hello, World! I\'m not sure where I\'m calling from...');

};
```

For more information on how to create a Lambda function, see [Getting started with the REST API console](#).

2. In the **Resources** pane, select **Create resource**, and then do the following:
 - a. For **Resource path**, select **/**.
 - b. For **Resource name**, enter **lambda****dav1**.
 - c. Choose **Create resource**.
3. Choose the **/lambda****dav1** resource, and then choose **Create method**.

Then, do the following:

- a. For **Method type**, select **GET**.
- b. For **Integration type**, select **Lambda function**.

- c. Keep **Lambda proxy integration** turned off.
- d. For **Lambda function**, enter `#{stageVariables.function}`.

Lambda function

Provide the Lambda function name or alias. You can also provide an ARN from another account.

us-east-1 ▾🔍 `#{stageVariables.function}`X

Tip

When prompted with the **Add permission command**, copy the [add-permission](#) command. Run the command on each Lambda function that will be assigned to the function stage variable. For example, if the `#{stageVariables.function}` value is `HelloWorld`, run the following AWS CLI command:

```
aws lambda add-permission --function-name arn:aws:lambda:us-east-1:account-id:function:HelloWorld --source-arn arn:aws:execute-api:us-east-1:account-id:api-id/*/GET/lambdav1 --principal apigateway.amazonaws.com --statement-id statement-id-guid --action lambda:InvokeFunction
```

Failing to do so results in a `500 Internal Server Error` response when invoking the method. Replace `#{stageVariables.function}` with the Lambda function name that is assigned to the stage variable.

Lambda function

Provide the Lambda function name or alias. You can also provide an ARN from another account.

us-east-1 ▾🔍 `#{stageVariables.function}`X

⚠ You defined your Lambda function as a stage variable. Run the following AWS CLI command to ensure you have the appropriate policy for this function. Replace the stage variable in the function-name parameter with the necessary function name.

▼ Add permission command

```
1 aws lambda add-permission \
2   --function-name "arn:aws:lambda:us-east-1:111122223333:function:#{stageVariables.function}" \
3   --source-arn "arn:aws:execute-api:us-east-1:111122223333:abcd1234/*/GET/lambdav1" \
4   --principal apigateway.amazonaws.com \
5   --statement-id abcd-12345-efg \
6   --action lambda:InvokeFunction
```

- e. Choose **Create method**.
4. Deploy the API to both the **prod** and **beta** stages.
5. In the main navigation pane, choose **Stages**. In the **Stages** navigation pane, choose **beta**. Under **Stage details**, choose the copy icon to copy your API's invoke URL, and then enter your API's invoke URL in a web browser. Append **/lambda1** to the URL before you press enter.

You get the following response.

"Hello, World! I'm not sure where I'm calling from..."

Pass stage-specific metadata to a Lambda function through a stage variable

This procedure describes how to use a stage variable to pass stage-specific configuration metadata into a Lambda function. You create a POST method and an input mapping template to generate payload using the `stageName` stage variable you declared earlier.

To pass stage-specific metadata to a Lambda function through a stage variable

1. Choose the **/lambda1** resource, and then choose **Create method**.

Then, do the following:

- a. For **Method type**, select **POST**.
 - b. For **Integration type**, select **Lambda function**.
 - c. Keep **Lambda proxy integration** turned off.
 - d. For **Lambda function**, enter `${stageVariables.function}`.
 - e. When prompted with the **Add permission command**, copy the the [add-permission](#) command. Run the command on each Lambda function that will be assigned to the function stage variable.
 - f. Choose **Create method**.
2. Choose the **Integration request** tab, and then in the **Integration request settings** section, choose **Edit**.
 3. Choose **Mapping templates**, and then choose **Add mapping template**.
 4. For **Content type**, enter **application/json**.
 5. For **Template body**, enter the following template:

```
#set($inputRoot = $input.path('$'))  
{  
    "stageName" : "$stageVariables.stageName"  
}
```

Note

In a mapping template, a stage variable must be referenced within quotes (as in `"$stageVariables.stageName"` or `"${stageVariables.stageName}"`). In other places, it must be referenced without quotes (as in `${stageVariables.function}`).

6. Choose **Save**.
7. Deploy the API to both the **beta** and **prod** stages.
8. To use a REST API client to pass stage-specific metadata, do the following:
 - a. In the **Stages** navigation pane, choose **beta**. Under **Stage details**, choose the copy icon to copy your API's invoke URL, and then enter your API's invoke URL in the input field of a REST API client. Append **/lambda1** before you submit your request.

You get the following response.

```
"Hello, World! I'm calling from the beta stage."
```

- b. In the **Stages** navigation pane, choose **prod**. Under **Stage details**, choose the copy icon to copy your API's invoke URL, and then enter your API's invoke URL in the input field of a REST API client. Append **/lambda1** before you submit your request.

You get the following response.

```
"Hello, World! I'm calling from the prod stage."
```

9. To use the **Test** feature to pass stage-specific metadata, do the following:
 - a. In the **Resources** navigation pane, choose the **Test** tab. You might need to choose the right arrow button to show the tab.
 - b. For **function**, enter **HelloWorld**.
 - c. For **stageName**, enter **beta**.

- d. Choose **Test**. You do not need to add a body to your POST request.

You get the following response.

```
"Hello, World! I'm calling from the beta stage."
```

- e. You can repeat the previous steps to test the **Prod** stage. For **stageName**, enter **Prod**.

You get the following response.

```
"Hello, World! I'm calling from the prod stage."
```

API Gateway stage variables reference for REST APIs in API Gateway

You can use API Gateway stage variables in the following cases.

Parameter mapping expressions

A stage variable can be used in a parameter mapping expression for an API method's request or response header parameter, without any partial substitution. In the following example, the stage variable is referenced without the \$ and the enclosing {...}.

- `stageVariables.<variable_name>`

Mapping templates

A stage variable can be used anywhere in a mapping template, as shown in the following examples.

- `{ "name" : "$stageVariables.<variable_name>" }`
- `{ "name" : "${stageVariables.<variable_name>}"}`

HTTP integration URIs

A stage variable can be used as part of an HTTP integration URL, as shown in the following examples:

- A full URI without protocol – `http://${stageVariables.<variable_name>}`
- A full domain – `http://${stageVariables.<variable_name>}/resource/operation`

- A subdomain – `http://${stageVariables.<variable_name>}.example.com/resource/operation`
- A path – `http://example.com/${stageVariables.<variable_name>}/bar`
- A query string – `http://example.com/foo?q=${stageVariables.<variable_name>}`

AWS integration URIs

A stage variable can be used as part of AWS URI action or path components, as shown in the following example.

- `arn:aws:apigateway:<region>:<service>:${stageVariables.<variable_name>}`

AWS integration URIs (Lambda functions)

A stage variable can be used in place of a Lambda function name, or version/alias, as shown in the following examples.

- `arn:aws:apigateway:<region>:lambda:path/2015-03-31/functions/arn:aws:lambda:<region>:<account_id>:function:${stageVariables.<function_variable_name>}/invocations`
- `arn:aws:apigateway:<region>:lambda:path/2015-03-31/functions/arn:aws:lambda:<region>:<account_id>:function:<function_name>:${stageVariables.<version_variable_name>}/invocations`

Note

To use a stage variable for a Lambda function, the function must be in the same account as the API. Stage variables don't support cross-account Lambda functions.

Amazon Cognito user pool

A stage variable can be used in place of a Amazon Cognito user pool for a COGNITO_USER_POOLS authorizer.

- `arn:aws:cognito-idp:<region>:<account_id>:userpool/${stageVariables.<variable_name>}`

AWS integration credentials

A stage variable can be used as part of AWS user/role credential ARN, as shown in the following example.

- `arn:aws:iam::<account_id>:${stageVariables.<variable_name>}`

Set up an API Gateway canary release deployment

[Canary release](#) is a software development strategy in which a new version of an API (as well as other software) is deployed for testing purposes, and the base version remains deployed as a production release for normal operations on the same stage. For purposes of discussion, we refer to the base version as a production release in this documentation. Although this is reasonable, you are free to apply canary release on any non-production version for testing.

In a canary release deployment, total API traffic is separated at random into a production release and a canary release with a pre-configured ratio. Typically, the canary release receives a small percentage of API traffic and the production release takes up the rest. The updated API features are only visible to API traffic through the canary. You can adjust the canary traffic percentage to optimize test coverage or performance.

By keeping canary traffic small and the selection random, most users are not adversely affected at any time by potential bugs in the new version, and no single user is adversely affected all the time.

After the test metrics pass your requirements, you can promote the canary release to the production release and disable the canary from the deployment. This makes the new features available in the production stage.

Topics

- [Canary release deployment in API Gateway](#)
- [Create a canary release deployment](#)
- [Update a canary release](#)
- [Promote a canary release](#)
- [Turn off a canary release](#)

Canary release deployment in API Gateway

In API Gateway, a canary release deployment uses the deployment stage for the production release of the base version of an API, and attaches to the stage a canary release for the new versions, relative to the base version, of the API. The stage is associated with the initial deployment and the canary with subsequent deployments. At the beginning, both the stage and the canary point to the same API version. We use stage and production release interchangeably and use canary and canary release interchangeably throughout this section.

To deploy an API with a canary release, you create a canary release deployment by adding [canary settings](#) to the [stage](#) of a regular [deployment](#). The canary settings describe the underlying canary release and the stage represents the production release of the API within this deployment. To add canary settings, set `canarySettings` on the deployment stage and specify the following:

- A deployment ID, initially identical to the ID of the base version deployment set on the stage.
- A [percentage of API traffic](#), between 0.0 and 100.0 inclusive, for the canary release.
- [Stage variables for the canary release](#) that can override production release stage variables.
- The [use of the stage cache](#) for canary requests, if the [useStageCache](#) is set and API caching is enabled on the stage.

After a canary release is enabled, the deployment stage cannot be associated with another non-canary release deployment until the canary release is disabled and the canary settings removed from the stage.

When you enable API execution logging, the canary release has its own logs and metrics generated for all canary requests. They are reported to a production stage CloudWatch Logs log group as well as a canary-specific CloudWatch Logs log group. The same applies to access logging. The separate canary-specific logs are helpful to validate new API changes and decide whether to accept the changes and promote the canary release to the production stage, or to discard the changes and revert the canary release from the production stage.

The production stage execution log group is named `API-Gateway-Execution-Logs/{rest-api-id}/{stage-name}` and the canary release execution log group is named `API-Gateway-Execution-Logs/{rest-api-id}/{stage-name}/Canary`. For access logging, you must create a new log group or choose an existing one. The canary release access log group name has the `/Canary` suffix appended to the selected log group name.

A canary release can use the stage cache, if enabled, to store responses and use cached entries to return results to the next canary requests, within a pre-configured time-to-live (TTL) period.

In a canary release deployment, the production release and canary release of the API can be associated with the same version or with different versions. When they are associated with different versions, responses for production and canary requests are cached separately and the stage cache returns corresponding results for production and canary requests. When the production release and canary release are associated with the same deployment, the stage cache uses a single cache key for both types of requests and returns the same response for the same requests from the production release and canary release.

Create a canary release deployment

You create a canary release deployment when deploying the API with [canary settings](#) as an additional input to the [deployment creation](#) operation.

You can also create a canary release deployment from an existing non-canary deployment by making a [stage:update](#) request to add the canary settings on the stage.

When creating a non-canary release deployment, you can specify a non-existing stage name. API Gateway creates one if the specified stage does not exist. However, you cannot specify any non-existing stage name when creating a canary release deployment. You will get an error and API Gateway will not create any canary release deployment.

You can create a canary release deployment in API Gateway using the API Gateway console, the AWS CLI, or an AWS SDK.

Topics

- [Create a canary deployment using the API Gateway console](#)
- [Create a canary deployment using the AWS CLI](#)

Create a canary deployment using the API Gateway console

To use the API Gateway console to create a canary release deployment, follow the instructions below:

To create the initial canary release deployment

1. Sign in to the API Gateway console.
2. Choose an existing REST API or create a new REST API.

3. In the main navigation pane, choose **Resources**, and then choose **Deploy API**. Follow the on-screen instructions in **Deploy API** to deploy the API to a new stage.

So far, you have deployed the API to a production release stage. Next, you configure canary settings on the stage and, if needed, also enable caching, set stage variables, or configure API execution or access logs.

4. To enable API caching or associate an AWS WAF web ACL with the stage, in the **Stage details** section, choose **Edit**. For more information, see [the section called “Cache settings”](#) or [the section called “To associate an AWS WAF web ACL with an API Gateway API stage using the API Gateway console”](#).
5. To configure execution or access logging, in the **Logs and tracing** section, choose **Edit** and follow the on-screen instructions. For more information, see [Set up CloudWatch logging for REST APIs in API Gateway](#).
6. To set stage variables, choose the **Stage variables** tab and follow the on-screen instructions to add or modify stage variables. For more information, see [the section called “Use stage variables”](#).
7. Choose the **Canary** tab, and then choose **Create canary**. You might need to choose the right arrow button to show the **Canary** tab.
8. Under **Canary settings**, for **Canary**, enter the percentage of requests to be diverted to the canary.
9. If desired, select **Stage cache** to turn on caching for the canary release. The cache is not available for the canary release until API caching is enabled.
10. To override existing stage variables, for **Canary override**, enter a new stage variable value.

After the canary release is initialized on the deployment stage, you change the API and want to test the changes. You can redeploy the API to the same stage so that both the updated version and the base version are accessible through the same stage. The following steps describe how to do that.

To deploy the latest API version to a canary

1. With each update of the API, choose **Deploy API**.
2. In **Deploy API**, choose the stage that contains a canary from the **Deployment stage** dropdown list.
3. (Optional) Enter a description for **Deployment description**.

4. Choose **Deploy** to push the latest API version to the canary release.
5. If desired, reconfigure the stage settings, logs, or canary settings, as described in [To create the initial canary release deployment](#).

As a result, the canary release points to the latest version while the production release still points to the initial version of the API. The [canarySettings](#) now has a new [deploymentId](#) value, whereas the stage still has the initial [deploymentId](#) value. Behind the scenes, the console calls [stage:update](#).

Create a canary deployment using the AWS CLI

To create a canary deployment for a new stage

1. Use the following [create-deployment](#) command to create a deployment with two stage variables, but without a canary:

```
aws apigateway create-deployment \
    --variables sv0=val0,sv1=val1 \
    --rest-api-id abcd1234 \
    --stage-name 'prod'
```

The output will look like the following:

```
{  
    "id": "du4ot1",  
    "createdDate": 1511379050  
}
```

2. Use the following [create-deployment](#) command to create a canary deployment on the prod stage:

```
aws apigateway create-deployment \
    --rest-api-id abcd1234 \
    --canary-settings
    percentTraffic=10.5,stageVariableOverrides={sv1='val2',sv2='val3'},useStageCache=false
    \
    --stage-name 'prod'
```

The output will look like the following:

```
{  
  "id": "a6rox0",  
  "createdDate": 1511379433  
}
```

The resulting deployment id identifies the test version of the API for the canary release. As a result, the associated stage is canary-enabled.

3. (Optional) Use the following [get-stage](#) command to view the stage representation:

```
aws apigateway get-stage --rest-api-id acbd1234 --stage-name prod
```

The following shows a representation of the Stage as the output of the command:

```
{  
  "stageName": "prod",  
  "variables": {  
    "sv0": "val0",  
    "sv1": "val1"  
  },  
  "cacheClusterEnabled": false,  
  "cacheClusterStatus": "NOT_AVAILABLE",  
  "deploymentId": "du4ot1",  
  "lastUpdatedDate": 1511379433,  
  "createdDate": 1511379050,  
  "canarySettings": {  
    "percentTraffic": 10.5,  
    "deploymentId": "a6rox0",  
    "useStageCache": false,  
    "stageVariableOverrides": {  
      "sv2": "val3",  
      "sv1": "val2"  
    }  
  },  
  "methodSettings": {}  
}
```

In this example, the base version of the API will use the stage variables of {"sv0":val0", "sv1":val1"}, while the test version uses the stage variables of {"sv1":val2", "sv2":val3"}. Both the production release and canary release use the same stage variable

of `sv1`, but with different values, `val1` and `val2`, respectively. The stage variable of `sv0` is used solely in the production release and the stage variable of `sv2` is used in the canary release only.

You can also create a canary release deployment from an existing regular deployment by updating the stage to enable a canary.

To create a canary release deployment from an existing deployment

1. Use the [create-deployment](#) command to create a deployment without a canary:

```
aws apigateway create-deployment \
--variables sv0=val0,sv1=val1 \
--rest-api-id abcd1234 \
--stage-name 'beta'
```

2. Use the [update-stage](#) command to update the stage to enable a canary:

```
aws apigateway update-stage \
--rest-api-id abcd1234 \
--stage-name 'beta' \
--patch-operations '[{
    "op": "replace",
    "value": "0.0",
    "path": "/canarySettings/percentTraffic"
}, {
    "op": "copy",
    "from": "/canarySettings/stageVariableOverrides",
    "path": "/variables"
}, {
    "op": "copy",
    "from": "/canarySettings/deploymentId",
    "path": "/deploymentId"
}]'
```

The output will look like the following:

```
{
  "stageName": "beta",
  "variables": {
    "sv0": "val0",
```

```
        "sv1": "val1"
    },
    "cacheClusterEnabled": false,
    "cacheClusterStatus": "NOT_AVAILABLE",
    "deploymentId": "cifeiw",
    "lastUpdatedDate": 1511381930,
    "createdDate": 1511380879,
    "canarySettings": {
        "percentTraffic": 10.5,
        "deploymentId": "cifeiw",
        "useStageCache": false,
        "stageVariableOverrides": {
            "sv2": "val3",
            "sv1": "val2"
        }
    },
    "methodSettings": {}
}
```

Because you enabled a canary on an existing version of the API, both the production release (Stage) and canary release (canarySettings) point to the same deployment. After you change the API and deploy it to this stage again, the new version will be in the canary release, while the base version remains in the production release. This is manifested in the stage evolution when the deploymentId in the canary release is updated to the new deployment id and the deploymentId in the production release remains unchanged.

Update a canary release

After a canary release is deployed, you may want to adjust the percentage of the canary traffic or enable or disable the use of a stage cache to optimize the test performance. You can also modify stage variables used in the canary release when the execution context is updated. To make such updates, call the [stage:update](#) operation with new values on [canarySettings](#).

You can update a canary release using the API Gateway console, the AWS CLI [update-stage](#) command or an AWS SDK.

Topics

- [Update a canary release using the API Gateway console](#)
- [Update a canary release using the AWS CLI](#)

Update a canary release using the API Gateway console

To use the API Gateway console to update existing canary settings on a stage, do the following:

To update existing canary settings

1. Sign in to the API Gateway console and choose an existing REST API.
2. In the main navigation pane, choose **Stages**, and then choose an existing stage.
3. Choose the **Canary** tab, and then choose **Edit**. You might need to choose the right arrow button to show the **Canary** tab.
4. Update the **Request distribution** by increasing or decreasing the percentage number between 0.0 and 100.0, inclusive.
5. Select or clear the **Stage cache** the check box.
6. Add, remove, or modify **Canary stage variables**.
7. Choose **Save**.

Update a canary release using the AWS CLI

To use the AWS CLI to update a canary, use the [update-stage](#) command and modify the patch operation for each parameter of the canary.

The following [update-stage](#) command updates if the canary uses the stage cache:

```
aws apigateway update-stage \
  --rest-api-id {rest-api-id} \
  --stage-name '{stage-name}' \
  --patch-operations op=replace,path=/canarySettings/useStageCache,value=true
```

The following [update-stage](#) command updates the canary traffic percentage:

```
aws apigateway update-stage \
  --rest-api-id {rest-api-id} \
  --stage-name '{stage-name}' \
  --patch-operations op=replace,path=/canarySettings/percentTraffic,value=25.0
```

The following [update-stage](#) updates stage variables. The example shows how to create a new stage variable named `newVar`, override the `var2` stage variable, and remove the `var1` stage variable:

```
aws apigateway update-stage \
--rest-api-id {rest-api-id} \
--stage-name '{stage-name}' \
--patch-operations '[{
    "op": "replace",
    "path": "/canarySettings/stageVariableOverrides/newVar",
    "value": "newVal"
}, {
    "op": "replace",
    "path": "/canarySettings/stageVariableOverrides/var2",
    "value": "val4"
}, {
    "op": "remove",
    "path": "/canarySettings/stageVariableOverrides/var1"
}]'
```

You can update all of the above by combining the operations into a single patch-operations value:

```
aws apigateway update-stage \
--rest-api-id {rest-api-id} \
--stage-name '{stage-name}' \
--patch-operations '[{
    "op": "replace",
    "path": "/canarySettings/percentTraffic",
    "value": "20.0"
}, {
    "op": "replace",
    "path": "/canarySettings/useStageCache",
    "value": "true"
}, {
    "op": "remove",
    "path": "/canarySettings/stageVariableOverrides/var1"
}, {
    "op": "replace",
    "path": "/canarySettings/stageVariableOverrides/newVar",
    "value": "newVal"
}, {
    "op": "replace",
    "path": "/canarySettings/stageVariableOverrides/var2",
    "value": "val4"
}]'
```

Promote a canary release

When you promote a canary release, the canary release replaces the current stage settings. Promoting a canary release does not disable the canary on the stage. To disable a canary, you must remove the canary settings on the stage. To promote a canary, do the following.

- Reset the [deployment ID](#) of the stage with the [deployment ID](#) settings of the canary. This updates the API snapshot of the stage with the snapshot of the canary, making the test version the production release as well.
- Update stage variables with canary stage variables, if any. This updates the API execution context of the stage with that of the canary. Without this update, the new API version may produce unexpected results if the test version uses different stage variables or different values of existing stage variables.
- Set the percentage of canary traffic to 0.0%.

Topics

- [Promote a canary release using the API Gateway console](#)
- [Promote a canary release using the AWS CLI](#)

Promote a canary release using the API Gateway console

To use the API Gateway console to promote a canary release deployment, do the following:

To promote a canary release deployment

1. Sign in to the API Gateway console and choose an existing API in the primary navigation pane.
2. In the main navigation pane, choose **Stages**, and then choose an existing stage.
3. Choose the **Canary** tab.
4. Choose **Promote canary**.
5. Confirm changes to be made and choose **Promote canary**.

After the promotion, the production release references the same API version (**deploymentId**) as the canary release. You can verify this using the AWS CLI. For example, see [the section called “Promote a canary release using the AWS CLI”](#).

Promote a canary release using the AWS CLI

To promote a canary release to the production release using the AWS CLI commands, call the `update-stage` command to copy the canary-associated deploymentId to the stage-associated deploymentId, to reset the canary traffic percentage to zero (`0.0`), and, to copy any canary-bound stage variables to the corresponding stage-bound ones.

Suppose we have a canary release deployment, described by a stage similar to the following:

```
{  
    "_links": {  
        ...  
    },  
    "accessLogSettings": {  
        ...  
    },  
    "cacheClusterEnabled": false,  
    "cacheClusterStatus": "NOT_AVAILABLE",  
    "canarySettings": {  
        "deploymentId": "eh1sby",  
        "useStageCache": false,  
        "stageVariableOverrides": {  
            "sv2": "val3",  
            "sv1": "val2"  
        },  
        "percentTraffic": 10.5  
    },  
    "createdDate": "2017-11-20T04:42:19Z",  
    "deploymentId": "nfcn0x",  
    "lastUpdatedDate": "2017-11-22T00:54:28Z",  
    "methodSettings": {  
        ...  
    },  
    "stageName": "prod",  
    "variables": {  
        "sv1": "val1"  
    }  
}
```

Use the following [update-stage](#) command to promote the canary:

```
aws apigateway update-stage \  
  --rest-api-id {rest-api-id} \  
  --stage-name prod
```

```
--stage-name '{stage-name}' \
--patch-operations '[{
    "op": "replace",
    "value": "0.0",
    "path": "/canarySettings/percentTraffic"
}, {
    "op": "copy",
    "from": "/canarySettings/stageVariableOverrides",
    "path": "/variables"
}, {
    "op": "copy",
    "from": "/canarySettings/deploymentId",
    "path": "/deploymentId"
}]'
```

The output will look like the following:

```
{
  "_links": {
    ...
  },
  "accessLogSettings": {
    ...
  },
  "cacheClusterEnabled": false,
  "cacheClusterStatus": "NOT_AVAILABLE",
  "canarySettings": {
    "deploymentId": "eh1sby",
    "useStageCache": false,
    "stageVariableOverrides": {
      "sv2": "val3",
      "sv1": "val2"
    },
    "percentTraffic": 0
  },
  "createdDate": "2017-11-20T04:42:19Z",
  "deploymentId": "eh1sby",
  "lastUpdatedDate": "2017-11-22T05:29:47Z",
  "methodSettings": {
    ...
  },
  "stageName": "prod",
  "variables": {
```

```
        "sv2": "val3",
        "sv1": "val2"
    }
}
```

Promoting a canary release to the stage does not disable the canary and the deployment remains to be a canary release deployment. To make it a regular production release deployment, you must disable the canary settings. For more information about how to disable a canary release deployment, see [the section called “Turn off a canary release”](#).

Turn off a canary release

To turn off a canary release deployment is to set the [canarySettings](#) to null to remove it from the stage.

You can disable a canary release deployment using the API Gateway console, the AWS CLI, or an AWS SDK.

Topics

- [Turn off a canary release using the API Gateway console](#)
- [Turn off a canary release using the AWS CLI](#)

Turn off a canary release using the API Gateway console

To use the API Gateway console to turn off a canary release deployment, use the following steps:

To turn off a canary release deployment

1. Sign in to the API Gateway console and choose an existing API in the main navigation pane.
2. In the main navigation pane, choose **Stages**, and then choose an existing stage.
3. Choose the **Canary** tab.
4. Choose **Delete**.
5. Confirm you want to delete the canary by choosing **Delete**.

As a result, the [canarySettings](#) property becomes null and is removed from the deployment [stage](#). You can verify this using the AWS CLI. For example, see [the section called “Turn off a canary release using the AWS CLI”](#).

Turn off a canary release using the AWS CLI

The following [update-stage](#) command turns off the canary release deployment:

```
aws apigateway update-stage \
--rest-api-id abcd1234 \
--stage-name canary \
--patch-operations '[{"op":"remove", "path":"/canarySettings"}]'
```

The output looks like the following:

```
{
  "stageName": "prod",
  "accessLogSettings": {
    ...
  },
  "cacheClusterEnabled": false,
  "cacheClusterStatus": "NOT_AVAILABLE",
  "deploymentId": "nfcn0x",
  "lastUpdatedDate": 1511309280,
  "createdDate": 1511152939,
  "methodSettings": {
    ...
  }
}
```

As shown in the output, the [canarySettings](#) property is no longer present in the [stage](#) of a canary-disabled deployment.

Updates to REST APIs that require redeployment

Maintaining an API amounts to viewing, updating and deleting the existing API setups. You can maintain an API using the API Gateway console, AWS CLI, CloudFormation, an SDK or the API Gateway REST API. Updating an API involves modifying certain resource properties or configuration settings of the API. Resource updates require redeploying the API, where configuration updates do not.

The following table describes API resources that require redeployment of your API when you update them.

Resource	Notes
ApiKey	For applicable properties and supported operations, see apikey:update . The update requires redeploying the API.
Authorizer	For applicable properties and supported operations, see authorizer:update . The update requires redeploying the API.
disableExecuteApiEndpoint	The update requires modifying any stage on the API such as redeploying the API to a stage.
DocumentationPart	For applicable properties and supported operations, see documentationpart:update . The update requires redeploying the API.
DocumentationVersion	For applicable properties and supported operations, see documentationversion:update . The update requires redeploying the API.
GatewayResponse	For applicable properties and supported operations, see gatewayresponse:update . The update requires redeploying the API.
Integration	For applicable properties and supported operations, see integration:update . The update requires redeploying the API.
IntegrationResponse	For applicable properties and supported operations, see integrationresponse:update . The update requires redeploying the API.
Method	For applicable properties and supported operations, see method:update . The update requires redeploying the API.
MethodResponse	For applicable properties and supported operations, see methodresponse:update . The update requires redeploying the API.
Model	For applicable properties and supported operations, see model:update . The update requires redeploying the API.
RequestValidator	For applicable properties and supported operations, see requestvalidator:update . The update requires redeploying the API.

Resource	Notes
Resource	For applicable properties and supported operations, see resource:update . The update requires redeploying the API.
RestApi	For applicable properties and supported operations, see restapi:update . The update requires redeploying the API. This includes modifying resource policies.
VpcLink	For applicable properties and supported operations, see vpclink:update . The update requires redeploying the API.

The following table describes API configurations that don't require redeployment of your API when you update them.

Configuration	Notes
Account	For applicable properties and supported operations, see account:update . The update does not require redeploying the API.
Deployment	For applicable properties and supported operations, see deployment:update .
DomainName	For applicable properties and supported operations, see domainname:update . The update does not require redeploying the API.
BasePathMapping	For applicable properties and supported operations, see basepathmapping:update . The update does not require redeploying the API.
IP address type	The update does not require redeploying the API.
Stage	For applicable properties and supported operations, see stage:update . The update does not require redeploying the API.
Usage	For applicable properties and supported operations, see usage:update . The update does not require redeploying the API.
UsagePlan	For applicable properties and supported operations, see usageplan:update . The update does not require redeploying the API.

Custom domain name for public REST APIs in API Gateway

Custom domain names are simpler and more intuitive URLs that you can provide to your API users.

After deploying your API, you (and your customers) can invoke the API using the default base URL of the following format:

```
https://api-id.execute-api.region.amazonaws.com/stage
```

where *api-id* is generated by API Gateway, *region* is the AWS Region, and *stage* is specified by you when deploying the API.

The hostname portion of the URL, *api-id*.execute-api.*region*.amazonaws.com refers to an API endpoint. The default API endpoint name is randomly generated, difficult to recall, and not user-friendly.

With custom domain names, you can set up your API's hostname, and choose a base path (for example, myservice) to map the alternative URL to your API. For example, a more user-friendly API base URL can become:

```
https://api.example.com/myservice
```

Note

For information about custom domain names for private APIs, see [the section called "Custom domain names for private APIs".](#)

Considerations

The following considerations might impact your use of a custom domain name:

- You can disable the default endpoint for your API. Clients can still connect to your default endpoint, but they will receive a 403 Forbidden status code.
- A Regional custom domain name can be associated with REST APIs and HTTP APIs. You can use the [API Gateway Version 2 APIs](#) to create and manage Regional custom domain names for REST APIs.
- A custom domain name must be unique within a Region across all AWS accounts.

- You can migrate your custom domain name between edge-optimized and Regional endpoints, but you can't migrate a public custom domain to a private custom domain name.
- You must create or update your DNS provider's resource record to map to your API endpoint. Without such a mapping, API requests bound for the custom domain name cannot reach API Gateway.
- You can support an almost infinite number of domain names without exceeding the default quota by using a wildcard certificate. For more information, see [the section called "Wildcard custom domain names"](#).
- You can choose a security policy for your custom domain name. For more information, see [the section called "Choose a security policy"](#).
- To configure API mappings with multiple levels, you must use a Regional custom domain name and use the TLS 1.2 security policy.

Prerequisites for custom domain names

The following are prerequisites for creating a public or private custom domain name. For information about custom domain names for private APIs, see [the section called "Custom domain names for private APIs"](#).

Register a domain name

You must have a registered internet domain name in order to set up custom domain names for your APIs. You can register your internet domain name using [Amazon Route 53](#) or using a third-party domain registrar of your choice. Your custom domain name can be the name of a subdomain or the root domain (also known as the "zone apex") of a registered internet domain.

Your domain name must follow the [RFC 1035](#) specification and can have a maximum of 63 octets per label and 255 octets in total.

Specify the certificate for your custom domain name

Before setting up a custom domain name for an API, you must have an SSL/TLS certificate ready in ACM. If ACM is not available in the AWS Region where you are creating your custom domain name, you must import a certificate to API Gateway in that Region.

To import an SSL/TLS certificate, you must provide the PEM-formatted SSL/TLS certificate body, its private key, and the certificate chain for the custom domain name.

Each certificate stored in ACM is identified by its ARN. With certificates issued by ACM, you do not have to worry about exposing any sensitive certificate details, such as the private key. To use an AWS managed certificate for a domain name, you simply reference its ARN.

If your application uses certificate pinning, sometimes known as SSL pinning, to pin an ACM certificate, the application might not be able to connect to your domain after AWS renews the certificate. For more information, see [Certificate pinning problems](#) in the *AWS Certificate Manager User Guide*.

Wildcard custom domain names

With wildcard custom domain names, you can support an almost infinite number of domain names without exceeding the [default quota](#). For example, you could give each of your customers their own domain name, *customername*.example.com.

To create a wildcard custom domain name, specify a wildcard (*) as the first subdomain of a custom domain that represents all possible subdomains of a root domain.

For example, the wildcard custom domain name *.example.com results in subdomains such as a.example.com, b.example.com, and c.example.com. When you create the wildcard custom domain name, all its subdomains are routed by the routing mode of the wildcard domain name. To route subdomains to different APIs, you can do either of the following:

- Use routing rules to route incoming requests to *.example.com to different target REST APIs using the Host header. For more information, see [the section called “Example 4: Routing rules for wildcard domain names”](#).
- Create a domain name for any subdomains that you want to route to a different endpoint. In a single AWS account, you can have both *.example.com and a.example.com.

You can use the \$context.domainName and \$context.domainPrefix context variables to determine the domain name that a client used to call your API. To learn more about context variables, see [Variables for data transformations for API Gateway](#).

To create a wildcard custom domain name, you must provide a certificate issued by ACM that has been validated using either the DNS or the email validation method.

Note

You can't create a wildcard custom domain name if a different AWS account has created a custom domain name that conflicts with the wildcard custom domain name. For example, if account A has created a.example.com, then account B can't create the wildcard custom domain name *.example.com.

If account A and account B share an owner, you can contact the [AWS Support Center](#) to request an exception.

Next steps for custom domain names

The following are next steps for custom domain names.

Next steps

- To learn how to set your SSL/TLS certificate, see [the section called "Get certificates ready in AWS Certificate Manager"](#).
- To learn how to create a Regional custom domain name, see [the section called "Set up a Regional custom domain name"](#).
- To learn how to create an edge-optimized custom domain name, see [the section called "Set up an edge-optimized custom domain name in API Gateway"](#).
- To learn how to migrate between Regional and edge-optimized custom domain names, see [the section called "Migrate custom domain names"](#).
- To learn how to connect API stages to a custom domain name, see [the section called "Send traffic to your APIs through your custom domain name in API Gateway"](#).
- To learn how to choose a security policy for your custom domain name, see [the section called "Choose a security policy"](#).
- To learn how to turn off the default endpoint for your custom domain name, see [the section called "Disable the default endpoint"](#).
- To learn how to use Route 53 health checks to control DNS failover from an API Gateway API, see [the section called "DNS failover"](#).

If this is your first time creating a custom domain name, we recommend that you start with [the section called "Get certificates ready in AWS Certificate Manager"](#), to specify your certificate, and

then [the section called “Set up a Regional custom domain name”](#) to create a Regional custom domain name.

Get certificates ready in AWS Certificate Manager

Before setting up a custom domain name for an API, you must have an SSL/TLS certificate ready in AWS Certificate Manager. For more information, see the [AWS Certificate Manager User Guide](#).

Considerations

The following are considerations for your SSL/TLS certificate.

- If you create an edge-optimized custom domain name, API Gateway leverages CloudFront to support certificates for custom domain names. As such, the requirements and constraints of a custom domain name SSL/TLS certificate are dictated by [CloudFront](#). For example, the maximum size of the public key is 2048 and the private key size can be 1024, 2048, and 4096. The public key size is determined by the certificate authority you use. Ask your certificate authority to return keys of a size different from the default length. For more information, see [Secure access to your objects](#) and [Create signed URLs and signed cookies](#).
- If you create a Regional custom domain name, the maximum size of the public key is 2048.
- To use an ACM certificate with a Regional custom domain name, you must request or import the certificate in the same Region as your API. The certificate must cover the custom domain name.
- To use an ACM certificate with an edge-optimized custom domain name, you must request or import the certificate in the US East (N. Virginia) – us-east-1 Region.
- You must have a registered domain name, such as *example.com*. You can use either [Amazon Route 53](#) or a third-party accredited domain registrar. For a list of such registrars, see [Accredited Registrar Directory](#) at the ICANN website.

To create or import an SSL/TLS certificate into ACM

The following procedures show how to create or import an SSL/TLS certificate for a domain name.

To request a certificate provided by ACM for a domain name

1. Sign in to the [AWS Certificate Manager console](#).
2. Choose **Request a certificate**.
3. For **Certificate type**, choose **Request a public certificate**.

4. Choose **Next**.
5. For **Fully qualified domain name**, enter a custom domain name for your API, for example, `api.example.com`.
6. Optionally, choose **Add another name to this certificate**.
7. For **Validation method**, choose a method for validating domain ownership.
8. For **Key algorithm**, choose an encryption algorithm.
9. Choose **Request**.
10. For a valid request, a registered owner of the internet domain must consent to the request before ACM issues the certificate. If you use Route 53 to manage your public DNS records, you can update your records through the ACM console directly.

To import into ACM a certificate for a domain name

1. Get a PEM-encoded SSL/TLS certificate for your custom domain name from a certificate authority. For a partial list of such CAs, see the [Mozilla Included CA List](#).
 - a. Generate a private key for the certificate and save the output to a file, using the [OpenSSL](#) toolkit at the OpenSSL website:

```
openssl genrsa -out private-key-file 2048
```
 - b. Generate a certificate signing request (CSR) with the previously generated private key, using OpenSSL:

```
openssl req -new -sha256 -key private-key-file -out CSR-file
```
 - c. Submit the CSR to the certificate authority and save the resulting certificate.
 - d. Download the certificate chain from the certificate authority.

 **Note**

If you obtain the private key in another way and the key is encrypted, you can use the following command to decrypt the key before submitting it to API Gateway for setting up a custom domain name.

```
openssl pkcs8 -topk8 -inform pem -in MyEncryptedKey.pem -outform pem -nocrypt -out MyDecryptedKey.pem
```

2. Upload the certificate to AWS Certificate Manager:

- a. Sign in to the [AWS Certificate Manager console](#).
- b. Choose **Import a certificate**.
- c. For **Certificate body**, enter the body of the PEM-formatted server certificate from your certificate authority. The following shows an abbreviated example of such a certificate.

```
-----BEGIN CERTIFICATE-----  
EXAMPLECA+KgAwIBAgIQJ1XxJ8P1++g0fQtj0IBoqDANBgkqhkiG9w0BAQUFADBB  
...  
az8Cg1aicxLBQ7EaWIhhgEXAMPLE  
-----END CERTIFICATE-----
```

- d. For **Certificate private key**, enter your PEM-formatted certificate's private key. The following shows an abbreviated example of such a key.

```
-----BEGIN RSA PRIVATE KEY-----  
EXAMPLEBAAKCAQEA2Qb3LDHD7StY7Wj6U2/opV6Xu37qUCCkeDWhwpZMYJ9/nET0  
...  
1qGvJ3u04vdnzaYN5WoyN5LFckrlA71+CszD1CGSqbVDWEXAMPLE  
-----END RSA PRIVATE KEY-----
```

- e. For **Certificate chain**, enter the PEM-formatted intermediate certificates and, optionally, the root certificate, one after the other without any blank lines. If you include the root certificate, your certificate chain must start with intermediate certificates and end with the root certificate. Use the intermediate certificates provided by your certificate authority. Do not include any intermediaries that are not in the chain of trust path. The following shows an abbreviated example.

```
-----BEGIN CERTIFICATE-----  
EXAMPLECA4ugAwIBAgIQWrYdrB5NogYUx1U9Pamy3DANBgkqhkiG9w0BAQUFADCB  
...  
8/ifBLIK3se2e4/hEfcEejX/arxbx1BJCHBv1EPNnsdw8EXAMPLE  
-----END CERTIFICATE-----
```

Here is another example.

```
-----BEGIN CERTIFICATE-----  
Intermediate certificate 2  
-----END CERTIFICATE-----  
-----BEGIN CERTIFICATE-----  
Intermediate certificate 1  
-----END CERTIFICATE-----  
-----BEGIN CERTIFICATE-----  
Optional: Root certificate  
-----END CERTIFICATE-----
```

- f. Choose **Next**, and then choose **Next**.

After the certificate is successfully created or imported, make note of the certificate ARN. You need it when setting up the custom domain name.

Set up a Regional custom domain name in API Gateway

Use a Regional custom domain name to create a user-friendly API base URL. With a Regional custom domain name, you can map HTTP and REST API stages to the same custom domain name and use mutual TLS authentication.

Considerations

The following are considerations for your Regional custom domain name:

- You must provide a Region-specific ACM certificate. This certificate must be in the same Region as your API. For more information about creating or uploading a custom domain name certificate, see [the section called “Get certificates ready in AWS Certificate Manager”](#).
- When you create a Regional custom domain name (or migrate one) with an ACM certificate, API Gateway creates a service-linked role in your account. The service-linked role is required to attach your ACM certificate to your Regional endpoint. The role is named **AWSServiceRoleForAPIGateway** and will have the **APIGatewayServiceRolePolicy** managed policy attached to it. For more information about use of the service-linked role, see [Using Service-Linked Roles](#).
- After you create your Regional custom domain name, you must create a DNS record to point the custom domain name to the Regional domain. This enables the traffic that is bound to the custom domain name to be routed to the API's Regional hostname.

The DNS record can be the CNAME or an A Alias record. If you use Route 53 as your DNS provider, create an A Alias record. If you use a third-party DNS provider, use a CNAME record. If you use a CNAME record and create an API Gateway interface VPC endpoint with private DNS enabled for a private API, you can't resolve the custom domain name within the VPC that hosts your private API.

Create a Regional custom domain name

The following procedure shows how to create a Regional custom domain name. After you complete this procedure, you create a routing rule to route stages of your API to your custom domain name.

AWS Management Console

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose **Custom domain names** from the main navigation pane.
3. Choose **Create**.
4. For **Domain name**, enter a domain name.
5. For **Routing mode**, choose **Routing rules only**.

In this routing mode, you can only send traffic from your custom domain name to your APIs by using routing rules. For more information, see [the section called "Send traffic to your APIs through your custom domain name in API Gateway"](#).

6. For **Minimum TLS version**, select a version.
7. Under **Endpoint configuration**, for **API endpoint type**, choose **Regional**.
8. Choose an ACM certificate. The certificate must be in the same Region as the API.
9. Choose **Create**.

AWS CLI

The following [create-domain-name](#) command creates a custom domain name:

```
aws apigatewayv2 create-domain-name \
--domain-name 'regional.example.com' \
--domain-name-configurations CertificateArn=arn:aws:acm:us-
west-2:123456789012:certificate/123456789012-1234-1234-1234-12345678 \
--routing-mode ROUTING_RULE_ONLY
```

The output will look like the following:

```
{  
    "ApiMappingSelectionExpression": "$request.basepath",  
    "DomainName": "regional.example.com",  
    "DomainNameConfigurations": [  
        {  
            "ApiGatewayDomainName": "d-numh1z56v6.execute-api.us-  
west-2.amazonaws.com",  
            "CertificateArn": "arn:aws:acm:us-  
west-2:123456789012:certificate/123456789012-1234-1234-1234-12345678",  
            "DomainNameStatus": "AVAILABLE",  
            "EndpointType": "REGIONAL",  
            "HostedZoneId": "Z20JLYMU09EFXC",  
            "SecurityPolicy": "TLS_1_2"  
        }  
        "RoutingMode": "ROUTING_RULE_ONLY"  
    ]  
}
```

The `DomainNameConfigurations` property value returns the Regional API's hostname. You must create a DNS record to point your custom domain name to this Regional domain name. This enables the traffic that is bound to the custom domain name to be routed to this Regional API's hostname.

Create a routing rule for your Regional custom domain name

After you create your custom domain name, you configure how traffic is routed from your custom domain name to your APIs. Because you set the routing mode to `ROUTING_RULE_ONLY`, you use routing rules to route incoming requests to your custom domain name to your APIs.

In this example, you create a catch-all rule that routes all incoming requests to your custom domain name to one stage of your API. You can also configure routing rules based on different header and path conditions. For more information, see [the section called “Routing rules”](#).

AWS Management Console

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose a custom domain name.
3. On the **Routing details** tab, choose **Add routing rule**.

4. Choose **Add a new condition** to add a new condition.
5. Keep this rule without any conditions. This routes all requests to your custom domain name to your target API and target stage.
6. For **Action**, use the dropdown to select your target API and target stage.
7. Choose **Next**.
8. In the priority field, enter **100**.

API Gateway evaluates rules in priority order, from the lowest value to the highest value.

Because this is a catch-all rule, you use a high priority so API Gateway can match any additional rules you create first.

9. Choose **Create routing rule**.

AWS CLI

The following `create-routing-rule` command creates a catch-all routing rule:

```
aws apigatewayv2 create-routing-rule \
--domain-name 'regional.example.com' \
--priority 100 \
--conditions \
--actions '[{
    "InvokeApi": {
        "ApiId": "a1b2c3",
        "Stage": "prod"
    }
}]'
```

You can change the routing mode and create new rules at any time. For more information, see [the section called “Send traffic to your APIs through your custom domain name in API Gateway”](#).

Create a DNS record for your Regional custom domain name

After you create your custom domain name and create base path mappings, you create a DNS record to point your custom domain name to your newly created Regional domain name.

AWS Management Console

To use the AWS Management Console, follow the Route 53 documentation on [configuring Route 53 to route traffic to API Gateway](#).

AWS CLI

To configure your DNS records to map the Regional custom domain name to its hostname of the given hosted zone ID, first create a JSON file that contains the configuration for setting up a DNS record for the Regional domain name.

The following `setup-dns-record.json` shows how to create a DNS A record to map a Regional custom domain name (`regional.example.com`) to its Regional hostname (`d-numh1z56v6.execute-api.us-west-2.amazonaws.com`) provisioned as part of the custom domain name creation. The `DNSName` and `HostedZoneId` properties of `AliasTarget` can take the `regionalDomainName` and `regionalHostedZoneId` values, respectively, of the custom domain name. You can also get the Regional Route 53 Hosted Zone IDs in [Amazon API Gateway Endpoints and Quotas](#).

```
{  
    "Changes": [  
        {  
            "Action": "CREATE",  
            "ResourceRecordSet": {  
                "Name": "regional.example.com",  
                "Type": "A",  
                "AliasTarget": {  
                    "DNSName": "d-numh1z56v6.execute-api.us-west-2.amazonaws.com",  
                    "HostedZoneId": "Z20JLYMU09EFCX",  
                    "EvaluateTargetHealth": false  
                }  
            }  
        }  
    ]  
}
```

The following [change-resource-record-sets](#) creates a DNS record for your Regional custom domain name:

```
aws route53 change-resource-record-sets \  
  --hosted-zone-id Z20JLYMU09EFCX \  
  --change-batch file://path/to/your/setup-dns-record.json
```

Replace the `hosted-zone-id` with the Route 53 Hosted Zone ID of the DNS record set in your account. The `change-batch` parameter value points to a JSON file (`setup-dns-record.json`) in a folder (`path/to/your`).

Set up an edge-optimized custom domain name in API Gateway

When you create a custom domain name for an edge-optimized API, API Gateway sets up a CloudFront distribution and a DNS record to map the API domain name to the CloudFront distribution domain name. Requests for the API are then routed to API Gateway through the mapped CloudFront distribution. This mapping is for API requests that are bound for the custom domain name to be routed to API Gateway through the mapped CloudFront distribution.

Considerations

The following are considerations for your edge-optimized custom domain name:

- To set up an edge-optimized custom domain name or to update its certificate, you must have a permission to update CloudFront distributions.

The following permissions are required to update CloudFront distributions:

JSON

```
{  
    "Version": "2012-10-17",  
    "Statement": [  
        {  
            "Sid": "AllowCloudFrontUpdateDistribution",  
            "Effect": "Allow",  
            "Action": [  
                "cloudfront:updateDistribution"  
            ],  
            "Resource": [  
                "*"  
            ]  
        }  
    ]  
}
```

- You must request or import a certificate for your edge-optimized custom domain name in the US East (N. Virginia) – us-east-1 Region.
- The CloudFront distribution created by API Gateway is owned by a Region-specific account affiliated with API Gateway. When tracing operations to create and update such a CloudFront distribution in CloudTrail, you must use this API Gateway account ID. For more information, see [Log custom domain name creation in CloudTrail](#).

- API Gateway supports edge-optimized custom domain names by leveraging Server Name Indication (SNI) on the CloudFront distribution. For more information on using custom domain names on a CloudFront distribution, including the required certificate format and the maximum size of a certificate key length, see [Using Alternate Domain Names and HTTPS](#) in the *Amazon CloudFront Developer Guide*
- An edge-optimized custom domain names takes about 40 minutes to be ready.
- After you create your edge-optimized custom domain name, you must create a DNS record to map the custom domain name to the CloudFront distribution name.

Create an edge-optimize custom domain name

The following procedure describes how to create an edge-optimized custom domain name for an API.

AWS Management Console

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose **Custom domain names** from the main navigation pane.
3. Choose **Add domain name**.
4. For **Domain name**, enter a domain name.
5. For **Routing mode**, choose **API_MAPPING_ONLY**.
6. For **API endpoint type**, choose **Edge-optimized**.
7. Choose a minimum TLS version.
8. Choose an ACM certificate.
9. Choose **Add domain name**.

REST API

1. Call [domainname:create](#), specifying the custom domain name and the ARN of a certificate stored in AWS Certificate Manager.

The successful API call returns a 201 Created response containing the certificate ARN as well as the associated CloudFront distribution name in its payload.

2. Note the CloudFront distribution domain name shown in the output. You need it in the next step to set the custom domain's A-record alias target in your DNS.

For code examples of this REST API call, see [domainname:create](#).

An edge-optimized custom domain names takes about 40 minutes to be ready, but the console immediately displays the associated CloudFront distribution domain name, in the form of ***distribution-id*.cloudfront.net**, along with the certificate ARN. In the meantime, you can create a base path mapping or a routing rule and then configure the DNS record alias to map the custom domain name to the associated CloudFront distribution domain name.

Configure base path mapping of an API with a custom domain name as its hostname

Because you set the routing mode to API_MAPPING_ONLY, you can use base path mapping to use a single custom domain name as the hostname of multiple APIs. This makes an API accessible through the combination of the custom domain name and the associated base path.

For example, if in API Gateway, you created an API named PetStore and another API named Dogs and then set up a custom domain name of `api.example.com`, you can set the PetStore API's URL as `https://api.example.com`.

This associates the PetStore API with the base path of an empty string. If you set the PetStore API's URL as `https://api.example.com/PetStore`, this associates the PetStore API with the base path of PetStore. You can assign a base path of MyDogList for the Dogs API. The URL of `https://api.example.com/MyDogList` is then the root URL of the Dogs API.

To configure API mappings on multiple levels, you can only use a Regional custom domain name. Edge-optimized custom domain names are not supported. For more information, see [the section called "API mappings"](#).

The following procedure sets up API mappings to map paths from your custom domain name to your API stages.

AWS Management Console

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose **Custom domain names** from the API Gateway console main navigation pane.
3. Choose a custom domain name.
4. Choose **Configure API mappings**.
5. Choose **Add new mapping**.
6. Specify the **API**, **Stage**, and **Path** (optional) for the mapping.

7. Choose Save.

REST API

Call [basepathmapping:create](#) on a specific custom domain name, specifying the basePath, restApiId, and a deployment stage property in the request payload.

The successful API call returns a 201 Created response.

For code examples of the REST API call, see [basepathmapping:create](#).

For more flexibility on how you route traffic to your APIs, you can change the routing mode to ROUTING_RULE_ONLY or ROUTING_RULE_THEN_API_MAPPING and create a routing rule. For more information, see [the section called “Send traffic to your APIs through your custom domain name in API Gateway”](#).

Create a DNS record for your edge-optimized custom domain name

After you initiate the creation of your edge-optimized custom domain name, set up the DNS record alias.

We recommend that you use Route 53 to create an A-record alias for your custom domain name and specify the CloudFront distribution domain name as the alias target. This means that Route 53 can route your custom domain name even if it is a zone apex. For more information, see [Choosing Between Alias and Non-Alias Resource Record Sets](#) in the *Amazon Route 53 Developer Guide*.

For instructions for Amazon Route 53, see [Routing traffic to an Amazon API Gateway API by using your domain name](#) in the *Amazon Route 53 Developer Guide*.

Log custom domain name creation in CloudTrail

When CloudTrail is enabled for logging API Gateway calls made by your account, API Gateway logs the associated CloudFront distribution updates when a custom domain name is created or updated for an API. These logs are available in us-east-1. Because these CloudFront distributions are owned by API Gateway, each of these reported CloudFront distributions is identified by one of the following Region-specific API Gateway account IDs, instead of the API owner's account ID.

Region	Account ID
us-east-1	392220576650

Region	Account ID
us-east-2	718770453195
us-west-1	968246515281
us-west-2	109351309407
ca-central-1	796887884028
eu-west-1	631144002099
eu-west-2	544388816663
eu-west-3	061510835048
eu-central-1	474240146802
eu-central-2	166639821150
eu-north-1	394634713161
eu-south-1	753362059629
eu-south-2	359345898052
ap-northeast-1	969236854626
ap-northeast-2	020402002396
ap-northeast-3	360671645888
ap-southeast-1	195145609632
ap-southeast-2	798376113853
ap-southeast-3	652364314486
ap-southeast-4	849137399833
ap-south-1	507069717855

Region	Account ID
ap-south-2	644042651268
ap-east-1	174803364771
sa-east-1	287228555773
me-south-1	855739686837
me-central-1	614065512851

Rotate a certificate imported into ACM

ACM automatically handles renewal of certificates it issues. You do not need to rotate any ACM-issued certificates for your custom domain names. CloudFront handles it on your behalf.

However, if you import a certificate into ACM and use it for a custom domain name, you must rotate the certificate before it expires. This involves importing a new third-party certificate for the domain name and rotate the existing certificate to the new one. You need to repeat the process when the newly imported certificate expires. Alternatively, you can request ACM to issue a new certificate for the domain name and rotate the existing one to the new ACM-issued certificate. After that, you can leave ACM and CloudFront to handle the certificate rotation for you automatically. To create or import a new ACM certificate, follow the steps in [the section called “To create or import an SSL/TLS certificate into ACM”](#).

The following procedure describes how to rotate a certificate for a domain name.

 **Note**

It takes about 40 minutes to rotate a certificate imported into ACM.

AWS Management Console

1. Request or import a certificate in ACM.
2. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
3. Choose **Custom domain names** from the API Gateway console main navigation pane.

4. Choose an edge-optimized custom domain name.
5. For **Endpoint configuration**, choose **Edit**.
6. For **ACM certificate**, select a certificate from dropdown list.
7. Choose **Save changes** to begin rotating the certificate for the custom domain name.

REST API

Call [domainname:update](#) action, specifying the ARN of the new ACM certificate for the specified domain name.

AWS CLI

The following [update-domain-name](#) updates the ACM certificate for an edge-optimized domain name.

```
aws apigateway update-domain-name \
--domain-name edge.example.com \
--patch-operations "op='replace',path='/certificateArn',value='arn:aws:acm:us-
east-2:111122223333:certificate/CERTEXAMPLE123EXAMPLE'"
```

The following [update-domain-name](#) updates the ACM certificate for a Regional domain name.

```
aws apigateway update-domain-name \
--domain-name regional.example.com \
--patch-operations "op='replace',path='/
regionalCertificateArn',value='arn:aws:acm:us-east-2:111122223333:certificate/
CERTEXAMPLE123EXAMPLE'"
```

Call your API with custom domain names when you use a base path mapping

Calling an API with a custom domain name is the same as calling the API with its default domain name, provided that the correct URL is used.

The following examples compare and contrast a set of default URLs and corresponding custom URLs of two APIs (udxjef and qf3duz) in a specified Region (us-east-1), and of a given custom domain name (api.example.com).

API ID	Stage	Default URL	Base path	Custom URL
udxjef	prod	<code>https://udxjef.execute-api.us-east-1.amazonaws.com/prod</code>	/petstore	<code>https://api.example.com/petstore</code>
udxjef	tst	<code>https://udxjef.execute-api.us-east-1.amazonaws.com/tst</code>	/petdepot	<code>https://api.example.com/petdepot</code>
qf3duz	dev	<code>https://qf3duz.execute-api.us-east-1.amazonaws.com/dev</code>	/bookstore	<code>https://api.example.com/bookstore</code>
qf3duz	tst	<code>https://qf3duz.execute-api.us-east-1.amazonaws.com/tst</code>	/bookstand	<code>https://api.example.com/bookstand</code>

For more flexibility on how you route traffic to your APIs, you can create a routing rule. For more information, see [the section called “Send traffic to your APIs through your custom domain name in API Gateway”](#).

API Gateway supports custom domain names for an API by using [Server Name Indication \(SNI\)](#). You can invoke the API with a custom domain name using a browser or a client library that supports SNI.

API Gateway enforces SNI on the CloudFront distribution. For information on how CloudFront uses custom domain names, see [Amazon CloudFront Custom SSL](#).

Migrate a custom domain name to a different API endpoint type in API Gateway

You can migrate your custom domain name between edge-optimized and Regional endpoints. You can't migrate a public custom domain name to a private custom domain name. You first add the new endpoint configuration type to the existing `endpointConfiguration.types` list for the custom domain name. Next, you set up a DNS record to point the custom domain name to the newly provisioned endpoint. Finally, you remove the obsolete custom domain name endpoint.

Considerations

The following are considerations for migrating your custom domain between a Regional API endpoint and an edge-optimized API endpoint:

- An edge-optimized custom domain name requires a certificate provided by ACM from the US East (N. Virginia) – `us-east-1` Region. This certificate is distributed to all the geographic locations.
- A Regional custom domain name requires a certificate provided by ACM in the same Region hosting the API. You can migrate an edge-optimized custom domain name that is not in the `us-east-1` Region to a Regional custom domain name by requesting a new ACM certificate from the Region that is local to the API.
- It might take up to 60 seconds to complete a migration between an edge-optimized custom domain name and a Regional custom domain name. The migration time also depends on when you update your DNS records.
- You can only add an additional endpoint configuration if the endpoint access mode is set to BASIC. Once you have two endpoint configurations, you can't change the endpoint access mode. For more information, see [the section called “Endpoint access mode”](#).
- If your custom domain name uses a security policy that starts with `SecurityPolicy_`, when you add a new endpoint configuration type, the endpoint access mode is the same across both endpoint types, and you must choose a security policy that starts with `SecurityPolicy_` for the new endpoint configuration type.

Migrate custom domain names

Note

To complete the migration, make sure that you remove the obsolete endpoint from your custom domain name.

The following procedure shows how to migrate an edge-optimized custom domain name to a Regional custom domain name.

AWS Management Console

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose **Custom domain names** from the main navigation pane.
3. Choose an edge-optimized custom domain name.
4. For **Endpoint configuration**, choose **Edit**.
5. Choose **Add Regional endpoint**.
6. For **ACM certificate**, choose a certificate.

The Regional certificate must be in the same Region as the Regional API.

7. Choose **Save changes**.
8. Set up a DNS record to point the Regional custom domain name to this Regional hostname. For more information, see [configuring Route 53 to route traffic to API Gateway](#).
9. After you confirm that your DNS configuration is using the correct endpoint, you delete the edge-optimized endpoint configuration. Choose your custom domain name, and then for **Edge-optimized endpoint configuration**, choose **Delete**.
10. Confirm your choice and delete the endpoint.

AWS CLI

The following [update-domain-name](#) command migrates an edge-optimized custom domain name to a Regional custom domain name:

```
aws apigateway update-domain-name \
--domain-name 'api.example.com' \
--patch-operations '[
    { "op":"add", "path": "/endpointConfiguration/types", "value": "REGIONAL" },
    { "op":"add", "path": "/regionalCertificateArn", "value": "arn:aws:acm:us-west-2:123456789012:certificate/cd833b28-58d2-407e-83e9-dce3fd852149" }
]'
```

The Regional certificate must be of the same Region as the Regional API.

The output will look like the following:

```
{  
    "certificateArn": "arn:aws:acm:us-  
east-1:123456789012:certificate/34a95aa1-77fa-427c-aa07-3a88bd9f3c0a",  
    "certificateName": "edge-cert",  
    "certificateUploadDate": "2017-10-16T23:22:57Z",  
    "distributionDomainName": "d1frvgze7vy1bf.cloudfront.net",  
    "domainName": "api.example.com",  
    "endpointConfiguration": {  
        "types": [  
            "EDGE",  
            "REGIONAL"  
        ]  
    },  
    "regionalCertificateArn": "arn:aws:acm:us-west-2:123456789012:certificate/  
cd833b28-58d2-407e-83e9-dce3fd852149",  
    "regionalDomainName": "d-fdisjghyn6.execute-api.us-west-2.amazonaws.com"  
}
```

For the migrated Regional custom domain name, the resulting `regionalDomainName` property returns the Regional API hostname. You must set up a DNS record to point the Regional custom domain name to this Regional hostname. This enables the traffic that is bound to the custom domain name to be routed to the Regional host.

After the DNS record is set, you can remove the edge-optimized custom domain name. The following [update-domain-name](#) command removes the edge-optimized custom domain name:

```
aws apigateway update-domain-name \  
--domain-name api.example.com \  
--patch-operations '[  
    {"op":"remove", "path":"/endpointConfiguration/types", "value":"EDGE"},  
    {"op":"remove", "path":"certificateName"},  
    {"op":"remove", "path":"certificateArn"}  
]'
```

The following procedure shows how to migrate an edge-optimized custom domain name that uses an enhanced security policy to a Regional custom domain name that also uses an enhanced security policy.

AWS Management Console

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose **Custom domain names** from the main navigation pane.
3. Choose an edge-optimized custom domain name.
4. For **Endpoint configuration**, choose **Edit**.
5. Choose **Add Regional endpoint**.
6. For **ACM certificate**, choose a certificate.

The Regional certificate must be in the same Region as the Regional API.

7. For **Security policy**, choose a security policy that starts with **SecurityPolicy_**.
8. For **Endpoint access mode**, choose **Basic**.
9. Choose **Save changes**.
10. Set up a DNS record to point the Regional custom domain name to this Regional hostname.
For more information, see [configuring Route 53 to route traffic to API Gateway](#).
11. After you confirm that your DNS configuration is using the correct endpoint, you delete the edge-optimized endpoint configuration. Choose your custom domain name, and then for **Edge-optimized endpoint configuration**, choose **Delete**.
12. Confirm your choice and delete the endpoint.

AWS CLI

The following [update-domain-name](#) command migrates an edge-optimized custom domain name to a Regional custom domain name:

```
aws apigateway update-domain-name \
--domain-name 'api.example.com' \
--patch-operations '[
    { "op":"add", "path": "/endpointConfiguration/types", "value": "REGIONAL" },
    { "op":"replace", "path": "/securityPolicy",
"value":"SecurityPolicy_TLS13_1_3_2025_09"},
    { "op":"add", "path": "/regionalCertificateArn", "value": "arn:aws:acm:us-
west-2:123456789012:certificate/cd833b28-58d2-407e-83e9-dce3fd852149" }
]'
```

The Regional certificate must be of the same Region as the Regional API.

The output will look like the following:

```
{  
    "certificateArn": "arn:aws:acm:us-  
east-1:123456789012:certificate/34a95aa1-77fa-427c-aa07-3a88bd9f3c0a",  
    "certificateName": "edge-cert",  
    "certificateUploadDate": "2017-10-16T23:22:57Z",  
    "distributionDomainName": "d1frvgze7vy1bf.cloudfront.net",  
    "domainName": "api.example.com",  
    "endpointConfiguration": {  
        "types": [  
            "EDGE",  
            "REGIONAL"  
        ]  
    },  
    "securityPolicy": "SecurityPolicy_TLS13_1_3_2025_09",  
    "endpointAccessMode": "BASIC",  
    "regionalCertificateArn": "arn:aws:acm:us-west-2:123456789012:certificate/  
cd833b28-58d2-407e-83e9-dce3fd852149",  
    "regionalDomainName": "d-fdisjghyn6.execute-api.us-west-2.amazonaws.com"  
}
```

For the migrated Regional custom domain name, the resulting `regionalDomainName` property returns the Regional API hostname. You must set up a DNS record to point the Regional custom domain name to this Regional hostname. This enables the traffic that is bound to the custom domain name to be routed to the Regional host.

After the DNS record is set, you can remove the edge-optimized custom domain name. The following [update-domain-name](#) command removes the edge-optimized custom domain name:

```
aws apigateway update-domain-name \  
--domain-name api.example.com \  
--patch-operations '[  
    {"op":"remove", "path":"/endpointConfiguration/types", "value":"EDGE"},  
    {"op":"remove", "path":"certificateName"},  
    {"op":"remove", "path":"certificateArn"}  
'
```

The following procedure shows how to migrate a Regional custom domain name to an edge-optimized custom domain name.

AWS Management Console

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. In the main navigation pane, choose **Custom domain names**.
3. Choose a Regional custom domain name.
4. For **Endpoint configuration**, choose **Edit**.
5. Choose **Add edge-optimized endpoint**.
6. For **ACM certificate**, choose a certificate.

The edge-optimized domain certificate must be created in the us-east-1 Region.

7. Choose **Save**.
8. Set up a DNS record to point the edge-optimized custom domain name to this edge-optimized hostname. For more information, see [configuring Route 53 to route traffic to API Gateway](#).
9. After you confirm that your DNS configuration is using the correct endpoint, you delete the Regional endpoint configuration. Choose your custom domain name, and then for **Regional endpoint configuration**, choose **Delete**.
10. Confirm your choice and delete the endpoint.

AWS CLI

The following [update-domain-name](#) command migrates your Regional custom domain name to an edge-optimized custom domain name:

```
aws apigateway update-domain-name \
--domain-name 'api.example.com' \
--patch-operations '[
    { "op":"add", "path": "/endpointConfiguration/types", "value": "EDGE" },
    { "op":"add", "path": "/certificateName", "value": "edge-cert" },
    {"op":"add", "path": "/certificateArn", "value": "arn:aws:acm:us-
east-1:738575810317:certificate/34a95aa1-77fa-427c-aa07-3a88bd9f3c0a"}]
```

The edge-optimized domain certificate must be created in the us-east-1 Region.

The output will look like the following:

```
{  
    "certificateArn": "arn:aws:acm:us-  
east-1:738575810317:certificate/34a95aa1-77fa-427c-aa07-3a88bd9f3c0a",  
    "certificateName": "edge-cert",  
    "certificateUploadDate": "2017-10-16T23:22:57Z",  
    "distributionDomainName": "d1frvgze7vy1bf.cloudfront.net",  
    "domainName": "api.example.com",  
    "endpointConfiguration": {  
        "types": [  
            "EDGE",  
            "REGIONAL"  
        ]  
    },  
    "regionalCertificateArn": "arn:aws:acm:us-  
east-1:123456789012:certificate/3d881b54-851a-478a-a887-f6502760461d",  
    "regionalDomainName": "d-cgkq2qwgf.execute-api.us-east-1.amazonaws.com"  
}
```

For the specified custom domain name, API Gateway returns the edge-optimized API hostname as the `distributionDomainName` property value. You must set a DNS record to point the edge-optimized custom domain name to this distribution domain name. This enables traffic that is bound to the edge-optimized custom domain name to be routed to the edge-optimized API hostname.

After the DNS record is set, you can remove the REGION endpoint type of the custom domain name. The following [update-domain-name](#) command removes the Regional endpoint type:

```
aws apigateway update-domain-name \  
--domain-name api.example.com \  
--patch-operations '[  
    {"op":"remove", "path":"/endpointConfiguration/types", value:"REGIONAL"},  
    {"op":"remove", "path":"/regionalCertificateArn"}  
]'
```

The output looks like the following:

```
{  
    "certificateArn": "arn:aws:acm:us-  
east-1:738575810317:certificate/34a95aa1-77fa-427c-aa07-3a88bd9f3c0a",  
    "certificateName": "edge-cert",  
    "certificateUploadDate": "2017-10-16T23:22:57Z",
```

```
"distributionDomainName": "d1frvgze7vy1bf.cloudfront.net",
"domainName": "api.example.com",
"endpointConfiguration": {
    "types": "EDGE"
}
}
```

Send traffic to your APIs through your custom domain name in API Gateway

When you configure the routing mode for your custom domain name, you set how incoming traffic is directed to your APIs. You send traffic to your APIs using routing rules, API mappings, or routing rules and API mappings. The following section explains when to use routing rules, when to use API mappings, and how to set the routing mode for your custom domain name.

When to use routing rules

When you use routing rules, you direct incoming requests that match certain conditions to specific REST APIs stages. For example, a rule can route a request to the production stage of your users REST API if it contains the header `version:v1` and the base path `/users`. Use routing rules to create advanced dynamic routing topologies that support use cases like A/B testing or increasing usage of new versions of your APIs.

We recommend that when directing traffic to a REST API, you use routing rules for your custom domain name. You can recreate any API mappings by using routing rules. For more information, see [the section called “Recreate an API mapping using routing rules”](#).

For REST APIs, you can also use routing rules and API mappings together. When you use routing rules and API mappings together, API Gateway always evaluates routing rules before it evaluates any API mappings. Use routing rules and API mappings together to migrate your current custom domain names or to explore routing rules.

Considerations for routing rules

The following considerations might impact your use of routing rules:

- WebSocket or HTTP APIs aren't supported as target APIs for routing rules.
- If your custom domain name has API mappings to both REST and HTTP APIs, routing rules isn't supported.
- You can create a routing rule for a private custom domain to a private REST API. You can create a routing rule for a public custom domain to a Regional or edge-optimized API.

- You can't create a routing rule for a public custom domain to a private API. You can't create a routing rule for a private custom domain name to a public API.

Choose between routing rules and API mappings

We recommend that when possible, you use routing rules. Only use API mappings to send traffic to an HTTP or WebSocket API.

Set the routing mode for your custom domain name

You can choose which routing mode API Gateway uses to route traffic to your APIs. For more information, see [the section called “Send traffic to your APIs through your custom domain name in API Gateway”](#). This section discusses routing modes for custom domain names. You must set a routing mode for your custom domain name to route traffic to your APIs. The following routing modes are supported:

- **ROUTING_RULE_THEN_API_MAPPING** – Use this mode to send traffic to your APIs with both routing rules and API mappings. In this mode, all routing rules take priority over any API mappings. For an example of this mode, see [the section called “Example 2: Routing rules and API mappings”](#).
- **ROUTING_RULE_ONLY** – Use this mode to only allow routing rules to send traffic to your APIs. When your custom domain name uses this mode, you can't create an API mapping, but you can use the [get-api-mappings](#) command to view them. API callers can't use API mappings to access this domain name.
- **API_MAPPING_ONLY** – Use this mode to only allow API mappings to send traffic to your APIs. When your custom domain name uses this mode, you can't create a routing rule, but you can use the [list-routing-rules](#) command to view them. API callers can't use routing rules to access this domain name.

This is the default routing mode for all your existing domain names, and any new domain names you create.

When you create a custom domain name using `apigateway`, **API_MAPPING_ONLY** is called **BASE_PATH_MAPPING_ONLY** and **ROUTING_RULE_THEN_API_MAPPING** is called **ROUTING_RULE_THEN_BASE_PATH_MAPPING**. This behavior is only present for the AWS CLI, CloudFormation, or any SDKs, not in the AWS Management Console.

The following procedure shows how to change the routing mode for an existing custom domain name. When you change the routing mode of your custom domain name, API callers can't access your domain name using any unsupported routing modes.

AWS Management Console

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose **Custom domain names** from the main navigation pane.
3. Choose a custom domain name.
4. For **Domain details**, choose **Edit**.
5. For **Routing mode**, choose **ROUTING_RULE_THEN_API_MAPPING**.
6. Choose **Save**.

If you change the routing mode to ROUTING_RULE_ONLY or API_MAPPING_ONLY, any API mappings or routing rules you've created are removed from the domain name details page of the console. If you change the routing mode to support either routing rules or API mappings, these resources will return.

AWS CLI - apigatewayv2

The following [update-domain-name](#) command updates a domain name to use the routing mode ROUTING_RULE_THEN_API_MAPPING:

```
aws apigatewayv2 update-domain-name \
--domain-name 'api.example.com' \
--routing-mode "ROUTING_RULE_THEN_API_MAPPING"
```

The output will look like the following:

```
{
  "ApiMappingSelectionExpression": "$request.basepath",
  "DomainName": "api.example.com",
  "DomainNameArn": "arn:aws:apigateway:us-west-2::/domainnames/api.example.com",
  "DomainNameConfigurations": [
    {
      "ApiGatewayDomainName": "d-abcdefg.execute-api.us-west-2.amazonaws.com",
      "CertificateArn": "arn:aws:acm:us-west-2:111122223333:certificate/
abcdefg-123456-abcdefg",
```

```
        "DomainNameStatus": "AVAILABLE",
        "EndpointType": "REGIONAL",
        "HostedZoneId": "Z20JLYMU09EFXC",
        "SecurityPolicy": "TLS_1_2"
    }
],
"RoutingMode": "ROUTING_RULE_THEN_API_MAPPING",
"Tags": {}
}
```

AWS CLI - apigateway

The following [update-domain-name](#) command updates a private custom domain name to use the routing mode ROUTING_RULE_THEN_BASE_PATH_MAPPING:

```
aws apigateway update-domain-name \
--domain-name 'private.example.com' \
--patch-operations "op='replace',path='/
routingMode',value='ROUTING_RULE_THEN_BASE_PATH_MAPPING'"
```

The output will look like the following:

```
{
"domainName": "private.example.com",
"domainNameId": "abcd1234",
"domainNameArn": "arn:aws:apigateway:us-west-2:111122223333:/domainnames/
private.example.com+abcd1234",
"certificateArn": "arn:aws:acm:us-west-2:111122223333:certificate/
a1b2c3d4-5678-90ab-cdef",
"certificateUploadDate": "2024-09-10T10:31:20-07:00",
"endpointConfiguration": {
    "types": [
        "PRIVATE"
    ],
    "ipAddressType": "dualstack"
},
"domainNameStatus": "AVAILABLE",
"securityPolicy": "TLS_1_2",
"policy": "...",
"routingMode" : "ROUTING_RULE_THEN_BASE_PATH_MAPPING"
}
```

Routing rules to connect API stages to a custom domain name for REST APIs

A routing rule is a set of conditions that when matched, invoke an action. For example, a rule can route any incoming request to a custom domain name that contains the header Hello:World and contains the base path users to the production stage of a REST API.

Rules are evaluated in priority order, and if you set the routing mode to ROUTING_RULE_THEN_API_MAPPING, API Gateway always evaluates all routing rules before evaluating any API mappings. The following list describes how a routing rule uses conditions, actions, and priorities.

Conditions

When the conditions for a rule are met, then its actions are performed. API Gateway supports up to two header conditions and one path condition. API Gateway evaluates header conditions and base path conditions together.

You can create a rule without any conditions. When API Gateway evaluates this rule, the action is always performed. You can create a rule without any conditions as a catch-all rule.

For more information about header conditions, see [the section called “Match headers conditions”](#). For more information about path conditions, see [the section called “Match base path conditions”](#).

Actions

Actions are the result of matching conditions to a routing rule. Currently, the only supported action is to invoke a stage of a REST API.

Each rule can have one action.

Priority

The priority determines what order the rules are evaluated in, from the lowest value to the highest value. Rules can't have the same priority.

You can set the priority from 1-1,000,000. If a rule has a priority of one, API Gateway evaluates it first. We recommend that when you create a rule, you add gaps in priorities. This helps you switch the priority of rules and add new rules. For more information, see [the section called “Change the priority of a routing rule”](#).

For examples of how API Gateway evaluates routing rules, see [the section called “Examples of how API Gateway evaluates routing rules”](#).

API Gateway routing rule condition types

The following section describes the routing rule condition types. API Gateway only matches a rule if all conditions are true.

Match headers conditions

When you create a header condition, you can match the header name and header glob value, such as Hello:World. API Gateway uses a literal match to validate match headers conditions. Your condition can use up to two headers using AND between them. For example, your condition can match if an incoming request contains Hello:World and x-version:beta.

The header name matching is case insensitive, but the header glob value is case sensitive. Hello:World will match hello:World, but not Hello:world.

For a list of restricted header values see, [the section called “Restrictions”](#).

Using wildcards with header conditions

You can only use wildcards in the header glob value, and the wildcard must be *prefix-match*, suffix-match*, or *contains*. The following table shows examples for how to use wildcards for matching for header conditions.

Header conditions	Requests that match the routing rule	Requests that don't match the routing rule
x-version: a*	<ul style="list-style-type: none">• x-version: account• x-version: alpha	<ul style="list-style-type: none">• x-version: backup• x-version: beta• x-version: users
x-version: *a	<ul style="list-style-type: none">• x-version: alpha• x-version: beta	<ul style="list-style-type: none">• x-version: account• x-version: backup• x-version: users
x-version: *a*	<ul style="list-style-type: none">• x-version: account• x-version: alpha	<ul style="list-style-type: none">• x-version: users

Header conditions	Requests that match the routing rule	Requests that don't match the routing rule
	<ul style="list-style-type: none"> • x-version: backup • x-version: beta 	
x-version: *a* and x-version: *b*	<ul style="list-style-type: none"> • x-version: backup • x-version: beta 	<ul style="list-style-type: none"> • x-version: account • x-version: alpha • x-version: users
x-version: b* and x-version: *a	<ul style="list-style-type: none"> • x-version: beta 	<ul style="list-style-type: none"> • x-version: account • x-version: alpha • x-version: backup • x-version: users
x-version: *	<ul style="list-style-type: none"> • x-version: account • x-version: alpha • x-version: backup • x-version: beta • x-version: users 	None

If you create conditions for multiple header values, such as `Accept:application/json, text/xml`, we recommend that you use `*contains*` for your header conditions and avoid creating conditions using the comma (,) character.

Because API Gateway matches header conditions literally, semantic matches might be routed differently. The following table shows the difference in routing rules outcomes.

Header conditions	Requests that match the routing rule	Requests that don't match the routing rule
Accept: *json	<ul style="list-style-type: none"> • Accept:application/json Accept:text/xml 	<ul style="list-style-type: none"> • Accept:application/json, text/xml
Accept: *json*	<ul style="list-style-type: none"> • Accept:application/json Accept:text/xml 	None

Header conditions	Requests that match the routing rule	Requests that don't match the routing rule
	<ul style="list-style-type: none"> Accept:application/json, text/xml 	

Match base path conditions

When you create a base path condition, if the incoming request contains the path you specified, the rule is matched. The matching is case sensitive, so the path New/Users will not match with new/users.

You can create a base path condition for only one base path.

For a list of restricted base path conditions, [the section called "Restrictions"](#).

Strip the base path with base path conditions

When you create a base path condition, you can choose to strip the base path. When you strip the base path, API Gateway removes the incoming matched base path when it invokes the target API. This is the same behavior as when you use an API mapping. When you don't strip the base path, API Gateway forwards the entire base path to the target API. We recommend that you only strip the base path when you are recreating an API mapping.

The following table shows examples for how API Gateway evaluates the strip base path condition.

Condition	Strip base path	Incoming request	Result
If base path contains PetStoreShopper/dogs	True	GET https://example.com/PetStoreShopper/dogs	API Gateway calls the GET method of the /resource.
If base path contains PetStoreShopper/dogs .	False	GET https://example.com/PetStoreShopper/dogs	API Gateway calls the GET method of the PetStoreShopper/dogs resource.

Condition	Strip base path	Incoming request	Result
If base path contains PetStoreShopper	True	GET https://example.com/PetStoreShopper/dogs	API Gateway calls the GET method of the dogs resource.
If base path contains PetStoreShopper	False	GET https://example.com/PetStoreShopper/dogs	API Gateway calls the GET method of the PetStoreShopper/dogs resource.
If base path contains PetStoreShopper	True	GET https://example.com/PetStoreShopper?birds=available	API Gateway calls the GET method of the / resource with the query string parameter birds=available .
If base path contains PetStoreShopper	False	GET https://example.com/PetStoreShopper?birds=available	API Gateway calls the GET method of the /PetStoreShopper resource with the query string parameter birds=available .

Restrictions

- The target API and the custom domain name must be in the same AWS account.
- Each rule can have one target API.
- You can only create a routing rule for a private custom domain name to a private API, and for a public custom domain name to a public API. You can't mix public and private resources.
- If your custom domain name has API mappings to both REST and HTTP APIs, routing rules isn't supported.

- The maximum priority number is 1,000,000.
- Header restrictions:
 - Each anyOf condition can only contain one header value.
 - The only allowed characters for header names and header glob values are specified by [RFC 7230](#), which are a-z, A-Z, 0-9, and the following special characters: *?-!#\$%&'.^_`|~.
 - You can use a wildcard in the header glob value, but the wildcard must be *prefix-match*, suffix-match*, or *contains*. You can't use * in the middle of a header glob value.
 - Wildcard header names aren't supported.
 - The header name must be less than 40 characters.
 - The header glob value must be less than 128 characters.
 - The header glob value for an infix match must be less than 40 characters.
- The following headers aren't supported as conditions:
 - access-control-*
 - apigw-*
 - Authorization
 - Connection
 - Content-Encoding
 - Content-Length
 - Content-Location
 - Forwarded
 - Keep-Alive
 - Origin
 - Proxy-Authenticate
 - Proxy-Authorization
 - TE
 - Trailers
 - Transfer-Encoding
 - Upgrade
 - x-amz-*
 - x-amzn-*

- X-Forwarded-For
 - X-Forwarded-Host
 - X-Forwarded-Proto
 - x-restAPI
 - Via
- Base path restrictions:
 - The base path length must be less than 128 characters.
 - The base path must contain only letters, numbers, and the following characters: \$-_+.+!*'()/.
These characters aren't supported for regular expressions (regex).

These characters aren't supported for regular expressions (regex).

- The base path can't start or end with backslash (\) character.

Examples of how API Gateway evaluates routing rules

The following section shows four examples of how API Gateway evaluates routing rules and API mappings.

Example 1: Routing rules only

In this example, the custom domain name `https://petstore.example.com` has the routing mode set to `ROUTING_RULE_ONLY` and has the following routing rules and priorities.

Rule ID	Priority	Conditions	Action
abc123	10	If request contains header: Hello:Wor ld	Target API 1
zzz000	50	If request contains headers: Accept:image/webp and Pet:Dog-* and if the base path contains PetStoreShopper	Target API 2

Rule ID	Priority	Conditions	Action
efg456	100	None	Target API 3

The following table shows how API Gateway applies the previous routing rules to example requests.

Request	Selected API	Explanation
<code>https://petstore.example.com -h "Hello:World"</code>	Target API 1	The request matches the routing rule abc123.
<code>https://petstore.example.com/PetStoreShopper -h "Hello:World", "Pet:Dog-Bella", "Accept:image/webp"</code>	Target API 1	API Gateway evaluates all routing rules in priority order. Routing rule abc123 has the first priority and the conditions match, so API Gateway invokes Target API 1. Although the conditions of the request also match routing rule zzz000, API Gateway doesn't evaluate any other routing rules after it makes a match.
<code>https://petstore.example.com/PetStoreShopper -h "Pet:Dog-Bella", "Accept:image/webp"</code>	Target API 2	The request matches the routing rule zzz000. This was a match because the Pet:Dog-Bella was a string match to Pet:Dog-*
<code>https://petstore.example.com/PetStoreShopper -h "Pet:Dog-Bella"</code>	Target API 3	The request doesn't match the routing rule abc123. The request doesn't match routing rule zzz000 as all

Request	Selected API	Explanation
		the required headers aren't present. The next priority rule matches all incoming requests, so API Gateway invokes Target API 3.

Example 2: Routing rules and API mappings


In this example, the custom domain name `https://petstore.diagram.example.com` has the routing mode set to `ROUTING_RULE_THEN_API_MAPPING` and has the following routing rules and API mappings.

Rule ID	Priority	Conditions	Action
abc123	1	If request the base contains pets	Invoke the Prod stage of the PetStore API.
000zzz	5	If request contains headers: Cookie:*ux=beta* and and if the base path contains / refunds	Invoke the Beta stage of the Refunds API.

The following table shows API mappings for `https://petstore.backup.example.com`.

API mapping	Selected API
/refunds	Invoke the Prod stage of the Refunds API.
(none)	Invoke the Prod stage of the Search API.

The following diagram shows how API Gateway applies the previous routing rules and API mappings to example requests. The example requests are summarized in the table after this diagram.



The following table shows how API Gateway applies the previous routing rules and API mappings to example requests.

Request	Selected API	Explanation
<code>https://petstore.diagram.example.com/pets</code>	The Prod stage of the PetStore API.	The request matches routing rule abc123.
<code>https://petstore.diagram.example.com/refunds -h "Cookie:lang=en-us;ux=beta"</code>	The Beta stage of the Refunds API.	The request matches routing rule 000zzz. The Cookie header contains the correct *contains* match and base path match for this condition.
<code>https://petstore.diagram.example.com/refunds</code>	The Prod stage of the Refunds API.	The request doesn't have the required headers to match the routing rule zzz000. If API Gateway can't successfully match a routing rule, it falls back to API mappings. API Gateway can map the

Request	Selected API	Explanation
		base path to the Prod stage of the Refunds API.
https://petstore.d iagram.example.com/	The Prod stage of the Search API.	The request matches the API mapping to the empty path (none).

Example 3: Routing rules and API mappings with multiple level

In this example, the custom domain name <https://petstore.backup.example.com> has the routing mode set to ROUTING_RULE_THEN_API_MAPPING and has the following routing rules and API mappings.

The following table shows routing rules for <https://petstore.backup.example.com>.

Rule ID	Priority	Conditions	Action
abc123	10	If request contains header: Hello:World	Target API 1
000zzz	50	If request contains headers: Accept:image/webp and Pet:Dog-* and if the base path contains PetStores hopper	Target API 2

The following table shows API mappings for <https://petstore.backup.example.com>.

API mapping	Selected API
PetStoreShopper	Target API 3

API mapping	Selected API
PetStoreShopper/cats	Target API 4

The following table shows how API Gateway applies the previous routing rules and API mappings to example requests.

Request	Selected API	Explanation
<code>https://petstore.example.com/PetStoreShopper -h "Accept:image/webp", "Pet:Cats"</code>	Target API 3	The request doesn't have the required headers to match the routing rule <code>zzz000</code> . If API Gateway can't successfully match a routing rule, it falls back to API mappings. API Gateway can map the base path to Target API 3.
<code>https://petstore.example.com/PetStoreShopper/cats -h "Hello:World"</code>	Target API 1	The request matches routing rule <code>abc123</code> . If the routing mode is set to <code>ROUTING_RULE_THEN_API_MAPPING</code> , routing rules always take priority over API mappings.
<code>https://petstore.example.com/Admin -h "Pet:Dog-Bella"</code>	None	The request doesn't match any routing rules or API mappings. Since there is no default routing rule, API Gateway rejects the call and sends the caller a <code>403 Forbidden</code> status code.

Example 4: Routing rules for wildcard domain names

In this example, the custom domain name `https://*.example.com` is a wildcard domain name. The wildcard supports all subdomains which route back to the same domain. The following example routing rules change this behavior to allow subdomains to route to different target APIs by using the Host header.

The following table shows routing rules for `https://*.example.com`.

Rule ID	Priority	Conditions	Action
abc123	10	If request contains header: Host:a.example.com	Target API 1
000zzz	50	If request contains headers: Host:b.example.com	Target API 2
efg456	500	None	Target API 3

The following table shows how API Gateway applies the previous routing rules to example requests.

Request	Selected API	Explanation
<code>https://a.example.com</code>	Target API 1	The Host header is <code>a.example.com</code> . This request matches routing rule abc123.
<code>https://b.example.com</code>	Target API 2	The Host header is <code>b.example.com</code> . This request matches routing rule 000zzz.
<code>https://testing.example.com</code>	Target API 3	This matches the catch-all routing rule efg456.

How to use routing rules

You can create a routing rule using the AWS Management Console, AWS CLI, or any AWS SDK. After you create a rule, you can change its priority.

Create a routing rule

The following procedure shows how to create a routing rule for a custom domain name with a routing mode set to either ROUTING_RULE_THEN_API_MAPPING or ROUTING_RULE_ONLY.

AWS Management Console

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose **Custom domain names** from the main navigation pane.
3. Choose a custom domain name.
4. On the **Routing details** tab, choose **Add routing rule**.
5. Choose **Add a new condition** to add a new condition.

You can add a header or base path condition. To match all incoming requests to your custom domain name, don't add a condition.

6. For **Action**, use the dropdown to select your target API and target stage.
7. Choose **Next**.
8. In the priority field, enter a number for your priority.

API Gateway evaluates rules in priority order, from the lowest value to the highest value.

If you're creating a rule without a condition, we recommend that you use a high value priority.

9. Choose **Create routing rule**.

AWS CLI

The following [create-routing-rule](#) command creates a routing rule with a priority of 50. In this example, API Gateway routes any incoming requests that have the headers Hello:World and x-version:beta and the base path PetStoreShopper to the target API a1b2c3.

```
aws apigatewayv2 create-routing-rule \
--domain-name 'api.example.com' \
```

```
--priority 50 \
--conditions '[
{
    "MatchHeaders": {
        "AnyOf": [
            {
                "Header": "Hello",
                "ValueGlob": "World"
            }
        ]
    }
},
{
    "MatchHeaders": {
        "AnyOf": [
            {
                "Header": "x-version",
                "ValueGlob": "beta"
            }
        ]
    }
},
{
    "MatchBasePaths": {
        "AnyOf": [
            "PetStoreShopper"
        ]
    }
}
]'\'
--actions '[
{
    "InvokeApi": {
        "ApiId": "a1b2c3",
        "Stage": "prod"
    }
}
]'
```

The output will look like the following.

```
{
    "Actions": [
```

```
{  
    "InvokeApi": {  
        "ApiId": "a1b2c3",  
        "Stage": "prod",  
        "StripBasePath": false  
    }  
},  
"Conditions": [  
    {  
        "MatchHeaders": {  
            "AnyOf": [  
                {  
                    "Header": "Hello",  
                    "ValueGlob": "World"  
                }  
            ]  
        }  
    },  
    {  
        "MatchHeaders": {  
            "AnyOf": [  
                {  
                    "Header": "x-version",  
                    "ValueGlob": "beta"  
                }  
            ]  
        }  
    },  
    {  
        "MatchBasePaths": {  
            "AnyOf": [  
                "PetStoreShopper"  
            ]  
        }  
    },  
    {"Priority": 50,  
     "RoutingRuleArn": "arn:aws:apigateway:us-west-2:111122223333:/domainnames/  
     api.example.com/routingrules/abc123",  
     "RoutingRuleId": "abc123"  
    }  
]
```

Change the priority of a routing rule

You can change the priority of a routing rule. This takes effect immediately and might impact how API consumers invoke your custom domain names. We recommend that when you set the priorities of your routing rules, you leave gaps between rules.

For example, consider two routing rules, rule abc123 with a priority of 50 and rule zzz000 with a priority of 150. To change the priority of the rules so that API Gateway evaluates rule zzz000 first, you can change the priority of rule zzz000 to 30.

AWS Management Console

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose **Custom domain names** from the main navigation pane.
3. Choose a custom domain name.
4. On the **Routing details** tab, choose your routing rule, and then choose **Edit**.
5. Choose **Next**.
6. For priority, enter the new priority.
7. Choose **Save changes**.

AWS CLI

The following [put-routing-rule](#) command changes the priority of a routing rule abc123.

```
aws apigatewayv2 put-routing-rule \
--domain-name 'api.example.com' \
--priority 30 \
--routing-rule-id abc123 \
--conditions '[
{
    "MatchHeaders": {
        "AnyOf": [
            {
                "Header": "Hello",
                "ValueGlob": "World"
            }
        ]
    }
},
```

```
{  
    "MatchHeaders": {  
        "AnyOf": [  
            {  
                "Header": "x-version",  
                "ValueGlob": "beta"  
            }  
        ]  
    },  
    {  
        "MatchBasePaths": {  
            "AnyOf": [  
                "PetStoreShopper"  
            ]  
        }  
    }  
}'\n--actions '[  
{  
    "InvokeApi": {  
        "ApiId": "a1b2c3",  
        "Stage": "prod"  
    }  
}  
]'
```

The output will look like the following:

```
{  
    "Actions": [  
        {  
            "InvokeApi": {  
                "ApiId": "a1b2c3",  
                "Stage": "prod",  
                "StripbasePath": false  
            }  
        }  
    ],  
    "Conditions": [  
        {  
            "MatchHeaders": {  
                "AnyOf": [  
                    {  
                        "Header": "x-version",  
                        "ValueGlob": "beta"  
                    }  
                ]  
            }  
        }  
    ]  
}
```

```
{  
    "Header": "Hello",  
    "ValueGlob": "World"  
}  
]  
}  
,  
{  
    "MatchHeaders": {  
        "AnyOf": [  
            {  
                "Header": "x-version",  
                "ValueGlob": "beta"  
            }  
        ]  
    }  
,  
{  
    "MatchBasePaths": {  
        "AnyOf": [  
            "PetStoreShopper"  
        ]  
    }  
}  
,  
]  
,  
"Priority": 38,  
"RoutingRuleArn": "arn:aws:apigateway:us-west-2:111122223333:/domainnames/  
api.example.com/routingrules/abc123",  
"RoutingRuleId": "abc123"  
}
```

Recreate an API mapping using routing rules

You can recreate an API mapping using routing rules. To recreate an API mapping, make sure to turn on base path striping. This preserves the behavior of API mappings. For more information, see [the section called “Strip the base path with base path conditions”](#).

The following tutorial shows how to recreate the API mapping <https://api.example.com/orders/v2/items/categories/5> as a routing rule and how to update your access logs to log the routing rule ID API Gateway uses to send traffic to your API.

AWS Management Console

To set the routing mode to ROUTING_RULE_THEN_API_MAPPING

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose **Custom domain names** from the main navigation pane.
3. Choose your custom domain name.
4. For **Domain details**, choose **Edit**.
5. For **Routing mode**, choose **ROUTING_RULE_THEN_API_MAPPING**.
6. Choose **Save**

After you set the routing mode, you create the routing rule.

To create the routing rule

1. On the **Routing details** tab, choose **Add routing rule**.
2. Choose **Add new condition** and then choose **Path**.
3. For **Path**, enter **orders/v2/items/categories/5**.
4. For **Strip base path**, choose **Active**.
5. For **Target API**, choose your target API.
6. For **Target stage**, choose your target stage.
7. Choose **Next**.
8. For priority, enter a priority.

Even if you keep your existing API mapping, API Gateway will always use the new routing rule as routing rules always take priority over API mappings.

9. Choose **Save changes**.

After you create the routing rule, update the access log format for your stage or create a new log to confirm that API Gateway uses your routing rule to send traffic to your API.

To update your access logs

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose your API.

3. In the main navigation pane, choose **Stages**.
4. For **Logs and tracing**, choose **Edit**.

If you don't have a log group, see [the section called "CloudWatch logs"](#).

5. Add **\$context.customDomain.routingRuleIdMatched** to your log format.

This log group records the routing rule ID that API Gateway used to send traffic to your API. For more information, see [the section called "I can't tell how API Gateway sent traffic to my APIs"](#).

6. Choose **Save**.

After you update your access logs, invoke your custom domain name. The following is an example curl command to invoke the custom domain name <https://api.example.com> with the base path `orders/v2/items/categories/5`.

```
curl "https://api.example.com/orders/v2/items/categories/5"
```

After you have successfully invoked your custom domain name, confirm that CloudWatch Logs shows the `routingRuleIdMatched`. To learn how to use the CloudWatch Logs console to view a log group, see [the section called "View log event in the CloudWatch console"](#).

AWS CLI

1. Use the following [update-domain-name](#) command to update the domain name api.example.com to use the routing mode `ROUTING_RULE_THEN_API_MAPPING`.

```
aws apigatewayv2 update-domain-name \
--domain-name 'api.example.com' \
--routing-mode ROUTING_RULE_THEN_API_MAPPING
```

2. Use the following [create-routing-rule](#) command to create a new routing rule to recreate the API mapping <https://api.example.com/orders/v2/items/categories/5>.

```
aws apigatewayv2 create-routing-rule \
--domain-name 'api.example.com' \
--priority 50 \
--conditions '[
{
    "MatchBasePaths": {
```

```
"AnyOf": [
    "orders/v2/items/categories/5"
]
}
]
]' \
--actions '[
{
    "InvokeApi": {
        "ApiId": "a1b2c3",
        "Stage": "prod",
        "StripBasePath": true
    }
}
]'
```

3. Use the following [update-stage](#) command to update the access logs format to include the `$context.customDomain.routingRuleIdMatched` variable. This variable records the routing rule ID that API Gateway used to send traffic to your API. You use this log to confirm that API Gateway uses your routing rule to send traffic to your API. For more information, see [the section called “I can't tell how API Gateway sent traffic to my APIs”](#).

```
aws apigateway update-stage \
--rest-api-id a1bc2c3 \
--stage-name prod \
--patch-operations "op=replace,path=/accessLogSettings/format,value='\
\$context.path \$context.customDomain.routingRuleIdMatched \$context.requestId \
\$context.extendedRequestId'"
```

If you don't have a log group, see [the section called “CloudWatch logs”](#).

4. Use the following example curl command to invoke your custom domain name with the base path `orders/v2/items/categories/5`.

```
curl "https://api.example.com/orders/v2/items/categories/5"
```

5. Use the following [filter-log-events](#) command to get the log events from the log group `access-log-group-orders` that contain routing rule ID abc123.

```
aws logs filter-log-events --log-group-name access-log-group-orders --filter-
pattern abc123
```

This confirms that API Gateway used the routing rule to send traffic to your API.

Troubleshooting issues with routing rules

The following troubleshooting guidance might help resolve issues with your routing rules.

I can't tell how API Gateway sent traffic to my APIs

You can use access logs for your REST API stage to log and troubleshoot your routing rules. You can view the routing rule ID that API Gateway used to send traffic to your API using the `$context.customDomain.routingRuleIdMatched` variable. To view the API mapping that API Gateway used to send traffic to your API, use the `$context.customDomain.basePathMatched` variable.

To log your routing rules, you need to configure [an appropriate CloudWatch Logs role](#) ARN for your account and create a log group.

The following example access log group can retrieve the relevant information for troubleshooting routing rules and API mappings. API Gateway only populates the context variable for the routing mechanism it used, otherwise the context variable is -.

CLF

```
$context.path $context.customDomain.routingRuleIdMatched  
$context.customDomain.basePathMatched $context.requestId $context.extendedRequestId
```

JSON

```
{"requestPath": "$context.path", "routingRuleId" :  
  "$context.customDomain.routingRuleIdMatched", "API mapping" :  
  "$context.customDomain.basePathMatched", "requestId": "$context.requestId",  
  "extendedRequestId": "$context.extendedRequestId"}
```

XML

```
<request id="$context.requestId"> <requestPath>$context.path</requestPath>  
  <ruleId>$context.customDomain.routingRuleIdMatched</ruleId> <ApiMapping>  
  $context.customDomain.basePathMatched</ApiMapping> <extendedRequestId>  
  $context.extendedRequestId</extendedRequestId> </request>
```

CSV

```
$context.path,$context.customDomain.routingRuleIdMatched,  
$context.customDomain.basePathMatched,$context.requestId,$context.extendedRequestId
```

We also recommend that you confirm the routing mode for your custom domain name. For more information, see [the section called “Set the routing mode for your custom domain name”](#).

I can't enable routing rules on my custom domain name

You might receive the following error from API Gateway:

Your account doesn't have permission to use RoutingRules.
This might be caused by an IAM policy in your account with a deny statement on
BasePathMapping or ApiMapping.
To grant permission for this account to use RoutingRules, use the UpdateAccount API.
This will impact any existing IAM policies that deny access to BasePathMapping or
ApiMapping.
See API Gateway documentation for further details.

You'll receive this error if have or had an IAM policy that denies access to [BasePathMapping](#) or [ApiMapping](#). When you enable routing rules for a custom domain name, although your policy will continue to deny access to BasePathMapping or ApiMapping, the same policy can be used to access RoutingRule. This might allow a user to change the routing behavior of your custom domain name.

For example, if you had a policy like the following:

```
{  
  "Sid": "DenyCreatingApiMappings",  
  "Effect": "Deny",  
  "Action": "apigateway:POST",  
  "Resource": [  
    "arn:aws:apigateway:us-west-2::/domainnames/example.com/apimappings"  
  ]  
}
```

When you enable routing rules for example.com, this policy will continue to deny access to creating an ApiMapping but will not deny access to creating a RoutingRule.

We recommend that you audit the IAM policies in your account. The following example policy will deny access to creating ApiMapping, BasePathMapping, and RoutingRule:

```
{  
    "Sid": "DenyCreatingBasePathMappingsApiMappings",  
    "Effect": "Deny",  
    "Action": "apigateway:POST",  
    "Resource": [  
        "arn:aws:apigateway:us-west-2::/domainnames/example.com/basepathmappings",  
        "arn:aws:apigateway:us-west-2::/domainnames/example.com/apimappings"  
    ]  
},  
{  
    "Sid": "DenyCreatingRoutingRules",  
    "Effect": "Deny",  
    "Action": "apigateway:CreateRoutingRule",  
    "Resource": [  
        "arn:aws:apigateway:us-west-2:111122223333:/domainnames/example.com/  
routingrules/*"  
    ]  
}
```

After you have confirmed all your policies have been updated, you can update your API's account-level settings to enable routing rules for a Region.

Use the following [update-account](#) command to update the settings for your API's account-level settings for a Region:

```
aws apigateway update-account --patch-operations 'op=remove,path=/  
features,value=BlockedForRoutingRules' --region us-west-2
```

After you update your API's account-level settings, you can change the routing mode of your custom domain name. You can also continue to use IAM policies to deny access to RoutingRules, ApiMapping or BasePathMapping.

Use API mappings to connect API stages to a custom domain name for REST APIs

You use API mappings to connect API stages to a custom domain name. This sends traffic to your APIs through your custom domain name.

An API mapping specifies an API, a stage, and optionally a path to use for the mapping. For example, you can map `https://api.example.com/orders` to the production stage of an API.

You can map HTTP and REST API stages to the same custom domain name.

Before you create an API mapping, you must have an API, a stage, and a custom domain name. To learn more about creating a custom domain name, see [the section called “Set up a Regional custom domain name”](#).

Incoming requests to your custom domain name

When you map a custom domain name to a stage of your API, API Gateway strips the incoming base path. This removes the mapped base path from the invocation to the API. For instance, if your base path mapping was `https://api.example.com/orders/shop/5` to the test stage, and you used the following request, `https://api.example.com/orders/shop/5/hats`, API Gateway would invoke the `/hats` resource of the test stage of your API, not the `orders/shop/5/hats` resource.

Mapping API requests

The following explains how API Gateway evaluates API mappings.

You can create an API mapping using single-level mappings, such an API mapping from `orders` to the beta stage of an API and an API mapping from `shipping` to the alpha stage of an API. For a Regional custom domain names with the TLS 1.2 security policy, API Gateway supports multi-level API mappings. You can create an API mapping from `orders/v1/items` to the alpha stage of an API and `orders/v2/items` to the beta stage of an API. When you create a mapping with multiple levels, API Gateway sends requests to the API mapping that has the longest matching path.

You can create an API mapping to the empty path (none). If no path matches the request, API Gateway sends the request to the empty path (none).

In this example, the custom domain name `https://api.example.com` has the following API mappings.

API Mapping	Selected API
(none)	API 1
orders	API 2
orders/v1/items	API 3

API Mapping	Selected API
orders/v2/items	API 4
orders/v1/items/categories	API 5

The following table shows how API Gateway applies the previous API mappings to example requests.

Request	Selected API	Explanation
<code>https://api.example.com/orders</code>	API 2	The request exactly matches this API mapping.
<code>https://api.example.com/orders/v1/items</code>	API 3	The request exactly matches this API mapping.
<code>https://api.example.com/orders/v2/items</code>	API 4	The request exactly matches this API mapping.
<code>https://api.example.com/orders/v1/items/123</code>	API 3	API Gateway chooses the mapping that has the longest matching path. The 123 at the end of the request doesn't affect the selection. See the section called "Incoming requests to your custom domain name" .
<code>https://api.example.com/orders/v2/items/categories/5</code>	API 5	API Gateway chooses the mapping that has the longest matching path.
<code>https://api.example.com/customers</code>	API 1	API Gateway uses the empty mapping as a catch-all.

Request	Selected API	Explanation
<code>https://api.example.com/ordersandmore</code>	API 2	<p>API Gateway chooses the mapping that has the longest matching prefix.</p> <p>For a custom domain name configured with single-level mappings, such as only <code>https://api.example.com/orders</code> and <code>https://api.example.com/</code>, API Gateway would choose API 1, as there is no matching path with <code>ordersandmore</code>.</p>

Restrictions

- In an API mapping, the custom domain name and mapped APIs must be in the same AWS account.
- API mappings must contain only letters, numbers, and the following characters: `$-_.+!*'()`.
- The maximum length for the path in an API mapping is 300 characters.
- You can have 200 API mappings with multiple levels for each domain name. This limit doesn't include API mapping with single levels, such as `/prod`.
- You can only map HTTP APIs to a regional custom domain name with the TLS 1.2 security policy.
- You can't map WebSocket APIs to the same custom domain name as an HTTP API or REST API.
- After you create your API mappings, you must create or update your DNS provider's resource record to map to your API endpoint.
- If you create an API mappings with multiple levels, API Gateway converts all header names to lowercase.

Create an API mapping

To create an API mapping, you must first create a custom domain name, API, and stage. Your custom domain name must have a routing mode set to either `ROUTING_RULE_THEN_API_MAPPING` or `API_MAPPING_ONLY`. For information about how to set the routing mode, see [the section called “Set the routing mode for your custom domain name”](#).

For example AWS Serverless Application Model templates that create all resources, see [Sessions With SAM](#) on GitHub.

AWS Management Console

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose **Custom domain names** from the main navigation pane.
3. Choose a custom domain name.
4. On the **Routing details** tab, choose **Configure API mappings**.
5. Enter the **API**, **Stage**, and **Path** for the mapping.
6. Choose **Save**.

AWS CLI

The following [create-api-mapping](#) command creates an API mapping. In this example, API Gateway sends requests to `api.example.com/v1/orders` to the specified API and stage.

 **Note**

To create API mappings with multiple levels, you must use `apigatewayv2`.

```
aws apigatewayv2 create-api-mapping \
  --domain-name api.example.com \
  --api-mapping-key v1/orders \
  --api-id a1b2c3d4 \
  --stage test
```

CloudFormation

The following CloudFormation example creates an API mapping.

Note

To create API mappings with multiple levels, you must use AWS::ApiGatewayV2.

```
MyApiMapping:  
  Type: 'AWS::ApiGatewayV2::ApiMapping'  
  Properties:  
    DomainName: api.example.com  
    ApiMappingKey: 'orders/v2/items'  
    ApiId: !Ref MyApi  
    Stage: !Ref MyStage
```

IP address types for custom domain names in API Gateway

When you create a custom domain name, you specify the type of IP addresses that can invoke your domain. You can choose IPv4 to resolve IPv4 addresses to invoke your domain, or you can choose dualstack to allow both IPv4 and IPv6 addresses to invoke your domain. We recommend that you set the IP address type to dualstack to alleviate IP space exhaustion or for your security posture. For more information about the benefits of a dualstack IP address type, see [IPv6 on AWS](#).

You can change the IP address type by updating the endpoint configuration of your domain name.

Considerations for IP address types

The following considerations might impact your use of IP address types.

- The default IP address type for API Gateway custom domain names for public APIs is IPv4.
- Private custom domain names can only have a dualstack IP address type.
- Your custom domain name doesn't need to have the same IP address type for all APIs mapped to it. If you disable your default API endpoint, this might affect how callers can invoke your domain.

Change the IP address type of a custom domain name

You can change the IP address type by updating the domain name's endpoint configuration. You can update the endpoint configuration by using the AWS Management Console, the AWS CLI, CloudFormation, or an AWS SDK.

AWS Management Console

To change the IP address type of a custom domain name

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose a public custom domain name.
3. Choose **Endpoint configuration**.
4. For IP address type, select either **IPv4** or **Dualstack**.
5. Choose **Save**.

AWS CLI

The following [update-domain-name](#) command updates an API to have an IP address type of dualstack:

```
aws apigateway update-domain-name \
--domain-name dualstack.example.com \
--patch-operations "op='replace',path='/endpointConfiguration/
ipAddressType',value='dualstack'"
```

The output will look like the following:

```
{
  "domainName": "dualstack.example.com",
  "certificateUploadDate": "2025-02-04T14:46:10-08:00",
  "regionalDomainName": "d-abcd1234.execute-api.us-east-1.amazonaws.com",
  "regionalHostedZoneId": "Z3LQWSYCGH4ADY",
  "regionalCertificateArn": "arn:aws:acm:us-east-1:111122223333:certificate/
a1b2c3d4-5678-90ab-cdef",
  "endpointConfiguration": {
    "types": [
      "REGIONAL"
    ],
    "ipAddressType": "dualstack"
  },
  "domainNameStatus": "AVAILABLE",
  "securityPolicy": "TLS_1_2",
  "tags": {}
}
```

Choose a security policy for your custom domain in API Gateway

A *security policy* is a predefined combination of minimum TLS version and cipher suites offered by API Gateway. When your clients establish a TLS handshake to your API or custom domain name, the security policy enforces the TLS version and cipher suite accepted by API Gateway. Security policies protect your APIs and custom domain names from network security problems such as tampering and eavesdropping between a client and server.

API Gateway supports legacy security policies and enhanced security policies. TLS_1_0 and TLS_1_2 are legacy security policies. Use these security policies for generalized workloads, or to get started creating an API. Any policy that starts with `SecurityPolicy_` is an enhanced security policy. Use these policies for regulated workloads, advanced governance, or to use post-quantum cryptography. When you use an enhanced security policy, you must also set the endpoint access mode for additional governance. For more information, see [the section called “Endpoint access mode”](#).

Considerations

The following are considerations for security policies for custom domain names for REST APIs in API Gateway:

- You can't enable mutual TLS on a domain name that uses an enhanced security policy.
- You can't map an HTTP API to a domain name that uses an enhanced security policy.
- If you enable multi-level base path mapping to a REST API that uses an enhanced security policy, you can't create a base path mapping to an HTTP API for the same domain name.
- Your API can be mapped to a custom domain name with a different security policy than your API. When you invoke that custom domain name, API Gateway uses the security policy of the API to negotiate the TLS handshake. If you disable your default API endpoint, this might affect how callers can invoke your API.
- API Gateway supports security policies on all APIs. However, you can only choose a security policy for REST APIs. API Gateway only supports the TLS_1_2 security policy for HTTP or WebSocket APIs.
- API Gateway doesn't support updating a security policy for a domain name with multiple endpoint types. If you have multiple endpoint types for a domain name, delete one of them to update the security policy.

How API Gateway applies security policies

The following example shows how API Gateway applies security policies using the `SecurityPolicy_TLS13_1_3_2025_09` security policy as an example.

The `SecurityPolicy_TLS13_1_3_2025_09` security policy accepts TLS 1.3 traffic and rejects TLS 1.2 and TLS 1.0 traffic. For TLS 1.3 traffic, the security policy accepts the following cipher suites:

- `TLS_AES_128_GCM_SHA256`
- `TLS_AES_256_GCM_SHA384`
- `TLS_CHACHA20_POLY1305_SHA256`

API Gateway does not accept any other cipher suites. For instance, the security policy would reject any TLS 1.3 traffic that uses the AES128-SHA cipher suite.

To monitor which TLS protocol and ciphers clients used to access your API Gateway, you can use the `$context.tlsVersion` and `$context.cipherSuite` context variables in your access logs. For more information, see [the section called “Monitor”](#).

To see the default security policies for all REST APIs and custom domain names, see [the section called “Default security policies”](#). To see the supported security policies for all REST APIs and custom domain names, see [the section called “Supported security policies”](#).

Change your custom domain name's security policy

If you change your security policy, it takes about 15 minutes for the update to complete. You can monitor the `lastUpdateStatus` of your custom domain name. As your custom domain name updates, the `lastUpdateStatus` is `PENDING` and when it completes, it will be `AVAILABLE`.

When you use a security policy that starts with `SecurityPolicy_`, you must also turn on endpoint access mode. For more information, see [the section called “Endpoint access mode”](#).

AWS Management Console

To change the security policy of a custom domain name

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose a custom domain name that sends traffic to REST APIs.

- Make sure there is only one endpoint type associated with your custom domain name.
3. Choose **Custom domain name settings**, and then choose **Edit**.
 4. For **Security policy**, select a new policy.
 5. For **Endpoint access mode**, choose **Strict**.
 6. Choose **Save changes**.

AWS CLI

The following [update-domain-name](#) command updates a domain name to use the `SecurityPolicy_TLS13_1_3_2025_09` security policy:

```
aws apigateway update-domain-name \
--domain-name example.com \
--patch-operations '[
    {
        "op": "replace",
        "path": "/securityPolicy",
        "value": "SecurityPolicy_TLS13_1_3_2025_09"
    },
    {
        "op": "replace",
        "path": "/endpointAccessMode",
        "value": "STRICT"
    }
]'
```

The output will look like the following:

```
{
    "domainName": "example.com",
    "endpointConfiguration": {
        "types": [ "REGIONAL" ],
        "ipAddressType": "dualstack"
    },
    "regionalCertificateArn": "arn:aws:acm:us-west-2:111122223333:certificate/a1b2c3d4-5678-90ab-cdef",
    "securityPolicy": "SecurityPolicy_TLS13_1_3_2025_09",
    "endpointAccessMode": "STRICT"
}
```

Information about HTTP APIs and WebSocket APIs

For more information about HTTP APIs and WebSocket APIs, see [the section called “Security policy for HTTP APIs in API Gateway”](#) and [the section called “Security policy for WebSocket APIs in API Gateway”](#).

Disable the default endpoint for REST APIs

By default, clients can invoke your API by using the execute-api endpoint that API Gateway generates for your API. To ensure that clients can access your API only by using a custom domain name, disable the default execute-api endpoint. Clients can still connect to your default endpoint, but they will receive a 403 Forbidden status code. Disabling the default endpoint affects all stages of the API. This setting takes effect when you update any setting on any stage, such as updating the deployment on the stage.

The following procedure shows how to disable the default endpoint for a REST API.

AWS Management Console

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose a REST API.
3. On the main navigation pane, choose **API settings**.
4. Choose an API.
5. On **API details**, choose **Edit**.
6. For **Default endpoint**, select **Inactive**.
7. Choose **Save changes**.
8. On the main navigation pane, choose **Resources**.
9. Choose **Deploy API**.
10. Redeploy your API to a stage or update any setting on a stage for the update to take effect.

AWS CLI

The following [update-rest-api](#) command disables the default endpoint:

```
aws apigateway update-rest-api \
--rest-api-id abcdef123 \
--patch-operations op=replace,path=/disableExecuteApiEndpoint,value='True'
```

After you disable the default endpoint, you must deploy your API for the change to take effect.

The following [create-deployment](#) command creates a deployment and associates it with a stage:

```
aws apigateway create-deployment \
--rest-api-id abcdef123 \
--stage-name dev
```

Configure custom health checks for DNS failover for an API Gateway API

You can use Amazon Route 53 health checks to control DNS failover from an API Gateway API in a primary AWS Region to one in a secondary Region. This can help mitigate impacts in the event of a Regional issue. If you use a custom domain, you can perform failover without requiring clients to change API endpoints.

When you choose [Evaluate Target Health](#) for an alias record, those records fail only when the API Gateway service is unavailable in the Region. In some cases, your own API Gateway APIs can experience interruption before that time. To control DNS failover directly, configure custom Route 53 health checks for your API Gateway APIs. For this example, you use a CloudWatch alarm that helps operators control DNS failover. For more examples and other considerations when you configure failover, see [Creating Disaster Recovery Mechanisms Using Route 53](#) and [Performing Route 53 health checks on private resources in a VPC with AWS Lambda and CloudWatch](#).

Topics

- [Prerequisites](#)
- [Step 1: Set up resources](#)
- [Step 2: Initiate failover to the secondary Region](#)
- [Step 3: Test the failover](#)
- [Step 4: Return to the primary region](#)
- [Next steps: Customize and test regularly](#)

Prerequisites

To complete this procedure, you must create and configure the following resources:

- A domain name that you own.

- An ACM certificate for that domain name in two AWS Regions. For more info, see [the section called “Prerequisites for custom domain names”](#).
- A Route 53 hosted zone for your domain name. For more information, see [Working with hosted zones](#) in the Amazon Route 53 Developer Guide.

For more information on how to create Route 53 failover DNS records for the domain names, see [Choose a routing policy](#) in the Amazon Route 53 Developer Guide. For more information on how to monitor a CloudWatch alarm, see [Monitoring a CloudWatch alarm](#) in the Amazon Route 53 Developer Guide.

Step 1: Set up resources

In this example, you create the following resources to configure DNS failover for your domain name:

- API Gateway APIs in two AWS Regions
- API Gateway custom domain names with the same name in two AWS Regions
- API Gateway API mappings that connect your API Gateway APIs to the custom domain names
- Route 53 failover DNS records for the domain names
- A CloudWatch alarm in the secondary Region
- A Route 53 health check based on the CloudWatch alarm in the secondary Region

First, make sure that you have all of the required resources in the primary and secondary Regions. The secondary Region should contain the alarm and health check. This way, you don't depend on the primary Region to perform failover. For example CloudFormation templates that create these resources, see [primary.yaml](#) and [secondary.yaml](#).

Important

Before failover to the secondary Region, make sure that all required resources are available. Otherwise, your API won't be ready for traffic in the secondary Region.

Step 2: Initiate failover to the secondary Region

In the following example, the standby Region receives a CloudWatch metric and initiates failover. We use a custom metric that requires operator intervention to initiate failover.

```
aws cloudwatch put-metric-data \
--metric-name Failover \
--namespace HealthCheck \
--unit Count \
--value 1 \
--region us-west-1
```

Replace the metric data with the corresponding data for the CloudWatch alarm you configured.

Step 3: Test the failover

Invoke your API and verify that you get a response from the secondary Region. If you used the example templates in step 1, the response changes from {"message": "Hello from the primary Region!"} to {"message": "Hello from the secondary Region!"} after failover.

```
curl https://my-api.example.com
```

```
{"message": "Hello from the secondary Region!"}
```

Step 4: Return to the primary region

To return to the primary Region, send a CloudWatch metric that causes the health check to pass.

```
aws cloudwatch put-metric-data \
--metric-name Failover \
--namespace HealthCheck \
--unit Count \
--value 0 \
--region us-west-1
```

Replace the metric data with the corresponding data for the CloudWatch alarm you configured.

Invoke your API and verify that you get a response from the primary Region. If you used the example templates in step 1, the response changes from {"message": "Hello from the secondary Region!"} to {"message": "Hello from the primary Region!"}.

```
curl https://my-api.example.com
```

```
{"message": "Hello from the primary Region!"}
```

Next steps: Customize and test regularly

This example demonstrates one way to configure DNS failover. You can use a variety of CloudWatch metrics or HTTP endpoints for the health checks that manage failover. Regularly test your failover mechanisms to make sure that they work as expected, and that operators are familiar with your failover procedures.

Optimize performance of REST APIs

After you've made your API available to be called, you might realize that it needs to be optimized to improve responsiveness. API Gateway provides a few strategies for optimizing your API, like response caching and payload compression. In this section, you can learn how to enable these capabilities.

Topics

- [Cache settings for REST APIs in API Gateway](#)
- [Payload compression for REST APIs in API Gateway](#)

Cache settings for REST APIs in API Gateway

You can enable API caching in API Gateway to cache your endpoint's responses. With caching, you can reduce the number of calls made to your endpoint and also improve the latency of requests to your API.

When you enable caching for a stage, API Gateway caches responses from your endpoint for a specified time-to-live (TTL) period, in seconds. API Gateway then responds to the request by looking up the endpoint response from the cache instead of making a request to your endpoint. The default TTL value for API caching is 300 seconds. The maximum TTL value is 3600 seconds. TTL=0 means caching is disabled.

Note

Caching is best-effort. You can use the CacheHitCount and CacheMissCount metrics in Amazon CloudWatch to monitor requests that API Gateway serves from the API cache.

The maximum size of a response that can be cached is 1048576 bytes. Cache data encryption may increase the size of the response when it is being cached.

This is a HIPAA Eligible Service. For more information about AWS, U.S. Health Insurance Portability and Accountability Act of 1996 (HIPAA), and using AWS services to process, store, and transmit protected health information (PHI), see [HIPAA Overview](#).

Important

When you enable caching for a stage, only GET methods have caching enabled by default. This helps to ensure the safety and availability of your API. You can enable caching for other methods by [overriding method settings](#).

Important

Caching is charged by the hour based on the cache size that you select. Caching is not eligible for the AWS Free Tier. For more information, see [API Gateway Pricing](#).

Enable Amazon API Gateway caching

In API Gateway, you can enable caching for a specific stage.

When you enable caching, you must choose a cache capacity. In general, a larger capacity gives a better performance, but also costs more. For supported cache sizes, see [cacheClusterSize](#) in the *API Gateway API Reference*.

API Gateway enables caching by creating a dedicated cache instance. This process can take up to 4 minutes.

API Gateway changes caching capacity by removing the existing cache instance and creating a new one with a modified capacity. All existing cached data is deleted.

Note

The cache capacity affects the CPU, memory, and network bandwidth of the cache instance. As a result, the cache capacity can affect the performance of your cache.

API Gateway recommends that you run a 10-minute load test to verify that your cache capacity is appropriate for your workload. Ensure that traffic during the load test mirrors

production traffic. For example, include ramp up, constant traffic, and traffic spikes. The load test should include responses that can be served from the cache, as well as unique responses that add items to the cache. Monitor the latency, 4xx, 5xx, cache hit, and cache miss metrics during the load test. Adjust your cache capacity as needed based on these metrics. For more information about load testing, see [How do I select the best API Gateway cache capacity to avoid hitting a rate limit?](#).

AWS Management Console

In the API Gateway console, you configure caching on the **Stages** page. You provision the stage cache and specify a default method-level cache setting. If you turn on the default method-level cache, method-level caching is turned on for all GET methods on your stage, unless that method has a method override. Any additional GET methods that you deploy to your stage will have a method-level cache. To configure method-level caching setting for specific methods of your stage, you can use method overrides. For more information about method overrides, see [the section called “Override stage caching for method caching”](#).

To configure API caching for a given stage:

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose **Stages**.
3. In the **Stages** list for the API, choose the stage.
4. In the **Stage details** section, choose **Edit**.
5. Under **Additional settings**, for **Cache settings**, turn on **Provision API cache**.

This provisions a cache cluster for your stage.

6. To activate caching for your stage, turn on **Default method-level caching**.

This turns on method-level caching for all GET methods on your stage. Any additional GET methods that you deploy to this stage will have a method-level cache.

Note

If you have an existing setting for a method-level cache, changing the default method-level caching setting doesn't affect that existing setting.

Additional settings

Cache settings Info

You can enable API caching to cache your endpoint's responses. With caching, you can reduce the number of calls made to your endpoint and also improve the latency of requests to your API. Caching is charged by the hour based on cache size, see API Gateway pricing for details.

Provision API cache

Provision API caching capabilities for your stage. Caching is not active until you enable the method-level cache.

Default method-level caching

Activate method-level caching for all GET methods in this stage.

7. Choose **Save changes**.

AWS CLI

The following [update-stage](#) command updates a stage to provision a cache and turns on method-level caching for all GET methods on your stage:

```
aws apigateway update-stage \
--rest-api-id a1b2c3 \
--stage-name 'prod' \
--patch-operations file://patch.json
```

The contents of patch.json are the following:

```
[  
 {  
     "op": "replace",  
     "path": "/cacheClusterEnabled",  
     "value": "true"  
 },  
 {  
     "op": "replace",  
     "path": "/cacheClusterSize",  
     "value": "0.5"  
 },  
 {  
     "op": "replace",  
     "path": "/*/*/caching/enabled",  
     "value": "true"  
 }
```

]

i Note

If you have an existing setting for a method-level cache, changing the default method-level caching setting doesn't affect that existing setting.

i Note

Creating or deleting a cache takes about 4 minutes for API Gateway to complete.

When a cache is created, the **Cache cluster** value changes from `Create in progress` to `Active`. When cache deletion is completed, the **Cache cluster** value changes from `Delete in progress` to `Inactive`.

When you turn on method-level caching for all methods on your stage, the **Default method-level caching** value changes to `Active`. If you turn off method-level caching for all methods on your stage, the **Default method-level caching** value changes to `Inactive`. If you have an existing setting for a method-level cache, changing the status of the cache doesn't affect that setting.

When you enable caching within a stage's **Cache settings**, only GET methods are cached. To ensure the safety and availability of your API, we recommend that you don't change this setting. However, you can enable caching for other methods by [overriding method settings](#).

If you would like to verify if caching is functioning as expected, you have two general options:

- Inspect the CloudWatch metrics of **CacheHitCount** and **CacheMissCount** for your API and stage.
- Put a timestamp in the response.

i Note

Don't use the X-Cache header from the CloudFront response to determine if your API is being served from your API Gateway cache instance.

Override API Gateway stage-level caching for method-level caching

You can override stage-level cache settings by turning on or turning off caching for a specific method. You can also modify the TTL period or turn encryption on or off for cached responses.

If you anticipate that a method that you are caching will receive sensitive data in its responses, encrypt your cache data. You might need to do this to comply with various compliance frameworks. For more information, see [Amazon API Gateway controls](#) in the *AWS Security Hub User Guide*.

AWS Management Console

If you change the default method-level caching setting in the **Stage details**, it doesn't affect the method-level cache settings that have overrides.

If you anticipate that a method that you are caching will receive sensitive data in its responses, in **Cache Settings**, choose **Encrypt cache data**.

To configure API caching for individual methods using the console:

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose the API.
3. Choose **Stages**.
4. In the **Stages** list for the API, expand the stage and choose a method in the API.
5. In the **Method overrides** section, choose **Edit**.
6. In the **Method settings** section, turn on or off **Enable method cache** or customize any other desired options.

 **Note**

Caching is not active until you provision a cache cluster for your stage.

7. Choose **Save**.

AWS CLI

The following [update-stage](#) command turns off the cache only for the GET /pets method:

```
aws apigateway update-stage /  
--rest-api-id a1b2c3 /
```

```
--stage-name 'prod' /  
--patch-operations file://patch.json
```

The contents of patch.json are the following:

```
[{  
    "op": "replace",  
    "path": "/~1pets/GET/caching/enabled",  
    "value": "false"  
}]
```

Use method or integration parameters as cache keys to index cached responses

You can use a method or integration parameter as cache keys to index cached responses. This includes custom headers, URL paths, or query strings. You can specify some or all of these parameters as the cache key, but you must specify at least one value. When you have a cache key, API Gateway caches the responses from each key value separately, including when the cache key isn't present.

 **Note**

Cache keys are required when setting up caching on a resource.

For example, suppose you have a request in the following format:

```
GET /users?type=... HTTP/1.1  
host: example.com  
...
```

In this request, type can take a value of admin or regular. If you include the type parameter as part of the cache key, the responses from GET /users?type=admin are cached separately from those from GET /users?type=regular.

When a method or integration request takes more than one parameter, you can choose to include some or all of the parameters to create the cache key. For example, you can include only the type parameter in the cache key for the following request, made in the listed order within a TTL period:

```
GET /users?type=admin&department=A HTTP/1.1  
host: example.com  
...
```

The response from this request is cached and is used to serve the following request:

```
GET /users?type=admin&department=B HTTP/1.1  
host: example.com  
...
```

AWS Management Console

To include a method or integration request parameter as part of a cache key in the API Gateway console, select **Caching** after you add the parameter.

Edit method request

Method request settings

Authorization

None

Request validator

None

API key required

Operation name - optional

GetPets

▼ URL query string parameters

Name

Required

Caching

page

Remove

type

Remove

Add query string

AWS CLI

The following [put-method](#) command creates a GET method and requires the type query string parameter:

```
aws apigateway put-method /  
  --rest-api-id a1b2c3 /  
  --resource-id aaa111 /  
  --http-method GET /  
  --authorization-type "NONE" /  
  --request-parameters "method.request.querystring.type=true"
```

The following [put-integration](#) command creates an integration for the GET method with an HTTP endpoint and specifies that API Gateway caches the type method request parameter:

```
aws apigateway put-integration /  
  --rest-api-id a1b2c3 /  
  --resource-id aaa111 /  
  --http-method GET /  
  --type HTTP /  
  --integration-http-method GET /  
  --uri 'https://example.com' /  
  --cache-key-parameters "method.request.querystring.type"
```

To specify API Gateway cache an integration request parameter, use `integration.request.location.name` as the cache key parameter.

Flush the API stage cache in API Gateway

When API caching is enabled, you can flush your API stage's cache to ensure that your API's clients get the most recent responses from your integration endpoints.

AWS Management Console

To flush the API stage cache

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose an API that has a stage with a cache.
3. In the main navigation pane, choose **Stages**, and then choose your stage with a cache.

4. Choose the **Stage actions** menu, and then select **Flush stage cache**.

AWS CLI

The following [flush-stage-cache](#) command flushes the stage cache:

```
aws apigateway flush-stage-cache \
--rest-api-id a1b2c3 \
--stage-name prod
```

Note

After the cache is flushed, responses are serviced from the integration endpoint until the cache is built up again. During this period, the number of requests sent to the integration endpoint may increase. This may temporarily increase the overall latency of your API.

Invalidate an API Gateway cache entry

A client of your API can invalidate an existing cache entry and reload it from the integration endpoint for individual requests. The client must send a request that contains the Cache-Control: max-age=0 header. The client receives the response directly from the integration endpoint instead of the cache, provided that the client is authorized to do so. This replaces the existing cache entry with the new response, which is fetched from the integration endpoint.

To grant permission for a client, attach a policy of the following format to an IAM execution role for the user.

Note

Cross-account cache invalidation is not supported.

JSON

```
{  
  "Version": "2012-10-17",  
  "Statement": [
```

```
{  
    "Effect": "Allow",  
    "Action": [  
        "execute-api:InvalidateCache"  
    ],  
    "Resource": [  
        "arn:aws:execute-api:us-east-1:111111111111:api-id/stage-name/  
GET/resource-path-specifier"  
    ]  
}  
}
```

This policy allows the API Gateway execution service to invalidate the cache for requests on the specified resource (or resources). To specify a group of targeted resources, use a wildcard (*) character for account-id, api-id, and other entries in the ARN value of Resource. For more information on how to set permissions for the API Gateway execution service, see [Control access to a REST API with IAM permissions](#).

If you don't impose an InvalidateCache policy (or choose the **Require authorization** check box in the console), any client can invalidate the API cache. If most or all of the clients invalidate the API cache, this could significantly increase the latency of your API.

When the policy is in place, caching is enabled and authorization is required.

You can specify how API Gateway handles unauthorized requests by choosing from the following options:

Fail the request with 403 status code

API Gateway returns a 403 Unauthorized response.

To set this option using the API, use FAIL_WITH_403.

Ignore cache control header; Add a warning in response header

API Gateway processes the request and adds a warning header in the response.

To set this option using the API, use SUCCEED_WITH_RESPONSE_HEADER.

Ignore cache control header

API Gateway processes the request and doesn't add a warning header in the response.

To set this option using the API, use `SUCCEED_WITHOUT_RESPONSE_HEADER`.

You can set the unauthorized request handling behavior using the API Gateway console or AWS CLI.

AWS Management Console

To specify how unauthorized requests are handled

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose an API that has a stage with a cache.
3. In the main navigation pane, choose **Stages**, and then choose your stage with a cache.
4. For **Stage details**, choose **Edit**.
5. For **Unauthorized request handling**, select an option.
6. Choose **Continue**.
7. Review your changes and choose **Save changes**.

AWS CLI

The following [update-stage](#) command updates a stage to handle unauthorized requests by failing the request with 403 status code:

```
aws apigateway update-stage /  
  --rest-api-id a1b2c3 /  
  --stage-name 'prod' /  
  --patch-operations 'op=replace,path=/*/*/caching/  
unauthorizedCacheControlHeaderStrategy,value="FAIL_WITH_403"'
```

CloudFormation example of a stage with a cache

The following CloudFormation template creates an example API, provisions a 0.5 GB cache for the Prod stage, and turns on method-level caching for all GET methods.

Important

Caching is charged by the hour based on the cache size that you select. Caching is not eligible for the AWS Free Tier. For more information, see [API Gateway Pricing](#).

Example CloudFormation template

```
AWSTemplateFormatVersion: 2010-09-09
Resources:
  Api:
    Type: 'AWS::ApiGateway::RestApi'
    Properties:
      Name: cache-example
  PetsResource:
    Type: 'AWS::ApiGateway::Resource'
    Properties:
      RestApiId: !Ref Api
      ParentId: !GetAtt Api.RootResourceId
      PathPart: 'pets'
  PetsMethodGet:
    Type: 'AWS::ApiGateway::Method'
    Properties:
      RestApiId: !Ref Api
      ResourceId: !Ref PetsResource
      HttpMethod: GET
      ApiKeyRequired: true
      AuthorizationType: NONE
      Integration:
        Type: HTTP_PROXY
        IntegrationHttpMethod: GET
        Uri: http://petstore-demo-endpoint.execute-api.com/petstore/pets/
  ApiDeployment:
    Type: 'AWS::ApiGateway::Deployment'
    DependsOn:
      - PetsMethodGet
    Properties:
      RestApiId: !Ref Api
  ApiStage:
    Type: 'AWS::ApiGateway::Stage'
    Properties:
      StageName: Prod
      Description: Prod Stage with a cache
      RestApiId: !Ref Api
      DeploymentId: !Ref ApiDeployment
      CacheClusterEnabled: True
      CacheClusterSize: 0.5
      MethodSettings:
        - ResourcePath: /*
          HttpMethod: '*'
```

CachingEnabled: True

Payload compression for REST APIs in API Gateway

API Gateway allows your client to call your API with compressed payloads by using one of the [supported content codings](#). By default, API Gateway supports decompression of the method request payload. However, you must configure your API to enable compression of the method response payload.

To enable compression on an [API](#), set the `minimumCompressionSize` property to a non-negative integer between 0 and 10485760 (10M bytes) when you create the API or after you've created the API. To disable compression on the API, set the `minimumCompressionSize` to null or remove it altogether. You can enable or disable compression for an API by using the API Gateway console, the AWS CLI, or the API Gateway REST API.

If you want the compression applied on a payload of any size, set the `minimumCompressionSize` value to zero. However, compressing data of a small size might actually increase the final data size. Furthermore, compression in API Gateway and decompression in the client might increase overall latency and require more computing times. You should run test cases against your API to determine an optimal value.

The client can submit an API request with a compressed payload and an appropriate Content-Encoding header for API Gateway to decompress and apply applicable mapping templates, before passing the request to the integration endpoint. After the compression is enabled and the API is deployed, the client can receive an API response with a compressed payload if it specifies an appropriate Accept-Encoding header in the method request.

When the integration endpoint expects and returns uncompressed JSON payloads, any mapping template that's configured for an uncompressed JSON payload is applicable to the compressed payload. For a compressed method request payload, API Gateway decompresses the payload, applies the mapping template, and passes the mapped request to the integration endpoint. For an uncompressed integration response payload, API Gateway applies the mapping template, compresses the mapped payload, and returns the compressed payload to the client.

Topics

- [Enable payload compression for an API in API Gateway](#)
- [Call an API method with a compressed payload in API Gateway](#)
- [Receive an API response with a compressed payload in API Gateway](#)

Enable payload compression for an API in API Gateway

You can enable compression for an API using the API Gateway console, the AWS CLI, or an AWS SDK.

For an existing API, you must deploy the API after enabling the compression in order for the change to take effect. For a new API, you can deploy the API after the API setup is complete.

 **Note**

The highest-priority content encoding must be one supported by API Gateway. If it is not, compression is not applied to the response payload.

Topics

- [Enable payload compression for an API using the API Gateway console](#)
- [Enable payload compression for an API using the AWS CLI](#)
- [Content codings supported by API Gateway](#)

Enable payload compression for an API using the API Gateway console

The following procedure describes how to enable payload compression for an API.

To enable payload compression by using the API Gateway console

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose an existing API or create a new one.
3. In the main navigation pane, choose **API settings**.
4. In the **API details** section, choose **Edit**.
5. Turn on **Content encoding** to enable payload compression. For **Minimum body size**, enter a number for the minimum compression size (in bytes). To turn off compression, turn off the **Content encoding** option.
6. Choose **Save changes**.

Enable payload compression for an API using the AWS CLI

The following [create-rest-api](#) command creates an API with payload compression:

```
aws apigateway create-rest-api \
--name "My test API" \
--minimum-compression-size 0
```

The following [update-rest-api](#) command enables payload compression for an existing API:

```
aws apigateway update-rest-api \
--rest-api-id 1234567890 \
--patch-operations op=replace,path=/minimumCompressionSize,value=0
```

The `minimumCompressionSize` property has a non-negative integer value between 0 and 10485760 (10M bytes). It measures the compression threshold. If the payload size is smaller than this value, compression or decompression are not applied on the payload. Setting it to zero allows compression for any payload size.

The following [update-rest-api](#) command turns off payload compression:

```
aws apigateway update-rest-api \
--rest-api-id 1234567890 \
--patch-operations op=replace,path=/minimumCompressionSize,value=
```

You can also set `value` to an empty string "" or omit the `value` property altogether in the preceding call.

Content codings supported by API Gateway

API Gateway supports the following content codings:

- `deflate`
- `gzip`
- `identity`

API Gateway also supports the following `Accept-Encoding` header format, according to the [RFC 7231](#) specification:

- `Accept-Encoding: deflate,gzip`

- Accept-Encoding:
- Accept-Encoding:*
- Accept-Encoding:deflate;q=0.5,gzip;q=1.0
- Accept-Encoding:gzip;q=1.0,identity;q=0.5,*;q=0

Call an API method with a compressed payload in API Gateway

To make an API request with a compressed payload, the client must set the Content-Encoding header with one of the [supported content codings](#).

Suppose that you're an API client and want to call the PetStore API method (POST /pets). Don't call the method by using the following JSON output:

```
POST /pets
Host: {petstore-api-id}.execute-api.{region}.amazonaws.com
Content-Length: ...

{
    "type": "dog",
    "price": 249.99
}
```

Instead, you can call the method with the same payload compressed by using the GZIP coding:

```
POST /pets
Host: {petstore-api-id}.execute-api.{region}.amazonaws.com
Content-Encoding:gzip
Content-Length: ...

◆◆◆RPP*◆,HU◆RPJ◆OW◆◆e&◆◆◆L,◆,-y◆j
```

When API Gateway receives the request, it verifies if the specified content coding is supported. Then, it attempts to decompress the payload with the specified content coding. If the decompression is successful, it dispatches the request to the integration endpoint. If the specified coding isn't supported or the supplied payload isn't compressed with specified coding, API Gateway returns the 415 Unsupported Media Type error response. The error is not logged to CloudWatch Logs, if it occurs in the early phase of decompression before your API and stage are identified.

Receive an API response with a compressed payload in API Gateway

When making a request on a compression-enabled API, the client can choose to receive a compressed response payload of a specific format by specifying an `Accept-Encoding` header with a [supported content coding](#).

API Gateway only compresses the response payload when the following conditions are satisfied:

- The incoming request has the `Accept-Encoding` header with a supported content coding and format.

 **Note**

If the header is not set, the default value is `*` as defined in [RFC 7231](#). In such a case, API Gateway does not compress the payload. Some browser or client may add `Accept-Encoding` (for example, `Accept-Encoding:gzip, deflate, br`) automatically to compression-enabled requests. This can turn on the payload compression in API Gateway. Without an explicit specification of supported `Accept-Encoding` header values, API Gateway does not compress the payload.

- The `minimumCompressionSize` is set on the API to enable compression.
- The integration response doesn't have a `Content-Encoding` header.
- The size of an integration response payload, after the applicable mapping template is applied, is greater than or equal to the specified `minimumCompressionSize` value.

API Gateway applies any mapping template that's configured for the integration response before compressing the payload. If the integration response contains a `Content-Encoding` header, API Gateway assumes that the integration response payload is already compressed and skips the compression processing.

An example is the PetStore API example and the following request:

```
GET /pets
Host: {petstore-api-id}.execute-api.{region}.amazonaws.com
Accept: application/json
```

The backend responds to the request with an uncompressed JSON payload that's similar to the following:

200 OK

```
[  
  {  
    "id": 1,  
    "type": "dog",  
    "price": 249.99  
  },  
  {  
    "id": 2,  
    "type": "cat",  
    "price": 124.99  
  },  
  {  
    "id": 3,  
    "type": "fish",  
    "price": 0.99  
  }  
]
```

To receive this output as a compressed payload, your API client can submit a request as follows:

```
GET /pets  
Host: {petstore-api-id}.execute-api.{region}.amazonaws.com  
Accept-Encoding:gzip
```

The client receives the response with a Content-Encoding header and GZIP-encoded payload that are similar to the following:

```
200 OK  
Content-Encoding:gzip  
...  
♦♦♦RP♦  
J♦)JV  
♦:P^IeA*♦♦♦♦♦+(*L ♦X♦YZ♦ku0L0B7!9♦♦C#♦&♦♦♦♦Y♦♦a♦♦♦^♦X
```

When the response payload is compressed, only the compressed data size is billed for data transfer.

Distribute your REST APIs to clients in API Gateway

This section provides details about distributing your API Gateway APIs to your customers. Distributing your API includes generating SDKs for your customers to download and integrate with their client applications, documenting your API so customers know how to call it from their client applications, and making your API available as part of product offerings.

Topics

- [Usage plans and API keys for REST APIs in API Gateway](#)
- [Documentation for REST APIs in API Gateway](#)
- [Generate SDKs for REST APIs in API Gateway](#)
- [Sell your API Gateway APIs through AWS Marketplace](#)

Usage plans and API keys for REST APIs in API Gateway

After you create, test, and deploy your APIs, you can use API Gateway usage plans to make them available as product offerings for your customers. You can configure usage plans and API keys to allow customers to access selected APIs, and begin throttling requests to those APIs based on defined limits and quotas. These can be set at the API, or API method level.

What are usage plans and API keys?

A *usage plan* specifies who can access one or more deployed API stages and methods—and optionally sets the target request rate to start throttling requests. The plan uses API keys to identify API clients and who can access the associated API stages for each key.

API keys are alphanumeric string values that you distribute to application developer customers to grant access to your API. You can use API keys together with [Lambda authorizers](#), [IAM roles](#), or [Amazon Cognito](#) to control access to your APIs. API Gateway can generate API keys on your behalf, or you can import them from a [CSV file](#). You can generate an API key in API Gateway, or import it into API Gateway from an external source. For more information, see [the section called "Set up API keys for REST APIs in API Gateway"](#).

An API key has a name and a value. (The terms "API key" and "API key value" are often used interchangeably.) The name cannot exceed 1024 characters. The value is an alphanumeric string between 20 and 128 characters, for example, apikey1234abcdefgij0123456789.

Important

API key values must be unique. If you try to create two API keys with different names and the same value, API Gateway considers them to be the same API key.

An API key can be associated with more than one usage plan. A usage plan can be associated with more than one stage. However, a given API key can only be associated with one usage plan for each stage of your API.

A *throttling limit* sets the target point at which request throttling should start. This can be set at the API or API method level.

A *quota limit* sets the target maximum number of requests with a given API key that can be submitted within a specified time interval. You can configure individual API methods to require API key authorization based on usage plan configuration.

Throttling and quota limits apply to requests for individual API keys that are aggregated across all API stages within a usage plan.

Note

Usage plan throttling and quotas are not hard limits, and are applied on a best-effort basis. In some cases, clients can exceed the quotas that you set. Don't rely on usage plan quotas or throttling to control costs or block access to an API. Consider using [AWS Budgets](#) to monitor costs and [AWS WAF](#) to manage API requests.

Best practices for API keys and usage plans

The following are suggested best practices to follow when using API keys and usage plans.

Important

- Don't use API keys for authentication or authorization to control access to your APIs. If you have multiple APIs in a usage plan, a user with a valid API key for one API in that usage plan can access *all* APIs in that usage plan. Instead, to control access to your API, use an IAM role, a [Lambda authorizer](#), or an [Amazon Cognito user pool](#).

- Use API keys that API Gateway generates. API keys shouldn't include confidential information; clients typically transmit them in headers that can be logged.
- If you're using a developer portal to publish your APIs, note that all your APIs in a given usage plan can be subscribed to by customers, even if you haven't made them visible to your customers.
- In some cases, clients can exceed the quotas that you set. Don't rely on usage plans to control costs. Consider using [AWS Budgets](#) to monitor costs and [AWS WAF](#) to manage API requests.
- After you add an API key to a usage plan, the update operation might take a few minutes to complete.

Choose an API key source in API Gateway

When you associate a usage plan with an API and enable API keys on API methods, every incoming request to the API must contain an [API key](#). API Gateway reads the key and compares it against the keys in the usage plan. If there is a match, API Gateway throttles the requests based on the plan's request limit and quota. Otherwise, it throws an `InvalidKeyParameter` exception. As a result, the caller receives a `403 Forbidden` response.

Your API Gateway API can receive API keys from one of two sources:

HEADER

You distribute API keys to your customers and require them to pass the API key as the `X-API-Key` header of each incoming request.

AUTHORIZER

You have a Lambda authorizer return the API key as part of the authorization response. For more information on the authorization response, see [the section called “Output from an API Gateway Lambda authorizer”](#).

Note

For best practices to consider, see [the section called “Best practices for API keys and usage plans”](#).

The following procedure shows how to choose an API key source for an API.

AWS Management Console

To choose an API key source for an API

1. Sign in to the API Gateway console.
2. Choose an existing API or create a new one.
3. In the main navigation pane, choose **API settings**.
4. In the **API details** section, choose **Edit**.
5. Under **API key source**, select Header or Authorizer from the dropdown list.
6. Choose **Save changes**.

AWS CLI

The following [update-rest-api](#) command updates an API to set the API key source to AUTHORIZER:

```
aws apigateway update-rest-api --rest-api-id 1234123412 --patch-operations op=replace,path=/apiKeySource,value=AUTHORIZER
```

To have the client submit an API key, set the value to HEADER in the previous command.

REST API

To choose an API key source for an API by using the API Gateway REST API, call [restapi:update](#) as follows:

```
PATCH /restapis/fugvwdxtri/ HTTP/1.1
Content-Type: application/json
Host: apigateway.us-east-1.amazonaws.com
X-Amz-Date: 20160603T205348Z
Authorization: AWS4-HMAC-SHA256 Credential={access_key_ID}/20160603/us-east-1/
apigateway/aws4_request, SignedHeaders=content-length;content-type;host;x-amz-date,
Signature={sig4_hash}

{
  "patchOperations" : [
    {
      "op" : "replace",
```

```
        "path" : "/apiKeySource",
        "value" : "HEADER"
    }
]
}
```

To have an authorizer return an API key, set the value to AUTHORIZER in the previous patchOperations input.

API Gateway API key file format

API Gateway can import API keys from external files of a comma-separated value (CSV) format, and then associate the imported keys with one or more usage plans. The imported file must contain the Name and Key columns. The column header names aren't case sensitive, and columns can be in any order, as shown in the following example:

```
Key,name
apikey1234abcdefgij0123456789,MyFirstApiKey
```

A Key value must be between 20 and 128 characters. A Name value cannot exceed 1024 characters.

An API key file can also have the Description, Enabled, or UsagePlanIds column, as shown in the following example:

```
Name,key,description,Enabled,usageplanIds
MyFirstApiKey,apikey1234abcdefgij0123456789,An imported key,TRUE,c7y23b
```

When a key is associated with more than one usage plan, the UsagePlanIds value is a comma-separated string of the usage plan IDs, enclosed with a pair of double or single quotes, as shown in the following example:

```
Enabled,Name,key,UsageplanIds
true,MyFirstApiKey,apikey1234abcdefgij0123456789,"c7y23b,glvrsr"
```

Unrecognized columns are permitted, but are ignored. The default value is an empty string or a true Boolean value.

The same API key can be imported multiple times, with the most recent version overwriting the previous one. Two API keys are identical if they have the same key value.

Note

For best practices to consider, see [the section called “Best practices for API keys and usage plans”](#).

Set up API keys for REST APIs in API Gateway

To set up API keys, do the following:

- Configure API methods to require an API key.
- Create or import an API key for the API in a Region.

Before setting up API keys, you must have created an API and deployed it to a stage. After you create an API key value, it cannot be changed.

For instructions on how to create and deploy an API by using the API Gateway console, see [Develop REST APIs in API Gateway](#) and [Deploy REST APIs in API Gateway](#), respectively.

After you create an API key, you must associate it with a usage plan. For more information, see [Set up usage plans for REST APIs in API Gateway](#).

Note

For best practices to consider, see [the section called “Best practices for API keys and usage plans”](#).

Topics

- [Require an API key on a method](#)
- [Create an API key](#)
- [Import API keys](#)


Require an API key on a method

The following procedure describes how to configure an API method to require an API key.

AWS Management Console

To configure an API method to require an API key

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose a REST API.
3. In the API Gateway main navigation pane, choose **Resources**.
4. Under **Resources**, create a new method or choose an existing one.
5. On the **Method request** tab, under **Method request settings**, choose **Edit**.



6. Select **API key required**.
7. Choose **Save**.
8. Deploy or redeploy the API for the requirement to take effect.

If the **API key required** option is set to `false` and you don't execute the previous steps, any API key that's associated with an API stage isn't used for the method.

AWS CLI

The following [put-method](#) command creates a PUT method that requires an API key:

```
aws apigateway put-method \
--rest-api-id 1234123412 \
--resource-id a1b2c3 \
--http-method PUT \
--authorization-type "NONE" \
--api-key-required
```

The following [update-method](#) command updates an existing method to require an API key:

```
aws apigateway update-method \
--rest-api-id 1234123412 \
--resource-id a1b2c3 \
--http-method PUT \
--patch-operations op="replace",path="/apiKeyRequired",value="true"
```

REST API

To require an API key on a method, do one of the following:

- Call [method:put](#) to create a method. Set `apiKeyRequired` to `true` in the request payload.
- Call [method:update](#) to set `apiKeyRequired` to `true`.

Create an API key

The following procedure shows how to create an API key. If you want to import your API key, skip this step.

AWS Management Console

To create an API key

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose a REST API.

3. In the API Gateway main navigation pane, choose **API keys**.

4. Choose **Create API key**.

The screenshot shows the AWS API Gateway interface. On the left, there's a sidebar with links: APIs, Custom domain names, VPC links, Usage plans, **API keys**, Client certificates, and Settings. The 'API keys' link is highlighted with a red box. The main content area has a header 'API keys (0) Info' with an 'Actions' dropdown and a 'Create API key' button (which is also highlighted with a red box). Below that is a search bar with 'Find API keys'. A table header row includes columns for Name, Status, ID, API key, Description, and Creation date. The main message says 'No API keys' and 'You don't have any API keys.' with a 'Create API Key' button.

5. For **Name**, enter a name.

6. (Optional) For **Description**, enter a description.

7. For **API key**, choose **Auto generate** to have API Gateway generate the key value, or choose **Custom** to create your own key value.

8. Choose **Save**.

AWS CLI

The following [create-api-key](#) command creates an API key:

```
aws apigateway create-api-key \
--name 'Dev API key' \
--description 'API key for Devs' \
--enabled
```

REST API

Call [apikey:create](#) to create an API key.

Import API keys

The following procedure describes how to import API keys. If you already created an API key, skip this step.

AWS Management Console

To import API keys

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose a REST API.
3. In the main navigation pane, choose **API keys**.
4. Choose the **Actions** dropdown menu, and then choose **Import API keys**.
5. To load a comma-separated key file, choose **Choose file**. You can also enter the keys in the text editor. For information about the file format, see [the section called “API Gateway API key file format”](#).
6. Choose **Fail on warnings** to stop the import when there's an error, or choose **Ignore warnings** to continue to import valid key entries when there's an warning.
7. Choose **Import** to import your API keys.

AWS CLI

The following [import-api-keys](#) command imports an API key:

```
aws apigateway import-api-key \
  --body fileb://keys.csv \
  --format csv
```

REST API

Call [apikey:import](#) to import an API key from a file. For the file format, see [API Gateway API key file format](#).

You cannot change the value of the new API key. After you create your API, you configure a usage plan. For more information, see [Set up usage plans for REST APIs in API Gateway](#).

Set up usage plans for REST APIs in API Gateway

Before you create a usage plan, make sure that you've set up the your API keys. For more information, see [Set up API keys for REST APIs in API Gateway](#).

Topics

- [Migrate your API to default usage plans \(if needed\)](#)
- [Create a usage plan](#)
- [Add a stage to a usage plan](#)
- [Add an API key to a usage plan](#)

Migrate your API to default usage plans (if needed)

If you started to use API Gateway *after* the usage plans feature was rolled out on August 11, 2016, you will automatically have usage plans enabled for you in all supported Regions.

If you started to use API Gateway before that date, you might need to migrate to default usage plans. You'll be prompted with the **Enable Usage Plans** option before using usage plans for the first time in the selected Region. When you enable this option, you have default usage plans created for every unique API stage that's associated with existing API keys. In the default usage plan, no throttle or quota limits are set initially, and the associations between the API keys and API stages are copied to the usage plans. The API behaves the same as before. However, you must use the [UsagePlan](#) `apiStages` property to associate specified API stage values (`apiId` and `stage`) with included API keys (via [UsagePlanKey](#)), instead of using the [ApiKey](#) `stageKeys` property.

To check whether you've already migrated to default usage plans, use the [get-account](#) CLI command. In the command output, the features list includes an entry of "UsagePlans" when usage plans are enabled.

You can also migrate your APIs to default usage plans by using the AWS CLI as follows:

To migrate to default usage plans using the AWS CLI

1. Call this CLI command: [update-account](#).
2. For the `cli-input-json` parameter, use the following JSON:

```
[  
  {  
    "op": "add",  
    "path": "/features",  
    "value": "UsagePlans"  
  }  
]
```


Create a usage plan

The following procedure describes how to create a usage plan.

AWS Management Console

To create a usage plan

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. In the API Gateway main navigation pane, choose **Usage plans**, and then choose **Create usage plan**.



3. For **Name**, enter a name.
4. (Optional) For **Description**, enter a description.
5. By default, usage plans enable throttling. Enter a **Rate** and a **Burst** for your usage plan. Choose **Throttling** to turn off throttling.
6. By default, usage plans enable a quota for a time period. For **Requests**, enter the total number of requests that a user can make in the time period of your usage plan. Choose **Quota** to turn off the quota.
7. Choose **Create usage plan**.

AWS CLI

The following [create-usage-plan](#) command creates a usage plan that resets at the beginning of the month:

```
aws apigateway create-usage-plan \
--name "New Usage Plan" \
```

```
--description "A new usage plan" \
--throttle burstLimit=10,rateLimit=5 \
--quota limit=500,offset=0,period=MONTH
```

REST API

Call [usageplan:create](#) to create a usage plan.

Add a stage to a usage plan

The following procedure describes how to add a stage to a usage plan.

AWS Management Console

To add a stage to a usage plan

1. Select your usage plan.
2. Under the **Associated stages** tab, choose **Add stage**.

MyUsagePlan

[Actions ▾](#)[Export usage data](#)

Usage plan details

Usage plan ID

abc123

Rate

100 requests per second

Description

My new usage plan

Burst

20 requests

AWS Marketplace product code

-

Quota

10 requests per month

[Associated stages](#)[Associated API keys](#)[Tags](#)**Associated stages (0)** [Info](#)[Edit](#)[Remove](#)[Add stage](#)[API](#)[▼](#)[Stage](#)[▼](#)[Method throttling](#)**No stages**

You don't have any stages.

[Add API stage](#)

3. For **API**, select an API.
4. For **Stage**, select a stage.
5. (Optional) To turn on method-level throttling, do the following:
 - a. Choose **Method-level throttling**, and then choose **Add method**.
 - b. For **Resource**, select a resource from your API.
 - c. For **Method**, select a method from your API.
 - d. Enter a **Rate** and a **Burst** for your usage plan.
6. Choose **Add to usage plan**.

AWS CLI

The following [update-usage-plan](#) command adds the Prod stage of an API to a usage plan:

```
aws apigateway update-usage-plan \
--usage-plan-id abc123 \
--patch-operations op="add",path="/apiStages",value="a1b1c2:Prod"
```

REST API

Call [usageplan:update](#) to update a usage plan.

Add an API key to a usage plan

The following procedure shows how to add an API key to a usage plan.

AWS Management Console

To add a key to a usage plan

1. Under the **Associated API keys** tab, choose **Add API key**.

MyUsagePlan

[Actions ▾](#)[Export usage data](#)

Usage plan details

Usage plan ID

abc123

Rate

100 requests per second

Description

My new usage plan

Burst

20 requests

AWS Marketplace product code

-

Quota

10 requests per month

[Associated stages](#)[Associated API keys](#)[Tags](#)**API keys (0)** [Info](#)[Actions ▾](#)[Add API key](#)< 1 > [⚙️](#)Name ▼ Status ▼ ID ▼ API key ▼ Requests remaining this month ▼**No API keys.**

This usage plan has no API keys.

[Add API key](#)

2.
 - a. To associate an existing key to your usage plan, select **Add existing key**, and then select your existing key from the dropdown menu.
 - b. To create a new API key, select **Create and add new key**, and then create a new key. For more information on how to create a new key, see [Create an API key](#).
3. Choose **Add API key**.

AWS CLI

The following [create-usage-plan-key](#) command associates an existing API key with a usage plan:

```
aws apigateway create-usage-plan-key \
--usage-plan-id a1b2c3 \
```

```
--key-type "API_KEY" \
--key-id aaa111bbb
```

REST API

Call [usageplankey:create](#) to associate an existing API key with a usage plan.

You can also directly associate your APIs keys with a usage plan when you import them. Call [apikey:import](#) to add one or more API keys directly to the specified usage plan. The request payload should contain API key values, the associated usage plan identifier, the Boolean flags to indicate that the keys are enabled for the usage plan, and, possibly, the API key names and descriptions.

The following example of the `apikey:import` request adds three API keys (as identified by key, name, and description) to one usage plan (as identified by `usageplanIds`):

```
POST /apikeys?mode=import&format=csv&failonwarnings=false HTTP/1.1
Host: apigateway.us-east-1.amazonaws.com
Content-Type: text/csv
Authorization: ...

key,name,description,enabled,usageplanIds
abcdef1234ghijklmnop8901234567, importedKey_1, firstone, tRuE, n371pt
abcdef1234ghijklmnop0123456789, importedKey_2, secondone, TRUE, n371pt
abcdef1234ghijklmnop9012345678, importedKey_3, , true, n371pt
```

As a result, three `UsagePlanKey` resources are created and added to the `UsagePlan`.

You can also add API keys to more than one usage plan this way. To do this, change each `usageplanIds` column value to a comma-separated string that contains the selected usage plan identifiers, and is enclosed within a pair of quotes ("n371pt,m282qs" or 'n371pt,m282qs').

Note

An API key can be associated with more than one usage plan. A usage plan can be associated with more than one stage. However, a given API key can only be associated with one usage plan for each stage of your API.

Maintain a usage plan for REST APIs in API Gateway

Maintaining a usage plan involves monitoring the used and remaining quotas over a given time period and, if needed, extending the remaining quotas by a specified amount. The following procedures describe how to monitor quotas.

AWS Management Console

To monitor used and remaining quotas

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. In the API Gateway main navigation pane, choose **Usage plans**.
3. Select a usage plan.
4. Choose the **Associated API keys** tab to see the number of request remaining for the time period for each key.
5. (Optional) Choose **Export usage data**, and then choose a **From** date and a **To** date. Then choose **JSON** or **CSV** for the exported data format, and then choose **Export**.

The following example shows an exported file.

```
{  
    "px1KW6...qBaz0JH": [  
        [  
            0,  
            5000  
        ],  
        [  
            0,  
            5000  
        ],  
        [  
            0,  
            10  
        ]  
    ]  
}
```

The usage data in the example shows the daily usage data for an API client, as identified by the API key (px1KW6...qBaz0JH), between August 1, 2016 and August 3, 2016. Each daily usage data shows used and remaining quotas. In this example, the subscriber hasn't used

any allotted quotas yet, and the API owner or administrator has reduced the remaining quota from 5000 to 10 on the third day.

The following procedures describe how to modify quotas.

To extend the remaining quotas

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. In the API Gateway main navigation pane, choose **Usage plans**.
3. Select a usage plan.
4. Choose the **Associated API keys** tab to see the number of request remaining for the time period for each key.
5. Select an API key, and then choose **Grant usage extension**.
6. Enter a number for the **Remaining requests** quota. You can increase the renaming requests or decrease the remaining requests for the time period of your usage plan.
7. Choose **Update quota**.

AWS CLI

The following [update-usage-plan](#) examples add, remove, or modify the method-level throttling settings in a usage plan.

 **Note**

Be sure to change us-east-1 to the appropriate Region value for your API.

To add or replace a rate limit for throttling an individual resource and method:

```
aws apigateway --region us-east-1 update-usage-plan --usage-plan-id planId --patch-operations op="replace",path="/apiStages/apiId:stage/throttle/resourcePath/httpMethod/rateLimit",value="0.1"
```

To add or replace a burst limit for throttling an individual resource and method:

```
aws apigateway --region us-east-1 update-usage-plan --usage-plan-id planId --patch-operations op="replace",path="/apiStages/apiId:stage/throttle/resourcePath/httpMethod/burstLimit",value="1"
```

To remove the method-level throttling settings for an individual resource and method:

```
aws apigateway --region us-east-1 update-usage-plan --usage-plan-id planId --patch-operations op="remove",path="/apiStages/apiId:stage/throttle/resourcePath/httpMethod",value=""
```

To remove all method-level throttling settings for an API:

```
aws apigateway --region us-east-1 update-usage-plan --usage-plan-id planId --patch-operations op="remove",path="/apiStages/apiId:stage/throttle ",value=""
```

Here is an example using the Pet Store sample API:

```
aws apigateway --region us-east-1 update-usage-plan --usage-plan-id planId --patch-operations op="replace",path="/apiStages/apiId:stage/throttle",value='"\\"/pets/GET\\":{\\\"rateLimit\\":1.0,\\\"burstLimit\\":1},\\\"//GET\\":{\\\"rateLimit\\":1.0,\\\"burstLimit\\":1}"}'
```

REST API

Call [usageplan:update](#) to maintain a usage plan.

Create and configure API keys and usage plans with CloudFormation

You can use CloudFormation to require API keys on API methods and create a usage plan for an API. The example CloudFormation template does the following:

- Creates an API Gateway API with GET and POST methods.
- Requires an API key for the GET and POST methods. This API receives keys from the X-API-KEY header of each incoming request.
- Creates an API key.
- Creates a usage plan to specify a monthly quota of 1,000 request each month, a throttling rate limit of 100 request each second, and a throttling burst limit of 200 request each second.

- Specifies a method-level throttling rate limit of 50 requests each second and a method-level throttling burst limit of 100 requests per second for the GET method.
- Associates the API stage and API key with the usage plan.

```
AWSTemplateFormatVersion: 2010-09-09
Parameters:
  StageName:
    Type: String
    Default: v1
    Description: Name of API stage.
  KeyName:
    Type: String
    Default: MyKeyName
    Description: Name of an API key
Resources:
  Api:
    Type: 'AWS::ApiGateway::RestApi'
    Properties:
      Name: keys-api
      ApiKeySourceType: HEADER
  PetsResource:
    Type: 'AWS::ApiGateway::Resource'
    Properties:
      RestApiId: !Ref Api
      ParentId: !GetAtt Api.RootResourceId
      PathPart: 'pets'
  PetsMethodGet:
    Type: 'AWS::ApiGateway::Method'
    Properties:
      RestApiId: !Ref Api
      ResourceId: !Ref PetsResource
      HttpMethod: GET
      ApiKeyRequired: true
      AuthorizationType: NONE
      Integration:
        Type: HTTP_PROXY
        IntegrationHttpMethod: GET
        Uri: http://petstore-demo-endpoint.execute-api.com/petstore/pets/
  PetsMethodPost:
    Type: 'AWS::ApiGateway::Method'
    Properties:
      RestApiId: !Ref Api
```

```
ResourceId: !Ref PetsResource
HttpMethod: POST
ApiKeyRequired: true
AuthorizationType: NONE
Integration:
  Type: HTTP_PROXY
  IntegrationHttpMethod: GET
  Uri: http://petstore-demo-endpoint.execute-api.com/petstore/pets/
ApiDeployment:
  Type: 'AWS::ApiGateway::Deployment'
  DependsOn:
    - PetsMethodGet
Properties:
  RestApiId: !Ref Api
  StageName: !Sub '${StageName}'
UsagePlan:
  Type: AWS::ApiGateway::UsagePlan
  DependsOn:
    - ApiDeployment
Properties:
  Description: Example usage plan with a monthly quota of 1000 calls and method-level throttling for /pets GET
  ApiStages:
    - ApiId: !Ref Api
      Stage: !Sub '${StageName}'
    Throttle:
      "/pets/GET":
        RateLimit: 50.0
        BurstLimit: 100
    Quota:
      Limit: 1000
      Period: MONTH
    Throttle:
      RateLimit: 100.0
      BurstLimit: 200
  UsagePlanName: "My Usage Plan"
ApiKey:
  Type: AWS::ApiGateway::ApiKey
  Properties:
    Description: API Key
    Name: !Sub '${KeyName}'
    Enabled: True
UsagePlanKey:
  Type: AWS::ApiGateway::UsagePlanKey
```

```
Properties:  
  KeyId: !Ref ApiKey  
  KeyType: API_KEY  
  UsagePlanId: !Ref UsagePlan  
Outputs:  
  ApiRootUrl:  
    Description: Root Url of the API  
    Value: !Sub 'https://${Api}.execute-api.${AWS::Region}.amazonaws.com/${StageName}'
```

Configure a method to use API keys with an OpenAPI definition

You can use an OpenAPI definition to require API keys on a method.

For each method, create a security requirement object to require an API key to invoke that method. Then, define `api_key` in the security definition. After you create your API, add the new API stage to your usage plan.

The following example creates an API and requires an API key for the POST and GET methods:

OpenAPI 2.0

```
{  
  "swagger" : "2.0",  
  "info" : {  
    "version" : "2024-03-14T20:20:12Z",  
    "title" : "keys-api"  
  },  
  "basePath" : "/v1",  
  "schemes" : [ "https" ],  
  "paths" : {  
    "/pets" : {  
      "get" : {  
        "responses" : { },  
        "security" : [ {  
          "api_key" : [ ]  
        } ],  
        "x-amazon-apigateway-integration" : {  
          "type" : "http_proxy",  
          "httpMethod" : "GET",  
          "uri" : "http://petstore-demo-endpoint.execute-api.com/petstore/pets/",  
          "passthroughBehavior" : "when_no_match"  
        }  
      },  
    },  
  },  
}
```

```
"post" : {
    "responses" : { },
    "security" : [ {
        "api_key" : [ ]
    } ],
    "x-amazon-apigateway-integration" : {
        "type" : "http_proxy",
        "httpMethod" : "GET",
        "uri" : "http://petstore-demo-endpoint.execute-api.com/petstore/pets/",
        "passthroughBehavior" : "when_no_match"
    }
},
},
"securityDefinitions" : {
    "api_key" : {
        "type" : "apiKey",
        "name" : "x-api-key",
        "in" : "header"
    }
}
}
```

OpenAPI 3.0

```
{
    "openapi" : "3.0.1",
    "info" : {
        "title" : "keys-api",
        "version" : "2024-03-14T20:20:12Z"
    },
    "servers" : [ {
        "url" : "{basePath}",
        "variables" : {
            "basePath" : {
                "default" : "v1"
            }
        }
    } ],
    "paths" : {
        "/pets" : {
            "get" : {
                "security" : [ {

```

```
        "api_key" : [ ]
    } ],
    "x-amazon-apigateway-integration" : {
        "httpMethod" : "GET",
        "uri" : "http://petstore-demo-endpoint.execute-api.com/petstore/pets/",
        "passthroughBehavior" : "when_no_match",
        "type" : "http_proxy"
    }
},
"post" : {
    "security" : [ {
        "api_key" : [ ]
    }],
    "x-amazon-apigateway-integration" : {
        "httpMethod" : "GET",
        "uri" : "http://petstore-demo-endpoint.execute-api.com/petstore/pets/",
        "passthroughBehavior" : "when_no_match",
        "type" : "http_proxy"
    }
}
}
},
"components" : {
    "securitySchemes" : {
        "api_key" : {
            "type" : "apiKey",
            "name" : "x-api-key",
            "in" : "header"
        }
    }
}
}
```

Test usage plans for REST APIs in API Gateway

As an example, let's use the PetStore API, which was created in [Tutorial: Create a REST API by importing an example](#). Assume that the API is configured to use an API key of Hiorr45VR...c4GJc. The following steps describe how to test a usage plan.

To test your usage plan

- Make a GET request on the Pets resource (/pets), with the ?type=...&page=... query parameters, of the API (for example, xbvx1pijch) in a usage plan:

```
GET /testStage/pets?type=dog&page=1 HTTP/1.1
x-api-key: Hiorr45VR...c4GJc
Content-Type: application/x-www-form-urlencoded
Host: xbvx1pijch.execute-api.ap-southeast-1.amazonaws.com
X-Amz-Date: 20160803T001845Z
Authorization: AWS4-HMAC-SHA256 Credential={access_key_ID}/20160803/ap-southeast-1/
execute-api/aws4_request, SignedHeaders=content-type;host;x-amz-date;x-api-key,
Signature={sigv4_hash}
```

Note

You must submit this request to the execute-api component of API Gateway and provide the required API key (for example, Hiorr45VR...c4GJc) in the required x-api-key header.

The successful response returns a 200 OK status code and a payload that contains the requested results from the backend. If you forget to set the x-api-key header or set it with an incorrect key, you get a 403 Forbidden response. However, if you didn't configure the method to require an API key, you will likely get a 200 OK response whether you set the x-api-key header correctly or not, and the throttle and quota limits of the usage plan are bypassed.

Occasionally, when an internal error occurs where API Gateway is unable to enforce usage plan throttling limits or quotas for the request, API Gateway serves the request without applying the throttling limits or quotas as specified in the usage plan. But, it logs an error message of Usage Plan check failed due to an internal error in CloudWatch. You can ignore such occasional errors.

Call a method using an API key

Depending on the API key source type you choose, use one of the following procedures to use header-sourced API keys or authorizer-returned API keys in method invocation:

To use header-sourced API keys:

1. Create an API with desired API methods, and then deploy the API to a stage.
2. Create a new usage plan or choose an existing one. Add the deployed API stage to the usage plan. Attach an API key to the usage plan or choose an existing API key in the plan. Note the chosen API key value.
3. Set up API methods to require an API key.
4. Redeploy the API to the same stage. If you deploy the API to a new stage, make sure to update the usage plan to attach the new API stage.
5. Call the API using the API key. The following example curl command invokes the GET method on the `getUsers` resource of the `prod` stage of an API using an API key.

```
curl -H "X-API-Key: abcd1234" 'https://b123abcde4.execute-api.us-west-2.amazonaws.com/prod/getUsers'
```

The client can now call the API methods while supplying the `x-api-key` header with the chosen API key as the header value. A call might look like the following:

To use authorizer-sourced API keys:

1. Create an API with desired API methods, and then deploy the API to a stage.
2. Create a new usage plan or choose an existing one. Add the deployed API stage to the usage plan. Attach an API key to the usage plan or choose an existing API key in the plan. Note the chosen API key value.
3. Create a token-based Lambda authorizer. Include, `usageIdentifierKey: {api-key}` as a root-level property of the authorization response. For instructions on creating a token-based authorizer, see [the section called “Example TOKEN authorizer Lambda function”](#).
4. Set up API methods to require an API key and enable the Lambda authorizer on the methods as well.
5. Redeploy the API to the same stage. If you deploy the API to a new stage, make sure to update the usage plan to attach the new API stage.

The client can now call the API key-required methods without explicitly supplying any API key. The authorizer-returned API key is used automatically.

Documentation for REST APIs in API Gateway

To help customers understand and use your API, you should document the API. To help you document your API, API Gateway lets you add and update the help content for individual API entities as an integral part of your API development process. API Gateway stores the source content and enables you to archive different versions of the documentation. You can associate a documentation version with an API stage, export a stage-specific documentation snapshot to an external OpenAPI file, and distribute the file as a publication of the documentation.

To document your API, you can call the [API Gateway REST API](#), use one of the [AWS SDKs](#), use the [AWS CLI](#) for API Gateway, or use the API Gateway console. In addition, you can import or export the documentation parts that are defined in an external OpenAPI file.

To share API documentation with developers, you can use a developer portal. For an example, see [Integrating ReadMe with API Gateway to Keep Your Developer Hub Up to Date](#) or [How to Streamline API Development on Amazon API Gateway Using SmartBear's SwaggerHub](#) on the AWS Partner Network (APN) blog.

Topics

- [Representation of API documentation in API Gateway](#)
- [Document an API using the API Gateway console](#)
- [Publish API documentation using the API Gateway console](#)
- [Document an API using the API Gateway REST API](#)
- [Publish API documentation using the API Gateway REST API](#)
- [Import API documentation](#)
- [Control access to API documentation in API Gateway](#)

Representation of API documentation in API Gateway

API Gateway API documentation consists of individual documentation parts associated with specific API entities that include API, resource, method, request, response, message parameters (i.e., path, query, header), as well as authorizers and models.

In API Gateway, a documentation part is represented by a [DocumentationPart](#) resource. The API documentation as a whole is represented by the [DocumentationParts](#) collection.

Documenting an API involves creating `DocumentationPart` instances, adding them to the `DocumentationParts` collection, and maintaining versions of the documentation parts as your API evolves.

Topics

- [Documentation parts](#)
- [Documentation versions](#)

Documentation parts

A `DocumentationPart` resource is a JSON object that stores the documentation content applicable to an individual API entity. This includes any UTF-8 content and all major localization languages for your documentation. Its `properties` field contains the documentation content as a map of key-value pairs. Its `location` property identifies the associated API entity.

The shape of a content map is determined by you, the API developer. The value of a key-value pair can be a string, number, boolean, object, or array. The shape of the `location` object depends on the targeted entity type.

The `DocumentationPart` resource supports content inheritance: the documentation content of an API entity is applicable to children of that API entity. For more information about the definition of child entities and content inheritance, see [Inherit Content from an API Entity of More General Specification](#).

Location of a documentation part

The `location` property of a `DocumentationPart` instance identifies an API entity to which the associated content applies. The API entity can be an API Gateway REST API resource, such as `RestApi`, `Resource`, `Method`, `MethodResponse`, `Authorizer`, or `Model`. The entity can also be a message parameter, such as a URL path parameter, a query string parameter, a request or response header parameter, a request or response body, or response status code.

To specify an API entity, set the `type` attribute of the `location` object to be one of `API`, `AUTHORIZER`, `MODEL`, `RESOURCE`, `METHOD`, `PATH_PARAMETER`, `QUERY_PARAMETER`, `REQUEST_HEADER`, `REQUEST_BODY`, `RESPONSE`, `RESPONSE_HEADER`, or `RESPONSE_BODY`.

Depending on the type of an API entity, you might specify other `location` attributes, including `method`, `name`, `path`, and `statusCode`. Not all of these attributes are valid for a given API entity. For example, `type`, `path`, `name`, and `statusCode` are valid attributes of the `RESPONSE` entity; only

type and path are valid location attributes of the RESOURCE entity. It is an error to include an invalid field in the location of a DocumentationPart for a given API entity.

Not all valid location fields are required. For example, type is both the valid and required location field of all API entities. However, method, path, and statusCode are valid but not required attributes for the RESPONSE entity. When not explicitly specified, a valid location field assumes its default value. The default path value is /, i.e., the root resource of an API. The default value of method, or statusCode is *, meaning any method, or status code values, respectively.

Content of a documentation part

The properties value is encoded as a JSON string. The properties value contains any information you choose to meet your documentation requirements. For example, the following is a valid content map:

```
{  
  "info": {  
    "description": "My first API with Amazon API Gateway."  
  },  
  "x-custom-info" : "My custom info, recognized by OpenAPI.",  
  "my-info" : "My custom info not recognized by OpenAPI."  
}
```

Although API Gateway accepts any valid JSON string as the content map, the content attributes are treated as two categories: those that can be recognized by OpenAPI and those that cannot. In the preceding example, info, description, and x-custom-info are recognized by OpenAPI as a standard OpenAPI object, property, or extension. In contrast, my-info is not compliant with the OpenAPI specification. API Gateway propagates OpenAPI-compliant content attributes into the API entity definitions from the associated DocumentationPart instances. API Gateway does not propagate the non-compliant content attributes into the API entity definitions.

As another example, here is DocumentationPart targeted for a Resource entity:

```
{  
  "location" : {  
    "type" : "RESOURCE",  
    "path": "/pets"  
  },  
  "properties" : {  
    "summary" : "The /pets resource represents a collection of pets in PetStore."  
  }  
}
```

```
        "description": "... a child resource under the root...",
    }
}
```

Here, both type and path are valid fields to identify the target of the RESOURCE type. For the root resource (/), you can omit the path field.

```
{
  "location" : {
    "type" : "RESOURCE"
  },
  "properties" : {
    "description" : "The root resource with the default path specification."
  }
}
```

This is the same as the following DocumentationPart instance:

```
{
  "location" : {
    "type" : "RESOURCE",
    "path": "/"
  },
  "properties" : {
    "description" : "The root resource with an explicit path specification"
  }
}
```

Inherit content from an API entity of more general specifications

The default value of an optional location field provides a patterned description of an API entity. Using the default value in the location object, you can add a general description in the properties map to a DocumentationPart instance with this type of location pattern. API Gateway extracts the applicable OpenAPI documentation attributes from the DocumentationPart of the generic API entity and injects them into a specific API entity with the location fields matching the general location pattern, or matching the exact value, unless the specific entity already has a DocumentationPart instance associated with it. This behavior is also known as content inheritance from an API entity of more general specifications.

Content inheritance does not apply to certain API entity types. See the table below for details.

When an API entity matches more than one DocumentationPart's location pattern, the entity will inherit the documentation part with the location fields of the highest precedence and specificities. The order of precedence is path > statusCode. For matching with the path field, API Gateway chooses the entity with the most specific path value. The following table shows this with a few examples.

Case	path	statusCode	name	Remark
1	/pets	*	id	Documentation associated with this location pattern will be inherited by entities matching the location pattern.
2	/pets	200	id	Documentation associated with this location pattern will be

Case	path	stat	name	Remark
		e		
				inherited by entities matching the location pattern when both Case 1 and Case 2 are matched, because Case 2 is more specific than Case 1.

Case	path	stat	name	Remar
		e		
3	/pets/ petId	*	id	Documenta tion associate d with this location pattern will be inherited by entities matching the location pattern when Cases 1, 2, and 3 are matched, because Case 3 has a higher precedenc e than Case 2

Case	path	stat	name	Remar
		e		
				and is more specific than Case 1.

Here is another example to contrast a more generic DocumentationPart instance to a more specific one. The following general error message of "Invalid request error" is injected into the OpenAPI definitions of the `400` error responses, unless overridden.

```
{
  "location" : {
    "type" : "RESPONSE",
    "statusCode": "400"
  },
  "properties" : {
    "description" : "Invalid request error."
  }
}
```

With the following overwrite, the `400` responses to any methods on the `/pets` resource has a description of "Invalid petId specified" instead.

```
{
  "location" : {
    "type" : "RESPONSE",
    "path": "/pets",
    "statusCode": "400"
  },
  "properties" : "{",
    "description" : "Invalid petId specified."
  }
}
```

Valid location fields of DocumentationPart

The following table shows the valid and required fields as well as applicable default values of a [DocumentationPart](#) resource that is associated with a given type of API entities.

API entity	Valid location fields	Required location fields	Default field values	Inheritable content
API	{ "location": { "type": "API" }, ... }	type	N/A	No
Resource	{ "location": { "type": "RESOURCE" }, "path": " resource_path " }, ... }	type	The default value of path is /.	No
Method	{ "location": { "type": " METHOD ", "path": " resource_path ", "method": " http_verb " }, ... }	type	The default values of path and method are / and *, respectively.	Yes, matching path by prefix and matching method of any values.
Query parameter	{	type	The default values of path	Yes, matching

API entity	Valid location fields	Required location fields	Default field values	Inheritable content
	<pre data-bbox="300 312 714 819"> "location": { "type": "QUERY_PARAMETER", "path": "<i>resource_path</i>", "method": "<i>HTTP_verb</i>", "name": "<i>query_parameter_name</i>" }, ... } </pre>		and method are / and *, respectively.	path by prefix and matching method by exact values.
Request body	<pre data-bbox="300 889 714 1332"> { "location": { "type": "REQUEST_BODY", "path": "<i>resource_path</i>", "method": "<i>http_verb</i>" }, ... } </pre>	type	The default values of path, and method are / and *, respectively.	Yes, matching path by prefix, and matching method by exact values.

API entity	Valid location fields	Required location fields	Default field values	Inheritable content
Request header parameter	<pre>{ "location": { "type": "REQUEST_HEADER", "path": "<i>resource_path</i>", "method": "<i>HTTP_verb</i>", "name": "<i>header_name</i>" }, ... }</pre>	type, name	The default values of path and method are / and *, respectively.	Yes, matching path by prefix and matching method by exact values.
Request path parameter	<pre>{ "location": { "type": "PATH_PARAMETER", "path": "<i>resource/{path_parameter_name}</i>", "method": "<i>HTTP_verb</i>", "name": "<i>path_parameter_name</i>" }, ... }</pre>	type, name	The default values of path and method are / and *, respectively.	Yes, matching path by prefix and matching method by exact values.

API entity	Valid location fields	Required location fields	Default field values	Inheritable content
Response	<pre>{ "location": { "type": "RESPONSE", "path": "<i>resource_path</i>", "method": "<i>http_verb</i>", "statusCode": "<i>status_code</i>" }, ... }</pre>	type	The default values of path, method, and statusCode are /, * and *, respectively.	Yes, matching path by prefix and matching method and statusCode by exact values.
Response header	<pre>{ "location": { "type": "RESPONSE_HEADER", "path": "<i>resource_path</i>", "method": "<i>http_verb</i>", "statusCode": "<i>status_code</i>", "name": "<i>header_name</i>" }, ... }</pre>	type, name	The default values of path, method and statusCode are /, * and *, respectively.	Yes, matching path by prefix and matching method, and statusCode by exact values.

API entity	Valid location fields	Required location fields	Default field values	Inheritable content
Response body	<pre>{ "location": { "type": "RESPONSE_BODY", "path": "<i>resource_path</i>", "method": "<i>http_verb</i>", "statusCode": "<i>status_code</i>" }, ... }</pre>	type	The default values of path, method and statusCode are /, * and *, respectively.	Yes, matching path by prefix and matching method, and statusCode by exact values.
<u>Authorize</u>	<pre>{ "location": { "type": "AUTHORIZER", "name": "<i>authorizer_name</i>" }, ... }</pre>	type	N/A	No
<u>Model</u>	<pre>{ "location": { "type": "MODEL", "name": "<i>model_name</i>" }, ... }</pre>	type	N/A	No

Documentation versions

A documentation version is a snapshot of the [DocumentationParts](#) collection of an API and is tagged with a version identifier. Publishing the documentation of an API involves creating a documentation version, associating it with an API stage, and exporting that stage-specific version of the API documentation to an external OpenAPI file. In API Gateway, a documentation snapshot is represented as a [DocumentationVersion](#) resource.

As you update an API, you create new versions of the API. In API Gateway, you maintain all the documentation versions using the [DocumentationVersions](#) collection.

Document an API using the API Gateway console

In this section, we describe how to create and maintain documentation parts of an API using the API Gateway console.

A prerequisite for creating and editing the documentation of an API is that you must have already created the API. In this section, we use the [PetStore](#) API as an example. To create an API using the API Gateway console, follow the instructions in [Tutorial: Create a REST API by importing an example](#).

Topics

- [Document the API entity](#)
- [Document a RESOURCE entity](#)
- [Document a METHOD entity](#)
- [Document a QUERY_PARAMETER entity](#)
- [Document a PATH_PARAMETER entity](#)
- [Document a REQUEST_HEADER entity](#)
- [Document a REQUEST_BODY entity](#)
- [Document a RESPONSE entity](#)
- [Document a RESPONSE_HEADER entity](#)
- [Document a RESPONSE_BODY entity](#)
- [Document a MODEL entity](#)
- [Document an AUTHORIZER entity](#)

Document the API entity

To add a new documentation part for the API entity, do the following:

1. In the main navigation pane, choose **Documentation**, and then choose **Create documentation part**.
2. For **Documentation type**, select **API**.

If a documentation part was not created for the API, you get the documentation part's properties map editor. Enter the following properties map in the text editor.

```
{  
  "info": {  
    "description": "Your first API Gateway API.",  
    "contact": {  
      "name": "John Doe",  
      "email": "john.doe@api.com"  
    }  
  }  
}
```

 **Note**


You do not need to encode the properties map into a JSON string. The API Gateway console stringifies the JSON object for you.

3. Choose **Create documentation part**.

To add a new documentation part for the API entity in the **Resources** pane, do the following:

1. In the main navigation pane, choose **Resources**.
2. Choose the **API actions** menu, and then choose **Update API documentation**.

Resources



To edit an existing documentation part, do the following:

1. In the **Documentation** pane, choose the **Resources and methods** tab.
2. Select the name of your API, and then on the API card, choose **Edit**.

Document a RESOURCE entity

To add a new documentation part for a RESOURCE entity, do the following:

1. In the main navigation pane, choose **Documentation**, and then choose **Create documentation part**.
2. For **Documentation type**, select **Resource**.
3. For **Path**, enter a path.
4. Enter a description in the text editor, for example:

```
{  
    "description": "The PetStore's root resource."  
}
```

5. Choose **Create documentation part**. You can create documentation for an unlisted resource.
6. If required, repeat these steps to add or edit another documentation part.

To add a new documentation part for a RESOURCE entity in the **Resources** pane, do the following:

1. In the main navigation pane, choose **Resources**.
2. Choose the resource, and then choose **Update documentation**.

Resources

[API actions ▾](#)[Deploy API](#)

The screenshot shows the AWS API Gateway interface under the 'Resources' tab. On the left, there's a sidebar with a 'Create resource' button. The main area shows a resource with the path '/pets' and a single method 'GET'. On the right, the 'Resource details' section shows the path '/pets' and a resource ID 'bbb111'. There are four buttons at the top of this section: 'Delete', 'Update documentation' (which is highlighted with a red box), 'Enable CORS', and another unlabeled blue button.

To edit an existing documentation part, do the following:

1. In the **Documentation** pane, choose the **Resources and methods** tab.
2. Select the resource containing your documentation part, and then choose **Edit**.

Document a METHOD entity

To add a new documentation part for a METHOD entity, do the following:

1. In the main navigation pane, choose **Documentation**, and then choose **Create documentation part**.
2. For **Documentation type**, select **Method**.
3. For **Path**, enter a path.
4. For **Method**, select an HTTP verb.
5. Enter a description in the text editor, for example:


```
{  
  "tags" : [ "pets" ],  
  "summary" : "List all pets"  
}
```

6. Choose **Create documentation part**. You can create documentation for an unlisted method.
7. If required, repeat these steps to add or edit another documentation part.

To add a new documentation part for a METHOD entity in the **Resources** pane, do the following:

1. In the main navigation pane, choose **Resources**.
2. Choose the method, and then choose **Update documentation**.

Resources



To edit an existing documentation part, do the following:

1. In the **Documentation** pane, choose the **Resources and methods** tab.
2. You can select the method or select the resource containing the method, and then use the search bar to find and select your documentation part.
3. Choose **Edit**.

Document a QUERY_PARAMETER entity

To add a new documentation part for a QUERY_PARAMETER entity, do the following:

1. In the main navigation pane, choose **Documentation**, and then choose **Create documentation part**.
2. For **Documentation type**, select **Query parameter**.
3. For **Path**, enter a path.
4. For **Method**, select an HTTP verb.
5. For **Name**, enter a name.
6. Enter a description in the text editor.
7. Choose **Create documentation part**. You can create documentation for an unlisted query parameter.

8. If required, repeat these steps to add or edit another documentation part.

To edit an existing documentation part, do the following:

1. In the **Documentation** pane, choose the **Resources and methods** tab.
2. You can select the query parameter or select the resource containing the query parameter, and then use the search bar to find and select your documentation part.
3. Choose **Edit**.

Document a PATH_PARAMETER entity

To add a new documentation part for a PATH_PARAMETER entity, do the following:

1. In the main navigation pane, choose **Documentation**, and then choose **Create documentation part**.
2. For **Documentation type**, select **Path parameter**.
3. For **Path**, enter a path.
4. For **Method**, select an HTTP verb.
5. For **Name**, enter a name.
6. Enter a description in the text editor.
7. Choose **Create documentation part**. You can create documentation for an unlisted path parameter.
8. If required, repeat these steps to add or edit another documentation part.

To edit an existing documentation part, do the following:

1. In the **Documentation** pane, choose the **Resources and methods** tab.
2. You can select the path parameter or select the resource containing the path parameter, and then use the search bar to find and select your documentation part.
3. Choose **Edit**.

Document a REQUEST_HEADER entity

To add a new documentation part for a REQUEST_HEADER entity, do the following:

1. In the main navigation pane, choose **Documentation**, and then choose **Create documentation part**.
2. For **Documentation type**, select **Request header**.
3. For **Path**, enter a path for the request header.
4. For **Method**, select an HTTP verb.
5. For **Name**, enter a name.
6. Enter a description in the text editor.
7. Choose **Create documentation part**. You can create documentation for an unlisted request header.
8. If required, repeat these steps to add or edit another documentation part.

To edit an existing documentation part, do the following:

1. In the **Documentation** pane, choose the **Resources and methods** tab.
2. You can select the request header or select the resource containing the request header, and then use the search bar to find and select your documentation part.
3. Choose **Edit**.

Document a REQUEST_BODY entity

To add a new documentation part for a REQUEST_BODY entity, do the following:

1. In the main navigation pane, choose **Documentation**, and then choose **Create documentation part**.
2. For **Documentation type**, select **Request body**.
3. For **Path**, enter a path for the request body.
4. For **Method**, select an HTTP verb.
5. Enter a description in the text editor.
6. Choose **Create documentation part**. You can create documentation for an unlisted request body.
7. If required, repeat these steps to add or edit another documentation part.

To edit an existing documentation part, do the following:

1. In the **Documentation** pane, choose the **Resources and methods** tab.
2. You can select the request body or select the resource containing the request body, and then use the search bar to find and select your documentation part.
3. Choose **Edit**.

Document a RESPONSE entity

To add a new documentation part for a RESPONSE entity, do the following:

1. In the main navigation pane, choose **Documentation**, and then choose **Create documentation part**.
2. For **Documentation type**, select **Response (status code)**.
3. For **Path**, enter a path for the response.
4. For **Method**, select an HTTP verb.
5. For **Status code**, enter an HTTP status code.
6. Enter a description in the text editor.
7. Choose **Create documentation part**. You can create documentation for an unlisted response status code.
8. If required, repeat these steps to add or edit another documentation part.

To edit an existing documentation part, do the following:

1. In the **Documentation** pane, choose the **Resources and methods** tab.
2. You can select the response status code or select the resource containing the response status code, and then use the search bar to find and select your documentation part.
3. Choose **Edit**.

Document a RESPONSE_HEADER entity

To add a new documentation part for a RESPONSE_HEADER entity, do the following:

1. In the main navigation pane, choose **Documentation**, and then choose **Create documentation part**.
2. For **Documentation type**, select **Response header**.

3. For **Path**, enter a path for the response header.
4. For **Method**, select an HTTP verb.
5. For **Status code**, enter an HTTP status code.
6. Enter a description in the text editor.
7. Choose **Create documentation part**. You can create documentation for an unlisted response header.
8. If required, repeat these steps to add or edit another documentation part.

To edit an existing documentation part, do the following:

1. In the **Documentation** pane, choose the **Resources and methods** tab.
2. You can select the response header or select the resource containing the response header, and then use the search bar to find and select your documentation part.
3. Choose **Edit**.

Document a RESPONSE_BODY entity

To add a new documentation part for a RESPONSE_BODY entity, do the following:

1. In the main navigation pane, choose **Documentation**, and then choose **Create documentation part**.
2. For **Documentation type**, select **Response body**.
3. For **Path**, enter a path for the response body.
4. For **Method**, select an HTTP verb.
5. For **Status code**, enter an HTTP status code.
6. Enter a description in the text editor.
7. Choose **Create documentation part**. You can create documentation for an unlisted response body.
8. If required, repeat these steps to add or edit another documentation part.

To edit an existing documentation part, do the following:

1. In the **Documentation** pane, choose the **Resources and methods** tab.

2. You can select the response body or select the resource containing the response body, and then use the search bar to find and select your documentation part.
3. Choose **Edit**.

Document a MODEL entity

Documenting a MODEL entity involves creating and managing DocumentPart instances for the model and each of the model's properties'. For example, for the Error model that comes with every API by default has the following schema definition,

```
{  
  "$schema": "http://json-schema.org/draft-04/schema#",  
  "title": "Error Schema",  
  "type": "object",  
  "properties": {  
    "message": { "type": "string" }  
  }  
}
```

and requires two DocumentationPart instances, one for the Model and the other for its message property:

```
{  
  "location": {  
    "type": "MODEL",  
    "name": "Error"  
  },  
  "properties": {  
    "title": "Error Schema",  
    "description": "A description of the Error model"  
  }  
}
```

and

```
{  
  "location": {  
    "type": "MODEL",  
    "name": "Error.message"  
  },
```

```
"properties": {  
    "description": "An error message."  
}  
}
```

When the API is exported, the DocumentationPart's properties will override the values in the original schema.

To add a new documentation part for a MODEL entity, do the following:

1. In the main navigation pane, choose **Documentation**, and then choose **Create documentation part**.
2. For **Documentation type**, select **Model**.
3. For **Name**, enter a name for the model.
4. Enter a description in the text editor.
5. Choose **Create documentation part**. You can create documentation for unlisted models.
6. If required, repeat these steps to add or edit a documentation part to other models.

To add a new documentation part for a MODEL entity in the **Models** pane, do the following:

1. In the main navigation pane, choose **Models**.
2. Choose the model, and then choose **Update documentation**.

Models (6)		
	Delete	Edit
	Content type	Description
<input type="radio"/> Empty	application/json	
<input type="radio"/> NewPet	application/json	
<input checked="" type="radio"/> NewPetResponse	application/json	
<input type="radio"/> Pet	application/json	
<input type="radio"/> Pets	application/json	
<input type="radio"/> PetType	application/json	

To edit an existing documentation part, do the following:

1. In the **Documentation** pane, choose the **Models** tab.
2. Use the search bar or select the model, and then choose **Edit**.

Document an AUTHORIZER entity

To add a new documentation part for an AUTHORIZER entity, do the following:

1. In the main navigation pane, choose **Documentation**, and then choose **Create documentation part**.
2. For **Documentation type**, select **Authorizer**.
3. For **Name**, enter the name of your authorizer.
4. Enter a description in the text editor. Specify a value for the valid location field for the authorizer.
5. Choose **Create documentation part**. You can create documentation for unlisted authorizers.
6. If required, repeat these steps to add or edit a documentation part to other authorizers.

To edit an existing documentation part, do the following:

1. In the **Documentation** pane, choose the **Authorizers** tab.
2. Use the search bar or select the authorizer, and then choose **Edit**.

Publish API documentation using the API Gateway console

The following procedure describes how to publish a documentation version.

To publish a documentation version using the API Gateway console

1. In the main navigation pane, choose **Documentation**.
2. Choose **Publish documentation**.
3. Set up the publication:
 - a. For **Stage**, select a stage.
 - b. For **Version**, enter a version identifier, e.g., `1.0.0`.
 - c. (Optional) For **Description**, enter a description.
4. Choose **Publish**.

You can now proceed to download the published documentation by exporting the documentation to an external OpenAPI file. To learn more, see [the section called “Export a REST API”](#).

Document an API using the API Gateway REST API

In this section, we describe how to create and maintain documentation parts of an API using the API Gateway REST API.

Before creating and editing the documentation of an API, first create the API. In this section, we use the [PetStore API](#) as an example. To create an API using the API Gateway console, follow the instructions in [Tutorial: Create a REST API by importing an example](#).

Topics

- [Document the API entity](#)
- [Document a RESOURCE entity](#)
- [Document a METHOD entity](#)
- [Document a QUERY_PARAMETER entity](#)
- [Document a PATH_PARAMETER entity](#)
- [Document a REQUEST_BODY entity](#)
- [Document a REQUEST_HEADER entity](#)
- [Document a RESPONSE entity](#)
- [Document a RESPONSE_HEADER entity](#)
- [Document an AUTHORIZER entity](#)
- [Document a MODEL entity](#)
- [Update documentation parts](#)
- [List documentation parts](#)

Document the API entity

To add documentation for an [API](#), add a [DocumentationPart](#) resource for the API entity:

```
POST /restapis/restapi_id/documentation/parts HTTP/1.1
Host: apigateway.region.amazonaws.com
Content-Type: application/json
X-Amz-Date: YYYYMMDDTtttttZ
```

```
Authorization: AWS4-HMAC-SHA256 Credential=access_key_id/YYYYMMDD/region/  
apigateway/aws4_request, SignedHeaders=content-length;content-type;host;x-amz-date,  
Signature=sigv4_secret  
  
{  
    "location" : {  
        "type" : "API"  
    },  
    "properties": "{\n\t\"info\": {\n\t\t\"description\" : \"Your first API with Amazon  
API Gateway.\n\t}\n}"  
}
```

If successful, the operation returns a 201 Created response containing the newly created DocumentationPart instance in the payload. For example:

```
{  
    ...  
    "id": "s2e5xf",  
    "location": {  
        "path": null,  
        "method": null,  
        "name": null,  
        "statusCode": null,  
        "type": "API"  
    },  
    "properties": "{\n\t\"info\": {\n\t\t\"description\" : \"Your first API with Amazon  
API Gateway.\n\t}\n}"  
}
```

If the documentation part has already been added, a 409 Conflict response returns, containing the error message of Documentation part already exists for the specified location: type 'API'." In this case, you must call the [documentationpart:update](#) operation.

```
PATCH /restapis/4wk1k4onj3/documentation/parts/part_id HTTP/1.1  
Host: apigateway.region.amazonaws.com  
Content-Type: application/json  
X-Amz-Date: YYYYMMDDTtttttZ  
Authorization: AWS4-HMAC-SHA256 Credential=access_key_id/YYYYMMDD/region/  
apigateway/aws4_request, SignedHeaders=content-length;content-type;host;x-amz-date,  
Signature=sigv4_secret  
  
{
```

```
"patchOperations" : [ {
    "op" : "replace",
    "path" : "/properties",
    "value" : "{\n\t\"info\": {\n\t\t\"description\" : \"Your first API with Amazon API\nGateway.\n\t}\n}"
} ]
```

The successful response returns a 200 OK status code with the payload containing the updated DocumentationPart instance in the payload.

Document a RESOURCE entity

To add documentation for the root resource of an API, add a [DocumentationPart](#) resource targeted for the corresponding [Resource](#) resource:

```
POST /restapis/restapi_id/documentation/parts HTTP/1.1
Host: apigateway.region.amazonaws.com
Content-Type: application/json
X-Amz-Date: YYYYMMDDTtttttZ
Authorization: AWS4-HMAC-SHA256 Credential=access_key_id/YYYYMMDD/region/
apigateway/aws4_request, SignedHeaders=content-length;content-type;host;x-amz-date,
Signature=sigv4_secret

{
    "location" : {
        "type" : "RESOURCE",
    },
    "properties" : "{\n\t\"description\" : \"The PetStore root resource.\n\""
}
```

If successful, the operation returns a 201 Created response containing the newly created DocumentationPart instance in the payload. For example:

```
{
    "_links": {
        "curies": {
            "href": "http://docs.aws.amazon.com/apigateway/latest/developerguide/restapi-
documentationpart-{rel}.html",
            "name": "documentationpart",
            "templated": true
        },
    }
}
```

```
"self": {
    "href": "/restapis/4wk1k4onj3/documentation/parts/p76vqo"
},
"documentationpart:delete": {
    "href": "/restapis/4wk1k4onj3/documentation/parts/p76vqo"
},
"documentationpart:update": {
    "href": "/restapis/4wk1k4onj3/documentation/parts/p76vqo"
}
},
"id": "p76vqo",
"location": {
    "path": "/",
    "method": null,
    "name": null,
    "statusCode": null,
    "type": "RESOURCE"
},
"properties": "{\n\t\"description\" : \"The PetStore root resource.\n}"
}
```

When the resource path is not specified, the resource is assumed to be the root resource. You can add "path": "/" to properties to make the specification explicit.

To create documentation for a child resource of an API, add a [DocumentationPart](#) resource targeted for the corresponding [Resource](#) resource:

```
POST /restapis/restapi_id/documentation/parts HTTP/1.1
Host: apigateway.region.amazonaws.com
Content-Type: application/json
X-Amz-Date: YYYYMMDDTtttttZ
Authorization: AWS4-HMAC-SHA256 Credential=access_key_id/YYYYMMDD/region/
apigateway/aws4_request, SignedHeaders=content-length;content-type;host;x-amz-date,
Signature=sigv4_secret

{
    "location" : {
        "type" : "RESOURCE",
        "path" : "/pets"
    },
    "properties": "{\n\t\"description\" : \"A child resource under the root of
PetStore.\n}"
}
```

If successful, the operation returns a 201 Created response containing the newly created DocumentationPart instance in the payload. For example:

```
{  
  "_links": {  
    "curies": {  
      "href": "http://docs.aws.amazon.com/apigateway/latest/developerguide/restapi-documentationpart-{rel}.html",  
      "name": "documentationpart",  
      "templated": true  
    },  
    "self": {  
      "href": "/restapis/4wk1k4onj3/documentation/parts/qcht86"  
    },  
    "documentationpart:delete": {  
      "href": "/restapis/4wk1k4onj3/documentation/parts/qcht86"  
    },  
    "documentationpart:update": {  
      "href": "/restapis/4wk1k4onj3/documentation/parts/qcht86"  
    }  
  },  
  "id": "qcht86",  
  "location": {  
    "path": "/pets",  
    "method": null,  
    "name": null,  
    "statusCode": null,  
    "type": "RESOURCE"  
  },  
  "properties": "{\n\t\"description\" : \"A child resource under the root of PetStore.\n\"}\n"}  
}
```

To add documentation for a child resource specified by a path parameter, add a [DocumentationPart](#) resource targeted for the [Resource](#) resource:

```
POST /restapis/restapi_id/documentation/parts HTTP/1.1  
Host: apigateway.region.amazonaws.com  
Content-Type: application/json  
X-Amz-Date: YYYYMMDDTtttttZ  
Authorization: AWS4-HMAC-SHA256 Credential=access_key_id/YYYYMMDD/region/  
apigateway/aws4_request, SignedHeaders=content-length;content-type;host;x-amz-date,  
Signature=sigv4_secret
```

```
{  
  "location" : {  
    "type" : "RESOURCE",  
    "path" : "/pets/{petId}"  
  },  
  "properties": "{\n\t\"description\" : \"A child resource specified by the petId  
path parameter.\n\"}  
}
```

If successful, the operation returns a 201 Created response containing the newly created DocumentationPart instance in the payload. For example:

```
{  
  "_links": {  
    "curies": {  
      "href": "http://docs.aws.amazon.com/apigateway/latest/developerguide/restapi-  
documentationpart-{rel}.html",  
      "name": "documentationpart",  
      "templated": true  
    },  
    "self": {  
      "href": "/restapis/4wk1k4onj3/documentation/parts/k6fpwb"  
    },  
    "documentationpart:delete": {  
      "href": "/restapis/4wk1k4onj3/documentation/parts/k6fpwb"  
    },  
    "documentationpart:update": {  
      "href": "/restapis/4wk1k4onj3/documentation/parts/k6fpwb"  
    }  
  },  
  "id": "k6fpwb",  
  "location": {  
    "path": "/pets/{petId}",  
    "method": null,  
    "name": null,  
    "statusCode": null,  
    "type": "RESOURCE"  
  },  
  "properties": "{\n\t\"description\" : \"A child resource specified by the petId path  
parameter.\n\"}  
}
```

Note

The [DocumentationPart](#) instance of a RESOURCE entity cannot be inherited by any of its child resources.

Document a METHOD entity

To add documentation for a method of an API, add a [DocumentationPart](#) resource targeted for the corresponding [Method](#) resource:

```
POST /restapis/restapi_id/documentation/parts HTTP/1.1
Host: apigateway.region.amazonaws.com
Content-Type: application/json
X-Amz-Date: YYYYMMDDTtttttZ
Authorization: AWS4-HMAC-SHA256 Credential=access_key_id/YYYYMMDD/region/
apigateway/aws4_request, SignedHeaders=content-length;content-type;host;x-amz-date,
Signature=sigv4_secret

{
  "location" : {
    "type" : "METHOD",
    "path" : "/pets",
    "method" : "GET"
  },
  "properties": "{\n\t\"summary\" : \"List all pets.\n\""
}
```

If successful, the operation returns a 201 Created response containing the newly created DocumentationPart instance in the payload. For example:

```
{
  "_links": {
    "curies": {
      "href": "http://docs.aws.amazon.com/apigateway/latest/developerguide/restapi-
documentationpart-{rel}.html",
      "name": "documentationpart",
      "templated": true
    },
    "self": {
      "href": "/restapis/4wk1k4onj3/documentation/parts/o64jbj"
    }
}
```

```
"documentationpart:delete": {
    "href": "/restapis/4wk1k4onj3/documentation/parts/o64bjbj"
},
"documentationpart:update": {
    "href": "/restapis/4wk1k4onj3/documentation/parts/o64bjbj"
}
},
"id": "o64bjbj",
"location": {
    "path": "/pets",
    "method": "GET",
    "name": null,
    "statusCode": null,
    "type": "METHOD"
},
"properties": "{\n\t\"summary\" : \"List all pets.\"\n}"
}
```

If successful, the operation returns a 201 Created response containing the newly created DocumentationPart instance in the payload. For example:

```
{
    "_links": {
        "curies": {
            "href": "http://docs.aws.amazon.com/apigateway/latest/developerguide/restapi-
documentationpart-{rel}.html",
            "name": "documentationpart",
            "templated": true
        },
        "self": {
            "href": "/restapis/4wk1k4onj3/documentation/parts/o64bjbj"
        }
    },
    "documentationpart:delete": {
        "href": "/restapis/4wk1k4onj3/documentation/parts/o64bjbj"
    },
    "documentationpart:update": {
        "href": "/restapis/4wk1k4onj3/documentation/parts/o64bjbj"
    }
},
"id": "o64bjbj",
"location": {
    "path": "/pets",
    "method": "GET",
}
```

```
"name": null,  
"statusCode": null,  
"type": "METHOD"  
,  
"properties": "{\n\t\"summary\" : \"List all pets.\\"\n}"  
}
```

If the `location.method` field is not specified in the preceding request, it is assumed to be ANY method that is represented by a wild card * character.

To update the documentation content of a METHOD entity, call the [documentationpart:update](#) operation, supplying a new properties map:

```
PATCH /restapis/4wk1k4onj3/documentation/parts/part_id HTTP/1.1  
Host: apigateway.region.amazonaws.com  
Content-Type: application/json  
X-Amz-Date: YYYYMMDDTtttttZ  
Authorization: AWS4-HMAC-SHA256 Credential=access_key_id/YYYYMMDD/region/  
apigateway/aws4_request, SignedHeaders=content-length;content-type;host;x-amz-date,  
Signature=sigv4_secret  
  
{  
  "patchOperations" : [ {  
    "op" : "replace",  
    "path" : "/properties",  
    "value" : "{\n\t\"tags\" : [ \"pets\" ],\n\t\"summary\" : \"List all pets.\\"\n}"  
  } ]  
}
```

The successful response returns a 200 OK status code with the payload containing the updated DocumentationPart instance in the payload. For example:

```
{  
  "_links": {  
    "curies": {  
      "href": "http://docs.aws.amazon.com/apigateway/latest/developerguide/restapi-  
documentationpart-{rel}.html",  
      "name": "documentationpart",  
      "templated": true  
    },  
    "self": {  
      "href": "/restapis/4wk1k4onj3/documentation/parts/o64bjbj"  
    }  
  }  
}
```

```
},
"documentationpart:delete": {
    "href": "/restapis/4wk1k4onj3/documentation/parts/o64bjj"
},
"documentationpart:update": {
    "href": "/restapis/4wk1k4onj3/documentation/parts/o64bjj"
}
},
"id": "o64bjj",
"location": {
    "path": "/pets",
    "method": "GET",
    "name": null,
    "statusCode": null,
    "type": "METHOD"
},
"properties": "{\n\t\"tags\" : [ \"pets\" ], \n\t\"summary\" : \"List all pets.\"\\n}"
}
```

Document a QUERY_PARAMETER entity

To add documentation for a request query parameter, add a [DocumentationPart](#) resource targeted for the QUERY_PARAMETER type, with the valid fields of path and name.

```
POST /restapis/restapi_id/documentation/parts HTTP/1.1
Host: apigateway.region.amazonaws.com
Content-Type: application/json
X-Amz-Date: YYYYMMDDTTttttZ
Authorization: AWS4-HMAC-SHA256 Credential=access_key_id/YYYYMMDD/region/
apigateway/aws4_request, SignedHeaders=content-length;content-type;host;x-amz-date,
Signature=sigv4_secret

{
    "location" : {
        "type" : "QUERY_PARAMETER",
        "path" : "/pets",
        "method" : "GET",
        "name" : "page"
    },
    "properties": "{\n\t\"description\" : \"Page number of results to return.\"\\n}"
}
```

If successful, the operation returns a 201 Created response containing the newly created DocumentationPart instance in the payload. For example:

```
{  
  "_links": {  
    "curies": {  
      "href": "http://docs.aws.amazon.com/apigateway/latest/developerguide/restapi-documentationpart-{rel}.html",  
      "name": "documentationpart",  
      "templated": true  
    },  
    "self": {  
      "href": "/restapis/4wk1k4onj3/documentation/parts/h9ht5w"  
    },  
    "documentationpart:delete": {  
      "href": "/restapis/4wk1k4onj3/documentation/parts/h9ht5w"  
    },  
    "documentationpart:update": {  
      "href": "/restapis/4wk1k4onj3/documentation/parts/h9ht5w"  
    }  
  },  
  "id": "h9ht5w",  
  "location": {  
    "path": "/pets",  
    "method": "GET",  
    "name": "page",  
    "statusCode": null,  
    "type": "QUERY_PARAMETER"  
  },  
  "properties": "{\n\t\"description\" : \"Page number of results to return.\n}"  
}
```

The documentation part's properties map of a QUERY_PARAMETER entity can be inherited by one of its child QUERY_PARAMETER entities. For example, if you add a treats resource after /pets/{petId}, enable the GET method on /pets/{petId}/treats, and expose the page query parameter, this child query parameter inherits the DocumentationPart's properties map from the like-named query parameter of the GET /pets method, unless you explicitly add a DocumentationPart resource to the page query parameter of the GET /pets/{petId}/treats method.

Document a PATH_PARAMETER entity

To add documentation for a path parameter, add a [DocumentationPart](#) resource for the PATH_PARAMETER entity.

```
POST /restapis/restapi_id/documentation/parts HTTP/1.1
Host: apigateway.region.amazonaws.com
Content-Type: application/json
X-Amz-Date: YYYYMMDDTtttttZ
Authorization: AWS4-HMAC-SHA256 Credential=access_key_id/YYYYMMDD/region/
apigateway/aws4_request, SignedHeaders=content-length;content-type;host;x-amz-date,
Signature=sigv4_secret

{
  "location" : {
    "type" : "PATH_PARAMETER",
    "path" : "/pets/{petId}",
    "method" : "*",
    "name" : "petId"
  },
  "properties": "{\n\t\"description\" : \"The id of the pet to retrieve.\"\n}"
}
```

If successful, the operation returns a 201 Created response containing the newly created DocumentationPart instance in the payload. For example:

```
{
  "_links": {
    "curies": {
      "href": "http://docs.aws.amazon.com/apigateway/latest/developerguide/restapi-documentationpart-{rel}.html",
      "name": "documentationpart",
      "templated": true
    },
    "self": {
      "href": "/restapis/4wk1k4onj3/documentation/parts/ckpgog"
    }
  },
  "documentationpart:delete": {
    "href": "/restapis/4wk1k4onj3/documentation/parts/ckpgog"
  },
  "documentationpart:update": {
    "href": "/restapis/4wk1k4onj3/documentation/parts/ckpgog"
  }
}
```

```
},
"id": "ckpgog",
"location": {
  "path": "/pets/{petId}",
  "method": "*",
  "name": "petId",
  "statusCode": null,
  "type": "PATH_PARAMETER"
},
"properties": "{\n  \"description\" : \"The id of the pet to retrieve\"\n}"
}
```

Document a REQUEST_BODY entity

To add documentation for a request body, add a [DocumentationPart](#) resource for the request body.

```
POST /restapis/restapi_id/documentation/parts HTTP/1.1
Host: apigateway.region.amazonaws.com
Content-Type: application/json
X-Amz-Date: YYYYMMDDTtttttZ
Authorization: AWS4-HMAC-SHA256 Credential=access_key_id/YYYYMMDD/region/
apigateway/aws4_request, SignedHeaders=content-length;content-type;host;x-amz-date,
Signature=sigv4_secret

{
  "location" : {
    "type" : "REQUEST_BODY",
    "path" : "/pets",
    "method" : "POST"
  },
  "properties": "{\n\t\"description\" : \"A Pet object to be added to PetStore.\"\n}"
}
```

If successful, the operation returns a 201 Created response containing the newly created DocumentationPart instance in the payload. For example:

```
{
  "_links": {
    "curies": {
      "href": "http://docs.aws.amazon.com/apigateway/latest/developerguide/restapi-
documentationpart-{rel}.html",
      "name": "documentationpart",
    }
}
```

```
        "templated": true
    },
    "self": {
        "href": "/restapis/4wk1k4onj3/documentation/parts/kgmfr1"
    },
    "documentationpart:delete": {
        "href": "/restapis/4wk1k4onj3/documentation/parts/kgmfr1"
    },
    "documentationpart:update": {
        "href": "/restapis/4wk1k4onj3/documentation/parts/kgmfr1"
    }
},
"id": "kgmfr1",
"location": {
    "path": "/pets",
    "method": "POST",
    "name": null,
    "statusCode": null,
    "type": "REQUEST_BODY"
},
"properties": "{\n\t\"description\" : \"A Pet object to be added to PetStore.\"\n}"}
```

Document a REQUEST_HEADER entity

To add documentation for a request header, add a [DocumentationPart](#) resource for the request header.

```
POST /restapis/restapi_id/documentation/parts HTTP/1.1
Host: apigateway.region.amazonaws.com
Content-Type: application/json
X-Amz-Date: YYYYMMDDTtttttZ
Authorization: AWS4-HMAC-SHA256 Credential=access_key_id/YYYYMMDD/region/
apigateway/aws4_request, SignedHeaders=content-length;content-type;host;x-amz-date,
Signature=sigv4_secret

{
    "location" : {
        "type" : "REQUEST_HEADER",
        "path" : "/pets",
        "method" : "GET",
        "name" : "x-my-token"
    },
}
```

```
    "properties": "{\n\t\"description\" : \"A custom token used to authorization the\nmethod invocation.\n\"}\n}
```

If successful, the operation returns a 201 Created response containing the newly created DocumentationPart instance in the payload. For example:

```
{
  "_links": {
    "curies": {
      "href": "http://docs.aws.amazon.com/apigateway/latest/developerguide/restapi-documentationpart-{rel}.html",
      "name": "documentationpart",
      "templated": true
    },
    "self": {
      "href": "/restapis/4wk1k4onj3/documentation/parts/h0m3uf"
    },
    "documentationpart:delete": {
      "href": "/restapis/4wk1k4onj3/documentation/parts/h0m3uf"
    },
    "documentationpart:update": {
      "href": "/restapis/4wk1k4onj3/documentation/parts/h0m3uf"
    }
  },
  "id": "h0m3uf",
  "location": {
    "path": "/pets",
    "method": "GET",
    "name": "x-my-token",
    "statusCode": null,
    "type": "REQUEST_HEADER"
  },
  "properties": "{\n\t\"description\" : \"A custom token used to authorization the\nmethod invocation.\n\"}\n}
```

Document a RESPONSE entity

To add documentation for a response of a status code, add a [DocumentationPart](#) resource targeted for the corresponding [MethodResponse](#) resource.

```
POST /restapis/restapi_id/documentation/parts HTTP/1.1
```

```
Host: apigateway.region.amazonaws.com
Content-Type: application/json
X-Amz-Date: YYYYMMDDTTttttZ
Authorization: AWS4-HMAC-SHA256 Credential=access_key_id/YYYYMMDD/region/
apigateway/aws4_request, SignedHeaders=content-length;content-type;host;x-amz-date,
Signature=sigv4_secret

{
  "location": {
    "path": "/",
    "method": "*",
    "name": null,
    "statusCode": "200",
    "type": "RESPONSE"
  },
  "properties": "{\n    \"description\" : \"Successful operation.\n}"
}
```

If successful, the operation returns a 201 Created response containing the newly created DocumentationPart instance in the payload. For example:

```
{
  "_links": {
    "self": {
      "href": "/restapis/4wk1k4onj3/documentation/parts/lattew"
    },
    "documentationpart:delete": {
      "href": "/restapis/4wk1k4onj3/documentation/parts/lattew"
    },
    "documentationpart:update": {
      "href": "/restapis/4wk1k4onj3/documentation/parts/lattew"
    }
  },
  "id": "lattew",
  "location": {
    "path": "/",
    "method": "*",
    "name": null,
    "statusCode": "200",
    "type": "RESPONSE"
  },
  "properties": "{\n    \"description\" : \"Successful operation.\n}"
}
```

Document a RESPONSE_HEADER entity

To add documentation for a response header, add a [DocumentationPart](#) resource for the response header.

```
POST /restapis/restapi_id/documentation/parts HTTP/1.1
Host: apigateway.region.amazonaws.com
Content-Type: application/json
X-Amz-Date: YYYYMMDDTtttttZ
Authorization: AWS4-HMAC-SHA256 Credential=access_key_id/YYYYMMDD/region/
apigateway/aws4_request, SignedHeaders=content-length;content-type;host;x-amz-date,
Signature=sigv4_secret

"location": {
  "path": "/",
  "method": "GET",
  "name": "Content-Type",
  "statusCode": "200",
  "type": "RESPONSE_HEADER"
},
"properties": "{\n  \"description\" : \"Media type of request\"\n}"
```

If successful, the operation returns a 201 Created response containing the newly created DocumentationPart instance in the payload. For example:

```
{
  "_links": {
    "curies": {
      "href": "http://docs.aws.amazon.com/apigateway/latest/developerguide/restapi-documentationpart-{rel}.html",
      "name": "documentationpart",
      "templated": true
    },
    "self": {
      "href": "/restapis/4wk1k4onj3/documentation/parts/fev7j7"
    }
  },
  "documentationpart:delete": {
    "href": "/restapis/4wk1k4onj3/documentation/parts/fev7j7"
  },
  "documentationpart:update": {
    "href": "/restapis/4wk1k4onj3/documentation/parts/fev7j7"
  }
},
```

```
"id": "fev7j7",
"location": {
    "path": "/",
    "method": "GET",
    "name": "Content-Type",
    "statusCode": "200",
    "type": "RESPONSE_HEADER"
},
"properties": "{\n    \"description\" : \"Media type of request\"\n}"
}
```

The documentation of this Content-Type response header is the default documentation for the Content-Type headers of any responses of the API.

Document an AUTHORIZER entity

To add documentation for an API authorizer, add a [DocumentationPart](#) resource targeted for the specified authorizer.

```
POST /restapis/restapi_id/documentation/parts HTTP/1.1
Host: apigateway.region.amazonaws.com
Content-Type: application/json
X-Amz-Date: YYYYMMDDTtttttZ
Authorization: AWS4-HMAC-SHA256 Credential=access_key_id/YYYYMMDD/region/
apigateway/aws4_request, SignedHeaders=content-length;content-type;host;x-amz-date,
Signature=sigv4_secret

{
    "location" : {
        "type" : "AUTHORIZER",
        "name" : "myAuthorizer"
    },
    "properties": "{\n\t\"description\" : \"Authorizes invocations of configured\nmethods.\"\\n\"}"
}
```

If successful, the operation returns a 201 Created response containing the newly created DocumentationPart instance in the payload. For example:

```
{
    "_links": {
        "curies": {
```

```
        "href": "http://docs.aws.amazon.com/apigateway/latest/developerguide/restapi-documentationpart-{rel}.html",
        "name": "documentationpart",
        "templated": true
    },
    "self": {
        "href": "/restapis/4wk1k4onj3/documentation/parts/pw3qw3"
    },
    "documentationpart:delete": {
        "href": "/restapis/4wk1k4onj3/documentation/parts/pw3qw3"
    },
    "documentationpart:update": {
        "href": "/restapis/4wk1k4onj3/documentation/parts/pw3qw3"
    }
},
"id": "pw3qw3",
"location": {
    "path": null,
    "method": null,
    "name": "myAuthorizer",
    "statusCode": null,
    "type": "AUTHORIZER"
},
"properties": "{\n\t\"description\" : \"Authorizes invocations of configured methods.\n\"\\n\""
}
```

Note

The [DocumentationPart](#) instance of an AUTHORIZER entity cannot be inherited by any of its child resources.

Document a MODEL entity

Documenting a MODEL entity involves creating and managing DocumentPart instances for the model and each of the model's properties'. For example, for the Error model that comes with every API by default has the following schema definition,

```
{
    "$schema" : "http://json-schema.org/draft-04/schema#",
    "title" : "Error Schema",
```

```
"type" : "object",
"properties" : {
    "message" : { "type" : "string" }
}
}
```

and requires two DocumentationPart instances, one for the Model and the other for its message property:

```
{
  "location": {
    "type": "MODEL",
    "name": "Error"
  },
  "properties": {
    "title": "Error Schema",
    "description": "A description of the Error model"
  }
}
```

and

```
{
  "location": {
    "type": "MODEL",
    "name": "Error.message"
  },
  "properties": {
    "description": "An error message."
  }
}
```

When the API is exported, the DocumentationPart's properties will override the values in the original schema.

To add documentation for an API model, add a [DocumentationPart](#) resource targeted for the specified model.

```
POST /restapis/restapi_id/documentation/parts HTTP/1.1
Host: apigateway.region.amazonaws.com
Content-Type: application/json
X-Amz-Date: YYYYMMDDTtttttZ
```

```
Authorization: AWS4-HMAC-SHA256 Credential=access_key_id/YYYYMMDD/region/  
apigateway/aws4_request, SignedHeaders=content-length;content-type;host;x-amz-date,  
Signature=sigv4_secret  
  
{  
    "location" : {  
        "type" : "MODEL",  
        "name" : "Pet"  
    },  
    "properties": "{\n\t\"description\" : \"Data structure of a Pet object.\n}"  
}
```

If successful, the operation returns a 201 Created response containing the newly created DocumentationPart instance in the payload. For example:

```
{  
    "_links": {  
        "curies": {  
            "href": "http://docs.aws.amazon.com/apigateway/latest/developerguide/restapi-documentationpart-{rel}.html",  
            "name": "documentationpart",  
            "templated": true  
        },  
        "self": {  
            "href": "/restapis/4wk1k4onj3/documentation/parts/lkn4uq"  
        },  
        "documentationpart:delete": {  
            "href": "/restapis/4wk1k4onj3/documentation/parts/lkn4uq"  
        },  
        "documentationpart:update": {  
            "href": "/restapis/4wk1k4onj3/documentation/parts/lkn4uq"  
        }  
    },  
    "id": "lkn4uq",  
    "location": {  
        "path": null,  
        "method": null,  
        "name": "Pet",  
        "statusCode": null,  
        "type": "MODEL"  
    },  
    "properties": "{\n\t\"description\" : \"Data structure of a Pet object.\n}"  
}
```

Repeat the same step to create a `DocumentationPart` instance for any of the model's properties.

Note

The `DocumentationPart` instance of a MODEL entity cannot be inherited by any of its child resources.

Update documentation parts

To update the documentation parts of any type of API entities, submit a PATCH request on a `DocumentationPart` instance of a specified part identifier to replace the existing properties map with a new one.

```
PATCH /restapis/4wk1k4onj3/documentation/parts/part_id HTTP/1.1
Host: apigateway.region.amazonaws.com
Content-Type: application/json
X-Amz-Date: YYYYMMDDTtttttZ
Authorization: AWS4-HMAC-SHA256 Credential=access_key_id/YYYYMMDD/region/
apigateway/aws4_request, SignedHeaders=content-length;content-type;host;x-amz-date,
Signature=sigv4_secret

{
  "patchOperations" : [ {
    "op" : "replace",
    "path" : "RESOURCE_PATH",
    "value" : "NEW_properties_VALUE_AS_JSON_STRING"
  } ]
}
```

The successful response returns a 200 OK status code with the payload containing the updated `DocumentationPart` instance in the payload.

You can update multiple documentation parts in a single PATCH request.

List documentation parts

To list the documentation parts of any type of API entities, submit a GET request on a `DocumentationParts` collection.

```
GET /restapis/restapi_id/documentation/parts HTTP/1.1
Host: apigateway.region.amazonaws.com
```

```
Content-Type: application/json
X-Amz-Date: YYYYMMDDTtttttZ
Authorization: AWS4-HMAC-SHA256 Credential=access_key_id/YYYYMMDD/region/
apigateway/aws4_request, SignedHeaders=content-length;content-type;host;x-amz-date,
Signature=sigv4_secret
```

The successful response returns a 200 OK status code with the payload containing the available DocumentationPart instances in the payload.

Publish API documentation using the API Gateway REST API

To publish the documentation for an API, create, update, or get a documentation snapshot, and then associate the documentation snapshot with an API stage. When creating a documentation snapshot, you can also associate it with an API stage at the same time.

Topics

- [Create a documentation snapshot and associate it with an API stage](#)
- [Create a documentation snapshot](#)
- [Update a documentation snapshot](#)
- [Get a documentation snapshot](#)
- [Associate a documentation snapshot with an API stage](#)
- [Download a documentation snapshot associated with a stage](#)

Create a documentation snapshot and associate it with an API stage

To create a snapshot of an API's documentation parts and associate it with an API stage at the same time, submit the following POST request:

```
POST /restapis/restapi_id/documentation/versions HTTP/1.1
Host: apigateway.region.amazonaws.com
Content-Type: application/json
X-Amz-Date: YYYYMMDDTtttttZ
Authorization: AWS4-HMAC-SHA256 Credential=access_key_id/YYYYMMDD/region/
apigateway/aws4_request, SignedHeaders=content-length;content-type;host;x-amz-date,
Signature=sigv4_secret

{
    "documentationVersion" : "1.0.0",
    "stageName": "prod",
```

```
        "description" : "My API Documentation v1.0.0"  
    }
```

If successful, the operation returns a 200 OK response, containing the newly created DocumentationVersion instance as the payload.

Alternatively, you can create a documentation snapshot without associating it with an API stage first and then call [restapi:update](#) to associate the snapshot with a specified API stage. You can also update or query an existing documentation snapshot and then update its stage association. We show the steps in the next four sections.

Create a documentation snapshot

To create a snapshot of an API's documentation parts, create a new [DocumentationVersion](#) resource and add it to the [DocumentationVersions](#) collection of the API:

```
POST /restapis/restapi_id/documentation/versions HTTP/1.1  
Host: apigateway.region.amazonaws.com  
Content-Type: application/json  
X-Amz-Date: YYYYMMDDTtttttZ  
Authorization: AWS4-HMAC-SHA256 Credential=access_key_id/YYYYMMDD/region/  
apigateway/aws4_request, SignedHeaders=content-length;content-type;host;x-amz-date,  
Signature=sigv4_secret  
  
{  
    "documentationVersion" : "1.0.0",  
    "description" : "My API Documentation v1.0.0"  
}
```

If successful, the operation returns a 200 OK response, containing the newly created DocumentationVersion instance as the payload.

Update a documentation snapshot

You can only update a documentation snapshot by modifying the description property of the corresponding [DocumentationVersion](#) resource. The following example shows how to update the description of the documentation snapshot as identified by its version identifier, *version*, e.g., 1.0.0.

```
PATCH /restapis/restapi_id/documentation/versions/version HTTP/1.1  
Host: apigateway.region.amazonaws.com  
Content-Type: application/json
```

```
X-Amz-Date: YYYYMMDDTtttttZ
Authorization: AWS4-HMAC-SHA256 Credential=access_key_id/YYYYMMDD/region/
apigateway/aws4_request, SignedHeaders=content-length;content-type;host;x-amz-date,
Signature=sigv4_secret

{
    "patchOperations": [
        {
            "op": "replace",
            "path": "/description",
            "value": "My API for testing purposes."
        }
    ]
}
```

If successful, the operation returns a `200 OK` response, containing the updated `DocumentationVersion` instance as the payload.

Get a documentation snapshot

To get a documentation snapshot, submit a GET request against the specified [DocumentationVersion](#) resource. The following example shows how to get a documentation snapshot of a given version identifier, 1.0.0.

```
GET /restapis/<restapi_id>/documentation/versions/1.0.0 HTTP/1.1
Host: apigateway.region.amazonaws.com
Content-Type: application/json
X-Amz-Date: YYYYMMDDTtttttZ
Authorization: AWS4-HMAC-SHA256 Credential=access_key_id/YYYYMMDD/region/
apigateway/aws4_request, SignedHeaders=content-length;content-type;host;x-amz-date,
Signature=sigv4_secret
```

Associate a documentation snapshot with an API stage

To publish the API documentation, associate a documentation snapshot with an API stage. You must have already created an API stage before associating the documentation version with the stage.

To associate a documentation snapshot with an API stage using the [API Gateway REST API](#), call the [stage:update](#) operation to set the desired documentation version on the `stage.documentationVersion` property:

```
PATCH /restapis/RESTAPI_ID/stages/STAGE_NAME
Host: apigateway.region.amazonaws.com
```

```
Content-Type: application/json
X-Amz-Date: YYYYMMDDTtttttZ
Authorization: AWS4-HMAC-SHA256 Credential=access_key_id/YYYYMMDD/region/
apigateway/aws4_request, SignedHeaders=content-length;content-type;host;x-amz-date,
Signature=sigv4_secret

{
  "patchOperations": [{"op": "replace",
    "path": "/documentationVersion",
    "value": "VERSION_IDENTIFIER"}
]
}
```

Download a documentation snapshot associated with a stage

After a version of the documentation parts is associated with a stage, you can export the documentation parts together with the API entity definitions, to an external file, using the API Gateway console, the API Gateway REST API, one of its SDKs, or the AWS CLI for API Gateway. The process is the same as for exporting the API. The exported file format can be JSON or YAML.

Using the API Gateway REST API, you can also explicitly set the `extension=documentation,integrations,authorizers` query parameter to include the API documentation parts, API integrations and authorizers in an API export. By default, documentation parts are included, but integrations and authorizers are excluded, when you export an API. The default output from an API export is suited for distribution of the documentation.

To export the API documentation in an external JSON OpenAPI file using the API Gateway REST API, submit the following GET request:

```
GET /restapis/restapi_id/stages/stage_name/exports/swagger?extensions=documentation
HTTP/1.1
Accept: application/json
Host: apigateway.region.amazonaws.com
Content-Type: application/json
X-Amz-Date: YYYYMMDDTtttttZ
Authorization: AWS4-HMAC-SHA256 Credential=access_key_id/YYYYMMDD/region/
apigateway/aws4_request, SignedHeaders=content-length;content-type;host;x-amz-date,
Signature=sigv4_secret
```

Here, the `x-amazon-apigateway-documentation` object contains the documentation parts and the API entity definitions contains the documentation properties

supported by OpenAPI. The output does not include details of integration or Lambda authorizers (formerly known as custom authorizers). To include both details, set `extensions=integrations,authorizers,documentation`. To include details of integrations but not of authorizers, set `extensions=integrations,documentation`.

You must set the `Accept:application/json` header in the request to output the result in a JSON file. To produce the YAML output, change the request header to `Accept:application/yaml`.

As an example, we will look at an API that exposes a simple GET method on the root resource (`/`). This API has four API entities defined in an OpenAPI definition file, one for each of the API, MODEL, METHOD, and RESPONSE types. A documentation part has been added to each of the API, METHOD, and RESPONSE entities. Calling the preceding documentation-exporting command, we get the following output, with the documentation parts listed within the `x-amazon-apigateway-documentation` object as an extension to a standard OpenAPI file.

OpenAPI 3.0

```
{  
  "openapi": "3.0.0",  
  "info": {  
    "description": "API info description",  
    "version": "2016-11-22T22:39:14Z",  
    "title": "doc",  
    "x-bar": "API info x-bar"  
  },  
  "paths": {  
    "/": {  
      "get": {  
        "description": "Method description.",  
        "responses": {  
          "200": {  
            "description": "200 response",  
            "content": {  
              "application/json": {  
                "schema": {  
                  "$ref": "#/components/schemas/Empty"  
                }  
              }  
            }  
          }  
        }  
      }  
    },  
  },  
}
```

```
        "x-example": "x- Method example"
    },
    "x-bar": "resource x-bar"
}
},
"x-amazon-apigateway-documentation": {
    "version": "1.0.0",
    "createdDate": "2016-11-22T22:41:40Z",
    "documentationParts": [
        {
            "location": {
                "type": "API"
            },
            "properties": {
                "description": "API description",
                "foo": "API foo",
                "x-bar": "API x-bar",
                "info": {
                    "description": "API info description",
                    "version": "API info version",
                    "foo": "API info foo",
                    "x-bar": "API info x-bar"
                }
            }
        },
        {
            "location": {
                "type": "METHOD",
                "method": "GET"
            },
            "properties": {
                "description": "Method description.",
                "x-example": "x- Method example",
                "foo": "Method foo",
                "info": {
                    "version": "method info version",
                    "description": "method info description",
                    "foo": "method info foo"
                }
            }
        }
    ],
    {
        "location": {
            "type": "RESOURCE"
        }
    }
}
```

```
        },
        "properties": {
            "description": "resource description",
            "foo": "resource foo",
            "x-bar": "resource x-bar",
            "info": {
                "description": "resource info description",
                "version": "resource info version",
                "foo": "resource info foo",
                "x-bar": "resource info x-bar"
            }
        }
    }
],
"x-bar": "API x-bar",
"servers": [
{
    "url": "https://rznaap68yi.execute-api.ap-southeast-1.amazonaws.com/
{basePath}",
    "variables": {
        "basePath": {
            "default": "/test"
        }
    }
},
],
"components": {
    "schemas": {
        "Empty": {
            "type": "object",
            "title": "Empty Schema"
        }
    }
}
}
```

OpenAPI 2.0

```
{
  "swagger" : "2.0",
  "info" : {
    "description" : "API info description",
```

```
"version" : "2016-11-22T22:39:14Z",
"title" : "doc",
"x-bar" : "API info x-bar"
},
"host" : "rznaap68yi.execute-api.ap-southeast-1.amazonaws.com",
"basePath" : "/test",
"schemes" : [ "https" ],
"paths" : {
"/" : {
"get" : {
"description" : "Method description.",
"produces" : [ "application/json" ],
"responses" : {
"200" : {
"description" : "200 response",
"schema" : {
"$ref" : "#/definitions/Empty"
}
},
"x-example" : "x- Method example"
},
"x-bar" : "resource x-bar"
}
},
"definitions" : {
"Empty" : {
"type" : "object",
"title" : "Empty Schema"
}
},
"x-amazon-apigateway-documentation" : {
"version" : "1.0.0",
"createdDate" : "2016-11-22T22:41:40Z",
"documentationParts" : [ {
"location" : {
"type" : "API"
},
"properties" : {
"description" : "API description",
"foo" : "API foo",
"x-bar" : "API x-bar",
"info" : {
"description" : "API info description",

```

```
        "version" : "API info version",
        "foo" : "API info foo",
        "x-bar" : "API info x-bar"
    }
}
],
{
    "location" : {
        "type" : "METHOD",
        "method" : "GET"
    },
    "properties" : {
        "description" : "Method description.",
        "x-example" : "x- Method example",
        "foo" : "Method foo",
        "info" : {
            "version" : "method info version",
            "description" : "method info description",
            "foo" : "method info foo"
        }
    }
},
{
    "location" : {
        "type" : "RESOURCE"
    },
    "properties" : {
        "description" : "resource description",
        "foo" : "resource foo",
        "x-bar" : "resource x-bar",
        "info" : {
            "description" : "resource info description",
            "version" : "resource info version",
            "foo" : "resource info foo",
            "x-bar" : "resource info x-bar"
        }
    }
}
],
{
    "x-bar" : "API x-bar"
}
```

For an OpenAPI-compliant attribute defined in the properties map of a documentation part, API Gateway inserts the attribute into the associated API entity definition. An attribute of

x-*something* is a standard OpenAPI extension. This extension gets propagated into the API entity definition. For example, see the x-example attribute for the GET method. An attribute like foo is not part of the OpenAPI specification and is not injected into its associated API entity definitions.

If a documentation-rendering tool (e.g., [OpenAPI UI](#)) parses the API entity definitions to extract documentation attributes, any non OpenAPI-compliant properties attributes of a DocumentationPart' instance are not available for the tool. However, if a documentation-rendering tool parses the x-amazon-apigateway-documentation object to get content, or if the tool calls [restapi:documentation-parts](#) and [documentationpart:by-id](#) to retrieve documentation parts from API Gateway, all the documentation attributes are available for the tool to display.

To export the documentation with API entity definitions containing integration details to a JSON OpenAPI file, submit the following GET request:

```
GET /restapis/restapi_id/stages/stage_name/exports/swagger?  
extensions=integrations,documentation HTTP/1.1  
Accept: application/json  
Host: apigateway.region.amazonaws.com  
Content-Type: application/json  
X-Amz-Date: YYYYMMDDTTttttZ  
Authorization: AWS4-HMAC-SHA256 Credential=access_key_id/YYYYMMDD/region/  
apigateway/aws4_request, SignedHeaders=content-length;content-type;host;x-amz-date,  
Signature=sigv4_secret
```

To export the documentation with API entity definitions containing details of integrations and authorizers to a YAML OpenAPI file, submit the following GET request:

```
GET /restapis/restapi_id/stages/stage_name/exports/swagger?  
extensions=integrations,authorizers,documentation HTTP/1.1  
Accept: application/yaml  
Host: apigateway.region.amazonaws.com  
Content-Type: application/json  
X-Amz-Date: YYYYMMDDTTttttZ  
Authorization: AWS4-HMAC-SHA256 Credential=access_key_id/YYYYMMDD/region/  
apigateway/aws4_request, SignedHeaders=content-length;content-type;host;x-amz-date,  
Signature=sigv4_secret
```

To use the API Gateway console to export and download the published documentation of an API, follow the instructions in [Export REST API using the API Gateway console](#).

Import API documentation

As with importing API entity definitions, you can import documentation parts from an external OpenAPI file into an API in API Gateway. You specify the to-be-imported documentation parts within the [x-amazon-apigateway-documentation object](#) extension in a valid OpenAPI definition file. Importing documentation does not alter the existing API entity definitions.

You have an option to merge the newly specified documentation parts into existing documentation parts in API Gateway or to overwrite the existing documentation parts. In the MERGE mode, a new documentation part defined in the OpenAPI file is added to the DocumentationParts collection of the API. If an imported DocumentationPart already exists, an imported attribute replaces the existing one if the two are different. Other existing documentation attributes remain unaffected. In the OVERWRITE mode, the entire DocumentationParts collection is replaced according to the imported OpenAPI definition file.

Importing documentation parts using the API Gateway REST API

To import API documentation using the API Gateway REST API, call the [documentationpart:import](#) operation. The following example shows how to overwrite existing documentation parts of an API with a single GET / method, returning a 200 OK response when successful.

OpenAPI 3.0

```
PUT /restapis/<restapi_id>/documentation/parts&mode=overwrite&failonwarnings=true
Host: apigateway.<region>.amazonaws.com
Content-Type: application/json
X-Amz-Date: <YYYYMMDDTtttttz>
Authorization: AWS4-HMAC-SHA256 Credential=<access_key_id>/<YYYYMMDD/><region>/apigateway/aws4_request, SignedHeaders=content-length;content-type;host;x-amz-date, Signature=<sigv4_secret>

{
    "openapi": "3.0.0",
    "info": {
        "description": "description",
        "version": "1",
        "title": "doc"
    },
    "paths": {
        "/": {
            "get": {
                "description": "Method description."
            }
        }
    }
}
```

```
"responses": {
    "200": {
        "description": "200 response",
        "content": {
            "application/json": {
                "schema": {
                    "$ref": "#/components/schemas/Empty"
                }
            }
        }
    }
},
"x-amazon-apigateway-documentation": {
    "version": "1.0.3",
    "documentationParts": [
        {
            "location": {
                "type": "API"
            },
            "properties": {
                "description": "API description",
                "info": {
                    "description": "API info description 4",
                    "version": "API info version 3"
                }
            }
        },
        {
            "location": {
                "type": "METHOD",
                "method": "GET"
            },
            "properties": {
                "description": "Method description."
            }
        },
        {
            "location": {
                "type": "MODEL",
                "name": "Empty"
            },
            "properties": {
                "description": "Empty model description"
            }
        }
    ]
}
```

```
        "properties": {
            "title": "Empty Schema"
        }
    },
{
    "location": {
        "type": "RESPONSE",
        "method": "GET",
        "statusCode": "200"
    },
    "properties": {
        "description": "200 response"
    }
}
]
},
"servers": [
{
    "url": "/"
},
],
"components": {
    "schemas": {
        "Empty": {
            "type": "object",
            "title": "Empty Schema"
        }
    }
}
}
```

OpenAPI 2.0

```
PUT /restapis/<restapi_id>/documentation/parts&mode=overwrite&failonwarnings=true
Host: apigateway.region.amazonaws.com
Content-Type: application/json
X-Amz-Date: YYYYMMDDTtttttz
Authorization: AWS4-HMAC-SHA256 Credential=<access_key_id>/YYYYMMDD/<region>/apigateway/aws4_request, SignedHeaders=content-length;content-type;host;x-amz-date, Signature=<sigv4_secret>

{
    "swagger": "2.0",
```

```
"info": {
    "description": "description",
    "version": "1",
    "title": "doc"
},
"host": "",
"basePath": "/",
"schemes": [
    "https"
],
"paths": {
    "/": {
        "get": {
            "description": "Method description.",
            "produces": [
                "application/json"
            ],
            "responses": {
                "200": {
                    "description": "200 response",
                    "schema": {
                        "$ref": "#/definitions/Empty"
                    }
                }
            }
        }
    }
},
"definitions": {
    "Empty": {
        "type": "object",
        "title": "Empty Schema"
    }
},
"x-amazon-apigateway-documentation": {
    "version": "1.0.3",
    "documentationParts": [
        {
            "location": {
                "type": "API"
            },
            "properties": {
                "description": "API description",
                "info": {

```

```
        "description": "API info description 4",
        "version": "API info version 3"
    },
},
{
    "location": {
        "type": "METHOD",
        "method": "GET"
    },
    "properties": {
        "description": "Method description."
    }
},
{
    "location": {
        "type": "MODEL",
        "name": "Empty"
    },
    "properties": {
        "title": "Empty Schema"
    }
},
{
    "location": {
        "type": "RESPONSE",
        "method": "GET",
        "statusCode": "200"
    },
    "properties": {
        "description": "200 response"
    }
}
]
```

When successful, this request returns a 200 OK response containing the imported DocumentationPartId in the payload.

```
{
  "ids": [
```

```
"kg3mth",
"796rtf",
"zhek4p",
"5ukm9s"
]
}
```

In addition, you can also call [restapi:import](#) or [restapi:put](#), supplying the documentation parts in the `x-amazon-apigateway-documentation` object as part of the input OpenAPI file of the API definition. To exclude the documentation parts from the API import, set `ignore=documentation` in the request query parameters.

Importing documentation parts using the API Gateway console

The following instructions describe how to import documentation parts.

To use the console to import documentation parts of an API from an external file

1. In the main navigation pane, choose **Documentation**.
2. Choose **Import**.
3. If you have existing documentation, select to either **Overwrite** or **Merge** your new documentation.
4. Choose **Choose file** to load a file from a drive, or enter file contents into the file view. For an example, see the payload of the example request in [Importing documentation parts using the API Gateway REST API](#).
5. Choose how to handle warnings on import. Select either **Fail on warnings** or **Ignore warnings**. For more information, see [the section called “Errors and warnings from importing your API into API Gateway”](#).
6. Choose **Import**.

Control access to API documentation in API Gateway

If you have a dedicated documentation team to write and edit your API documentation, you can configure separate access permissions for your developers (for API development) and for your writers or editors (for content development). This is especially appropriate when a third-party vendor is involved in creating the documentation for you.

To grant your documentation team the access to create, update, and publish your API documentation, you can assign the documentation team an IAM role with the following IAM policy, where *account_id* is the AWS account ID of your documentation team.

JSON

```
{  
    "Version": "2012-10-17",  
    "Statement": [  
  
        {  
            "Sid": "StmtDocPartsAddEditViewDelete",  
            "Effect": "Allow",  
            "Action": [  
                "apigateway:GET",  
                "apigateway:PUT",  
                "apigateway:POST",  
                "apigateway:PATCH",  
                "apigateway:DELETE"  
            ],  
            "Resource": [  
                "arn:aws:apigateway:us-east-1:111111111111:restapis/*/*documentation/*"  
            ]  
        }  
    ]  
}
```

For information on setting permissions to access API Gateway resources, see [the section called “How Amazon API Gateway works with IAM”](#).

Generate SDKs for REST APIs in API Gateway

To call your REST API in a platform- or language-specific way, you must generate the platform- or language-specific SDK of the API. You generate your SDK after you create, test, and deploy your API to a stage. Currently, API Gateway supports generating an SDK for an API in Java, JavaScript, Java for Android, Objective-C or Swift for iOS, and Ruby.

This section explains how to generate an SDK of an API Gateway API. It also demonstrates how to use the generated SDK in a Java app, a Java for Android app, Objective-C and Swift for iOS apps, and a JavaScript app.

To facilitate the discussion, we use this API Gateway [API](#), which exposes this [Simple Calculator Lambda function](#).

Before proceeding, create or import the API and deploy it at least once in API Gateway. For instructions, see [Deploy REST APIs in API Gateway](#).

Topics

- [Simple calculator Lambda function](#)
- [Simple calculator API in API Gateway](#)
- [Simple calculator API OpenAPI definition](#)
- [Generate the Java SDK of an API in API Gateway](#)
- [Generate the Android SDK of an API in API Gateway](#)
- [Generate the iOS SDK of an API in API Gateway](#)
- [Generate the JavaScript SDK of a REST API in API Gateway](#)
- [Generate the Ruby SDK of an API in API Gateway](#)
- [Generate SDKs for an API using AWS CLI commands in API Gateway](#)

Simple calculator Lambda function

As an illustration, we will use a Node.js Lambda function that performs the binary operations of addition, subtraction, multiplication and division.

Topics

- [Simple calculator Lambda function input format](#)
- [Simple calculator Lambda function output format](#)
- [Simple calculator Lambda function implementation](#)

Simple calculator Lambda function input format

This function takes an input of the following format:

```
{ "a": "Number", "b": "Number", "op": "string"}
```

where op can be any of (+, -, *, /, add, sub, mul, div).

Simple calculator Lambda function output format

When an operation succeeds, it returns the result of the following format:

```
{ "a": "Number", "b": "Number", "op": "string", "c": "Number"}
```

where c holds the result of the calculation.

Simple calculator Lambda function implementation

The implementation of the Lambda function is as follows:

```
export const handler = async function (event, context) {
    console.log("Received event:", JSON.stringify(event));

    if (
        event.a === undefined ||
        event.b === undefined ||
        event.op === undefined
    ) {
        return "400 Invalid Input";
    }

    const res = {};
    res.a = Number(event.a);
    res.b = Number(event.b);
    res.op = event.op;
    if (isNaN(event.a) || isNaN(event.b)) {
        return "400 Invalid Operand";
    }
    switch (event.op) {
        case "+":
        case "add":
            res.c = res.a + res.b;
            break;
        case "-":
        case "sub":
            res.c = res.a - res.b;
            break;
        case "*":
        case "mul":
            res.c = res.a * res.b;
            break;
    }
}
```


```
case "/":
case "div":
    if (res.b == 0) {
        return "400 Divide by Zero";
    } else {
        res.c = res.a / res.b;
    }
    break;
default:
    return "400 Invalid Operator";
}

return res;
};
```

Simple calculator API in API Gateway

Our simple calculator API exposes three methods (GET, POST, GET) to invoke the [the section called "Simple calculator Lambda function"](#). A graphical representation of this API is shown as follows:

Resources



These three methods show different ways to supply the input for the backend Lambda function to perform the same operation:

- The GET `/?a=...&b=...&op=...` method uses the query parameters to specify the input.
- The POST `/` method uses a JSON payload of `{"a": "Number", "b": "Number", "op": "string"}` to specify the input.
- The GET `/{a}/{b}/{op}` method uses the path parameters to specify the input.

If not defined, API Gateway generates the corresponding SDK method name by combining the HTTP method and path parts. The root path part `(/)` is referred to as `Api Root`. For example, the default Java SDK method name for the API method of `GET /?a=...&b=...&op=...` is `getABOp`, the default SDK method name for `POST /` is `postApiRoot`, and the default SDK method name for `GET /{a}/{b}/{op}` is `getABOp`. Individual SDKs may customize the convention. Consult the documentation in the generated SDK source for SDK specific method names.

You can, and should, override the default SDK method names by specifying the [operationName](#) property on each API method. You can do so when [creating the API method](#) or [updating the API method](#) using the API Gateway REST API. In the API Swagger definition, you can set the `operationId` to achieve the same result.

Before showing how to call these methods using an SDK generated by API Gateway for this API, let's recall briefly how to set them up. For detailed instructions, see [Develop REST APIs in API Gateway](#). If you're new to API Gateway, see [Choose an AWS Lambda integration tutorial](#) first.

Create models for input and output

To specify strongly typed input in the SDK, we create an Input model for the API. To describe the response body data type, we create an Output model and a Result model.

To create models for the input, output, and result

1. In the main navigation pane, choose **Models**.
2. Choose **Create model**.
3. For **Name**, enter **input**.
4. For **Content type**, enter **application/json**.

If no matching content type is found, request validation is not performed. To use the same model regardless of the content type, enter **\$default**.

5. For **Model schema**, enter the following model:

```
{  
  "$schema" : "$schema": "http://json-schema.org/draft-04/schema#",  
  "type": "object",  
  "properties": {  
    "a": {"type": "number"},  
    "b": {"type": "number"},  
    "op": {"type": "string"}  
  },  
  "title": "Input"  
}
```

6. Choose **Create model**.

7. Repeat the following steps to create an Output model and a Result model.

For the Output model, enter the following for the **Model schema**:

```
{  
  "$schema": "http://json-schema.org/draft-04/schema#",  
  "type": "object",  
  "properties": {  
    "c": {"type": "number"}  
  },  
  "title": "Output"  
}
```

For the Result model, enter the following for the **Model schema**. Replace the API ID abc123 with your API ID.

```
{  
  "$schema": "http://json-schema.org/draft-04/schema#",  
  "type": "object",  
  "properties": {  
    "input": {  
      "$ref": "https://apigateway.amazonaws.com/restapis/abc123/models/Input"  
    },  
    "output": {  
      "$ref": "https://apigateway.amazonaws.com/restapis/abc123/models/Output"  
    }  
  },  
  "title": "Result"
```

{}

Set up GET / method query parameters

For the GET `/?a=..&b=..&op=..` method, the query parameters are declared in **Method Request**:

To set up GET / URL query string parameters

1. In the **Method request** section for the GET method on the root (/) resource, choose **Edit**.
2. Choose **URL query string parameters** and do the following:
 - a. Choose **Add query string**.
 - b. For **Name**, enter **a**.
 - c. Keep **Required** and **Caching** turned off.
 - d. Keep **Caching** turned off.

Repeat the same steps and create a query string named **b** and a query string named **op**.

3. Choose **Save**.

Set up data model for the payload as input to the backend

For the POST / method, we create the Input model and add it to the method request to define the shape of input data.

To set up the data model for the payload as input to the backend

1. In the **Method request** section, for the POST method on the root (/) resource choose **Edit**.
2. Choose **Request body**.
3. Choose **Add model**.
4. For **Content type**, enter **application/json**.
5. For **Model**, select **Input**.
6. Choose **Save**.

With this model, your API customers can call the SDK to specify the input by instantiating an Input object. Without this model, your customers would be required to create dictionary object to represent the JSON input to the Lambda function.

Set up data model for the result output from the backend

For all three methods, we create the Result model and add it to the method's Method Response to define the shape of output returned by the Lambda function.

To set up the data model for the result output from the backend

1. Select the **/{{a}}/{{b}}/{{op}}** resource, and then choose the **GET** method.
2. On the **Method response** tab, under **Response 200**, choose **Edit**.
3. Under **Response body**, choose **Add model**.
4. For **Content type**, enter **application/json**.
5. For **Model**, select **Result**.
6. Choose **Save**.

With this model, your API customers can parse a successful output by reading properties of a Result object. Without this model, customers would be required to create dictionary object to represent the JSON output.

Simple calculator API OpenAPI definition

The following is the OpenAPI definition of the simple calculator API. You can import it into your account. However, you need to reset the resource-based permissions on the [Lambda function](#) after the import. To do so, re-select the Lambda function that you created in your account from the **Integration Request** in the API Gateway console. This will cause the API Gateway console to reset the required permissions. Alternatively, you can use AWS Command Line Interface for Lambda command of [add-permission](#).

OpenAPI 2.0

```
{  
  "swagger": "2.0",  
  "info": {  
    "version": "2016-09-29T20:27:30Z",  
    "title": "SimpleCalc"  
  },
```

```
"host": "t6dve4zn25.execute-api.us-west-2.amazonaws.com",
"basePath": "/demo",
"schemes": [
  "https"
],
"paths": {
  "/": {
    "get": {
      "consumes": [
        "application/json"
      ],
      "produces": [
        "application/json"
      ],
      "parameters": [
        {
          "name": "op",
          "in": "query",
          "required": false,
          "type": "string"
        },
        {
          "name": "a",
          "in": "query",
          "required": false,
          "type": "string"
        },
        {
          "name": "b",
          "in": "query",
          "required": false,
          "type": "string"
        }
      ],
      "responses": {
        "200": {
          "description": "200 response",
          "schema": {
            "$ref": "#/definitions/Result"
          }
        }
      },
      "x-amazon-apigateway-integration": {
        "requestTemplates": {
```

```
        "application/json": "#set($inputRoot = $input.path('$'))\n\n\"a\" : $input.params('a'),\n  \"b\" : $input.params('b'),\n  \"op\" :\n    \"$input.params('op')\"\n}\n\n  \"uri\": \"arn:aws:apigateway:us-west-2:lambda:path/2015-03-31/functions/\narn:aws:lambda:us-west-2:123456789012:function:Calc/invocations\",\n  \"passthroughBehavior\": \"when_no_templates\", \n  \"httpMethod\": \"POST\", \n  \"responses\": {\n    \"default\": {\n      \"statusCode\": \"200\", \n      \"responseTemplates\": {\n        \"application/json\": "#set($inputRoot = $input.path('$'))\n\n\"input\" : {\n    \"a\" : $inputRoot.a,\n    \"b\" : $inputRoot.b,\n    \"op\" :\n      \"$inputRoot.op\"\n  },\n  \"output\" : {\n    \"c\" : $inputRoot.c\n  }\n}\n      }\n    }, \n    \"type\": \"aws\"\n  }, \n}, \n  \"post\": {\n    \"consumes\": [\n      \"application/json\"\n    ], \n    \"produces\": [\n      \"application/json\"\n    ], \n    \"parameters\": [\n      {\n        \"in\": \"body\", \n        \"name\": \"Input\", \n        \"required\": true, \n        \"schema\": {\n          \"$ref\": \"#/definitions/Input\"\n        }\n      }\n    ], \n    \"responses\": {\n      \"200\": {\n        \"description\": \"200 response\", \n        \"schema\": {\n          \"$ref\": \"#/definitions/Result\"\n        }\n      }\n    }\n  }\n}
```

```
        }
    },
    "x-amazon-apigateway-integration": {
        "uri": "arn:aws:apigateway:us-west-2:lambda:path/2015-03-31/functions/arn:aws:lambda:us-west-2:123456789012:function:Calc/invocations",
        "passthroughBehavior": "when_no_match",
        "httpMethod": "POST",
        "responses": {
            "default": {
                "statusCode": "200",
                "responseTemplates": {
                    "application/json": "#set($inputRoot = $input.path('$'))\n\n$input\" : {\n    \"a\" : $inputRoot.a,\n    \"b\" : $inputRoot.b,\n    \"op\" : \"$inputRoot.op\"\n},\n    \"output\" : {\n        \"c\" : $inputRoot.c\n    }\n}"
                }
            },
            "type": "aws"
        }
    },
    "/{a)": {
        "x-amazon-apigateway-any-method": {
            "consumes": [
                "application/json"
            ],
            "produces": [
                "application/json"
            ],
            "parameters": [
                {
                    "name": "a",
                    "in": "path",
                    "required": true,
                    "type": "string"
                }
            ],
            "responses": {
                "404": {
                    "description": "404 response"
                }
            },
            "x-amazon-apigateway-integration": {
                "requestTemplates": {
```

```
        "application/json": "{\"statusCode\": 200}"
    },
    "passthroughBehavior": "when_no_match",
    "responses": {
        "default": {
            "statusCode": "404",
            "responseTemplates": {
                "application/json": "{ \"Message\" : \"Can't $context.httpMethod\n$context.resourcePath\" }"
            }
        }
    },
    "type": "mock"
}
},
"/{a}/{b)": {
    "x-amazon-apigateway-any-method": {
        "consumes": [
            "application/json"
        ],
        "produces": [
            "application/json"
        ],
        "parameters": [
            {
                "name": "a",
                "in": "path",
                "required": true,
                "type": "string"
            },
            {
                "name": "b",
                "in": "path",
                "required": true,
                "type": "string"
            }
        ],
        "responses": {
            "404": {
                "description": "404 response"
            }
        },
        "x-amazon-apigateway-integration": {
```

```
"requestTemplates": {
    "application/json": "{\"statusCode\": 200}"
},
"passthroughBehavior": "when_no_match",
"responses": {
    "default": {
        "statusCode": "404",
        "responseTemplates": {
            "application/json": "{ \"Message\" : \"Can't $context.httpMethod\n$context.resourcePath\" }"
        }
    }
},
"type": "mock"
}
},
"/{a}/{b}/{op)": {
    "get": {
        "consumes": [
            "application/json"
        ],
        "produces": [
            "application/json"
        ],
        "parameters": [
            {
                "name": "a",
                "in": "path",
                "required": true,
                "type": "string"
            },
            {
                "name": "b",
                "in": "path",
                "required": true,
                "type": "string"
            },
            {
                "name": "op",
                "in": "path",
                "required": true,
                "type": "string"
            }
        ]
    }
}
```

```
        ],
        "responses": {
            "200": {
                "description": "200 response",
                "schema": {
                    "$ref": "#/definitions/Result"
                }
            }
        },
        "x-amazon-apigateway-integration": {
            "requestTemplates": {
                "application/json": "#set($inputRoot = $input.path('$'))\n{\n\"a\" : $input.params('a'),\n\"b\" : $input.params('b'),\n\"op\" :\n\"$input.params('op')\"\n}"
            },
            "uri": "arn:aws:apigateway:us-west-2:lambda:path/2015-03-31/functions/arn:aws:lambda:us-west-2:123456789012:function:Calc/invocations",
            "passthroughBehavior": "when_no_templates",
            "httpMethod": "POST",
            "responses": {
                "default": {
                    "statusCode": "200",
                    "responseTemplates": {
                        "application/json": "#set($inputRoot = $input.path('$'))\n{\n\"input\" : {\n\"a\" : $inputRoot.a,\n\"b\" : $inputRoot.b,\n\"op\" :\n\"$inputRoot.op\"\n},\n\"output\" : {\n\"c\" : $inputRoot.c\n}\n}"
                    }
                }
            },
            "type": "aws"
        }
    }
},
"definitions": {
    "Input": {
        "type": "object",
        "properties": {
            "a": {
                "type": "number"
            },
            "b": {
                "type": "number"
            }
        }
    }
}
```

```
        "op": {
            "type": "string"
        },
        "title": "Input"
    },
    "Output": {
        "type": "object",
        "properties": {
            "c": {
                "type": "number"
            }
        },
        "title": "Output"
    },
    "Result": {
        "type": "object",
        "properties": {
            "input": {
                "$ref": "#/definitions/Input"
            },
            "output": {
                "$ref": "#/definitions/Output"
            }
        },
        "title": "Result"
    }
}
}
```

OpenAPI 3.0

```
{
  "openapi" : "3.0.1",
  "info" : {
    "title" : "SimpleCalc",
    "version" : "2016-09-29T20:27:30Z"
  },
  "servers" : [ {
    "url" : "https://t6dve4zn25.execute-api.us-west-2.amazonaws.com/{basePath}",
    "variables" : {
      "basePath" : {
        "default" : "demo"
      }
    }
  }
]
```

```
        }
    },
},
"paths" : {
    "/{a}/{b}" : {
        "x-amazon-apigateway-any-method" : {
            "parameters" : [ {
                "name" : "a",
                "in" : "path",
                "required" : true,
                "schema" : {
                    "type" : "string"
                }
            }, {
                "name" : "b",
                "in" : "path",
                "required" : true,
                "schema" : {
                    "type" : "string"
                }
            } ],
            "responses" : {
                "404" : {
                    "description" : "404 response",
                    "content" : { }
                }
            },
            "x-amazon-apigateway-integration" : {
                "type" : "mock",
                "responses" : {
                    "default" : {
                        "statusCode" : "404",
                        "responseTemplates" : {
                            "application/json" : "{ \"Message\" : \"Can't $context.httpMethod\n$context.resourcePath\" }"
                        }
                    }
                },
                "requestTemplates" : {
                    "application/json" : "{\"statusCode\": 200}"
                },
                "passthroughBehavior" : "when_no_match"
            }
        }
    }
}
```

```
,  
"/{a}/{b}/{op}" : {  
    "get" : {  
        "parameters" : [ {  
            "name" : "a",  
            "in" : "path",  
            "required" : true,  
            "schema" : {  
                "type" : "string"  
            }  
        }, {  
            "name" : "b",  
            "in" : "path",  
            "required" : true,  
            "schema" : {  
                "type" : "string"  
            }  
        }, {  
            "name" : "op",  
            "in" : "path",  
            "required" : true,  
            "schema" : {  
                "type" : "string"  
            }  
        } ],  
        "responses" : {  
            "200" : {  
                "description" : "200 response",  
                "content" : {  
                    "application/json" : {  
                        "schema" : {  
                            "$ref" : "#/components/schemas/Result"  
                        }  
                    }  
                }  
            }  
        },  
        "x-amazon-apigateway-integration" : {  
            "type" : "aws",  
            "httpMethod" : "POST",  
            "uri" : "arn:aws:apigateway:us-west-2:lambda:path/2015-03-31/functions/  
arn:aws:lambda:us-west-2:1112223333:function:Calc/invocations",  
            "responses" : {  
                "default" : {
```

```
        "statusCode" : "200",
        "responseTemplates" : {
            "application/json" : "#set($inputRoot = $input.path('$'))\n{\n\"input\" : {\n    \"a\" : $inputRoot.a,\n    \"b\" : $inputRoot.b,\n    \"op\" : \"$inputRoot.op\"\n},\n    \"output\" : {\n        \"c\" : $inputRoot.c\n    }\n}\n}",
            "requestTemplates" : {
                "application/json" : "#set($inputRoot = $input.path('$'))\n{\n\"a\" : $input.params('a'),\n    \"b\" : $input.params('b'),\n    \"op\" : \"$input.params('op')\"\n}\n}",
                "passthroughBehavior" : "when_no_templates"
            }
        },
        "/": {
            "get" : {
                "parameters" : [ {
                    "name" : "op",
                    "in" : "query",
                    "schema" : {
                        "type" : "string"
                    }
                }, {
                    "name" : "a",
                    "in" : "query",
                    "schema" : {
                        "type" : "string"
                    }
                }, {
                    "name" : "b",
                    "in" : "query",
                    "schema" : {
                        "type" : "string"
                    }
                } ],
                "responses" : {
                    "200" : {
                        "description" : "200 response",
                        "content" : {
                            "application/json" : {
                                "schema" : {

```

```
        "$ref" : "#/components/schemas/Result"
    }
}
}
},
"x-amazon-apigateway-integration" : {
    "type" : "aws",
    "httpMethod" : "POST",
    "uri" : "arn:aws:apigateway:us-west-2:lambda:path/2015-03-31/functions/
arn:aws:lambda:us-west-2:111122223333:function:Calc/invocations",
    "responses" : {
        "default" : {
            "statusCode" : "200",
            "responseTemplates" : {
                "application/json" : "#set($inputRoot = $input.path('$'))\n{\n\
\"input\" : {\n    \"a\" : $inputRoot.a,\n    \"b\" : $inputRoot.b,\n    \"op\" :
\"$inputRoot.op\"\n},\n    \"output\" : {\n        \"c\" : $inputRoot.c\n    }\n}\n"
            }
        },
        "requestTemplates" : {
            "application/json" : "#set($inputRoot = $input.path('$'))\n{\n\
\"a\" : $input.params('a'),\n    \"b\" : $input.params('b'),\n    \"op\" :
$input.params('op')\"\n}"
        },
        "passthroughBehavior" : "when_no_templates"
    }
},
"post" : {
    "requestBody" : {
        "content" : {
            "application/json" : {
                "schema" : {
                    "$ref" : "#/components/schemas/Input"
                }
            }
        },
        "required" : true
    },
    "responses" : {
        "200" : {
            "description" : "200 response",
            "content" : {
```

```
        "application/json" : {
            "schema" : {
                "$ref" : "#/components/schemas/Result"
            }
        }
    },
    "x-amazon-apigateway-integration" : {
        "type" : "aws",
        "httpMethod" : "POST",
        "uri" : "arn:aws:apigateway:us-west-2:lambda:path/2015-03-31/functions/
arn:aws:lambda:us-west-2:111122223333:function:Calc/invocations",
        "responses" : {
            "default" : {
                "statusCode" : "200",
                "responseTemplates" : {
                    "application/json" : "#set($inputRoot = $input.path('$'))\n{\n\\\"input\\\" : {\n    \\\"a\\\" : $inputRoot.a,\n    \\\"b\\\" : $inputRoot.b,\n    \\\"op\\\" :
\\\"$inputRoot.op\\\"\n},\n    \\\"output\\\" : {\n        \\\"c\\\" : $inputRoot.c\n    }\n}\n"
                }
            }
        },
        "passthroughBehavior" : "when_no_match"
    }
},
"/{a}" : {
    "x-amazon-apigateway-any-method" : {
        "parameters" : [ {
            "name" : "a",
            "in" : "path",
            "required" : true,
            "schema" : {
                "type" : "string"
            }
        }],
        "responses" : {
            "404" : {
                "description" : "404 response",
                "content" : { }
            }
        },
        "x-amazon-apigateway-integration" : {
```

```
        "type" : "mock",
        "responses" : {
            "default" : {
                "statusCode" : "404",
                "responseTemplates" : {
                    "application/json" : "{ \"Message\" : \"Can't $context.httpMethod\n$context.resourcePath\" }"
                }
            }
        },
        "requestTemplates" : {
            "application/json" : "{\"statusCode\": 200}"
        },
        "passthroughBehavior" : "when_no_match"
    }
}
},
"components" : {
    "schemas" : {
        "Input" : {
            "title" : "Input",
            "type" : "object",
            "properties" : {
                "a" : {
                    "type" : "number"
                },
                "b" : {
                    "type" : "number"
                },
                "op" : {
                    "type" : "string"
                }
            }
        },
        "Output" : {
            "title" : "Output",
            "type" : "object",
            "properties" : {
                "c" : {
                    "type" : "number"
                }
            }
        }
    }
},
```

```
"Result" : {  
    "title" : "Result",  
    "type" : "object",  
    "properties" : {  
        "input" : {  
            "$ref" : "#/components/schemas/Input"  
        },  
        "output" : {  
            "$ref" : "#/components/schemas/Output"  
        }  
    }  
}  
}  
}  
}
```

Generate the Java SDK of an API in API Gateway

The following procedure shows how to generate the Java SDK of an API in API Gateway.

To generate the Java SDK of an API in API Gateway

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose a REST API.
3. Choose **Stages**.
4. In the **Stages** pane, select the name of the stage.
5. Open the **Stage actions** menu, and then choose **Generate SDK**.
6. For **Platform**, choose the **Java** platform and do the following:
 - a. For **Service Name**, specify the name of your SDK. For example, **SimpleCalcSdk**. This becomes the name of your SDK client class. The name corresponds to the `<name>` tag under `<project>` in the `pom.xml` file, which is in the SDK's project folder. Do not include hyphens.
 - b. For **Java Package Name**, specify a package name for your SDK. For example, **examples.aws.apig.simpleCalc.sdk**. This package name is used as the namespace of your SDK library. Do not include hyphens.
 - c. For **Java Build System**, enter **maven** or **gradle** to specify the build system.

- d. For **Java Group Id**, enter a group identifier for your SDK project. For example, enter **my-apig-api-examples**. This identifier corresponds to the `<groupId>` tag under `<project>` in the `pom.xml` file, which is in the SDK's project folder.
 - e. For **Java Artifact Id**, enter an artifact identifier for your SDK project. For example, enter **simple-calc-sdk**. This identifier corresponds to the `<artifactId>` tag under `<project>` in the `pom.xml` file, which is in the SDK's project folder.
 - f. For **Java Artifact Version**, enter a version identifier string. For example, **1.0.0**. This version identifier corresponds to the `<version>` tag under `<project>` in the `pom.xml` file, which is in the SDK's project folder.
 - g. For **Source Code License Text**, enter the license text of your source code, if any.
7. Choose **Generate SDK**, and then follow the on-screen directions to download the SDK generated by API Gateway.

Follow the instructions in [Use a Java SDK generated by API Gateway for a REST API](#) to use the generated SDK.

Every time you update an API, you must redeploy the API and regenerate the SDK to have the updates included.

Generate the Android SDK of an API in API Gateway

The following procedure shows how to generate the Android SDK of an API in API Gateway.

To generate the Android SDK of an API in API Gateway

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose a REST API.
3. Choose **Stages**.
4. In the **Stages** pane, select the name of the stage.
5. Open the **Stage actions** menu, and then choose **Generate SDK**.
6. For **Platform**, choose the Android platform and do the following:
 - a. For **Group ID**, enter the unique identifier for the corresponding project. This is used in the `pom.xml` file (for example, **com.mycompany**).
 - b. For **Invoker package**, enter the namespace for the generated client classes (for example, **com.mycompany.clientsdk**).

- c. For **Artifact ID**, enter the name of the compiled .jar file without the version. This is used in the pom.xml file (for example, **aws-apigateway-api-sdk**).
 - d. For **Artifact version**, enter the artifact version number for the generated client. This is used in the pom.xml file and should follow a *major.minor.patch* pattern (for example, **1.0.0**).
7. Choose **Generate SDK**, and then follow the on-screen directions to download the SDK generated by API Gateway.

Follow the instructions in [Use an Android SDK generated by API Gateway for a REST API](#) to use the generated SDK.

Every time you update an API, you must redeploy the API and regenerate the SDK to have the updates included.

Generate the iOS SDK of an API in API Gateway

The following procedure shows how to generate the iOS SDK of an API in API Gateway.

To generate the iOS SDK of an API in API Gateway

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose a REST API.
3. Choose **Stages**.
4. In the **Stages** pane, select the name of the stage.
5. Open the **Stage actions** menu, and then choose **Generate SDK**.
6. For **Platform**, choose the **iOS (Objective-C) or iOS (Swift)** platform and do the following:
 - Type a unique prefix in the **Prefix** box.

The effect of prefix is as follows: if you assign, for example, **SIMPLE_CALC** as the prefix for the SDK of the [SimpleCalc](#) API with `input`, `output`, and `result` models, the generated SDK will contain the `SIMPLE_CALCSimpleCalcClient` class that encapsulates the API, including the method requests/responses. In addition, the generated SDK will contain the `SIMPLE_CALCinput`, `SIMPLE_CALCoutput`, and `SIMPLE_CALCresult` classes to represent the input, output, and results, respectively, to represent the request input and response output. For more information, see [Use iOS SDK generated by API Gateway for a REST API in Objective-C or Swift](#).

7. Choose **Generate SDK**, and then follow the on-screen directions to download the SDK generated by API Gateway.

Follow the instructions in [Use iOS SDK generated by API Gateway for a REST API in Objective-C or Swift](#) to use the generated SDK.

Every time you update an API, you must redeploy the API and regenerate the SDK to have the updates included.

Generate the JavaScript SDK of a REST API in API Gateway

The following procedure shows how to generate the JavaScript SDK of an API in API Gateway.

To generate the JavaScript SDK of an API in API Gateway

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose a REST API.
3. Choose **Stages**.
4. In the **Stages** pane, select the name of the stage.
5. Open the **Stage actions** menu, and then choose **Generate SDK**.
6. For **Platform**, choose the **JavaScript** platform.
7. Choose **Generate SDK**, and then follow the on-screen directions to download the SDK generated by API Gateway.

Follow the instructions in [Use a JavaScript SDK generated by API Gateway for a REST API](#) to use the generated SDK.

Every time you update an API, you must redeploy the API and regenerate the SDK to have the updates included.

Generate the Ruby SDK of an API in API Gateway

The following procedure shows how to generate the Ruby SDK of an API in API Gateway.

To generate the Ruby SDK of an API in API Gateway

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.

2. Choose a REST API.
3. Choose **Stages**.
4. In the **Stages** pane, select the name of the stage.
5. Open the **Stage actions** menu, and then choose **Generate SDK**.
6. For **Platform**, choose the **Ruby** platform and do the following:
 - a. For **Service Name**, specify the name of your SDK. For example, **SimpleCalc**. This is used to generate the Ruby Gem namespace of your API. The name must be all letters, (a-zA-Z), without any other special characters or numbers.
 - b. For **Ruby Gem Name**, specify the name of the Ruby Gem to contain the generated SDK source code for your API. By default, it is the lower-cased service name plus the -sdk suffix—for example, **simplecalc-sdk**.
 - c. For **Ruby Gem Version**, specify a version number for the generated Ruby Gem. By default, it is set to **1.0.0**.
7. Choose **Generate SDK**, and then follow the on-screen directions to download the SDK generated by API Gateway.

Follow the instructions in [Use a Ruby SDK generated by API Gateway for a REST API](#) to use the generated SDK.

Every time you update an API, you must redeploy the API and regenerate the SDK to have the updates included.

Generate SDKs for an API using AWS CLI commands in API Gateway

You can use AWS CLI to generate and download an SDK of an API for a supported platform by calling the [get-sdk](#) command. We demonstrate this for some of the supported platforms in the following.

Topics

- [Generate and download the Java for Android SDK using the AWS CLI](#)
- [Generate and download the JavaScript SDK using the AWS CLI](#)
- [Generate and download the Ruby SDK using the AWS CLI](#)

Generate and download the Java for Android SDK using the AWS CLI

To generate and download a Java for Android SDK generated by API Gateway of an API (udpuvvzbkc) at a given stage (test), call the command as follows:

```
aws apigateway get-sdk \
    --rest-api-id udpuvvzbkc \
    --stage-name test \
    --sdk-type android \
    --parameters groupId='com.mycompany', \
        invokerPackage='com.mycompany.myApiSdk', \
        artifactId='myApiSdk', \
        artifactVersion='0.0.1' \
    ~/apps/myApi/myApi-android-sdk.zip
```

The last input of `~/apps/myApi/myApi-android-sdk.zip` is the path to the downloaded SDK file named `myApi-android-sdk.zip`.

Generate and download the JavaScript SDK using the AWS CLI

To generate and download a JavaScript SDK generated by API Gateway of an API (udpuvvzbkc) at a given stage (test), call the command as follows:

```
aws apigateway get-sdk \
    --rest-api-id udpuvvzbkc \
    --stage-name test \
    --sdk-type javascript \
    ~/apps/myApi/myApi-js-sdk.zip
```

The last input of `~/apps/myApi/myApi-js-sdk.zip` is the path to the downloaded SDK file named `myApi-js-sdk.zip`.

Generate and download the Ruby SDK using the AWS CLI

To generate and download a Ruby SDK of an API (udpuvvzbkc) at a given stage (test), call the command as follows:

```
aws apigateway get-sdk \
    --rest-api-id udpuvvzbkc \
    --stage-name test \
    --sdk-type ruby \
```

```
--parameters service.name=myApiRubySdk,ruby.gem-name=myApi,ruby.gem-version=0.01 \
~/apps/myApi/myApi-ruby-sdk.zip
```

The last input of `~/apps/myApi/myApi-ruby-sdk.zip` is the path to the downloaded SDK file named `myApi-ruby-sdk.zip`.

Next, we show how to use the generated SDK to call the underlying API. For more information, see [Invoke REST APIs in API Gateway](#).

Sell your API Gateway APIs through AWS Marketplace

After you build, test, and deploy your APIs, you can package them in an API Gateway [usage plan](#) and sell the plan as a Software as a Service (SaaS) product through AWS Marketplace. API buyers subscribing to your product offering are billed by AWS Marketplace based on the number of requests made to the usage plan.

To sell your APIs on AWS Marketplace, you must set up the sales channel to integrate AWS Marketplace with API Gateway. Generally speaking, this involves listing your product on AWS Marketplace, setting up an IAM role with appropriate policies to allow API Gateway to send usage metrics to AWS Marketplace, associating an AWS Marketplace product with an API Gateway usage plan, and associating an AWS Marketplace buyer with an API Gateway API key. Details are discussed in the following sections.

For more information about selling your API as a SaaS product on AWS Marketplace, see the [AWS Marketplace User Guide](#).

Topics

- [Initialize AWS Marketplace integration with API Gateway](#)
- [Handle customer subscription to usage plans](#)

Initialize AWS Marketplace integration with API Gateway

The following tasks are for one-time initialization of AWS Marketplace integration with API Gateway, which enables you to sell your APIs as a SaaS product.

List a product on AWS Marketplace

To list your usage plan as a SaaS product, submit a product load form through [AWS Marketplace](#). The product must contain a dimension named apigateway of the requests type. This dimension defines the price-per-request and is used by API Gateway to meter requests to your APIs.

Create the metering role

Create an IAM role named ApiGatewayMarketplaceMeteringRole with the following execution policy and trust policy. This role allows API Gateway to send usage metrics to AWS Marketplace on your behalf.

Execution policy of the metering role

JSON

```
{  
    "Version": "2012-10-17",  
    "Statement": [  
        {  
            "Action": [  
                "aws-marketplace:BatchMeterUsage",  
                "aws-marketplace:ResolveCustomer"  
            ],  
            "Resource": "*",  
            "Effect": "Allow"  
        }  
    ]  
}
```

Trusted relationship policy of the metering role

JSON

```
{  
    "Version": "2012-10-17",  
    "Statement": [  
        {  
            "Effect": "Allow",  

```

```
        "Service": "apigateway.amazonaws.com"
    },
    "Action": "sts:AssumeRole"
}
]
```

Associate usage plan with AWS Marketplace product

When you list a product on AWS Marketplace, you receive an AWS Marketplace product code. To integrate API Gateway with AWS Marketplace, associate your usage plan with the AWS Marketplace product code. You enable the association by setting the API Gateway UsagePlan's [productCode](#) field to your AWS Marketplace product code, using the API Gateway console, the API Gateway REST API, the AWS CLI for API Gateway, or AWS SDK for API Gateway. The following code example uses the API Gateway REST API:

```
PATCH /usageplans/USAGE_PLAN_ID
Host: apigateway.region.amazonaws.com
Authorization: ...

{
  "patchOperations" : [
    {
      "path" : "/productCode",
      "value" : "MKTPLACE_PRODUCT_CODE",
      "op" : "replace"
    }
  ]
}
```

Handle customer subscription to usage plans

The following tasks are handled by your developer portal application.

When a customer subscribes to your product through AWS Marketplace, AWS Marketplace forwards a POST request to the SaaS subscriptions URL that you registered when listing your product on AWS Marketplace. The POST request comes with an x-amzn-marketplace-token parameter containing buyer information. Follow the instructions in [SaaS customer onboarding](#) to handle this redirect in your developer portal application.

Responding to a customer's subscribing request, AWS Marketplace sends a subscribe-success notification to an Amazon SNS topic that you can subscribe to. (See [SaaS customer onboarding](#)).

To accept the customer subscription request, you handle the subscribe-success notification by creating or retrieving an API Gateway API key for the customer, associating the customer's AWS Marketplace-provisioned customerId with the API keys, and then adding the API key to your usage plan.

When the customer's subscription request completes, the developer portal application should present the customer with the associated API key and inform the customer that the API key must be included in the x-api-key header in requests to the APIs.

When a customer cancels a subscription to a usage plan, AWS Marketplace sends an unsubscribe-success notification to the SNS topic. To complete the process of unsubscribing the customer, you handle the unsubscribe-success notification by removing the customer's API keys from the usage plan.

Authorize a customer to access a usage plan

To authorize access to your usage plan for a given customer, use the API Gateway API to fetch or create an API key for the customer and add the API key to the usage plan.

The following example shows how to call the API Gateway REST API to create a new API key with a specific AWS Marketplace customerId value ([MARKETPLACE_CUSTOMER_ID](#)).

```
POST apikeys HTTP/1.1
Host: apigateway.region.amazonaws.com
Authorization: ...

{
    "name" : "my_api_key",
    "description" : "My API key",
    "enabled" : "false",
    "stageKeys" : [ {
        "restApiId" : "uycll6xg9a",
        "stageName" : "prod"
    }],
    "customerId" : "MARKETPLACE\_CUSTOMER\_ID"
}
```

The following example shows how to get an API key with a specific AWS Marketplace customerId value ([MARKETPLACE_CUSTOMER_ID](#)).

```
GET apikeys?customerId=MARKETPLACE\_CUSTOMER\_ID HTTP/1.1
```

```
Host: apigateway.region.amazonaws.com
Authorization: ...
```

To add an API key to a usage plan, create a [UsagePlanKey](#) with the API key for the relevant usage plan. The following example shows how to accomplish this using the API Gateway REST API, where n371pt is the usage plan ID and q5ugs7qjjh is an example API keyId returned from the preceding examples.

```
POST /usageplans/n371pt/keys HTTP/1.1
Host: apigateway.region.amazonaws.com
Authorization: ...

{
    "keyId": "q5ugs7qjjh",
    "keyType": "API_KEY"
}
```

Associate a customer with an API key

You must update the [ApiKey](#)'s customerId field to the AWS Marketplace customer ID of the customer. This associates the API key with the AWS Marketplace customer, which enables metering and billing for the buyer. The following code example calls the API Gateway REST API to do that.

```
PATCH /apikeys/q5ugs7qjjh
Host: apigateway.region.amazonaws.com
Authorization: ...

{
    "patchOperations" : [
        {
            "path" : "/customerId",
            "value" : "MARKEPLACE_CUSTOMER_ID",
            "op" : "replace"
        }
    ]
}
```

Protect your REST APIs in API Gateway

API Gateway provides a number of ways to protect your API from certain threats, like malicious users or spikes in traffic. You can protect your API using strategies like generating SSL certificates, configuring a web application firewall, setting throttling targets, and only allowing access to

your API from a Virtual Private Cloud (VPC). In this section you can learn how to enable these capabilities using API Gateway.

Topics

- [How to turn on mutual TLS authentication for your REST APIs in API Gateway](#)
- [Generate and configure an SSL certificate for backend authentication in API Gateway](#)
- [Use AWS WAF to protect your REST APIs in API Gateway](#)
- [Throttle requests to your REST APIs for better throughput in API Gateway](#)
- [Private REST APIs in API Gateway](#)

How to turn on mutual TLS authentication for your REST APIs in API Gateway

Mutual TLS authentication requires two-way authentication between the client and the server. With mutual TLS, clients must present X.509 certificates to verify their identity to access your API. Mutual TLS is a common requirement for Internet of Things (IoT) and business-to-business applications.

You can use mutual TLS along with other [authorization and authentication operations](#) that API Gateway supports. API Gateway forwards the certificates that clients provide to Lambda authorizers and to backend integrations.

Important

By default, clients can invoke your API by using the execute-api endpoint that API Gateway generates for your API. To ensure that clients can access your API only by using a custom domain name with mutual TLS, disable the default execute-api endpoint. To learn more, see [the section called “Disable the default endpoint”](#).

Topics

- [Prerequisites for mutual TLS](#)
- [Configuring mutual TLS for a custom domain name](#)
- [Invoke an API by using a custom domain name that requires mutual TLS](#)
- [Updating your truststore](#)

- [Disable mutual TLS](#)
- [Troubleshoot mutual TLS for your REST API](#)

Prerequisites for mutual TLS

To configure mutual TLS you need:

- A Regional custom domain name
- At least one certificate configured in AWS Certificate Manager for your custom domain name
- A truststore configured and uploaded to Amazon S3

Custom domain names

To enable mutual TLS for a REST API, you must configure a custom domain name for your API. You can enable mutual TLS for a custom domain name, and then provide the custom domain name to clients. To access an API by using a custom domain name that has mutual TLS enabled, clients must present certificates that you trust in API requests. You can find more information at [the section called "Custom domain names"](#).

Using AWS Certificate Manager issued certificates

You can request a publicly trusted certificate directly from ACM or import public or self-signed certificates. To setup a certificate in ACM, go to [ACM](#). If you would like to import a certificate, continue reading in the following section.

Using an imported or AWS Private Certificate Authority certificate

To use a certificate imported into ACM or a certificate from AWS Private Certificate Authority with mutual TLS, API Gateway needs an ownershipVerificationCertificate issued by ACM. This ownership certificate is only used to verify that you have permissions to use the domain name. It is not used for the TLS handshake. If you don't already have a ownershipVerificationCertificate, go to <https://console.aws.amazon.com/acm/> to set one up.

You will need to keep this certificate valid for the lifetime of your domain name. If a certificate expires and auto-renew fails, all updates to the domain name will be locked. You will need to update the ownershipVerificationCertificateArn with a valid ownershipVerificationCertificate before you can make any other changes. The ownershipVerificationCertificate cannot be used as a server certificate for another

mutual TLS domain in API Gateway. If a certificate is directly re-imported into ACM, the issuer must stay the same.

Configuring your truststore

Truststores are text files with a . pem file extension. They are a trusted list of certificates from Certificate Authorities. To use mutual TLS, create a truststore of X.509 certificates that you trust to access your API.

You must include the complete chain of trust, starting from the issuing CA certificate, up to the root CA certificate, in your truststore. API Gateway accepts client certificates issued by any CA present in the chain of trust. The certificates can be from public or private certificate authorities. Certificates can have a maximum chain length of four. You can also provide self-signed certificates. The following algorithms are supported in the truststore:

- SHA-256 or stronger
- RSA-2048 or stronger
- ECDSA-256 or ECDSA-384

API Gateway validates a number of certificate properties. You can use Lambda authorizers to perform additional checks when a client invokes an API, including checking whether a certificate has been revoked. API Gateway validates the following properties:

Validation	Description
X.509 syntax	The certificate must meet X.509 syntax requirements.
Integrity	The certificate's content must not have been altered from that signed by the certificate authority from the truststore.
Validity	The certificate's validity period must be current.
Name chaining / key chaining	The names and subjects of certificates must form an unbroken chain. Certificates can have a maximum chain length of four.

Upload the truststore to an Amazon S3 bucket in a single file

The following is an example of what a .pem file might look like.

Example certificates.pem

```
-----BEGIN CERTIFICATE-----  
<Certificate contents>  
-----END CERTIFICATE-----  
-----BEGIN CERTIFICATE-----  
<Certificate contents>  
-----END CERTIFICATE-----  
-----BEGIN CERTIFICATE-----  
<Certificate contents>  
-----END CERTIFICATE-----  
...  
...
```

The following [cp](#) AWS CLI command uploads certificates.pem to your Amazon S3 bucket:

```
aws s3 cp certificates.pem s3://bucket-name
```

Configuring mutual TLS for a custom domain name

To configure mutual TLS for a REST API, you must use a Regional custom domain name for your API, with a TLS_1_2 security policy. For more information about choosing a security policy, see [the section called “Choose a security policy”](#).

Note

Mutual TLS isn't supported for private APIs.

After you've uploaded your truststore to Amazon S3, you can configure your custom domain name to use mutual TLS. The following [create-domain-name](#) creates a custom domain name with mutual TLS:

```
aws apigateway create-domain-name --region us-east-2 \  
  --domain-name api.example.com \  
  --regional-certificate-arn arn:aws:acm:us-  
  east-2:123456789012:certificate/123456789012-1234-1234-1234-12345678 \  
  --endpoint-configuration types=REGIONAL \  
  ...
```

```
--security-policy TLS_1_2 \
--mutual-tls-authentication truststoreUri=s3://bucket-name/key-name
```

After you create the domain name, you must configure DNS records and basepath mappings for API operations. To learn more, see [Set up a Regional custom domain name in API Gateway](#).

Invoke an API by using a custom domain name that requires mutual TLS

To invoke an API with mutual TLS enabled, clients must present a trusted certificate in the API request. When a client attempts to invoke your API, API Gateway looks for the client certificate's issuer in your truststore. For API Gateway to proceed with the request, the certificate's issuer and the complete chain of trust up to the root CA certificate must be in your truststore.

The following example `curl` command sends a request to `api.example.com`, that includes `my-cert.pem` in the request. `my-key.key` is the private key for the certificate.

```
curl -v --key ./my-key.key --cert ./my-cert.pem api.example.com
```

Your API is invoked only if your truststore trusts the certificate. The following conditions will cause API Gateway to fail the TLS handshake and deny the request with a 403 status code. If your certificate:

- isn't trusted
- is expired
- doesn't use a supported algorithm

 **Note**

API Gateway doesn't verify if a certificate has been revoked.

Updating your truststore

To update the certificates in your truststore, upload a new certificate bundle to Amazon S3. Then, you can update your custom domain name to use the updated certificate.

Use [Amazon S3 versioning](#) to maintain multiple versions of your truststore. When you update your custom domain name to use a new truststore version, API Gateway returns warnings if certificates are invalid.

API Gateway produces certificate warnings only when you update your domain name. API Gateway doesn't notify you if a previously uploaded certificate expires.

The following [update-domain-name](#) command updates a custom domain name to use a new truststore version:

```
aws apigateway update-domain-name \
--domain-name api.example.com \
--patch-operations op='replace',path='/mutualTlsAuthentication/
truststoreVersion',value='abcdef123'
```

Disable mutual TLS

The following [update-domain-name](#) disables mutual TLS:

```
aws apigateway update-domain-name \
--domain-name api.example.com \
--patch-operations op='replace',path='/mutualTlsAuthentication/
truststoreUri',value=''
```

Troubleshoot mutual TLS for your REST API

The following provides troubleshooting advice for errors and issues that you might encounter when turning on mutual TLS.

Troubleshooting certificate warnings

When creating a custom domain name with mutual TLS, API Gateway returns warnings if certificates in the truststore are not valid. This can also occur when updating a custom domain name to use a new truststore. The warnings indicate the issue with the certificate and the subject of the certificate that produced the warning. Mutual TLS is still enabled for your API, but some clients might not be able to access your API.

You'll need to decode the certificates in your truststore in order to identify which certificate produced the warning. You can use tools such as `openssl` to decode the certificates and identify their subjects.

The following command displays the contents of a certificate, including its subject:

```
openssl x509 -in certificate.crt -text -noout
```

Update or remove the certificates that produced warnings, and then upload a new truststore to Amazon S3. After uploading the new truststore, update your custom domain name to use the new truststore.

Troubleshooting domain name conflicts

The error "The certificate subject <certSubject> conflicts with an existing certificate from a different issuer." means multiple Certificate Authorities have issued a certificate for this domain. For each subject in the certificate, there can only be one issuer in API Gateway for mutual TLS domains. You will need to get all of your certificates for that subject through a single issuer. If the problem is with a certificate you don't have control of but you can prove ownership of the domain name, [contact Support](#) to open a ticket.

Troubleshooting domain name status messages

PENDING_CERTIFICATE_REIMPORT: This means you reimporrted a certificate to ACM and it failed validation because the new certificate has a SAN (subject alternative name) that is not covered by the ownershipVerificationCertificate or the subject or SANs in the certificate don't cover the domain name. Something might be configured incorrectly or an invalid certificate was imported. You need to reimport a valid certificate into ACM. For more information about validation see [Validating domain ownership](#).

PENDING_OWNERSHIP_VERIFICATION: This means your previously verified certificate has expired and ACM was unable to auto-renew it. You will need to renew the certificate or request a new certificate. More information about certificate renewal can be found at [ACM's troubleshooting managed certificate renewal](#) guide.

Troubleshoot incorrect returned certificate

When migrating a dedicated certificate from a fully qualified domain name (FQDN) to a wildcard customer domain name, API Gateway might return the certificate for the FQDN instead of the wildcard domain name.

The following command displays which certificate is being returned by API Gateway:

```
openssl s_client -connect hostname:port
```

If the resulting certificate is for the FQDN, [contact Support](#) to open a ticket.

Generate and configure an SSL certificate for backend authentication in API Gateway

You can use API Gateway to generate an SSL certificate and then use its public key in the backend to verify that HTTP requests to your backend system are from API Gateway. This allows your HTTP backend to control and accept only requests that originate from Amazon API Gateway, even if the backend is publicly accessible.

Note

Some backend servers might not support SSL client authentication as API Gateway does and could return an SSL certificate error. For a list of incompatible backend servers, see [the section called “Important notes”](#).

The SSL certificates that are generated by API Gateway are self-signed, and only the public key of a certificate is visible in the API Gateway console or through the APIs.

Topics

- [Generate a client certificate using the API Gateway console](#)
- [Configure an API to use SSL certificates](#)
- [Test invoke to verify the client certificate configuration](#)
- [Configure a backend HTTPS server to verify the client certificate](#)
- [Rotate an expiring client certificate](#)
- [API Gateway-supported certificate authorities for HTTP and HTTP proxy integrations in API Gateway](#)

Generate a client certificate using the API Gateway console

1. Open the API Gateway console at <https://console.aws.amazon.com/apigateway/>.
2. Choose a REST or WebSocket API.
3. In the main navigation pane, choose **Client certificates**.
4. From the **Client certificates** page, choose **Generate certificate**.
5. (Optional) For **Description**, enter a description.

6. Choose **Generate certificate** to generate the certificate. API Gateway generates a new certificate and returns the new certificate GUID, along with the PEM-encoded public key.

You're now ready to configure an API to use the certificate.

Configure an API to use SSL certificates

These instructions assume that you already completed [Generate a client certificate using the API Gateway console](#).

1. In the API Gateway console, create or open an REST or WebSocket API for which you want to use the client certificate. Make sure that the API has been deployed to a stage.
2. In the main navigation pane, choose **Stages**.
3. In the **Stage details** section, choose **Edit**.
4. For **Client certificate**, select a certificate.
5. Choose **Save changes**.

After a certificate is selected for the API and saved, API Gateway uses the certificate for all calls to HTTP integrations in your API.

Test invoke to verify the client certificate configuration

1. Choose a REST API method. Choose the **Test** tab. You might need to choose the right arrow button to show the **Test** tab.
2. For **Client certificate**, select a certificate.
3. Choose **Test**.

API Gateway presents the chosen SSL certificate for the HTTP backend to authenticate the API.

Configure a backend HTTPS server to verify the client certificate

These instructions assume that you already completed [Generate a client certificate using the API Gateway console](#) and downloaded a copy of the client certificate. You can download a client certificate by calling [clientcertificate:by-id](#) of the API Gateway REST API or [get-client-certificate](#) of AWS CLI.

Before configuring a backend HTTPS server to verify the client SSL certificate of API Gateway, you must have obtained the PEM-encoded private key and a server-side certificate that is provided by a trusted certificate authority.

If the server domain name is `myserver.mydomain.com`, the server certificate's CNAME value must be `myserver.mydomain.com` or `*.mydomain.com`.

Supported certificate authorities include [Let's Encrypt](#) or one of [the section called "Supported certificate authorities for HTTP and HTTP proxy integration"](#).

As an example, suppose that the client certificate file is `apig-cert.pem` and the server private key and certificate files are `server-key.pem` and `server-cert.pem`, respectively. For a Node.js server in the backend, you can configure the server similar to the following:

```
var fs = require('fs');
var https = require('https');
var options = {
  key: fs.readFileSync('server-key.pem'),
  cert: fs.readFileSync('server-cert.pem'),
  ca: fs.readFileSync('apig-cert.pem'),
  requestCert: true,
  rejectUnauthorized: true
};
https.createServer(options, function (req, res) {
  res.writeHead(200);
  res.end("hello world\n");
}).listen(443);
```

For a node-[express](#) app, you can use the [client-certificate-auth](#) modules to authenticate client requests with PEM-encoded certificates.

For other HTTPS server, see the documentation for the server.

Rotate an expiring client certificate

The client certificate generated by API Gateway is valid for 365 days. You must rotate the certificate before a client certificate on an API stage expires to avoid any downtime for the API.

Rotate an expiring client certificate using the AWS Management Console

The following procedure shows how to rotate a client certificate in the console for a previously deployed API.

1. In the main navigation pane, choose **Client certificates**.
2. From the **Client certificates** pane, choose **Generate certificate**.
3. Open the API for which you want to use the client certificate.
4. Choose **Stages** under the selected API and then choose a stage.
5. In the **Stage details** section, choose **Edit**.
6. For **Client certificate**, select the new certificate.
7. To save the settings, choose **Save changes**.

Rotate an expiring client certificate using the AWS CLI

You can check the expiration date of certificate by calling [clientCertificate:by-id](#) of the API Gateway REST API or the AWS CLI command of [get-client-certificate](#) and inspecting the returned [expirationDate](#) property.

To rotate a client certificate, do the following:

1. Generate a new client certificate by calling [clientcertificate:generate](#) of the API Gateway REST API or the AWS CLI command of [generate-client-certificate](#). In this tutorial, we assume that the new client certificate ID is ndiqef.
2. Update the backend server to include the new client certificate. Don't remove the existing client certificate yet.

Some servers might require a restart to finish the update. Consult the server documentation to see if you must restart the server during the update.

3. Update the API stage to use the new client certificate by calling [stage:update](#) of the API Gateway REST API, with the new client certificate ID (ndiqef):

```
PATCH /restapis/{restapi-id}/stages/stage1 HTTP/1.1
Content-Type: application/json
Host: apigateway.us-east-1.amazonaws.com
X-Amz-Date: 20170603T200400Z
Authorization: AWS4-HMAC-SHA256 Credential=...

{
  "patchOperations" : [
    {
      "op" : "replace",
```

```
        "path" : "/clientCertificateId",
        "value" : "ndiqef"
    }
]
}
```

You can also use the [update-stage](#) command.

If you are using a WebSocket API, use the `apigatewayv2 update-stage` command.

4. Update the backend server to remove the old certificate.
5. Delete the old certificate from API Gateway by calling the [clientcertificate:delete](#) of the API Gateway REST API, specifying the `clientCertificateId` (a1b2c3) of the old certificate:

```
DELETE /clientcertificates/a1b2c3
```

You can also call the [delete-client-certificate](#) command:

```
aws apigateway delete-client-certificate --client-certificate-id a1b2c3
```

API Gateway-supported certificate authorities for HTTP and HTTP proxy integrations in API Gateway

The following list shows the certificate authorities supported by API Gateway for HTTP, HTTP proxy, and private integrations.

```
Alias name: accvraiz1
SHA1: 93:05:7A:88:15:C6:4F:CE:88:2F:FA:91:16:52:28:78:BC:53:64:17
SHA256:
9A:6E:C0:12:E1:A7:DA:9D:BE:34:19:4D:47:8A:D7:C0:DB:18:22:FB:07:1D:F1:29:81:49:6E:D1:04:38:41:1

Alias name: acraizfnmtrcm
SHA1: EC:50:35:07:B2:15:C4:95:62:19:E2:A8:9A:5B:42:99:2C:4C:2C:20
SHA256:
EB:C5:57:0C:29:01:8C:4D:67:B1:AA:12:7B:AF:12:F7:03:B4:61:1E:BC:17:B7:DA:B5:57:38:94:17:9B:93:F

Alias name: actalis
SHA1: F3:73:B3:87:06:5A:28:84:8A:F2:F3:4A:CE:19:2B:DD:C7:8E:9C:AC
SHA256:
55:92:60:84:EC:96:3A:64:B9:6E:2A:BE:01:CE:0B:A8:6A:64:FB:FE:BC:C7:AA:B5:AF:C1:55:B3:7F:D7:60:6

Alias name: actalisauthenticationrootca
SHA1: F3:73:B3:87:06:5A:28:84:8A:F2:F3:4A:CE:19:2B:DD:C7:8E:9C:AC
```

SHA256:

55:92:60:84:EC:96:3A:64:B9:6E:2A:BE:01:CE:0B:A8:6A:64:FB:FE:BC:C7:AA:B5:AF:C1:55:B3:7F:D7:60:6

Alias name: addtrustclass1ca

SHA1: CC:AB:0E:A0:4C:23:01:D6:69:7B:DD:37:9F:CD:12:EB:24:E3:94:9D

SHA256:

8C:72:09:27:9A:C0:4E:27:5E:16:D0:7F:D3:B7:75:E8:01:54:B5:96:80:46:E3:1F:52:DD:25:76:63:24:E9:A

Alias name: addtrustexternalca

SHA1: 02:FA:F3:E2:91:43:54:68:60:78:57:69:4D:F5:E4:5B:68:85:18:68

SHA256:

68:7F:A4:51:38:22:78:FF:F0:C8:B1:1F:8D:43:D5:76:67:1C:6E:B2:BC:EA:B4:13:FB:83:D9:65:D0:6D:2F:F

Alias name: addtrustqualifiedca

SHA1: 4D:23:78:EC:91:95:39:B5:00:7F:75:8F:03:3B:21:1E:C5:4D:8B:CF

SHA256:

80:95:21:08:05:DB:4B:BC:35:5E:44:28:D8:FD:6E:C2:CD:E3:AB:5F:B9:7A:99:42:98:8E:B8:F4:DC:D0:60:1

Alias name: affirmtrustcommercial

SHA1: F9:B5:B6:32:45:5F:9C:BE:EC:57:5F:80:DC:E9:6E:2C:C7:B2:78:B7

SHA256:

03:76:AB:1D:54:C5:F9:80:3C:E4:B2:E2:01:A0:EE:7E:EF:7B:57:B6:36:E8:A9:3C:9B:8D:48:60:C9:6F:5F:A

Alias name: affirmtrustcommercialca

SHA1: F9:B5:B6:32:45:5F:9C:BE:EC:57:5F:80:DC:E9:6E:2C:C7:B2:78:B7

SHA256:

03:76:AB:1D:54:C5:F9:80:3C:E4:B2:E2:01:A0:EE:7E:EF:7B:57:B6:36:E8:A9:3C:9B:8D:48:60:C9:6F:5F:A

Alias name: affirmtrustnetworking

SHA1: 29:36:21:02:8B:20:ED:02:F5:66:C5:32:D1:D6:ED:90:9F:45:00:2F

SHA256:

0A:81:EC:5A:92:97:77:F1:45:90:4A:F3:8D:5D:50:9F:66:B5:E2:C5:8F:CD:B5:31:05:8B:0E:17:F3:F0:B4:1

Alias name: affirmtrustnetworkingca

SHA1: 29:36:21:02:8B:20:ED:02:F5:66:C5:32:D1:D6:ED:90:9F:45:00:2F

SHA256:

0A:81:EC:5A:92:97:77:F1:45:90:4A:F3:8D:5D:50:9F:66:B5:E2:C5:8F:CD:B5:31:05:8B:0E:17:F3:F0:B4:1

Alias name: affirmtrustpremium

SHA1: D8:A6:33:2C:E0:03:6F:B1:85:F6:63:4F:7D:6A:06:65:26:32:28:27

SHA256:

70:A7:3F:7F:37:6B:60:07:42:48:90:45:34:B1:14:82:D5:BF:0E:69:8E:CC:49:8D:F5:25:77:EB:F2:E9:3B:9

Alias name: affirmtrustpremiumca

SHA1: D8:A6:33:2C:E0:03:6F:B1:85:F6:63:4F:7D:6A:06:65:26:32:28:27

SHA256:

70:A7:3F:7F:37:6B:60:07:42:48:90:45:34:B1:14:82:D5:BF:0E:69:8E:CC:49:8D:F5:25:77:EB:F2:E9:3B:9

Alias name: affirmtrustpremiumecc

SHA1: B8:23:6B:00:2F:1D:16:86:53:01:55:6C:11:A4:37:CA:EB:FF:C3:BB

SHA256:

BD:71:FD:F6:DA:97:E4:CF:62:D1:64:7A:DD:25:81:B0:7D:79:AD:F8:39:7E:B4:EC:BA:9C:5E:84:88:82:14:2

Alias name: affirmtrustpremiumeccca

SHA1: B8:23:6B:00:2F:1D:16:86:53:01:55:6C:11:A4:37:CA:EB:FF:C3:BB

SHA256:
BD:71:FD:F6:DA:97:E4:CF:62:D1:64:7A:DD:25:81:B0:7D:79:AD:F8:39:7E:B4:EC:BA:9C:5E:84:88:82:14:2
Alias name: amazon-ca-g4-acm1
SHA1: F2:0D:28:B6:29:C2:2C:5E:84:05:E6:02:4D:97:FE:8F:A0:84:93:A0
SHA256:
B0:11:A4:F7:29:6C:74:D8:2B:F5:62:DF:87:D7:28:C7:1F:B5:8C:F4:E6:73:F2:78:FC:DA:F3:FF:83:A6:8C:8
Alias name: amazon-ca-g4-acm2
SHA1: A7:E6:45:32:1F:7A:B7:AD:C0:70:EA:73:5F:AB:ED:C3:DA:B4:D0:C8
SHA256:
D7:A8:7C:69:95:D0:E2:04:2A:32:70:A7:E2:87:FE:A7:E8:F4:C1:70:62:F7:90:C3:EB:BB:53:F2:AC:39:26:B
Alias name: amazon-ca-g4-acm3
SHA1: 7A:DB:56:57:5F:D6:EE:67:85:0A:64:BB:1C:E9:E4:B0:9A:DB:9D:07
SHA256:
6B:EB:9D:20:2E:C2:00:70:BD:D2:5E:D3:C0:C8:33:2C:B4:78:07:C5:82:94:4E:7E:23:28:22:71:A4:8E:0E:C
Alias name: amazon-ca-g4-legacy
SHA1: EA:E7:DE:F9:0A:BE:9F:0B:68:CE:B7:24:0D:80:74:03:BF:6E:B1:6E
SHA256:
CD:72:C4:7F:B4:AD:28:A4:67:2B:E1:86:47:D4:40:E9:3B:16:2D:95:DB:3C:2F:94:BB:81:D9:09:F7:91:24:5
Alias name: amazon-root-ca-ecc-384-1
SHA1: F9:5E:4A:AB:9C:2D:57:61:63:3D:B2:57:B4:0F:24:9E:7B:E2:23:7D
SHA256:
C6:BD:E5:66:C2:72:2A:0E:96:E9:C1:2C:BF:38:92:D9:55:4D:29:03:57:30:72:40:7F:4E:70:17:3B:3C:9B:6
Alias name: amazon-root-ca-rsa-2k-1
SHA1: 8A:9A:AC:27:FC:86:D4:50:23:AD:D5:63:F9:1E:AE:2C:AF:63:08:6C
SHA256:
0F:8F:33:83:FB:70:02:89:49:24:E1:AA:B0:D7:FB:5A:BF:98:DF:75:8E:0F:FE:61:86:92:BC:F0:75:35:CC:8
Alias name: amazon-root-ca-rsa-4k-1
SHA1: EC:BD:09:61:F5:7A:B6:A8:76:BB:20:8F:14:05:ED:7E:70:ED:39:45
SHA256:
36:AE:AD:C2:6A:60:07:90:6B:83:A3:73:2D:D1:2B:D4:00:5E:C7:F2:76:11:99:A9:D4:DA:63:2F:59:B2:8B:C
Alias name: amazon1
SHA1: 8D:A7:F9:65:EC:5E:FC:37:91:0F:1C:6E:59:FD:C1:CC:6A:6E:DE:16
SHA256:
8E:CD:E6:88:4F:3D:87:B1:12:5B:A3:1A:C3:FC:B1:3D:70:16:DE:7F:57:CC:90:4F:E1:CB:97:C6:AE:98:19:6
Alias name: amazon2
SHA1: 5A:8C:EF:45:D7:A6:98:59:76:7A:8C:8B:44:96:B5:78:CF:47:4B:1A
SHA256:
1B:A5:B2:AA:8C:65:40:1A:82:96:01:18:F8:0B:EC:4F:62:30:4D:83:CE:C4:71:3A:19:C3:9C:01:1E:A4:6D:B
Alias name: amazon3
SHA1: 0D:44:DD:8C:3C:8C:1A:1A:58:75:64:81:E9:0F:2E:2A:FF:B3:D2:6E
SHA256:
18:CE:6C:FE:7B:F1:4E:60:B2:E3:47:B8:DF:E8:68:CB:31:D0:2E:BB:3A:DA:27:15:69:F5:03:43:B4:6D:B3:A
Alias name: amazon4
SHA1: F6:10:84:07:D6:F8:BB:67:98:0C:C2:E2:44:C2:EB:AE:1C:EF:63:BE

SHA256:

E3:5D:28:41:9E:D0:20:25:CF:A6:90:38:CD:62:39:62:45:8D:A5:C6:95:FB:DE:A3:C2:2B:0B:FB:25:89:70:9

Alias name: amazonrootca1

SHA1: 8D:A7:F9:65:EC:5E:FC:37:91:0F:1C:6E:59:FD:C1:CC:6A:6E:DE:16

SHA256:

8E:CD:E6:88:4F:3D:87:B1:12:5B:A3:1A:C3:FC:B1:3D:70:16:DE:7F:57:CC:90:4F:E1:CB:97:C6:AE:98:19:6

Alias name: amazonrootca2

SHA1: 5A:8C:EF:45:D7:A6:98:59:76:7A:8C:8B:44:96:B5:78:CF:47:4B:1A

SHA256:

1B:A5:B2:AA:8C:65:40:1A:82:96:01:18:F8:0B:EC:4F:62:30:4D:83:CE:C4:71:3A:19:C3:9C:01:1E:A4:6D:B

Alias name: amazonrootca3

SHA1: 0D:44:DD:8C:3C:8C:1A:1A:58:75:64:81:E9:0F:2E:2A:FF:B3:D2:6E

SHA256:

18:CE:6C:FE:7B:F1:4E:60:B2:E3:47:B8:DF:E8:68:CB:31:D0:2E:BB:3A:DA:27:15:69:F5:03:43:B4:6D:B3:A

Alias name: amazonrootca4

SHA1: F6:10:84:07:D6:F8:BB:67:98:0C:C2:E2:44:C2:EB:AE:1C:EF:63:BE

SHA256:

E3:5D:28:41:9E:D0:20:25:CF:A6:90:38:CD:62:39:62:45:8D:A5:C6:95:FB:DE:A3:C2:2B:0B:FB:25:89:70:9

Alias name: amzninternalinfoseccag3

SHA1: B9:B1:CA:38:F7:BF:9C:D2:D4:95:E7:B6:5E:75:32:9B:A8:78:2E:F6

SHA256:

81:03:0B:C7:E2:54:DA:7B:F8:B7:45:DB:DD:41:15:89:B5:A3:81:86:FB:4B:29:77:1F:84:0A:18:D9:67:6D:6

Alias name: amzninternalrootca

SHA1: A7:B7:F6:15:8A:FF:1E:C8:85:13:38:BC:93:EB:A2:AB:A4:09:EF:06

SHA256:

0E:DE:63:C1:DC:7A:8E:11:F1:AB:BC:05:4F:59:EE:49:9D:62:9A:2F:DE:9C:A7:16:32:A2:64:29:3E:8B:66:A

Alias name: aolrootca1

SHA1: 39:21:C1:15:C1:5D:0E:CA:5C:CB:5B:C4:F0:7D:21:D8:05:0B:56:6A

SHA256:

77:40:73:12:C6:3A:15:3D:5B:C0:0B:4E:51:75:9C:DF:DA:C2:37:DC:2A:33:B6:79:46:E9:8E:9B:FA:68:0A:E

Alias name: aolrootca2

SHA1: 85:B5:FF:67:9B:0C:79:96:1F:C8:6E:44:22:00:46:13:DB:17:92:84

SHA256:

7D:3B:46:5A:60:14:E5:26:C0:AF:FC:EE:21:27:D2:31:17:27:AD:81:1C:26:84:2D:00:6A:F3:73:06:CC:80:B

Alias name: atostrustedroot2011

SHA1: 2B:B1:F5:3E:55:0C:1D:C5:F1:D4:E6:B7:6A:46:4B:55:06:02:AC:21

SHA256:

F3:56:BE:A2:44:B7:A9:1E:B3:5D:53:CA:9A:D7:86:4A:CE:01:8E:2D:35:D5:F8:F9:6D:DF:68:A6:F4:1A:A4:7

Alias name: autoridaddecertificacionfirmaprofesionalcifa62634068

SHA1: AE:C5:FB:3F:C8:E1:BF:C4:E5:4F:03:07:5A:9A:E8:00:B7:F7:B6:FA

SHA256:

04:04:80:28:BF:1F:28:64:D4:8F:9A:D4:D8:32:94:36:6A:82:88:56:55:3F:3B:14:30:3F:90:14:7F:5D:40:E

Alias name: baltimorecodesigningca

SHA1: 30:46:D8:C8:88:FF:69:30:C3:4A:FC:CD:49:27:08:7C:60:56:7B:0D

SHA256:

A9:15:45:DB:D2:E1:9C:4C:CD:F9:09:AA:71:90:0D:18:C7:35:1C:89:B3:15:F0:F1:3D:05:C1:3A:8F:FB:46:8

Alias name: baltimorecybertrustca

SHA1: D4:DE:20:D0:5E:66:FC:53:FE:1A:50:88:2C:78:DB:28:52:CA:E4:74

SHA256:

16:AF:57:A9:F6:76:B0:AB:12:60:95:AA:5E:BA:DE:F2:2A:B3:11:19:D6:44:AC:95:CD:4B:93:DB:F3:F2:6A:E

Alias name: baltimorecybertrustroot

SHA1: D4:DE:20:D0:5E:66:FC:53:FE:1A:50:88:2C:78:DB:28:52:CA:E4:74

SHA256:

16:AF:57:A9:F6:76:B0:AB:12:60:95:AA:5E:BA:DE:F2:2A:B3:11:19:D6:44:AC:95:CD:4B:93:DB:F3:F2:6A:E

Alias name: buypassclass2ca

SHA1: 49:0A:75:74:DE:87:0A:47:FE:58:EE:F6:C7:6B:EB:C6:0B:12:40:99

SHA256:

9A:11:40:25:19:7C:5B:B9:5D:94:E6:3D:55:CD:43:79:08:47:B6:46:B2:3C:DF:11:AD:A4:A0:0E:FF:15:FB:4

Alias name: buypassclass2rootca

SHA1: 49:0A:75:74:DE:87:0A:47:FE:58:EE:F6:C7:6B:EB:C6:0B:12:40:99

SHA256:

9A:11:40:25:19:7C:5B:B9:5D:94:E6:3D:55:CD:43:79:08:47:B6:46:B2:3C:DF:11:AD:A4:A0:0E:FF:15:FB:4

Alias name: buypassclass3ca

SHA1: DA:FA:F7:FA:66:84:EC:06:8F:14:50:BD:C7:C2:81:A5:BC:A9:64:57

SHA256:

ED:F7:EB:BC:A2:7A:2A:38:4D:38:7B:7D:40:10:C6:66:E2:ED:B4:84:3E:4C:29:B4:AE:1D:5B:93:32:E6:B2:4

Alias name: buypassclass3rootca

SHA1: DA:FA:F7:FA:66:84:EC:06:8F:14:50:BD:C7:C2:81:A5:BC:A9:64:57

SHA256:

ED:F7:EB:BC:A2:7A:2A:38:4D:38:7B:7D:40:10:C6:66:E2:ED:B4:84:3E:4C:29:B4:AE:1D:5B:93:32:E6:B2:4

Alias name: cadisigrootr2

SHA1: B5:61:EB:EA:A4:DE:E4:25:4B:69:1A:98:A5:57:47:C2:34:C7:D9:71

SHA256:

E2:3D:4A:03:6D:7B:70:E9:F5:95:B1:42:20:79:D2:B9:1E:DF:BB:1F:B6:51:A0:63:3E:AA:8A:9D:C5:F8:07:0

Alias name: camerfirmachambersca

SHA1: 78:6A:74:AC:76:AB:14:7F:9C:6A:30:50:BA:9E:A8:7E:FE:9A:CE:3C

SHA256:

06:3E:4A:FA:C4:91:DF:D3:32:F3:08:9B:85:42:E9:46:17:D8:93:D7:FE:94:4E:10:A7:93:7E:E2:9D:96:93:C

Alias name: camerfirmachamberscommerceca

SHA1: 6E:3A:55:A4:19:0C:19:5C:93:84:3C:C0:DB:72:2E:31:30:61:F0:B1

SHA256:

0C:25:8A:12:A5:67:4A:EF:25:F2:8B:A7:DC:FA:EC:EE:A3:48:E5:41:E6:F5:CC:4E:E6:3B:71:B3:61:60:6A:C

Alias name: camerfirmachambersignca

SHA1: 4A:BD:EE:EC:95:0D:35:9C:89:AE:C7:52:A1:2C:5B:29:F6:D6:AA:0C

SHA256:

13:63:35:43:93:34:A7:69:80:16:A0:D3:24:DE:72:28:4E:07:9D:7B:52:20:BB:8F:BD:74:78:16:EE:BE:BA:C

Alias name: certigna

SHA1: B1:2E:13:63:45:86:A4:6F:1A:B2:60:68:37:58:2D:C4:AC:FD:94:97

SHA256:
E3:B6:A2:DB:2E:D7:CE:48:84:2F:7A:C5:32:41:C7:B7:1D:54:14:4B:FB:40:C1:1F:3F:1D:0B:42:F5:EE:A1:2
Alias name: certignarootca
SHA1: 2D:0D:52:14:FF:9E:AD:99:24:01:74:20:47:6E:6C:85:27:27:F5:43
SHA256:
D4:8D:3D:23:EE:DB:50:A4:59:E5:51:97:60:1C:27:77:4B:9D:7B:18:C9:4D:5A:05:95:11:A1:02:50:B9:31:6
Alias name: certplusclass2primaryca
SHA1: 74:20:74:41:72:9C:DD:92:EC:79:31:D8:23:10:8D:C2:81:92:E2:BB
SHA256:
0F:99:3C:8A:EF:97:BA:AF:56:87:14:0E:D5:9A:D1:82:1B:B4:AF:AC:F0:AA:9A:58:B5:D5:7A:33:8A:3A:FB:C
Alias name: certplusclass3pprimaryca
SHA1: 21:6B:2A:29:E6:2A:00:CE:82:01:46:D8:24:41:41:B9:25:11:B2:79
SHA256:
CC:C8:94:89:37:1B:AD:11:1C:90:61:9B:EA:24:0A:2E:6D:AD:D9:9F:9F:6E:1D:4D:41:E5:8E:D6:DE:3D:02:8
Alias name: certsignrootca
SHA1: FA:B7:EE:36:97:26:62:FB:2D:B0:2A:F6:BF:03:FD:E8:7C:4B:2F:9B
SHA256:
EA:A9:62:C4:FA:4A:6B:AF:EB:E4:15:19:6D:35:1C:CD:88:8D:4F:53:F3:FA:8A:E6:D7:C4:66:A9:4E:60:42:B
Alias name: certsignrootcag2
SHA1: 26:F9:93:B4:ED:3D:28:27:B0:B9:4B:A7:E9:15:1D:A3:8D:92:E5:32
SHA256:
65:7C:FE:2F:A7:3F:AA:38:46:25:71:F3:32:A2:36:3A:46:FC:E7:02:09:51:71:07:02:CD:FB:B6:EE:DA:33:0
Alias name: certum2
SHA1: D3:DD:48:3E:2B:BF:4C:05:E8:AF:10:F5:FA:76:26:CF:D3:DC:30:92
SHA256:
B6:76:F2:ED:DA:E8:77:5C:D3:6C:B0:F6:3C:D1:D4:60:39:61:F4:9E:62:65:BA:01:3A:2F:03:07:B6:D0:B8:0
Alias name: certumca
SHA1: 62:52:DC:40:F7:11:43:A2:2F:DE:9E:F7:34:8E:06:42:51:B1:81:18
SHA256:
D8:E0:FE:BC:1D:B2:E3:8D:00:94:0F:37:D2:7D:41:34:4D:99:3E:73:4B:99:D5:65:6D:97:78:D4:D8:14:36:2
Alias name: certumtrustednetworkca
SHA1: 07:E0:32:E0:20:B7:2C:3F:19:2F:06:28:A2:59:3A:19:A7:0F:06:9E
SHA256:
5C:58:46:8D:55:F5:8E:49:7E:74:39:82:D2:B5:00:10:B6:D1:65:37:4A:CF:83:A7:D4:A3:2D:B7:68:C4:40:8
Alias name: certumtrustednetworkca2
SHA1: D3:DD:48:3E:2B:BF:4C:05:E8:AF:10:F5:FA:76:26:CF:D3:DC:30:92
SHA256:
B6:76:F2:ED:DA:E8:77:5C:D3:6C:B0:F6:3C:D1:D4:60:39:61:F4:9E:62:65:BA:01:3A:2F:03:07:B6:D0:B8:0
Alias name: cfcaevroot
SHA1: E2:B8:29:4B:55:84:AB:6B:58:C2:90:46:6C:AC:3F:B8:39:8F:84:83
SHA256:
5C:C3:D7:8E:4E:1D:5E:45:54:7A:04:E6:87:3E:64:F9:0C:F9:53:6D:1C:CC:2E:F8:00:F3:55:C4:C5:FD:70:F
Alias name: chambersofcommerceroot2008
SHA1: 78:6A:74:AC:76:AB:14:7F:9C:6A:30:50:BA:9E:A8:7E:FE:9A:CE:3C

SHA256:

06:3E:4A:FA:C4:91:DF:D3:32:F3:08:9B:85:42:E9:46:17:D8:93:D7:FE:94:4E:10:A7:93:7E:E2:9D:96:93:0

Alias name: chunghwaepkirootca

SHA1: 67:65:0D:F1:7E:8E:7E:5B:82:40:A4:F4:56:4B:CF:E2:3D:69:C6:F0

SHA256:

C0:A6:F4:DC:63:A2:4B:FD:CF:54:EF:2A:6A:08:2A:0A:72:DE:35:80:3E:2F:F5:FF:52:7A:E5:D8:72:06:DF:D

Alias name: cia-crt-g3-01-ca

SHA1: 2B:EE:2C:BA:A3:1D:B5:FE:60:40:41:95:08:ED:46:82:39:4D:ED:E2

SHA256:

20:48:AD:4C:EC:90:7F:FA:4A:15:D4:CE:45:E3:C8:E4:2C:EA:78:33:DC:C7:D3:40:48:FC:60:47:27:42:99:E

Alias name: cia-crt-g3-02-ca

SHA1: 96:4A:BB:A7:BD:DA:FC:97:34:C0:0A:2D:F0:05:98:F7:E6:C6:6F:09

SHA256:

93:F1:72:FB:BA:43:31:5C:06:EE:0F:9F:04:89:B8:F6:88:BC:75:15:3C:BE:B4:80:AC:A7:14:3A:F6:FC:4A:C

Alias name: comodo-ca

SHA1: AF:E5:D2:44:A8:D1:19:42:30:FF:47:9F:E2:F8:97:BB:CD:7A:8C:B4

SHA256:

52:F0:E1:C4:E5:8E:C6:29:29:1B:60:31:7F:07:46:71:B8:5D:7E:A8:0D:5B:07:27:34:63:53:4B:32:B4:02:3

Alias name: comodoaaaca

SHA1: D1:EB:23:A4:6D:17:D6:8F:D9:25:64:C2:F1:F1:60:17:64:D8:E3:49

SHA256:

D7:A7:A0:FB:5D:7E:27:31:D7:71:E9:48:4E:BC:DE:F7:1D:5F:0C:3E:0A:29:48:78:2B:C8:3E:E0:EA:69:9E:F

Alias name: comodoaaaservicesroot

SHA1: D1:EB:23:A4:6D:17:D6:8F:D9:25:64:C2:F1:F1:60:17:64:D8:E3:49

SHA256:

D7:A7:A0:FB:5D:7E:27:31:D7:71:E9:48:4E:BC:DE:F7:1D:5F:0C:3E:0A:29:48:78:2B:C8:3E:E0:EA:69:9E:F

Alias name: comodocertificationauthority

SHA1: 66:31:BF:9E:F7:4F:9E:B6:C9:D5:A6:0C:BA:6A:BE:D1:F7:BD:EF:7B

SHA256:

0C:2C:D6:3D:F7:80:6F:A3:99:ED:E8:09:11:6B:57:5B:F8:79:89:F0:65:18:F9:80:8C:86:05:03:17:8B:AF:6

Alias name: comodoecccertificationauthority

SHA1: 9F:74:4E:9F:2B:4D:BA:EC:0F:31:2C:50:B6:56:3B:8E:2D:93:C3:11

SHA256:

17:93:92:7A:06:14:54:97:89:AD:CE:2F:8F:34:F7:F0:B6:6D:0F:3A:E3:A3:B8:4D:21:EC:15:DB:BA:4F:AD:C

Alias name: comodorsacertificationauthority

SHA1: AF:E5:D2:44:A8:D1:19:42:30:FF:47:9F:E2:F8:97:BB:CD:7A:8C:B4

SHA256:

52:F0:E1:C4:E5:8E:C6:29:29:1B:60:31:7F:07:46:71:B8:5D:7E:A8:0D:5B:07:27:34:63:53:4B:32:B4:02:3

Alias name: cybertrustglobalroot

SHA1: 5F:43:E5:B1:BF:F8:78:8C:AC:1C:C7:CA:4A:9A:C6:22:2B:CC:34:C6

SHA256:

96:0A:DF:00:63:E9:63:56:75:0C:29:65:DD:0A:08:67:DA:0B:9C:BD:6E:77:71:4A:EA:FB:23:49:AB:39:3D:A

Alias name: deprecateditsecca

SHA1: 12:12:0B:03:0E:15:14:54:F4:DD:B3:F5:DE:13:6E:83:5A:29:72:9D

SHA256:

9A:59:DA:86:24:1A:FD:BA:A3:39:FA:9C:FD:21:6A:0B:06:69:4D:E3:7E:37:52:6B:BE:63:C8:BC:83:74:2E:0

Alias name: deutschetelkomrootca2

SHA1: 85:A4:08:C0:9C:19:3E:5D:51:58:7D:CD:D6:13:30:FD:8C:DE:37:BF

SHA256:

B6:19:1A:50:D0:C3:97:7F:7D:A9:9B:CD:AA:C8:6A:22:7D:AE:B9:67:9E:C7:0B:A3:B0:C9:D9:22:71:C1:70:D

Alias name: digicertassuredidrootca

SHA1: 05:63:B8:63:0D:62:D7:5A:BB:C8:AB:1E:4B:DF:B5:A8:99:B2:4D:43

SHA256:

3E:90:99:B5:01:5E:8F:48:6C:00:BC:EA:9D:11:1E:E7:21:FA:BA:35:5A:89:BC:F1:DF:69:56:1E:3D:C6:32:5

Alias name: digicertassuredidrootg2

SHA1: A1:4B:48:D9:43:EE:0A:0E:40:90:4F:3C:E0:A4:C0:91:93:51:5D:3F

SHA256:

7D:05:EB:B6:82:33:9F:8C:94:51:EE:09:4E:EB:FE:FA:79:53:A1:14:ED:B2:F4:49:49:45:2F:AB:7D:2F:C1:8

Alias name: digicertassuredidrootg3

SHA1: F5:17:A2:4F:9A:48:C6:C9:F8:A2:00:26:9F:DC:0F:48:2C:AB:30:89

SHA256:

7E:37:CB:8B:4C:47:09:0C:AB:36:55:1B:A6:F4:5D:B8:40:68:0F:BA:16:6A:95:2D:B1:00:71:7F:43:05:3F:C

Alias name: digicertglobalrootca

SHA1: A8:98:5D:3A:65:E5:E5:C4:B2:D7:D6:6D:40:C6:DD:2F:B1:9C:54:36

SHA256:

43:48:A0:E9:44:4C:78:CB:26:5E:05:8D:5E:89:44:B4:D8:4F:96:62:BD:26:DB:25:7F:89:34:A4:43:C7:01:6

Alias name: digicertglobalrootg2

SHA1: DF:3C:24:F9:BF:D6:66:76:1B:26:80:73:FE:06:D1:CC:8D:4F:82:A4

SHA256:

CB:3C:CB:B7:60:31:E5:E0:13:8F:8D:D3:9A:23:F9:DE:47:FF:C3:5E:43:C1:14:4C:EA:27:D4:6A:5A:B1:CB:5

Alias name: digicertglobalrootg3

SHA1: 7E:04:DE:89:6A:3E:66:6D:00:E6:87:D3:3F:FA:D9:3B:E8:3D:34:9E

SHA256:

31:AD:66:48:F8:10:41:38:C7:38:F3:9E:A4:32:01:33:39:3E:3A:18:CC:02:29:6E:F9:7C:2A:C9:EF:67:31:D

Alias name: digicerthighassuranceevrootca

SHA1: 5F:B7:EE:06:33:E2:59:DB:AD:0C:4C:9A:E6:D3:8F:1A:61:C7:DC:25

SHA256:

74:31:E5:F4:C3:C1:CE:46:90:77:4F:0B:61:E0:54:40:88:3B:A9:A0:1E:D0:0B:A6:AB:D7:80:6E:D3:B1:18:C

Alias name: digicerttrustedrootg4

SHA1: DD:FB:16:CD:49:31:C9:73:A2:03:7D:3F:C8:3A:4D:7D:77:5D:05:E4

SHA256:

55:2F:7B:DC:F1:A7:AF:9E:6C:E6:72:01:7F:4F:12:AB:F7:72:40:C7:8E:76:1A:C2:03:D1:D9:D2:0A:C8:99:8

Alias name: dstrootcax3

SHA1: DA:C9:02:4F:54:D8:F6:DF:94:93:5F:B1:73:26:38:CA:6A:D7:7C:13

SHA256:

06:87:26:03:31:A7:24:03:D9:09:F1:05:E6:9B:CF:0D:32:E1:BD:24:93:FF:C6:D9:20:6D:11:BC:D6:77:07:3

Alias name: dtrustrootclass3ca22009

SHA1: 58:E8:AB:B0:36:15:33:FB:80:F7:9B:1B:6D:29:D3:FF:8D:5F:00:F0

SHA256:

49:E7:A4:42:AC:F0:EA:62:87:05:00:54:B5:25:64:B6:50:E4:F4:9E:42:E3:48:D6:AA:38:E0:39:E9:57:B1:C

Alias name: dtrustrootclass3ca2ev2009

SHA1: 96:C9:1B:0B:95:B4:10:98:42:FA:D0:D8:22:79:FE:60:FA:B9:16:83

SHA256:

EE:C5:49:6B:98:8C:E9:86:25:B9:34:09:2E:EC:29:08:BE:D0:B0:F3:16:C2:D4:73:0C:84:EA:F1:F3:D3:48:8

Alias name: ecacc

SHA1: 28:90:3A:63:5B:52:80:FA:E6:77:4C:0B:6D:A7:D6:BA:A6:4A:F2:E8

SHA256:

88:49:7F:01:60:2F:31:54:24:6A:E2:8C:4D:5A:EF:10:F1:D8:7E:BB:76:62:6F:4A:E0:B7:F9:5B:A7:96:87:9

Alias name: emsigneccrootcac3

SHA1: B6:AF:43:C2:9B:81:53:7D:F6:EF:6B:C3:1F:1F:60:15:0C:EE:48:66

SHA256:

BC:4D:80:9B:15:18:9D:78:DB:3E:1D:8C:F4:F9:72:6A:79:5D:A1:64:3C:A5:F1:35:8E:1D:DB:0E:DC:0D:7E:B

Alias name: emsigneccrootcag3

SHA1: 30:43:FA:4F:F2:57:DC:A0:C3:80:EE:2E:58:EA:78:B2:3F:E6:BB:C1

SHA256:

86:A1:EC:BA:08:9C:4A:8D:3B:BE:27:34:C6:12:BA:34:1D:81:3E:04:3C:F9:E8:A8:62:CD:5C:57:A3:6B:BE:6

Alias name: emsignrootcac1

SHA1: E7:2E:F1:DF:FC:B2:09:28:CF:5D:D4:D5:67:37:B1:51:CB:86:4F:01

SHA256:

12:56:09:AA:30:1D:A0:A2:49:B9:7A:82:39:CB:6A:34:21:6F:44:DC:AC:9F:39:54:B1:42:92:F2:E8:C8:60:8

Alias name: emsignrootcag1

SHA1: 8A:C7:AD:8F:73:AC:4E:C1:B5:75:4D:A5:40:F4:FC:CF:7C:B5:8E:8C

SHA256:

40:F6:AF:03:46:A9:9A:A1:CD:1D:55:5A:4E:9C:CE:62:C7:F9:63:46:03:EE:40:66:15:83:3D:C8:C8:D0:03:6

Alias name: entrust2048ca

SHA1: 50:30:06:09:1D:97:D4:F5:AE:39:F7:CB:E7:92:7D:7D:65:2D:34:31

SHA256:

6D:C4:71:72:E0:1C:BC:B0:BF:62:58:0D:89:5F:E2:B8:AC:9A:D4:F8:73:80:1E:0C:10:B9:C8:37:D2:1E:B1:7

Alias name: entrustevca

SHA1: B3:1E:B1:B7:40:E3:6C:84:02:DA:DC:37:D4:4D:F5:D4:67:49:52:F9

SHA256:

73:C1:76:43:4F:1B:C6:D5:AD:F4:5B:0E:76:E7:27:28:7C:8D:E5:76:16:C1:E6:E6:14:1A:2B:2C:BC:7D:8E:4

Alias name: entrustnetpremium2048secureserverca

SHA1: 50:30:06:09:1D:97:D4:F5:AE:39:F7:CB:E7:92:7D:7D:65:2D:34:31

SHA256:

6D:C4:71:72:E0:1C:BC:B0:BF:62:58:0D:89:5F:E2:B8:AC:9A:D4:F8:73:80:1E:0C:10:B9:C8:37:D2:1E:B1:7

Alias name: entrustrootcag2

SHA1: 8C:F4:27:FD:79:0C:3A:D1:66:06:8D:E8:1E:57:EF:BB:93:22:72:D4

SHA256:

43:DF:57:74:B0:3E:7F:EF:5F:E4:0D:93:1A:7B:ED:F1:BB:2E:6B:42:73:8C:4E:6D:38:41:10:3D:3A:A7:F3:3

Alias name: entrustrootcertificationauthority

SHA1: B3:1E:B1:B7:40:E3:6C:84:02:DA:DC:37:D4:4D:F5:D4:67:49:52:F9

SHA256:

73:C1:76:43:4F:1B:C6:D5:AD:F4:5B:0E:76:E7:27:28:7C:8D:E5:76:16:C1:E6:E6:14:1A:2B:2C:BC:7D:8E:4

Alias name: entrustrootcertificationauthorityec1

SHA1: 20:D8:06:40:DF:9B:25:F5:12:25:3A:11:EA:F7:59:8A:EB:14:B5:47

SHA256:

02:ED:0E:B2:8C:14:DA:45:16:5C:56:67:91:70:0D:64:51:D7:FB:56:F0:B2:AB:1D:3B:8E:B0:70:E5:6E:DF:F

Alias name: entrustrootcertificationauthorityg2

SHA1: 8C:F4:27:FD:79:0C:3A:D1:66:06:8D:E8:1E:57:EF:BB:93:22:72:D4

SHA256:

43:DF:57:74:B0:3E:7F:EF:5F:E4:0D:93:1A:7B:ED:F1:BB:2E:6B:42:73:8C:4E:6D:38:41:10:3D:3A:A7:F3:3

Alias name: entrustrootcertificationauthorityg4

SHA1: 14:88:4E:86:26:37:B0:26:AF:59:62:5C:40:77:EC:35:29:BA:96:01

SHA256:

DB:35:17:D1:F6:73:2A:2D:5A:B9:7C:53:3E:C7:07:79:EE:32:70:A6:2F:B4:AC:42:38:37:24:60:E6:F0:1E:8

Alias name: epkirootcertificationauthority

SHA1: 67:65:0D:F1:7E:8E:7E:5B:82:40:A4:F4:56:4B:CF:E2:3D:69:C6:F0

SHA256:

C0:A6:F4:DC:63:A2:4B:FD:CF:54:EF:2A:6A:08:2A:0A:72:DE:35:80:3E:2F:F5:FF:52:7A:E5:D8:72:06:DF:D

Alias name: equifaxsecurebusinessca1

SHA1: AE:E6:3D:70:E3:76:FB:C7:3A:EB:B0:A1:C1:D4:C4:7A:A7:40:B3:F4

SHA256:

2E:3A:2B:B5:11:25:05:83:6C:A8:96:8B:E2:CB:37:27:CE:9B:56:84:5C:6E:E9:8E:91:85:10:4A:FB:9A:F5:9

Alias name: equifaxsecureglobalebusinessca1

SHA1: 3A:74:CB:7A:47:DB:70:DE:89:1F:24:35:98:64:B8:2D:82:BD:1A:36

SHA256:

86:AB:5A:65:71:D3:32:9A:BC:D2:E4:E6:37:66:8B:A8:9C:73:1E:C2:93:B6:CB:A6:0F:71:63:40:A0:91:CE:A

Alias name: eszignorootca2017

SHA1: 89:D4:83:03:4F:9E:9A:48:80:5F:72:37:D4:A9:A6:EF:CB:7C:1F:D1

SHA256:

BE:B0:0B:30:83:9B:9B:C3:2C:32:E4:44:79:05:95:06:41:F2:64:21:B1:5E:D0:89:19:8B:51:8A:E2:EA:1B:9

Alias name: etugracertificationauthority

SHA1: 51:C6:E7:08:49:06:6E:F3:92:D4:5C:A0:0D:6D:A3:62:8F:C3:52:39

SHA256:

B0:BF:D5:2B:B0:D7:D9:BD:92:BF:5D:4D:C1:3D:A2:55:C0:2C:54:2F:37:83:65:EA:89:39:11:F5:5E:55:F2:3

Alias name: gd-class2-root.pem

SHA1: 27:96:BA:E6:3F:18:01:E2:77:26:1B:A0:D7:77:70:02:8F:20:EE:E4

SHA256:

C3:84:6B:F2:4B:9E:93:CA:64:27:4C:0E:C6:7C:1E:CC:5E:02:4F:FC:AC:D2:D7:40:19:35:0E:81:FE:54:6A:E

Alias name: gd_bundle-g2.pem

SHA1: 27:AC:93:69:FA:F2:52:07:BB:26:27:CE:FA:CC:BE:4E:F9:C3:19:B8

SHA256:

97:3A:41:27:6F:FD:01:E0:27:A2:AA:D4:9E:34:C3:78:46:D3:E9:76:FF:6A:62:0B:67:12:E3:38:32:04:1A:A

Alias name: gdcatrustauthr5root

SHA1: 0F:36:38:5B:81:1A:25:C3:9B:31:4E:83:CA:E9:34:66:70:CC:74:B4

SHA256:

BF:FF:F0:44:33:48:7D:6A:8A:A6:0C:1A:29:76:7A:9F:C2:BB:B0:5E:42:0F:71:3A:13:B9:92:89:1D:38:9

Alias name: gdroot-g2.pem

SHA1: 47:BE:AB:C9:22:EA:E8:0E:78:78:34:62:A7:9F:45:C2:54:FD:E6:8B

SHA256:

45:14:0B:32:47:EB:9C:C8:C5:B4:F0:D7:B5:30:91:F7:32:92:08:9E:6E:5A:63:E2:74:9D:D3:AC:A9:19:8E:D

Alias name: geotrustglobalca

SHA1: DE:28:F4:A4:FF:E5:B9:2F:A3:C5:03:D1:A3:49:A7:F9:96:2A:82:12

SHA256:

FF:85:6A:2D:25:1D:CD:88:D3:66:56:F4:50:12:67:98:CF:AB:AA:DE:40:79:9C:72:2D:E4:D2:B5:DB:36:A7:3

Alias name: geotrustprimaryca

SHA1: 32:3C:11:8E:1B:F7:B8:B6:52:54:E2:E2:10:0D:D6:02:90:37:F0:96

SHA256:

37:D5:10:06:C5:12:EA:AB:62:64:21:F1:EC:8C:92:01:3F:C5:F8:2A:E9:8E:E5:33:EB:46:19:B8:DE:B4:D0:6

Alias name: geotrustprimarycag2

SHA1: 8D:17:84:D5:37:F3:03:7D:EC:70:FE:57:8B:51:9A:99:E6:10:D7:B0

SHA256:

5E:DB:7A:C4:3B:82:A0:6A:87:61:E8:D7:BE:49:79:EB:F2:61:1F:7D:D7:9B:F9:1C:1C:6B:56:6A:21:9E:D7:6

Alias name: geotrustprimarycag3

SHA1: 03:9E:ED:B8:0B:E7:A0:3C:69:53:89:3B:20:D2:D9:32:3A:4C:2A:FD

SHA256:

B4:78:B8:12:25:0D:F8:78:63:5C:2A:A7:EC:7D:15:5E:AA:62:5E:E8:29:16:E2:CD:29:43:61:88:6C:D1:FB:D

Alias name: geotrustprimarycertificationauthority

SHA1: 32:3C:11:8E:1B:F7:B8:B6:52:54:E2:E2:10:0D:D6:02:90:37:F0:96

SHA256:

37:D5:10:06:C5:12:EA:AB:62:64:21:F1:EC:8C:92:01:3F:C5:F8:2A:E9:8E:E5:33:EB:46:19:B8:DE:B4:D0:6

Alias name: geotrustprimarycertificationauthorityg2

SHA1: 8D:17:84:D5:37:F3:03:7D:EC:70:FE:57:8B:51:9A:99:E6:10:D7:B0

SHA256:

5E:DB:7A:C4:3B:82:A0:6A:87:61:E8:D7:BE:49:79:EB:F2:61:1F:7D:D7:9B:F9:1C:1C:6B:56:6A:21:9E:D7:6

Alias name: geotrustprimarycertificationauthorityg3

SHA1: 03:9E:ED:B8:0B:E7:A0:3C:69:53:89:3B:20:D2:D9:32:3A:4C:2A:FD

SHA256:

B4:78:B8:12:25:0D:F8:78:63:5C:2A:A7:EC:7D:15:5E:AA:62:5E:E8:29:16:E2:CD:29:43:61:88:6C:D1:FB:D

Alias name: geotrustuniversalca

SHA1: E6:21:F3:35:43:79:05:9A:4B:68:30:9D:8A:2F:74:22:15:87:EC:79

SHA256:

A0:45:9B:9F:63:B2:25:59:F5:FA:5D:4C:6D:B3:F9:F7:2F:F1:93:42:03:35:78:F0:73:BF:1D:1B:46:CB:B9:1

Alias name: geotrustuniversalca2

SHA1: 37:9A:19:7B:41:85:45:35:0C:A6:03:69:F3:3C:2E:AF:47:4F:20:79

SHA256:

A0:23:4F:3B:C8:52:7C:A5:62:8E:EC:81:AD:5D:69:89:5D:A5:68:0D:C9:1D:1C:B8:47:7F:33:F8:78:B9:5B:0

Alias name: globalchambersignroot2008

SHA1: 4A:BD:EE:EC:95:0D:35:9C:89:AE:C7:52:A1:2C:5B:29:F6:D6:AA:0C

SHA256:
13:63:35:43:93:34:A7:69:80:16:A0:D3:24:DE:72:28:4E:07:9D:7B:52:20:BB:8F:BD:74:78:16:EE:BE:BA:C
Alias name: globalsignca
SHA1: B1:BC:96:8B:D4:F4:9D:62:2A:A8:9A:81:F2:15:01:52:A4:1D:82:9C
SHA256:
EB:D4:10:40:E4:BB:3E:C7:42:C9:E3:81:D3:1E:F2:A4:1A:48:B6:68:5C:96:E7:CE:F3:C1:DF:6C:D4:33:1C:9
Alias name: globalsigneccrootcar4
SHA1: 69:69:56:2E:40:80:F4:24:A1:E7:19:9F:14:BA:F3:EE:58:AB:6A:BB
SHA256:
BE:C9:49:11:C2:95:56:76:DB:6C:0A:55:09:86:D7:6E:3B:A0:05:66:7C:44:2C:97:62:B4:FB:B7:73:DE:22:8
Alias name: globalsigneccrootcar5
SHA1: 1F:24:C6:30:CD:A4:18:EF:20:69:FF:AD:4F:DD:5F:46:3A:1B:69:AA
SHA256:
17:9F:BC:14:8A:3D:D0:0F:D2:4E:A1:34:58:CC:43:BF:A7:F5:9C:81:82:D7:83:A5:13:F6:EB:EC:10:0C:89:2
Alias name: globalsignr2ca
SHA1: 75:E0:AB:B6:13:85:12:27:1C:04:F8:5F:DD:DE:38:E4:B7:24:2E:FE
SHA256:
CA:42:DD:41:74:5F:D0:B8:1E:B9:02:36:2C:F9:D8:BF:71:9D:A1:BD:1B:1E:FC:94:6F:5B:4C:99:F4:2C:1B:9
Alias name: globalsignr3ca
SHA1: D6:9B:56:11:48:F0:1C:77:C5:45:78:C1:09:26:DF:5B:85:69:76:AD
SHA256:
CB:B5:22:D7:B7:F1:27:AD:6A:01:13:86:5B:DF:1C:D4:10:2E:7D:07:59:AF:63:5A:7C:F4:72:0D:C9:63:C5:3
Alias name: globalsignrootca
SHA1: B1:BC:96:8B:D4:F4:9D:62:2A:A8:9A:81:F2:15:01:52:A4:1D:82:9C
SHA256:
EB:D4:10:40:E4:BB:3E:C7:42:C9:E3:81:D3:1E:F2:A4:1A:48:B6:68:5C:96:E7:CE:F3:C1:DF:6C:D4:33:1C:9
Alias name: globalsignrootcar2
SHA1: 75:E0:AB:B6:13:85:12:27:1C:04:F8:5F:DD:DE:38:E4:B7:24:2E:FE
SHA256:
CA:42:DD:41:74:5F:D0:B8:1E:B9:02:36:2C:F9:D8:BF:71:9D:A1:BD:1B:1E:FC:94:6F:5B:4C:99:F4:2C:1B:9
Alias name: globalsignrootcar3
SHA1: D6:9B:56:11:48:F0:1C:77:C5:45:78:C1:09:26:DF:5B:85:69:76:AD
SHA256:
CB:B5:22:D7:B7:F1:27:AD:6A:01:13:86:5B:DF:1C:D4:10:2E:7D:07:59:AF:63:5A:7C:F4:72:0D:C9:63:C5:3
Alias name: globalsignrootcar6
SHA1: 80:94:64:0E:B5:A7:A1:CA:11:9C:1F:DD:D5:9F:81:02:63:A7:FB:D1
SHA256:
2C:AB:EA:FE:37:D0:6C:A2:2A:BA:73:91:C0:03:3D:25:98:29:52:C4:53:64:73:49:76:3A:3A:B5:AD:6C:CF:6
Alias name: godaddyclass2ca
SHA1: 27:96:BA:E6:3F:18:01:E2:77:26:1B:A0:D7:77:70:02:8F:20:EE:E4
SHA256:
C3:84:6B:F2:4B:9E:93:CA:64:27:4C:0E:C6:7C:1E:CC:5E:02:4F:FC:AC:D2:D7:40:19:35:0E:81:FE:54:6A:E
Alias name: godaddyrootcertificateauthorityg2
SHA1: 47:BE:AB:C9:22:EA:E8:0E:78:78:34:62:A7:9F:45:C2:54:FD:E6:8B

SHA256:

45:14:0B:32:47:EB:9C:C8:C5:B4:F0:D7:B5:30:91:F7:32:92:08:9E:6E:5A:63:E2:74:9D:D3:AC:A9:19:8E:D

Alias name: godaddyrootg2ca

SHA1: 47:BE:AB:C9:22:EA:E8:0E:78:78:34:62:A7:9F:45:C2:54:FD:E6:8B

SHA256:

45:14:0B:32:47:EB:9C:C8:C5:B4:F0:D7:B5:30:91:F7:32:92:08:9E:6E:5A:63:E2:74:9D:D3:AC:A9:19:8E:D

Alias name: gtsrootr1

SHA1: E1:C9:50:E6:EF:22:F8:4C:56:45:72:8B:92:20:60:D7:D5:A7:A3:E8

SHA256:

2A:57:54:71:E3:13:40:BC:21:58:1C:BD:2C:F1:3E:15:84:63:20:3E:CE:94:BC:F9:D3:CC:19:6B:F0:9A:54:7

Alias name: gtsrootr2

SHA1: D2:73:96:2A:2A:5E:39:9F:73:3F:E1:C7:1E:64:3F:03:38:34:FC:4D

SHA256:

C4:5D:7B:B0:8E:6D:67:E6:2E:42:35:11:0B:56:4E:5F:78:FD:92:EF:05:8C:84:0A:EA:4E:64:55:D7:58:5C:6

Alias name: gtsrootr3

SHA1: 30:D4:24:6F:07:FF:DB:91:89:8A:0B:E9:49:66:11:EB:8C:5E:46:E5

SHA256:

15:D5:B8:77:46:19:EA:7D:54:CE:1C:A6:D0:B0:C4:03:E0:37:A9:17:F1:31:E8:A0:4E:1E:6B:7A:71:BA:BC:E

Alias name: gtsrootr4

SHA1: 2A:1D:60:27:D9:4A:B1:0A:1C:4D:91:5C:CD:33:A0:CB:3E:2D:54:CB

SHA256:

71:CC:A5:39:1F:9E:79:4B:04:80:25:30:B3:63:E1:21:DA:8A:30:43:BB:26:66:2F:EA:4D:CA:7F:C9:51:A4:B

Alias name: hellenicacademicandresearchinstitutionsccrootca2015

SHA1: 9F:F1:71:8D:92:D5:9A:F3:7D:74:97:B4:BC:6F:84:68:0B:BA:B6:66

SHA256:

44:B5:45:AA:8A:25:E6:5A:73:CA:15:DC:27:FC:36:D2:4C:1C:B9:95:3A:06:65:39:B1:15:82:DC:48:7B:48:3

Alias name: hellenicacademicandresearchinstitutionsrootca2011

SHA1: FE:45:65:9B:79:03:5B:98:A1:61:B5:51:2E:AC:DA:58:09:48:22:4D

SHA256:

BC:10:4F:15:A4:8B:E7:09:DC:A5:42:A7:E1:D4:B9:DF:6F:05:45:27:E8:02:EA:A9:2D:59:54:44:25:8A:FE:7

Alias name: hellenicacademicandresearchinstitutionsrootca2015

SHA1: 01:0C:06:95:A6:98:19:14:FF:BF:5F:C6:B0:B6:95:EA:29:E9:12:A6

SHA256:

A0:40:92:9A:02:CE:53:B4:AC:F4:F2:FF:C6:98:1C:E4:49:6F:75:5E:6D:45:FE:0B:2A:69:2B:CD:52:52:3F:3

Alias name: hongkongpostrootca1

SHA1: D6:DA:A8:20:8D:09:D2:15:4D:24:B5:2F:CB:34:6E:B2:58:B2:8A:58

SHA256:

F9:E6:7D:33:6C:51:00:2A:C0:54:C6:32:02:2D:66:DD:A2:E7:E3:FF:F1:0A:D0:61:ED:31:D8:BB:B4:10:CF:B

Alias name: hongkongpostrootca3

SHA1: 58:A2:D0:EC:20:52:81:5B:C1:F3:F8:64:02:24:4E:C2:8E:02:4B:02

SHA256:

5A:2F:C0:3F:0C:83:B0:90:BB:FA:40:60:4B:09:88:44:6C:76:36:18:3D:F9:84:6E:17:10:1A:44:7F:B8:EF:D

Alias name: identrustcommercialrootca1

SHA1: DF:71:7E:AA:4A:D9:4E:C9:55:84:99:60:2D:48:DE:5F:BC:F0:3A:25

SHA256:
5D:56:49:9B:E4:D2:E0:8B:CF:CA:D0:8A:3E:38:72:3D:50:50:3B:DE:70:69:48:E4:2F:55:60:30:19:E5:28:A
Alias name: identrustpublicsectorrootca1
SHA1: BA:29:41:60:77:98:3F:F4:F3:EF:F2:31:05:3B:2E:EA:6D:4D:45:FD
SHA256:
30:D0:89:5A:9A:44:8A:26:20:91:63:55:22:D1:F5:20:10:B5:86:7A:CA:E1:2C:78:EF:95:8F:D4:F4:38:9F:2
Alias name: isrgrootx1
SHA1: CA:BD:2A:79:A1:07:6A:31:F2:1D:25:36:35:CB:03:9D:43:29:A5:E8
SHA256:
96:BC:EC:06:26:49:76:F3:74:60:77:9A:CF:28:C5:A7:CF:E8:A3:C0:AA:E1:1A:8F:FC:EE:05:C0:BD:DF:08:C
Alias name: izenpecom
SHA1: 2F:78:3D:25:52:18:A7:4A:65:39:71:B5:2C:A2:9C:45:15:6F:E9:19
SHA256:
25:30:CC:8E:98:32:15:02:BA:D9:6F:9B:1F:BA:1B:09:9E:2D:29:9E:0F:45:48:BB:91:4F:36:3B:C0:D4:53:1
Alias name: keynectisrootca
SHA1: 9C:61:5C:4D:4D:85:10:3A:53:26:C2:4D:BA:EA:E4:A2:D2:D5:CC:97
SHA256:
42:10:F1:99:49:9A:9A:C3:3C:8D:E0:2B:A6:DB:AA:14:40:8B:DD:8A:6E:32:46:89:C1:92:2D:06:97:15:A3:3
Alias name: microseceszignorootca2009
SHA1: 89:DF:74:FE:5C:F4:0F:4A:80:F9:E3:37:7D:54:DA:91:E1:01:31:8E
SHA256:
3C:5F:81:FE:A5:FA:B8:2C:64:BF:A2:EA:EC:AF:CD:E8:E0:77:FC:86:20:A7:CA:E5:37:16:3D:F3:6E:DB:F3:7
Alias name: mozillacert0.pem
SHA1: 97:81:79:50:D8:1C:96:70:CC:34:D8:09:CF:79:44:31:36:7E:F4:74
SHA256:
A5:31:25:18:8D:21:10:AA:96:4B:02:C7:B7:C6:DA:32:03:17:08:94:E5:FB:71:FF:FB:66:67:D5:E6:81:0A:3
Alias name: mozillacert1.pem
SHA1: 23:E5:94:94:51:95:F2:41:48:03:B4:D5:64:D2:A3:A3:F5:D8:8B:8C
SHA256:
B4:41:0B:73:E2:E6:EA:CA:47:FB:C4:2F:8F:A4:01:8A:F4:38:1D:C5:4C:FA:A8:44:50:46:1E:ED:09:45:4D:E
Alias name: mozillacert10.pem
SHA1: 5F:3A:FC:0A:8B:64:F6:86:67:34:74:DF:7E:A9:A2:FE:F9:FA:7A:51
SHA256:
21:DB:20:12:36:60:BB:2E:D4:18:20:5D:A1:1E:E7:A8:5A:65:E2:BC:6E:55:B5:AF:7E:78:99:C8:A2:66:D9:2
Alias name: mozillacert100.pem
SHA1: 58:E8:AB:B0:36:15:33:FB:80:F7:9B:1B:6D:29:D3:FF:8D:5F:00:F0
SHA256:
49:E7:A4:42:AC:F0:EA:62:87:05:00:54:B5:25:64:B6:50:E4:F4:9E:42:E3:48:D6:AA:38:E0:39:E9:57:B1:C
Alias name: mozillacert101.pem
SHA1: 99:A6:9B:E6:1A:FE:88:6B:4D:2B:82:00:7C:B8:54:FC:31:7E:15:39
SHA256:
62:F2:40:27:8C:56:4C:4D:D8:BF:7D:9D:4F:6F:36:6E:A8:94:D2:2F:5F:34:D9:89:A9:83:AC:EC:2F:FF:ED:5
Alias name: mozillacert102.pem
SHA1: 96:C9:1B:0B:95:B4:10:98:42:FA:D0:D8:22:79:FE:60:FA:B9:16:83

SHA256:
EE:C5:49:6B:98:8C:E9:86:25:B9:34:09:2E:EC:29:08:BE:D0:B0:F3:16:C2:D4:73:0C:84:EA:F1:F3:D3:48:8
Alias name: mozillacert103.pem
SHA1: 70:C1:8D:74:B4:28:81:0A:E4:FD:A5:75:D7:01:9F:99:B0:3D:50:74
SHA256:
3C:FC:3C:14:D1:F6:84:FF:17:E3:8C:43:CA:44:0C:00:B9:67:EC:93:3E:8B:FE:06:4C:A1:D7:2C:90:F2:AD:B
Alias name: mozillacert104.pem
SHA1: 4F:99:AA:93:FB:2B:D1:37:26:A1:99:4A:CE:7F:F0:05:F2:93:5D:1E
SHA256:
1C:01:C6:F4:DB:B2:FE:FC:22:55:8B:2B:CA:32:56:3F:49:84:4A:CF:C3:2B:7B:E4:B0:FF:59:9F:9E:8C:7A:F
Alias name: mozillacert105.pem
SHA1: 77:47:4F:C6:30:E4:0F:4C:47:64:3F:84:BA:B8:C6:95:4A:8A:41:EC
SHA256:
F0:9B:12:2C:71:14:F4:A0:9B:D4:EA:4F:4A:99:D5:58:B4:6E:4C:25:CD:81:14:0D:29:C0:56:13:91:4C:38:4
Alias name: mozillacert106.pem
SHA1: E7:A1:90:29:D3:D5:52:DC:0D:0F:C6:92:D3:EA:88:0D:15:2E:1A:6B
SHA256:
D9:5F:EA:3C:A4:EE:DC:E7:4C:D7:6E:75:FC:6D:1F:F6:2C:44:1F:0F:A8:BC:77:F0:34:B1:9E:5D:B2:58:01:5
Alias name: mozillacert107.pem
SHA1: 8E:1C:74:F8:A6:20:B9:E5:8A:F4:61:FA:EC:2B:47:56:51:1A:52:C6
SHA256:
F9:6F:23:F4:C3:E7:9C:07:7A:46:98:8D:5A:F5:90:06:76:A0:F0:39:CB:64:5D:D1:75:49:B2:16:C8:24:40:C
Alias name: mozillacert108.pem
SHA1: B1:BC:96:8B:D4:F4:9D:62:2A:A8:9A:81:F2:15:01:52:A4:1D:82:9C
SHA256:
EB:D4:10:40:E4:BB:3E:C7:42:C9:E3:81:D3:1E:F2:A4:1A:48:B6:68:5C:96:E7:CE:F3:C1:DF:6C:D4:33:1C:9
Alias name: mozillacert109.pem
SHA1: B5:61:EB:EA:A4:DE:E4:25:4B:69:1A:98:A5:57:47:C2:34:C7:D9:71
SHA256:
E2:3D:4A:03:6D:7B:70:E9:F5:95:B1:42:20:79:D2:B9:1E:DF:BB:1F:B6:51:A0:63:3E:AA:8A:9D:C5:F8:07:0
Alias name: mozillacert111.pem
SHA1: 05:63:B8:63:0D:62:D7:5A:BB:C8:AB:1E:4B:DF:B5:A8:99:B2:4D:43
SHA256:
3E:90:99:B5:01:5E:8F:48:6C:00:BC:EA:9D:11:1E:E7:21:FA:BA:35:5A:89:BC:F1:DF:69:56:1E:3D:C6:32:5
Alias name: mozillacert110.pem
SHA1: 93:05:7A:88:15:C6:4F:CE:88:2F:FA:91:16:52:28:78:BC:53:64:17
SHA256:
9A:6E:C0:12:E1:A7:DA:9D:BE:34:19:4D:47:8A:D7:C0:DB:18:22:FB:07:1D:F1:29:81:49:6E:D1:04:38:41:1
Alias name: mozillacert111.pem
SHA1: 9C:BB:48:53:F6:A4:F6:D3:52:A4:E8:32:52:55:60:13:F5:AD:AF:65
SHA256:
59:76:90:07:F7:68:5D:0F:CD:50:87:2F:9F:95:D5:75:5A:5B:2B:45:7D:81:F3:69:2B:61:0A:98:67:2F:0E:1
Alias name: mozillacert112.pem
SHA1: 43:13:BB:96:F1:D5:86:9B:C1:4E:6A:92:F6:CF:F6:34:69:87:82:37

SHA256:

DD:69:36:FE:21:F8:F0:77:C1:23:A1:A5:21:C1:22:24:F7:22:55:B7:3E:03:A7:26:06:93:E8:A2:4B:0F:A3:8

Alias name: mozillacert113.pem

SHA1: 50:30:06:09:1D:97:D4:F5:AE:39:F7:CB:E7:92:7D:7D:65:2D:34:31

SHA256:

6D:C4:71:72:E0:1C:BC:B0:BF:62:58:0D:89:5F:E2:B8:AC:9A:D4:F8:73:80:1E:0C:10:B9:C8:37:D2:1E:B1:7

Alias name: mozillacert114.pem

SHA1: 51:C6:E7:08:49:06:6E:F3:92:D4:5C:A0:0D:6D:A3:62:8F:C3:52:39

SHA256:

B0:BF:D5:2B:B0:D7:D9:BD:92:BF:5D:4D:C1:3D:A2:55:C0:2C:54:2F:37:83:65:EA:89:39:11:F5:5E:55:F2:3

Alias name: mozillacert115.pem

SHA1: 59:0D:2D:7D:88:4F:40:2E:61:7E:A5:62:32:17:65:CF:17:D8:94:E9

SHA256:

91:E2:F5:78:8D:58:10:EB:A7:BA:58:73:7D:E1:54:8A:8E:CA:CD:01:45:98:BC:0B:14:3E:04:1B:17:05:25:5

Alias name: mozillacert116.pem

SHA1: 2B:B1:F5:3E:55:0C:1D:C5:F1:D4:E6:B7:6A:46:4B:55:06:02:AC:21

SHA256:

F3:56:BE:A2:44:B7:A9:1E:B3:5D:53:CA:9A:D7:86:4A:CE:01:8E:2D:35:D5:F8:F9:6D:DF:68:A6:F4:1A:A4:7

Alias name: mozillacert117.pem

SHA1: D4:DE:20:D0:5E:66:FC:53:FE:1A:50:88:2C:78:DB:28:52:CA:E4:74

SHA256:

16:AF:57:A9:F6:76:B0:AB:12:60:95:AA:5E:BA:DE:F2:2A:B3:11:19:D6:44:AC:95:CD:4B:93:DB:F3:F2:6A:E

Alias name: mozillacert118.pem

SHA1: 7E:78:4A:10:1C:82:65:CC:2D:E1:F1:6D:47:B4:40:CA:D9:0A:19:45

SHA256:

5F:0B:62:EA:B5:E3:53:EA:65:21:65:16:58:FB:B6:53:59:F4:43:28:0A:4A:FB:D1:04:D7:7D:10:F9:F0:4C:0

Alias name: mozillacert119.pem

SHA1: 75:E0:AB:B6:13:85:12:27:1C:04:F8:5F:DD:DE:38:E4:B7:24:2E:FE

SHA256:

CA:42:DD:41:74:5F:D0:B8:1E:B9:02:36:2C:F9:D8:BF:71:9D:A1:BD:1B:1E:FC:94:6F:5B:4C:99:F4:2C:1B:9

Alias name: mozillacert120.pem

SHA1: A8:98:5D:3A:65:E5:E5:C4:B2:D7:D6:6D:40:C6:DD:2F:B1:9C:54:36

SHA256:

43:48:A0:E9:44:4C:78:CB:26:5E:05:8D:5E:89:44:B4:D8:4F:96:62:BD:26:DB:25:7F:89:34:A4:43:C7:01:6

Alias name: mozillacert121.pem

SHA1: DA:40:18:8B:91:89:A3:ED:EE:AE:DA:97:FE:2F:9D:F5:B7:D1:8A:41

SHA256:

CF:56:FF:46:A4:A1:86:10:9D:D9:65:84:B5:EE:B5:8A:51:0C:42:75:B0:E5:F9:4F:40:BB:AE:86:5E:19:F6:7

Alias name: mozillacert122.pem

SHA1: 02:FA:F3:E2:91:43:54:68:60:78:57:69:4D:F5:E4:5B:68:85:18:68

SHA256:

68:7F:A4:51:38:22:78:FF:F0:C8:B1:1F:8D:43:D5:76:67:1C:6E:B2:BC:EA:B4:13:FB:83:D9:65:D0:6D:2F:F

Alias name: mozillacert123.pem

SHA1: 2A:B6:28:48:5E:78:FB:F3:AD:9E:79:10:DD:6B:DF:99:72:2C:96:E5

SHA256:

07:91:CA:07:49:B2:07:82:AA:D3:C7:D7:BD:0C:DF:C9:48:58:35:84:3E:B2:D7:99:60:09:CE:43:AB:6C:69:2

Alias name: mozillacert124.pem

SHA1: 4D:23:78:EC:91:95:39:B5:00:7F:75:8F:03:3B:21:1E:C5:4D:8B:CF

SHA256:

80:95:21:08:05:DB:4B:BC:35:5E:44:28:D8:FD:6E:C2:CD:E3:AB:5F:B9:7A:99:42:98:8E:B8:F4:DC:D0:60:1

Alias name: mozillacert125.pem

SHA1: B3:1E:B1:B7:40:E3:6C:84:02:DA:DC:37:D4:4D:F5:D4:67:49:52:F9

SHA256:

73:C1:76:43:4F:1B:C6:D5:AD:F4:5B:0E:76:E7:27:28:7C:8D:E5:76:16:C1:E6:E6:14:1A:2B:2C:BC:7D:8E:4

Alias name: mozillacert126.pem

SHA1: 25:01:90:19:CF:FB:D9:99:1C:B7:68:25:74:8D:94:5F:30:93:95:42

SHA256:

AF:8B:67:62:A1:E5:28:22:81:61:A9:5D:5C:55:9E:E2:66:27:8F:75:D7:9E:83:01:89:A5:03:50:6A:BD:6B:4

Alias name: mozillacert127.pem

SHA1: DE:28:F4:A4:FF:E5:B9:2F:A3:C5:03:D1:A3:49:A7:F9:96:2A:82:12

SHA256:

FF:85:6A:2D:25:1D:CD:88:D3:66:56:F4:50:12:67:98:CF:AB:AA:DE:40:79:9C:72:2D:E4:D2:B5:DB:36:A7:3

Alias name: mozillacert128.pem

SHA1: A9:E9:78:08:14:37:58:88:F2:05:19:B0:6D:2B:0D:2B:60:16:90:7D

SHA256:

CA:2D:82:A0:86:77:07:2F:8A:B6:76:4F:F0:35:67:6C:FE:3E:5E:32:5E:01:21:72:DF:3F:92:09:6D:B7:9B:8

Alias name: mozillacert129.pem

SHA1: E6:21:F3:35:43:79:05:9A:4B:68:30:9D:8A:2F:74:22:15:87:EC:79

SHA256:

A0:45:9B:9F:63:B2:25:59:F5:FA:5D:4C:6D:B3:F9:F7:2F:F1:93:42:03:35:78:F0:73:BF:1D:1B:46:CB:B9:1

Alias name: mozillacert130.pem

SHA1: 06:08:3F:59:3F:15:A1:04:A0:69:A4:6B:A9:03:D0:06:B7:97:09:91

SHA256:

6C:61:DA:C3:A2:DE:F0:31:50:6B:E0:36:D2:A6:FE:40:19:94:FB:D1:3D:F9:C8:D4:66:59:92:74:C4:46:EC:9

Alias name: mozillacert131.pem

SHA1: E5:DF:74:3C:B6:01:C4:9B:98:43:DC:AB:8C:E8:6A:81:10:9F:E4:8E

SHA256:

F4:C1:49:55:1A:30:13:A3:5B:C7:BF:FE:17:A7:F3:44:9B:C1:AB:5B:5A:0A:E7:4B:06:C2:3B:90:00:4C:01:0

Alias name: mozillacert132.pem

SHA1: 37:9A:19:7B:41:85:45:35:0C:A6:03:69:F3:3C:2E:AF:47:4F:20:79

SHA256:

A0:23:4F:3B:C8:52:7C:A5:62:8E:EC:81:AD:5D:69:89:5D:A5:68:0D:C9:1D:1C:B8:47:7F:33:F8:78:B9:5B:0

Alias name: mozillacert133.pem

SHA1: 39:21:C1:15:C1:5D:0E:CA:5C:CB:5B:C4:F0:7D:21:D8:05:0B:56:6A

SHA256:

77:40:73:12:C6:3A:15:3D:5B:C0:0B:4E:51:75:9C:DF:DA:C2:37:DC:2A:33:B6:79:46:E9:8E:9B:FA:68:0A:E

Alias name: mozillacert133.pem

SHA1: 85:B5:FF:67:9B:0C:79:96:1F:C8:6E:44:22:00:46:13:DB:17:92:84

SHA256:

7D:3B:46:5A:60:14:E5:26:C0:AF:FC:EE:21:27:D2:31:17:27:AD:81:1C:26:84:2D:00:6A:F3:73:06:CC:80:B

Alias name: mozillacert134.pem

SHA1: 70:17:9B:86:8C:00:A4:FA:60:91:52:22:3F:9F:3E:32:BD:E0:05:62

SHA256:

69:FA:C9:BD:55:FB:0A:C7:8D:53:BB:EE:5C:F1:D5:97:98:9F:D0:AA:AB:20:A2:51:51:BD:F1:73:3E:E7:D1:2

Alias name: mozillacert135.pem

SHA1: 62:52:DC:40:F7:11:43:A2:2F:DE:9E:F7:34:8E:06:42:51:B1:81:18

SHA256:

D8:E0:FE:BC:1D:B2:E3:8D:00:94:0F:37:D2:7D:41:34:4D:99:3E:73:4B:99:D5:65:6D:97:78:D4:D8:14:36:2

Alias name: mozillacert136.pem

SHA1: D1:EB:23:A4:6D:17:D6:8F:D9:25:64:C2:F1:F1:60:17:64:D8:E3:49

SHA256:

D7:A7:A0:FB:5D:7E:27:31:D7:71:E9:48:4E:BC:DE:F7:1D:5F:0C:3E:0A:29:48:78:2B:C8:3E:E0:EA:69:9E:F

Alias name: mozillacert137.pem

SHA1: 4A:65:D5:F4:1D:EF:39:B8:B8:90:4A:4A:D3:64:81:33:CF:C7:A1:D1

SHA256:

BD:81:CE:3B:4F:65:91:D1:1A:67:B5:FC:7A:47:FD:EF:25:52:1B:F9:AA:4E:18:B9:E3:DF:2E:34:A7:80:3B:E

Alias name: mozillacert138.pem

SHA1: E1:9F:E3:0E:8B:84:60:9E:80:9B:17:0D:72:A8:C5:BA:6E:14:09:BD

SHA256:

3F:06:E5:56:81:D4:96:F5:BE:16:9E:B5:38:9F:9F:2B:8F:F6:1E:17:08:DF:68:81:72:48:49:CD:5D:27:CB:6

Alias name: mozillacert139.pem

SHA1: DE:3F:40:BD:50:93:D3:9B:6C:60:F6:DA:BC:07:62:01:00:89:76:C9

SHA256:

A4:5E:DE:3B:BB:F0:9C:8A:E1:5C:72:EF:C0:72:68:D6:93:A2:1C:99:6F:D5:1E:67:CA:07:94:60:FD:6D:88:7

Alias name: mozillacert140.pem

SHA1: 5F:B7:EE:06:33:E2:59:DB:AD:0C:4C:9A:E6:D3:8F:1A:61:C7:DC:25

SHA256:

74:31:E5:F4:C3:C1:CE:46:90:77:4F:0B:61:E0:54:40:88:3B:A9:A0:1E:D0:0B:A6:AB:D7:80:6E:D3:B1:18:C

Alias name: mozillacert141.pem

SHA1: CA:3A:FB:CF:12:40:36:4B:44:B2:16:20:88:80:48:39:19:93:7C:F7

SHA256:

85:A0:DD:7D:D7:20:AD:B7:FF:05:F8:3D:54:2B:20:9D:C7:FF:45:28:F7:D6:77:B1:83:89:FE:A5:E5:C4:9E:8

Alias name: mozillacert142.pem

SHA1: 31:7A:2A:D0:7F:2B:33:5E:F5:A1:C3:4E:4B:57:E8:B7:D8:F1:FC:A6

SHA256:

58:D0:17:27:9C:D4:DC:63:AB:DD:B1:96:A6:C9:90:6C:30:C4:E0:87:83:EA:E8:C1:60:99:54:D6:93:55:59:6

SHA256:

18:F1:FC:7F:20:5D:F8:AD:DD:EB:7F:E0:07:DD:57:E3:AF:37:5A:9C:4D:8D:73:54:6B:F4:F1:FE:D1:E1:8D:3

Alias name: mozillacert143.pem

SHA1: 36:B1:2B:49:F9:81:9E:D7:4C:9E:BC:38:0F:C6:56:8F:5D:AC:B2:F7

SHA256:

E7:5E:72:ED:9F:56:0E:EC:6E:B4:80:00:73:A4:3F:C3:AD:19:19:5A:39:22:82:01:78:95:97:4A:99:02:6B:6

Alias name: mozillacert144.pem

SHA1: 37:F7:6D:E6:07:7C:90:C5:B1:3E:93:1A:B7:41:10:B4:F2:E4:9A:27

SHA256:

79:08:B4:03:14:C1:38:10:0B:51:8D:07:35:80:7F:FB:FC:F8:51:8A:00:95:33:71:05:BA:38:6B:15:3D:D9:2

Alias name: mozillacert145.pem

SHA1: 10:1D:FA:3F:D5:0B:CB:BB:9B:B5:60:0C:19:55:A4:1A:F4:73:3A:04

SHA256:

D4:1D:82:9E:8C:16:59:82:2A:F9:3F:CE:62:BF:FC:DE:26:4F:C8:4E:8B:95:0C:5F:F2:75:D0:52:35:46:95:A

Alias name: mozillacert146.pem

SHA1: 21:FC:BD:8E:7F:6C:AF:05:1B:D1:B3:43:EC:A8:E7:61:47:F2:0F:8A

SHA256:

48:98:C6:88:8C:0C:FF:B0:D3:E3:1A:CA:8A:37:D4:E3:51:5F:F7:46:D0:26:35:D8:66:46:CF:A0:A3:18:5A:E

Alias name: mozillacert147.pem

SHA1: 58:11:9F:0E:12:82:87:EA:50:FD:D9:87:45:6F:4F:78:DC:FA:D6:D4

SHA256:

85:FB:2F:91:DD:12:27:5A:01:45:B6:36:53:4F:84:02:4A:D6:8B:69:B8:EE:88:68:4F:F7:11:37:58:05:B3:4

Alias name: mozillacert148.pem

SHA1: 04:83:ED:33:99:AC:36:08:05:87:22:ED:BC:5E:46:00:E3:BE:F9:D7

SHA256:

6E:A5:47:41:D0:04:66:7E:ED:1B:48:16:63:4A:A3:A7:9E:6E:4B:96:95:0F:82:79:DA:FC:8D:9B:D8:81:21:3

Alias name: mozillacert149.pem

SHA1: 6E:3A:55:A4:19:0C:19:5C:93:84:3C:C0:DB:72:2E:31:30:61:F0:B1

SHA256:

0C:25:8A:12:A5:67:4A:EF:25:F2:8B:A7:DC:FA:EC:EE:A3:48:E5:41:E6:F5:CC:4E:E6:3B:71:B3:61:60:6A:C

Alias name: mozillacert150.pem

SHA1: 74:20:74:41:72:9C:DD:92:EC:79:31:D8:23:10:8D:C2:81:92:E2:BB

SHA256:

0F:99:3C:8A:EF:97:BA:AF:56:87:14:0E:D5:9A:D1:82:1B:B4:AF:AC:F0:AA:9A:58:B5:D5:7A:33:8A:3A:FB:C

Alias name: mozillacert151.pem

SHA1: 33:9B:6B:14:50:24:9B:55:7A:01:87:72:84:D9:E0:2F:C3:D2:D8:E9

SHA256:

EF:3C:B4:17:FC:8E:BF:6F:97:87:6C:9E:4E:CE:39:DE:1E:A5:FE:64:91:41:D1:02:8B:7D:11:C0:B2:29:8C:E

Alias name: mozillacert152.pem

SHA1: AC:ED:5F:65:53:FD:25:CE:01:5F:1F:7A:48:3B:6A:74:9F:61:78:C6

SHA256:

7F:12:CD:5F:7E:5E:29:0E:C7:D8:51:79:D5:B7:2C:20:A5:BE:75:08:FF:DB:5B:F8:1A:B9:68:4A:7F:C9:F6:6

Alias name: mozillacert153.pem

SHA1: DA:C9:02:4F:54:D8:F6:DF:94:93:5F:B1:73:26:38:CA:6A:D7:7C:13

SHA256:
06:87:26:03:31:A7:24:03:D9:09:F1:05:E6:9B:CF:0D:32:E1:BD:24:93:FF:C6:D9:20:6D:11:BC:D6:77:07:3
Alias name: mozillacert17.pem
SHA1: 40:54:DA:6F:1C:3F:40:74:AC:ED:0F:EC:CD:DB:79:D1:53:FB:90:1D
SHA256:
76:7C:95:5A:76:41:2C:89:AF:68:8E:90:A1:C7:0F:55:6C:FD:6B:60:25:DB:EA:10:41:6D:7E:B6:83:1F:8C:4
Alias name: mozillacert18.pem
SHA1: 79:98:A3:08:E1:4D:65:85:E6:C2:1E:15:3A:71:9F:BA:5A:D3:4A:D9
SHA256:
44:04:E3:3B:5E:14:0D:CF:99:80:51:FD:FC:80:28:C7:C8:16:15:C5:EE:73:7B:11:1B:58:82:33:A9:B5:35:A
Alias name: mozillacert19.pem
SHA1: B4:35:D4:E1:11:9D:1C:66:90:A7:49:EB:B3:94:BD:63:7B:A7:82:B7
SHA256:
C4:70:CF:54:7E:23:02:B9:77:FB:29:DD:71:A8:9A:7B:6C:1F:60:77:7B:03:29:F5:60:17:F3:28:BF:4F:6B:E
Alias name: mozillacert2.pem
SHA1: 22:D5:D8:DF:8F:02:31:D1:8D:F7:9D:B7:CF:8A:2D:64:C9:3F:6C:3A
SHA256:
69:DD:D7:EA:90:BB:57:C9:3E:13:5D:C8:5E:A6:FC:D5:48:0B:60:32:39:BD:C4:54:FC:75:8B:2A:26:CF:7F:7
Alias name: mozillacert20.pem
SHA1: D8:C5:38:8A:B7:30:1B:1B:6E:D4:7A:E6:45:25:3A:6F:9F:1A:27:61
SHA256:
62:DD:0B:E9:B9:F5:0A:16:3E:A0:F8:E7:5C:05:3B:1E:CA:57:EA:55:C8:68:8F:64:7C:68:81:F2:C8:35:7B:9
Alias name: mozillacert21.pem
SHA1: 9B:AA:E5:9F:56:EE:21:CB:43:5A:BE:25:93:DF:A7:F0:40:D1:1D:CB
SHA256:
BE:6C:4D:A2:BB:B9:BA:59:B6:F3:93:97:68:37:42:46:C3:C0:05:99:3F:A9:8F:02:0D:1D:ED:BE:D4:8A:81:D
Alias name: mozillacert22.pem
SHA1: 32:3C:11:8E:1B:F7:B8:B6:52:54:E2:E2:10:0D:D6:02:90:37:F0:96
SHA256:
37:D5:10:06:C5:12:EA:AB:62:64:21:F1:EC:8C:92:01:3F:C5:F8:2A:E9:8E:E5:33:EB:46:19:B8:DE:B4:D0:6
Alias name: mozillacert23.pem
SHA1: 91:C6:D6:EE:3E:8A:C8:63:84:E5:48:C2:99:29:5C:75:6C:81:7B:81
SHA256:
8D:72:2F:81:A9:C1:13:C0:79:1D:F1:36:A2:96:6D:B2:6C:95:0A:97:1D:B4:6B:41:99:F4:EA:54:B7:8B:FB:9
Alias name: mozillacert24.pem
SHA1: 59:AF:82:79:91:86:C7:B4:75:07:CB:CF:03:57:46:EB:04:DD:B7:16
SHA256:
66:8C:83:94:7D:A6:3B:72:4B:EC:E1:74:3C:31:A0:E6:AE:D0:DB:8E:C5:B3:1B:E3:77:BB:78:4F:91:B6:71:6
Alias name: mozillacert25.pem
SHA1: 4E:B6:D5:78:49:9B:1C:CF:5F:58:1E:AD:56:BE:3D:9B:67:44:A5:E5
SHA256:
9A:CF:AB:7E:43:C8:D8:80:D0:6B:26:2A:94:DE:EE:E4:B4:65:99:89:C3:D0:CA:F1:9B:AF:64:05:E4:1A:B7:D
Alias name: mozillacert26.pem
SHA1: 87:82:C6:C3:04:35:3B:CF:D2:96:92:D2:59:3E:7D:44:D9:34:FF:11

SHA256:
F1:C1:B5:0A:E5:A2:0D:D8:03:0E:C9:F6:BC:24:82:3D:D3:67:B5:25:57:59:B4:E7:1B:61:FC:E9:F7:37:5D:7
Alias name: mozillacert27.pem
SHA1: 3A:44:73:5A:E5:81:90:1F:24:86:61:46:1E:3B:9C:C4:5F:F5:3A:1B
SHA256:
42:00:F5:04:3A:C8:59:0E:BB:52:7D:20:9E:D1:50:30:29:FB:CB:D4:1C:A1:B5:06:EC:27:F1:5A:DE:7D:AC:6
Alias name: mozillacert28.pem
SHA1: 66:31:BF:9E:F7:4F:9E:B6:C9:D5:A6:0C:BA:6A:BE:D1:F7:BD:EF:7B
SHA256:
0C:2C:D6:3D:F7:80:6F:A3:99:ED:E8:09:11:6B:57:5B:F8:79:89:F0:65:18:F9:80:8C:86:05:03:17:8B:AF:6
Alias name: mozillacert29.pem
SHA1: 74:F8:A3:C3:EF:E7:B3:90:06:4B:83:90:3C:21:64:60:20:E5:DF:CE
SHA256:
15:F0:BA:00:A3:AC:7A:F3:AC:88:4C:07:2B:10:11:A0:77:BD:77:C0:97:F4:01:64:B2:F8:59:8A:BD:83:86:0
Alias name: mozillacert3.pem
SHA1: 87:9F:4B:EE:05:DF:98:58:3B:E3:60:D6:33:E7:0D:3F:FE:98:71:AF
SHA256:
39:DF:7B:68:2B:7B:93:8F:84:71:54:81:CC:DE:8D:60:D8:F2:2E:C5:98:87:7D:0A:AA:C1:2B:59:18:2B:03:1
Alias name: mozillacert30.pem
SHA1: E7:B4:F6:9D:61:EC:90:69:DB:7E:90:A7:40:1A:3C:F4:7D:4F:E8:EE
SHA256:
A7:12:72:AE:AA:A3:CF:E8:72:7F:7F:B3:9F:0F:B3:D1:E5:42:6E:90:60:B0:6E:E6:F1:3E:9A:3C:58:33:CD:4
Alias name: mozillacert31.pem
SHA1: 9F:74:4E:9F:2B:4D:BA:EC:0F:31:2C:50:B6:56:3B:8E:2D:93:C3:11
SHA256:
17:93:92:7A:06:14:54:97:89:AD:CE:2F:8F:34:F7:F0:B6:6D:0F:3A:E3:A3:B8:4D:21:EC:15:DB:BA:4F:AD:C
Alias name: mozillacert32.pem
SHA1: 60:D6:89:74:B5:C2:65:9E:8A:0F:C1:88:7C:88:D2:46:69:1B:18:2C
SHA256:
B9:BE:A7:86:0A:96:2E:A3:61:1D:AB:97:AB:6D:A3:E2:1C:10:68:B9:7D:55:57:5E:D0:E1:12:79:C1:1C:89:3
Alias name: mozillacert33.pem
SHA1: FE:B8:C4:32:DC:F9:76:9A:CE:AE:3D:D8:90:8F:FD:28:86:65:64:7D
SHA256:
A2:2D:BA:68:1E:97:37:6E:2D:39:7D:72:8A:AE:3A:9B:62:96:B9:FD:BA:60:BC:2E:11:F6:47:F2:C6:75:FB:3
Alias name: mozillacert34.pem
SHA1: 59:22:A1:E1:5A:EA:16:35:21:F8:98:39:6A:46:46:B0:44:1B:0F:A9
SHA256:
41:C9:23:86:6A:B4:CA:D6:B7:AD:57:80:81:58:2E:02:07:97:A6:CB:DF:4F:FF:78:CE:83:96:B3:89:37:D7:F
Alias name: mozillacert35.pem
SHA1: 2A:C8:D5:8B:57:CE:BF:2F:49:AF:F2:FC:76:8F:51:14:62:90:7A:41
SHA256:
92:BF:51:19:AB:EC:CA:D0:B1:33:2D:C4:E1:D0:5F:BA:75:B5:67:90:44:EE:0C:A2:6E:93:1F:74:4F:2F:33:C
Alias name: mozillacert36.pem
SHA1: 23:88:C9:D3:71:CC:9E:96:3D:FF:7D:3C:A7:CE:FC:D6:25:EC:19:0D

SHA256:
32:7A:3D:76:1A:BA:DE:A0:34:EB:99:84:06:27:5C:B1:A4:77:6E:FD:AE:2F:DF:6D:01:68:EA:1C:4F:55:67:D
Alias name: mozillacert37.pem
SHA1: B1:2E:13:63:45:86:A4:6F:1A:B2:60:68:37:58:2D:C4:AC:FD:94:97
SHA256:
E3:B6:A2:DB:2E:D7:CE:48:84:2F:7A:C5:32:41:C7:B7:1D:54:14:4B:FB:40:C1:1F:3F:1D:0B:42:F5:EE:A1:2
Alias name: mozillacert38.pem
SHA1: CB:A1:C5:F8:B0:E3:5E:B8:B9:45:12:D3:F9:34:A2:E9:06:10:D3:36
SHA256:
A6:C5:1E:0D:A5:CA:0A:93:09:D2:E4:C0:E4:0C:2A:F9:10:7A:AE:82:03:85:7F:E1:98:E3:E7:69:E3:43:08:5
Alias name: mozillacert39.pem
SHA1: AE:50:83:ED:7C:F4:5C:BC:8F:61:C6:21:FE:68:5D:79:42:21:15:6E
SHA256:
E6:B8:F8:76:64:85:F8:07:AE:7F:8D:AC:16:70:46:1F:07:C0:A1:3E:EF:3A:1F:F7:17:53:8D:7A:BA:D3:91:B
Alias name: mozillacert4.pem
SHA1: E3:92:51:2F:0A:CF:F5:05:DF:F6:DE:06:7F:75:37:E1:65:EA:57:4B
SHA256:
0B:5E:ED:4E:84:64:03:CF:55:E0:65:84:84:40:ED:2A:82:75:8B:F5:B9:AA:1F:25:3D:46:13:CF:A0:80:FF:3
Alias name: mozillacert40.pem
SHA1: 80:25:EF:F4:6E:70:C8:D4:72:24:65:84:FE:40:3B:8A:8D:6A:DB:F5
SHA256:
8D:A0:84:FC:F9:9C:E0:77:22:F8:9B:32:05:93:98:06:FA:5C:B8:11:E1:C8:13:F6:A1:08:C7:D3:36:B3:40:8
Alias name: mozillacert41.pem
SHA1: 6B:2F:34:AD:89:58:BE:62:FD:B0:6B:5C:CE:BB:9D:D9:4F:4E:39:F3
SHA256:
EB:F3:C0:2A:87:89:B1:FB:7D:51:19:95:D6:63:B7:29:06:D9:13:CE:0D:5E:10:56:8A:8A:77:E2:58:61:67:E
Alias name: mozillacert42.pem
SHA1: 85:A4:08:C0:9C:19:3E:5D:51:58:7D:CD:D6:13:30:FD:8C:DE:37:BF
SHA256:
B6:19:1A:50:D0:C3:97:7F:7D:A9:9B:CD:AA:C8:6A:22:7D:AE:B9:67:9E:C7:0B:A3:B0:C9:D9:22:71:C1:70:D
Alias name: mozillacert43.pem
SHA1: F9:CD:0E:2C:DA:76:24:C1:8F:BD:F0:F0:AB:B6:45:B8:F7:FE:D5:7A
SHA256:
50:79:41:C7:44:60:A0:B4:70:86:22:0D:4E:99:32:57:2A:B5:D1:B5:BB:CB:89:80:AB:1C:B1:76:51:A8:44:D
Alias name: mozillacert44.pem
SHA1: 5F:43:E5:B1:BF:F8:78:8C:AC:1C:C7:CA:4A:9A:C6:22:2B:CC:34:C6
SHA256:
96:0A:DF:00:63:E9:63:56:75:0C:29:65:DD:0A:08:67:DA:0B:9C:BD:6E:77:71:4A:EA:FB:23:49:AB:39:3D:A
Alias name: mozillacert45.pem
SHA1: 67:65:0D:F1:7E:8E:7E:5B:82:40:A4:F4:56:4B:CF:E2:3D:69:C6:F0
SHA256:
C0:A6:F4:DC:63:A2:4B:FD:CF:54:EF:2A:6A:08:2A:0A:72:DE:35:80:3E:2F:F5:FF:52:7A:E5:D8:72:06:DF:D
Alias name: mozillacert46.pem
SHA1: 40:9D:4B:D9:17:B5:5C:27:B6:9B:64:CB:98:22:44:0D:CD:09:B8:89

SHA256:

EC:C3:E9:C3:40:75:03:BE:E0:91:AA:95:2F:41:34:8F:F8:8B:AA:86:3B:22:64:BE:FA:C8:07:90:15:74:E9:3

Alias name: mozillacert47.pem

SHA1: 1B:4B:39:61:26:27:6B:64:91:A2:68:6D:D7:02:43:21:2D:1F:1D:96

SHA256:

E4:C7:34:30:D7:A5:B5:09:25:DF:43:37:0A:0D:21:6E:9A:79:B9:D6:DB:83:73:A0:C6:9E:B1:CC:31:C7:C5:2

Alias name: mozillacert48.pem

SHA1: A0:A1:AB:90:C9:FC:84:7B:3B:12:61:E8:97:7D:5F:D3:22:61:D3:CC

SHA256:

0F:4E:9C:DD:26:4B:02:55:50:D1:70:80:63:40:21:4F:E9:44:34:C9:B0:2F:69:7E:C7:10:FC:5F:EA:FB:5E:3

Alias name: mozillacert49.pem

SHA1: 61:57:3A:11:DF:0E:D8:7E:D5:92:65:22:EA:D0:56:D7:44:B3:23:71

SHA256:

B7:B1:2B:17:1F:82:1D:AA:99:0C:D0:FE:50:87:B1:28:44:8B:A8:E5:18:4F:84:C5:1E:02:B5:C8:FB:96:2B:2

Alias name: mozillacert5.pem

SHA1: B8:01:86:D1:EB:9C:86:A5:41:04:CF:30:54:F3:4C:52:B7:E5:58:C6

SHA256:

CE:CD:DC:90:50:99:D8:DA:DF:C5:B1:D2:09:B7:37:CB:E2:C1:8C:FB:2C:10:C0:FF:0B:CF:0D:32:86:FC:1A:A

Alias name: mozillacert50.pem

SHA1: 8C:96:BA:EB:DD:2B:07:07:48:EE:30:32:66:A0:F3:98:6E:7C:AE:58

SHA256:

35:AE:5B:DD:D8:F7:AE:63:5C:FF:BA:56:82:A8:F0:0B:95:F4:84:62:C7:10:8E:E9:A0:E5:29:2B:07:4A:AF:B

Alias name: mozillacert51.pem

SHA1: FA:B7:EE:36:97:26:62:FB:2D:B0:2A:F6:BF:03:FD:E8:7C:4B:2F:9B

SHA256:

EA:A9:62:C4:FA:4A:6B:AF:EB:E4:15:19:6D:35:1C:CD:88:8D:4F:53:F3:FA:8A:E6:D7:C4:66:A9:4E:60:42:B

Alias name: mozillacert52.pem

SHA1: 8B:AF:4C:9B:1D:F0:2A:92:F7:DA:12:8E:B9:1B:AC:F4:98:60:4B:6F

SHA256:

E2:83:93:77:3D:A8:45:A6:79:F2:08:0C:C7:FB:44:A3:B7:A1:C3:79:2C:B7:EB:77:29:FD:CB:6A:8D:99:AE:A

Alias name: mozillacert53.pem

SHA1: 7F:8A:B0:CF:D0:51:87:6A:66:F3:36:0F:47:C8:8D:8C:D3:35:FC:74

SHA256:

2D:47:43:7D:E1:79:51:21:5A:12:F3:C5:8E:51:C7:29:A5:80:26:EF:1F:CC:0A:5F:B3:D9:DC:01:2F:60:0D:1

Alias name: mozillacert54.pem

SHA1: 03:9E:ED:B8:0B:E7:A0:3C:69:53:89:3B:20:D2:D9:32:3A:4C:2A:FD

SHA256:

B4:78:B8:12:25:0D:F8:78:63:5C:2A:A7:EC:7D:15:5E:AA:62:5E:E8:29:16:E2:CD:29:43:61:88:6C:D1:FB:D

Alias name: mozillacert55.pem

SHA1: AA:DB:BC:22:23:8F:C4:01:A1:27:BB:38:DD:F4:1D:DB:08:9E:F0:12

SHA256:

A4:31:0D:50:AF:18:A6:44:71:90:37:2A:86:AF:AF:8B:95:1F:FB:43:1D:83:7F:1E:56:88:B4:59:71:ED:15:5

Alias name: mozillacert56.pem

SHA1: F1:8B:53:8D:1B:E9:03:B6:A6:F0:56:43:5B:17:15:89:CA:F3:6B:F2

SHA256:
4B:03:F4:58:07:AD:70:F2:1B:FC:2C:AE:71:C9:FD:E4:60:4C:06:4C:F5:FF:B6:86:BA:E5:DB:AA:D7:FD:D3:4
Alias name: mozillacert57.pem
SHA1: D6:DA:A8:20:8D:09:D2:15:4D:24:B5:2F:CB:34:6E:B2:58:B2:8A:58
SHA256:
F9:E6:7D:33:6C:51:00:2A:C0:54:C6:32:02:2D:66:DD:A2:E7:E3:FF:F1:0A:D0:61:ED:31:D8:BB:B4:10:CF:B
Alias name: mozillacert58.pem
SHA1: 8D:17:84:D5:37:F3:03:7D:EC:70:FE:57:8B:51:9A:99:E6:10:D7:B0
SHA256:
5E:DB:7A:C4:3B:82:A0:6A:87:61:E8:D7:BE:49:79:EB:F2:61:1F:7D:D7:9B:F9:1C:1C:6B:56:6A:21:9E:D7:6
Alias name: mozillacert59.pem
SHA1: 36:79:CA:35:66:87:72:30:4D:30:A5:FB:87:3B:0F:A7:7B:B7:0D:54
SHA256:
23:99:56:11:27:A5:71:25:DE:8C:EF:EA:61:0D:DF:2F:A0:78:B5:C8:06:7F:4E:82:82:90:BF:B8:60:E8:4B:3
Alias name: mozillacert6.pem
SHA1: 27:96:BA:E6:3F:18:01:E2:77:26:1B:A0:D7:77:70:02:8F:20:EE:E4
SHA256:
C3:84:6B:F2:4B:9E:93:CA:64:27:4C:0E:C6:7C:1E:CC:5E:02:4F:FC:AC:D2:D7:40:19:35:0E:81:FE:54:6A:E
Alias name: mozillacert60.pem
SHA1: 3B:C4:9F:48:F8:F3:73:A0:9C:1E:BD:F8:5B:B1:C3:65:C7:D8:11:B3
SHA256:
BF:0F:EE:FB:9E:3A:58:1A:D5:F9:E9:DB:75:89:98:57:43:D2:61:08:5C:4D:31:4F:6F:5D:72:59:AA:42:16:1
Alias name: mozillacert61.pem
SHA1: E0:B4:32:2E:B2:F6:A5:68:B6:54:53:84:48:18:4A:50:36:87:43:84
SHA256:
03:95:0F:B4:9A:53:1F:3E:19:91:94:23:98:DF:A9:E0:EA:32:D7:BA:1C:DD:9B:C8:5D:B5:7E:D9:40:0B:43:4
Alias name: mozillacert62.pem
SHA1: A1:DB:63:93:91:6F:17:E4:18:55:09:40:04:15:C7:02:40:B0:AE:6B
SHA256:
A4:B6:B3:99:6F:C2:F3:06:B3:FD:86:81:BD:63:41:3D:8C:50:09:CC:4F:A3:29:C2:CC:F0:E2:FA:1B:14:03:0
Alias name: mozillacert63.pem
SHA1: 89:DF:74:FE:5C:F4:0F:4A:80:F9:E3:37:7D:54:DA:91:E1:01:31:8E
SHA256:
3C:5F:81:FE:A5:FA:B8:2C:64:BF:A2:EA:EC:AF:CD:E8:E0:77:FC:86:20:A7:CA:E5:37:16:3D:F3:6E:DB:F3:7
Alias name: mozillacert64.pem
SHA1: 62:7F:8D:78:27:65:63:99:D2:7D:7F:90:44:C9:FE:B3:F3:3E:FA:9A
SHA256:
AB:70:36:36:5C:71:54:AA:29:C2:C2:9F:5D:41:91:16:3B:16:2A:22:25:01:13:57:D5:6D:07:FF:A7:BC:1F:7
Alias name: mozillacert65.pem
SHA1: 69:BD:8C:F4:9C:D3:00:FB:59:2E:17:93:CA:55:6A:F3:EC:AA:35:FB
SHA256:
BC:23:F9:8A:31:3C:B9:2D:E3:BB:FC:3A:5A:9F:44:61:AC:39:49:4C:4A:E1:5A:9E:9D:F1:31:E9:9B:73:01:9
Alias name: mozillacert66.pem
SHA1: DD:E1:D2:A9:01:80:2E:1D:87:5E:84:B3:80:7E:4B:B1:FD:99:41:34

SHA256:

E6:09:07:84:65:A4:19:78:0C:B6:AC:4C:1C:0B:FB:46:53:D9:D9:CC:6E:B3:94:6E:B7:F3:D6:99:97:BA:D5:9

Alias name: mozillacert67.pem

SHA1: D6:9B:56:11:48:F0:1C:77:C5:45:78:C1:09:26:DF:5B:85:69:76:AD

SHA256:

CB:B5:22:D7:B7:F1:27:AD:6A:01:13:86:5B:DF:1C:D4:10:2E:7D:07:59:AF:63:5A:7C:F4:72:0D:C9:63:C5:3

Alias name: mozillacert68.pem

SHA1: AE:C5:FB:3F:C8:E1:BF:C4:E5:4F:03:07:5A:9A:E8:00:B7:F7:B6:FA

SHA256:

04:04:80:28:BF:1F:28:64:D4:8F:9A:D4:D8:32:94:36:6A:82:88:56:55:3F:3B:14:30:3F:90:14:7F:5D:40:E

Alias name: mozillacert69.pem

SHA1: 2F:78:3D:25:52:18:A7:4A:65:39:71:B5:2C:A2:9C:45:15:6F:E9:19

SHA256:

25:30:CC:8E:98:32:15:02:BA:D9:6F:9B:1F:BA:1B:09:9E:2D:29:9E:0F:45:48:BB:91:4F:36:3B:C0:D4:53:1

Alias name: mozillacert7.pem

SHA1: AD:7E:1C:28:B0:64:EF:8F:60:03:40:20:14:C3:D0:E3:37:0E:B5:8A

SHA256:

14:65:FA:20:53:97:B8:76:FA:A6:F0:A9:95:8E:55:90:E4:0F:CC:7F:AA:4F:B7:C2:C8:67:75:21:FB:5F:B6:5

Alias name: mozillacert70.pem

SHA1: 78:6A:74:AC:76:AB:14:7F:9C:6A:30:50:BA:9E:A8:7E:FE:9A:CE:3C

SHA256:

06:3E:4A:FA:C4:91:DF:D3:32:F3:08:9B:85:42:E9:46:17:D8:93:D7:FE:94:4E:10:A7:93:7E:E2:9D:96:93:C

Alias name: mozillacert71.pem

SHA1: 4A:BD:EE:EC:95:0D:35:9C:89:AE:C7:52:A1:2C:5B:29:F6:D6:AA:0C

SHA256:

13:63:35:43:93:34:A7:69:80:16:A0:D3:24:DE:72:28:4E:07:9D:7B:52:20:BB:8F:BD:74:78:16:EE:BE:BA:C

Alias name: mozillacert72.pem

SHA1: 47:BE:AB:C9:22:EA:E8:0E:78:78:34:62:A7:9F:45:C2:54:FD:E6:8B

SHA256:

45:14:0B:32:47:EB:9C:C8:C5:B4:F0:D7:B5:30:91:F7:32:92:08:9E:6E:5A:63:E2:74:9D:D3:AC:A9:19:8E:D

Alias name: mozillacert73.pem

SHA1: B5:1C:06:7C:EE:2B:0C:3D:F8:55:AB:2D:92:F4:FE:39:D4:E7:0F:0E

SHA256:

2C:E1:CB:0B:F9:D2:F9:E1:02:99:3F:BE:21:51:52:C3:B2:DD:0C:AB:DE:1C:68:E5:31:9B:83:91:54:DB:B7:F

Alias name: mozillacert74.pem

SHA1: 92:5A:8F:8D:2C:6D:04:E0:66:5F:59:6A:FF:22:D8:63:E8:25:6F:3F

SHA256:

56:8D:69:05:A2:C8:87:08:A4:B3:02:51:90:ED:CF:ED:B1:97:4A:60:6A:13:C6:E5:29:0F:CB:2A:E6:3E:DA:B

Alias name: mozillacert75.pem

SHA1: D2:32:09:AD:23:D3:14:23:21:74:E4:0D:7F:9D:62:13:97:86:63:3A

SHA256:

08:29:7A:40:47:DB:A2:36:80:C7:31:DB:6E:31:76:53:CA:78:48:E1:BE:BD:3A:0B:01:79:A7:07:F9:2C:F1:7

Alias name: mozillacert76.pem

SHA1: F9:B5:B6:32:45:5F:9C:BE:EC:57:5F:80:DC:E9:6E:2C:C7:B2:78:B7

SHA256:

03:76:AB:1D:54:C5:F9:80:3C:E4:B2:E2:01:A0:EE:7E:EF:7B:57:B6:36:E8:A9:3C:9B:8D:48:60:C9:6F:5F:A

Alias name: mozillacert77.pem

SHA1: 13:2D:0D:45:53:4B:69:97:CD:B2:D5:C3:39:E2:55:76:60:9B:5C:C6

SHA256:

EB:04:CF:5E:B1:F3:9A:FA:76:2F:2B:B1:20:F2:96:CB:A5:20:C1:B9:7D:B1:58:95:65:B8:1C:B9:A1:7B:72:4

Alias name: mozillacert78.pem

SHA1: 29:36:21:02:8B:20:ED:02:F5:66:C5:32:D1:D6:ED:90:9F:45:00:2F

SHA256:

0A:81:EC:5A:92:97:77:F1:45:90:4A:F3:8D:5D:50:9F:66:B5:E2:C5:8F:CD:B5:31:05:8B:0E:17:F3:F0:B4:1

Alias name: mozillacert79.pem

SHA1: D8:A6:33:2C:E0:03:6F:B1:85:F6:63:4F:7D:6A:06:65:26:32:28:27

SHA256:

70:A7:3F:7F:37:6B:60:07:42:48:90:45:34:B1:14:82:D5:BF:0E:69:8E:CC:49:8D:F5:25:77:EB:F2:E9:3B:9

Alias name: mozillacert8.pem

SHA1: 3E:2B:F7:F2:03:1B:96:F3:8C:E6:C4:D8:A8:5D:3E:2D:58:47:6A:0F

SHA256:

C7:66:A9:BE:F2:D4:07:1C:86:3A:31:AA:49:20:E8:13:B2:D1:98:60:8C:B7:B7:CF:E2:11:43:B8:36:DF:09:E

Alias name: mozillacert80.pem

SHA1: B8:23:6B:00:2F:1D:16:86:53:01:55:6C:11:A4:37:CA:EB:FF:C3:BB

SHA256:

BD:71:FD:F6:DA:97:E4:CF:62:D1:64:7A:DD:25:81:B0:7D:79:AD:F8:39:7E:B4:EC:BA:9C:5E:84:88:82:14:2

Alias name: mozillacert81.pem

SHA1: 07:E0:32:E0:20:B7:2C:3F:19:2F:06:28:A2:59:3A:19:A7:0F:06:9E

SHA256:

5C:58:46:8D:55:F5:8E:49:7E:74:39:82:D2:B5:00:10:B6:D1:65:37:4A:CF:83:A7:D4:A3:2D:B7:68:C4:40:8

Alias name: mozillacert82.pem

SHA1: 2E:14:DA:EC:28:F0:FA:1E:8E:38:9A:4E:AB:EB:26:C0:0A:D3:83:C3

SHA256:

FC:BF:E2:88:62:06:F7:2B:27:59:3C:8B:07:02:97:E1:2D:76:9E:D1:0E:D7:93:07:05:A8:09:8E:FF:C1:4D:1

Alias name: mozillacert83.pem

SHA1: A0:73:E5:C5:BD:43:61:0D:86:4C:21:13:0A:85:58:57:CC:9C:EA:46

SHA256:

8C:4E:DF:D0:43:48:F3:22:96:9E:7E:29:A4:CD:4D:CA:00:46:55:06:1C:16:E1:B0:76:42:2E:F3:42:AD:63:0

Alias name: mozillacert84.pem

SHA1: D3:C0:63:F2:19:ED:07:3E:34:AD:5D:75:0B:32:76:29:FF:D5:9A:F2

SHA256:

79:3C:BF:45:59:B9:FD:E3:8A:B2:2D:F1:68:69:F6:98:81:AE:14:C4:B0:13:9A:C7:88:A7:8A:1A:FC:CA:02:F

Alias name: mozillacert85.pem

SHA1: CF:9E:87:6D:D3:EB:FC:42:26:97:A3:B5:A3:7A:A0:76:A9:06:23:48

SHA256:

BF:D8:8F:E1:10:1C:41:AE:3E:80:1B:F8:BE:56:35:0E:E9:BA:D1:A6:B9:BD:51:5E:DC:5C:6D:5B:87:11:AC:4

Alias name: mozillacert86.pem

SHA1: 74:2C:31:92:E6:07:E4:24:EB:45:49:54:2B:E1:BB:C5:3E:61:74:E2

SHA256:

E7:68:56:34:EF:AC:F6:9A:CE:93:9A:6B:25:5B:7B:4F:AB:EF:42:93:5B:50:A2:65:AC:B5:CB:60:27:E4:4E:7

Alias name: mozillacert87.pem

SHA1: 5F:3B:8C:F2:F8:10:B3:7D:78:B4:CE:EC:19:19:C3:73:34:B9:C7:74

SHA256:

51:3B:2C:EC:B8:10:D4:CD:E5:DD:85:39:1A:DF:C6:C2:DD:60:D8:7B:B7:36:D2:B5:21:48:4A:A4:7A:0E:BE:F

Alias name: mozillacert88.pem

SHA1: FE:45:65:9B:79:03:5B:98:A1:61:B5:51:2E:AC:DA:58:09:48:22:4D

SHA256:

BC:10:4F:15:A4:8B:E7:09:DC:A5:42:A7:E1:D4:B9:DF:6F:05:45:27:E8:02:EA:A9:2D:59:54:44:25:8A:FE:7

Alias name: mozillacert89.pem

SHA1: C8:EC:8C:87:92:69:CB:4B:AB:39:E9:8D:7E:57:67:F3:14:95:73:9D

SHA256:

E3:89:36:0D:0F:DB:AE:B3:D2:50:58:4B:47:30:31:4E:22:2F:39:C1:56:A0:20:14:4E:8D:96:05:61:79:15:0

Alias name: mozillacert9.pem

SHA1: F4:8B:11:BF:DE:AB:BE:94:54:20:71:E6:41:DE:6B:BE:88:2B:40:B9

SHA256:

76:00:29:5E:EF:E8:5B:9E:1F:D6:24:DB:76:06:2A:AA:AE:59:81:8A:54:D2:77:4C:D4:C0:B2:C0:11:31:E1:B

Alias name: mozillacert90.pem

SHA1: F3:73:B3:87:06:5A:28:84:8A:F2:F3:4A:CE:19:2B:DD:C7:8E:9C:AC

SHA256:

55:92:60:84:EC:96:3A:64:B9:6E:2A:BE:01:CE:0B:A8:6A:64:FB:FE:BC:C7:AA:B5:AF:C1:55:B3:7F:D7:60:6

Alias name: mozillacert91.pem

SHA1: 3B:C0:38:0B:33:C3:F6:A6:0C:86:15:22:93:D9:DF:F5:4B:81:C0:04

SHA256:

C1:B4:82:99:AB:A5:20:8F:E9:63:0A:CE:55:CA:68:A0:3E:DA:5A:51:9C:88:02:A0:D3:A6:73:BE:8F:8E:55:7

Alias name: mozillacert92.pem

SHA1: A3:F1:33:3F:E2:42:BF:CF:C5:D1:4E:8F:39:42:98:40:68:10:D1:A0

SHA256:

E1:78:90:EE:09:A3:FB:F4:F4:8B:9C:41:4A:17:D6:37:B7:A5:06:47:E9:BC:75:23:22:72:7F:CC:17:42:A9:1

Alias name: mozillacert93.pem

SHA1: 31:F1:FD:68:22:63:20:EE:C6:3B:3F:9D:EA:4A:3E:53:7C:7C:39:17

SHA256:

C7:BA:65:67:DE:93:A7:98:AE:1F:AA:79:1E:71:2D:37:8F:AE:1F:93:C4:39:7F:EA:44:1B:B7:CB:E6:FD:59:9

Alias name: mozillacert94.pem

SHA1: 49:0A:75:74:DE:87:0A:47:FE:58:EE:F6:C7:6B:EB:C6:0B:12:40:99

SHA256:

9A:11:40:25:19:7C:5B:B9:5D:94:E6:3D:55:CD:43:79:08:47:B6:46:B2:3C:DF:11:AD:A4:A0:0E:FF:15:FB:4

Alias name: mozillacert95.pem

SHA1: DA:FA:F7:FA:66:84:EC:06:8F:14:50:BD:C7:C2:81:A5:BC:A9:64:57

SHA256:

ED:F7:EB:BC:A2:7A:2A:38:4D:38:7B:7D:40:10:C6:66:E2:ED:B4:84:3E:4C:29:B4:AE:1D:5B:93:32:E6:B2:4

Alias name: mozillacert96.pem

SHA1: 55:A6:72:3E:CB:F2:EC:CD:C3:23:74:70:19:9D:2A:BE:11:E3:81:D1

SHA256:
FD:73:DA:D3:1C:64:4F:F1:B4:3B:EF:0C:CD:DA:96:71:0B:9C:D9:87:5E:CA:7E:31:70:7A:F3:E9:6D:52:2B:B
Alias name: mozillacert97.pem
SHA1: 85:37:1C:A6:E5:50:14:3D:CE:28:03:47:1B:DE:3A:09:E8:F8:77:0F
SHA256:
83:CE:3C:12:29:68:8A:59:3D:48:5F:81:97:3C:0F:91:95:43:1E:DA:37:CC:5E:36:43:0E:79:C7:A8:88:63:8
Alias name: mozillacert98.pem
SHA1: C9:A8:B9:E7:55:80:5E:58:E3:53:77:A7:25:EB:AF:C3:7B:27:CC:D7
SHA256:
3E:84:BA:43:42:90:85:16:E7:75:73:C0:99:2F:09:79:CA:08:4E:46:85:68:1F:F1:95:CC:BA:8A:22:9B:8A:7
Alias name: mozillacert99.pem
SHA1: F1:7F:6F:B6:31:DC:99:E3:A3:C8:7F:FE:1C:F1:81:10:88:D9:60:33
SHA256:
97:8C:D9:66:F2:FA:A0:7B:A7:AA:95:00:D9:C0:2E:9D:77:F2:CD:AD:A6:AD:6B:A7:4A:F4:B9:1C:66:59:3C:5
Alias name: netlockaranyclassgoldfotanusitvany
SHA1: 06:08:3F:59:3F:15:A1:04:A0:69:A4:6B:A9:03:D0:06:B7:97:09:91
SHA256:
6C:61:DA:C3:A2:DE:F0:31:50:6B:E0:36:D2:A6:FE:40:19:94:FB:D1:3D:F9:C8:D4:66:59:92:74:C4:46:EC:9
Alias name: networksolutionscertificateauthority
SHA1: 74:F8:A3:C3:EF:E7:B3:90:06:4B:83:90:3C:21:64:60:20:E5:DF:CE
SHA256:
15:F0:BA:00:A3:AC:7A:F3:AC:88:4C:07:2B:10:11:A0:77:BD:77:C0:97:F4:01:64:B2:F8:59:8A:BD:83:86:0
Alias name: oistewisekeyglobalrootgaca
SHA1: 59:22:A1:E1:5A:EA:16:35:21:F8:98:39:6A:46:46:B0:44:1B:0F:A9
SHA256:
41:C9:23:86:6A:B4:CA:D6:B7:AD:57:80:81:58:2E:02:07:97:A6:CB:DF:4F:FF:78:CE:83:96:B3:89:37:D7:F
Alias name: oistewisekeyglobalrootgbca
SHA1: 0F:F9:40:76:18:D3:D7:6A:4B:98:F0:A8:35:9E:0C:FD:27:AC:CC:ED
SHA256:
6B:9C:08:E8:6E:B0:F7:67:CF:AD:65:CD:98:B6:21:49:E5:49:4A:67:F5:84:5E:7B:D1:ED:01:9F:27:B8:6B:D
Alias name: oistewisekeyglobalrootgcc
SHA1: E0:11:84:5E:34:DE:BE:88:81:B9:9C:F6:16:26:D1:96:1F:C3:B9:31
SHA256:
85:60:F9:1C:36:24:DA:BA:95:70:B5:FE:A0:DB:E3:6F:F1:1A:83:23:BE:94:86:85:4F:B3:F3:4A:55:71:19:8
Alias name: quovadisrootca
SHA1: DE:3F:40:BD:50:93:D3:9B:6C:60:F6:DA:BC:07:62:01:00:89:76:C9
SHA256:
A4:5E:DE:3B:BB:F0:9C:8A:E1:5C:72:EF:C0:72:68:D6:93:A2:1C:99:6F:D5:1E:67:CA:07:94:60:FD:6D:88:7
Alias name: quovadisrootca1g3
SHA1: 1B:8E:EA:57:96:29:1A:C9:39:EA:B8:0A:81:1A:73:73:C0:93:79:67
SHA256:
8A:86:6F:D1:B2:76:B5:7E:57:8E:92:1C:65:82:8A:2B:ED:58:E9:F2:F2:88:05:41:34:B7:F1:F4:BF:C9:CC:7
Alias name: quovadisrootca2
SHA1: CA:3A:FB:CF:12:40:36:4B:44:B2:16:20:88:80:48:39:19:93:7C:F7

SHA256:

85:A0:DD:7D:D7:20:AD:B7:FF:05:F8:3D:54:2B:20:9D:C7:FF:45:28:F7:D6:77:B1:83:89:FE:A5:E5:C4:9E:8

Alias name: quovadisrootca2g3

SHA1: 09:3C:61:F3:8B:8B:DC:7D:55:DF:75:38:02:05:00:E1:25:F5:C8:36

SHA256:

8F:E4:FB:0A:F9:3A:4D:0D:67:DB:0B:EB:B2:3E:37:C7:1B:F3:25:DC:BC:DD:24:0E:A0:4D:AF:58:B4:7E:18:4

Alias name: quovadisrootca3

SHA1: 1F:49:14:F7:D8:74:95:1D:DD:AE:02:C0:BE:FD:3A:2D:82:75:51:85

SHA256:

18:F1:FC:7F:20:5D:F8:AD:DD:EB:7F:E0:07:DD:57:E3:AF:37:5A:9C:4D:8D:73:54:6B:F4:F1:FE:D1:E1:8D:3

Alias name: quovadisrootca3g3

SHA1: 48:12:BD:92:3C:A8:C4:39:06:E7:30:6D:27:96:E6:A4:CF:22:2E:7D

SHA256:

88:EF:81:DE:20:2E:B0:18:45:2E:43:F8:64:72:5C:EA:5F:BD:1F:C2:D9:D2:05:73:07:09:C5:D8:B8:69:0F:4

Alias name: secomevrootca1

SHA1: FE:B8:C4:32:DC:F9:76:9A:CE:AE:3D:D8:90:8F:FD:28:86:65:64:7D

SHA256:

A2:2D:BA:68:1E:97:37:6E:2D:39:7D:72:8A:AE:3A:9B:62:96:B9:FD:BA:60:BC:2E:11:F6:47:F2:C6:75:FB:3

Alias name: secomscrootca1

SHA1: 36:B1:2B:49:F9:81:9E:D7:4C:9E:BC:38:0F:C6:56:8F:5D:AC:B2:F7

SHA256:

E7:5E:72:ED:9F:56:0E:EC:6E:B4:80:00:73:A4:3F:C3:AD:19:19:5A:39:22:82:01:78:95:97:4A:99:02:6B:6

Alias name: secomscrootca2

SHA1: 5F:3B:8C:F2:F8:10:B3:7D:78:B4:CE:EC:19:19:C3:73:34:B9:C7:74

SHA256:

51:3B:2C:EC:B8:10:D4:CD:E5:DD:85:39:1A:DF:C6:C2:DD:60:D8:7B:B7:36:D2:B5:21:48:4A:A4:7A:0E:BE:F

Alias name: secomvalicertclass1ca

SHA1: E5:DF:74:3C:B6:01:C4:9B:98:43:DC:AB:8C:E8:6A:81:10:9F:E4:8E

SHA256:

F4:C1:49:55:1A:30:13:A3:5B:C7:BF:FE:17:A7:F3:44:9B:C1:AB:5B:5A:0A:E7:4B:06:C2:3B:90:00:4C:01:0

Alias name: secureglobalca

SHA1: 3A:44:73:5A:E5:81:90:1F:24:86:61:46:1E:3B:9C:C4:5F:F5:3A:1B

SHA256:

42:00:F5:04:3A:C8:59:0E:BB:52:7D:20:9E:D1:50:30:29:FB:CB:D4:1C:A1:B5:06:EC:27:F1:5A:DE:7D:AC:6

Alias name: securesignrootca11

SHA1: 3B:C4:9F:48:F8:F3:73:A0:9C:1E:BD:F8:5B:B1:C3:65:C7:D8:11:B3

SHA256:

BF:0F:EE:FB:9E:3A:58:1A:D5:F9:E9:DB:75:89:98:57:43:D2:61:08:5C:4D:31:4F:6F:5D:72:59:AA:42:16:1

Alias name: securetrustca

SHA1: 87:82:C6:C3:04:35:3B:CF:D2:96:92:D2:59:3E:7D:44:D9:34:FF:11

SHA256:

F1:C1:B5:0A:E5:A2:0D:D8:03:0E:C9:F6:BC:24:82:3D:D3:67:B5:25:57:59:B4:E7:1B:61:FC:E9:F7:37:5D:7

Alias name: securitycommunicationrootca

SHA1: 36:B1:2B:49:F9:81:9E:D7:4C:9E:BC:38:0F:C6:56:8F:5D:AC:B2:F7

SHA256:
E7:5E:72:ED:9F:56:0E:EC:6E:B4:80:00:73:A4:3F:C3:AD:19:19:5A:39:22:82:01:78:95:97:4A:99:02:6B:6
Alias name: securitycommunicationrootca2
SHA1: 5F:3B:8C:F2:F8:10:B3:7D:78:B4:CE:EC:19:19:C3:73:34:B9:C7:74
SHA256:
51:3B:2C:EC:B8:10:D4:CD:E5:DD:85:39:1A:DF:C6:C2:DD:60:D8:7B:B7:36:D2:B5:21:48:4A:A4:7A:0E:BE:F
Alias name: soneraaclass1ca
SHA1: 07:47:22:01:99:CE:74:B9:7C:B0:3D:79:B2:64:A2:C8:55:E9:33:FF
SHA256:
CD:80:82:84:CF:74:6F:F2:FD:6E:B5:8A:A1:D5:9C:4A:D4:B3:CA:56:FD:C6:27:4A:89:26:A7:83:5F:32:31:3
Alias name: soneraaclass2ca
SHA1: 37:F7:6D:E6:07:7C:90:C5:B1:3E:93:1A:B7:41:10:B4:F2:E4:9A:27
SHA256:
79:08:B4:03:14:C1:38:10:0B:51:8D:07:35:80:7F:FB:FC:F8:51:8A:00:95:33:71:05:BA:38:6B:15:3D:D9:2
Alias name: soneraaclass2rootca
SHA1: 37:F7:6D:E6:07:7C:90:C5:B1:3E:93:1A:B7:41:10:B4:F2:E4:9A:27
SHA256:
79:08:B4:03:14:C1:38:10:0B:51:8D:07:35:80:7F:FB:FC:F8:51:8A:00:95:33:71:05:BA:38:6B:15:3D:D9:2
Alias name: sslcomevrootcertificationauthorityecc
SHA1: 4C:DD:51:A3:D1:F5:20:32:14:B0:C6:C5:32:23:03:91:C7:46:42:6D
SHA256:
22:A2:C1:F7:BD:ED:70:4C:C1:E7:01:B5:F4:08:C3:10:88:0F:E9:56:B5:DE:2A:4A:44:F9:9C:87:3A:25:A7:C
Alias name: sslcomevrootcertificationauthorityrsar2
SHA1: 74:3A:F0:52:9B:D0:32:A0:F4:4A:83:CD:D4:BA:A9:7B:7C:2E:C4:9A
SHA256:
2E:7B:F1:6C:C2:24:85:A7:BB:E2:AA:86:96:75:07:61:B0:AE:39:BE:3B:2F:E9:D0:CC:6D:4E:F7:34:91:42:5
Alias name: sslcomrootcertificationauthorityecc
SHA1: C3:19:7C:39:24:E6:54:AF:1B:C4:AB:20:95:7A:E2:C3:0E:13:02:6A
SHA256:
34:17:BB:06:CC:60:07:DA:1B:96:1C:92:0B:8A:B4:CE:3F:AD:82:0E:4A:A3:0B:9A:CB:C4:A7:4E:BD:CE:BC:6
Alias name: sslcomrootcertificationauthorityrsa
SHA1: B7:AB:33:08:D1:EA:44:77:BA:14:80:12:5A:6F:BD:A9:36:49:0C:BB
SHA256:
85:66:6A:56:2E:E0:BE:5C:E9:25:C1:D8:89:0A:6F:76:A8:7E:C1:6D:4D:7D:5F:29:EA:74:19:CF:20:12:3B:6
Alias name: staatdernederlandenrevrootca
SHA1: 76:E2:7E:C1:4F:DB:82:C1:C0:A6:75:B5:05:BE:3D:29:B4:ED:DB:BB
SHA256:
4D:24:91:41:4C:FE:95:67:46:EC:4C:EF:A6:CF:6F:72:E2:8A:13:29:43:2F:9D:8A:90:7A:C4:CB:5D:AD:C1:5
Alias name: staatdernederlandenrootcag3
SHA1: D8:EB:6B:41:51:92:59:E0:F3:E7:85:00:C0:3D:B6:88:97:C9:EE:FC
SHA256:
3C:4F:B0:B9:5A:B8:B3:00:32:F4:32:B8:6F:53:5F:E1:72:C1:85:D0:FD:39:86:58:37:CF:36:18:7F:A6:F4:2
Alias name: starfieldclass2ca
SHA1: AD:7E:1C:28:B0:64:EF:8F:60:03:40:20:14:C3:D0:E3:37:0E:B5:8A

SHA256:
14:65:FA:20:53:97:B8:76:FA:A6:F0:A9:95:8E:55:90:E4:0F:CC:7F:AA:4F:B7:C2:C8:67:75:21:FB:5F:B6:5
Alias name: starfieldrootcertificateauthorityg2
SHA1: B5:1C:06:7C:EE:2B:0C:3D:F8:55:AB:2D:92:F4:FE:39:D4:E7:0F:0E
SHA256:
2C:E1:CB:0B:F9:D2:F9:E1:02:99:3F:BE:21:51:52:C3:B2:DD:0C:AB:DE:1C:68:E5:31:9B:83:91:54:DB:B7:F
Alias name: starfieldrootg2ca
SHA1: B5:1C:06:7C:EE:2B:0C:3D:F8:55:AB:2D:92:F4:FE:39:D4:E7:0F:0E
SHA256:
2C:E1:CB:0B:F9:D2:F9:E1:02:99:3F:BE:21:51:52:C3:B2:DD:0C:AB:DE:1C:68:E5:31:9B:83:91:54:DB:B7:F
Alias name: starfieldservicesrootcertificateauthorityg2
SHA1: 92:5A:8F:8D:2C:6D:04:E0:66:5F:59:6A:FF:22:D8:63:E8:25:6F:3F
SHA256:
56:8D:69:05:A2:C8:87:08:A4:B3:02:51:90:ED:CF:ED:B1:97:4A:60:6A:13:C6:E5:29:0F:CB:2A:E6:3E:DA:B
Alias name: starfieldservicesrootg2ca
SHA1: 92:5A:8F:8D:2C:6D:04:E0:66:5F:59:6A:FF:22:D8:63:E8:25:6F:3F
SHA256:
56:8D:69:05:A2:C8:87:08:A4:B3:02:51:90:ED:CF:ED:B1:97:4A:60:6A:13:C6:E5:29:0F:CB:2A:E6:3E:DA:B
Alias name: swisssigngoldcag2
SHA1: D8:C5:38:8A:B7:30:1B:1B:6E:D4:7A:E6:45:25:3A:6F:9F:1A:27:61
SHA256:
62:DD:0B:E9:B9:F5:0A:16:3E:A0:F8:E7:5C:05:3B:1E:CA:57:EA:55:C8:68:8F:64:7C:68:81:F2:C8:35:7B:9
Alias name: swisssignoldg2ca
SHA1: D8:C5:38:8A:B7:30:1B:1B:6E:D4:7A:E6:45:25:3A:6F:9F:1A:27:61
SHA256:
62:DD:0B:E9:B9:F5:0A:16:3E:A0:F8:E7:5C:05:3B:1E:CA:57:EA:55:C8:68:8F:64:7C:68:81:F2:C8:35:7B:9
Alias name: swisssignplatinumg2ca
SHA1: 56:E0:FA:C0:3B:8F:18:23:55:18:E5:D3:11:CA:E8:C2:43:31:AB:66
SHA256:
3B:22:2E:56:67:11:E9:92:30:0D:C0:B1:5A:B9:47:3D:AF:DE:F8:C8:4D:0C:EF:7D:33:17:B4:C1:82:1D:14:3
Alias name: swisssignsilvercag2
SHA1: 9B:AA:E5:9F:56:EE:21:CB:43:5A:BE:25:93:DF:A7:F0:40:D1:1D:CB
SHA256:
BE:6C:4D:A2:BB:B9:BA:59:B6:F3:93:97:68:37:42:46:C3:C0:05:99:3F:A9:8F:02:0D:1D:ED:BE:D4:8A:81:D
Alias name: swisssignsilverg2ca
SHA1: 9B:AA:E5:9F:56:EE:21:CB:43:5A:BE:25:93:DF:A7:F0:40:D1:1D:CB
SHA256:
BE:6C:4D:A2:BB:B9:BA:59:B6:F3:93:97:68:37:42:46:C3:C0:05:99:3F:A9:8F:02:0D:1D:ED:BE:D4:8A:81:D
Alias name: szafirrootca2
SHA1: E2:52:FA:95:3F:ED:DB:24:60:BD:6E:28:F3:9C:CC:CF:5E:B3:3F:DE
SHA256:
A1:33:9D:33:28:1A:0B:56:E5:57:D3:D3:2B:1C:E7:F9:36:7E:B0:94:BD:5F:A7:2A:7E:50:04:C8:DE:D7:CA:F
Alias name: teliasonerarootcav1
SHA1: 43:13:BB:96:F1:D5:86:9B:C1:4E:6A:92:F6:CF:F6:34:69:87:82:37

SHA256:

DD:69:36:FE:21:F8:F0:77:C1:23:A1:A5:21:C1:22:24:F7:22:55:B7:3E:03:A7:26:06:93:E8:A2:4B:0F:A3:8

Alias name: thawtepessoalfreemailca

SHA1: E6:18:83:AE:84:CA:C1:C1:CD:52:AD:E8:E9:25:2B:45:A6:4F:B7:E2

SHA256:

5B:38:BD:12:9E:83:D5:A0:CA:D2:39:21:08:94:90:D5:0D:4A:AE:37:04:28:F8:DD:FF:FF:FA:4C:15:64:E1:8

Alias name: thawtepessoalpremiumserverca

SHA1: E0:AB:05:94:20:72:54:93:05:60:62:02:36:70:F7:CD:2E:FC:66:66

SHA256:

3F:9F:27:D5:83:20:4B:9E:09:C8:A3:D2:06:6C:4B:57:D3:A2:47:9C:36:93:65:08:80:50:56:98:10:5D:BC:E

Alias name: thawteprimaryrootca

SHA1: 91:C6:D6:EE:3E:8A:C8:63:84:E5:48:C2:99:29:5C:75:6C:81:7B:81

SHA256:

8D:72:2F:81:A9:C1:13:C0:79:1D:F1:36:A2:96:6D:B2:6C:95:0A:97:1D:B4:6B:41:99:F4:EA:54:B7:8B:FB:9

Alias name: thawteprimaryrootcag2

SHA1: AA:DB:BC:22:23:8F:C4:01:A1:27:BB:38:DD:F4:1D:DB:08:9E:F0:12

SHA256:

A4:31:0D:50:AF:18:A6:44:71:90:37:2A:86:AF:AF:8B:95:1F:FB:43:1D:83:7F:1E:56:88:B4:59:71:ED:15:5

Alias name: thawteprimaryrootcag3

SHA1: F1:8B:53:8D:1B:E9:03:B6:A6:F0:56:43:5B:17:15:89:CA:F3:6B:F2

SHA256:

4B:03:F4:58:07:AD:70:F2:1B:FC:2C:AE:71:C9:FD:E4:60:4C:06:4C:F5:FF:B6:86:BA:E5:DB:AA:D7:FD:D3:4

Alias name: thawteserverca

SHA1: 9F:AD:91:A6:CE:6A:C6:C5:00:47:C4:4E:C9:D4:A5:0D:92:D8:49:79

SHA256:

87:C6:78:BF:B8:B2:5F:38:F7:E9:7B:33:69:56:BB:CF:14:4B:BA:CA:A5:36:47:E6:1A:23:25:BC:10:55:31:6

Alias name: trustcenterclass2caii

SHA1: AE:50:83:ED:7C:F4:5C:BC:8F:61:C6:21:FE:68:5D:79:42:21:15:6E

SHA256:

E6:B8:F8:76:64:85:F8:07:AE:7F:8D:AC:16:70:46:1F:07:C0:A1:3E:EF:3A:1F:F7:17:53:8D:7A:BA:D3:91:B

Alias name: trustcenterclass4caii

SHA1: A6:9A:91:FD:05:7F:13:6A:42:63:0B:B1:76:0D:2D:51:12:0C:16:50

SHA256:

32:66:96:7E:59:CD:68:00:8D:9D:D3:20:81:11:85:C7:04:20:5E:8D:95:FD:D8:4F:1C:7B:31:1E:67:04:FC:3

Alias name: trustcenteruniversalcai

SHA1: 6B:2F:34:AD:89:58:BE:62:FD:B0:6B:5C:CE:BB:9D:D9:4F:4E:39:F3

SHA256:

EB:F3:C0:2A:87:89:B1:FB:7D:51:19:95:D6:63:B7:29:06:D9:13:CE:0D:5E:10:56:8A:8A:77:E2:58:61:67:E

Alias name: trustcorecal

SHA1: 58:D1:DF:95:95:67:6B:63:C0:F0:5B:1C:17:4D:8B:84:0B:C8:78:BD

SHA256:

5A:88:5D:B1:9C:01:D9:12:C5:75:93:88:93:8C:AF:BB:DF:03:1A:B2:D4:8E:91:EE:15:58:9B:42:97:1D:03:9

Alias name: trustcorootcertca1

SHA1: FF:BD:CD:E7:82:C8:43:5E:3C:6F:26:86:5C:CA:A8:3A:45:5B:C3:0A

SHA256:
D4:0E:9C:86:CD:8F:E4:68:C1:77:69:59:F4:9E:A7:74:FA:54:86:84:B6:C4:06:F3:90:92:61:F4:DC:E2:57:5
Alias name: trustcorrootcertca2
SHA1: B8:BE:6D:CB:56:F1:55:B9:63:D4:12:CA:4E:06:34:C7:94:B2:1C:C0
SHA256:
07:53:E9:40:37:8C:1B:D5:E3:83:6E:39:5D:AE:A5:CB:83:9E:50:46:F1:BD:0E:AE:19:51:CF:10:FE:C7:C9:6
Alias name: trustisfpsrootca
SHA1: 3B:C0:38:0B:33:C3:F6:A6:0C:86:15:22:93:D9:DF:F5:4B:81:C0:04
SHA256:
C1:B4:82:99:AB:A5:20:8F:E9:63:0A:CE:55:CA:68:A0:3E:DA:5A:51:9C:88:02:A0:D3:A6:73:BE:8F:8E:55:7
Alias name: ttelesecglobalrootclass2
SHA1: 59:0D:2D:7D:88:4F:40:2E:61:7E:A5:62:32:17:65:CF:17:D8:94:E9
SHA256:
91:E2:F5:78:8D:58:10:EB:A7:BA:58:73:7D:E1:54:8A:8E:CA:CD:01:45:98:BC:0B:14:3E:04:1B:17:05:25:5
Alias name: ttelesecglobalrootclass2ca
SHA1: 59:0D:2D:7D:88:4F:40:2E:61:7E:A5:62:32:17:65:CF:17:D8:94:E9
SHA256:
91:E2:F5:78:8D:58:10:EB:A7:BA:58:73:7D:E1:54:8A:8E:CA:CD:01:45:98:BC:0B:14:3E:04:1B:17:05:25:5
Alias name: ttelesecglobalrootclass3
SHA1: 55:A6:72:3E:CB:F2:EC:CD:C3:23:74:70:19:9D:2A:BE:11:E3:81:D1
SHA256:
FD:73:DA:D3:1C:64:4F:F1:B4:3B:EF:0C:CD:DA:96:71:0B:9C:D9:87:5E:CA:7E:31:70:7A:F3:E9:6D:52:2B:B
Alias name: ttelesecglobalrootclass3ca
SHA1: 55:A6:72:3E:CB:F2:EC:CD:C3:23:74:70:19:9D:2A:BE:11:E3:81:D1
SHA256:
FD:73:DA:D3:1C:64:4F:F1:B4:3B:EF:0C:CD:DA:96:71:0B:9C:D9:87:5E:CA:7E:31:70:7A:F3:E9:6D:52:2B:B
Alias name: tubitakkamusmsslkoksertifikasisurum1
SHA1: 31:43:64:9B:EC:CE:27:EC:ED:3A:3F:0B:8F:0D:E4:E8:91:DD:EE:CA
SHA256:
46:ED:C3:68:90:46:D5:3A:45:3F:B3:10:4A:B8:0D:CA:EC:65:8B:26:60:EA:16:29:DD:7E:86:79:90:64:87:1
Alias name: twcaglobalrootca
SHA1: 9C:BB:48:53:F6:A4:F6:D3:52:A4:E8:32:52:55:60:13:F5:AD:AF:65
SHA256:
59:76:90:07:F7:68:5D:0F:CD:50:87:2F:9F:95:D5:75:5A:5B:2B:45:7D:81:F3:69:2B:61:0A:98:67:2F:0E:1
Alias name: twcarootcertificationauthority
SHA1: CF:9E:87:6D:D3:EB:FC:42:26:97:A3:B5:A3:7A:A0:76:A9:06:23:48
SHA256:
BF:D8:8F:E1:10:1C:41:AE:3E:80:1B:F8:BE:56:35:0E:E9:BA:D1:A6:B9:BD:51:5E:DC:5C:6D:5B:87:11:AC:4
Alias name: ucaextendedvalidationroot
SHA1: A3:A1:B0:6F:24:61:23:4A:E3:36:A5:C2:37:FC:A6:FF:DD:F0:D7:3A
SHA256:
D4:3A:F9:B3:54:73:75:5C:96:84:FC:06:D7:D8:CB:70:EE:5C:28:E7:73:FB:29:4E:B4:1E:E7:17:22:92:4D:2
Alias name: ucaglobalalg2root
SHA1: 28:F9:78:16:19:7A:FF:18:25:18:AA:44:FE:C1:A0:CE:5C:B6:4C:8A

SHA256:

9B:EA:11:C9:76:FE:01:47:64:C1:BE:56:A6:F9:14:B5:A5:60:31:7A:BD:99:88:39:33:82:E5:16:1A:A0:49:3

Alias name: usertrustecc

SHA1: D1:CB:CA:5D:B2:D5:2A:7F:69:3B:67:4D:E5:F0:5A:1D:0C:95:7D:F0

SHA256:

4F:F4:60:D5:4B:9C:86:DA:BF:BC:FC:57:12:E0:40:0D:2B:ED:3F:BC:4D:4F:BD:AA:86:E0:6A:DC:D2:A9:AD:7

Alias name: usertrustecccertificationauthority

SHA1: D1:CB:CA:5D:B2:D5:2A:7F:69:3B:67:4D:E5:F0:5A:1D:0C:95:7D:F0

SHA256:

4F:F4:60:D5:4B:9C:86:DA:BF:BC:FC:57:12:E0:40:0D:2B:ED:3F:BC:4D:4F:BD:AA:86:E0:6A:DC:D2:A9:AD:7

Alias name: usertrustrsa

SHA1: 2B:8F:1B:57:33:0D:BB:A2:D0:7A:6C:51:F7:0E:E9:0D:DA:B9:AD:8E

SHA256:

E7:93:C9:B0:2F:D8:AA:13:E2:1C:31:22:8A:CC:B0:81:19:64:3B:74:9C:89:89:64:B1:74:6D:46:C3:D4:CB:D

Alias name: usertrustrsacertificationauthority

SHA1: 2B:8F:1B:57:33:0D:BB:A2:D0:7A:6C:51:F7:0E:E9:0D:DA:B9:AD:8E

SHA256:

E7:93:C9:B0:2F:D8:AA:13:E2:1C:31:22:8A:CC:B0:81:19:64:3B:74:9C:89:89:64:B1:74:6D:46:C3:D4:CB:D

Alias name: utndatacorpsgcca

SHA1: 58:11:9F:0E:12:82:87:EA:50:FD:D9:87:45:6F:4F:78:DC:FA:D6:D4

SHA256:

85:FB:2F:91:DD:12:27:5A:01:45:B6:36:53:4F:84:02:4A:D6:8B:69:B8:EE:88:68:4F:F7:11:37:58:05:B3:4

Alias name: utnuserfirstclientauthemailca

SHA1: B1:72:B1:A5:6D:95:F9:1F:E5:02:87:E1:4D:37:EA:6A:44:63:76:8A

SHA256:

43:F2:57:41:2D:44:0D:62:74:76:97:4F:87:7D:A8:F1:FC:24:44:56:5A:36:7A:E6:0E:DD:C2:7A:41:25:31:A

Alias name: utnuserfirsthardwareca

SHA1: 04:83:ED:33:99:AC:36:08:05:87:22:ED:BC:5E:46:00:E3:BE:F9:D7

SHA256:

6E:A5:47:41:D0:04:66:7E:ED:1B:48:16:63:4A:A3:A7:9E:6E:4B:96:95:0F:82:79:DA:FC:8D:9B:D8:81:21:3

Alias name: utnuserfirstobjectca

SHA1: E1:2D:FB:4B:41:D7:D9:C3:2B:30:51:4B:AC:1D:81:D8:38:5E:2D:46

SHA256:

6F:FF:78:E4:00:A7:0C:11:01:1C:D8:59:77:C4:59:FB:5A:F9:6A:3D:F0:54:08:20:D0:F4:B8:60:78:75:E5:8

Alias name: valicertclass2ca

SHA1: 31:7A:2A:D0:7F:2B:33:5E:F5:A1:C3:4E:4B:57:E8:B7:D8:F1:FC:A6

SHA256:

58:D0:17:27:9C:D4:DC:63:AB:DD:B1:96:A6:C9:90:6C:30:C4:E0:87:83:EA:E8:C1:60:99:54:D6:93:55:59:6

Alias name: verisignc1g1.pem

SHA1: 90:AE:A2:69:85:FF:14:80:4C:43:49:52:EC:E9:60:84:77:AF:55:6F

SHA256:

D1:7C:D8:EC:D5:86:B7:12:23:8A:48:2C:E4:6F:A5:29:39:70:74:2F:27:6D:8A:B6:A9:E4:6E:E0:28:8F:33:5

Alias name: verisignc1g2.pem

SHA1: 27:3E:E1:24:57:FD:C4:F9:0C:55:E8:2B:56:16:7F:62:F5:32:E5:47

SHA256:
34:1D:E9:8B:13:92:AB:F7:F4:AB:90:A9:60:CF:25:D4:BD:6E:C6:5B:9A:51:CE:6E:D0:67:D0:0E:C7:CE:9B:7
Alias name: verisignc1g3.pem
SHA1: 20:42:85:DC:F7:EB:76:41:95:57:8E:13:6B:D4:B7:D1:E9:8E:46:A5
SHA256:
CB:B5:AF:18:5E:94:2A:24:02:F9:EA:CB:C0:ED:5B:B8:76:EE:A3:C1:22:36:23:D0:04:47:E4:F3:BA:55:4B:6
Alias name: verisignc1g6.pem
SHA1: 51:7F:61:1E:29:91:6B:53:82:FB:72:E7:44:D9:8D:C3:CC:53:6D:64
SHA256:
9D:19:0B:2E:31:45:66:68:5B:E8:A8:89:E2:7A:A8:C7:D7:AE:1D:8A:AD:DB:A3:C1:EC:F9:D2:48:63:CD:34:B
Alias name: verisignc2g1.pem
SHA1: 67:82:AA:E0:ED:EE:E2:1A:58:39:D3:C0:CD:14:68:0A:4F:60:14:2A
SHA256:
BD:46:9F:F4:5F:AA:E7:C5:4C:CB:D6:9D:3F:3B:00:22:55:D9:B0:6B:10:B1:D0:FA:38:8B:F9:6B:91:8B:2C:E
Alias name: verisignc2g2.pem
SHA1: B3:EA:C4:47:76:C9:C8:1C:EA:F2:9D:95:B6:CC:A0:08:1B:67:EC:9D
SHA256:
3A:43:E2:20:FE:7F:3E:A9:65:3D:1E:21:74:2E:AC:2B:75:C2:0F:D8:98:03:05:BC:50:2C:AF:8C:2D:9B:41:A
Alias name: verisignc2g3.pem
SHA1: 61:EF:43:D7:7F:CA:D4:61:51:BC:98:E0:C3:59:12:AF:9F:EB:63:11
SHA256:
92:A9:D9:83:3F:E1:94:4D:B3:66:E8:BF:AE:7A:95:B6:48:0C:2D:6C:6C:2A:1B:E6:5D:42:36:B6:08:FC:A1:B
Alias name: verisignc2g6.pem
SHA1: 40:B3:31:A0:E9:BF:E8:55:BC:39:93:CA:70:4F:4E:C2:51:D4:1D:8F
SHA256:
CB:62:7D:18:B5:8A:D5:6D:DE:33:1A:30:45:6B:C6:5C:60:1A:4E:9B:18:DE:DC:EA:08:E7:DA:AA:07:81:5F:F
Alias name: verisignc3g1.pem
SHA1: A1:DB:63:93:91:6F:17:E4:18:55:09:40:04:15:C7:02:40:B0:AE:6B
SHA256:
A4:B6:B3:99:6F:C2:F3:06:B3:FD:86:81:BD:63:41:3D:8C:50:09:CC:4F:A3:29:C2:CC:F0:E2:FA:1B:14:03:0
Alias name: verisignc3g2.pem
SHA1: 85:37:1C:A6:E5:50:14:3D:CE:28:03:47:1B:DE:3A:09:E8:F8:77:0F
SHA256:
83:CE:3C:12:29:68:8A:59:3D:48:5F:81:97:3C:0F:91:95:43:1E:DA:37:CC:5E:36:43:0E:79:C7:A8:88:63:8
Alias name: verisignc3g3.pem
SHA1: 13:2D:0D:45:53:4B:69:97:CD:B2:D5:C3:39:E2:55:76:60:9B:5C:C6
SHA256:
EB:04:CF:5E:B1:F3:9A:FA:76:2F:2B:B1:20:F2:96:CB:A5:20:C1:B9:7D:B1:58:95:65:B8:1C:B9:A1:7B:72:4
Alias name: verisignc3g4.pem
SHA1: 22:D5:D8:DF:8F:02:31:D1:8D:F7:9D:B7:CF:8A:2D:64:C9:3F:6C:3A
SHA256:
69:DD:D7:EA:90:BB:57:C9:3E:13:5D:C8:5E:A6:FC:D5:48:0B:60:32:39:BD:C4:54:FC:75:8B:2A:26:CF:7F:7
Alias name: verisignc3g5.pem
SHA1: 4E:B6:D5:78:49:9B:1C:CF:5F:58:1E:AD:56:BE:3D:9B:67:44:A5:E5

SHA256:
9A:CF:AB:7E:43:C8:D8:80:D0:6B:26:2A:94:DE:EE:E4:B4:65:99:89:C3:D0:CA:F1:9B:AF:64:05:E4:1A:B7:D
Alias name: verisignc4g2.pem
SHA1: 0B:77:BE:BB:CB:7A:A2:47:05:DE:CC:0F:BD:6A:02:FC:7A:BD:9B:52
SHA256:
44:64:0A:0A:0E:4D:00:0F:BD:57:4D:2B:8A:07:BD:B4:D1:DF:ED:3B:45:BA:AB:A7:6F:78:57:78:C7:01:19:6
Alias name: verisignc4g3.pem
SHA1: C8:EC:8C:87:92:69:CB:4B:AB:39:E9:8D:7E:57:67:F3:14:95:73:9D
SHA256:
E3:89:36:0D:0F:DB:AE:B3:D2:50:58:4B:47:30:31:4E:22:2F:39:C1:56:A0:20:14:4E:8D:96:05:61:79:15:0
Alias name: verisignclass1ca
SHA1: CE:6A:64:A3:09:E4:2F:BB:D9:85:1C:45:3E:64:09:EA:E8:7D:60:F1
SHA256:
51:84:7C:8C:BD:2E:9A:72:C9:1E:29:2D:2A:E2:47:D7:DE:1E:3F:D2:70:54:7A:20:EF:7D:61:0F:38:B8:84:2
Alias name: verisignclass1g2ca
SHA1: 27:3E:E1:24:57:FD:C4:F9:0C:55:E8:2B:56:16:7F:62:F5:32:E5:47
SHA256:
34:1D:E9:8B:13:92:AB:F7:F4:AB:90:A9:60:CF:25:D4:BD:6E:C6:5B:9A:51:CE:6E:D0:67:D0:0E:C7:CE:9B:7
Alias name: verisignclass1g3ca
SHA1: 20:42:85:DC:F7:EB:76:41:95:57:8E:13:6B:D4:B7:D1:E9:8E:46:A5
SHA256:
CB:B5:AF:18:5E:94:2A:24:02:F9:EA:CB:C0:ED:5B:B8:76:EE:A3:C1:22:36:23:D0:04:47:E4:F3:BA:55:4B:6
Alias name: verisignclass2g2ca
SHA1: B3:EA:C4:47:76:C9:C8:1C:EA:F2:9D:95:B6:CC:A0:08:1B:67:EC:9D
SHA256:
3A:43:E2:20:FE:7F:3E:A9:65:3D:1E:21:74:2E:AC:2B:75:C2:0F:D8:98:03:05:BC:50:2C:AF:8C:2D:9B:41:A
Alias name: verisignclass2g3ca
SHA1: 61:EF:43:D7:7F:CA:D4:61:51:BC:98:E0:C3:59:12:AF:9F:EB:63:11
SHA256:
92:A9:D9:83:3F:E1:94:4D:B3:66:E8:BF:AE:7A:95:B6:48:0C:2D:6C:6C:2A:1B:E6:5D:42:36:B6:08:FC:A1:B
Alias name: verisignclass3ca
SHA1: A1:DB:63:93:91:6F:17:E4:18:55:09:40:04:15:C7:02:40:B0:AE:6B
SHA256:
A4:B6:B3:99:6F:C2:F3:06:B3:FD:86:81:BD:63:41:3D:8C:50:09:CC:4F:A3:29:C2:CC:F0:E2:FA:1B:14:03:0
Alias name: verisignclass3g2ca
SHA1: 85:37:1C:A6:E5:50:14:3D:CE:28:03:47:1B:DE:3A:09:E8:F8:77:0F
SHA256:
83:CE:3C:12:29:68:8A:59:3D:48:5F:81:97:3C:0F:91:95:43:1E:DA:37:CC:5E:36:43:0E:79:C7:A8:88:63:8
Alias name: verisignclass3g3ca
SHA1: 13:2D:0D:45:53:4B:69:97:CD:B2:D5:C3:39:E2:55:76:60:9B:5C:C6
SHA256:
EB:04:CF:5E:B1:F3:9A:FA:76:2F:2B:B1:20:F2:96:CB:A5:20:C1:B9:7D:B1:58:95:65:B8:1C:B9:A1:7B:72:4
Alias name: verisignclass3g4ca
SHA1: 22:D5:D8:DF:8F:02:31:D1:8D:F7:9D:B7:CF:8A:2D:64:C9:3F:6C:3A

SHA256:
69:DD:D7:EA:90:BB:57:C9:3E:13:5D:C8:5E:A6:FC:D5:48:0B:60:32:39:BD:C4:54:FC:75:8B:2A:26:CF:7F:7
Alias name: verisignclass3g5ca
SHA1: 4E:B6:D5:78:49:9B:1C:CF:5F:58:1E:AD:56:BE:3D:9B:67:44:A5:E5
SHA256:
9A:CF:AB:7E:43:C8:D8:80:D0:6B:26:2A:94:DE:EE:E4:B4:65:99:89:C3:D0:CA:F1:9B:AF:64:05:E4:1A:B7:D
Alias name: verisignclass3publicprimarycertificationauthorityg4
SHA1: 22:D5:D8:DF:8F:02:31:D1:8D:F7:9D:B7:CF:8A:2D:64:C9:3F:6C:3A
SHA256:
69:DD:D7:EA:90:BB:57:C9:3E:13:5D:C8:5E:A6:FC:D5:48:0B:60:32:39:BD:C4:54:FC:75:8B:2A:26:CF:7F:7
Alias name: verisignclass3publicprimarycertificationauthorityg5
SHA1: 4E:B6:D5:78:49:9B:1C:CF:5F:58:1E:AD:56:BE:3D:9B:67:44:A5:E5
SHA256:
9A:CF:AB:7E:43:C8:D8:80:D0:6B:26:2A:94:DE:EE:E4:B4:65:99:89:C3:D0:CA:F1:9B:AF:64:05:E4:1A:B7:D
Alias name: verisignroot.pem
SHA1: 36:79:CA:35:66:87:72:30:4D:30:A5:FB:87:3B:0F:A7:7B:B7:0D:54
SHA256:
23:99:56:11:27:A5:71:25:DE:8C:EF:EA:61:0D:DF:2F:A0:78:B5:C8:06:7F:4E:82:82:90:BF:B8:60:E8:4B:3
Alias name: verisigntsaca
SHA1: 20:CE:B1:F0:F5:1C:0E:19:A9:F3:8D:B1:AA:8E:03:8C:AA:7A:C7:01
SHA256:
CB:6B:05:D9:E8:E5:7C:D8:82:B1:0B:4D:B7:0D:E4:BB:1D:E4:2B:A4:8A:7B:D0:31:8B:63:5B:F6:E7:78:1A:9
Alias name: verisignuniversalrootca
SHA1: 36:79:CA:35:66:87:72:30:4D:30:A5:FB:87:3B:0F:A7:7B:B7:0D:54
SHA256:
23:99:56:11:27:A5:71:25:DE:8C:EF:EA:61:0D:DF:2F:A0:78:B5:C8:06:7F:4E:82:82:90:BF:B8:60:E8:4B:3
Alias name: verisignuniversalrootcertificationauthority
SHA1: 36:79:CA:35:66:87:72:30:4D:30:A5:FB:87:3B:0F:A7:7B:B7:0D:54
SHA256:
23:99:56:11:27:A5:71:25:DE:8C:EF:EA:61:0D:DF:2F:A0:78:B5:C8:06:7F:4E:82:82:90:BF:B8:60:E8:4B:3
Alias name: xrampglobalca
SHA1: B8:01:86:D1:EB:9C:86:A5:41:04:CF:30:54:F3:4C:52:B7:E5:58:C6
SHA256:
CE:CD:DC:90:50:99:D8:DA:DF:C5:B1:D2:09:B7:37:CB:E2:C1:8C:FB:2C:10:C0:FF:0B:CF:0D:32:86:FC:1A:A
Alias name: xrampglobalcaroot
SHA1: B8:01:86:D1:EB:9C:86:A5:41:04:CF:30:54:F3:4C:52:B7:E5:58:C6
SHA256:
CE:CD:DC:90:50:99:D8:DA:DF:C5:B1:D2:09:B7:37:CB:E2:C1:8C:FB:2C:10:C0:FF:0B:CF:0D:32:86:FC:1A:A

Use AWS WAF to protect your REST APIs in API Gateway

AWS WAF is a web application firewall that helps protect web applications and APIs from attacks. It enables you to configure a set of rules called a web access control list (web ACL) that allow, block,

or count web requests based on customizable web security rules and conditions that you define. For more information, see [How AWS WAF Works](#).

You can use AWS WAF to protect your API Gateway REST API from common web exploits, such as SQL injection and cross-site scripting (XSS) attacks. These could affect API availability and performance, compromise security, or consume excessive resources. For example, you can create rules to allow or block requests from specified IP address ranges, requests from CIDR blocks, requests that originate from a specific country or region, requests that contain malicious SQL code, or requests that contain malicious script.

You can also create rules that match a specified string or a regular expression pattern in HTTP headers, method, query string, URI, and the request body (limited to the first 64 KB). Additionally, you can create rules to block attacks from specific user agents, bad bots, and content scrapers. For example, you can use rate-based rules to specify the number of web requests that are allowed by each client IP in a trailing, continuously updated, 5-minute period.

⚠ Important

AWS WAF is your first line of defense against web exploits. When AWS WAF is enabled on an API, AWS WAF rules are evaluated before other access control features, such as [resource policies](#), [IAM policies](#), [Lambda authorizers](#), and [Amazon Cognito authorizers](#). For example, if AWS WAF blocks access from a CIDR block that a resource policy allows, AWS WAF takes precedence and the resource policy isn't evaluated.

To enable AWS WAF for your API, you need to do the following:

1. Use the AWS WAF console, AWS SDK, or CLI to create a web ACL that contains the desired combination of AWS WAF managed rules and your own custom rules. For more information, see [Getting Started with AWS WAF](#) and [Web access control lists \(web ACLs\)](#).

⚠ Important

API Gateway requires an AWS WAFV2 web ACL for a Regional application or an AWS WAF Classic Regional web ACL.

2. Associate the AWS WAF web ACL with an API stage. You can do this by using the AWS WAF console, AWS SDK, CLI, or by using the API Gateway console.

To associate an AWS WAF web ACL with an API Gateway API stage using the API Gateway console

To use the API Gateway console to associate an AWS WAF web ACL with an existing API Gateway API stage, use the following steps:

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose an existing API or create a new one.
3. In the main navigation pane, choose **Stages**, and then choose a stage.
4. In the **Stage details** section, choose **Edit**.
5. Under **Web application firewall (AWS WAF)**, select your web ACL.

If you are using AWS WAFV2, select an AWS WAFV2 web ACL for a Regional application. The web ACL and any other AWS WAFV2 resources that it uses must be located in the same Region as your API.

If you are using AWS WAF Classic Regional, select a Regional web ACL.

6. Choose **Save changes**.

Associate an AWS WAF web ACL with an API Gateway API stage using the AWS CLI

The following [associate-web-acl](#) command associates an AWS WAFV2 web ACL for a Regional application with an existing API Gateway API stage:

```
aws wafv2 associate-web-acl \
--web-acl-arn arn:aws:wafv2:{region}:111122223333:regional/webacl/test-cli/
a1b2c3d4-5678-90ab-cdef-EXAMPLE11111 \
--resource-arn arn:aws:apigateway:{region}::/restapis/4wk1k4onj3/stages/prod
```

The following [associate-web-acl](#) command associates an AWS WAF Classic Regional web ACL with an existing API Gateway API stage:

```
aws waf-regional associate-web-acl \
--web-acl-id 'aabc123a-fb4f-4fc6-becb-2b00831cadcf' \
--resource-arn 'arn:aws:apigateway:{region}::/restapis/4wk1k4onj3/stages/prod'
```

Associate an AWS WAF web ACL with an API stage using the AWS WAF REST API

To use the AWS WAFV2 REST API to associate an AWS WAFV2 web ACL for a Regional application with an existing API Gateway API stage, use the [AssociateWebACL](#) command, as in the following example:

```
import boto3

wafv2 = boto3.client('wafv2')

wafv2.associate_web_acl(
    WebACLArn='arn:aws:wafv2:{region}:111122223333:regional/webacl/test/abc6aa3b-
fc33-4841-b3db-0ef3d3825b25',
    ResourceArn='arn:aws:apigateway:{region}::/restapis/4wk1k4onj3/stages/prod'
)
```

To use the AWS WAF REST API to associate an AWS WAF Classic Regional web ACL with an existing API Gateway API stage, use the [AssociateWebACL](#) command, as in the following example:

```
import boto3

waf = boto3.client('waf-regional')

waf.associate_web_acl(
    WebACLId='aabc123a-fb4f-4fc6-becb-2b00831cadcf',
    ResourceArn='arn:aws:apigateway:{region}::/restapis/4wk1k4onj3/stages/prod'
)
```

Throttle requests to your REST APIs for better throughput in API Gateway

You can configure throttling and quotas for your APIs to help protect them from being overwhelmed by too many requests. Both throttles and quotas are applied on a best-effort basis and should be thought of as targets rather than guaranteed request ceilings.

API Gateway throttles requests to your API using the token bucket algorithm, where a token counts for a request. Specifically, API Gateway examines the rate and a burst of request submissions against all APIs in your account, per Region. In the token bucket algorithm, a burst can allow predefined overrun of those limits, but other factors can also cause limits to be overrun in some cases.

When request submissions exceed the steady-state request rate and burst limits, API Gateway begins to throttle requests. Clients may receive 429 Too Many Requests error responses at this point. Upon catching such exceptions, the client can resubmit the failed requests in a way that is rate limiting.

As an API developer, you can set the target limits for individual API stages or methods to improve overall performance across all APIs in your account. Alternatively, you can enable usage plans to set throttles on client request submissions based on specified requests rates and quotas.

Topics

- [How throttling limit settings are applied in API Gateway](#)
- [Account-level throttling per Region](#)
- [Configuring API-level and stage-level throttling targets in a usage plan](#)
- [Configuring stage-level throttling targets](#)
- [Configuring method-level throttling targets in a usage plan](#)

How throttling limit settings are applied in API Gateway

Before you configure throttle and quota settings for your API, it's useful to understand the types of throttling-related settings for your API and how API Gateway applies them.

Amazon API Gateway provides four basic types of throttling-related settings:

- *AWS throttling limits* are applied across all accounts and clients in a Region. These limit settings exist to prevent your API—and your account—from being overwhelmed by too many requests. These limits are set by AWS and can't be changed by a customer.
- Per-account limits are applied to all APIs in an account in a specified Region. The account-level rate limit can be increased upon request - higher limits are possible with APIs that have shorter timeouts and smaller payloads. To request an increase of account-level throttling limits per Region, contact the [AWS Support Center](#). For more information, see [Quotas and important notes](#). Note that these limits can't be higher than the AWS throttling limits.
- Per-API, per-stage throttling limits are applied at the API method level for a stage. You can configure the same settings for all methods, or configure different throttle settings for each method. Note that these limits can't be higher than the AWS throttling limits.
- *Per-client throttling limits* are applied to clients that use API keys associated with your usage plan as client identifier. Note that these limits can't be higher than the per-account limits.

API Gateway applies your throttling-related settings in the following order:

1. [Per-client or per-method throttling limits](#) that you set for an API stage in a [usage plan](#)
2. [Per-method throttling limits that you set for an API stage](#)
3. [Account-level throttling per Region](#)
4. AWS Regional throttling

Account-level throttling per Region

By default, API Gateway limits the steady-state requests per second (RPS) across all APIs within an AWS account, per Region. It also limits the burst (that is, the maximum bucket size) across all APIs within an AWS account, per Region. In API Gateway, the burst limit represents the target maximum number of concurrent request submissions that API Gateway will fulfill before returning 429 Too Many Requests error responses. For more information on throttling quotas, see [Quotas and important notes](#).

Configuring API-level and stage-level throttling targets in a usage plan

In a [usage plan](#), you can set a per-method throttling target for all methods at the API or stage level. You can specify a *throttling rate*, which is the rate, in requests per second, that tokens are added to the token bucket. You can also specify a *throttling burst*, which is the capacity of the token bucket.

You can use the AWS CLI, SDKs, and the AWS Management Console to create a usage plan. For more information about how to create a usage plan, see [???](#).

Configuring stage-level throttling targets

You can use the AWS CLI, SDKs, and the AWS Management Console to create stage-level throttling targets.

For more information about how to use the AWS Management Console to create stage-level throttling targets, see [???](#). For more information about how to use the AWS CLI to create stage-level throttling targets, see [create-stage](#).

Configuring method-level throttling targets in a usage plan

You can set additional throttling targets at the method level in **Usage Plans** as shown in [Create a usage plan](#). In the API Gateway console, these are set by specifying Resource=<resource>,

Method=<*method*> in the **Configure Method Throttling** setting. For example, for the [PetStore example](#), you might specify Resource=/pets, Method=GET.

Private REST APIs in API Gateway

A private API is a REST API that is only callable from within an Amazon VPC. You can access your API using an [interface VPC endpoint](#), which is an endpoint network interface that you create in your VPC. Interface endpoints are powered by AWS PrivateLink, a technology that enables you to privately access AWS services by using private IP addresses.

You can also use Direct Connect to establish a connection from an on-premises network to Amazon VPC and then access your private API over that connection. In all cases, traffic to your private API uses secure connections and is isolated from the public internet. Traffic doesn't leave the Amazon network.

Best practices for private APIs

We recommend that you use the following best practices when you create your private API:

- Use a single VPC endpoint to access multiple private APIs. This reduces the number of VPC endpoints that you might need.
- Associate your VPC endpoint to your API. This creates a Route 53 alias DNS record and simplifies invoking your private API.
- Turn on private DNS for your VPC. When you turn on private DNS for your VPC, you can invoke your API within a VPC without passing the Host or x-apigw-api-id header.

If you turn on private DNS, you can't access the default endpoint for public APIs. To access the default endpoint for public APIs, you can turn off private DNS, create a private hosted zone for each private API in your VPC, and then provision the required records in Route 53. This allows your private API to resolve while you can still invoke public default endpoint from your VPC. For more information, see [Creating a private hosted zone](#).

- Restrict access to your private API to specific VPCs or VPC endpoints. Add aws:SourceVpc or aws:SourceVpc conditions to your API's resource policy to restrict access.
- For the most secure data perimeter, you can create a VPC endpoint policy. This controls access to the VPC endpoints that can invoke your private API.

Considerations for private APIs

The following considerations might impact your use of private APIs:

- Only REST APIs are supported.
- You cannot convert a private API to an edge-optimized API.
- Private APIs only support TLS 1.2. Earlier TLS versions are not supported.
- If you make a request using HTTP/2 protocol, the request is enforced to use HTTP/1.1 protocol.
- You can't set the IP address type for private APIs to only allow IPv4 addresses to invoke your private API. Only dualstack is supported. For more information, see [the section called “IP address types for REST APIs in API Gateway”](#).
- To send traffic using your private API, you can use all IP address types supported by Amazon VPC. You can send dualstack and IPv6 traffic by configuring the settings on your VPC endpoint. You can't modify this using API Gateway. For more information, see [Add IPv6 support for your VPC](#).
- VPC endpoints for private APIs are subject to the same limitations as other interface VPC endpoints. For more information, see [Access an AWS service using an interface VPC endpoint](#) in the *AWS PrivateLink Guide*. For more information about using API Gateway with shared VPCs and shared subnets, see [Shared subnets](#) in the *AWS PrivateLink Guide*.

Next steps for private APIs

To learn how to create a private API and associate a VPC endpoint see, [the section called “Create a private API”](#). To follow a tutorial where you create dependencies in CloudFormation and a private API in the AWS Management Console, see [the section called “Tutorial: Create a private REST API”](#).

Create a private API

Before you create a private API, you first create a VPC endpoint for API Gateway. Next you create your private API and attach a resource policy to it. Optionally, you can associate your VPC endpoint with your private API to simplify how you invoke your API. Finally, you deploy your API.

The following procedures describe how to accomplish this. You can create a private REST API using the AWS Management Console, AWS CLI or an AWS SDK.

Prerequisites

To follow these steps, you must have a fully configured VPC. To learn how to create a VPC, see [Create a VPC only](#) in the *Amazon VPC User Guide*. To follow all recommended steps when you create your VPC, enable private DNS. This way you can invoke your API within a VPC without having to pass the Host or x-apigw-api-id header.

To enable private DNS, the enableDnsSupport and enableDnsHostnames attributes of your VPC must be set to true. For more information, see [DNS Support in Your VPC](#) and [Updating DNS Support for Your VPC](#).

Step 1: Create a VPC endpoint for API Gateway in your VPC

The following procedure shows how to create a VPC endpoint for API Gateway. To create a VPC endpoint for API Gateway, you specify the execute-api domain for the AWS Region where you create your private API. The execute-api domain is the API Gateway component service for API execution.

When you create your VPC endpoint for API Gateway, you specify the DNS settings. If you turn off private DNS, you can only access your API using public DNS. For more information, see [the section called "Issue: I can't connect to my public API from an API Gateway VPC endpoint"](#).

AWS Management Console

To create an interface VPC endpoint for API Gateway

1. Sign in to the AWS Management Console and open the Amazon VPC console at <https://console.aws.amazon.com/vpc/>.
2. In the navigation pane, under **Virtual private cloud**, choose **Endpoints**.
3. Choose **Create endpoint**.
4. (Optional) For **Name tag**, enter a name to help identify your VPC endpoint.
5. For **Service category**, choose **AWS services**.
6. Under **Services**, in the search bar, enter **execute-api**. Then, choose the API Gateway service endpoint in the AWS Region where you will create your API. The service name should look like com.amazonaws.us-east-1.execute-api and the **Type** should be **Interface**.
7. For **VPC**, choose the VPC that you want to create the endpoint in.

8. (Optional) To turn off **Enable Private DNS Name**, choose **Additional settings** and then clear **Enable Private DNS Name**.
9. For **Subnets**, choose the Availability Zones where you created the endpoint network interfaces. To improve the availability of your API, choose multiple subnets.
10. For **Security group**, select the security group to associate with the VPC endpoint network interfaces.

The security group you choose must be set to allow TCP Port 443 inbound HTTPS traffic from either an IP range in your VPC or another security group in your VPC.

11. For **Policy**, do one of the following:
 - If you have not created your private API or you don't want to configure a custom VPC endpoint policy, choose **Full access**.
 - If you have already created a private API and want to configure a custom VPC endpoint policy, you can enter a custom VPC endpoint policy. For more information, see [the section called "Use VPC endpoint policies for private APIs"](#).

You can update the VPC endpoint policy after you create your VPC endpoint. For more information, see [Update a VPC endpoint policy](#).

12. Choose **Create endpoint**.
13. Copy the resulting VPC endpoint ID, as you might use it in future steps.

AWS CLI

The following [create-vpc-endpoint](#) command creates a VPC endpoint:

```
aws ec2 create-vpc-endpoint \
--vpc-id vpc-1a2b3c4d \
--vpc-endpoint-type Interface \
--service-name com.amazonaws.us-east-1.execute-api \
--subnet-ids subnet-7b16de0c \
--security-group-id sg-1a2b3c4d
```

Copy the resulting VPC endpoint ID, as you might use it in future steps.

Step 2: Create a private API

After you create your VPC endpoint, you create a private REST API. The following procedure shows how to create a private API.

AWS Management Console

To create a private API

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose **Create API**.
3. Under **REST API**, choose **Build**.
4. For **Name**, enter a name.
5. (Optional) For **Description**, enter a description.
6. For **API endpoint type**, select **Private**.
7. (Optional) For **VPC endpoint IDs**, enter a VPC endpoint ID.

If you associate a VPC endpoint ID with your private API, you can invoke your API from within your VPC without overriding a Host header or passing an x-apigw-api-id header. For more information, see [the section called "\(Optional\) Associate or disassociate a VPC endpoint with a private API"](#).

8. For **IP address type**, choose **Dualstack**.
9. Choose **Create API**.

After completing the preceding steps, you can follow the instructions in [the section called "Get started with the REST API console"](#) to set up methods and integrations for this API, but you can't deploy your API. To deploy your API, follow step 3 and attach a resource policy to your API.

AWS CLI

The following [create-rest-api](#) command creates a private API:

```
aws apigateway create-rest-api \
    --name 'Simple PetStore (AWS CLI, Private)' \
    --description 'Simple private PetStore API' \
    --region us-west-2 \
    --endpoint-configuration '{ "types": ["PRIVATE"], "ipAddressType": "dualstack" }'
```

A successful call returns output similar to the following:

```
{  
  "createdDate": "2017-10-13T18:41:39Z",  
  "description": "Simple private PetStore API",  
  "endpointConfiguration": {  
    "types": [  
      "PRIVATE"  
    ],  
    "ipAddressType": "dualstack"  
  },  
  "id": "0qzs2sy7bh",  
  "name": "Simple PetStore (AWS CLI, Private)"  
}
```

After completing the preceding steps, you can follow the instructions in [the section called "Tutorial: Create a REST API using AWS SDKs or the AWS CLI"](#) to set up methods and integrations for this API, but you can't deploy your API. To deploy your API, follow step 3 and attach a resource policy to your API.

SDK JavaScript v3

The following example shows how to create a private API by using the AWS SDK for JavaScript v3:

```
import {APIGatewayClient, CreateRestApiCommand} from "@aws-sdk/client-api-gateway";  
const apig = new APIGatewayClient({region:"us-east-1"});  
  
const input = { // CreateRestApiRequest  
  name: "Simple PetStore (JavaScript v3 SDK, private)", // required  

```

```
    console.error(err)
}
};
```

A successful call returns output similar to the following:

```
{
  apiKeySource: 'HEADER',
  createdDate: 2024-04-03T17:56:36.000Z,
  description: 'Demo private API created using the AWS SDK for JavaScript v3',
  disableExecuteApiEndpoint: false,
  endpointConfiguration: { types: [ 'PRIVATE' ] },
  id: 'abcd1234',
  name: 'Simple PetStore (JavaScript v3 SDK, private)',
  rootResourceId: 'efg567',
  version: '0.00.001'
}
```

After completing the preceding steps, you can follow the instructions in [the section called "Tutorial: Create a REST API using AWS SDKs or the AWS CLI"](#) to set up methods and integrations for this API, but you can't deploy your API. To deploy your API, follow step 3 and attach a resource policy to your API.

Python SDK

The following example shows how to create a private API by using the AWS SDK for Python:

```
import json
import boto3
import logging

logger = logging.getLogger()
apig = boto3.client('apigateway')

def lambda_handler(event, context):
    try:
        result = apig.create_rest_api(
            name='Simple PetStore (Python SDK, private)',
            description='Demo private API created using the AWS SDK for Python',
            version='0.00.001',
            endpointConfiguration={
                'types': [
                    'PRIVATE',

```

```
        ],
    },
)

except botocore.exceptions.ClientError as error:
    logger.exception("Couldn't create private API %s.", error)
    raise

attribute=["id", "name", "description", "createdDate", "version",
"apiKeySource", "endpointConfiguration"]
filtered_data ={key:result[key] for key in attribute}
result = json.dumps(filtered_data, default=str, sort_keys='true')
return result
```

A successful call returns output similar to the following:

```
{"\"apiKeySource\": \"HEADER\", \"\"createdDate\": \"2024-04-03 17:27:05+00:00\", \"\"description\": \"Demo private API created using the AWS SDK for \", \"\"endpointConfiguration\": {\"\"types\": [\"PRIVATE\"]}, \"\"id\": \"abcd1234\", \"\"name\": \"Simple PetStore (Python SDK, private)\", \"\"version\": \"0.00.001\"}"
```

After completing the preceding steps, you can follow the instructions in [the section called “Tutorial: Create a REST API using AWS SDKs or the AWS CLI”](#) to set up methods and integrations for this API, but you can't deploy your API. To deploy your API, follow step 3 and attach a resource policy to your API.

Step 3: Set up a resource policy for a private API

Your current private API is inaccessible to all VPCs. Use a resource policy to grant your VPCs and VPC endpoints access to your private APIs. You can grant access to a VPC endpoint in any AWS account.

Your resource policy should contain `aws:SourceVpc` or `aws:SourceVpce` conditions to restrict access. We recommend that you identify specific VPCs and VPC endpoints and don't create a resource policy that allows access for all VPCs and VPC endpoints.

The following procedure shows how to attach a resource policy to your API.

AWS Management Console

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose a REST API.

3. In the main navigation pane, choose **Resource policy**.
4. Choose **Create policy**.
5. Choose **Select a template** and then choose **Source VPC**.
6. Replace `{{vpcID}}` (including the curly braces) with your VPC ID.
7. Choose **Save changes**.

AWS CLI

The following [update-rest-api](#) command attaches a resource policy to an existing API:

```
aws apigateway update-rest-api \
--rest-api-id a1b2c3 \
--patch-operations op=replace,path=/
policy,value='{"jsonEscapedPolicyDocument"}'
```

You might also want to control which resources have access to your VPC endpoint. To control which resources have access to your VPC endpoint, attach an endpoint policy to your VPC endpoint. For more information, see [the section called “Use VPC endpoint policies for private APIs”](#).

(Optional) Associate or disassociate a VPC endpoint with a private API

When you associate a VPC endpoint with your private API, API Gateway generates a new Route 53 alias DNS record. You can use this record to invoke your private APIs just as you do your public APIs without overriding a Host header or passing an `x-apigw-api-id` header.

The generated base URL is in the following format:

```
https://{rest-api-id}-{vpce-id}.execute-api.{region}.amazonaws.com/{stage}
```

Associate a VPC endpoint (AWS Management Console)

You can associate a VPC endpoint with your private API when you create it, or after it's created. The following procedure shows how to associate a VPC endpoint with a previously created API.

To associate a VPC endpoint with a private API

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose your private API.

3. In the main navigation pane, choose **Resource policy**.
4. Edit your resource policy to allow calls from your additional VPC endpoint.
5. In the main navigation pane, choose **API settings**.
6. In the **API details** section, choose **Edit**.
7. For **VPC endpoint IDs**, select additional VPC endpoint IDs.
8. Choose **Save**.
9. Redeploy your API for the changes to take effect.

Dissociate a VPC endpoint (AWS Management Console)

To disassociate a VPC endpoint from a private REST API

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose your private API.
3. In the main navigation pane, choose **Resource policy**.
4. Edit your resource policy to remove mentions of the VPC endpoint you want to dissociate from your private API.
5. In the main navigation pane, choose **API settings**.
6. In the **API details** section, choose **Edit**.
7. For **VPC endpoint IDs**, choose the X to dissociate the VPC endpoint.
8. Choose **Save**.
9. Redeploy your API for the changes to take effect.

Associate a VPC endpoint (AWS CLI)

The following [create-rest-api](#) command associates VPC endpoints at the time of API creation:

```
aws apigateway create-rest-api \
--name Petstore \
--endpoint-configuration '{ "types": ["PRIVATE"], "vpcEndpointIds" : \
["vpce-0212a4ababd5b8c3e", "vpce-0393a628149c867ee"] }' \
--region us-west-2
```

The output will look like the following:

```
{  
    "apiKeySource": "HEADER",  
    "endpointConfiguration": {  
        "types": [  
            "PRIVATE"  
        ],  
        "vpcEndpointIds": [  
            "vpce-0212a4ababd5b8c3e",  
            "vpce-0393a628149c867ee"  
        ]  
    },  
    "id": "u67n3ov968",  
    "createdDate": 1565718256,  
    "name": "Petstore"  
}
```

The following [update-rest-api](#) command associates VPC endpoints to an API that you already created:

```
aws apigateway update-rest-api \  
    --rest-api-id u67n3ov968 \  
    --patch-operations "op='add',path='/endpointConfiguration/  
vpcEndpointIds',value='vpce-01d622316a7df47f9'" \  
    --region us-west-2
```

The output will look like the following:

```
{  
    "name": "Petstore",  
    "apiKeySource": "1565718256",  
    "tags": {},  
    "createdDate": 1565718256,  
    "endpointConfiguration": {  
        "vpcEndpointIds": [  
            "vpce-0212a4ababd5b8c3e",  
            "vpce-0393a628149c867ee",  
            "vpce-01d622316a7df47f9"  
        ],  
        "types": [  
            "PRIVATE"  
        ]  
    }  
}
```

```
},  
"id": "u67n3ov968"  
}
```

Redeploy your API for the changes to take effect.

Disassociate a VPC endpoint (AWS CLI)

The following [update-rest-api](#) command dissociates a VPC endpoint from a private API:

```
aws apigateway update-rest-api \  
--rest-api-id u67n3ov968 \  
--patch-operations "op='remove',path='/endpointConfiguration/  
vpcEndpointIds',value='vpce-0393a628149c867ee'" \  
--region us-west-2
```

The output will look like the following:

```
{  
    "name": "Petstore",  
    "apiKeySource": "1565718256",  
    "tags": {},  
    "createdDate": 1565718256,  
    "endpointConfiguration": {  
        "vpcEndpointIds": [  
            "vpce-0212a4ababd5b8c3e",  
            "vpce-01d622316a7df47f9"  
        ],  
        "types": [  
            "PRIVATE"  
        ]  
    },  
    "id": "u67n3ov968"  
}
```

Redeploy your API for the changes to take effect.

Step 4: Deploy a private API

To deploy your API, you create an API deployment and associate it with a stage. The following procedure shows how to deploy your private API.

AWS Management Console

To deploy a private API

1. Choose your API.
2. Choose **Deploy API**.
3. For **Stage**, select **New stage**.
4. For **Stage name**, enter a stage name.
5. (Optional) For **Description**, enter a description.
6. Choose **Deploy**.

AWS CLI

The following [create-deployment](#) command deploys a private API:

```
aws apigateway create-deployment --rest-api-id a1b2c3 \
--stage-name test \
--stage-description 'Private API test stage' \
--description 'First deployment'
```

Troubleshoot your private API

The following provides troubleshooting advice for errors and issues that you might encounter when creating a private API.

Issue: I can't connect to my public API from an API Gateway VPC endpoint

When you create your VPC, you can configure the DNS settings. We recommend that you turn on private DNS for your VPC. If you choose turn off private DNS, you're only able to access your API via public DNS.

If you enable private DNS, you can't access the default endpoint of a public API Gateway API from your VPC endpoint. You can access an API with a custom domain name.

If you create a Regional custom domain name, use an A type alias record, if you create an edge-optimized custom domain name, there are no restrictions for your record type. You can access these public APIs with private DNS enabled. For more information, see [Issue: I connect to my public API from an API Gateway VPC endpoint](#).

Issue: My API returns {"Message": "User: anonymous is not authorized to perform: execute-api:Invoke on resource: arn:aws:execute-api:us-east-1:***/*-----*/**

In your resource policy, if you set the Principal to an AWS principal, such as the following:

JSON

```
{  
    "Version": "2012-10-17",  
    "Statement": [  
        {  
            "Effect": "Allow",  
            "Principal": {  
                "AWS": [  
                    "arn:aws:iam::111122223333:role/developer",  
                    "arn:aws:iam::111122223333:role/Admin"  
                ]  
            },  
            "Action": "execute-api:Invoke",  
            "Resource": [  
                "execute-api:/stage/GET/pets"  
            ]  
        }  
    ]  
}
```

You must use AWS_IAM authorization for every method in your API, or else your API returns the previous error message. For more instructions on how to turn on AWS_IAM authorization for a method, see [the section called “Methods”](#).

Issue: I can't tell if my VPC endpoint is associated with my API

If you associate or dissociate a VPC endpoint with your private API, you need to redeploy your API. The update operation might take few minutes to complete due to DNS propagation. During this time, your API is available, but DNS propagation for the newly generated DNS URLs may still be in progress. If after several minutes, your new URLs are not resolving in DNS, we recommend that you redeploy your API.

Custom domain names for private APIs in API Gateway

You can create a custom domain name for your private APIs. Use a private custom domain name to provide API callers with a simpler and more intuitive URL. With a private custom domain name, you can reduce complexity, configure security measures during the TLS handshake, and control the certificate lifecycle of your domain name using AWS Certificate Manager (ACM). For more information, see [the section called “Securing your certificate's private key for your custom domain name”](#).

Custom domain names for private APIs don't need to be unique across multiple accounts. You can create example.private.com in account 111122223333 and in account 555555555555, as long as your ACM certificate covers the domain name. To identify a private custom domain name, use the private custom domain name ARN. This identifier is unique to private custom domain names.

When you create a private custom domain name in API Gateway, you're an *API provider*. You can provide your private custom domain name to other AWS accounts using API Gateway or AWS Resource Access Manager (AWS RAM).

When you invoke a private custom domain name, you're an *API consumer*. You can consume a private custom domain name from your own AWS account or from another AWS account.

When you consume a private custom domain name, you create a domain name access association between a VPC endpoint and a private custom domain name. With a domain name access association, API consumers can invoke your private custom domain name while isolated from the public internet. For more information, see [the section called “API providers and API consumers”](#).

Securing your certificate's private key for your custom domain name

When you request an SSL/TLS certificate using ACM to create your custom domain name for private APIs, ACM generates a public/private key pair. When you import a certificate, you generate the key pair. The public key becomes part of the certificate. To safely store the private key, ACM creates another key using AWS KMS, called the KMS key, with the alias **aws/acm**. AWS KMS uses this key to encrypt your certificate's private key. For more information, see [Data protection in AWS Certificate Manager](#) in the *AWS Certificate Manager User Guide*.

API Gateway uses AWS TLS Connection Manager, a service that is only accessible to AWS services, to secure and use your certificate's private keys. When you use your ACM certificate to create a API Gateway custom domain name, API Gateway associates your certificate with AWS TLS Connection Manager. We do this by creating a grant in AWS KMS against your AWS managed key. This grant

allows TLS Connection Manager to use AWS KMS to decrypt your certificate's private key. TLS Connection Manager uses the certificate and the decrypted (plaintext) private key to establish a secure connection (SSL/TLS session) with clients of API Gateway services. When the certificate is disassociated from a API Gateway service, the grant is retired. For more information, see [Grants](#) in the *AWS Key Management Service Developer Guide*.

For more information, see [the section called "Encryption at rest"](#).

Considerations for private custom domain names

The following considerations might impact your use of private custom domain names:

- It takes about 15 minutes for API Gateway to provision your private custom domain name.
- If you update your ACM certificate, it takes about 15 minutes for API Gateway to complete the update. During this time, your domain name is in the UPDATING state, and you can still access it.
- To invoke a private custom domain name, you must create a domain name access association. After you create a domain name access association, it takes about 15 minutes to be ready.
- The private custom domain name ARN contains the *account-id* and the *domain-name-id*. When you create a domain name, API Gateway uses the ARN format of `arn:partition:apigateway:region::/domainnames/domain-name`. When you access a private custom domain name, you use the ARN format of `arn:partition:apigateway:region:account-id::/domainnames/domain-name+domain-name-id`.

You might need to modify your IAM permissions to allow access to a private domain name after you create it.

- You can't invoke private custom domain names with the same name from the same VPC endpoint. For example, if you wanted to invoke `arn:aws:apigateway:us-west-2:111122223333:/domainnames/private.example.com+abcd1234` and `arn:aws:apigateway:us-west-2:111122223333:/domainnames/private.example.com+xyz000`, associate each private custom domain name with a different VPC endpoint.
- Wildcard certificates are supported, such as a certificate for `*.private.example.com`.
- Wildcard custom domain names aren't supported.
- Only RSA certificates with a 2048-bit key length and ECDSA certificates with 256-bit and 384-bit key lengths are supported.

- You can't set the IP address type for private APIs to only allow IPv4 addresses to invoke your private API. Only dualstack is supported. For more information, see [the section called "IP address types for REST APIs in API Gateway"](#).
- To send traffic using your private API, you can use all IP address types supported by Amazon VPC. You can send dualstack and IPv6 traffic by configuring the settings on your VPC endpoint. You can't modify this using API Gateway. For more information, see [Add IPv6 support for your VPC](#).
- Multi-level base path mapping, such as mapping your private API to /developers/feature, isn't supported, but you can use a routing rule to create a multi-level path condition. For more information, see [the section called "Send traffic to your APIs through your custom domain name in API Gateway"](#).
- You can't set a minimum TLS version for your private custom domain name. All private custom domain names have the security policy of TLS-1-2.
- You can use VPC endpoint policy to control access to a private custom domain name. For more information, see examples 4 and 5 in [the section called "Use VPC endpoint policies for private APIs"](#).
- You must create a separate resource policy for your private API and for your private custom domain name. To invoke a private custom domain name, an API consumer needs access from the private custom domain name resource policy, the private API resource policy, and any VPC endpoint policies or authorization on the private API.

Considerations for using private custom domain names with other API Gateway resources

The following considerations might impact how you use private custom domain names with other API Gateway resources:

- You can't send traffic from a private custom domain name to a public API.
- When a private API is mapped to a private custom domain name, you can't change the API's endpoint type.
- You can't migrate a public custom domain name to a private custom domain name.
- If you have a VPC endpoint that you use to access a public custom domain name, don't use it to create a domain name access association with a private custom domain name.

Differences between private custom domain names and public custom domain names

The following describes the differences between private and public custom domain names:

- Private custom domain names don't need to be unique across multiple accounts.
- A private domain name has a domain name ID. This ID uniquely identifies a private custom domain name and isn't generated for public custom domain names.
- When you use the AWS CLI to update or delete your private custom domain name, you must provide the domain name ID. If you have a private custom domain name called example.com and a public custom domain name called example.com and you don't provide the domain name ID, API Gateway will modify or delete your public custom domain name.

Next steps for custom domain names for private APIs

For information about the tasks of an API provider and an API consumer, see [the section called "API providers and API consumers"](#).

For instructions on creating a private custom domain name that you can invoke in your own AWS account, see [the section called "Tutorial: Create and invoke a custom domain name for private APIs"](#).

For instructions on providing another AWS account access to your private custom domain name, see [the section called "API provider: Share your private custom domain name using AWS RAM"](#). For instructions on associating your VPC endpoint with a private custom domain name in another AWS account, see [the section called "API consumer: Associate your VPC endpoint with a private custom domain name shared with you"](#).

Tasks of API providers and API consumers for custom domain names for private APIs

When you create a private custom domain name, you're an *API provider*. When you invoke a private custom domain name, you're an *API consumer*. You can consume a private custom domain name from your own AWS account or from another AWS account.

The following section explains the tasks required by the API provider and API consumer to use a private custom domain name. If you want to invoke a private custom domain name in your own AWS account, you are both the API provider and the API consumer. If you want to invoke a private custom domain in another AWS account, depending on the trust relationship between the API provider and API consumer in AWS Organizations, AWS RAM might complete some tasks for you.

Tasks of an API provider

API providers create private APIs and map them to custom domain names.

API providers manage two resource policies to protect their private custom domain names. The first policy is for the execute-api service and controls which VPC endpoints can invoke your private custom domain name. In the private custom domain name configuration, it's called the `policy`.

The second policy is for the Amazon API Gateway Management service and controls which VPC endpoints in other AWS accounts can form a domain name access association with your private custom domain name. A VPC endpoint needs to form a domain name access association with a private custom domain name to invoke it. In the private custom domain name configuration, it's the `managementPolicy`. You can use AWS RAM or API Gateway to update this policy. If you don't plan on allowing VPC endpoints in other AWS accounts to invoke your custom domain name, you don't edit the `managementPolicy`.

If you are an API provider, you must do the following:

1. Create a private API.
2. Update your private API's policy to grant your VPC endpoint access to your private API.
3. Create a private custom domain name.
4. Update your private custom domain name's policy to grant your VPC endpoint access to your private custom domain name.
5. Create a base path mapping or a routing rule to send traffic from your private API to your private custom domain name. For more information, see [the section called "Send traffic to your APIs through your custom domain name in API Gateway"](#).

If you want to allow API consumers in other AWS accounts to access your private custom domain name, do the following:

1. Update the `managementPolicy` of your private custom domain name to allow API consumers in other accounts to associate their VPC endpoints with your private custom domain name. You can do this using the following methods:

AWS RAM

With AWS RAM, if the API provider and the API consumer are in the same organization using AWS Organizations, the resource share between provider and consumer is automatically

accepted. Otherwise, you should wait until the API consumer accepts the resource share. **We recommend that you use AWS RAM to share your private custom domain name.**

API Gateway

With API Gateway, only the AWS CLI is supported. You must update your private custom domain name using a patch operation and provide your own policy document for the managementPolicy.

2. Update the policy of your private custom domain name and any private APIs mapped to it to grant access to the API consumer's VPC endpoint.

For instructions on how to provide your API to another AWS account, see [the section called "API provider: Share your private custom domain name using AWS RAM".](#)

Tasks of an API consumer

API consumers associate their VPC endpoints with a domain name ARN to invoke a private custom domain name. API consumers don't need to create an API Gateway API.

If you are an API consumer, do the following:

1. Create a VPC endpoint with private DNS enabled in Amazon VPC.
2. (Optional - if AWS RAM is used) Accept a private custom domain resource share in AWS RAM within **12 hours** of the resource share. If you and the API provider are in the same organization, the resource share is automatically accepted.
3. Get the private custom domain name ARN. Because the private custom domain name URL is not unique, you use the private custom domain name ARN to form the domain name access association between your VPC endpoint and the private custom domain name. You can use AWS RAM to retrieve the private custom domain name ARN.
4. Associate the private custom domain ARN with your VPC endpoint in API Gateway. This creates a secure connection between your VPC endpoint and the private custom domain name. Traffic doesn't leave the Amazon network.
5. Wait for the API provider to grant your VPC endpoint access to the private custom domain name and any private APIs mapped to the private custom domain name. If you're both the API provider and the API consumer, you grant your own VPC endpoint invoke access.
6. Create a Route 53 Private Hosted Zone and a Route 53 record to resolve the private custom domain name in Route 53.

For instructions on how to consume an API in another AWS account, see [the section called “API consumer: Associate your VPC endpoint with a private custom domain name shared with you”](#).

Tutorial: Create and invoke a custom domain name for private APIs

In this tutorial, you create a private custom domain name that you can invoke in a VPC in your own account. To accomplish this, you are the API provider and the API consumer. You need an existing private API and VPC endpoint to complete this tutorial. If you have a VPC endpoint that you use to access a public custom domain name, don't use it for this tutorial or to create any domain name access associations.

Step 1: Create a private custom domain name

You create your private custom domain name by specifying the domain name, the ACM certificate, and the policy for the execute-api service to control which VPC endpoints can invoke it.

AWS Management Console

To create a private custom domain name

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. In the main navigation pane, choose **Custom domain names**.
3. Choose **Add domain name**.
4. For **Domain name**, enter a domain name.

Your ACM certificate must cover this domain name, but the domain name doesn't need to be unique.

5. Select **Private**.
6. For **Routing mode**, choose **API mappings only**.
7. For **ACM certificate**, select a certificate.
8. Choose **Add domain name**.

API Gateway provisions a domain name with a deny all resource policy. This is the resource policy for the execute-api service. You need to update this resource policy to grant access to your VPC endpoints to invoke your private custom domain name.

To update your resource policy

1. Choose the **Resource policy** tab, and then choose **Edit resource policy**.

2. Enter the following resource policy in the code editor. Replace the VPC endpoint `vpce-abcd1234efg` with your own VPC endpoint ID.

```
{  
    "Version": "2012-10-17",  
    "Statement": [  
        {  
            "Effect": "Allow",  
            "Principal": "*",  
            "Action": "execute-api:Invoke",  
            "Resource": [  
                "execute-api:/*"  
            ]  
        },  
        {  
            "Effect": "Deny",  
            "Principal": "*",  
            "Action": "execute-api:Invoke",  
            "Resource": [  
                "execute-api:/*"  
            ],  
            "Condition" : {  
                "StringNotEquals": {  
                    "aws:SourceVpce": "vpce-abcd1234"  
                }  
            }  
        }  
    ]  
}
```

3. Choose **Save changes**.

AWS CLI

When you create a private custom domain name using the AWS CLI, you provide a resource policy for the execute-api service to grant access to VPC endpoints to invoke your private custom domain name, using the `--policy file://policy.json` parameter. You can modify this policy later.

For this example, you'll attach the following resource policy as the policy by loading parameters from a file. Copy and save this file as `policy.json`. This policy only allows

incoming traffic to a private custom domain name from the VPC endpoint `vpce-abcd1234efg`:

```
{  
    "Version": "2012-10-17",  
    "Statement": [  
        {  
            "Effect": "Allow",  
            "Principal": "*",  
            "Action": "execute-api:Invoke",  
            "Resource": [  
                "execute-api:/*"  
            ]  
        },  
        {  
            "Effect": "Deny",  
            "Principal": "*",  
            "Action": "execute-api:Invoke",  
            "Resource": [  
                "execute-api:/*"  
            ],  
            "Condition": {  
                "StringNotEquals": {  
                    "aws:SourceVpce": "vpce-abcd1234"  
                }  
            }  
        }  
    ]  
}
```

The following [create-domain-name](#) command creates a private custom domain name:

```
aws apigateway create-domain-name \  
    --domain-name 'private.example.com' \  
    --certificate-arn 'arn:aws:acm:us-west-2:111122223333:certificate/  
    a1b2c3d4-5678-90ab-cdef' \  
    --security-policy 'TLS_1_2' \  
    --endpoint-configuration '{"types":["PRIVATE"]}' \  
    --policy file://policy.json
```

The output will like the following.

```
{  
    "domainName": "private.example.com",  
    "domainNameId": "abcd1234",  
    "domainNameArn": "arn:aws:apigateway:us-west-2:111122223333:/domainnames/  
private.example.com+abcd1234",  
    "certificateArn": "arn:aws:acm:us-west-2:111122223333:certificate/  
a1b2c3d4-5678-90ab-cdef",  
    "certificateUploadDate": "2024-09-10T10:31:20-07:00",  
    "endpointConfiguration": {  
        "types": [  
            "PRIVATE"  
        ]  
    },  
    "domainNameStatus": "AVAILABLE",  
    "securityPolicy": "TLS_1_2",  
    "routingMode" : "API_MAPPING_ONLY",  
    "policy": "..."  
}
```

Step 2: Create a base path mapping to map your private API to your private custom domain name

After you create your private custom domain name, you map a private API to it. A base path mapping makes an API accessible through the combination of the private custom domain name and an associated base path. We recommend that you use a single private custom domain name as the hostname of multiple private APIs.

All API providers need to create a base path mapping, even if you don't plan on invoking your own API. You also need to grant access for VPC endpoints to invoke any private APIs that you map to your private custom domain name.

AWS Management Console

To create a base path mapping

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. In the main navigation pane, choose **Custom domain names**.
3. Choose a private custom domain name.
4. On the **API mappings** tab, choose **Configure mappings**.

5. Choose **Add new mapping**.
6. Enter an **API**, a **Stage**, and optionally a **Path**.
7. Choose **Save**.

AWS CLI

The following [create-base-path-mapping](#) command creates a mapping between a private API and a private custom domain name:

```
aws apigateway create-base-path-mapping \
--domain-name-id abcd1234 \
--domain-name 'private.example.com' \
--rest-api-id a1b2c3 \
--stage prod \
--base-path v1
```

The output will look like the following.

```
{  
    "basePath": "v1",  
    "restApiId": "a1b2c3",  
    "stage": "prod"  
}
```

For more flexibility on how you route traffic to your APIs, you can change the routing mode to `ROUTING_RULE_ONLY` or `ROUTING_RULE_THEN_API_MAPPING` and create a routing rule. For more information, see [the section called “Send traffic to your APIs through your custom domain name in API Gateway”](#).

Note

If you want other AWS accounts to invoke your private custom domain name, after you complete this tutorial, follow the steps in [the section called “API provider: Share your private custom domain name using AWS RAM”](#).

Step 3: Create a domain name access association between your custom domain name and a VPC endpoint

Next, you create a domain name access association between your private custom domain name and your VPC endpoint. Your VPC endpoint uses the domain name access association to invoke your private custom domain name while isolated from the public internet.

AWS Management Console

To create a domain name access association

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. In the main navigation pane, choose **Custom domain names**.
3. Choose a private custom domain name.
4. In the **Resource sharing** tab, for **Domain name access associations**, choose **Create domain name access association**.
5. For **Domain name ARN**, select your domain name.
6. For **VPC endpoint ID**, select the VPC endpoint ID you provided access to in step 1.
7. Choose **Domain name access association**.

You can also create your domain name access association using the **Domain name access associations** page of the console.

AWS CLI

The following `create-domain-name-access-association` command creates a domain name access association between your private custom domain name and your VPC endpoint.

```
aws apigateway create-domain-name-access-association \
  --domain-name-arn arn:aws:apigateway:us-west-2:111122223333:/domainnames/
private.example.com+abcd1234 \
  --access-association-source vpce-abcd1234efg \
  --access-association-source-type VPCE \
  --region us-west-2
```

The output will look like the following.

```
{
```

```
"domainNameAccessAssociationARN": "arn:aws:apigateway:us-west-2:111122223333:/domainnameaccessassociations/domainname/private.example.com+abcd1234/vpcresource/vpce-abcd1234efg",
"accessAssociationSource": "vpce-abcd1234efg",
"accessAssociationSourceType": "VPCE",
"domainNameARN" : "arn:aws:apigateway:us-west-2:111122223333:/domainnames/private.example.com+abcd1234"
}
```

After you create your domain name access association, it takes about 15 minutes to be ready. While you wait, you can proceed with the following steps.

Step 4: Create a Route 53 hosted zone

After you update your resource policy and associate your private custom domain name with your VPC endpoint, you create a private hosted zone in Route 53 to resolve your custom domain name. A hosted zone is container that holds information about how you want to route traffic for a domain within one or more VPCs without exposing your resources to the internet. For more information, see [Working with private hosted zones](#).

AWS Management Console

To use the AWS Management Console, see [Creating a private hosted zone](#) in the *Amazon Route 53 Developer Guide*.

For **Name**, use the name of your private custom domain name. For **VPC ID**, use the VPC containing the VPC endpoint that you used in the previous steps.

AWS CLI

The following [create-hosted-zone](#) command creates a private hosted zone:

```
aws route53 create-hosted-zone --name private.example.com \
--caller-reference 2014-04-01-18:47 \
--hosted-zone-config Comment="command-line version",PrivateZone=true \
--vpc VPCRegion=us-west-2,VPCId=vpc-abcd1234
```

The output contains the hosted zone ID. You use the hosted zone ID in the following steps.

Step 5: Create a Route 53 DNS record

After you create the hosted zone, you create a record to resolve your private custom domain name. You use the hosted zone ID you created in the previous step. In this example, you create an A record type. If you are using IPv6 for your VPC endpoint, create an AAAA record type. If you are using dualstack for your VPC endpoint, create both an AAAA and an A record type.

AWS Management Console

To use the AWS Management Console, see [Routing traffic to an Amazon API Gateway API by using your domain name](#).

Use **Quick create** and turn on **Alias**. For endpoint, use the VPC endpoint DNS name.

AWS CLI

To configure your DNS records to map the private custom domain name to its hostname of the given hosted zone ID, you create a JSON file that contains the configuration for setting up a DNS record for the private domain name.

The following `setup-dns-record.json` shows how to create a DNS A record to map a private custom domain name to its private hostname. You provide the `DNSName` of your VPC DNS ID, and the hosted zone ID you created in the previous step.

```
{  
    "Changes": [  
        {  
            "Action": "UPSERT",  
            "ResourceRecordSet": {  
                "Name": "private.example.com",  
                "Type": "A",  
                "AliasTarget": {  
                    "DNSName": "vpce-abcd1234.execute-api.us-west-2.vpce.amazonaws.com",  
                    "HostedZoneId": "Z20JLYMU09EFXC",  
                    "EvaluateTargetHealth": false  
                }  
            }  
        }  
    ]  
}
```

The following [change-resource-record-sets](#) command creates a DNS record for your private custom domain name:

```
aws route53 change-resource-record-sets \
--hosted-zone-id ZABCDEFG1234 \
--change-batch file://path/to/your/setup-dns-record.json
```

Replace the `hosted-zone-id` with the Route 53 Hosted Zone ID of the DNS record set in your account. The `change-batch` parameter value points to a JSON file.

If you don't plan on invoking your own private custom domain name, after you confirm your private custom domain name is working, you can delete these resources.

Step 6: Invoke your private custom domain name

You can now invoke your private custom domain name in your own AWS account. In your VPC, use the following curl command to access your private custom domain name.

```
curl https://private.example.com/v1
```

For more information about other ways to invoke your private API, see [the section called “Invoke a private API using a custom domain name”](#).

Step 7: Clean up

To prevent unnecessary costs, delete the association between your VPC endpoint and your private custom domain name, and then delete your private custom domain name.

AWS Management Console

To delete the domain name access association

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. In the main navigation pane, choose **Domain name access associations**.
3. Select your domain name access association, and then choose **Delete**.
4. Confirm your choice, and then choose **Delete**.

After you delete your domain name access association, you can delete your private custom domain name.

To delete your private custom domain name

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. In the main navigation pane, choose **Custom domain names**.
3. Choose your private custom domain name.
4. Choose **Delete**.
5. Confirm your choice, and then choose **Delete**.

If necessary, you can also delete your VPC endpoint. For more information, see [Delete an interface endpoint](#).

AWS CLI

To clean up

1. The following `delete-access-association` command deletes the domain name access association:

```
aws apigateway delete-domain-name-access-association \
    --domain-name-access-association-arn 'arn:aws:apigateway:us-
    west-2:111122223333:/domainnameaccessassociations/domainname/private.example.com
    +abcd1234/vpcresource/vpce-abcd1234efg' \
    --region us-west-2
```

2. The following `delete-domain-name` command deletes your private custom domain name. This command also removes all base path mappings.

```
aws apigateway delete-domain-name \
    --domain-name test.private.com \
    --domain-name-id abcd1234
```

If necessary, you can also delete your VPC endpoint. For more information, see [Delete an interface endpoint](#).

Best practices

We recommend that you use the following best practices when you create your private custom domain name:

- Use base path mapping or routing rules to send traffic from one private custom domain name to multiple private APIs.
- When a VPC endpoint no longer needs access to a private custom domain name, delete the association. In addition, remove the VPC endpoint from the policy for the execute-api service for the private custom domain.
- Configure at least two Availability Zones per VPC endpoint.
- Disable the default endpoint. We recommend that you disable the default endpoint to allow your API consumers to only call your API from the custom domain name. For more information, see [the section called “Disable the default endpoint”](#).
- We recommend that you provision a Route 53 private hosted zone and an A-type record when you set up your private custom domain name. If you don't plan on invoking your own private custom domain name, you can delete these resources later.

Working with cross-account private custom domain names

This section explains how to work with cross-account private custom domain names. You can provide a private custom domain name to another AWS account and use another AWS account to invoke a private custom domain name.

You can share your private custom domain name to another AWS account using AWS Resource Access Manager or API Gateway. AWS Resource Access Manager (AWS RAM) helps you securely share your resources across AWS accounts and within your organization or organizational units (OUs). For more information, see [What is AWS Resource Access Manager](#).

For instructions on how to share a private custom domain name with another AWS account using AWS RAM, see [the section called “API provider: Share your private custom domain name using AWS RAM”](#).

For instructions on how to share a private custom domain name with another AWS account using API Gateway, see [the section called “API provider: Share your private custom domain name using the API Gateway AWS CLI”](#).

For instructions on how to consume a private custom domain name in another AWS account, see [the section called “API consumer: Associate your VPC endpoint with a private custom domain name shared with you”](#).

Best practices for working with cross-account private custom domain names

We recommend the following best practices for working with cross-account private custom domain names:

- Use AWS RAM to share your private custom domain names. When you use AWS RAM, you can reduce operational overhead and you don't have to create a `managementPolicy` for the Amazon API Gateway Management service.
- Use the `resource-owner` parameter when you list your private custom domain names or domain name access associations. Use the `resource-owner` parameter to only list the resources owned by you or by other AWS accounts.

The following example shows how to get all domain name access associations that you own:

```
aws apigateway get-domain-name-access-associations --resource-owner SELF
```

Use `--resource-owner OTHER_ACCOUNTS` to list all the domain name access associations that other accounts have formed with your private custom domain name.

API provider: Share your private custom domain name using AWS RAM

You can provide API consumers in other AWS accounts access to your private custom domain name. In this section, you learn how to share your private custom domain name using AWS RAM and how to control access to your private custom domain name.

Considerations for sharing your private custom domain name

The following considerations might impact how you provide access to your private custom domain name using AWS RAM. To learn how to share your private custom domain name without using AWS RAM, see [the section called "API provider: Share your private custom domain name using the API Gateway AWS CLI"](#).

- Private custom domain names are shared at the AWS Region level. Both the private custom domain name and the VPC endpoint need to be in the same AWS Region.
- You can use one resource share with multiple principals, and after you create the resource share, you can add more principals to it. We recommend that when possible, you reuse your resource share.

- You always need to grant the API consumer's VPC endpoint access to invoke your private custom domain name and any private APIs mapped to it.
- If the API consumer and API provider are in the same organization using AWS Organizations, the resource share is automatically accepted. You still need to create the resource share using AWS RAM.
- If the API consumer and API provider are in the same organization using AWS Organizations and resource sharing within your organization is enabled, any principals in the organization that you share with are automatically granted access to the resource shares. There is no need for an invitation and you can skip the resource share.
- If the API consumer doesn't accept the resource share within **12 hours**, the API provider must share the resource again.
- After you create the resource share, AWS RAM updates the managementPolicy for the Amazon API Gateway Management service for your private custom domain name to prevent access to principals without explicit allow access. For more information, see [Determining whether a request is allowed or denied within an account](#) in the IAM User Guide.

The updated managementPolicy will look like the following:

JSON

```
{  
    "Version": "2012-10-17",  
    "Id": "abcd1234-1234-abcd-abcd-1234abcdefg",  
    "Statement": [  
        {  
            "Sid":  
                "APIGatewayPrivateDomainNameManagementPolicyDefaultPermission-org",  
                "Effect": "Allow",  
                "Principal": "*",  
                "Action": "apigateway:CreateAccessAssociation",  
                "Resource": "arn:aws:apigateway:us-west-2:111122223333:/  
domainnames/private.example.com+abcd1234",  
                "Condition": {  
                    "StringEquals": {  
                        "aws:PrincipalOrgID": "o-1234abcd"  
                    },  
                    "StringNotEquals": {  
                        "aws:PrincipalAccount": "111122223333"  
                    }  
                }  
        }  
    ]  
}
```

```
    }  
]  
}
```

AWS RAM has prevented principals without explicit allow access to create access associations with your private custom domain name, by adding the following:

```
"StringNotEquals": {  
    "aws:PrincipalAccount": "111122223333"  
}
```

You can still use the principal in the AWS account who created the private custom domain name to create domain name access associations.

Allow other accounts to create domain name access associations with your private custom domain name

First, you grant access to another AWS account to create domain name access associations with your private custom domain name.

AWS Management Console

To use the AWS Management Console, see [Creating a resource share in AWS RAM](#) in the *AWS RAM User Guide*.

For **Select resource type**, choose **API Gateway Private Custom Domains**.

AWS CLI

The following [create-resource-share](#) creates a resource share for your private custom domain name. It can take a few minutes for the resource and principal associations to complete. For principals, provide an account ID or an Organizations ID, such as arn:aws:organizations::123456789012:organization/o-1234abcd. You can provide multiple principals for your resource share.

```
aws ram create-resource-share \  
  --region us-west-2 \  
  --name privateCustomDomain-resource-share \  
  --permission-arns arn:aws:ram::aws:permission/  
  APIGatewayPrivateDomainNameManagementPolicyDefaultPermission \  
  --principal arn:aws:organizations::123456789012:organization/o-1234abcd
```

```
--resource-arns arn:aws:apigateway:us-west-2:111122223333:/domainnames/  
private.example.com+abcd1234 \  
--principals 222222222222
```

After you have provided access to another AWS account, API consumers in that account must create a domain name access association between their VPC endpoint with your private custom domain name. You can't create the domain name access association for them. For more information, see [the section called "Associate your VPC endpoint with a shared private custom domain name"](#).

Allow other accounts to invoke your private custom domain name

Next, you grant access for the API consumer's VPC endpoint to invoke your private custom domain name and any private APIs mapped to it.

AWS Management Console

To allow VPC endpoints in other accounts to invoke your private custom domain name

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. In the main navigation pane, choose **Custom domain names**.
3. Choose the private custom domain name that you shared with other AWS accounts.
4. On the **Resource policy** tab, choose **Edit resource policy**.
5. Add the VPC endpoint ID of the API consumer to your resource policy.

You can find the VPC endpoint ID of the API consumer on the **Domain name access associations** section of the **Resource sharing** tab on the **Domain details** page of your private custom domain name.

6. Choose **Save changes**.

AWS CLI

The following policy for the execute-api service allows incoming traffic to a private custom domain name from both VPC endpoint *vpce-abcd1234efg* and *vpce-xyz000abc*.

```
{  
  "Version": "2012-10-17",  
  "Statement": [
```

```
{  
    "Effect": "Allow",  
    "Principal": "*",  
    "Action": "execute-api:Invoke",  
    "Resource": [  
        "execute-api:/*"  
    ]  
,  
{  
    "Effect": "Deny",  
    "Principal": "*",  
    "Action": "execute-api:Invoke",  
    "Resource": [  
        "execute-api:/*"  
    ],  
    "Condition" : {  
        "StringNotEquals": {  
            "aws:SourceVpce": [  
                "vpce-abcd1234",  
                "vpce-xyz0000"  
            ]  
        }  
    }  
}  
}  
]
```

The following [update-domain-name](#) command uses a patch operation to update the policy for a private custom domain name:

```
aws apigateway update-domain-name  
--domain-name private.example.com \  
--domain-name-id abcd1234 \  
--patch-operations op=replace,path=/policy,value='{"Version": "2012-10-17",  
    "Statement": [{"Effect": "Allow","Principal": "*","Action":  
        "execute-api:Invoke","Resource": ["execute-api:/*"]}, {"Effect": "Deny",  
        "Principal": "*","Action": "execute-api:Invoke","Resource": ["execute-  
        api:/*"]}, {"Condition": {"StringNotEquals": ["vpce-abcd1234efg", "vpce-xyz000abc  
        ""]}}]}"
```

API provider: Stop sharing a private custom domain name using AWS RAM

To stop sharing your private custom domain name, first you stop the API consumer from creating more domain name access associations by dissociating the resource share. Then, you reject the domain name access association and remove the API consumer's VPC endpoint from your policy for the execute-api service. The API consumer can then delete their domain name access association.

Stop sharing your private custom domain name

First, you stop the resource share using AWS RAM.

AWS Management Console

To use the AWS Management Console, see [Update a resource share in AWS RAM](#).

AWS CLI

The following [disassociate-resource-share](#) disassociates a resource share for your private custom domain name.

```
aws ram disassociate-resource-share \
--region us-west-2 \
--resource-arns arn:aws:apigateway:us-west-2:111122223333:/domainnames/
private.example.com+abcd1234 \
--principals 222222222222
```

Reject the domain name access association

After you stop sharing your resource using AWS RAM, you reject the domain name access association between a VPC endpoint in another account and your private custom domain name.

Note

You can't reject a domain name access association in your own account. To stop resource sharing, delete the domain name access association. For more information, see [Delete a domain name access association](#).

When you reject a domain name access association with a VPC endpoint, if an API consumer tries to call your private custom domain name, API Gateway rejects the call and returns a 403 status code.

AWS Management Console

To reject a domain name access association

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. In the main navigation pane, choose **Custom domain names**.
3. Choose the private custom domain name that you shared with other AWS accounts.
4. On the **Resource sharing**, choose the domain name access association you want to reject.
5. Choose **Reject association**.
6. Confirm your choice, and then choose **Reject**.

AWS CLI

The following `reject-domain-name-access-association` command rejects the domain name access association between the VPC endpoint and your private custom domain name:

```
aws apigateway reject-domain-name-access-association \
    --domain-name-access-association-arn arn:aws:apigateway:us-west-2:444455556666:/
domainnameaccessassociations/domainname/private.example.com+abcd1234/vpcresource/
vpce-abcd1234efg \
    --domain-name-arn arn:aws:apigateway:us-west-2:111122223333:/domainnames/
private.example.com+abcd1234
```

Deny the API provider access to invoke your private custom domain name

After you reject the domain name access association, you remove the API consumer's VPC endpoint from your policy for the `execute-api` service.

AWS Management Console

To remove the API consumer's VPC endpoint from your resource policy

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. In the main navigation pane, choose **Custom domain names**.
3. Choose the private custom domain name that you shared with other AWS accounts.
4. On the **Resource policy** tab, choose **Edit**.
5. Remove the VPC endpoint from the policy.

6. Choose **Save changes**.

AWS CLI

The following [update-domain-name](#) command uses a patch operation to update the policy for the execute-api service for a private custom domain name. This new policy removes an additional VPC endpoint ID added in [the section called "Allow other accounts to invoke your private custom domain name"](#):

```
aws apigateway update-domain-name
  --domain-name private.example.com \
  --domain-name-id abcd1234 \
  --patch-operations op=replace,path=/policy,value='{"Version": "2012-10-17",
  "Statement": [{"Effect": "Allow","Principal": "*","Action":
  "execute-api:Invoke","Resource": ["execute-api:/{*}"]},{Effect": "Deny",
  "Principal": "*","Action": "execute-api:Invoke","Resource": ["execute-
  api:/{*}"]}, {"Condition": {"StringNotEquals": {"aws:SourceVpce": "vpce-abcd1234efg
  }}}]}'
```

The API consumer should then delete the domain name access association. You can't delete it for them. For more information, see [the section called "API consumer: Delete your domain name access association with a private custom domain name"](#).

API provider: Share your private custom domain name using the API Gateway AWS CLI

You can share a private custom domain name using the API Gateway AWS CLI, but we recommend that you use AWS RAM to reduce your operational overhead. For instructions on how to use AWS RAM to share your private custom domain name, see [the section called "API provider: Share your private custom domain name using AWS RAM"](#).

To share a private custom domain name using the API Gateway AWS CLI, you grant other AWS accounts access to create domain name access associations and invoke your private custom domain name. You do this by updating the `managementPolicy` for the API Gateway Management service and the policy for the `execute-api` service for your private custom domain name. You also need to grant access for the API consumer's VPC endpoint in the resource policy for any private APIs mapped to your private custom domain name.

The API consumer still needs to create a domain name access association in their own account between their VPC endpoint and your private custom domain name. You can't do this for them.

Grant access to your private custom domain name

1. To update the `managementPolicy` for the API Gateway Management service, you create a JSON file that contains the patch operation to update the policy. The following `patch-managementPolicy.json` replaces the current `managementPolicy` with an example policy that grants AWS accounts 111122223333 and 444455556666 access to create domain name access associations with the private custom domain name `private.example.com`.

```
[{
    "op": "replace",
    "path": "/managementPolicy",
    "value": "{\"Version\": \"2012-10-17\", \"Statement\": [{\"Effect\": \"Allow\", \"Principal\": {\"AWS\": [\"arn:aws:iam::111122223333:root\", \"arn:aws:iam::444455556666:root\"]}, \"Action\": \"apigateway:CreateAccessAssociation\", \"Resource\": \"arn:aws:apigateway:us-west-2:111122223333:/domainnames/private.example.com+abcd1234\"}]}"]
```

The following [update-domain-name](#) command updates the `managementPolicy` using `patch-managementPolicy.json`.

```
aws apigateway update-domain-name \
--domain-name private.example.com \
--domain-name-id abcd1234 \
--patch-operations file://patch-managementPolicy.json
```

Once you grant access, you need to notify the API consumer that they can form the domain name access association. If you use AWS RAM, AWS RAM will do this step for you.

2. To update the policy for the `execute-api` service, you create a JSON file that contains the patch operation to update the policy. The following `patch-policy.json` replaces the current policy with an example policy that grants two VPC endpoints to invoke the private custom domain name `private.example.com`.

```
[{
    "op": "replace",
    "path": "/policy",
    "value": "{\"Version\": \"2012-10-17\", \"Statement\": [{\"Effect\": \"Allow\", \"Principal\": \"*\", \"Action\": \"execute-api:Invoke\", \"Resource\": \"arn:aws:execute-api:us-west-2:111122223333:abcd1234/*\"}]}"]
```

```
\\"arn:aws:execute-api:us-west-2:111122223333:/domainnames/private.example.com+abcd1234\"}, {\\"Effect\\": \\"Deny\\", \\"Principal\\": \\"*\", \\"Action\\": \\"execute-api:Invoke\\", \\"Resource\\": \\"arn:aws:execute-api:us-west-2:111122223333:/domainnames/private.example.com+abcd1234\\", \\"Condition\\": {\\"StringNotEquals\\": {\\"aws:SourceVpce\\": [\\"vpce-abcd1234\\", \\"vpce-xyz000\\"]}}}]}"\n}]
```

Use the following [update-domain-name](#) command to update the policy using patch-policy.json.

```
aws apigateway update-domain-name \
--domain-name private.example.com \
--domain-name-id abcd1234 \
--patch-operations file://patch-policy.json
```

Deny access to your private custom domain name

To stop sharing your private custom domain name, you need to reject the domain name access association between your private custom domain name and the API consumer's VPC endpoint.

To deny access to your private custom domain name

1. The following `reject-domain-name-access-association` command rejects the domain name access association.

```
aws apigateway reject-domain-name-access-association \
--domain-name-access-association-arn arn:aws:apigateway:us-west-2:44445556666:/domainnameaccessassociations/domainname/private.example.com+abcd1234/vpcresource/vpce-abcd1234 \
--domain-name-arn arn:aws:apigateway:us-west-2:111122223333:/domainnames/private.example.com+abcd1234
```

2. Modify the `patch-managementPolicy.json` to remove access for the API provider's account to create a domain name access association with your private custom domain name. The following `patch-managementPolicy.json` removes one account from the `managementPolicy`:

```
[{
  "op": "replace",
  "path": "/managementPolicy",
```

```
"value": "{\"Version\":\"2012-10-17\", \"Statement\":[{\"Effect\": \"Allow\", \"Principal\":\"*\", \"Action\":\"apigateway:CreateAccessAssociation\", \"Resource\":\"arn:aws:apigateway:us-west-2:111122223333:/domainnames/private.example.com+abcd1234\"]}]}
```

The following [update-domain-name](#) command updates the managementPolicy using patch-managementPolicy.json.

```
aws apigateway update-domain-name \
--domain-name private.example.com \
--domain-name-id abcd1234 \
--patch-operations file://patch-managementPolicy.json
```

3. Modify the patch-policy.json to remove access for the API provider's VPC endpoint to invoke your private custom domain name. The following patch-policy.json removes the VPC endpoint ID from the policy:

```
[{
  "op": "replace",
  "path": "/policy",
  "value": "{\"Version\":\"2012-10-17\", \"Statement\":[{\"Effect\": \"Allow\", \"Principal\":\"*\", \"Action\":\"execute-api:Invoke\", \"Resource\":\"arn:aws:execute-api:us-west-2:111122223333:/domainnames/private.example.com+abcd1234\"}, {\"Effect\": \"Deny\", \"Principal\":\"*\", \"Action\":\"execute-api:Invoke\", \"Resource\":\"arn:aws:execute-api:us-west-2:111122223333:/domainnames/private.example.com+abcd1234\"}, {\"Condition\": {\"StringNotEquals\": {\"aws:SourceVpce\": \"vpce-abcd1234\"}}}]}]}
```

The following [update-domain-name](#) command updates the policy using patch-policy.json.

```
aws apigateway update-domain-name \
--domain-name private.example.com \
--domain-name-id abcd1234 \
--patch-operations file://patch-policy.json
```

Example policies used in this procedure

The following section shows the example policies used in the previous procedure.

The following example policy is for the `managementPolicy` for the Amazon API Gateway Management service. This policy grants AWS accounts 111122223333 and 444455556666 access to create domain name access associations with the private custom domain name `private.example.com`.

JSON

```
{  
    "Version": "2012-10-17",  
    "Statement": [  
        {  
            "Effect": "Allow",  
            "Principal": {  
                "AWS": [  
                    "111122223333",  
                    "444455556666"  
                ]  
            },  
            "Action": "apigateway:CreateAccessAssociation",  
            "Resource": "arn:aws:apigateway:us-west-2:111122223333:/domainnames/  
private.example.com+a1b2c3"  
        }  
    ]  
}
```

The following example policy is the policy for the `execute-api` service. This policy grants VPC endpoints `vpce-abcd1234` and `vpce-xyz0000` access to invoke the private custom domain name.

JSON

```
{  
    "Version": "2012-10-17",  
    "Statement": [  
        {  
            "Effect": "Allow",  
            "Principal": {  
                "AWS": [  
                    "vpce-abcd1234",  
                    "vpce-xyz0000"  
                ]  
            },  
            "Action": "execute-api:Invoke",  
            "Resource": "arn:aws:execute-api:us-west-2:111122223333:privateexamplecom-a1b2c3/  
ANY"  
        }  
    ]  
}
```

```
        "Principal": "*",
        "Action": "execute-api:Invoke",
        "Resource": "arn:aws:execute-api:us-west-2:111122223333:/domainnames/
private.example.com+abcd1234"
    },
    {
        "Effect": "Deny",
        "Principal": "*",
        "Action": "execute-api:Invoke",
        "Resource": "arn:aws:execute-api:us-west-2:111122223333:/domainnames/
private.example.com+abcd1234",
        "Condition": {
            "StringNotEquals": {
                "aws:SourceVpce": [
                    "vpce-abcd1234",
                    "vpce-xyzz0000"
                ]
            }
        }
    }
]
```

API consumer: Associate your VPC endpoint with a private custom domain name shared with you

The following procedure shows how to consume a private domain name in another AWS account. Depending on your trust relationship with the API provider, AWS RAM might complete some tasks for you.

When you are in a different AWS account from a private custom domain name, you can only associate your VPC endpoint with a private custom domain name and invoke it. You can't view the policy or any other parameters of the private custom domain name.

Prerequisites

The following prerequisites are required to consume a private custom domain name in another AWS account:

- A VPC and a VPC endpoint for the execute-api service. Your VPC must have enableDnsHostnames and enableDnsSupport set to true.

- We recommend that you configure at least two Availability Zones per VPC endpoint.

(Optional) Accept the private custom domain resource share

If your API provider used AWS RAM to create a resource share, you have **12 hours** to accept it. If you are in the same organization using AWS Organizations as the API provider, the share is automatically accepted. If you are in an organization that has automatic shared resources enabled, the resource is automatically shared with you.

AWS Management Console

To use the AWS Management Console, see [Accepting and rejecting resource share invitations](#) in the *AWS RAM User Guide*.

AWS CLI

To find all resources shared with you, use the following [get-resource-share-invitations](#) command:

```
aws ram get-resource-share-invitations \
--region us-west-2
```

Use the resulting resource share ARN to accept the resource share invitation. The following [accept-resource-share-invitation](#) command accepts the resource share.

```
aws ram accept-resource-share-invitation \
--resource-share-invitation-arn arn:aws:ram:us-west-2:123456789012:resource-
share-invitation/1e3477be-4a95-46b4-bbe0-c4001EXAMPLE \
--region us-west-2
```

Associate your VPC endpoint with a shared private custom domain name

Because private custom domain names aren't unique, you associate your VPC endpoint with the unique custom domain name ARN. After you create your domain name access association, it can take up to 15 minutes for your VPC endpoint to successfully invoke your private custom domain name. If you have a VPC endpoint that you use to access a public custom domain name, don't use it to create any domain name access associations.

AWS Management Console

To associate your VPC endpoint with a shared private custom domain name

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. In the main navigation pane, choose **Domain name access associations**.
3. Choose **Create domain name access association**.
4. For **Domain name ARN**, select the domain name ARN that the API provider shared with you.

The domain name ARN might not appear in the dropdown list. You can use the AWS RAM console to view domain names shared with you and then copy the domain name ARN and enter it into this field.

5. For **VPC endpoint ID**, select the VPC endpoint ID you want to form the domain name access association with.
6. Choose **Create domain name access association**.

AWS CLI

Because private custom domain names aren't unique, you associate your VPC endpoint with the unique custom domain name ARN. To find the domain name ARN, use one of the following commands.

1. AWS RAM

The following [list-resources](#) command lists resources that are shared with you. The API provider must have used AWS RAM to share their private custom domain with you to use this command.

```
aws ram list-resources \
--resource-owner OTHER-ACCOUNTS \
--region us-west-2 \
--resource-type apigateway:Domainnames
```

API Gateway

The following get-domain-names command lists all private custom domain names owned by other AWS accounts that you can form domain name access associations with.

```
aws apigateway get-domain-names \
--resource-owner OTHER_ACCOUNTS \
--region us-west-2
```

2. After you retrieve the ARN, use API Gateway to create the domain name access association between your VPC endpoint and a shared private custom domain name. Use the following `create-domain-name-access-association` command:

```
aws apigateway create-domain-name-access-association \
--access-association-source-type VPCE \
--access-association-source 'vpce-1a2b3c4d5e6f1a2b3' \
--domain-name-arn arn:aws:apigateway:us-west-2:111122223333:/domainnames/
private.example.com+abcd1234"
```

The output will look like the following.

```
{  
    "domainNameAccessAssociationARN": "arn:aws:apigateway:us-  
west-2:444455556666:/domainnameaccessassociations/domainname/private.example.com  
+abcd1234/vpcresource/vpce-abcd1234efg",  
    "accessAssociationSource": "vpce-1a2b3c4d5e6f1a2b3",  
    "accessAssociationSourceType": "VPCE",  
    "domainNameARN" : "arn:aws:apigateway:us-west-1:111122223333:/domainnames/  
private.example.com+a1b2c3"  
}
```

After you associate your VPC endpoint with the private custom domain name, confirm that your API provider has updated the policy of their private custom domain name to allow your VPC endpoint to invoke their domain name. For more information, see [the section called “Allow other accounts to invoke your private custom domain name”](#).

Create a Route 53 hosted zone

To resolve the private custom domain name, you need to create a Route 53 private hosted zone. A hosted zone is container that holds information about how you want to route traffic for a domain within one or more VPCs without exposing your resources to the internet. For more information, see [Working with private hosted zones](#).

AWS Management Console

To use the AWS Management Console, see [Creating a private hosted zone](#) in the *Amazon Route 53 Developer Guide*.

For **Name**, use the name of the private custom domain name. For **VPC ID**, use the VPC containing the VPC endpoint that you used for your domain name access association.

AWS CLI

The following [create-hosted-zone](#) command creates a private hosted zone:

```
aws route53 create-hosted-zone --name private.example.com \
--caller-reference 2014-04-01-18:47 \
--hosted-zone-config Comment="command-line version",PrivateZone=true \
--vpc VPCRegion=us-west-2,VPCId=vpc-abcd1234
```

The output contains the hosted zone ID. You use the hosted zone ID in the following steps.

Create a Route 53 DNS record

After you create the hosted zone, you create an record to resolve the private custom domain. In this example, you create an A record type. If you are using IPv6 for your VPC endpoint, create an AAAA record type. If you are using dualstack for your VPC endpoint, create both an AAAA and an A record type.

AWS Management Console

To use the AWS Management Console, see [Routing traffic to an Amazon API Gateway API by using your domain name](#).

Use **Quick create** and turn on **Alias**. For endpoint, use the VPC endpoint DNS name.

AWS CLI

To configure your DNS records to map the private custom domain name to its hostname of the given hosted zone ID, first create a JSON file that contains the configuration for setting up a DNS record for the private domain name.

The following `setup-dns-record.json` shows how to create a DNS A record to map a private custom domain name to its private hostname. You provide the `DNSName` of your VPC DNS ID, and the hosted zone ID you created in the previous step.

```
{  
  "Changes": [  
    {  
      "Action": "UPSERT",  
      "ResourceRecordSet": {  
        "Name": "private.example.com",  
        "Type": "A",  
        "AliasTarget": {  
          "DNSName": "vpce-abcd1234.execute-api.us-west-2.vpce.amazonaws.com",  
          "HostedZoneId": "Z20JLYMU09EFXC",  
          "EvaluateTargetHealth": false  
        }  
      }  
    }  
  ]  
}
```

The following [change-resource-record-sets](#) command creates a DNS record for the private custom domain name:

```
aws route53 change-resource-record-sets \  
--hosted-zone-id ZABCDEFG1234 \  
--change-batch file://path/to/your/setup-dns-record.json
```

Replace the `hosted-zone-id` with the Route 53 Hosted Zone ID of the DNS record set in your account. The `change-batch` parameter value points to a JSON file.

Next steps for an API consumer

You can now invoke the private API in your own AWS account. In your VPC, you can use the following curl command to access your private custom domain name.

```
curl https://private.example.com/v1
```

For more information about other ways to invoke your private API, see [the section called “Invoke a private API using a custom domain name”](#).

API consumer: Delete your domain name access association with a private custom domain name

If you are an API consumer, at any time, you can delete the access association resource. The API provider can't delete the domain name access association for you.

We recommend that you always delete a domain name access association when you're no longer using it.

AWS Management Console

To delete the domain name access association

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. In the main navigation pane, choose **Domain name access associations**.
3. Select your domain name access association, and then choose **Delete**.
4. Confirm your choice, and then choose **Delete**.

AWS CLI

The following `delete-access-association` command deletes the access association:

```
aws apigateway delete-domain-name-access-association \
--domain-name-access-association-arn 'arn:aws:apigateway:us-
west-2:444455556666:/domainnameaccessassociations/domainname/private.example.com
+abcd1234/vpcresource/vpce-abcd1234efg'
```

Create a custom domain name for private APIs using CloudFormation

The following example CloudFormation template creates a private API and a private custom domain name, maps the private API to the custom domain name, and then creates a domain name access association. You need to provide your own VPC endpoint, domain name, and certificate ARN.

The following considerations might impact your use of CloudFormation to create a private custom domain name:

- You can't reject a domain name access association using CloudFormation. To reject a domain name access association, use the AWS CLI.
- Use the `AWS::ApiGateway::DomainNameV2` CloudFormation property to create a private custom domain name.
- Use the `AWS::ApiGateway::BasePathMappingV2` CloudFormation property to create a base path mapping.

```
AWSTemplateFormatVersion: 2010-09-09
Parameters:
  EndpointID:
    Type: String
    Default: vpce-abcd1234567efg
    Description: A VPC endpoint with enableDnsHostnames and enableDnsSupport set to true.
  DomainName:
    Type: String
    Default: private.example.com
    Description: A domain name that you own.
  CertificateArn:
    Type: String
    Default: arn:aws:acm:us-west-2:123456789:certificate/abcd-000-1234-0000-00000abcd
    Description: An ACM certificate that covers the domain name.
Resources:
  PrivateApi:
    Type: 'AWS::ApiGateway::RestApi'
    Properties:
      EndpointConfiguration:
        Types:
          - PRIVATE
      VpcEndpointIds:
        - !Ref EndpointID
      Name: private-api
      Policy:
        Statement:
          - Action: 'execute-api:Invoke'
            Effect: Allow
            Principal: '*'
            Resource: 'execute-api:/*'
          - Action: 'execute-api:Invoke'
            Condition:
              StringNotEquals:
                'aws:SourceVpce': !Ref EndpointID
            Effect: Deny
            Principal: '*'
            Resource: 'execute-api:/*'
      Version: 2012-10-17
  PrivateApiDeployment:
    Type: 'AWS::ApiGateway::Deployment'
    Properties:
      RestApiId: !Ref PrivateApi
```

```
    Description: Private API deployment
    DependsOn:
      - PrivateApiMethod
  PrivateApiStage:
    Type: 'AWS::ApiGateway::Stage'
    Properties:
      RestApiId: !Ref PrivateApi
      DeploymentId: !Ref PrivateApiDeployment
      StageName: prod
  PrivateApiMethod:
    Type: 'AWS::ApiGateway::Method'
    Properties:
      HttpMethod: ANY
      ResourceId: !GetAtt PrivateApi.RootResourceId
      RestApiId: !Ref PrivateApi
      AuthorizationType: NONE
      Integration:
        Type: MOCK
        RequestTemplates:
          application/json: "{\"statusCode\": 200}"
      IntegrationResponses:
        - StatusCode: '200'
      MethodResponses:
        - StatusCode: '200'
  PrivateDomainName:
    Type: AWS::ApiGateway::DomainNameV2
    Properties:
      DomainName: !Ref DomainName
      CertificateArn: !Ref CertificateArn
      EndpointConfiguration:
        Types:
          - PRIVATE
      SecurityPolicy: TLS_1_2
      Policy:
        Statement:
          - Action: 'execute-api:Invoke'
            Effect: Allow
            Principal: '*'
            Resource: 'execute-api:/"'
          - Action: 'execute-api:Invoke'
            Condition:
              StringNotEquals:
                'aws:SourceVpce': !Ref EndpointID
            Effect: Deny
```

```
Principal: '*'
Resource: 'execute-api:/*'
Version: 2012-10-17
PrivateBasePathMapping:
  Type: AWS::ApiGateway::BasePathMappingV2
  DependsOn:
    - PrivateApiStage
  Properties:
    BasePath: prod
    DomainNameArn: !GetAtt PrivateDomainName.DomainNameArn
    RestApiId: !Ref PrivateApi
    Stage: prod
DomainNameAccessAssociation:
  Type: AWS::ApiGateway::DomainNameAccessAssociation
  Properties:
    DomainNameArn: !GetAtt PrivateDomainName.DomainNameArn
    AccessAssociationSource: !Ref EndpointID
    AccessAssociationSourceType: VPCE
```

Invoke a private API

You can only invoke a private API from within a VPC using a VPC endpoint. Your private API must have a resource policy that allows specific VPCs and VPC endpoints to invoke your API.

If you invoke a private API without using a custom domain name or private DNS names and your APIs or domain name uses a security policy that starts with `SecurityPolicy_`, you must set the endpoint access mode to BASIC. For more information, see [the section called “Endpoint access mode”](#).

Invoke a private API using a custom domain name

To invoke a private API using a custom domain name, your VPC endpoint needs a domain name access association with a custom domain name, and the custom domain name needs to allow access for the VPC endpoint to invoke it. For more information, see [the section called “Custom domain names for private APIs”](#).

There are no differences between invoking a private custom domain name in a VPC in your own AWS account or in a different AWS account.

Use your custom domain name

Inside your VPC, you can invoke your API using the custom domain name. The following example is a curl command to invoke your private custom domain name:

```
curl https://private.example.com
```

Use endpoint-specific private DNS hostnames

You can invoke your API using the custom domain name and the endpoint-specific private DNS hostname.

```
curl https://private-dns-hostname.execute-api.region.vpce.amazonaws.com/basepath -H  
'Host:custom-domain-name'
```

The following example is a curl command to invoke your custom domain name using an endpoint-specific private DNS hostname:

```
curl https://vpce-123456-abc000.execute-api.us-east-2.vpce.amazonaws.com/test -H  
'Host:private.example.com'
```

Invoke a private API without using a custom domain name

To invoke your private API without using a custom domain name, you need to identify the DNS names for your API. The following procedure shows how to find your DNS names.

AWS Management Console

To find the DNS names

1. Sign in to the AWS Management Console and open the Amazon VPC console at <https://console.aws.amazon.com/vpc/>.
2. In the main navigation pane, choose **Endpoints** and then choose your interface VPC endpoint for API Gateway.
3. In the **Details** pane, you'll see five values in the **DNS names** field. The first three are the public DNS names for your API. The other two are the private DNS names for it.

AWS CLI

Use the following [describe-vpc-endpoints](#) command to list your DNS values.

```
aws ec2 describe-vpc-endpoints --vpc-endpoint-ids vpce-01234567abcdef012
```

The first three are the public DNS names for your API. The other two are the private DNS names for it.

Invoke a private API using a Route53 alias

You can associate or disassociate a VPC endpoint with your private API. For more information, see [the section called “\(Optional\) Associate or disassociate a VPC endpoint with a private API”](#).

After you associate your VPC endpoints with your private API, you can use the following base URL to invoke the API:

```
https://{rest-api-id}-{vpce-id}.execute-api.{region}.amazonaws.com/{stage}
```

For example, if you set up the GET /pets method for the test stage, and your REST API ID was 01234567ab, and your VPC endpoint ID was vpce-01234567abcdef012, and your Region was us-west-2, you can invoke your API as:

```
curl -v https://01234567ab-vpce-01234567abcdef012.execute-api.us-west-2.amazonaws.com/test/pets
```

Invoke a private API using private DNS names

If you've enabled private DNS, you can access your private API using the following private DNS name:

```
{restapi-id}.execute-api.{region}.amazonaws.com
```

The base URL to invoke the API is in the following format:

```
https://{restapi-id}.execute-api.{region}.amazonaws.com/{stage}
```

For example, if you set up the GET /pets method for the test stage, and your REST API ID was 01234567ab and your Region was us-west-2, you could invoke your private API by entering the following URL in a browser:

```
https://01234567ab.execute-api.us-west-2.amazonaws.com/test/pets
```

Alternatively, you could use the following cURL command to invoke your private API:

```
curl -X GET https://01234567ab.execute-api.us-west-2.amazonaws.com/test/pets
```

Warning

If you enable private DNS for your VPC endpoint, you won't be able to access the default endpoint for public APIs. For more information, see [Why can't I connect to my public API from an API Gateway VPC endpoint?](#).

Invoke a private API using Direct Connect

You can use Direct Connect to establish a dedicated private connection from an on-premises network to Amazon VPC and access your private API endpoint over that connection by using public DNS names.

You can also use private DNS names to access your private API from an on-premises network by setting up an Amazon Route 53 Resolver inbound endpoint and forwarding it all DNS queries of the private DNS from your remote network. For more information, see [Forwarding inbound DNS queries to your VPCs](#) in the *Amazon Route 53 Developer Guide*.

Invoke a private API using endpoint-specific public DNS hostnames

You can access your private API using endpoint-specific DNS hostnames. These are public DNS hostnames containing the VPC endpoint ID or API ID for your private API.

The generated base URL is in the following format:

```
https://{public-dns-hostname}.execute-api.{region}.vpce.amazonaws.com/{stage}
```

For example, if you set up the GET /pets method for the test stage, and your REST API ID was abc1234, its public DNS hostname was vpce-def-01234567, and your Region was us-west-2, you could invoke your private API using its VPCe ID by using the Host header in a cURL command:

```
curl -v https://vpce-def-01234567.execute-api.us-west-2.vpce.amazonaws.com/test/pets -H  
'Host: abc1234.execute-api.us-west-2.amazonaws.com'
```

Alternatively, you can invoke your private API via its API ID by using the x-apigw-api-id header in a cURL command in the following format:

```
curl -v https://{public-dns-hostname}.execute-api.{region}.vpce.amazonaws.com/{stage} -H 'x-apigw-api-id:{api-id}'
```

Monitor REST APIs in API Gateway

In this section, you can learn how to monitor your API by using CloudWatch metrics, CloudWatch Logs, Firehose, and AWS X-Ray. By combining CloudWatch execution logs and CloudWatch metrics, you can log errors and execution traces, and monitor your API's performance. You might also want to log API calls to Firehose. You can also use AWS X-Ray to trace calls through the downstream services that make up your API.

Note

API Gateway might not generate logs and metrics in the following cases:

- 413 Request Entity Too Large errors
- 431 Request Header Fields Too Large errors
- Excessive 429 Too Many Requests errors
- 400 series errors from requests sent to a custom domain that has no API mapping
- 500 series errors caused by internal failures

API Gateway will not generate logs and metrics when testing a REST API method. The CloudWatch entries are simulated. For more information, see [the section called “Use the console to test a REST API method”](#).

Topics

- [Monitor REST API execution with Amazon CloudWatch metrics](#)
- [Set up CloudWatch logging for REST APIs in API Gateway](#)
- [Log REST API calls to Amazon Data Firehose in API Gateway](#)
- [Variables for access logging for API Gateway](#)
- [Trace user requests to REST APIs using X-Ray in API Gateway](#)

Monitor REST API execution with Amazon CloudWatch metrics

You can monitor API execution by using CloudWatch, which collects and processes raw data from API Gateway into readable, near-real-time metrics. These statistics are recorded for a period of 15 months so you can access historical information and gain a better perspective on how your web application or service is performing. By default, API Gateway metric data is automatically sent to CloudWatch in one-minute periods. For more information, see [What Is Amazon CloudWatch?](#) in the *Amazon CloudWatch User Guide*.

The metrics reported by API Gateway provide information that you can analyze in different ways. The following list shows some common uses for the metrics that are suggestions to get you started:

- Monitor the **IntegrationLatency** metrics to measure the responsiveness of the backend.
- Monitor the **Latency** metrics to measure the overall responsiveness of your API calls.
- Monitor the **CacheHitCount** and **CacheMissCount** metrics to optimize cache capacities to achieve a desired performance.

Topics

- [Amazon API Gateway dimensions and metrics](#)
- [View CloudWatch metrics with the API dashboard in API Gateway](#)
- [View API Gateway metrics in the CloudWatch console](#)
- [View API Gateway log events in the CloudWatch console](#)
- [Monitoring tools in AWS for API Gateway](#)

Amazon API Gateway dimensions and metrics

The metrics and dimensions that API Gateway sends to Amazon CloudWatch are listed below. For more information, see [Monitor REST API execution with Amazon CloudWatch metrics](#).

API Gateway metrics

Amazon API Gateway sends metric data to CloudWatch every minute.

The AWS/ApiGateway namespace includes the following metrics.

Metric	Description
4XXError	<p>The number of client-side errors captured in a given period.</p> <p>API Gateway counts modified gateway response status codes as 4XXError errors.</p> <p>The Sum statistic represents this metric, namely, the total count of the 4XXError errors in the given period. The Average statistic represents the 4XXError error rate, namely, the total count of the 4XXError errors divided by the total number of requests during the period. The denominator corresponds to the Count metric (below).</p> <p>Unit: Count</p>
5XXError	<p>The number of server-side errors captured in a given period.</p> <p>The Sum statistic represents this metric, namely, the total count of the 5XXError errors in the given period. The Average statistic represents the 5XXError error rate, namely, the total count of the 5XXError errors divided by the total number of requests during the period. The denominator corresponds to the Count metric (below).</p> <p>Unit: Count</p>
CacheHitCount	<p>The number of requests served from the API cache in a given period.</p> <p>The Sum statistic represents this metric, namely, the total count of the cache hits in the given period. The Average statistic represents the cache hit rate, namely, the total count of the cache hits divided by the total number of requests during the</p>

Metric	Description
	<p>period. The denominator corresponds to the Count metric (below).</p> <p>Unit: Count</p>
CacheMissCount	<p>The number of requests served from the backend in a given period, when API caching is enabled.</p> <p>The Sum statistic represents this metric, namely, the total count of the cache misses in the given period. The Average statistic represents the cache miss rate, namely, the total count of the cache misses divided by the total number of requests during the period. The denominator corresponds to the Count metric (below).</p> <p>Unit: Count</p>
Count	<p>The total number API requests in a given period.</p> <p>The SampleCount statistic represents this metric.</p> <p>Unit: Count</p>
IntegrationLatency	<p>The time between when API Gateway relays a request to the backend and when it receives a response from the backend.</p> <p>Unit: Millisecond</p>
Latency	<p>The time between when API Gateway receives a request from a client and when it returns a response to the client. The latency includes the integration latency and other API Gateway overhead.</p> <p>Unit: Millisecond</p>

Dimensions for metrics

You can use the dimensions in the following table to filter API Gateway metrics.

 **Note**

API Gateway removes non-ASCII characters from the ApiName dimension before sending metrics to CloudWatch. If the APIName contains no ASCII characters, the API ID is used as the ApiName.

Dimension	Description
ApiName	Filters API Gateway metrics for the REST API with the specified API name.
ApiName, Method, Resource, Stage	<p>Filters API Gateway metrics for the API method with the specified API name, stage, resource, and method.</p> <p>API Gateway will not send these metrics unless you have explicitly enabled detailed CloudWatch metrics. In the console, choose a stage, and then for Logs and tracing, select Edit. Select Detailed metrics, and then choose Save changes. Alternatively, you can call the update-stage AWS CLI command to update the metricsEnabled property to true.</p> <p>Enabling these metrics will incur additional charges to your account. For pricing information, see Amazon CloudWatch Pricing.</p>
ApiName, Stage	Filters API Gateway metrics for the API stage resource with the specified API name and stage.

View CloudWatch metrics with the API dashboard in API Gateway

You can use the API dashboard in the API Gateway Console to display the CloudWatch metrics of your deployed API in API Gateway. These are shown as a summary of API activity over time.

Topics

- [Prerequisites](#)
- [Examine API activities in the dashboard](#)

Prerequisites

1. You must have an API created in API Gateway. Follow the instructions in [Develop REST APIs in API Gateway](#).
2. You must have the API deployed at least once. Follow the instructions in [Deploy REST APIs in API Gateway](#).

Examine API activities in the dashboard

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose an API.
3. In the main navigation pane, choose **Dashboard**.
4. For **Stage**, choose the desired stage.
5. Choose **Date range** to specify a range of dates.
6. Refresh, if needed, and view individual metrics displayed in separate graphs titled **API calls**, **Latency**, **Integration latency**, **Latency**, **4xx error** and **5xx error**.

 **Tip**

To examine method-level CloudWatch metrics, make sure that you have enabled CloudWatch Logs on a method level. For more information about how to set up method-level logging, see [Override stage-level settings](#).

View API Gateway metrics in the CloudWatch console

Metrics are grouped first by the service namespace, and then by the various dimension combinations within each namespace. To view the metrics at the method-level for your API, turn on detailed metrics. For more information, see [the section called “Update stage settings”](#).

To view API Gateway metrics using the CloudWatch console

1. Open the CloudWatch console at <https://console.aws.amazon.com/cloudwatch/>.
2. If necessary, change the AWS Region. From the navigation bar, select the Region where your AWS resources reside.
3. In the navigation pane, choose **Metrics**.
4. In the **All metrics** tab, choose **API Gateway**.
5. To view metrics by stage, choose the **By Stage** panel. Then, select your APIs and metric names.
6. To view metrics by specific API, choose the **By Api Name** panel. Then, select your APIs and metric names.

To view metrics using the AWS CLI

1. Use the following [list-metrics](#) command to list metrics:

```
aws cloudwatch list-metrics --namespace "AWS/ApiGateway"
```

After you create a metric, allow up to 15 minutes for the metric to appear. To see metric statistics sooner, use [get-metric-data](#) or [get-metric-statistics](#).

2. Use the following [get-metrics-statistics](#) command to view the average over a period of time using 5 minute intervals:

```
aws cloudwatch get-metric-statistics --namespace AWS/ApiGateway --metric-name Count  
--start-time 2011-10-03T23:00:00Z --end-time 2017-10-05T23:00:00Z --period 300 --  
statistics Average
```

View API Gateway log events in the CloudWatch console

The following section explains the necessary prerequisites and how to view API Gateway log events in the CloudWatch console.

Prerequisites

1. You must have an API created in API Gateway. Follow the instructions in [Develop REST APIs in API Gateway](#).
2. You must have the API deployed and invoked at least once. Follow the instructions in [Deploy REST APIs in API Gateway](#) and [Invoke REST APIs in API Gateway](#).
3. You must have CloudWatch Logs enabled for a stage. Follow the instructions in [Set up CloudWatch logging for REST APIs in API Gateway](#).

To view logged API requests and responses using the CloudWatch console

1. Open the CloudWatch console at <https://console.aws.amazon.com/cloudwatch/>.
2. If necessary, change the AWS Region. From the navigation bar, select the Region where your AWS resources reside. For more information, see [Regions and Endpoints](#).
3. In the navigation pane, choose **Logs, Log groups**.
4. Under the **Log Groups** table, choose a log group of the **API-Gateway-Execution-Logs_{rest-api-id}/{stage-name}** name.
5. Under the **Log Streams** table, choose a log stream. You can use the timestamp to help locate the log stream of your interest.
6. Choose **Text** to view raw text or choose **Row** to view the event row by row.

Important

CloudWatch lets you delete log groups or streams. Do not manually delete API Gateway API log groups or streams; let API Gateway manage these resources. Manually deleting log groups or streams may cause API requests and responses not to be logged. If that happens, you can delete the entire log group for the API and redeploy the API. This is because API Gateway creates log groups or log streams for an API stage at the time when it is deployed.

Monitoring tools in AWS for API Gateway

AWS provides various tools that you can use to monitor API Gateway. You can configure some of these tools to do the monitoring for you automatically, while other tools require manual intervention. We recommend that you automate monitoring tasks as much as possible.

Automated monitoring tools in AWS

You can use the following automated monitoring tools to watch API Gateway and report when something is wrong:

- **Amazon CloudWatch Alarms** – Watch a single metric over a time period that you specify, and perform one or more actions based on the value of the metric relative to a given threshold over a number of time periods. The action is a notification sent to an Amazon Simple Notification Service (Amazon SNS) topic or Amazon EC2 Auto Scaling policy. CloudWatch alarms do not invoke actions simply because they are in a particular state; the state must have changed and been maintained for a specified number of periods. For more information, see [Monitor REST API execution with Amazon CloudWatch metrics](#).
- **Amazon CloudWatch Logs** – Monitor, store, and access your log files from AWS CloudTrail or other sources. For more information, see [What is CloudWatch Logs?](#) in the *Amazon CloudWatch User Guide*.
- **Amazon EventBridge (formerly called CloudWatch Events)** – Match events and route them to one or more target functions or streams to make changes, capture state information, and take corrective action. For more information, see [What Is Amazon EventBridge?](#) in the *EventBridge User Guide*.
- **AWS CloudTrail Log Monitoring** – Share log files between accounts, monitor CloudTrail log files in real time by sending them to CloudWatch Logs, write log processing applications in Java, and validate that your log files have not changed after delivery by CloudTrail. For more information, see [Working with CloudTrail Log Files](#) in the *AWS CloudTrail User Guide*.

Manual monitoring tools

Another important part of monitoring API Gateway involves manually monitoring those items that the CloudWatch alarms don't cover. The API Gateway, CloudWatch, and other AWS console dashboards provide an at-a-glance view of the state of your AWS environment. We recommend that you also check the log files on API execution.

- API Gateway dashboard shows the following statistics for a given API stage during a specified period of time:
 - **API Calls**
 - **Cache Hit**, only when API caching is enabled.
 - **Cache Miss**, only when API caching is enabled.

- **Latency**
- **Integration Latency**
- **4XX Error**
- **5XX Error**
- The CloudWatch home page shows:
 - Current alarms and status
 - Graphs of alarms and resources
 - Service health status

In addition, you can use CloudWatch to do the following:

- Create [customized dashboards](#) to monitor the services you care about
- Graph metric data to troubleshoot issues and discover trends
- Search and browse all your AWS resource metrics
- Create and edit alarms to be notified of problems

Creating CloudWatch alarms to monitor API Gateway

You can create a CloudWatch alarm that sends an Amazon SNS message when the alarm changes state. An alarm watches a single metric over a time period you specify, and performs one or more actions based on the value of the metric relative to a given threshold over a number of time periods. The action is a notification sent to an Amazon SNS topic or Auto Scaling policy. Alarms invoke actions for sustained state changes only. CloudWatch alarms do not invoke actions simply because they are in a particular state; the state must have changed and been maintained for a specified number of periods.

Set up CloudWatch logging for REST APIs in API Gateway

To help debug issues related to request execution or client access to your API, you can enable Amazon CloudWatch Logs to log API calls. For more information about CloudWatch, see [the section called "CloudWatch metrics"](#).

CloudWatch log formats for API Gateway

There are two types of API logging in CloudWatch: execution logging and access logging. In execution logging, API Gateway manages the CloudWatch Logs. The process includes creating log groups and log streams, and reporting to the log streams any caller's requests and responses.

The logged data includes errors or execution traces (such as request or response parameter values or payloads), data used by Lambda authorizers (formerly known as custom authorizers), whether API keys are required, whether usage plans are enabled, and other information. API Gateway redacts authorization headers, API key values, and similar sensitive request parameters from the logged data.

To improve your security posture, we recommend that you use execution logging at the ERROR or INFO level. You might need to do this to comply with various compliance frameworks. For more information, see [Amazon API Gateway controls](#) in the *AWS Security Hub User Guide*.

When you deploy an API, API Gateway creates a log group and log streams under the log group. The log group is named following the API-Gateway-Execution-Logs_{rest-api-id}/ {stage_name} format. Within each log group, the logs are further divided into log streams, which are ordered by **Last Event Time** as logged data is reported.

In access logging, you, as an API developer, want to log who has accessed your API and how the caller accessed the API. You can create your own log group or choose an existing log group that could be managed by API Gateway. To specify the access details, you select [\\$context](#) variables, a log format, and a log group destination.

The access log format must include at least `$context.requestId` or `$context.extendedRequestId`. As a best practice, include `$context.requestId` and `$context.extendedRequestId` in your log format.

\$context.requestId

This logs the value in the `x-amzn-RequestId` header. Clients can override the value in the `x-amzn-RequestId` header with a value in the format of a universally unique identifier (UUID). API Gateway returns this request ID in the `x-amzn-RequestId` response header. API Gateway replaces overridden request IDs that aren't in the format of a UUID with `UUID_REPLACED_INVALID_REQUEST_ID` in your access logs.

\$context.extendedRequestId

The `extendedRequestId` is a unique ID that API Gateway generates. API Gateway returns this request ID in the `x-amz-apigw-id` response header. An API caller can't provide or override this request ID. You might need to provide this value to AWS Support to help troubleshoot your API. For more information, see [the section called “Variables for access logging for API Gateway”](#).

Choose a log format that is also adopted by your analytic backend, such as [Common Log Format](#) (CLF), JSON, XML, or CSV. You can then feed the access logs to it directly to have your metrics computed and rendered. To define the log format, set the log group ARN on the [accessLogSettings/destinationArn](#) property on the [stage](#). You can obtain a log group ARN in the CloudWatch console. To define the access log format, set a chosen format on the [accessLogSetting/format](#) property on the [stage](#).

Examples of some commonly used access log formats are shown in the API Gateway console and are listed as follows.

- CLF ([Common Log Format](#)):

```
$context.identity.sourceIp $context.identity.caller $context.identity.user  
[$context.requestTime]"$context.httpMethod $context.resourcePath  
$context.protocol" $context.status $context.responseLength $context.requestId  
$context.extendedRequestId
```

- JSON:

```
{ "requestId": "$context.requestId",  
  "extendedRequestId": "$context.extendedRequestId", "ip": "$context.identity.sourceIp",  
  "caller": "$context.identity.caller", "user": "$context.identity.user",  
  "requestTime": "$context.requestTime", "httpMethod": "$context.httpMethod",  
  "resourcePath": "$context.resourcePath", "status": "$context.status",  
  "protocol": "$context.protocol", "responseLength": "$context.responseLength" }
```

- XML:

```
<request id="$context.requestId"> <extendedRequestId>$context.extendedRequestId</  
extendedRequestId> <ip>$context.identity.sourceIp</ip> <caller>  
$context.identity.caller</caller> <user>$context.identity.user</user> <requestTime>  
$context.requestTime</requestTime> <httpMethod>$context.httpMethod</httpMethod>  
 <resourcePath>$context.resourcePath</resourcePath> <status>$context.status</status>  
 <protocol>$context.protocol</protocol> <responseLength>$context.responseLength</  
responseLength> </request>
```

- CSV (comma-separated values):

```
$context.identity.sourceIp,$context.identity.caller,$context.identity.user,  
$context.requestTime,$context.httpMethod,$context.resourcePath,$context.protocol,  
$context.status,$context.responseLength,$context.requestId,$context.extendedRequestId
```

Permissions for CloudWatch logging

To enable CloudWatch Logs, you must grant API Gateway permission to read and write logs to CloudWatch for your account. The [AmazonAPIGatewayPushToCloudWatchLogs](#) has all the required permissions.

Note

API Gateway calls AWS Security Token Service in order to assume the IAM role, so make sure that AWS STS is enabled for the Region. For more information, see [Managing AWS STS in an AWS Region](#).

To grant these permissions to your account, create an IAM role with `apigateway.amazonaws.com` as its trusted entity, attach the preceding policy to the IAM role, and set the IAM role ARN on the [cloudWatchRoleArn](#) property on your [Account](#). You must set the [cloudWatchRoleArn](#) property separately for each AWS Region in which you want to enable CloudWatch Logs.

If you receive an error when setting the IAM role ARN, check your AWS Security Token Service account settings to make sure that AWS STS is enabled in the Region that you're using. For more information about enabling AWS STS, see [Managing AWS STS in an AWS Region](#) in the *IAM User Guide*.

Set up CloudWatch API logging using the API Gateway console

To set up CloudWatch API logging, you must have deployed the API to a stage. You must also have configured [an appropriate CloudWatch Logs role](#) ARN for your account.

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. On the main navigation pane, choose **Settings**, and then under **Logging**, choose **Edit**.
3. For **CloudWatch log role ARN**, enter an ARN of an IAM role with appropriate permissions. You need to do this once for each AWS account that creates APIs using API Gateway.
4. In the main navigation pane, choose **APIs**, and then do one of the following:
 - a. Choose an existing API, and then choose a stage.
 - b. Create an API, and then deploy it to a stage.
5. In the main navigation pane, choose **Stages**.

6. In the **Logs and tracing** section, choose **Edit**.
7. To enable execution logging:
 - a. Select a logging level from the **CloudWatch Logs** dropdown menu. The logging levels are the following:
 - **Off** – Logging is not turned on for this stage.
 - **Errors only** – Logging is enabled for errors only.
 - **Errors and info logs** – Logging is enabled for all events.
 - b. (Optional) Select **Data tracing** to turn on data trace logging for your stage. This can be useful to troubleshoot APIs, but can result in logging sensitive data.

 **Note**

We recommend that you don't use **Data tracing** for production APIs.

- c. (Optional) Select **Detailed metrics** to turn on detailed CloudWatch metrics.

For more information about CloudWatch metrics, see [the section called “CloudWatch metrics”](#).

8. To enable access logging:
 - a. Turn on **Custom access logging**.
 - b. For **Access log destination ARN**, enter the ARN of a log group. The ARN format is `arn:aws:logs:{region}:{account-id}:log-group:{log-group-name}`.
 - c. For **Log Format**, enter a log format. You can choose **CLF**, **JSON**, **XML**, or **CSV**. To learn more about example log formats, see [the section called “CloudWatch log formats for API Gateway”](#).
9. Choose **Save changes**.

 **Note**

You can enable execution logging and access logging independently of each other.

API Gateway is now ready to log requests to your API. You don't need to redeploy the API when you update the stage settings, logs, or stage variables.

Set up CloudWatch API logging using CloudFormation

Use the following example CloudFormation template to create an Amazon CloudWatch Logs log group and configure execution and access logging for a stage. To enable CloudWatch Logs, you must grant API Gateway permission to read and write logs to CloudWatch for your account. To learn more, see [Associate account with IAM role](#) in the *AWS CloudFormation User Guide*.

```
TestStage:
  Type: AWS::ApiGateway::Stage
  Properties:
    StageName: test
    RestApiId: !Ref MyAPI
    DeploymentId: !Ref Deployment
    Description: "test stage description"
    MethodSettings:
      - ResourcePath: /*
        HttpMethod: "*"
        LoggingLevel: INFO
    AccessLogSetting:
      DestinationArn: !GetAtt MyLogGroup.Arn
      Format: $context.extendedRequestId $context.identity.sourceIp
$context.identity.caller $context.identity.user [$context.requestTime]
"$context.httpMethod $context.resourcePath $context.protocol" $context.status
$context.responseLength $context.requestId
MyLogGroup:
  Type: AWS::Logs::LogGroup
  Properties:
    LogGroupName: !Join
      - '-'
      - - !Ref MyAPI
      - - access-logs
```

Log REST API calls to Amazon Data Firehose in API Gateway

To help debug issues related to client access to your API, you can log API calls to Amazon Data Firehose. For more information about Firehose, see [What Is Amazon Data Firehose?](#).

For access logging, you can only enable CloudWatch or Firehose—you can't enable both. However, you can enable CloudWatch for execution logging and Firehose for access logging.

Topics

- [Firehose log formats for API Gateway](#)
- [Permissions for Firehose logging](#)
- [Set up Firehose access logging by using the API Gateway console](#)

Firehose log formats for API Gateway

Firehose logging uses the same format as [CloudWatch logging](#).

Permissions for Firehose logging

When Firehose access logging is enabled on a stage, API Gateway creates a service-linked role in your account if the role doesn't exist already. The role is named AWSServiceRoleForAPIGateway and has the APIGatewayServiceRolePolicy managed policy attached to it. For more information about service-linked roles, see [Using Service-Linked Roles](#).

 **Note**

The name of your Firehose stream must be amazon-apigateway-*{your-stream-name}*.

Set up Firehose access logging by using the API Gateway console

To set up API logging, you must have deployed the API to a stage. You must also have created a Firehose stream.

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Do one of the following:
 - a. Choose an existing API, and then choose a stage.
 - b. Create an API and deploy it to a stage.
3. In the main navigation pane, choose **Stages**.
4. In the **Logs and tracing** section, choose **Edit**.
5. To enable access logging to a Firehose stream:
 - a. Turn on **Custom access logging**.

- b. For **Access log destination ARN**, enter the ARN of a Firehose stream. The ARN format is `arn:aws:firehose:{region}:{account-id}:deliverystream/amazon-apigateway-{your-stream-name}`.

 **Note**

The name of your Firehose stream must be `amazon-apigateway-{your-stream-name}`.

- c. For **Log format**, enter a log format. You can choose **CLF**, **JSON**, **XML**, or **CSV**. To learn more about example log formats, see [the section called “CloudWatch log formats for API Gateway”](#).

6. Choose **Save changes**.

API Gateway is now ready to log requests to your API to Firehose. You don't need to redeploy the API when you update the stage settings, logs, or stage variables.

Variables for access logging for API Gateway

In access logging, you, as an API developer, want to log who has accessed your API and how the caller accessed the API. You can create your own log group or choose an existing log group that could be managed by API Gateway. To specify the access details, you can use the following case-sensitive \$context variables.

For a list of reference variables for data transformations, see [the section called “Variables for data transformations”](#).

Parameter	Description
<code>\$context.accountId</code>	The API owner's AWS account ID.
<code>\$context.apiId</code>	The identifier API Gateway assigns to your API.
<code>\$context.authorize.error</code>	The authorization error message.
<code>\$context.authorize.latency</code>	The authorization latency in ms.

Parameter	Description
\$context.authorize.status	The status code returned from an authorization attempt.
\$context.authorizer.claims. <i>property</i>	<p>A property of the claims returned from the Amazon Cognito user pool after the method caller is successfully authenticated. For more information, see the section called “Use Amazon Cognito user pool as authorizer for a REST API”.</p> <div style="border: 1px solid #ccc; padding: 10px; margin-top: 10px;"> <p> Note</p> <p>Calling <code>\$context.authorizer.claims</code> returns null.</p> </div>
\$context.authorizer.error	The error message returned from an authorizer.
\$context.authorizer.integrationLatency	The authorizer integration latency in ms.
\$context.authorizer.integrationStatus	The status code returned from a Lambda authorizer.
\$context.authorizer.latency	The authorizer latency in ms.
\$context.authorizer.principalId	The principal user identification associated with the token sent by the client and returned from an API Gateway Lambda authorizer (formerly known as a custom authorizer). For more information, see the section called “Use Lambda authorizers” .

Parameter	Description
\$context.authorizer. <i>property</i>	<p>The stringified value of the specified key-value pair of the context map returned from an API Gateway Lambda authorizer function. For example, if the authorizer returns the following context map:</p> <pre data-bbox="855 523 1132 705"> "context" : { "key": "value", "numKey": 1, "boolKey": true } </pre> <p>Calling <code>\$context.authorizer.key</code> returns the "value" string, calling <code>\$context.authorizer.numKey</code> returns the "1" string, and calling <code>\$context.authorizer.boolKey</code> returns the "true" string.</p> <p>For <i>property</i>, the only supported special character is the underscore (_) character.</p> <p>For more information, see the section called "Use Lambda authorizers".</p>
\$context.authorizer.requestId	The AWS endpoint's request ID.
\$context.authorizer.status	The status code returned from an authorizer.
\$context.authenticate.error	The error message returned from an authentication attempt.
\$context.authenticate.latency	The authentication latency in ms.
\$context.authenticate.status	The status code returned from an authentication attempt.

Parameter	Description
\$context.awsEndpointRequestId	The AWS endpoint's request ID.
\$context.cipherSuite	The cipher, in IANA format, that is negotiated during the TLS handshake between the client and API Gateway.
\$context.customDomain.basePathMatched	The path for an API mapping that an incoming request matched. Applicable when a client uses a custom domain name to access an API. For example if a client sends a request to <code>https://api.example.com/v1/orders/1234</code> , and the request matches the API mapping with the path <code>v1/orders</code> , the value is <code>v1/orders</code> . To learn more, see the section called "API mappings" .
\$context.customDomain.routingRuleIdMatched	The routing rule that an incoming request matched. Applicable when a client uses a custom domain name to access an API. To learn more, see the section called "Routing rules" .
\$context.deploymentId	The ID of the API deployment.
\$context.domainName	The full domain name used to invoke the API. This should be the same as the incoming Host header.
\$context.domainPrefix	The first label of the \$context.domainName.
\$context.endpointType	The endpoint type of the API.

Parameter	Description
\$context.error.message	A string containing an API Gateway error message. This variable can only be used for simple variable substitution in a GatewayResponse body-mapping template, which is not processed by the Velocity Template Language engine, and in access logging. For more information, see the section called “Metrics” and the section called “Setting up gateway responses to customize error responses” .
\$context.error.messageString	The quoted value of \$context.error.message , namely "\$context.error.message" .
\$context.error.responseType	A type of GatewayResponse . This variable can only be used for simple variable substitution in a GatewayResponse body-mapping template, which is not processed by the Velocity Template Language engine, and in access logging. For more information, see the section called “Metrics” and the section called “Setting up gateway responses to customize error responses” .
\$context.error.validationErrorMessage	A string containing a detailed validation error message.
\$context.extendedRequestId	The extended ID that API Gateway generates and assigns to the API request. The extended request ID contains useful information for debugging and troubleshooting.
\$context.httpMethod	The HTTP method used. Valid values include: DELETE, GET, HEAD, OPTIONS, PATCH, POST, and PUT.

Parameter	Description
\$context.identity.accountId	The AWS account ID associated with the request.
\$context.identity.apiKey	For API methods that require an API key, this variable is the API key associated with the method request. For methods that don't require an API key, this variable is null. For more information, see the section called "Usage plans" .
\$context.identity.apiKeyId	The API key ID associated with an API request that requires an API key.
\$context.identity.caller	The principal identifier of the caller that signed the request. Supported for resources that use IAM authorization.
\$context.identity.cognitoAuthenticationProvider	<p>A comma-separated list of all the Amazon Cognito authentication providers used by the caller making the request. Available only if the request was signed with Amazon Cognito credentials.</p> <p>For example, for an identity from an Amazon Cognito user pool, cognito-idp.<i>region</i>.amazonaws.com/ <i>user_pool_id</i>, cognito-idp. <i>region</i>.amazonaws.com/ <i>user_pool_id</i> :CognitoSignIn: <i>token subject claim</i></p> <p>For information about the available Amazon Cognito authentication providers, see Using Federated Identities in the Amazon Cognito Developer Guide.</p>

Parameter	Description
\$context.identity.cognitoAuthenticationType	The Amazon Cognito authentication type of the caller making the request. Available only if the request was signed with Amazon Cognito credentials. Possible values include authenticated for authenticated identities and unauthenticated for unauthenticated identities.
\$context.identity.cognitoIdentityId	The Amazon Cognito identity ID of the caller making the request. Available only if the request was signed with Amazon Cognito credentials.
\$context.identity.cognitoIdentityPoolId	The Amazon Cognito identity pool ID of the caller making the request. Available only if the request was signed with Amazon Cognito credentials.
\$context.identity.principalOrgId	The AWS organization ID .
\$context.identity.sourceIp	The source IP address of the immediate TCP connection making the request to the API Gateway endpoint.
\$context.identity.clientCert.clientCertPem	The PEM-encoded client certificate that the client presented during mutual TLS authentication. Present when a client accesses an API by using a custom domain name that has mutual TLS enabled. Present only in access logs if mutual TLS authentication fails.

Parameter	Description
\$context.identity.clientCertificate.subjectDN	The distinguished name of the subject of the certificate that a client presents. Present when a client accesses an API by using a custom domain name that has mutual TLS enabled. Present only in access logs if mutual TLS authentication fails.
\$context.identity.clientCertificate.issuerDN	The distinguished name of the issuer of the certificate that a client presents. Present when a client accesses an API by using a custom domain name that has mutual TLS enabled. Present only in access logs if mutual TLS authentication fails.
\$context.identity.clientCertificate.serialNumber	The serial number of the certificate. Present when a client accesses an API by using a custom domain name that has mutual TLS enabled. Present only in access logs if mutual TLS authentication fails.
\$context.identity.clientCertificate.validity.notBefore	The date before which the certificate is invalid. Present when a client accesses an API by using a custom domain name that has mutual TLS enabled. Present only in access logs if mutual TLS authentication fails.
\$context.identity.clientCertificate.validity.notAfter	The date after which the certificate is invalid. Present when a client accesses an API by using a custom domain name that has mutual TLS enabled. Present only in access logs if mutual TLS authentication fails.
\$context.identity.vpcId	The VPC ID of the VPC making the request to the API Gateway endpoint.

Parameter	Description
\$context.identity.vpceId	The VPC endpoint ID of the VPC endpoint making the request to the API Gateway endpoint. Present only when you have a private API.
\$context.identity.user	The principal identifier of the user that will be authorized against resource access. Supported for resources that use IAM authorization.
\$context.identity.userAgent	The User-Agent header of the API caller.
\$context.identity.userArn	The Amazon Resource Name (ARN) of the effective user identified after authentication. For more information, see https://docs.aws.amazon.com/IAM/latest/UserGuide/id_users.html .
\$context.integration.error	The error message returned from an integration.
\$context.integration.integrationStatus	For Lambda proxy integration, the status code returned from AWS Lambda, not from the backend Lambda function code.
\$context.integration.latency	The integration latency in ms. Equivalent to \$context.integrationLatency .
\$context.integration.requestId	The AWS endpoint's request ID. Equivalent to \$context.awsEndpointRequestId .
\$context.integration.responseTransferMode	The response transfer mode of your integration. This can be either BUFFERED or STREAMED.

Parameter	Description
\$context.integration.status	The status code returned from an integration. For Lambda proxy integrations, this is the status code that your Lambda function code returns.
\$context.integration.timeToAllHeaders	The time between when API Gateway establishes the integration connection to when it receives all integration response headers from the client.
\$context.integration.timeToFirstContent	The time between when API Gateway establishes the integration connection to when it receives the first content bytes.
\$context.integrationLatency	The integration latency in ms.
\$context.integrationStatus	For Lambda proxy integration, this parameter represents the status code returned from AWS Lambda, not from the backend Lambda function code.
\$context.isCanaryRequest	Returns true if the request was directed to the canary and false if the request was not directed to the canary. Present only when you have a canary enabled.
\$context.path	The request path. For example, for a non-proxy request URL of https://rest-api-id.execute-api.region.amazonaws.com/stage/root/child , the \$context.path value is /{stage}/root/child .

Parameter	Description
\$context.protocol	<p>The request protocol, for example, HTTP/1.1.</p> <div data-bbox="845 312 1519 762" style="border: 1px solid #ccc; padding: 10px;"><p> Note</p><p>API Gateway APIs can accept HTTP/2 requests, but API Gateway sends requests to backend integrations using HTTP/1.1. As a result, the request protocol is logged as HTTP/1.1 even if a client sends a request that uses HTTP/2.</p></div>
\$context.requestId	An ID for the request. Clients can override this request ID. Use \$context.extendedRequestId for a unique request ID that API Gateway generates.
\$context.requestOverride.header. <i>header_name</i>	The request header override. If this parameter is defined, it contains the headers to be used instead of the HTTP Headers that are defined in the Integration Request pane. For more information, see Override your API's request and response parameters and status codes for REST APIs in API Gateway .
\$context.requestOverride.path. <i>path_name</i>	The request path override. If this parameter is defined, it contains the request path to be used instead of the URL Path Parameters that are defined in the Integration Request pane. For more information, see Override your API's request and response parameters and status codes for REST APIs in API Gateway .

Parameter	Description
\$context.requestOverride.querystring. <i>querystring_name</i>	The request query string override. If this parameter is defined, it contains the request query strings to be used instead of the URL Query String Parameters that are defined in the Integration Request pane. For more information, see Override your API's request and response parameters and status codes for REST APIs in API Gateway .
\$context.responseLatency	The response latency in ms.
\$context.responseLength	The response payload length in bytes.
\$context.responseOverride.header. <i>header_name</i>	The response header override. If this parameter is defined, it contains the header to be returned instead of the Response header that is defined as the Default mapping in the Integration Response pane. For more information, see Override your API's request and response parameters and status codes for REST APIs in API Gateway .
\$context.responseOverride.status	The response status code override. If this parameter is defined, it contains the status code to be returned instead of the Method response status that is defined as the Default mapping in the Integration Response pane. For more information, see Override your API's request and response parameters and status codes for REST APIs in API Gateway .
\$context.requestTime	The CLF -formatted request time (dd/MMM/yy yy:HH:mm:ss +-hhmm).
\$context.requestTimeEpoch	The Epoch -formatted request time, in milliseconds.

Parameter	Description
\$context.resourceId	The identifier that API Gateway assigns to your resource.
\$context.resourcePath	The path to your resource. For example, for the non-proxy request URI of <code>https://[rest-api-id].execute-api.[region].amazonaws.com/{stage}/root/child</code> , The <code>\$context.resourcePath</code> value is <code>/root/child</code> . For more information, see Tutorial: Create a REST API with an HTTP non-proxy integration .
\$context.stage	The deployment stage of the API request (for example, Beta or Prod).
\$context.status	The method response status.
\$context.tlsVersion	The TLS version that is negotiated during the TLS handshake between the client and API Gateway.
\$context.waf.error	The error message returned from AWS WAF.
\$context.waf.latency	The AWS WAF latency in ms.
\$context.waf.status	The status code returned from AWS WAF.
\$context.xrayTraceId	The trace ID for the X-Ray trace. For more information, see the section called "Set up AWS X-Ray" .
\$context.wafResponseCode	The response received from AWS WAF : <code>WAF_ALLOW</code> or <code>WAF_BLOCK</code> . Will not be set if the stage is not associated with a web ACL. For more information, see the section called "AWS WAF" .

Parameter	Description
\$context.webaclArn	The complete ARN of the web ACL that is used to decide whether to allow or block the request. Will not be set if the stage is not associated with a web ACL. For more information, see the section called "AWS WAF" .

Trace user requests to REST APIs using X-Ray in API Gateway

You can use [AWS X-Ray](#) to trace and analyze user requests as they travel through your Amazon API Gateway REST APIs to the underlying services. API Gateway supports X-Ray tracing for all API Gateway REST API endpoint types: Regional, edge-optimized, and private. You can use X-Ray with Amazon API Gateway in all AWS Regions where X-Ray is available.

Because X-Ray gives you an end-to-end view of an entire request, you can analyze latencies in your APIs and their backend services. You can use an X-Ray service map to view the latency of an entire request and that of the downstream services that are integrated with X-Ray. You can also configure sampling rules to tell X-Ray which requests to record and at what sampling rates, according to criteria that you specify.

If you call an API Gateway API from a service that's already being traced, API Gateway passes the trace through, even if X-Ray tracing isn't enabled on the API.

You can enable X-Ray for an API stage by using the API Gateway console, or by using the API Gateway API or CLI.

Topics

- [Set up AWS X-Ray with API Gateway REST APIs](#)
- [Use AWS X-Ray service maps and trace views with API Gateway](#)
- [Configure AWS X-Ray sampling rules for API Gateway APIs](#)
- [AWS X-Ray traces for Amazon API Gateway APIs](#)

Set up AWS X-Ray with API Gateway REST APIs

In this section you can find detailed information on how to set up [AWS X-Ray](#) with API Gateway REST APIs.

Topics

- [X-Ray tracing modes for API Gateway](#)
- [Permissions for X-Ray tracing](#)
- [Enabling X-Ray tracing in the API Gateway console](#)
- [Enabling AWS X-Ray tracing using the API Gateway CLI](#)

X-Ray tracing modes for API Gateway

The path of a request through your application is tracked with a trace ID. A trace collects all of the segments generated by a single request, typically an HTTP GET or POST request.

There are two modes of tracing for an API Gateway API:

- **Passive:** This is the default setting if you have not enabled X-Ray tracing on an API stage. This approach means that the API Gateway API is only traced if X-Ray has been enabled on an upstream service.
- **Active:** When an API Gateway API stage has this setting, API Gateway automatically samples API invocation requests, based on the sampling algorithm specified by X-Ray.

When active tracing is enabled on a stage, API Gateway creates a service-linked role in your account, if the role does not exist already. The role is named `AWSServiceRoleForAPIGateway` and will have the `APIGatewayServiceRolePolicy` managed policy attached to it. For more information about service-linked roles, see [Using Service-Linked Roles](#).

 **Note**

X-Ray applies a sampling algorithm to ensure that tracing is efficient, while still providing a representative sample of the requests that your API receives. The default sampling algorithm is 1 request per second, with 5 percent of requests sampled past that limit.

You can change the tracing mode for your API by using the API Gateway management console, the API Gateway CLI, or an AWS SDK.

Permissions for X-Ray tracing

When you enable X-Ray tracing on a stage, API Gateway creates a service-linked role in your account, if the role does not exist already. The role is named `AWSServiceRoleForAPIGateway`

and will have the `APIGatewayServiceRolePolicy` managed policy attached to it. For more information about service-linked roles, see [Using Service-Linked Roles](#).

Enabling X-Ray tracing in the API Gateway console

You can use the Amazon API Gateway console to enable active tracing on an API stage.

These steps assume that you have already deployed the API to a stage.

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose your API, and then in the main navigation pane, choose **Stages**.
3. In the **Stages** pane, choose a stage.
4. In the **Logs and tracing** section, choose **Edit**.
5. To enable active X-Ray tracing, select **X-Ray tracing** to turn on X-Ray tracing.
6. Choose **Save changes**.

Once you've enabled X-Ray for your API stage, you can use the X-Ray management console to view the traces and service maps.

Enabling AWS X-Ray tracing using the API Gateway CLI

The following [create-stage](#) command creates a stage with active X-Ray tracing:

```
aws apigateway create-stage \
  --rest-api-id rest-api-id \
  --stage-name stage-name \
  --deployment-id deployment-id \
  --region region \
  --tracing-enabled=true
```

The output will look like the following:

```
{  
  "tracingEnabled": true,  
  "stageName": stage-name,  
  "cacheClusterEnabled": false,  
  "cacheClusterStatus": "NOT_AVAILABLE",  
  "deploymentId": deployment-id,  
  "lastUpdatedDate": 1533849811,  
  "createdDate": 1533849811,
```

```
"methodSettings": {}  
}
```

The following [create-stage](#) command creates a stage without active X-Ray tracing:

```
aws apigateway create-stage \  
  --rest-api-id rest-api-id \  
  --stage-name stage-name \  
  --deployment-id deployment-id \  
  --region region \  
  --tracing-enabled=false
```

The output will look like the following:

```
{  
  "tracingEnabled": false,  
  "stageName": stage-name,  
  "cacheClusterEnabled": false,  
  "cacheClusterStatus": "NOT_AVAILABLE",  
  "deploymentId": deployment-id,  
  "lastUpdatedDate": 1533849811,  
  "createdDate": 1533849811,  
  "methodSettings": {}  
}
```

The following [update-stage](#) turns on active X-Ray tracing for a deployed API:

```
aws apigateway update-stage \  
  --rest-api-id rest-api-id \  
  --stage-name stage-name \  
  --patch-operations op=replace,path=/tracingEnabled,value=true
```

The following [update-stage](#) turns off active X-Ray tracing for a deployed API:

```
aws apigateway update-stage \  
  --rest-api-id rest-api-id \  
  --stage-name stage-name \  
  --region region \  
  --patch-operations op=replace,path=/tracingEnabled,value=false
```

The output will look like the following:

```
{  
    "tracingEnabled": false,  
    "stageName": stage-name,  
    "cacheClusterEnabled": false,  
    "cacheClusterStatus": "NOT_AVAILABLE",  
    "deploymentId": deployment-id,  
    "lastUpdatedDate": 1533850033,  
    "createdDate": 1533849811,  
    "methodSettings": {}  
}
```

Once you've enabled X-Ray for your API stage, use the X-Ray CLI to retrieve trace information. For more information, see [Using the X-Ray API with the AWS CLI](#).

Use AWS X-Ray service maps and trace views with API Gateway

In this section you can find detailed information on how to use [AWS X-Ray](#) service maps and trace views with API Gateway.

Topics


- [Example X-Ray service map](#)
- [Example X-Ray trace view](#)

Example X-Ray service map

AWS X-Ray service maps show information about your API and all of its downstream services. When X-Ray is enabled for an API stage in API Gateway, you'll see a node in the service map containing information about the overall time spent in the API Gateway service. You can get detailed information about the response status and a histogram of the API response time for the selected timeframe. For APIs integrating with AWS services such as AWS Lambda and Amazon DynamoDB, you will see more nodes providing performance metrics related to those services. There will be a service map for each API stage.

The following example shows a service map for the test stage of an API called `xray`. This API has two Lambda integrations. The nodes represent the API Gateway service and the two Lambda functions.

For a detailed explanation of service map structure, see [Use the X-Ray trace map](#).



From the service map, you can zoom in to see a trace view of your API stage. The trace will display in-depth information regarding your API, represented as segments and subsegments. For example, the trace for the service map shown above would include segments for the Lambda service and Lambda function. For more information, see [AWS Lambda and AWS X-Ray](#).

If you choose a node or edge on an X-Ray service map, the X-Ray console shows a latency distribution histogram. You can use a latency histogram to see how long it takes for a service to complete its requests. Following is a histogram of the API Gateway stage named `xray/test` in the previous service map. For a detailed explanation of latency distribution histograms, see [Use Latency Histograms](#).


Service details ?

Name: xray/test

Type: AWS::ApiGateway::Stage

Response distribution

Click and drag to select an area to zoom in on or use as a latency filter when viewing traces.



Response status

Choose response statuses to add to the filter when viewing traces.


- OK: 100% Error: 0%

- Fault: 0% Throttle: 0%

Example X-Ray trace view

The following diagram shows a trace view generated for the example API described above, with a Lambda backend function. A successful API method request is shown with a response code of 200.

For a detailed explanation of trace views, see [View traces and trace details](#).



Configure AWS X-Ray sampling rules for API Gateway APIs

You can use AWS X-Ray console or SDK to configure sampling rules for your Amazon API Gateway API. A sampling rule specifies which requests X-Ray should record for your API. By customizing sampling rules, you can control the amount of data that you record, and modify sampling behavior on the fly without modifying or redeploying your code.

Before you specify your X-Ray sampling rules, read the following topics in the X-Ray Developer Guide:

- [Configure sampling rules](#)
- [Using Sampling Rules with the X-Ray API](#)

Topics

- [X-Ray sampling rule option values for API Gateway APIs](#)
- [X-Ray sampling rule examples](#)

X-Ray sampling rule option values for API Gateway APIs

The following X-Ray sampling options are relevant for API Gateway. String values can use wildcards to match a single character (?) or zero or more characters (*). For more details, including a detailed explanation of how the **Reservoir** and **Rate** settings are used, [Configure sampling rules](#).

- **Rule name** (string) — A unique name for the rule.
- **Priority** (integer between 1 and 9999) — The priority of the sampling rule. Services evaluate rules in ascending order of priority, and make a sampling decision with the first rule that matches.
- **Reservoir** (nonnegative integer) — A fixed number of matching requests to instrument per second, before applying the fixed rate. The reservoir is not used directly by services, but applies to all services using the rule collectively.
- **Rate** (number between 0 and 100) — The percentage of matching requests to instrument, after the reservoir is exhausted.
- **Service name** (string) — API stage name, in the form **{api-name}/{stage-name}**. For example, if you were to deploy the [PetStore](#) sample API to a stage named test, the **Service name** value to specify in your sampling rule would be **pets/test**.
- **Service type** (string) — For an API Gateway API, either **AWS::ApiGateway::Stage** or **AWS::ApiGateway::*** can be specified.
- **Host** (string) — The hostname from the HTTP host header. Set this to * to match against all hostnames. Or you can specify a full or partial hostname to match, for example, **api.example.com** or ***.example.com**.
- **Resource ARN** (string) — The ARN of the API stage, for example, **arn:aws:apigateway:region::restapis/api-id/stages/stage-name**.

The stage name can be obtained from the console or the API Gateway CLI or API. For more information about ARN formats, see the [Amazon Web Services General Reference](#).

- **HTTP method** (string) — The method to be sampled, for example, **GET**.
- **URL path** (string) — The URL path of the request.
- (optional) **Attributes** (key and value) — Headers from the original HTTP request, for example, **Connection**, **Content-Length**, or **Content-Type**. Each attribute value can be up to 32 characters long.

X-Ray sampling rule examples

Sampling rule example #1

This rule samples all GET requests for the testxray API at the test stage.

- **Rule name — test-sampling**
- **Priority — 17**
- **Reservoir size — 10**
- **Fixed rate — 10**
- **Service name — testxray/test**
- **Service type — AWS::ApiGateway::Stage**
- **HTTP method — GET**
- **Resource ARN — ***
- **Host — ***

Sampling rule example #2

This rule samples all requests for the testxray API at the prod stage.

- **Rule name — prod-sampling**
- **Priority — 478**
- **Reservoir size — 1**
- **Fixed rate — 60**
- **Service name — testxray/prod**
- **Service type — AWS::ApiGateway::Stage**
- **HTTP method — ***
- **Resource ARN — ***
- **Host — ***
- **Attributes — {}**

AWS X-Ray traces for Amazon API Gateway APIs

This section discusses AWS X-Ray trace segments, subsegments, and other trace fields for Amazon API Gateway APIs.

Before you read this section, review the following topics in the X-Ray Developer Guide:

- [Use an AWS Management Console](#)
- [X-Ray segment documents](#)
- [Concepts](#)

Topics

- [Examples of trace objects for an API Gateway API](#)
- [Understanding the trace](#)

Examples of trace objects for an API Gateway API

This section discusses some of the objects you may see in a trace for an API Gateway API.

Annotations

Annotations can appear in segments and subsegments. They are used as filtering expressions in sampling rules to filter traces. For more information, see [Configure sampling rules](#).

Following is an example of an annotations object, in which an API stage is identified by the API ID and the API stage name:

```
"annotations": {  
    "aws:api_id": "a1b2c3d4e5",  
    "aws:api_stage": "dev"  
}
```

For more information about annotations, see [X-Ray segment documents](#), and then choose **X-Ray segment documents, Annotations**.

AWS resource data

The aws object appears only in segments. Following is an example of an aws object that matches the Default sampling rule. For an in-depth explanation of sampling rules, see [Configure sampling rules](#).

```
"aws": {  
    "xray": {  
        "sampling_rule_name": "Default"  
    },
```

```
        "api_gateway": {  
            "account_id": "123412341234",  
            "rest_api_id": "a1b2c3d4e5",  
            "stage": "dev",  
            "request_id": "a1b2c3d4-a1b2-a1b2-a1b2-a1b2c3d4e5f6"  
        }  
    }  
}
```

For more information about the aws object, see [X-Ray segment documents](#), and then choose **X-Ray segment documents, AWS resource data**.

Understanding the trace

Following is a trace segment for an API Gateway stage. For a detailed explanation of the fields that make up the trace segment, see [X-Ray segment documents](#).

```
        "sampling_rule_name": "Default"
    },
    "api_gateway": {
        "account_id": "123412341234",
        "rest_api_id": "a1b2c3d4e5",
        "stage": "dev",
        "request_id": "a1b2c3d4-a1b2-a1b2-a1b2c3d4e5f6"
    }
},
"annotations": {
    "aws:api_id": "a1b2c3d4e5",
    "aws:api_stage": "dev"
},
"trace_id": "1-a1b2c3d4-a1b2c3d4a1b2c3d4a1b2c3d4",
"origin": "AWS::ApiGateway::Stage",
"resource_arn": "arn:aws:apigateway:us-east-1::/restapis/a1b2c3d4e5/stages/dev",
"subsegments": [
    {
        "id": "abcdefghijklm",
        "name": "Lambda",
        "start_time": 1533928226.233,
        "end_time": 1533928226.6130002,
        "http": {
            "request": {
                "url": "https://example.com/2015-03-31/functions/arn:aws:lambda:us-east-1:123412341234:function:xray123/invocations",
                "method": "GET"
            },
            "response": {
                "status": 200,
                "content_length": 62
            }
        },
        "aws": {
            "function_name": "xray123",
            "region": "us-east-1",
            "operation": "Invoke",
            "resource_names": [
                "xray123"
            ]
        },
        "namespace": "aws"
    }
]
```

```
        ],
    },
    "Id": "a1b2c3d4a1b2c3d4"
}
```

API Gateway portals

You can use an API Gateway portal to share your APIs and API documentation with API consumers in a web page. A portal contains a set of *portal products*. Each portal product is a logical grouping of REST APIs and contains the documentation that you create and publish for your API consumers. Product pages within a portal contain the custom documentation at the portal product level. *Product REST endpoint pages* contain the documentation for each of the REST APIs and the path, method, and stage of a REST API. The combination of product pages and product REST endpoint pages provide the complete documentation to allow API consumers to learn how to start using your REST APIs.

Use a portal to do the following:

- Use API Gateway for your entire API lifecycle, from creating your APIs to documenting and distributing them.
- Share portal products across AWS accounts.
- Customize and share a central location for your portal products and provide product pages.

Considerations

The following considerations might impact your use of API Gateway portals:

- You can only create portals to share REST APIs.
- Portals are created at the AWS Region level. Your portal can only contain REST APIs that are in the same Region where you create the portal.
- You can only use the AWS Management Console, AWS CLI, or AWS SDKs to create and share your portals.
- You can only control access to your portal using Amazon Cognito user pools. Your portal consumers can either sign in directly through a user pool, or they can federate through a third-party identity provider (IdP). If you use an Amazon Cognito user pool, you cannot set a client secret for your user pool. For more information, see [Amazon Cognito user pools](#).

Portal products in API Gateway

A *portal product* represents a service or functionality that you want to share. Your portal product is a collection of product REST endpoints and product pages. *Product REST endpoints* are the access points to your portal product, and they consist of the path and method of a REST API and the stage it's deployed to. *Product pages* are documentation that you provide to explain how API consumers can use your product endpoints. A portal product can contain the entire Prod stage as a collection of product REST endpoints or just the GET /pets resource deployed to the Prod stage as a singular product REST endpoint.

Your portal product is customizable. You can add custom documentation, rename the product REST endpoints, reorganize the display order, add new sections, and share products across AWS accounts. In order for any changes you make to your portal product to take effect, you must republish any portals that use your portal product.

Pet adoption portal product example

As an example, you could have multiple REST APIs that represent a pet adoption service. You could use API Gateway to create a pet adoption portal product. This portal product would help customers discover which APIs they should use to meet and adopt pets. This portal product uses REST APIs that you already created, but it allows you to regroup and organize them. You can also provide documentation about the terms and conditions of using your pet adoption portal product and let customers try out your APIs. This information is all stored in your portal product.

The following table shows three APIs that represent a pet adoption portal product, and their corresponding product REST endpoint operation names and page section names.

REST API ID	REST API path and method	REST API stage	Operation name	Page section
kf5387miad	GET /dogs	Prod	View dogs	AdoptAnimals
kf5387miad	GET /dogs/{dogId}	Prod	View dog	AdoptAnimals
ra8obxcevg	GET /cats	Prod	View cats	AdoptAnimals

REST API ID	REST API path and method	REST API stage	Operation name	Page section
ra8obxcevg	GET /cats/{catId}	Prod	View cat	AdoptAnimals
h0rpx9cm62	ANY /user/{userId}/ {petId+}	Beta	Request visit	AdoptProcess

In this example, two REST APIs, `ra8obxcevg` and `kf5387miad`, are grouped together in the `AdoptAnimals` section. The result of this ordering navigation would look like the following in a portal:

The screenshot shows the API documentation for a "Pet adoption" product. On the left, a sidebar lists sections: "Documentation" (Pet adoption) and "API reference". Under "API reference", there are two expanded sections: "AdoptAnimals" and "AdoptProcess".

- AdoptAnimals:** Contains operations for viewing cats and dogs.
 - View cat:** GET https://ra8obxcevg.execute-api.us-west-1.amazonaws.com/Prod/cats/{catId}
 - View cats:** GET https://ra8obxcevg.execute-api.us-west-1.amazonaws.com/Prod/cats
 - View dogs:** GET https://ra8obxcevg.execute-api.us-west-1.amazonaws.com/Prod/dogs
 - View dog:** GET https://ra8obxcevg.execute-api.us-west-1.amazonaws.com/Prod/dogs
- AdoptProcess:** Contains operations for requesting visits.
 - Request visit:** GET https://ra8obxcevg.execute-api.us-west-1.amazonaws.com/Prod/visits
 - Request visit:** POST https://ra8obxcevg.execute-api.us-west-1.amazonaws.com/Prod/visits
 - Request visit:** PUT https://ra8obxcevg.execute-api.us-west-1.amazonaws.com/Prod/visits
 - Request visit:** PATCH https://ra8obxcevg.execute-api.us-west-1.amazonaws.com/Prod/visits
 - Request visit:** DELETE https://ra8obxcevg.execute-api.us-west-1.amazonaws.com/Prod/visits
 - Request visit:** OPTIONS https://ra8obxcevg.execute-api.us-west-1.amazonaws.com/Prod/visits
 - Request visit:** HEAD https://ra8obxcevg.execute-api.us-west-1.amazonaws.com/Prod/visits

The main content area displays the "View cat" operation. It includes a summary, arguments (with one required argument "catId"), request body (none), and responses (200 status code with a JSON schema example). Below this, the "View cats" operation is also shown with its own summary, request body (none), and responses.

Because the ANY method is a catch-all method, the portal shows all the supported HTTP methods. This portal also contains documentation that was created by the portal product owner.

Next steps

To get started with portal products, you can do the following:

- To create a portal product, see [the section called “Create a portal product”](#).
- To learn about the try it functionality, see [the section called “Enable try it for a product REST endpoint in your portal”](#).
- To learn about product pages, see [the section called “Create a product page”](#).
- To learn about sharing your portal product, see [the section called “Share portal products”](#).

After you create a portal product, you can publish it to a portal. For more information, see [the section called “Create a portal”](#).

Create a portal product in API Gateway

The following procedure shows how to create a portal product. A portal is a collection of *portal products*. After you create your portal product, you create product REST endpoints and product pages. To learn about portal products, see [the section called “Portal product”](#).

Considerations

The following considerations might impact how you create a portal product:

- Your portal product can contain both private and public REST APIs. Private APIs aren't supported for the try it functionality and, as a result, have a visual difference in your portal. As a portal owner, you might need to provide documentation to explain this.
- If you create your portal product using the AWS CLI or AWS SDKs, your portal won't have any product endpoints or product pages. You need to add these resources using the AWS CLI or console. To learn how to create a product REST endpoint, see [the section called “Create a product REST endpoint”](#). To learn how to create a product page, see [the section called “Create a product page”](#).

Create a portal product


The following procedure shows how to create a portal product.

To create a portal product

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. In the main navigation pane, choose **Portal products**.
3. Choose **Create product**.
4. For **Product name**, enter the name of your portal product.
5. For **Product description**, enter a description.
6. Choose **Next**.
7. To select your product REST endpoints, under **API endpoints** choose an API, and then choose a stage.
8. To add an endpoint to your product REST endpoints, select the API endpoint, and then choose **Add to product**.

Note

Do not choose **Next** without first choosing **Add to product**.



The API endpoint will appear in the **Selected API endpoints** list.

9. Choose **Next**.
10. Review your selection and choose **Create product**.

After you create your portal product using the console, all your product pages and product REST endpoint pages are drafts and won't appear in a portal. To have your product pages and product REST endpoint pages visible to consumers, you need to add your draft to a section. If you create

your portal product using the AWS CLI or AWS SDKs, you add the draft to the section in the AWS CLI command. Regardless of how you add your draft to a section, you must publish the portal that uses your portal products for it to be visible to consumers.

To add your draft to a page section

1. Your drafts are listed in the **Documentation** tab. There are **Draft documentation pages** for your product pages and **Draft API reference pages** for your product REST endpoint pages. Choose **Draft API reference pages**.
2. Choose a draft API reference page.

If you don't have any product REST endpoints, you won't have any draft API reference pages.

To learn how to create a product REST endpoint, see [the section called "Create a product REST endpoint".](#)

3. Choose **Edit page**.
4. On this page, you can overwrite any existing API documentation parts or use the API Gateway documentation. To allow the contents of your product REST endpoint page to be visible to consumers, under **Section name**, enter a name. If this was the /pets-GET endpoint, the page name could be Pets.
5. Choose **Save changes**.
6. The new page name you created appears under the **API reference pages** section.

To allow the new page to be visible to consumers, you still need to republish your portal. For more information, see [the section called "Publish a portal".](#)

Create a product REST endpoint in API Gateway

A product REST endpoint is an access point to your portal product. Each endpoint consists of the path and method of a REST API and the stage it's deployed to. The endpoint includes any documentation you've defined for your REST API, or can be updated with custom documentation. When you create your product REST endpoint, you configure the following settings:

- The product REST endpoint's operation name. If your REST API has the path and method GET /pets, in a portal, the name is /pets. Using the operation name, you can change the product REST endpoint name to Pet summaries. This doesn't impact your existing API.
- The try it functionality for your product endpoint. This lets API consumers try your APIs in your portal. If you create a product endpoint for a private API, the try it functionality is set to

UNAVAILABLE. For more information, see [the section called “Enable try it for a product REST endpoint in your portal”](#).

- If you currently have documentation parts defined for your REST API, you can either import the documentation or override your existing documentation and create new product-level documentation using [GitHub Flavored Markdown](#). Any documentation overrides do not propagate back to your API Gateway API documentation parts. If you import your current documentation parts, API Gateway syncs changes across your API to your product REST endpoint.

Create a product REST endpoint

The following procedure shows how to add a product REST endpoint to an existing portal product. To learn how to create a portal product and a product REST endpoint together, see [the section called “Create a portal product”](#).

To create a product REST endpoint for a product portal

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. In the main navigation pane, choose **Portal products**.
3. Choose a portal product.
4. Choose the **Associated endpoints** tab, and then choose **Add endpoints**.
5. To select your product REST endpoints, under **API endpoints** choose an API, and then choose a stage.
6. To add an endpoint to your product REST endpoints, select the API endpoint, and then choose **Add to product**.

The API endpoint will appear in the **Selected API endpoints** list.

7. Choose **Submit**.
8. Your product REST endpoint page is now a draft. Choose **Draft API reference pages**, and then choose your product REST endpoint page to finalize the content of the page.
9. Choose **Edit page**.
10. To override the existing API Gateway documentation, for **Documentation source**, turn on **Override the documentation** and do the following:
 - a. For **Display content**, choose **Create override**.

- b. For **Operation name**, enter a new operation name.
 - c. For **Page body**, enter your custom documentation.
 - d. (Optional) For **Endpoint**, enter a custom endpoint that appears in your portal.
11. To let customers invoke your API in your portal, select **Try it functionality**. For more information, see [the section called “Enable try it for a product REST endpoint in your portal”](#).
12. For **Section name**, enter a name or choose an existing section. When you add your product REST endpoint to a section, consumers can view your content on a published portal.
13. Choose **Save changes**.

To allow the new page to be visible to consumers, you still need to republish your portal. For more information, see [the section called “Publish a portal”](#).

Create a product page in API Gateway

A product page helps your product consumers understand and use your products. The documentation is at the product-level, so any portals that include your product have this documentation. API Gateway supports two types of product pages written in [GitHub Flavored Markdown](#):

Overview page

When you create your product, API Gateway automatically generates an **Overview** page for your product based on the information you provide when you create your product. This page has additional formatting that can't be changed. You can modify the text or remove the page from the portal product.

Custom pages

A custom page is a page written in Markdown. You might use this section for terms and conditions or a tutorial on how to use your product. You can change any custom page into an overview page. When you change a custom page into an overview page, the page content is formatted to match the overview page.

Considerations

The following considerations might impact your use of product pages:

- This documentation is not at the API-level and doesn't include any methods, resources, or any request parameters. To learn how to modify the documentation at the API-level for a product, see [the section called "Update a product REST endpoint"](#).
- You can't directly upload a .md file to your product.
- You can modify the order of the product pages by modifying the page list in the display order of your portal product. For more information, see [the section called "Update a portal product"](#).
- You need to republish any portals that include your product for documentation changes to take effect.
- If you have multiple portals that use the same portal product, the product pages are the same across all portals. To have the same product REST endpoints but different product pages, create multiple products.

Create a product page

The following procedure shows how to create a product page.

To create a product page

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. In the main navigation pane, choose **Portal products**.
3. Choose a product.
4. Under **Documentation**, choose **Create custom page**.
5. For **Page title**, enter the page title.
6. For **Body**, enter your supplemental documentation using GitHub Flavored Markdown.

The **Preview** section shows how your content appears in a portal. The final visual style might change based on your portal settings.

7. Choose **Create product page**.
8. Your product page is now a draft. Choose **Draft documentation pages**, and then choose your product page to finalize the content of the page.
9. Choose **Edit page**.
10. For **Section name**, enter a name or choose an existing section. When you add your product page to a section, consumers can view your content on a published portal.
11. Choose **Save changes**.

To allow the new page to be visible to consumers, you still need to republish your portal. For more information, see [the section called “Publish a portal”](#).

Update a portal product in API Gateway

When you update a portal product, you can change the name, description, or the display order of how your product REST endpoints and product pages appear. To modify the display order, you modify the page list for product pages and the section name for product endpoints. If you do this using the AWS CLI or SDKs, you specify the product page ARN or the product REST endpoint ARN. You need to republish any portals that use your products for your API consumers to see the changes reflected in a portal.

Update a portal product

The following procedure shows how to change the section list to reorder the product REST endpoints as they will appear in a portal. In this procedure, we assume you have at least two product REST endpoints in your portal product.

To update a portal product

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. In the main navigation pane, choose **Portal products**.
3. Choose a product.
4. In the **Documentation** tab, for **Product pages**, choose **Manage**.
5. Drag and drop the product REST endpoints to reorder them. You can also move product REST endpoints and product pages into the draft pages section. Pages in the draft pages are won't be visible in your portal.
6. (Optional) Rename the product REST endpoint names or add a new API reference section. These changes won't impact your REST APIs.
7. Choose **Save changes**.

Update a product REST endpoint in API Gateway

When you update a product REST endpoint, you can change all the settings of the product endpoint except for the path and method of a REST API and the stage it's deployed to. Any changes to your product endpoints are updated automatically, but you need to republish any portals that use your products to see the changes reflected in a portal.

Update a product REST endpoint

The following procedure shows how to update a product REST endpoint to overwrite the current API documentation with custom API reference documentation.

To update a product REST endpoint

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. In the main navigation pane, choose **Portal products**.
3. Choose a product.
4. In the **Documentation** tab, under **API reference pages**, choose the name of a product REST endpoint, such as **/dogs - GET**.
5. For **Preview**, choose **Edit page**.
6. For **Documentation source**, turn on **Override the documentation**.
7. For **Display content**, choose **Override the existing content**.

If you choose **Remove all content**, the content is removed from the page, but you can choose **Override the existing content** to access the documentation again.

8. In **Page body**, enter custom API reference documentation using [GitHub Flavored Markdown](#).
This documentation will not propagate back to API Gateway.
9. Choose **Save changes**.
10. You must republish any portals that use this portal product for the changes to take effect.

Update a product page in API Gateway

When you update a product page, you can change all the settings of the product page. Any changes to your product page are updated automatically, but you need to republish any portals that use your products to see the changes reflected in a portal.

Share portal products in API Gateway

You can share a portal product across AWS accounts using AWS RAM. When you share a portal product, the other account can use your portal product in their own portal. With shared portal products, you can create a single catalog of your organization's APIs and enforce governance

standards across your API ecosystem. At the same time, sharing portal products provides flexibility for API providers to develop, test, and maintain APIs in their own accounts.

Considerations

The following considerations might impact how you share portal resources:

- When you share your product with another account, that account cannot modify any properties of your REST API. This includes the integration endpoints, the authorization strategy, or the stage configuration.
 - When you add another account's portal product into your portal, the portal product owner cannot view or control any other properties of your portal. The portal product owner only knows that the product is being used in your portal.
 - API Gateway portal products are shared at the AWS Region level.
 - You can use one resource share with multiple principals, and after you create the resource share, you can add more principals to it. We recommend that when possible, you reuse your resource share.
 - If both accounts are in the same organization using AWS Organizations, the resource share is automatically accepted. You still need to create the resource share using AWS RAM.
 - If both accounts are in the same organization using AWS Organizations and resource sharing within your organization is enabled, any principals in the organization that you share with are automatically granted access to the resource shares. There is no need for an invitation and you can skip the resource share.
 - If the account you shared the product with doesn't accept the resource share within **12 hours**, you must share the resource again.
 - After you create the resource share, AWS RAM updates the product sharing policy of your product to prevent access to principals without explicit allow access. For more information, see [Determining whether a request is allowed or denied within an account](#) in the IAM User Guide.

The updated resource policy will look like the following:

```
{
    "Version": "2012-10-17",
    "Statement": [
        {
            "Effect": "Allow",
            "Action": [
                "apigateway:GetProduct",
                "apigateway:PutItem"
            ],
            "Resource": [
                "arn:aws:apigateway:us-east-1:execute-api:action:PutItem"
            ]
        }
    ]
}
```

```
        "apigateway>ListEndpoints",
        "apigateway>ListPages",
        "apigateway>GetEndpoint",
        "apigateway>GetPage"
    ],
    "Resource": [
        "arn:aws:apigateway:us-east-1:111122223333:/portalproducts/product-id",
        "arn:aws:apigateway:us-east-1:111122223333:/portalproducts/product-id/*"
    ]
}
```

AWS RAM has prevented principals without explicit allow access to add your product to their portal, by adding the following:

```
"StringNotEquals": { "aws:PrincipalAccount": "555555555555" }
```

To learn how to share a product, see [the section called “Share your portal product with a portal owner”](#). To learn how to add a product shared with you to your portal, see [the section called “Add a shared portal product to your portal”](#).

Share your portal product with a portal owner in API Gateway

As a product owner, you can share your product with a portal owner in another AWS account using AWS RAM. You maintain full control of all product pages and product REST endpoint pages.

Considerations

The following considerations might impact how you share portal products:

- You can share or unshare your portal products at any time. If you unshare a portal product while it's being used in a published portal, the portal owner won't be able to view the portal product, view any updates made to it, or republish or preview the portal until they remove the portal product.
- You can view the portal products that you've shared with other accounts.
- You can't modify any portals that contain your portal product, unless you create the portal yourself.

Share your portal product

The following procedure shows how to create a resource share.

AWS Management Console

To use the AWS Management Console, see [Creating a resource share in AWS RAM](#) in the *AWS RAM User Guide*.

For **Select resource type**, choose **API Gateway Product**.

AWS CLI

The following [create-resource-share](#) creates a resource share for your private custom domain name. It can take a few minutes for the resource and principal associations to complete. For principals, provide an account ID or an Organizations ID, such as arn:aws:organizations::123456789012:organization/o-1234abcd. You can provide multiple principals for your resource share.

```
aws ram create-resource-share \
--region us-west-2 \
--name portal-product-resource-share \
--permission-arns arn:aws:ram::aws:permission/
AWSRAMDefaultPermissionAPIGatewayDeveloperPortalProduct \
--resource-arns arn:aws:apigateway:us-west-2:111122223333:/portalproducts/
p000000000 \
--principals 222222222222
```

To unshare your portal product, use AWS RAM to delete the resource share.

At any time, you can modify the product sharing policy to modify which principals can use your portal products in their portals.

To update the product sharing policy

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. In the main navigation pane, choose **Portal products**.
3. Choose a product.
4. In the **Product sharing** tab, for **Product sharing policy**, choose **Manage product sharing policy**.

5. If you haven't shared your product before, your product sharing policy will deny all access to other accounts to your portal products. You need to update the policy to allow access for certain accounts to your portal product.
6. After you have updated your product sharing policy, choose **Save changes**.

Add a shared portal product to your portal in API Gateway

As a portal owner, you can use portal products shared with you by other accounts in your portal. You maintain full control of your portal.

Considerations

The following considerations might impact how you share portal resources:

- You must accept the product resource share from the product owner to use their product in your portal. If you and the product owner are in the same Organizations, AWS RAM can complete some sharing steps for you.
- If the product owner unshares a product while it's in your published portal, the product will still be visible on the portal, but you won't be able to publish the portal again until you remove this product. It's your responsibility as the portal owner to remove the product from your portal, as the product owner can't do that for you.
- You can view the portal products, the product pages, and the product REST endpoint pages, but you cannot modify any of these resources.
- If a product is shared with you, you can't share it with another account.

(Optional) Accept the resource share

After your product owner creates a resource share, you have **12 hours** to accept it. If you are in the same organization using AWS Organizations as the product owner, the share is automatically accepted. If you are in an organization that has automatic shared resources enabled, the resource is automatically shared with you.

AWS Management Console

To use the AWS Management Console, see [Accepting and rejecting resource share invitations](#) in the *AWS RAM User Guide*.

AWS CLI

To find all the resources shared with you, use the following [get-resource-share-invitations](#) command:

```
aws ram get-resource-share-invitations \
--region us-west-2
```

Use the resulting resource share ARN to accept the resource share invitation. The following [accept-resource-share-invitation](#) command accepts the resource share.

```
aws ram accept-resource-share-invitation \
--resource-share-invitation-arn arn:aws:ram:us-west-2:123456789012:resource-
share-invitation/1e3477be-4a95-46b4-bbe0-c4001EXAMPLE \
--region us-west-2
```

Add a shared product to your portal

After you accept the resource share, you add the product to your portal.

AWS Management Console

To add a shared product to your portal

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. In the main navigation pane, choose **Portals**.
3. Choose a portal.
4. In the **Products** tab, for **Portal products**, choose **Add products**.
5. Add a product to your portal. Shared products are shown as shared in the products list.
6. Choose **Save changes**.

AWS CLI

To find all the portal products shared with you, use the following [get-portal-products](#) command:

```
aws apigatewayv2 get-portal-products \
--resource-owner OTHER_ACCOUNTS \
```

```
--region us-west-2
```

To add a shared portal product to your portal, use the following update-portal command:

```
aws apigateway update-portal \
--included-portal-product-arns arn:aws:apigateway:us-west-2:111122223333:/
portalproducts/p00000000 \
--region us-west-2
```

Enable try it for an API Gateway product REST endpoint in your portal

Use try it to let an API consumer invoke your product endpoint from your portal. When an API consumer uses try it, they enter method request parameters and invoke your product endpoint. Then, API Gateway invokes your API over the public internet and returns the response in the try it window. You can use a custom product page to provide any additional information about required parameters to access your API.

API Gateway uses the following limits to protect your APIs:

- API Gateway only allows 3 requests per second to your API.
- API Gateway uses a built-in timeout limit of 29000 ms. Your actual API might have a higher timeout limit, but API Gateway does not apply this timeout when a customer uses try it.
- API Gateway limits the response payload to 6MB.

Considerations

The following considerations might impact how you use try it:

- Try it is not supported when you preview a portal.
- Try it is not supported for the REST APIs with the following features:
 - Private APIs
 - APIs that use mutual TLS
 - APIs that use private or self signed SSL certificates

As the portal owner you are responsible for communicating with your API consumers the reasoning of the why try it button isn't there for any REST APIs that aren't supported. API Gateway does not explain this for you.

Enable try it for a product REST endpoint

The following procedure shows how to enable try it for a product endpoint.

To learn how to use try it in a portal, see [the section called “Use a portal”](#).

Enable try it for a product REST endpoint

1. In the main navigation pane, choose **Portal products**.
2. Choose a product.
3. In the **Documentation** tab, under **API reference pages**, choose the name of a product REST endpoint, such as `/dogs - GET`.
4. Choose **Edit page**.
5. To let customers invoke your API in your portal, select **Try it functionality**.
6. Choose **Save changes**.
7. You must republish any portals that use this portal product for the changes to take effect.

Delete a portal product in API Gateway

When you delete a portal product, it cannot be recovered.

Delete a portal product

The following procedure shows how to delete a portal product.

To delete a portal product

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. In the main navigation pane, choose **Portal products**.
3. Choose a portal product.
4. Choose **Delete**.
5. Confirm your choice and choose **Delete**.
6. You must republish any portals that use this portal product for the changes to take effect.

Create a portal in API Gateway

A portal is a collection of products. You control the authorization, branding, and publication of your portal. When you create a portal, its publish status is **Disabled**. This means your portal is not discoverable on the web. To let consumers access your portal, you need to publish it. Before you publish your portal, you can also preview it.

API Gateway supports portals on the following browsers:

- Firefox
- Google Chrome
- Microsoft Edge
- Safari

Choose a domain name

By default, your portal URL is hosted at the following Amazon-owned domain name:

`https://p-portalId.apigw-portal.us-east-1.on.aws`

To customize the domain name, you can provide a domain name that you own and an SSL certificate for the custom domain. The certificate must be managed with [AWS Certificate Manager \(ACM\)](#) in US East (N. Virginia) and be supported by Amazon CloudFront. For more information, see [Requirements for using SSL/TLS certificates with CloudFront](#).

When you use a custom domain name, API Gateway creates a CloudFront distribution, secured in transit with your ACM certificate. Then, API Gateway provides an alias record, which you add to your DNS configuration. The alias record is the Amazon-owned domain name. You must add this alias record to direct traffic to the CloudFront distribution for your custom domain. The domain name you provide must be unique and not already be used by the aliases list on an existing CloudFront distribution.

If you use your own domain name, API Gateway uses the **TLS_1_2** security policy to protect your portal. For more information, see [Supported protocols and ciphers between viewers](#). You can't change this value.

Create a portal

You use the API Gateway console to create and configure your portal. The following procedures guide you through all required steps. You can also choose **Skip to Review and create** at the end of the first procedure to create an empty portal.

The following procedure shows how to create a portal. First, you define your portal details.

To define your portal details

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. In the main navigation pane, choose **Portals**.
3. Choose **Create portal**.
4. Under portal details, for **Portal name**, enter a name.
5. For **Portal description**, enter a description.
6. For **Portal authorization**, select how to authorize your portal.
 - If this is your first time creating a portal, we recommend that you choose **None**. If you plan on adding any production APIs to your portal, use **Require authorization**.
 - To require portal consumers to authenticate to use your portal, choose **Require authorization**, and do the following:
 - a. For **Amazon Cognito user pool**, select your user pool.
The user pool must be in the same Region as your portal.
 - b. For **Application client ID**, choose the app client ID.
In your app client, you must set the callback URL to the portal's default URL.
 - c. For **User pool domain**, enter the user pool domain. For more information, see [Configuring a user pool domain](#).
7. For **Domain configuration**, select the domain name for your portal.
 - If this is your first time creating a portal, we recommend that you choose **Default domain**. Once you publish your portal, it will be available at `https://p-portalId.apigw-portal.us-east-1.on.aws`.
 - To provide a custom domain name that you own, select **Custom domain name** and do the following:
 - a. For **Domain name**, enter a fully qualified domain name.

- b. For **ACM certificate**, choose an ACM certificate that covers the domain name.

You'll need to add the alias record that API Gateway provisions to your DNS record, in order to serve traffic from your portal.

8. To add a CloudWatch RUM app monitor to your portal, for **RUM app monitor**, choose an app monitor. For more information, see [CloudWatch RUM](#).
9. Choose **Next**.

After you define your portal details, you add portal products. You can change the portal products in your portal at any time, but you need to republish your portal for the changes to take effect.

To select your portal products

1. From the resource list, select the products to add to your portal.
2. Choose **Next**.

After you select your products, you customize the portal design. To upload a portal logo, you must have an image uploaded to Amazon S3. You can change these values at any time, but you need to republish your portal for the changes to take effect.

(Optional) To customize your portal

1. For **Portal logo**, provide the S3 URI for your file.

Only .svg, .png, or .jpg are supported.
2. To customize the design of your portal, you have two options:
 - a. You can choose **Portal theme** to apply a pre-made color theme on your portal.
 - b. You can use the color selectors to select all your portal design options.
3. Choose **Next**.

After you select the portal design, review the information for the portal.

To review your portal

- Review your settings on the review and create page. When you're satisfied with the settings, choose **Create**.

If you use an Amazon Cognito user pool to control access to your portal, you must set the callback URL to the portal's default URL in the app client. For more information, see [Application-specific settings with app clients](#).

Your portal won't be available to consumers after you create it. You must publish your portal for it to be accessible on the internet. For more information, see [the section called "Publish a portal"](#).

Update a portal in API Gateway

You can update the theme, logo, or the portal products in your portal. When you update your portal, the changes don't take effect until you republish your portal.

Update a portal

The following procedure shows how to update the design of a portal.

To update a portal design

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. In the main navigation pane, choose **Portals**.
3. Choose a portal.
4. In the **Portal design** tab, choose **Edit**.
5. To update the portal logo, choose **Update portal logo**. You can either remove the existing logo or use a new logo.
6. Make any theme or background updates to your portal design.
7. Choose **Save changes**.
8. (Optional) Choose **Generate portal preview** to see your changes.

After you've confirmed your changes, publish your portal.

9. Choose **Publish portal**.
10. Enter a description for your portal update and choose **Publish**.

Preview a portal in API Gateway

You can preview your portal before you publish it. API Gateway creates a short-lived URL that you can use to preview the version of your portal that customers will see once your portal is published.

Considerations

The following considerations might impact how you preview a portal:

- Try it is not enabled for your preview portal. For more information, see [the section called “Enable try it for a product REST endpoint in your portal”](#).

Preview a portal

The following procedure shows how to preview a portal.

To preview a portal

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. In the main navigation pane, choose **Portals**.
3. Choose a portal.
4. Choose **Generate portal preview**.

Do not refresh your page.

5. After API Gateway generates your preview, choose **Open portal preview**.

Your portal preview will open in a new tab.

Publish a portal in API Gateway

For API consumers to access your portal, you must publish it. A portal URL can be discovered by anyone on the internet. We recommend that you preview and secure your portal before publishing it.

Considerations

It might take API Gateway a few minutes to publish your portal. You can monitor the **Publish status** in the console.

Publish a portal

The following procedure shows how to publish a portal.

To publish a portal

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. In the main navigation pane, choose **Portals**.
3. Choose a portal.
4. Choose **Publish portal**.
5. (Optional) For **Description of changes**, enter a description of your change.

When you publish a portal, we recommend that you always provide a brief description of your changes.

6. Choose **Publish**.

It takes API Gateway a few minutes to finish publishing your portal. API Gateway provides a link to your portal when it's available.

To delete your portal, you must disable it first. For more information, see [the section called "Disable a portal"](#).

Use an API Gateway portal

After you publish your portal, it's available on the web. To use your portal, copy the **Portal default domain name** or the **domain name** and enter it in a browser. If your portal uses a domain name, the default domain name can't be used to access your portal.

Use a portal

The following procedure shows how to access a portal and use try it for a product REST endpoint.

To use a portal

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. In the main navigation pane, choose **Portals**.
3. Choose a portal.
4. Copy the **Portal default domain name** or the **domain name** and enter it in a browser.
5. On the portal homepage, you can search for portal products and discover product pages. Use the search at the top of the portal to search all the content in your portal. Use the search bar under **Products** to search for portal products.

6. Choose a portal product.
7. Choose a product REST endpoint.
8. In the **Try it** window, enter parameters to try a call to your API.
9. Choose **Try it**. API Gateway will invoke your API and show the results in the window.

Troubleshoot your portal

The following provides troubleshooting advice for errors and issues that you might encounter when using a portal.

The portal webpage site can't be reached

If you receive an error message that the portal webpage site can't be reached, make sure you published your portal. If you used a domain name, make sure that you added the alias record that API Gateway provided to direct traffic to the CloudFront distribution for your custom domain.

Try it failed

If you are unable to use try it for a product REST endpoint, make sure that the try it state is ACTIVE. In addition, make sure you entered the correct parameters to invoke your API.

Pages are not appearing in your portal

If you created a product REST endpoint page or a product page and it's not visible in your portal, make sure your pages are not drafts. To verify this, do the following:

To verify your pages are not in drafts

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. In the main navigation pane, choose **Portal products**.
3. Choose your portal product.
4. In the **Documentation** tab, confirm your pages are not in the **Draft documentation pages** or **Draft API reference pages** section, but are in the **Custom documentation pages** or **API reference pages**.

Disable a portal in API Gateway

When you disable a portal, your portal is no longer available on the web. After you disable a portal, you can either delete the portal or republish it if necessary.

Disable a portal

The following procedure shows how to disable a portal.

To disable a portal

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. In the main navigation pane, choose **Portals**.
3. Choose a portal.
4. Choose **Actions**, and then choose **Disable portal**.
5. Confirm your choice and choose **Disable portal**.

The **Publish status** will change to **Disabled**.

To remove the disable status of the portal, publish the portal again.

Delete a portal in API Gateway

When you delete a portal, it cannot be recovered and you must disable it first. If you want to remove your portal from the web, you can disable it. This lets you modify your portal and republish it later.

Delete a portal

The following procedure shows how to delete a portal.

To delete a portal

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. In the main navigation pane, choose **Portals**.
3. Choose a portal.
4. If your portal is not disabled, disable it by choosing **Actions, Disable portal**.

It takes a few minutes for your portal to be disabled. You can monitor the **Publish status** to see when your portal publish status is disabled.

5. After you have unpublished your portal, you can delete it. To delete your portal, choose **Actions, Delete portal**. Confirm your choice and choose **Delete**.

API Gateway HTTP APIs

REST APIs and HTTP APIs are both RESTful API products. REST APIs support more features than HTTP APIs, while HTTP APIs are designed with minimal features so that they can be offered at a lower price. For more information, see [the section called “Choose between REST APIs and HTTP APIs”](#).

You can use HTTP APIs to send requests to AWS Lambda functions or to any routable HTTP endpoint. For example, you can create an HTTP API that integrates with a Lambda function on the backend. When a client calls your API, API Gateway sends the request to the Lambda function and returns the function's response to the client.

HTTP APIs support [OpenID Connect](#) and [OAuth 2.0](#) authorization. They come with built-in support for cross-origin resource sharing (CORS) and automatic deployments.

You can create HTTP APIs by using the AWS Management Console, the AWS CLI, APIs, CloudFormation, or SDKs.

Topics

- [Develop HTTP APIs in API Gateway](#)
- [Publish HTTP APIs for customers to invoke](#)
- [Protect your HTTP APIs in API Gateway](#)
- [Monitor HTTP APIs in API Gateway](#)
- [Troubleshooting issues with HTTP APIs in API Gateway](#)

Develop HTTP APIs in API Gateway

This section provides details about API Gateway capabilities that you need while you're developing your API Gateway APIs.

As you're developing your API Gateway API, you decide on a number of characteristics of your API. These characteristics depend on the use case of your API. For example, you might want to only allow certain clients to call your API, or you might want it to be available to everyone. You might want an API call to execute a Lambda function, make a database query, or call an application.

Topics

- [Create an HTTP API](#)
- [Create routes for HTTP APIs in API Gateway](#)
- [IP address types for HTTP APIs in API Gateway](#)
- [Control and manage access to HTTP APIs in API Gateway](#)
- [Create integrations for HTTP APIs in API Gateway](#)
- [Configure CORS for HTTP APIs in API Gateway](#)
- [Transform API requests and responses for HTTP APIs in API Gateway](#)
- [Use OpenAPI definitions for HTTP APIs in API Gateway](#)

Create an HTTP API

To create a functional API, you must have at least one route, integration, stage, and deployment.

The following examples show how to create an API with an AWS Lambda or HTTP integration, a route, and a default stage that is configured to automatically deploy changes.

This guide assumes that you're already familiar with API Gateway and Lambda. For a more detailed guide, see [Get started](#).

Topics

- [Create an HTTP API by using the AWS Management Console](#)
- [Create an HTTP API by using the AWS CLI](#)

Create an HTTP API by using the AWS Management Console

1. Open the [API Gateway console](#).
2. Choose **Create API**.
3. Under **HTTP API**, choose **Build**.
4. Choose **Add integration**, and then choose an AWS Lambda function or enter an HTTP endpoint.
5. For **Name**, enter a name for your API.
6. Choose **Review and create**.
7. Choose **Create**.

Now your API is ready to invoke. You can test your API by entering its invoke URL in a browser, or by using Curl.

```
curl https://api-id.execute-api.us-east-2.amazonaws.com
```

Create an HTTP API by using the AWS CLI

You can use quick create to create an API with a Lambda or HTTP integration, a default catch-all route, and a default stage that is configured to automatically deploy changes. The following [create-api](#) command uses quick create to create an API that integrates with a Lambda function on the backend.

Note

To invoke a Lambda integration, API Gateway must have the required permissions. You can use a resource-based policy or an IAM role to grant API Gateway permissions to invoke a Lambda function. To learn more, see [AWS Lambda Permissions](#) in the *AWS Lambda Developer Guide*.

Example

```
aws apigatewayv2 create-api --name my-api --protocol-type HTTP --target  
arn:aws:lambda:us-east-2:123456789012:function:function-name
```

Now your API is ready to invoke. You can test your API by entering its invoke URL in a browser, or by using Curl.

```
curl https://api-id.execute-api.us-east-2.amazonaws.com
```

Create routes for HTTP APIs in API Gateway

Routes direct incoming API requests to backend resources. Routes consist of two parts: an HTTP method and a resource path—for example, GET /pets. You can define specific HTTP methods for your route. Or, you can use the ANY method to match all methods that you haven't defined for a resource. You can create a \$default route that acts as a catch-all for requests that don't match any other routes.

Note

API Gateway decodes URL-encoded request parameters before passing them to your backend integration.

Working with path variables

You can use path variables in HTTP API routes.

For example, the GET `/pets/{petID}` route catches a GET request that a client submits to `https://api-id.execute-api.us-east-2.amazonaws.com/pets/6`.

A *greedy path variable* catches all child resources of a route. To create a greedy path variable, add `+` to the variable name—for example, `{proxy+}`. The greedy path variable must be at the end of the resource path.

Working with query string parameters

By default, API Gateway sends query string parameters to your backend integration if they are included in a request to an HTTP API.

For example, when a client sends a request to `https://api-id.execute-api.us-east-2.amazonaws.com/pets?id=4&type=dog`, the query string parameters `?id=4&type=dog` are sent to your integration.

Working with the \$default route

The `$default` route catches requests that don't explicitly match other routes in your API.

When the `$default` route receives a request, API Gateway sends the full request path to the integration. For example, you can create an API with only a `$default` route and integrate it on the ANY method with the `https://petstore-demo-endpoint.execute-api.com` HTTP endpoint. When you send a request to `https://api-id.execute-api.us-east-2.amazonaws.com/store/checkout`, API Gateway sends a request to `https://petstore-demo-endpoint.execute-api.com/store/checkout`.

To learn more about HTTP integrations, see [Create HTTP proxy integrations for HTTP APIs](#).

Routing API requests

When a client sends an API request, API Gateway first determines which [stage](#) to route the request to. If the request explicitly matches a stage, API Gateway sends the request to that stage. If no stage fully matches the request, API Gateway sends the request to the \$default stage. If there's no \$default stage, then the API returns {"message": "Not Found"} and does not generate CloudWatch logs.

After selecting a stage, API Gateway selects a route. API Gateway selects the route with the most-specific match, using the following priorities:

1. Full match for a route and method.
2. Match for a route and method with a greedy path variable ({proxy+}).
3. The \$default route.

If no routes match a request, API Gateway returns {"message": "Not Found"} to the client.

For example, consider an API with a \$default stage and the following example routes:

1. GET /pets/dog/1
2. GET /pets/dog/{id}
3. GET /pets/{proxy+}
4. ANY /{proxy+}
5. \$default

The following table summarizes how API Gateway routes requests to the example routes.

Request	Selected route	Explanation
GET https:// <i>api-id</i> .execute-api. <i>region</i> .amazonaws.com/pets/dog/1	GET /pets/dog/1	The request fully matches this static route.
GET https:// <i>api-id</i> .execute-	GET /pets/dog/{id}	The request fully matches this route.

Request	Selected route	Explanation
api. <i>region</i> .amazonaws.com/pets/dog/2		
GET https:// <i>api-id</i> .execute-api. <i>region</i> .amazonaws.com/pets/cat/1	GET /pets/{proxy+}	The request doesn't fully match a route. The route with a GET method and a greedy path variable catches this request.
POST https:// <i>api-id</i> .execute-api. <i>region</i> .amazonaws.com/test/5	ANY /{proxy+}	The ANY method matches all methods that you haven't defined for a route. Routes with greedy path variables have higher priority than the \$default route.

IP address types for HTTP APIs in API Gateway

When you create an API, you specify the type of IP addresses that can invoke your API. You can choose IPv4 to resolve IPv4 addresses to invoke your API, or you can choose dualstack to allow both IPv4 and IPv6 addresses to invoke your API. You might want to set the IP address type to dualstack to alleviate IP space exhaustion or for your security posture. For more information about the benefits of a dualstack IP address type, see [IPv6 on AWS](#).

Considerations for IP address types

The following considerations might impact your use of IP address types:

- The default IP address type for HTTP APIs is IPv4.
- If you change the IP address type for an existing API from IPv4 to dualstack, confirm that any policies controlling access to your APIs have been updated to account for IPv6 calls. When you change the IP address type, the change takes effect immediately.
- Your API can be mapped to a custom domain name with a different IP address type than your API. If you disable your default API endpoint, this might affect how callers can invoke your API.

Change the IP address type of an HTTP API

You can change the IP address type by updating the API's configuration. You can update the API's configuration by using the AWS Management Console, the AWS CLI, CloudFormation, or an AWS SDK. If you change the API's IP address type, you don't redeploy your API for the changes to take effect.

AWS Management Console

To change the IP address type of an HTTP API

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose an HTTP API.
3. For **API settings**, choose **Edit**.
4. For IP address type, select either **IPv4** or **Dualstack**.
5. Choose **Save**.

The change to your API's configuration will take effect immediately.

AWS CLI

The following [update-api](#) command updates an API to have an IP address type of dualstack:

```
aws apigatewayv2 update-api \
--api-id abcd1234 \
--ip-address-type dualstack
```

The output will look like the following:

```
{
  "ApiEndpoint": "https://abcd1234.execute-api.us-east-1.amazonaws.com",
  "ApiId": "abcd1234",
  "ApiKeySelectionExpression": "$request.header.x-api-key",
  "CreatedDate": "2025-02-04T22:20:20+00:00",
  "DisableExecuteApiEndpoint": false,
  "Name": "My-HTTP-API",
  "ProtocolType": "HTTP",
  "RouteSelectionExpression": "$request.method $request.path",
  "Tags": {}}
```

```
"NotificationUris": [],
"IpAddressType": "dualstack"
}
```

Control and manage access to HTTP APIs in API Gateway

API Gateway supports multiple mechanisms for controlling and managing access to your HTTP API:

- **Lambda authorizers** use Lambda functions to control access to APIs. For more information, see [Control access to HTTP APIs with AWS Lambda authorizers](#).
- **JWT authorizers** use JSON web tokens to control access to APIs. For more information, see [Control access to HTTP APIs with JWT authorizers in API Gateway](#).
- **Standard AWS IAM roles and policies** offer flexible and robust access controls. You can use IAM roles and policies to control who can create and manage your APIs, as well as who can invoke them. For more information, see [Control access to HTTP APIs with IAM authorization in API Gateway](#).

To improve your security posture, we recommend that you configure an authorizer for all routes on your HTTP API. You might need to do this to comply with various compliance frameworks. For more information, see [Amazon API Gateway controls](#) in the *AWS Security Hub User Guide*.

Control access to HTTP APIs with AWS Lambda authorizers

You use a Lambda authorizer to use a Lambda function to control access to your HTTP API. Then, when a client calls your API, API Gateway invokes your Lambda function. API Gateway uses the response from your Lambda function to determine whether the client can access your API.

Payload format version

The authorizer payload format version specifies the format of the data that API Gateway sends to a Lambda authorizer, and how API Gateway interprets the response from Lambda. If you don't specify a payload format version, the AWS Management Console uses the latest version by default. If you create a Lambda authorizer by using the AWS CLI, CloudFormation, or an SDK, you must specify an `authorizerPayloadFormatVersion`. The supported values are `1.0` and `2.0`.

If you need compatibility with REST APIs, use version `1.0`.

The following examples show the structure of each payload format version.

2.0

```
{  
    "version": "2.0",  
    "type": "REQUEST",  
    "routeArn": "arn:aws:execute-api:us-east-1:123456789012:abcdef123/test/GET/  
request",  
    "identitySource": ["user1", "123"],  
    "routeKey": "$default",  
    "rawPath": "/my/path",  
    "rawQueryString": "parameter1=value1&parameter1=value2&parameter2=value",  
    "cookies": ["cookie1", "cookie2"],  
    "headers": {  
        "header1": "value1",  
        "header2": "value2"  
    },  
    "queryStringParameters": {  
        "parameter1": "value1,value2",  
        "parameter2": "value"  
    },  
    "requestContext": {  
        "accountId": "123456789012",  
        "apiId": "api-id",  
        "authentication": {  
            "clientCert": {  
                "clientCertPem": "CERT_CONTENT",  
                "subjectDN": "www.example.com",  
                "issuerDN": "Example issuer",  
                "serialNumber": "1",  
                "validity": {  
                    "notBefore": "May 28 12:30:02 2019 GMT",  
                    "notAfter": "Aug 5 09:36:04 2021 GMT"  
                }  
            }  
        },  
        "domainName": "id.execute-api.us-east-1.amazonaws.com",  
        "domainPrefix": "id",  
        "http": {  
            "method": "POST",  
            "path": "/my/path",  
            "protocol": "HTTP/1.1",  
            "sourceIp": "IP",  
            "userAgent": "agent"  
        },  
    }  
}
```

```
"requestId": "id",
"routeKey": "$default",
"stage": "$default",
"time": "12/Mar/2020:19:03:58 +0000",
"timeEpoch": 1583348638390
},
"pathParameters": { "parameter1": "value1" },
"stageVariables": { "stageVariable1": "value1", "stageVariable2": "value2" }
}
```

1.0

```
{
  "version": "1.0",
  "type": "REQUEST",
  "methodArn": "arn:aws:execute-api:us-east-1:123456789012:abcdef123/test/GET/
request",
  "identitySource": "user1,123",
  "authorizationToken": "user1,123",
  "resource": "/request",
  "path": "/request",
  "httpMethod": "GET",
  "headers": {
    "X-AMZ-Date": "20170718T062915Z",
    "Accept": "*/*",
    "HeaderAuth1": "headerValue1",
    "CloudFront-Viewer-Country": "US",
    "CloudFront-Forwarded-Proto": "https",
    "CloudFront-Is-Tablet-Viewer": "false",
    "CloudFront-Is-Mobile-Viewer": "false",
    "User-Agent": "..."
  },
  "queryStringParameters": {
    "QueryString1": "queryValue1"
  },
  "pathParameters": {},
  "stageVariables": {
    "StageVar1": "stageValue1"
  },
  "requestContext": {
    "path": "/request",
    "accountId": "123456789012",
    "resourceId": "05c7jb",
    "stage": "$default"
  }
}
```

Lambda authorizer response format

The payload format version also determines the structure of the response that you must return from your Lambda function.

Lambda function response for format 1.0

If you choose the 1.0 format version, Lambda authorizers must return an IAM policy that allows or denies access to your API route. You can use standard IAM policy syntax in the policy. For examples of IAM policies, see [the section called “Control access for invoking an API”](#). You can pass context properties to Lambda integrations or access logs by using `$context.authorizer.property`. The context object is optional and `claims` is a reserved placeholder and cannot be used as the context object. To learn more, see [the section called “Logging variables”](#).

Example

JSON

{

```
"principalId": "abcdef",
"policyDocument": {
    "Version": "2012-10-17",
    "Statement": [
        {
            "Action": "execute-api:Invoke",
            "Effect": "Allow|Deny",
            "Resource": "arn:aws:execute-api:{regionId}:{accountId}:{apiId}/{stage}/
{httpVerb}/{resource}/{child-resources}]"
        }
    ],
},
"context": {
    "exampleKey": "exampleValue"
}
}
```

Lambda function response for format 2.0

If you choose the 2.0 format version, you can return a Boolean value or an IAM policy that uses standard IAM policy syntax from your Lambda function. To return a Boolean value, enable simple responses for the authorizer. The following examples demonstrate the format that you must code your Lambda function to return. The context object is optional. You can pass context properties to Lambda integrations or access logs by using `$context.authorizer.property`. To learn more, see [the section called “Logging variables”](#).

Simple response

```
{
    "isAuthorized": true/false,
    "context": {
        "exampleKey": "exampleValue"
    }
}
```

IAM policy

```
{
    "principalId": "abcdef",
    "policyDocument": {
```

```
"Version": "2012-10-17",
"Statement": [
    {
        "Action": "execute-api:Invoke",
        "Effect": "Allow|Deny",
        "Resource": "arn:aws:execute-api:{regionId}:{accountId}:{apiId}/{stage}/
{httpVerb}/{resource}/{child-resources}]]"
    }
],
"context": {
    "exampleKey": "exampleValue"
}
}
```

Example Lambda authorizer functions

The following example Node.js Lambda functions demonstrate the required response formats you need to return from your Lambda function for the 2.0 payload format version.

Simple response - Node.js

```
export const handler = async(event) => {
    let response = {
        "isAuthorized": false,
        "context": {
            "stringKey": "value",
            "numberKey": 1,
            "booleanKey": true,
            "arrayKey": ["value1", "value2"],
            "mapKey": {"value1": "value2"}
        }
    };

    if (event.headers.authorization === "secretToken") {
        console.log("allowed");
        response = {
            "isAuthorized": true,
            "context": {
                "stringKey": "value",
                "numberKey": 1,
                "booleanKey": true,
            }
        };
    }

    return response;
}
```

```
        "arrayKey": ["value1", "value2"],
        "mapKey": {"value1": "value2"}
    }
};

return response;

};
```

Simple response - Python

```
import json

def lambda_handler(event, context):
    response = {
        "isAuthorized": False,
        "context": {
            "stringKey": "value",
            "numberKey": 1,
            "booleanKey": True,
            "arrayKey": ["value1", "value2"],
            "mapKey": {"value1": "value2"}
        }
    }

    try:
        if (event["headers"]["authorization"] == "secretToken"):
            response = {
                "isAuthorized": True,
                "context": {
                    "stringKey": "value",
                    "numberKey": 1,
                    "booleanKey": True,
                    "arrayKey": ["value1", "value2"],
                    "mapKey": {"value1": "value2"}
                }
            }
            print('allowed')
            return response
        else:
            print('denied')
    
```

```
        return response
    except BaseException:
        print('denied')
        return response
```

IAM policy - Node.js

```
export const handler = async(event) => {
    if (event.headers.authorization == "secretToken") {
        console.log("allowed");
        return {
            "principalId": "abcdef", // The principal user identification associated with
            // the token sent by the client.
            "policyDocument": {
                "Version": "2012-10-17",
                "Statement": [{
                    "Action": "execute-api:Invoke",
                    "Effect": "Allow",
                    "Resource": event.routeArn
                }]
            },
            "context": {
                "stringKey": "value",
                "numberKey": 1,
                "booleanKey": true,
                "arrayKey": ["value1", "value2"],
                "mapKey": { "value1": "value2" }
            }
        };
    } else {
        console.log("denied");
        return {
            "principalId": "abcdef", // The principal user identification associated with
            // the token sent by the client.
            "policyDocument": {
                "Version": "2012-10-17",
                "Statement": [{
                    "Action": "execute-api:Invoke",
                    "Effect": "Deny",
                    "Resource": event.routeArn
                }]
            },
        };
    }
}
```

```
"context": {  
    "stringKey": "value",  
    "numberKey": 1,  
    "booleanKey": true,  
    "arrayKey": ["value1", "value2"],  
    "mapKey": { "value1": "value2" }  
}  
};  
};  
};
```

IAM policy - Python

```
import json  
  
def lambda_handler(event, context):  
    response = {  
        # The principal user identification associated with the token sent by  
        # the client.  
        "principalId": "abcdef",  
        "policyDocument": {  
            "Version": "2012-10-17",  
            "Statement": [{  
                "Action": "execute-api:Invoke",  
                "Effect": "Deny",  
                "Resource": event["routeArn"]  
            }]  
        },  
        "context": {  
            "stringKey": "value",  
            "numberKey": 1,  
            "booleanKey": True,  
            "arrayKey": ["value1", "value2"],  
            "mapKey": {"value1": "value2"}  
        }  
    }  
  
    try:  
        if (event["headers"]["authorization"] == "secretToken"):  
            response = {  
                # The principal user identification associated with the token  
                # sent by the client.
```

```
        "principalId": "abcdef",
        "policyDocument": {
            "Version": "2012-10-17",
            "Statement": [{
                "Action": "execute-api:Invoke",
                "Effect": "Allow",
                "Resource": event["routeArn"]
            }]
        },
        "context": {
            "stringKey": "value",
            "numberKey": 1,
            "booleanKey": True,
            "arrayKey": ["value1", "value2"],
            "mapKey": {"value1": "value2"}
        }
    }
    print('allowed')
    return response
else:
    print('denied')
    return response
except BaseException:
    print('denied')
    return response
```

Identity sources

You can optionally specify identity sources for a Lambda authorizer. Identity sources specify the location of data that's required to authorize a request. For example, you can specify header or query string values as identity sources. If you specify identity sources, clients must include them in the request. If the client's request doesn't include the identity sources, API Gateway doesn't invoke your Lambda authorizer, and the client receives a 401 error.

The following table describes the supported identity sources for a Lambda authorizer.

Type	Example	Notes
Header value	\$request.header. <i>name</i>	Header names are case-insensitive.

Type	Example	Notes
Query string value	<code>\$request.querystring.name</code>	Query string names are case-sensitive.
Context variable	<code>\$context.variableName</code>	The value of a supported context variable .
Stage variable	<code>\$stageVariables.variableName</code>	The value of a stage variable .

You can also directly return `{"errorMessage" : "Unauthorized"}` from your Lambda function to return a `401` error to your clients. If you directly return a `401` error from your Lambda function to your clients, don't specify any identity sources when you create your Lambda authorizer.

Caching authorizer responses

You can enable caching for a Lambda authorizer by specifying an [authorizerResultTtlInSeconds](#). When caching is enabled for an authorizer, API Gateway uses the authorizer's identity sources as the cache key. If a client specifies the same parameters in identity sources within the configured TTL, API Gateway uses the cached authorizer result, rather than invoking your Lambda function.

To enable caching, your authorizer must have at least one identity source.

If you enable simple responses for an authorizer, the authorizer's response fully allows or denies all API requests that match the cached identity source values. For more granular permissions, disable simple responses and return an IAM policy. Depending on your authorizer, your IAM policy might need to control access to multiple.

By default, API Gateway uses the cached authorizer response for all routes of an API that use the authorizer. To cache responses per route, add `$context.routeKey` to your authorizer's identity sources.

Create a Lambda authorizer

When you create a Lambda authorizer, you specify the Lambda function for API Gateway to use. You must grant API Gateway permission to invoke the Lambda function by using either the function's resource policy or an IAM role. The following [create-authorizer](#) command creates a Lambda authorizer:

```
aws apigatewayv2 create-authorizer \
--api-id abcdef123 \
--authorizer-type REQUEST \
--identity-source '$request.header.Authorization' \
--name lambda-authorizer \
--authorizer-uri 'arn:aws:apigateway:us-west-2:lambda:path/2015-03-31/
functions/arn:aws:lambda:us-west-2:123456789012:function:my-function/invocations' \
--authorizer-payload-format-version '2.0' \
--enable-simple-responses
```

The following [add-permission](#) command updates the Lambda function's resource policy to grant API Gateway permission to invoke the function. If API Gateway doesn't have permission to invoke your function, clients receive a 500 Internal Server Error.

```
aws lambda add-permission \
--function-name my-authorizer-function \
--statement-id apigateway-invoke-permissions-abc123 \
--action lambda:InvokeFunction \
--principal apigateway.amazonaws.com \
--source-arn "arn:aws:execute-api:us-west-2:123456789012:api-
id/authorizers/authorizer-id"
```

After you've created an authorizer and granted API Gateway permission to invoke it, update your route to use the authorizer. The following [update-route](#) command adds the Lambda authorizer to the route. If your Lambda authorizer uses policy caching, make sure you update the policy to control access for the additional route.

```
aws apigatewayv2 update-route \
--api-id abcdef123 \
--route-id abc123 \
--authorization-type CUSTOM \
--authorizer-id def123
```

Troubleshooting Lambda authorizers

If API Gateway can't invoke your Lambda authorizer, or your Lambda authorizer returns a response in an invalid format, clients receive a 500 Internal Server Error.

To troubleshoot errors, [enable access logging](#) for your API stage. Include the `$context.authorizer.error` logging variable in your log format.

If the logs indicate that API Gateway doesn't have permission to invoke your function, update your function's resource policy or provide an IAM role to grant API Gateway permission to invoke your authorizer.

If the logs indicate that your Lambda function returns an invalid response, verify that your Lambda function returns a response in the [required format](#).

Control access to HTTP APIs with JWT authorizers in API Gateway

You can use JSON Web Tokens (JWTs) as a part of [OpenID Connect \(OIDC\)](#) and [OAuth 2.0](#) frameworks to restrict client access to your APIs.

If you configure a JWT authorizer for a route of your API, API Gateway validates the JWTs that clients submit with API requests. API Gateway allows or denies requests based on token validation, and optionally, scopes in the token. If you configure scopes for a route, the token must include at least one of the route's scopes.

You can configure distinct authorizers for each route of an API, or use the same authorizer for multiple routes.

Note

There is no standard mechanism to differentiate JWT access tokens from other types of JWTs, such as OpenID Connect ID tokens. Unless you require ID tokens for API authorization, we recommend that you configure your routes to require authorization scopes. You can also configure your JWT authorizers to require issuers or audiences that your identity provider uses only when issuing JWT access tokens.

Authorizing API requests with a JWT authorizer

API Gateway uses the following general workflow to authorize requests to routes that are configured to use a JWT authorizer.

1. Check the [identitySource](#) for a token. The `identitySource` can include only the token, or the token prefixed with `Bearer`.
2. Decode the token.
3. Check the token's algorithm and signature by using the public key that is fetched from the issuer's `jwks_uri`. Currently, only RSA-based algorithms are supported. API Gateway can cache

the public key for two hours. As a best practice, when you rotate keys, allow a grace period during which both the old and new keys are valid.

4. Validate claims. API Gateway evaluates the following token claims:

- kid – The token must have a header claim that matches the key in the `jwks_uri` that signed the token.
- iss – Must match the issuer that is configured for the authorizer.
- aud or client_id – Must match one of the audience entries that is configured for the authorizer. API Gateway validates `client_id` only if `aud` is not present. When both `aud` and `client_id` are present, API Gateway evaluates `aud`.
- exp – Must be after the current time in UTC.
- nbf – Must be before the current time in UTC.
- iat – Must be before the current time in UTC.
- scope or scp – The token must include at least one of the scopes in the route's authorizationScopes.

If any of these steps fail, API Gateway denies the API request.

After validating the JWT, API Gateway passes the claims in the token to the API route's integration. Backend resources, such as Lambda functions, can access the JWT claims. For example, if the JWT includes an identity claim `emailID`, it's available to a Lambda integration in `$event.requestContext.authorizer.jwt.claims.emailID`. For more information about the payload that API Gateway sends to Lambda integrations, see [the section called "AWS Lambda integrations"](#).

Create a JWT authorizer

Before you create a JWT authorizer, you must register a client application with an identity provider. You must also have created an HTTP API. For examples of creating an HTTP API, see [Create an HTTP API](#).

Create a JWT authorizer using the console

The following steps show how to create JWT authorizer using the console.

To create a JWT authorizer using the console

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.

2. Choose an HTTP API.
3. In the main navigation pane, choose **Authorization**.
4. Choose the **Manage authorizers** tab.
5. Choose **Create**.
6. For **Authorizer type**, choose **JWT**.
7. Configure your JWT authorizer, and specify an **Identity source** that defines the source of the token.
8. Choose **Create**.

Create a JWT authorizer using the AWS CLI

The following [create-authorizer](#) command creates a JWT authorizer. For `jwt-configuration`, specify the Audience and Issuer for your identity provider. If you use Amazon Cognito as an identity provider, the `IssuerUrl` is `https://cognito-idp.us-east-2.amazonaws.com/userPoolID`.

```
aws apigatewayv2 create-authorizer \
--name authorizer-name \
--api-id api-id \
--authorizer-type JWT \
--identity-source '$request.header.Authorization' \
--jwt-configuration Audience=audience,Issuer=IssuerUrl
```

Create a JWT authorizer using AWS CloudFormation

The following CloudFormation template creates an HTTP API with a JWT authorizer that uses Amazon Cognito as an identity provider.

The output of the CloudFormation template is a URL for an Amazon Cognito hosted UI where clients can sign up and sign in to receive a JWT. After a client signs in, the client is redirected to your HTTP API with an access token in the URL. To invoke the API with the access token, change the # in the URL to a ? to use the token as a query string parameter.

Example CloudFormation template

```
AWSTemplateFormatVersion: '2010-09-09'
Description: |
  Example HTTP API with a JWT authorizer. This template includes an Amazon Cognito user pool as the issuer for the JWT authorizer
```

and an Amazon Cognito app client as the audience for the authorizer. The outputs include a URL for an Amazon Cognito hosted UI where clients can sign up and sign in to receive a JWT. After a client signs in, the client is redirected to your HTTP API with an access token in the URL. To invoke the API with the access token, change the '#' in the URL to a '?' to use the token as a query string parameter.

Resources:

MyAPI:

Type: AWS::ApiGatewayV2::Api

Properties:

Description: Example HTTP API

Name: api-with-auth

ProtocolType: HTTP

Target: !GetAtt MyLambdaFunction.Arn

DefaultRouteOverrides:

Type: AWS::ApiGatewayV2::ApiGatewayManagedOverrides

Properties:

ApiId: !Ref MyAPI

Route:

AuthorizationType: JWT

AuthorizerId: !Ref JWTAuthorizer

JWTAuthorizer:

Type: AWS::ApiGatewayV2::Authorizer

Properties:

ApiId: !Ref MyAPI

AuthorizerType: JWT

IdentitySource:

- '\$request.querystring.access_token'

JwtConfiguration:

Audience:

- !Ref AppClient

Issuer: !Sub https://cognito-idp.\${AWS::Region}.amazonaws.com/\${UserPool}

Name: test-jwt-authorizer

MyLambdaFunction:

Type: AWS::Lambda::Function

Properties:

Runtime: nodejs18.x

Role: !GetAtt FunctionExecutionRole.Arn

Handler: index.handler

Code:

ZipFile: |

```
exports.handler = async (event) => {
```

```
    const response = {
```

```
        statusCode: 200,
        body: JSON.stringify('Hello from the ' + event.routeKey + ' route!'),
    };
    return response;
};

APIInvokeLambdaPermission:
Type: AWS::Lambda::Permission
Properties:
  FunctionName: !Ref MyLambdaFunction
  Action: lambda:InvokeFunction
  Principal: apigateway.amazonaws.com
  SourceArn: !Sub arn:${AWS::Partition}:execute-api:${AWS::Region}:
${AWS::AccountId}: ${MyAPI}/$default/$default
FunctionExecutionRole:
Type: AWS::IAM::Role
Properties:
  AssumeRolePolicyDocument:
    Version: '2012-10-17'
    Statement:
      - Effect: Allow
        Principal:
          Service:
            - lambda.amazonaws.com
        Action:
          - 'sts:AssumeRole'
  ManagedPolicyArns:
    - arn:aws:iam::aws:policy/service-role/AWSLambdaBasicExecutionRole
UserPool:
Type: AWS::Cognito::UserPool
Properties:
  UserPoolName: http-api-user-pool
  AutoVerifiedAttributes:
    - email
  Schema:
    - Name: name
      AttributeDataType: String
      Mutable: true
      Required: true
    - Name: email
      AttributeDataType: String
      Mutable: false
      Required: true
AppClient:
Type: AWS::Cognito::UserPoolClient
```

```
Properties:  
  AllowedOAuthFlows:  
    - implicit  
  AllowedOAuthScopes:  
    - aws.cognito.signin.user.admin  
    - email  
    - openid  
    - profile  
  AllowedOAuthFlowsUserPoolClient: true  
  ClientName: api-app-client  
  CallbackURLs:  
    - !Sub https://${MyAPI}.execute-api.${AWS::Region}.amazonaws.com  
  ExplicitAuthFlows:  
    - ALLOW_USER_PASSWORD_AUTH  
    - ALLOW_REFRESH_TOKEN_AUTH  
  UserPoolId: !Ref UserPool  
  SupportedIdentityProviders:  
    - COGNITO  
HostedUI:  
  Type: AWS::Cognito::UserPoolDomain  
  Properties:  
    Domain: !Join  
      - '-'  
      - - !Ref MyAPI  
        - !Ref AppClient  
  UserPoolId: !Ref UserPool  
Outputs:  
  SignupURL:  
    Value: !Sub https://${HostedUI}.auth.${AWS::Region}.amazoncognito.com/login?  
client_id=${AppClient}&response_type=token&scope=email+profile&redirect_uri=https://  
${MyAPI}.execute-api.${AWS::Region}.amazonaws.com
```

Update a route to use a JWT authorizer

You can use the console, the AWS CLI, or an AWS SDK to update a route to use a JWT authorizer.

Update a route to use a JWT authorizer by using the console

The following steps show how to update a route to use JWT authorizer using the console.

To create a JWT authorizer using the console

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose an HTTP API.

3. In the main navigation pane, choose **Authorization**.
4. Choose a method, and then select your authorizer from the dropdown menu, and choose **Attach authorizer**.

Update a route to use a JWT authorizer by using the AWS CLI

The following [update-route](#) command updates a route to use a JWT authorizer:

```
aws apigatewayv2 update-route \
--api-id api-id \
--route-id route-id \
--authorization-type JWT \
--authorizer-id authorizer-id \
--authorization-scopes user.email
```

Control access to HTTP APIs with IAM authorization in API Gateway

You can enable IAM authorization for HTTP API routes. When IAM authorization is enabled, clients must use [Signature Version 4 \(SigV4\)](#) to sign their requests with AWS credentials. API Gateway invokes your API route only if the client has execute-api permission for the route.

IAM authorization for HTTP APIs is similar to that for [REST APIs](#).

 **Note**

Resource policies aren't currently supported for HTTP APIs.

For examples of IAM policies that grant clients the permission to invoke APIs, see [the section called "Control access for invoking an API"](#).

Enable IAM authorization for a route

The following [update-route](#) command enables IAM authorization for an HTTP API route:

```
aws apigatewayv2 update-route \
--api-id abc123 \
--route-id abcdef \
--authorization-type AWS_IAM
```

Create integrations for HTTP APIs in API Gateway

Integrations connect a route to backend resources. HTTP APIs support Lambda proxy, AWS service, and HTTP proxy integrations. For example, you can configure a POST request to the /signup route of your API to integrate with a Lambda function that handles signing up customers.

Topics

- [Create AWS Lambda proxy integrations for HTTP APIs in API Gateway](#)
- [Create HTTP proxy integrations for HTTP APIs](#)
- [Create AWS service integrations for HTTP APIs in API Gateway](#)
- [Create private integrations for HTTP APIs in API Gateway](#)

Create AWS Lambda proxy integrations for HTTP APIs in API Gateway

A Lambda proxy integration enables you to integrate an API route with a Lambda function. When a client calls your API, API Gateway sends the request to the Lambda function and returns the function's response to the client. For examples of creating an HTTP API, see [Create an HTTP API](#).

Payload format version

The payload format version specifies the format of the event that API Gateway sends to a Lambda integration, and how API Gateway interprets the response from Lambda. If you don't specify a payload format version, the AWS Management Console uses the latest version by default. If you create a Lambda integration by using the AWS CLI, CloudFormation, or an SDK, you must specify a `payloadFormatVersion`. The supported values are `1.0` and `2.0`.

For more information about how to set the `payloadFormatVersion`, see [create-integration](#).

For more information about how to determine the `payloadFormatVersion` of an existing integration, see [get-integration](#)

Payload format differences

The following list shows differences between the `1.0` and `2.0` payload format versions:

- Format `2.0` doesn't have `multiValueHeaders` or `multiValueQueryStringParameters` fields. Duplicate headers are combined with commas and included in the `headers` field. Duplicate query strings are combined with commas and included in the `queryStringParameters` field.

- Format 2.0 has `rawPath`. If you use an API mapping to connect your stage to a custom domain name, `rawPath` won't provide the API mapping value. Use format 1.0 and `path` to access the API mapping for your custom domain name.
 - Format 2.0 includes a new `cookies` field. All cookie headers in the request are combined with commas and added to the `cookies` field. In the response to the client, each cookie becomes a `set-cookie` header.

Payload format structure

The following examples show the structure of each payload format version. All header names are lowercased.

2.0

```
        "notBefore": "May 28 12:30:02 2019 GMT",
        "notAfter": "Aug 5 09:36:04 2021 GMT"
    }
}
},
"authorizer": {
    "jwt": {
        "claims": {
            "claim1": "value1",
            "claim2": "value2"
        },
        "scopes": [
            "scope1",
            "scope2"
        ]
    }
},
"domainName": "id.execute-api.us-east-1.amazonaws.com",
"domainPrefix": "id",
"http": {
    "method": "POST",
    "path": "/my/path",
    "protocol": "HTTP/1.1",
    "sourceIp": "192.0.2.1",
    "userAgent": "agent"
},
"requestId": "id",
"routeKey": "$default",
"stage": "$default",
"time": "12/Mar/2020:19:03:58 +0000",
"timeEpoch": 1583348638390
},
"body": "Hello from Lambda",
"pathParameters": {
    "parameter1": "value1"
},
"isBase64Encoded": false,
"stageVariables": {
    "stageVariable1": "value1",
    "stageVariable2": "value2"
}
}
```

1.0

```
{  
    "version": "1.0",  
    "resource": "/my/path",  
    "path": "/my/path",  
    "httpMethod": "GET",  
    "headers": {  
        "header1": "value1",  
        "header2": "value2"  
    },  
    "multiValueHeaders": {  
        "header1": [  
            "value1"  
        ],  
        "header2": [  
            "value1",  
            "value2"  
        ]  
    },  
    "queryStringParameters": {  
        "parameter1": "value1",  
        "parameter2": "value"  
    },  
    "multiValueQueryStringParameters": {  
        "parameter1": [  
            "value1",  
            "value2"  
        ],  
        "parameter2": [  
            "value"  
        ]  
    },  
    "requestContext": {  
        "accountId": "123456789012",  
        "apiId": "id",  
        "authorizer": {  
            "claims": null,  
            "scopes": null  
        },  
        "domainName": "id.execute-api.us-east-1.amazonaws.com",  
        "domainPrefix": "id",  
        "extendedRequestId": "request-id",  
        "httpMethod": "GET",  
        "stage": "prod"  
    }  
}
```

```
"identity": {  
    "accessKey": null,  
    "accountId": null,  
    "caller": null,  
    "cognitoAuthenticationProvider": null,  
    "cognitoAuthenticationType": null,  
    "cognitoIdentityId": null,  
    "cognitoIdentityPoolId": null,  
    "principalOrgId": null,  
    "sourceIp": "192.0.2.1",  
    "user": null,  
    "userAgent": "user-agent",  
    "userArn": null,  
    "clientCert": {  
        "clientCertPem": "CERT_CONTENT",  
        "subjectDN": "www.example.com",  
        "issuerDN": "Example issuer",  
        "serialNumber": "a1:a1:a1:a1:a1:a1:a1:a1:a1:a1:a1:a1:a1:a1:a1:a1",  
        "validity": {  
            "notBefore": "May 28 12:30:02 2019 GMT",  
            "notAfter": "Aug 5 09:36:04 2021 GMT"  
        }  
    }  
},  
"path": "/my/path",  
"protocol": "HTTP/1.1",  
"requestId": "id=",  
"requestTime": "04/Mar/2020:19:15:17 +0000",  
"requestTimeEpoch": 1583349317135,  
"resourceId": null,  
"resourcePath": "/my/path",  
"stage": "$default"  
},  
"pathParameters": null,  
"stageVariables": null,  
"body": "Hello from Lambda!",  
"isBase64Encoded": false  
}
```

Lambda function response format

The payload format version determines the structure of the response that your Lambda function must return.

Lambda function response for format 1.0

With the 1.0 format version, Lambda integrations must return a response in the following JSON format:

Example

```
{  
    "isBase64Encoded": true|false,  
    "statusCode": httpStatusCode,  
    "headers": { "headername": "headervalue", ... },  
    "multiValueHeaders": { "headername": ["headervalue", "headervalue2", ...], ... },  
    "body": "..."  
}
```

Lambda function response for format 2.0

With the 2.0 format version, API Gateway can infer the response format for you. API Gateway makes the following assumptions if your Lambda function returns valid JSON and doesn't return a statusCode:

- isBase64Encoded is false.
- statusCode is 200.
- content-type is application/json.
- body is the function's response.

The following examples show the output of a Lambda function and API Gateway's interpretation.

Lambda function output	API Gateway interpretation
"Hello from Lambda!"	{ "isBase64Encoded": false, "statusCode": 200, "body": "Hello from Lambda!", "headers": {

Lambda function output	API Gateway interpretation
{ "message": "Hello from Lambda!" }	"content-type": "application/json" } } { "isBase64Encoded": false, "statusCode": 200, "body": "{ \"message\": \"Hello from Lambda!\" }", "headers": { "content-type": "application/json" } }

To customize the response, your Lambda function should return a response with the following format.

```
{  
  "cookies" : ["cookie1", "cookie2"],  
  "isBase64Encoded": true|false,  
  "statusCode": httpStatusCode,  
  "headers": { "headername": "headervalue", ... },  
  "body": "Hello from Lambda!"  
}
```

Create HTTP proxy integrations for HTTP APIs

An HTTP proxy integration enables you to connect an API route to a publicly routable HTTP endpoint. With this integration type, API Gateway passes the entire request and response between the frontend and the backend.

To create an HTTP proxy integration, provide the URL of a publicly routable HTTP endpoint.

HTTP proxy integration with path variables

You can use path variables in HTTP API routes.

For example, the route `/pets/{petID}` catches requests to `/pets/6`. You can reference path variables in the integration URI to send the variable's contents to an integration. An example is `/pets/extendedpath/{petID}`.

You can use greedy path variables to catch all child resources of a route. To create a greedy path variable, add `+` to the variable name—for example, `{proxy+}`.

To set up a route with an HTTP proxy integration that catches all requests, create an API route with a greedy path variable (for example, `/parent/{proxy+}`). Integrate the route with an HTTP endpoint (for example, `https://petstore-demo-endpoint.execute-api.com/petstore/{proxy}`) on the ANY method. The greedy path variable must be at the end of the resource path.

Create AWS service integrations for HTTP APIs in API Gateway

You can integrate your HTTP API with AWS services by using *first-class integrations*. A first-class integration connects an HTTP API route to an AWS service API. When a client invokes a route that's backed by a first-class integration, API Gateway invokes an AWS service API for you. For example, you can use first-class integrations to send a message to an Amazon Simple Queue Service queue, or to start an AWS Step Functions state machine. For supported service actions, see [the section called "AWS service integrations reference"](#).

Mapping request parameters

First-class integrations have required and optional parameters. You must configure all required parameters to create an integration. You can use static values or map parameters that are dynamically evaluated at runtime. For a full list of supported integrations and parameters, see [the section called "AWS service integrations reference"](#).

The following table describes the supported mapping request parameters.

Type	Example	Notes
Header value	<code>\$request.header.name</code>	Header names are case-insensitive. API Gateway combines multiple header values with commas, for example "header1": "value1,value2" .

Type	Example	Notes
Query string value	<code>\$request.querystring.name</code>	Query string names are case-sensitive. API Gateway combines multiple values with commas, for example "querystring1": "Value1,Value2" .
Path parameter	<code>\$request.path.name</code>	The value of a path parameter in the request. For example if the route is /pets/{petId} , you can map the petId parameter from the request with <code>\$request.path.petId</code> .
Request body passthrough	<code>\$request.body</code>	API Gateway passes the entire request body through.

Type	Example	Notes
Request body	<code>\$request.body.name</code>	A JSON path expression . Recursive descent (<code>\$request.body.. name</code>) and filter expressions (<code>? (expression) </code>) aren't supported.
		<p>Note</p> <p>When you specify a JSON path, API Gateway truncates the request body at 100 KB and then applies the selection expression. To send payloads larger than 100 KB, specify <code>\$request.body</code>.</p>
Context variable	<code>\$context.variableName</code>	The value of a supported context variable .
Stage variable	<code>\$stageVariables.variableName</code>	The value of a stage variable .
Static value	<code>string</code>	A constant value.

Create a first-class integration

Before you create a first-class integration, you must create an IAM role that grants API Gateway permissions to invoke the AWS service action that you're integrating with. To learn more, see [Creating a role for an AWS service](#).

To create a first-class integration, choose a supported AWS service action, such as SQS-SendMessage, configure the request parameters, and provide a role that grants API Gateway permissions to invoke the integrated AWS service API. Depending on the integration subtype, different request parameters are required. To learn more, see [the section called “AWS service integrations reference”](#).

The following [create-integration](#) command creates an integration that sends an Amazon SQS message:

```
aws apigatewayv2 create-integration \
--api-id abcdef123 \
--integration-subtype SQS-SendMessage \
--integration-type AWS_PROXY \
--payload-format-version 1.0 \
--credentials-arn arn:aws:iam::123456789012:role/apigateway-sqs \
--request-parameters '{"QueueUrl": "$request.header.queueUrl", "MessageBody": \
"$request.body.message"}'
```

Create a first-class integration using CloudFormation

The following example shows an CloudFormation snippet that creates a /{source}/{detailType} route with a first-class integration with Amazon EventBridge.

The Source parameter is mapped to the {source} path parameter, the DetailType is mapped to the {DetailType} path parameter, and the Detail parameter is mapped to the request body.

The snippet does not show the event bus or the IAM role that grants API Gateway permissions to invoke the PutEvents action.

```
Route:
  Type: AWS::ApiGatewayV2::Route
  Properties:
    ApiId: !Ref HttpApi
    AuthorizationType: None
    RouteKey: 'POST /{source}/{detailType}'
    Target: !Join
      - /
      - - integrations
        - !Ref Integration
Integration:
  Type: AWS::ApiGatewayV2::Integration
```

```
Properties:  
  ApiId: !Ref HttpApi  
  IntegrationType: AWS_PROXY  
  IntegrationSubtype: EventBridge-PutEvents  
  CredentialsArn: !GetAtt EventBridgeRole.Arn  
  RequestParameters:  
    Source: $request.path.source  
    DetailType: $request.path.detailType  
    Detail: $request.body  
    EventBusName: !GetAtt EventBus.Arn  
  PayloadFormatVersion: "1.0"
```

Integration subtype reference

The following [integration subtypes](#) are supported for HTTP APIs.

Integration subtypes

- [EventBridge-PutEvents 1.0](#)
- [SQS-SendMessage 1.0](#)
- [SQS-ReceiveMessage 1.0](#)
- [SQS>DeleteMessage 1.0](#)
- [SQS-PurgeQueue 1.0](#)
- [AppConfig-GetConfiguration 1.0](#)
- [Kinesis-PutRecord 1.0](#)
- [StepFunctions-StartExecution 1.0](#)
- [StepFunctions-StartSyncExecution 1.0](#)
- [StepFunctions-StopExecution 1.0](#)

EventBridge-PutEvents 1.0

Sends custom events to Amazon EventBridge so that they can be matched to rules.

Parameter	Required
Detail	True
DetailType	True

Parameter	Required
Source	True
Time	False
EventBusName	False
Resources	False
Region	False
TraceHeader	False

To learn more, see [PutEvents](#) in the *Amazon EventBridge API Reference*.

SQS-SendMessage 1.0

Delivers a message to the specified queue.

Parameter	Required
QueueUrl	True
MessageBody	True
DelaySeconds	False
MessageAttributes	False
MessageDeduplicationId	False
MessageGroupId	False
MessageSystemAttributes	False
Region	False

To learn more, see [SendMessage](#) in the *Amazon Simple Queue Service API Reference*.

SQS-ReceiveMessage 1.0

Retrieves one or more messages (up to 10), from the specified queue.

Parameter	Required
QueueUrl	True
AttributeNames	False
MaxNumberOfMessages	False
MessageAttributeNames	False
ReceiveRequestAttemptId	False
VisibilityTimeout	False
WaitTimeSeconds	False
Region	False

To learn more, see [ReceiveMessage](#) in the *Amazon Simple Queue Service API Reference*.

SQS-DeleteMessage 1.0

Deletes the specified message from the specified queue.

Parameter	Required
ReceiptHandle	True
QueueUrl	True
Region	False

To learn more, see [DeleteMessage](#) in the *Amazon Simple Queue Service API Reference*.

SQS-PurgeQueue 1.0

Deletes all messages in the specified queue.

Parameter	Required
QueueUrl	True
Region	False

To learn more, see [PurgeQueue](#) in the *Amazon Simple Queue Service API Reference*.

AppConfig-GetConfiguration 1.0

Receive information about a configuration.

Parameter	Required
Application	True
Environment	True
Configuration	True
ClientId	True
ClientConfigurationVersion	False
Region	False

To learn more, see [GetConfiguration](#) in the *AWS AppConfig API Reference*.

Kinesis-PutRecord 1.0

Writes a single data record into an Amazon Kinesis data stream.

Parameter	Required
StreamName	True
Data	True
PartitionKey	True

Parameter	Required
SequenceNumberForOrdering	False
ExplicitHashKey	False
Region	False

To learn more, see [PutRecord](#) in the *Amazon Kinesis Data Streams API Reference*.

StepFunctions-StartExecution 1.0

Starts a state machine execution.

Parameter	Required
StateMachineArn	True
Name	False
Input	False
Region	False

To learn more, see [StartExecution](#) in the *AWS Step Functions API Reference*.

StepFunctions-StartSyncExecution 1.0

Starts a synchronous state machine execution.

Parameter	Required
StateMachineArn	True
Name	False
Input	False
Region	False

Parameter	Required
TraceHeader	False

To learn more, see [StartSyncExecution](#) in the *AWS Step Functions API Reference*.

StepFunctions-StopExecution 1.0

Stops an execution.

Parameter	Required
ExecutionArn	True
Cause	False
Error	False
Region	False

To learn more, see [StopExecution](#) in the *AWS Step Functions API Reference*.

Create private integrations for HTTP APIs in API Gateway

Private integrations enable you to create API integrations with private resources in a VPC, such as Application Load Balancers or Amazon ECS container-based applications.

You can expose your resources in a VPC for access by clients outside of the VPC by using private integrations. You can control access to your API by using any of the [authorization methods](#) that API Gateway supports.

Note

To create a private integration, you must first create a VPC link. VPC links V2 are now supported for both HTTP and REST APIs. To learn more about VPC links V2, see [the section called “VPC links V2”](#).

After you've created a VPC link V2, you can set up private integrations that connect to an Application Load Balancer, Network Load Balancer, or resources registered with an AWS Cloud Map service.

Considerations

The following considerations might impact your use of private integrations:

- All resources must be owned by the same AWS account. This includes the load balancer or AWS Cloud Map service, VPC link and HTTP API.
- By default, private integration traffic uses the HTTP protocol. To use HTTPS, specify a [tlsConfig](#). To do this using the AWS Management Console, when you create your private integration, choose **Advanced settings** and then enter a secure server name.
- For private integrations, API Gateway includes the [stage](#) portion of the API endpoint in the request to your backend resources. For example, a request to the test stage of an API includes `test/route-path` in the request to your private integration. To remove the stage name from the request to your backend resources, use [parameter mapping](#) to overwrite the request path to `$request.path`.

Create a private integration using an Application Load Balancer or Network Load Balancer

Before you create a private integration, you must create a VPC link V2. To learn more about VPC links V2, see [the section called "VPC links V2"](#).

To create a private integration with an Application Load Balancer or Network Load Balancer, create an HTTP proxy integration, specify the VPC link to use, and provide the listener ARN of the load balancer.

The following [create-integration](#) command creates a private integration that connects to a load balancer by using a VPC link:

```
aws apigatewayv2 create-integration --api-id api-id --integration-type HTTP_PROXY \
    --integration-method GET --connection-type VPC_LINK \
    --connection-id VPC-link-ID \
    --integration-uri arn:aws:elasticloadbalancing:us-east-2:123456789012:listener/app/
my-load-balancer/50dc6c495c0c9188/0467ef3c8400ae65
    --payload-format-version 1.0
```

Create a private integration using AWS Cloud Map service discovery

Before you create a private integration, you must create a VPC link V2. To learn more about VPC links, see [the section called "VPC links V2"](#).

For integrations with AWS Cloud Map, API Gateway uses `DiscoverInstances` to identify resources. You can use query parameters to target specific resources. The registered resources' attributes must include IP addresses and ports. API Gateway distributes requests across healthy resources that are returned from `DiscoverInstances`. To learn more, see [DiscoverInstances](#) in the AWS Cloud Map API Reference.

Note

If you use Amazon ECS to populate entries in AWS Cloud Map, you must configure your Amazon ECS task to use SRV records with Amazon ECS Service Discovery or turn on Amazon ECS Service Connect. For more information, see [Interconnecting services](#) in the Amazon Elastic Container Service Developer Guide.

To create a private integration with AWS Cloud Map, create an HTTP proxy integration, specify the VPC link to use, and provide the ARN of the AWS Cloud Map service.

The following [create-integration](#) command creates a private integration that uses AWS Cloud Map service discovery to identify resources:

```
aws apigatewayv2 create-integration --api-id api-id --integration-type HTTP_PROXY \
--integration-method GET --connection-type VPC_LINK \
--connection-id VPC-link-ID \
--integration-uri arn:aws:servicediscovery:us-east-2:123456789012:service/srv-id?
stage=prod&deployment=green_deployment
--payload-format-version 1.0
```

Configure CORS for HTTP APIs in API Gateway

[Cross-origin resource sharing \(CORS\)](#) is a browser security feature that restricts HTTP requests that are initiated from scripts running in the browser. If you cannot access your API and receive an error message that contains Cross-Origin Request Blocked, you might need to enable CORS. For more information, see [What is CORS?](#).

CORS is typically required to build web applications that access APIs hosted on a different domain or origin. You can enable CORS to allow requests to your API from a web application hosted on a different domain. For example, if your API is hosted on `https://[api_id].execute-api.[region].amazonaws.com/` and you want to call your API from a web application hosted on `example.com`, your API must support CORS.

If you configure CORS for an API, API Gateway automatically sends a response to preflight OPTIONS requests, even if there isn't an OPTIONS route configured for your API. For a CORS request, API Gateway adds the configured CORS headers to the response from an integration.

 **Note**

If you configure CORS for an API, API Gateway ignores CORS headers returned from your backend integration.

You can specify the following parameters in a CORS configuration. To add these parameters using the API Gateway HTTP API console, choose **Add** after you enter your value.

CORS headers	CORS configuration property	Example values
Access-Control-Allow-Origin	allowOrigins	<ul style="list-style-type: none"><code>https://www.example.com</code><code>*</code> (allow all origins)<code>https:///*</code> (allow any origin that begins with <code>https://</code>)<code>http:///*</code> (allow any origin that begins with <code>http://</code>)
Access-Control-Allow-Credentials	allowCredentials	true
Access-Control-Expose-Headers	exposeHeaders	date, x-api-id, *
Access-Control-Max-Age	maxAge	300

CORS headers	CORS configuration property	Example values
Access-Control-Allow-Methods S	allowMethods	GET, POST, DELETE, *
Access-Control-Allow-Headers S	allowHeaders	authorization, *

To return CORS headers, your request must contain an `origin` header. For the `OPTIONS` method, your request must contain an `origin` header and an `Access-Control-Request-Method` header.

Your CORS configuration might look similar to the following:

The screenshot shows the AWS API Gateway CORS configuration page. On the left, there's a sidebar with navigation links: API Gateway, APIs, Custom domain names, VPC links, API: HelloWorld... (abcd1234), Develop (Routes, Authorization, Integrations, CORS), Deploy (Stages), Monitor (Metrics, Logging), and Protect (Throttling). The main content area has a breadcrumb trail: API Gateway > APIs > HelloWorld (abcd1234) > CORS. The title is "Cross-Origin Resource Sharing". Under "Configure CORS", there's an "Info" section stating that CORS allows resources from different domains to be loaded by browsers. It notes that API Gateway ignores CORS headers returned from your backend integration and points to the CORS documentation for more details. The configuration section contains several fields: "Access-Control-Allow-Origin" with a value of "https://www.example.com" and an "Add" button; "Access-Control-Allow-Headers" with a value of "authorization" and an "Add" button; "Access-Control-Allow-Methods" with a dropdown menu showing "Choose Allowed Methods" and a value of "*"; "Access-Control-Expose-Headers" with a value of "date,x-api-id" and an "Add" button; "Access-Control-Max-Age" with a value of "300"; and "Access-Control-Allow-Credentials" with a "YES" toggle switch. At the bottom right are "Cancel" and "Save" buttons.

Configuring CORS for an HTTP API with a \$default route and an authorizer

You can enable CORS and configure authorization for any route of an HTTP API. When you enable CORS and authorization for the [\\$default route](#), there are some special considerations. The \$default route catches requests for all methods and routes that you haven't explicitly defined, including OPTIONS requests. To support unauthorized OPTIONS requests, add an OPTIONS / {proxy+} route to your API that doesn't require authorization and attach an integration to the route. The OPTIONS /{proxy+} route has higher priority than the \$default route. As a result, it enables clients to submit OPTIONS requests to your API without authorization. For more information about routing priorities, see [Routing API requests](#).

Configure CORS for an HTTP API by using the AWS CLI

The following [update-api](#) command enables CORS requests from https://www.example.com:

Example

```
aws apigatewayv2 update-api --api-id api-id --cors-configuration AllowOrigins="https://www.example.com"
```

For more information, see [CORS](#) in the Amazon API Gateway Version 2 API Reference.

Transform API requests and responses for HTTP APIs in API Gateway

You can modify API requests from clients before they reach your backend integrations. You can also change the response from integrations before API Gateway returns the response to clients. You use *parameter mapping* to modify API requests and responses for HTTP APIs. To use parameter mapping, you specify API request or response parameters to modify, and specify how to modify those parameters.

Transforming API requests

You use request parameters to change requests before they reach your backend integrations. You can modify headers, query strings, or the request path.

Request parameters are a key-value map. The key identifies the location of the request parameter to change, and how to change it. The value specifies the new data for the parameter.

The following table shows supported keys.

Type	Syntax
Header	append overwrite remove:header. <i>headername</i>
Query string	append overwrite remove:querystring. <i>querystring-name</i>
Path	overwrite:path

The following table shows supported values that you can map to parameters.

Type	Syntax	Notes
Header value	<code>\$request.header.<i>name</i></code> or <code> \${request.header.<i>name</i>}</code>	Header names are case-insensitive. API Gateway combines multiple header values with commas, for example "header1": "value1,value2" . Some headers are reserved. To learn more, see the section called "Reserved headers" .
Query string value	<code>\$request.querystring.<i>name</i></code> or <code> \${request.querystring.<i>name</i>}</code>	Query string names are case-sensitive. API Gateway combines multiple values with commas, for example "querystring1" "Value1,Value2" .
Request body	<code>\$request.body.<i>name</i></code> or <code> \${request.body.<i>name</i>}</code>	A JSON path expression. Recursive descent (<code>\$request.body..name</code>) and filter expressions (<code>(?(<expression>))</code>) aren't supported.

Type	Syntax	Notes
		<p>Note</p> <p>When you specify a JSON path, API Gateway truncates the request body at 100 KB and then applies the selection expression. To send payloads larger than 100 KB, specify <code>\$request.body</code> .</p>
Request path	<code>\$request.path</code> or <code> \${request.path}</code>	The request path, without the stage name.
Path parameter	<code>\$request.path.<i>name</i></code> or <code> \${request.path.<i>name</i>}</code>	The value of a path parameter in the request. For example if the route is <code>/pets/{petId}</code> , you can map the petId parameter from the request with <code>\$request.path.petId</code> .
Context variable	<code>\$context.<i>variableName</i></code> or <code> \${context.<i>variableName</i>}</code>	<p>The value of a context variable.</p> <p>Note</p> <p>Only the special characters . and _ are supported.</p>

Type	Syntax	Notes
Stage variable	<code>\$stageVariables.<i>variableName</i> or \${stageVariables.<i>variableName</i>}</code>	The value of a stage variable .
Static value	<code><i>string</i></code>	A constant value.

 **Note**

To use multiple variables in a selection expression, enclose the variable in brackets. For example, `${request.path.name} ${request.path.id}`.

Transforming API responses

You use response parameters to transform the HTTP response from a backend integration before returning the response to clients. You can modify headers or the status code of a response before API Gateway returns the response to clients.

You configure response parameters for each status code that your integration returns. Response parameters are a key-value map. The key identifies the location of the request parameter to change, and how to change it. The value specifies the new data for the parameter.

The following table shows supported keys.

Type	Syntax
Header	<code>append overwrite remove:header. <i>headername</i></code>
Status code	<code>overwrite:statuscode</code>

The following table shows supported values that you can map to parameters.

Type	Syntax	Notes
Header value	<code>\$response.header.<i>name</i> or \${response.header.<i>name</i>}</code>	Header names are case-insensitive. API Gateway combines multiple header values with commas, for example "header1": "value1,value2" . Some headers are reserved. To learn more, see the section called "Reserved headers".
Response body	<code>\$response.body.<i>name</i> or \${response.body.<i>name</i>}</code>	A JSON path expression. Recursive descent (<code>\$response.body..name</code>) and filter expressions (<code>?(expression)</code>) aren't supported.
Context variable	<code>\$context.<i>variableName</i> or \${context.<i>variableName</i> }</code>	The value of a supported context variable .

 **Note**

When you specify a JSON path, API Gateway truncates the response body at 100 KB and then applies the selection expression. To send payloads larger than 100 KB, specify `$response.body` .

Type	Syntax	Notes
Stage variable	<code>\$stageVariables.<i>variableName</i> or \${stageVariables.<i>variableName</i>}</code>	The value of a stage variable .
Static value	<code>string</code>	A constant value.

 **Note**

To use multiple variables in a selection expression, enclose the variable in brackets. For example, `${request.path.name} ${request.path.id}`.

Reserved headers

The following headers are reserved. You can't configure request or response mappings for these headers.

- access-control-*
- apigw-*
- Authorization
- Connection
- Content-Encoding
- Content-Length
- Content-Location
- Forwarded
- Keep-Alive
- Origin
- Proxy-Authenticate
- Proxy-Authorization
- TE
- Trailers

- Transfer-Encoding
- Upgrade
- x-amz-*
- x-amzn-*
- X-Forwarded-For
- X-Forwarded-Host
- X-Forwarded-Proto
- Via

Examples

The following AWS CLI examples configure parameter mappings. For example CloudFormation templates, see [GitHub](#).

Add a header to an API request

The following [create-integration](#) command creates a header named header1 to an API request before it reaches your backend integration. API Gateway populates the header with the request ID.

```
aws apigatewayv2 create-integration \
  --api-id abcdef123 \
  --integration-type HTTP_PROXY \
  --payload-format-version 1.0 \
  --integration-uri 'https://api.example.com' \
  --integration-method ANY \
  --request-parameters '{ "append:header.header1": "$context.requestId" }'
```

Rename a request header

The following [create-integration](#) command renames a request header from header1 to header2:

```
aws apigatewayv2 create-integration \
  --api-id abcdef123 \
  --integration-type HTTP_PROXY \
  --payload-format-version 1.0 \
  --integration-uri 'https://api.example.com' \
  --integration-method ANY \
```

```
--request-parameters '{ "append:header.header2": "$request.header.header1",
"remove:header.header1": ""}'
```

Change the response from an integration

The following [create-integration](#) command configures response parameters for an integration. When the integrations returns a 500 status code, API Gateway changes the status code to 403, and adds header11 to the response. When the integration returns a 404 status code, API Gateway adds an error header to the response.

```
aws apigatewayv2 create-integration \
--api-id abcdef123 \
--integration-type HTTP_PROXY \
--payload-format-version 1.0 \
--integration-uri 'https://api.example.com' \
--integration-method ANY \
--response-parameters '{"500" : {"append:header.header1": "$context.requestId",
"overwrite:statuscode" : "403"}, "404" : {"append:header.error" :
"$stageVariables.environmentId"} }'
```

Remove configured parameter mappings

The following [update-integration](#) command removes previously configured request parameters for append:header.header1. It also removes previously configured response parameters for a 200 status code.

```
aws apigatewayv2 update-integration \
--api-id abcdef123 \
--integration-id hijk456 \
--request-parameters '{"append:header.header1" : ""}' \
--response-parameters '{"200" : {}}'
```

Use OpenAPI definitions for HTTP APIs in API Gateway

You can define your HTTP API by using an OpenAPI 3.0 definition file. Then you can import the definition into API Gateway to create an API. To learn more about API Gateway extensions to OpenAPI, see [OpenAPI extensions](#).

Importing an HTTP API

You can create an HTTP API by importing an OpenAPI 3.0 definition file.

To migrate from a REST API to an HTTP API, you can export your REST API as an OpenAPI 3.0 definition file. Then import the API definition as an HTTP API. To learn more about exporting a REST API, see [Export a REST API from API Gateway](#).

Note

HTTP APIs support the same AWS variables as REST APIs. To learn more, see [AWS variables for OpenAPI import](#).

Import validation information

As you import an API, API Gateway provides three categories of validation information.

Info

A property is valid according to the OpenAPI specification, but that property isn't supported for HTTP APIs.

For example, the following OpenAPI 3.0 snippet produces info on import because HTTP APIs don't support request validation. API Gateway ignores the `requestBody` and `schema` fields.

```
"paths": {  
  "/": {  
    "get": {  
      "x-amazon-apigateway-integration": {  
        "type": "AWS_PROXY",  
        "httpMethod": "POST",  
        "uri": "arn:aws:lambda:us-east-2:123456789012:function:HelloWorld",  
        "payloadFormatVersion": "1.0"  
      },  
      "requestBody": {  
        "content": {  
          "application/json": {  
            "schema": {  
              "$ref": "#/components/schemas/Body"  
            }  
          }  
        }  
      }  
    }  
  }  
}
```

```
...  
},  
"components": {  
  "schemas": {  
    "Body": {  
      "type": "object",  
      "properties": {  
        "key": {  
          "type": "string"  
        }  
      }  
    }  
  }  
}  
...  
}  
...
```

Warning

A property or structure is invalid according to the OpenAPI specification, but it doesn't block API creation. You can specify whether API Gateway should ignore these warnings and continue creating the API, or stop creating the API on warnings.

The following OpenAPI 3.0 document produces warnings on import because HTTP APIs support only Lambda proxy and HTTP proxy integrations.

```
"x-amazon-apigateway-integration": {  
  "type": "AWS",  
  "httpMethod": "POST",  
  "uri": "arn:aws:lambda:us-east-2:123456789012:function:HelloWorld",  
  "payloadFormatVersion": "1.0"  
}
```

Error

The OpenAPI specification is invalid or malformed. API Gateway can't create any resources from the malformed document. You must fix the errors, and then try again.

The following API definition produces errors on import because HTTP APIs support only the OpenAPI 3.0 specification.

```
{  
  "swagger": "2.0.0",
```

```
"info": {
    "title": "My API",
    "description": "An Example OpenAPI definition for Errors/Warnings/ImportInfo",
    "version": "1.0"
}
...
}
```

As another example, while OpenAPI allows users to define an API with multiple security requirements attached to a particular operation, API Gateway does not support this. Each operation can have only one of IAM authorization, a Lambda authorizer, or a JWT authorizer. Attempting to model multiple security requirements results in an error.

Import an API by using the AWS CLI

The following [import-api](#) command imports the OpenAPI 3.0 definition file `api-definition.json` as an HTTP API:

Example

```
aws apigatewayv2 import-api --body file://api-definition.json
```

Example

You can import the following example OpenAPI 3.0 definition to create an HTTP API.

```
{
  "openapi": "3.0.1",
  "info": {
    "title": "Example Pet Store",
    "description": "A Pet Store API.",
    "version": "1.0"
  },
  "paths": {
    "/pets": {
      "get": {
        "operationId": "GET HTTP",
        "parameters": [
          {
            "name": "type",
            "in": "query",
            "schema": {
              "type": "string"
            }
          }
        ]
      }
    }
  }
}
```

```
        "type": "string"
    }
},
{
    "name": "page",
    "in": "query",
    "schema": {
        "type": "string"
    }
}
],
"responses": {
    "200": {
        "description": "200 response",
        "headers": {
            "Access-Control-Allow-Origin": {
                "schema": {
                    "type": "string"
                }
            }
        },
        "content": {
            "application/json": {
                "schema": {
                    "$ref": "#/components/schemas/Pets"
                }
            }
        }
    }
},
"x-amazon-apigateway-integration": {
    "type": "HTTP_PROXY",
    "httpMethod": "GET",
    "uri": "http://petstore.execute-api.us-west-1.amazonaws.com/petstore/pets",
    "payloadFormatVersion": 1.0
}
},
"post": {
    "operationId": "Create Pet",
    "requestBody": {
        "content": {
            "application/json": {
                "schema": {
                    "$ref": "#/components/schemas/NewPet"
                }
            }
        }
    }
}
```

```
        }
    },
},
"required": true
},
"responses": {
"200": {
"description": "200 response",
"headers": {
"Access-Control-Allow-Origin": {
"schema": {
"type": "string"
}
}
},
"content": {
"application/json": {
"schema": {
"$ref": "#/components/schemas/NewPetResponse"
}
}
}
}
},
"x-amazon-apigateway-integration": {
"type": "HTTP_PROXY",
"httpMethod": "POST",
"uri": "http://petstore.execute-api.us-west-1.amazonaws.com/petstore/pets",
"payloadFormatVersion": 1.0
}
}
},
"/pets/{petId)": {
"get": {
"operationId": "Get Pet",
"parameters": [
{
"name": "petId",
"in": "path",
"required": true,
"schema": {
"type": "string"
}
}
]
}
```

```
],
  "responses": {
    "200": {
      "description": "200 response",
      "headers": {
        "Access-Control-Allow-Origin": {
          "schema": {
            "type": "string"
          }
        }
      },
      "content": {
        "application/json": {
          "schema": {
            "$ref": "#/components/schemas/Pet"
          }
        }
      }
    }
  },
  "x-amazon-apigateway-integration": {
    "type": "HTTP_PROXY",
    "httpMethod": "GET",
    "uri": "http://petstore.execute-api.us-west-1.amazonaws.com/petstore/pets/{petId}",
    "payloadFormatVersion": 1.0
  }
}
},
  ],
  "x-amazon-apigateway-cors": {
    "allowOrigins": [
      "*"
    ],
    "allowMethods": [
      "GET",
      "OPTIONS",
      "POST"
    ],
    "allowHeaders": [
      "x-amzm-header",
      "x-apigateway-header",
      "x-api-key",
      "authorization",
      "Content-Type"
    ]
  }
}
```

```
"x-amz-date",
"content-type"
],
},
"components": {
"schemas": {
"Pets": {
"type": "array",
"items": {
"$ref": "#/components/schemas/Pet"
}
},
"Empty": {
"type": "object"
},
"NewPetResponse": {
"type": "object",
"properties": {
"pet": {
"$ref": "#/components/schemas/Pet"
},
"message": {
"type": "string"
}
}
},
"Pet": {
"type": "object",
"properties": {
"id": {
"type": "string"
},
"type": {
"type": "string"
},
"price": {
"type": "number"
}
}
}
},
"NewPet": {
"type": "object",
"properties": {
"type": {

```

```
        "$ref": "#/components/schemas/PetType"
    },
    "price": {
        "type": "number"
    }
},
"PetType": {
    "type": "string",
    "enum": [
        "dog",
        "cat",
        "fish",
        "bird",
        "gecko"
    ]
}
}
```

Export HTTP APIs from API Gateway

After you've created an HTTP API, you can export an OpenAPI 3.0 definition of your API from API Gateway. You can either choose a stage to export, or export the latest configuration of your API. You can also import an exported API definition into API Gateway to create another, identical API. To learn more about importing API definitions, see [Importing an HTTP API](#).

Export an OpenAPI 3.0 definition of a stage by using the AWS CLI

The following [export-api](#) command exports an OpenAPI definition of an API stage named `prod` to a YAML file named `stage-definition.yaml`. The exported definition file includes [API Gateway extensions](#) by default.

```
aws apigatewayv2 export-api \
--api-id api-id \
--output-type YAML \
--specification OAS30 \
--stage-name prod \
stage-definition.yaml
```

Export an OpenAPI 3.0 definition of your API's latest changes by using the AWS CLI

The following [export-api](#) command exports an OpenAPI definition of an HTTP API to a JSON file named `latest-api-definition.json`. Because the command doesn't specify a stage, API Gateway exports the latest configuration of your API, whether it has been deployed to a stage or not. The exported definition file doesn't include [API Gateway extensions](#).

```
aws apigatewayv2 export-api \
--api-id api-id \
--output-type JSON \
--specification OAS30 \
--no-include-extensions \
latest-api-definition.json
```

For more information, see [ExportAPI](#) in the *Amazon API Gateway Version 2 API Reference*.

Export an OpenAPI 3.0 definition by using the API Gateway console

The following procedure shows how to export an OpenAPI definition of an HTTP API.

To export an OpenAPI 3.0 definition using the API Gateway console

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose an HTTP API.
3. On the main navigation pane, under **Develop**, choose **Export**.
4. Select from the following options to export your API:

The screenshot shows the 'Export' section of the API Gateway console. At the top, the navigation path is: API Gateway > APIs > my-http-api (abcdef1234) > Export. The main title is 'Export'. Below it, there's a section titled 'Export an OpenAPI 3 definition' with a 'Info' link. A sub-instruction says 'Download an OpenAPI 3 definition of your latest changes or a stage's configuration.' Under 'Source', a dropdown menu is set to '\$default'. There's a '▼' icon to its right. Below this, there's a 'Extensions' section with a 'Learn more' link and a toggle switch labeled 'Include API Gateway extensions' which is turned on. Under 'Output format', there are two radio buttons: 'JSON' (selected) and 'YAML'. At the bottom right is a large orange 'Download' button.

- a. For **Source**, select a source for the OpenAPI 3.0 definition. You can choose a stage to export, or export the latest configuration of your API.
 - b. Turn on **Include API Gateway extensions** to include [API Gateway extensions](#).
 - c. For **Output format**, select an output format.
5. Choose **Download**.

Publish HTTP APIs for customers to invoke

You can use stages and custom domain names to publish your API for clients to invoke.

An API stage is a logical reference to a lifecycle state of your API (for example, dev, prod, beta, or v2). Each stage is a named reference to a deployment of the API and is made available for client applications to call. You can configure different integrations and settings for each stage of an API.

You can use custom domain names to provide a simpler, more intuitive URL for clients to invoke your API than the default URL, `https://api-id.execute-api.region.amazonaws.com/stage`.

Note

To augment the security of your API Gateway APIs, the `execute-api`.

{`region`}.amazonaws.com domain is registered in the [Public Suffix List \(PSL\)](#). For further security, we recommend that you use cookies with a __Host- prefix if you ever need to set sensitive cookies in the default domain name for your API Gateway APIs. This practice will help to defend your domain against cross-site request forgery attempts (CSRF). For more information see the [Set-Cookie](#) page in the Mozilla Developer Network.

Topics

- [Stages for HTTP APIs in API Gateway](#)
- [Security policy for HTTP APIs in API Gateway](#)
- [Custom domain names for HTTP APIs in API Gateway](#)

Stages for HTTP APIs in API Gateway

An API stage is a logical reference to a lifecycle state of your API (for example, dev, prod, beta, or v2). API stages are identified by their API ID and stage name, and they're included in the URL you use to invoke the API. Each stage is a named reference to a deployment of the API and is made available for client applications to call.

You can create a \$default stage that is served from the base of your API's URL—for example, `https://{api_id}.execute-api.{region}.amazonaws.com/`

. You use this URL to invoke an API stage.

A deployment is a snapshot of your API configuration. After you deploy an API to a stage, it's available for clients to invoke. You must deploy an API for changes to take effect. If you enable automatic deployments, changes to an API are automatically released for you.

Use stage variables for HTTP APIs in API Gateway

Stage variables are key-value pairs that you can define for a stage of an HTTP API. They act like environment variables and can be used in your API setup.

Stage variables are not intended to be used for sensitive data, such as credentials. To pass sensitive data to integrations, use an AWS Lambda authorizer. You can pass sensitive data to integrations

in the output of the Lambda authorizer. To learn more, see [the section called “Lambda authorizer response format”](#).

Example – Use a stage variable to customize the HTTP integration endpoint

For example, you can define a stage variable, and then set its value as an HTTP endpoint for an HTTP proxy integration. Later, you can reference the endpoint by using the associated stage variable name. By doing this, you can use the same API setup with a different endpoint at each stage. Similarly, you can use stage variables to specify a different AWS Lambda function integration for each stage of your API.

To use a stage variable to customize the HTTP integration endpoint, you must first set the name and value of the stage variable (for example, `url1`) with a value of `example.com`. Next, set up an HTTP proxy integration. Instead of entering the endpoint's URL, you can tell API Gateway to use the stage variable value, `http://${stageVariables.url1}`. This value tells API Gateway to substitute your stage variable `$ {}` at runtime, depending on the stage of your API.

You can reference stage variables in a similar way to specify a Lambda function name or an AWS role ARN.

When specifying a Lambda function name as a stage variable value, you must configure the permissions on the Lambda function manually. The following [add-permission](#) command configures the permission for the Lambda function:

```
aws lambda add-permission --function-name arn:aws:lambda:XXXXXX:your-lambda-function-name --source-arn arn:aws:execute-api:us-east-1:YOUR_ACCOUNT_ID:api_id/*/* /HTTP_METHOD/resource --principal apigateway.amazonaws.com --statement-id apigateway-access --action lambda:InvokeFunction
```

API Gateway stage variables reference for HTTP APIs in API Gateway

You can use API Gateway stage variables for HTTP APIs in the following cases.

HTTP integration URIs

You can use a stage variable as part of an HTTP integration URI, as shown in the following examples.

- A full URI without protocol – `http://${stageVariables.<variable_name>}`
- A full domain – `http://${stageVariables.<variable_name>}/resource/operation`

- A subdomain – `http://${stageVariables.<variable_name>}.example.com/resource/operation`
- A path – `http://example.com/${stageVariables.<variable_name>}/bar`
- A query string – `http://example.com/foo?q=${stageVariables.<variable_name>}`

Lambda functions

You can use a stage variable in place of a Lambda function integration name or alias, as shown in the following examples.

- `arn:aws:apigateway:<region>:lambda:path/2015-03-31/functions/arn:aws:lambda:<region>:<account_id>:function:${stageVariables.<function_variable_name>}/invocations`
- `arn:aws:apigateway:<region>:lambda:path/2015-03-31/functions/arn:aws:lambda:<region>:<account_id>:function:<function_name>:${stageVariables.<version_variable_name>}/invocations`

 **Note**

To use a stage variable for a Lambda function, the function must be in the same account as the API. Stage variables don't support cross-account Lambda functions.

AWS integration credentials

You can use a stage variable as part of an AWS user or role credential ARN, as shown in the following example.

- `arn:aws:iam::<account_id>:${stageVariables.<variable_name>}`

Security policy for HTTP APIs in API Gateway

API Gateway enforces a security policy of TLS_1_2 for all HTTP API endpoints.

A *security policy* is a predefined combination of minimum TLS version and cipher suites offered by Amazon API Gateway. The TLS protocol addresses network security problems such as tampering and eavesdropping between a client and server. When your clients establish a TLS handshake to

your API through the custom domain, the security policy enforces the TLS version and cipher suite options your clients can choose to use. This security policy accepts TLS 1.2 and TLS 1.3 traffic and rejects TLS 1.0 traffic.

Supported TLS protocols and ciphers for HTTP APIs

The following table describes the supported TLS protocols for HTTP APIs.

TLS protocols	TLS_1_2 security policy
TLSv1.3	Yes
TLSv1.2	Yes

The following table describes the TLS ciphers that are available for the TLS 1_2 security policy for HTTP APIs.

TLS ciphers	TLS_1_2 security policy
TLS-AES-128-GCM-SHA256	Yes
TLS-AES-256-GCM-SHA384	Yes
TLS-CHACHA20-POLY1305-SHA256	Yes
ECDHE-ECDSA-AES128-GCM-SHA256	Yes
ECDHE-RSA-AES128-GCM-SHA256	Yes

TLS ciphers	TLS_1_2 security policy
ECDHE-ECDSA-AES128-SHA256	Yes
ECDHE-RSA-AES128-SHA256	Yes
ECDHE-ECDSA-AES256-GCM-SHA384	Yes
ECDHE-RSA-AES256-GCM-SHA384	Yes
ECDHE-ECDSA-AES256-SHA384	Yes
ECDHE-RSA-AES256-SHA384	Yes
AES128-GCM-SHA256	Yes
AES128-SHA256	Yes
AES256-GCM-SHA384	Yes
AES256-SHA256	Yes

OpenSSL and RFC cipher names

OpenSSL and IETF RFC 5246 use different names for the same ciphers. For a list of the cipher names, see [the section called “OpenSSL and RFC cipher names”](#).

Information about REST APIs and WebSocket APIs

For more information about REST APIs and WebSocket APIs, see [the section called “Choose a security policy”](#) and [the section called “Security policy for WebSocket APIs in API Gateway”](#).

Custom domain names for HTTP APIs in API Gateway

Custom domain names are simpler and more intuitive URLs that you can provide to your API users.

After deploying your API, you (and your customers) can invoke the API using the default base URL of the following format:

```
https://api-id.execute-api.region.amazonaws.com/stage
```

where *api-id* is generated by API Gateway, *region* is the AWS Region, and *stage* is specified by you when deploying the API.

The hostname portion of the URL, *api-id*.execute-api.*region*.amazonaws.com refers to an API endpoint. The default API endpoint name is randomly generated, difficult to recall, and not user-friendly.

With custom domain names, you can set up your API's hostname, and choose a base path (for example, *myservice*) to map the alternative URL to your API. For example, a more user-friendly API base URL can become:

```
https://api.example.com/myservice
```

Considerations

The following considerations might impact your use of a custom domain name.

- A Regional custom domain name can be associated with REST APIs and HTTP APIs. You can use the API Gateway Version 2 APIs to create and manage Regional custom domain names for REST APIs.
- For the minimum TLS version, only TLS 1.2 is supported.
- You must create or update your DNS provider's resource record to map to your API endpoint. Without such a mapping, API requests bound for the custom domain name cannot reach API Gateway.

- You can support an almost infinite number of domain names without exceeding the default quota by using a wildcard certificate. For more information, see [the section called "Wildcard custom domain names"](#).

Prerequisites

The following are prerequisites for creating a custom domain name.

Register a domain name

You must have a registered internet domain name in order to set up custom domain names for your APIs. You can register your internet domain name using [Amazon Route 53](#) or using a third-party domain registrar of your choice. Your custom domain name can be the name of a subdomain or the root domain (also known as the "zone apex") of a registered internet domain.

Your domain name must follow the [RFC 1035](#) specification and can have a maximum of 63 octets per label and 255 octets in total.

Certificates for custom domain names

Before setting up a custom domain name for an API, you must have an SSL/TLS certificate ready in ACM. If ACM is not available in the AWS Region where you are creating your custom domain name, you must import a certificate to API Gateway in that Region.

To import an SSL/TLS certificate, you must provide the PEM-formatted SSL/TLS certificate body, its private key, and the certificate chain for the custom domain name.

Each certificate stored in ACM is identified by its ARN. With certificates issued by ACM, you do not have to worry about exposing any sensitive certificate details, such as the private key. To use an AWS managed certificate for a domain name, you simply reference its ARN.

If your application uses certificate pinning, sometimes known as SSL pinning, to pin an ACM certificate, the application might not be able to connect to your domain after AWS renews the certificate. For more information, see [Certificate pinning problems](#) in the *AWS Certificate Manager User Guide*.

Wildcard custom domain names

With wildcard custom domain names, you can support an almost infinite number of domain names without exceeding the [default quota](#). For example, you could give each of your customers their own domain name, *customername*.api.example.com.

To create a wildcard custom domain name, specify a wildcard (*) as the first subdomain of a custom domain that represents all possible subdomains of a root domain.

For example, the wildcard custom domain name *.example.com results in subdomains such as a.example.com, b.example.com, and c.example.com, which all route to the same domain.

Wildcard custom domain names support distinct configurations from API Gateway's standard custom domain names. For example, in a single AWS account, you can configure *.example.com and a.example.com to behave differently.

To create a wildcard custom domain name, you must provide a certificate issued by ACM that has been validated using either the DNS or the email validation method.

Note

You can't create a wildcard custom domain name if a different AWS account has created a custom domain name that conflicts with the wildcard custom domain name. For example, if account A has created a.example.com, then account B can't create the wildcard custom domain name *.example.com.

If account A and account B share an owner, you can contact the [AWS Support Center](#) to request an exception.

Next steps for custom domain names

To set up a custom domain name for an HTTP API, you use documentation from the REST API section of the API Gateway Developer Guide.

First, specify a certificate for your custom domain name. For more information, see [the section called "Get certificates ready in AWS Certificate Manager"](#). Next, you create a Regional custom domain name. For more information, see [the section called "Set up a Regional custom domain name"](#).

Map API stages to a custom domain name for HTTP APIs

You use API mappings to connect API stages to a custom domain name. After you create a domain name and configure DNS records, you use API mappings to send traffic to your APIs through your custom domain name.

An API mapping specifies an API, a stage, and optionally a path to use for the mapping. For example, you can map the production stage of an API to `https://api.example.com/orders`.

You can map HTTP and REST API stages to the same custom domain name.

Before you create an API mapping, you must have an API, a stage, and a custom domain name. To learn more about creating a custom domain name, see [the section called “Set up a Regional custom domain name”](#).

Routing API requests

You can configure API mappings with multiple levels, for example `orders/v1/items` and `orders/v2/items`.

For API mappings with multiple levels, API Gateway routes requests to the API mapping that has the longest matching path. API Gateway considers only the paths configured for API mappings, and not API routes, to select the API to invoke. If no path matches the request, API Gateway sends the request to the API that you've mapped to the empty path (none).

For custom domain names that use API mappings with multiple levels, API Gateway routes requests to the API mapping that has the longest matching prefix.

For example, consider a custom domain name `https://api.example.com` with the following API mappings:

1. (none) mapped to API 1.
2. `orders` mapped to API 2.
3. `orders/v1/items` mapped to API 3.
4. `orders/v2/items` mapped to API 4.
5. `orders/v2/items/categories` mapped to API 5.

Request	Selected API	Explanation
<code>https://api.example.com/orders</code>	API 2	The request exactly matches this API mapping.

Request	Selected API	Explanation
<code>https://api.example.com/orders/v1/items</code>	API 3	The request exactly matches this API mapping.
<code>https://api.example.com/orders/v2/items</code>	API 4	The request exactly matches this API mapping.
<code>https://api.example.com/orders/v1/items/123</code>	API 3	API Gateway chooses the mapping that has the longest matching path. The 123 at the end of the request doesn't affect the selection.
<code>https://api.example.com/orders/v2/items/categories/5</code>	API 5	API Gateway chooses the mapping that has the longest matching path.
<code>https://api.example.com/customers</code>	API 1	API Gateway uses the empty mapping as a catch-all.
<code>https://api.example.com/ordersandmore</code>	API 2	<p>API Gateway chooses the mapping that has the longest matching prefix.</p> <p>For a custom domain name configured with single-level mappings, such as only <code>https://api.example.com/orders</code> and <code>https://api.example.com/</code>, API Gateway would choose API 1, as there is no matching path with <code>ordersandmore</code>.</p>

Restrictions

- In an API mapping, the custom domain name and mapped APIs must be in the same AWS account.
- API mappings must contain only letters, numbers, and the following characters: \$-_.+!*'()./.
- The maximum length for the path in an API mapping is 300 characters.
- You can have 200 API mappings with multiple levels for each domain name. This limit doesn't include API mapping with single levels, such as /prod.
- You can only map HTTP APIs to a regional custom domain name with the TLS 1.2 security policy.
- You can't map WebSocket APIs to the same custom domain name as an HTTP API or REST API.
- If you create an API mappings with multiple levels, API Gateway converts all header names to lowercase.

Create an API mapping

To create an API mapping, you must first create a custom domain name, API, and stage. For information about creating a custom domain name, see [the section called “Set up a Regional custom domain name”](#).

For example AWS Serverless Application Model templates that create all resources, see [Sessions With SAM](#) on GitHub.

AWS Management Console

To create an API mapping

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose **Custom domain names**.
3. Select a custom domain name that you've already created.
4. Choose **API mappings**.
5. Choose **Configure API mappings**.
6. Choose **Add new mapping**.
7. Enter an **API**, a **Stage**, and optionally a **Path**.
8. Choose **Save**.

AWS CLI

The following [create-api-mapping](#) command creates an API mapping. In this example, API Gateway sends requests to `api.example.com/v1/orders` to the specified API and stage.

```
aws apigatewayv2 create-api-mapping \
--domain-name api.example.com \
--api-mapping-key v1/orders \
--api-id a1b2c3d4 \
--stage test
```

CloudFormation

The following CloudFormation example creates an API mapping.

```
MyApiMapping:
  Type: 'AWS::ApiGatewayV2::ApiMapping'
  Properties:
    DomainName: api.example.com
    ApiMappingKey: 'orders/v2/items'
    ApiId: !Ref MyApi
    Stage: !Ref MyStage
```

Disable the default endpoint for HTTP APIs

By default, clients can invoke your API by using the `execute-api` endpoint that API Gateway generates for your API. To ensure that clients can access your API only by using a custom domain name, disable the default `execute-api` endpoint. When you disable the default endpoint, it affects all stages of an API.

The following procedure shows how to disable the default endpoint for an HTTP API.

AWS Management Console

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose an HTTP API.
3. Choose your API's ID to open the **API details** page.
4. On **API details**, choose **Edit**.
5. For **Default endpoint**, select **Disable**.

6. Choose **Save**.

If you turn on automatic deployments for your stage, you do not need to redeploy your API for the change to take effect. Otherwise, you must redeploy your API.

7. (Optional) Choose **Deploy**, and then redeploy your API or create a new stage for the change to take effect.

AWS CLI

The following [update-domain-name](#) command disables the default endpoint for an HTTP API:

```
aws apigatewayv2 update-api \
--api-id abcdef123 \
--disable-execute-api-endpoint
```

After you disable the default endpoint, you must deploy your API for the change to take effect, unless automatic deployments are enabled.

The following [create-deployment](#) command creates a deployment:

```
aws apigatewayv2 create-deployment \
--api-id abcdef123 \
--stage-name dev
```

IP address types for custom domain names for HTTP APIs

When you create an API, you specify the type of IP addresses that can invoke your domain. You can choose IPv4 to resolve IPv4 addresses to invoke your domain, or you can choose dualstack to allow both IPv4 and IPv6 addresses to invoke your domain. We recommend that you set the IP address type to dualstack to alleviate IP space exhaustion or for your security posture. For more information about the benefits of a dualstack IP address type, see [IPv6 on AWS](#).

Considerations for IP address types

The following considerations might impact your use of IP address types.

- The default IP address type for API Gateway custom domain names is IPv4.
- Your custom domain name doesn't need to have the same IP address type for all APIs mapped to it. If you disable your default API endpoint, this might affect how callers can invoke your API.

Change the IP address type of a custom domain name

You can change the IP address type by updating the domain's endpoint configuration. You can update the domain's endpoint configuration by using the AWS Management Console, the AWS CLI, CloudFormation, or an AWS SDK.

AWS Management Console

To change the IP address type of a custom domain name

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose a public custom domain name.
3. Choose **Endpoint configuration**.
4. For IP address type, select either **IPv4** or **Dualstack**.
5. Choose **Save**.

AWS CLI

The following [update-domain-name](#) command updates an API to have an IP address type of dualstack:

```
aws apigatewayv2 update-domain-name \
--domain-name dualstack.example.com \
--domain-name-configurations CertificateArn=arn:aws:acm:us-
east-1:111122223333:certificate/abcd1234-5678-abc,IpAddressType=dualstack
```

The output will look like the following:

```
{
  "ApiMappingSelectionExpression": "$request.basepath",
  "DomainName": "dualstack.example.com",
  "DomainNameConfigurations": [
    {
      "ApiGatewayDomainName": "d-abcd1234.execute-api.us-
east-1.amazonaws.com",
      "CertificateArn": "arn:aws:acm:us-east-1:111122223333:certificate/
abcd1234-5678-abc",
      "DomainNameStatus": "AVAILABLE",
      "EndpointType": "REGIONAL",
      "HostedZoneId": "Z3LQWSYCGH4ADY",
```

```
        "SecurityPolicy": "TLS_1_2",
        "IpAddressType": "dualstack"
    },
],
"Tags": {}
}
```

Protect your HTTP APIs in API Gateway

API Gateway provides a number of ways to protect your API from certain threats, like malicious users or spikes in traffic. You can protect your API using strategies like setting throttling targets, and enabling mutual TLS. In this section you can learn how to enable these capabilities using API Gateway.

Topics

- [Throttle requests to your HTTP APIs for better throughput in API Gateway](#)
- [How to turn on mutual TLS authentication for your HTTP APIs in API Gateway](#)

Throttle requests to your HTTP APIs for better throughput in API Gateway

You can configure throttling for your APIs to help protect them from being overwhelmed by too many requests. Throttles are applied on a best-effort basis and should be thought of as targets rather than guaranteed request ceilings.

API Gateway throttles requests to your API using the token bucket algorithm, where a token counts for a request. Specifically, API Gateway examines the rate and a burst of request submissions against all APIs in your account, per Region. In the token bucket algorithm, a burst can allow predefined overrun of those limits, but other factors can also cause limits to be overrun in some cases.

When request submissions exceed the steady-state request rate and burst limits, API Gateway begins to throttle requests. Clients may receive 429 Too Many Requests error responses at this point. Upon catching such exceptions, the client can resubmit the failed requests in a way that is rate limiting.

As an API developer, you can set the target limits for individual API stages or routes to improve overall performance across all APIs in your account.

Account-level throttling per Region

By default, API Gateway limits the steady-state requests per second (RPS) across all APIs within an AWS account, per Region. It also limits the burst (that is, the maximum bucket size) across all APIs within an AWS account, per Region. In API Gateway, the burst limit represents the target maximum number of concurrent request submissions that API Gateway will fulfill before returning 429 Too Many Requests error responses. For more information on throttling quotas, see [Quotas and important notes](#).

Per-account limits are applied to all APIs in an account in a specified Region. The account-level rate limit can be increased upon request - higher limits are possible with APIs that have shorter timeouts and smaller payloads. To request an increase of account-level throttling limits per Region, contact the [AWS Support Center](#). For more information, see [Quotas and important notes](#). Note that these limits can't be higher than the AWS throttling limits.

Route-level throttling

You can set route-level throttling to override the account-level request throttling limits for a specific stage or for individual routes in your API. The default route throttling limits can't exceed account-level rate limits.

You can configure route-level throttling by using the AWS CLI. The following [update-stage](#) command configures custom throttling for the specified stage and route of an API:

```
aws apigatewayv2 update-stage \
--api-id a1b2c3d4 \
--stage-name dev \
--route-settings '{
  "GET /pets": {
    "ThrottlingBurstLimit": 100,
    "ThrottlingRateLimit": 2000
  }
}'
```

How to turn on mutual TLS authentication for your HTTP APIs in API Gateway

Mutual TLS authentication requires two-way authentication between the client and the server. With mutual TLS, clients must present X.509 certificates to verify their identity to access your API. Mutual TLS is a common requirement for Internet of Things (IoT) and business-to-business applications.

You can use mutual TLS along with other [authorization and authentication operations](#) that API Gateway supports. API Gateway forwards the certificates that clients provide to Lambda authorizers and to backend integrations.

Important

By default, clients can invoke your API by using the `execute-api` endpoint that API Gateway generates for your API. To ensure that clients can access your API only by using a custom domain name with mutual TLS, disable the default `execute-api` endpoint. To learn more, see [the section called “Disable the default endpoint”](#).

Prerequisites for mutual TLS

To configure mutual TLS you need:

- A custom domain name
- At least one certificate configured in AWS Certificate Manager for your custom domain name
- A truststore configured and uploaded to Amazon S3

Custom domain names

To enable mutual TLS for a HTTP API, you must configure a custom domain name for your API. You can enable mutual TLS for a custom domain name, and then provide the custom domain name to clients. To access an API by using a custom domain name that has mutual TLS enabled, clients must present certificates that you trust in API requests. You can find more information at [the section called “Custom domain names”](#).

Using AWS Certificate Manager issued certificates

You can request a publicly trusted certificate directly from ACM or import public or self-signed certificates. To setup a certificate in ACM, go to [ACM](#). If you would like to import a certificate, continue reading in the following section.

Using an imported or AWS Private Certificate Authority certificate

To use a certificate imported into ACM or a certificate from AWS Private Certificate Authority with mutual TLS, API Gateway needs an `ownershipVerificationCertificate` issued

by ACM. This ownership certificate is only used to verify that you have permissions to use the domain name. It is not used for the TLS handshake. If you don't already have a ownershipVerificationCertificate, go to <https://console.aws.amazon.com/acm/> to set one up.

You will need to keep this certificate valid for the lifetime of your domain name. If a certificate expires and auto-renew fails, all updates to the domain name will be locked. You will need to update the ownershipVerificationCertificateArn with a valid ownershipVerificationCertificate before you can make any other changes. The ownershipVerificationCertificate cannot be used as a server certificate for another mutual TLS domain in API Gateway. If a certificate is directly re-imported into ACM, the issuer must stay the same.

Configuring your truststore

Truststores are text files with a .pem file extension. They are a trusted list of certificates from Certificate Authorities. To use mutual TLS, create a truststore of X.509 certificates that you trust to access your API.

You must include the complete chain of trust, starting from the issuing CA certificate, up to the root CA certificate, in your truststore. API Gateway accepts client certificates issued by any CA present in the chain of trust. The certificates can be from public or private certificate authorities. Certificates can have a maximum chain length of four. You can also provide self-signed certificates. The following hashing algorithms are supported in the truststore:

- SHA-256 or stronger
- RSA-2048 or stronger
- ECDSA-256 or stronger

API Gateway validates a number of certificate properties. You can use Lambda authorizers to perform additional checks when a client invokes an API, including checking whether a certificate has been revoked. API Gateway validates the following properties:

Validation	Description
X.509 syntax	The certificate must meet X.509 syntax requirements.

Validation	Description
Integrity	The certificate's content must not have been altered from that signed by the certificate authority from the truststore.
Validity	The certificate's validity period must be current.
Name chaining / key chaining	The names and subjects of certificates must form an unbroken chain. Certificates can have a maximum chain length of four.

Upload the truststore to an Amazon S3 bucket in a single file

Example certificates.pem

```
-----BEGIN CERTIFICATE-----
<Certificate contents>
-----END CERTIFICATE-----
-----BEGIN CERTIFICATE-----
<Certificate contents>
-----END CERTIFICATE-----
-----BEGIN CERTIFICATE-----
<Certificate contents>
-----END CERTIFICATE-----
...
...
```

The following [cp](#) AWS CLI command uploads certificates.pem to your Amazon S3 bucket:

```
aws s3 cp certificates.pem s3://bucket-name
```

Configuring mutual TLS for a custom domain name

To configure mutual TLS for a HTTP API, you must use a Regional custom domain name for your API, with a minimum TLS version of 1.2. To learn more about creating and configuring a custom domain name, see [the section called “Set up a Regional custom domain name”](#).

Note

Mutual TLS isn't supported for private APIs.

After you've uploaded your truststore to Amazon S3, you can configure your custom domain name to use mutual TLS. The following [create-domain-name](#) creates a custom domain name with mutual TLS:

```
aws apigatewayv2 create-domain-name \
--domain-name api.example.com \
--domain-name-configurations CertificateArn=arn:aws:acm:us-west-2:123456789012:certificate/123456789012-1234-1234-1234-12345678 \
--mutual-tls-authentication TruststoreUri=s3://bucket-name/key-name
```

After you create the domain name, you must configure DNS records and basepath mappings for API operations. To learn more, see [Set up a Regional custom domain name in API Gateway](#).

Invoke an API by using a custom domain name that requires mutual TLS

To invoke an API with mutual TLS enabled, clients must present a trusted certificate in the API request. When a client attempts to invoke your API, API Gateway looks for the client certificate's issuer in your truststore. For API Gateway to proceed with the request, the certificate's issuer and the complete chain of trust up to the root CA certificate must be in your truststore.

The following example curl command sends a request to *api.example.com*, that includes *my-cert.pem* in the request. *my-key.key* is the private key for the certificate.

```
curl -v --key ./my-key.key --cert ./my-cert.pem api.example.com
```

Your API is invoked only if your truststore trusts the certificate. The following conditions will cause API Gateway to fail the TLS handshake and deny the request with a 403 status code. If your certificate:

- isn't trusted
- is expired
- doesn't use a supported algorithm

Note

API Gateway doesn't verify if a certificate has been revoked.

Updating your truststore

To update the certificates in your truststore, upload a new certificate bundle to Amazon S3. Then, you can update your custom domain name to use the updated certificate.

Use [Amazon S3 versioning](#) to maintain multiple versions of your truststore. When you update your custom domain name to use a new truststore version, API Gateway returns warnings if certificates are invalid.

API Gateway produces certificate warnings only when you update your domain name. API Gateway doesn't notify you if a previously uploaded certificate expires.

The following [update-domain-name](#) command updates a custom domain name to use a new truststore version:

```
aws apigatewayv2 update-domain-name \
  --domain-name api.example.com \
  --domain-name-configurations CertificateArn=arn:aws:acm:us-west-2:123456789012:certificate/123456789012-1234-1234-1234-12345678 \
  --mutual-tls-authentication TruststoreVersion='abcdef123'
```

Disable mutual TLS

To disable mutual TLS for a custom domain name, remove the truststore from your custom domain name, as shown in the following command.

The following [update-domain-name](#) command updates a custom domain name to remove the truststore from your custom domain name:

```
aws apigatewayv2 update-domain-name \
  --domain-name api.example.com \
  --domain-name-configurations CertificateArn=arn:aws:acm:us-west-2:123456789012:certificate/123456789012-1234-1234-1234-12345678 \
  --mutual-tls-authentication TruststoreUri=''
```

Troubleshoot mutual TLS for your HTTP API

The following provides troubleshooting advice for errors and issues that you might encounter when turning on mutual TLS.

Troubleshooting certificate warnings

When creating a custom domain name with mutual TLS, API Gateway returns warnings if certificates in the truststore are not valid. This can also occur when updating a custom domain name to use a new truststore. The warnings indicate the issue with the certificate and the subject of the certificate that produced the warning. Mutual TLS is still enabled for your API, but some clients might not be able to access your API.

You'll need to decode the certificates in your truststore in order to identify which certificate produced the warning. You can use tools such as `openssl` to decode the certificates and identify their subjects.

The following command displays the contents of a certificate, including its subject:

```
openssl x509 -in certificate.crt -text -noout
```

Update or remove the certificates that produced warnings, and then upload a new truststore to Amazon S3. After uploading the new truststore, update your custom domain name to use the new truststore.

Troubleshooting domain name conflicts

The error "The certificate subject <certSubject> conflicts with an existing certificate from a different issuer." means multiple Certificate Authorities have issued a certificate for this domain. For each subject in the certificate, there can only be one issuer in API Gateway for mutual TLS domains. You will need to get all of your certificates for that subject through a single issuer. If the problem is with a certificate you don't have control of but you can prove ownership of the domain name, [contact Support](#) to open a ticket.

Troubleshooting domain name status messages

PENDING_CERTIFICATE_REIMPORT: This means you reimported a certificate to ACM and it failed validation because the new certificate has a SAN (subject alternative name) that is not covered by the `ownershipVerificationCertificate` or the subject or SANs in the certificate don't

cover the domain name. Something might be configured incorrectly or an invalid certificate was imported. You need to reimport a valid certificate into ACM. For more information about validation see [Validating domain ownership](#).

PENDING_OWNERSHIP_VERIFICATION: This means your previously verified certificate has expired and ACM was unable to auto-renew it. You will need to renew the certificate or request a new certificate. More information about certificate renewal can be found at [ACM's troubleshooting managed certificate renewal](#) guide.

Monitor HTTP APIs in API Gateway

You can use CloudWatch metrics and CloudWatch Logs to monitor HTTP APIs. By combining logs and metrics, you can log errors and monitor your API's performance.

Note

API Gateway might not generate logs and metrics in the following cases:

- 413 Request Entity Too Large errors
- Excessive 429 Too Many Requests errors
- 400 series errors from requests sent to a custom domain that has no API mapping
- 500 series errors caused by internal failures

Topics

- [Monitor CloudWatch metrics for HTTP APIs in API Gateway](#)
- [Configure logging for HTTP APIs in API Gateway](#)

Monitor CloudWatch metrics for HTTP APIs in API Gateway

You can monitor API execution by using CloudWatch, which collects and processes raw data from API Gateway into readable, near-real-time metrics. These statistics are recorded for a period of 15 months so you can access historical information and gain a better perspective on how your web application or service is performing. By default, API Gateway metric data is automatically sent to CloudWatch in one-minute periods. To monitor your metrics, create a CloudWatch dashboard for your API. For more information about how to create a CloudWatch dashboard, see [Creating a](#)

[CloudWatch dashboard](#) in the *Amazon CloudWatch User Guide*. For more information, see [What Is Amazon CloudWatch?](#) in the *Amazon CloudWatch User Guide*.

The following metrics are supported for HTTP APIs. You can also enable detailed metrics to write route-level metrics to Amazon CloudWatch.

Metric	Description
4xx	The number of client-side errors captured in a given period.
5xx	The number of server-side errors captured in a given period.
Count	The total number API requests in a given period.
IntegrationLatency	The time between when API Gateway relays a request to the backend and when it receives a response from the backend.
Latency	The time between when API Gateway receives a request from a client and when it returns a response to the client. The latency includes the integration latency and other API Gateway overhead.
DataProcessed	The amount of data processed in bytes.

You can use the dimensions in the following table to filter API Gateway metrics.

Dimension	Description
Apild	Filters API Gateway metrics for an API with the specified API ID.
Apild, Stage	Filters API Gateway metrics for an API stage with the specified API ID and stage ID.
Apild, Method, Resource, Stage	<p>Filters API Gateway metrics for an API method with the specified API ID, stage ID, resource path, and route ID.</p> <p>API Gateway will not send these metrics unless you have explicitly enabled detailed CloudWatch metrics. You can do this by calling the UpdateStage action of the API Gateway V2 REST API to update the <code>detailedMetricsEnabled</code> property to true. Alternatively, you can call the update-stage AWS CLI command to update the <code>DetailedMetricsEnabled</code> property to true. Enabling such metrics will incur additional charges to your account. For pricing information, see Amazon CloudWatch Pricing.</p>

Configure logging for HTTP APIs in API Gateway

You can turn on logging to write logs to CloudWatch Logs. You can use [logging variables](#) to customize the content of your logs.

To improve your security posture, we recommend that you write logs to CloudWatch Logs for all stages of your HTTP API. You might need to do this to comply with various compliance frameworks. For more information, see [Amazon API Gateway controls](#) in the *AWS Security Hub User Guide*.

To turn on logging for an HTTP API, you must do the following.

1. Ensure that your user has the required permissions to activate logging.
2. Create a CloudWatch Logs log group.
3. Provide the ARN of the CloudWatch Logs log group for a stage of your API.

Permissions to activate logging

To turn on logging for an API, your user must have the following permissions.

Example

JSON

```
{  
    "Version": "2012-10-17",  
    "Statement": [  
        {  
            "Effect": "Allow",  
            "Action": [  
                "logs:DescribeLogGroups",  
                "logs:DescribeLogStreams",  
                "logs:GetLogEvents",  
                "logs:FilterLogEvents"  
            ],  
            "Resource": "arn:aws:logs:us-east-2:123456789012:log-group:/*"  
        },  
        {  
            "Effect": "Allow",  
            "Action": [  
                "logs:PutLogEvents"  
            ]  
        }  
    ]  
}
```

```
        "logs:CreateLogDelivery",
        "logs:PutResourcePolicy",
        "logs:UpdateLogDelivery",
        "logs>DeleteLogDelivery",
        "logs>CreateLogGroup",
        "logs:DescribeResourcePolicies",
        "logs:GetLogDelivery",
        "logs>ListLogDeliveries"
    ],
    "Resource": "*"
}
]
```

Create a log group and activate logging for HTTP APIs

You can create a log group and activate access logging using the AWS Management Console or the AWS CLI.

AWS Management Console

1. Create a log group.
To learn how to create a log group using the console, see [Create a Log Group in Amazon CloudWatch Logs User Guide](#).
2. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
3. Choose an HTTP API.
4. Under the **Monitor** tab in the primary navigation panel, choose **Logging**.
5. Select a stage to activate logging and choose **Select**.
6. Choose **Edit** to activate access logging.
7. Turn on **Access logging**, enter a CloudWatch Logs, and select a log format.
8. Choose **Save**.

AWS CLI

The following [create-log-group](#) command creates a log group:

```
aws logs create-log-group --log-group-name my-log-group
```

You need the Amazon Resource Name (ARN) for your log group to turn on logging. The ARN format is `arn:aws:logs:region:account-id:log-group:log-group-name`.

The following [update-stage](#) command turns on logging for the `$default` stage of an HTTP API:

```
aws apigatewayv2 update-stage --api-id abcdef \  
  --stage-name '$default' \  
  --access-log-settings '{"DestinationArn": "arn:aws:logs:region:account-id:log-group:log-group-name", "Format": "$context.identity.sourceIp - -  
[$context.requestTime] \"$context.httpMethod $context.routeKey $context.protocol\"  
$context.status $context.responseLength $context.requestId"}'
```

Example log formats

Examples of some common access log formats are available in the API Gateway console and are listed as follows.

- CLF ([Common Log Format](#)):

```
$context.identity.sourceIp - - [$context.requestTime] "$context.httpMethod  
$context.routeKey $context.protocol" $context.status $context.responseLength  
$context.requestId $context.extendedRequestId
```

- JSON:

```
{ "requestId": "$context.requestId", "ip": "$context.identity.sourceIp",  
"requestTime": "$context.requestTime",  
"httpMethod": "$context.httpMethod", "routeKey": "$context.routeKey",  
"status": "$context.status", "protocol": "$context.protocol",  
"responseLength": "$context.responseLength", "extendedRequestId":  
"$context.extendedRequestId" }
```

- XML:

```
<request id="$context.requestId"> <ip>$context.identity.sourceIp</ip> <requestTime>  
$context.requestTime</requestTime> <httpMethod>$context.httpMethod</httpMethod>  
<routeKey>$context.routeKey</routeKey> <status>$context.status</status> <protocol>
```

```
$context.protocol</protocol> <responseLength>$context.responseLength</responseLength>
<extendedRequestId>$context.extendedRequestId</extendedRequestId> </request>
```

- CSV (comma-separated values):

```
$context.identity.sourceIp,$context.requestTime,$context.httpMethod,
$context.routeKey,$context.protocol,$context.status,$context.responseLength,
$context.requestId,$context.extendedRequestId
```

Customize HTTP API access logs

You can use the following variables to customize HTTP API access logs. To learn more about access logs for HTTP APIs, see [Configure logging for HTTP APIs in API Gateway](#).

Parameter	Description
<code>\$context.accountId</code>	The API owner's AWS account ID.
<code>\$context.apiId</code>	The identifier API Gateway assigns to your API.
<code>\$context.authorizer.claims. property</code>	A property of the claims returned from the JSON Web Token (JWT) after the method caller is successfully authenticated, such as <code>\$context.authorizer.claims.username</code> . For more information, see Control access to HTTP APIs with JWT authorizers in API Gateway .
<code>\$context.authorizer.error</code>	The error message returned from an authorizer.
<code>\$context.authorizer. <i>property</i></code>	The value of the specified key-value pair of the context map returned from an

 **Note**

Calling `$context.authorizer.claims` returns null.

Parameter	Description
	<p>API Gateway Lambda authorizer function. For example, if the authorizer returns the following context map:</p> <pre data-bbox="850 403 1132 593"> "context" : { "key": "value", "numKey": 1, "boolKey": true } </pre> <p>calling <code>\$context.authorizer.key</code> returns the "value" string, calling <code>\$context.authorizer.numKey</code> returns the 1, and calling <code>\$context.authorizer.boolKey</code> returns true.</p>
\$context.awsEndpointRequestId	The AWS endpoint's request ID from the <code>x-amz-request-id</code> or <code>x-amzn-requestId</code> header.
\$context.awsEndpointRequestId2	The AWS endpoint's request ID from the <code>x-amz-id-2</code> header.
\$context.customDomain.basePathMatched	The path for an API mapping that an incoming request matched. Applicable when a client uses a custom domain name to access an API. For example if a client sends a request to <code>https://api.example.com/v1/orders/1234</code> , and the request matches the API mapping with the path <code>v1/orders</code> , the value is <code>v1/orders</code> . To learn more, see the section called "API mappings" .
\$context.dataProcessed	The amount of data processed in bytes.

Parameter	Description
\$context.domainName	The full domain name used to invoke the API. This should be the same as the incoming Host header.
\$context.domainPrefix	The first label of the \$context.domainName .
\$context.error.message	A string that contains an API Gateway error message.
\$context.error.messageString	The quoted value of \$context.error.message , namely "\$context.error.message" .
\$context.error.responseType	A type of <code>GatewayResponse</code> . For more information, see the section called "Metrics" and the section called "Setting up gateway responses to customize error responses" .
\$context.extendedRequestId	Equivalent to \$context.requestId .
\$context.httpMethod	The HTTP method used. Valid values include: DELETE, GET, HEAD, OPTIONS, PATCH, POST, and PUT.
\$context.identity.accountId	The AWS account ID associated with the request. Supported for routes that use IAM authorization.
\$context.identity.caller	The principal identifier of the caller that signed the request. Supported for routes that use IAM authorization.

Parameter	Description
\$context.identity.cognitoAuthenticationProvider	<p>A comma-separated list of all the Amazon Cognito authentication providers used by the caller making the request. Available only if the request was signed with Amazon Cognito credentials.</p> <p>For example, for an identity from an Amazon Cognito user pool, <code>cognito-idp.<i>region</i>.amazonaws.com/ <i>user_pool_id</i></code>, <code>cognito-idp.<i>region</i>.amazonaws.com/ <i>user_pool_id</i> :CognitoSignIn: <i>token subject claim</i></code></p> <p>For information about the available Amazon Cognito authentication providers, see Using Federated Identities in the Amazon Cognito Developer Guide.</p>
\$context.identity.cognitoAuthenticationType	<p>The Amazon Cognito authentication type of the caller making the request. Available only if the request was signed with Amazon Cognito credentials. Possible values include <code>authenticated</code> for authenticated identities and <code>unauthenticated</code> for unauthenticated identities.</p>
\$context.identity.cognitoIdentityId	<p>The Amazon Cognito identity ID of the caller making the request. Available only if the request was signed with Amazon Cognito credentials.</p>
\$context.identity.cognitoIdentityPoolId	<p>The Amazon Cognito identity pool ID of the caller making the request. Available only if the request was signed with Amazon Cognito credentials.</p>

Parameter	Description
\$context.identity.principalOrgId	The AWS organization ID . Supported for routes that use IAM authorization.
\$context.identity.clientCert.clientCertPem	The PEM-encoded client certificate that the client presented during mutual TLS authentication. Present when a client accesses an API by using a custom domain name that has mutual TLS enabled.
\$context.identity.clientCert.subjectDN	The distinguished name of the subject of the certificate that a client presents. Present when a client accesses an API by using a custom domain name that has mutual TLS enabled.
\$context.identity.clientCert.issuerDN	The distinguished name of the issuer of the certificate that a client presents. Present when a client accesses an API by using a custom domain name that has mutual TLS enabled.
\$context.identity.clientCert.serialNumber	The serial number of the certificate. Present when a client accesses an API by using a custom domain name that has mutual TLS enabled.
\$context.identity.clientCert.validity.notBefore	The date before which the certificate is invalid. Present when a client accesses an API by using a custom domain name that has mutual TLS enabled.
\$context.identity.clientCert.validity.notAfter	The date after which the certificate is invalid. Present when a client accesses an API by using a custom domain name that has mutual TLS enabled.

Parameter	Description
\$context.identity.sourceIp	The source IP address of the immediate TCP connection making the request to API Gateway endpoint.
\$context.identity.user	The principal identifier of the user that will be authorized against resource access. Supported for routes that use IAM authorization.
\$context.identity.userAgent	The User-Agent header of the API caller.
\$context.identity.userArn	The Amazon Resource Name (ARN) of the effective user identified after authentication. Supported for routes that use IAM authorization. For more information, see https://docs.aws.amazon.com/IAM/latest/UserGuide/id_users.html .
\$context.integration.error	The error message returned from an integration. Equivalent to \$context.integrationErrorMessage .
\$context.integration.integrationStatus	For Lambda proxy integration, the status code returned from AWS Lambda, not from the backend Lambda function code.
\$context.integration.latency	The integration latency in ms. Equivalent to \$context.integrationLatency .
\$context.integration.requestId	The AWS endpoint's request ID. Equivalent to \$context.awsEndpointRequestId .
\$context.integration.status	The status code returned from an integration. For Lambda proxy integrations, this is the status code that your Lambda function code returns.

Parameter	Description
\$context.integrationErrorMessage	A string that contains an integration error message.
\$context.integrationLatency	The integration latency in ms.
\$context.integrationStatus	For Lambda proxy integration, this parameter represents the status code returned from AWS Lambda, not from the backend Lambda function.
\$context.path	The request path. For example, /{stage}/root/child .
\$context.protocol	The request protocol, for example, HTTP/1.1.
 Note API Gateway APIs can accept HTTP/2 requests, but API Gateway sends requests to backend integrations using HTTP/1.1. As a result, the request protocol is logged as HTTP/1.1 even if a client sends a request that uses HTTP/2.	
\$context.requestId	The ID that API Gateway assigns to the API request.
\$context.requestTime	The CLF -formatted request time (dd/MMM/yy yy:HH:mm:ss +-hhmm).
\$context.requestTimeEpoch	The Epoch -formatted request time.
\$context.responseLatency	The response latency in ms.
\$context.responseLength	The response payload length in bytes.

Parameter	Description
<code>\$context.routeKey</code>	The route key of the API request, for example /pets.
<code>\$context.stage</code>	The deployment stage of the API request (for example, beta or prod).
<code>\$context.status</code>	The method response status.

Troubleshooting issues with HTTP APIs in API Gateway

The following topics provide troubleshooting advice for errors and issues that you might encounter when using HTTP APIs.

Topics

- [Troubleshooting issues with HTTP API Lambda integrations](#)
- [Troubleshooting issues with HTTP API JWT authorizers](#)

Troubleshooting issues with HTTP API Lambda integrations

The following provides troubleshooting advice for errors and issues that you might encounter when using [AWS Lambda integrations](#) with HTTP APIs.

Issue: My API with a Lambda integration returns {"message": "Internal Server Error"}

To troubleshoot the internal server error, add the `$context.integrationErrorMessage` [logging variable](#) to your log format, and view your HTTP API's logs. To achieve this, do the following:

To create a log group by using the AWS Management Console

1. Open the CloudWatch console at <https://console.aws.amazon.com/cloudwatch/>.
2. Choose **Log groups**.
3. Choose **Create log group**.

4. Enter a log group name, and then choose **Create**.
5. Note the Amazon Resource Name (ARN) for your log group. The ARN format is `arn:aws:logs:region:account-id:log-group:log-group-name`. You need the log group ARN to enable access logging for your HTTP API.

To add the `$context.integrationErrorMessage` logging variable

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose your HTTP API.
3. Under **Monitor**, choose **Logging**.
4. Select a stage of your API.
5. Choose **Edit**, and then enable access logging.
6. For **Log destination**, enter the ARN of the log group that you created in the previous step.
7. For **Log format**, choose **CLF**. API Gateway creates an example log format.
8. Add `$context.integrationErrorMessage` to the end of the log format.
9. Choose **Save**.

To view your API's logs

1. Generate logs. Use a browser or `curl` to invoke your API.

```
$curl https://api-id.execute-api.us-west-2.amazonaws.com/route
```

2. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
3. Choose your HTTP API.
4. Under **Monitor**, choose **Logging**.
5. Select the stage of your API for which you enabled logging.
6. Choose **View logs in CloudWatch**.
7. Choose the latest log stream to view your HTTP API's logs.
8. Your log entry should look similar to the following:

Log events		C	Actions ▾	Create Metric Filter				
Filter events		Clear	1m	30m	1h	12h	custom	grid
▶	Timestamp	Message						
There are older events to load. Load more.								
▼	2020-05-12T17:10:49.435-07:00	192.0.2.1 - - [13/May/2020:00:10:49 +0000] "GET \$default HTTP/1.1" 500 35 McYpFnSrPHcEJ3g= The IAM role configured on the integration or API Gateway doesn't have permissions to call the integration. Check the permissions and try again.						
		>Loading newer events						

Because we added `$context.integrationErrorMessage` to the log format, we see an error message in our logs that summarizes the problem.

Your logs might include a different error message that indicates that there's a problem with your Lambda function code. In that case, check your Lambda function code, and verify that your Lambda function returns a response in the [required format](#). If your logs don't include an error message, add `$context.error.message` and `$context.error.responseType` to your log format for more information to help troubleshoot.

In this case, the logs show that API Gateway didn't have the required permissions to invoke the Lambda function.

When you create a Lambda integration in the API Gateway console, API Gateway automatically configures permissions to invoke the Lambda function. When you create a Lambda integration by using the AWS CLI, CloudFormation, or an SDK, you must grant permissions for API Gateway to invoke the function. The following [add-permission](#) commands grant permission for different HTTP API routes to invoke a Lambda function.

Example Example – For the `$default` stage and `$default` route of an HTTP API

```
aws lambda add-permission \
--function-name my-function \
--statement-id apigateway-invoke-permissions \
--action lambda:InvokeFunction \
--principal apigateway.amazonaws.com \
```

```
--source-arn "arn:aws:execute-api:us-west-2:123456789012:api-id/\$default/\$default"
```

Example Example – For the prod stage and test route of an HTTP API

```
aws lambda add-permission \
--function-name my-function \
--statement-id apigateway-invoke-permissions \
--action lambda:InvokeFunction \
--principal apigateway.amazonaws.com \
--source-arn "arn:aws:execute-api:us-west-2:123456789012:api-id/prod/*/test"
```

Confirm the function policy in the **Permissions** tab of the Lambda console.

Try invoking your API again. You should see your Lambda function's response.

Troubleshooting issues with HTTP API JWT authorizers

The following provides troubleshooting advice for errors and issues that you might encounter when using JSON Web Token (JWT) authorizers with HTTP APIs.

Issue: My API returns 401 {"message": "Unauthorized"}

Check the `www-authenticate` header in the response from the API.

The following command uses `curl` to send a request to an API with a JWT authorizer that uses `$request.header.Authorization` as its identity source.

```
$curl -v -H "Authorization: token" https://api-id.execute-api.us-west-2.amazonaws.com/route
```

The response from the API includes a `www-authenticate` header.

```
...
< HTTP/1.1 401 Unauthorized
< Date: Wed, 13 May 2020 04:07:30 GMT
< Content-Length: 26
< Connection: keep-alive
< www-authenticate: Bearer scope="" error="invalid_token" error_description="the token does not have a valid audience"
< apigw-requestid: Mc7UVioPPHcEKPA=
```

```
<
* Connection #0 to host api-id.execute-api.us-west-2.amazonaws.com left intact
{"message":"Unauthorized"}}
```

In this case, the `www-authenticate` header shows that the token wasn't issued for a valid audience. For API Gateway to authorize a request, the JWT's `aud` or `client_id` claim must match one of the audience entries that's configured for the authorizer. API Gateway validates `client_id` only if `aud` is not present. When both `aud` and `client_id` are present, API Gateway evaluates `aud`.

You can also decode a JWT and verify that it matches the issuer, audience, and scopes that your API requires. The website [jwt.io](#) can debug JWTs in the browser. The OpenID Foundation maintains a [list of libraries for working with JWTs](#).

To learn more about JWT authorizers, see [Control access to HTTP APIs with JWT authorizers in API Gateway](#).

API Gateway WebSocket APIs

A WebSocket API in API Gateway is a collection of WebSocket routes that are integrated with backend HTTP endpoints, Lambda functions, or other AWS services. You can use API Gateway features to help you with all aspects of the API lifecycle, from creation through monitoring your production APIs.

API Gateway WebSocket APIs are bidirectional. A client can send messages to a service, and services can independently send messages to clients. This bidirectional behavior enables richer client/service interactions because services can push data to clients without requiring clients to make an explicit request. WebSocket APIs are often used in real-time applications such as chat applications, collaboration platforms, multiplayer games, and financial trading platforms.

For an example app to get started with, see [Tutorial: Create a WebSocket chat app with a WebSocket API, Lambda and DynamoDB](#).

In this section, you can learn how to develop, publish, protect, and monitor your WebSocket APIs using API Gateway.

Topics

- [Overview of WebSocket APIs in API Gateway](#)
- [Develop WebSocket APIs in API Gateway](#)
- [Publish WebSocket APIs for customers to invoke](#)
- [Protect your WebSocket APIs in API Gateway](#)
- [Monitor WebSocket APIs in API Gateway](#)

Overview of WebSocket APIs in API Gateway

In API Gateway you can create a WebSocket API as a stateful frontend for an AWS service (such as Lambda or DynamoDB) or for an HTTP endpoint. The WebSocket API invokes your backend based on the content of the messages it receives from client apps.

Unlike a REST API, which receives and responds to requests, a WebSocket API supports two-way communication between client apps and your backend. The backend can send callback messages to connected clients.

In your WebSocket API, incoming JSON messages are directed to backend integrations based on routes that you configure. (Non-JSON messages are directed to a \$default route that you configure.)

A *route* includes a *route key*, which is the value that is expected once a *route selection expression* is evaluated. The `routeSelectionExpression` is an attribute defined at the API level. It specifies a JSON property that is expected to be present in the message payload. For more information about route selection expressions, see [the section called “”](#).

For example, if your JSON messages contain an `action` property, and you want to perform different actions based on this property, your route selection expression might be `${request.body.action}`. Your routing table would specify which action to perform by matching the value of the `action` property against the custom route key values that you have defined in the table.

Use routes for a WebSocket API

There are three predefined routes that can be used: `$connect`, `$disconnect`, and `$default`. In addition, you can create custom routes.

- API Gateway calls the `$connect` route when a persistent connection between the client and a WebSocket API is being initiated.
- API Gateway calls the `$disconnect` route when the client or the server disconnects from the API.
- API Gateway calls a custom route after the route selection expression is evaluated against the message if a matching route is found; the match determines which integration is invoked.
- API Gateway calls the `$default` route if the route selection expression cannot be evaluated against the message or if no matching route is found.

For more information about the `$connect` and `$disconnect` routes, see [the section called “Manage connected users and client apps”](#).

For more information about the `$default` route and custom routes, see [the section called “Invoke your backend integration”](#).

Send data to connected client apps

Backend services can send data to connected client apps. You can send data by doing the following:

- Use an integration to send a response, which is returned to the client by a route response that you have defined.
- You can use the @connections API to send a POST request. For more information, see [the section called “Use @connections commands in your backend service”](#).

WebSocket API status codes

API Gateway WebSocket APIs use the following status codes for communication from the server to client as described in the [WebSocket Close Code Number Registry](#):

1001

API Gateway returns this status code when the client is idle for 10 minutes or reaches the maximum 2 hour connection lifetime.

1003

API Gateway returns this status code when an endpoint receives a binary media type. Binary media types aren't supported for WebSocket APIs.

1005

API Gateway returns this status code if the client sends a close frame without a closure code.

1006

API Gateway returns this status code if there is an unexpected closure of the connection, such as the TCP connection closed without a WebSocket close frame.

1008

API Gateway returns this status code when an endpoint receives too many requests from a particular client.

1009

API Gateway returns this status code when an endpoint receives a message that is too big for it to process.

1011

API Gateway returns this status code when there is an internal server error.

1012

API Gateway returns this status code if the service restarts.

Manage connected users and client apps: \$connect and \$disconnect routes

The following section describes how to use the \$connect and \$disconnect routes for your WebSocket API.

Topics

- [The \\$connect route](#)
- [Passing connection information from the \\$connect route](#)
- [The \\$disconnect route](#)

The \$connect route

Client apps connect to your WebSocket API by sending a WebSocket upgrade request. If the request succeeds, the \$connect route is executed while the connection is being established.

Because the WebSocket connection is a stateful connection, you can configure authorization on the \$connect route only. AuthN/AuthZ will be performed only at connection time.

Until execution of the integration associated with the \$connect route is completed, the upgrade request is pending and the actual connection will not be established. If the \$connect request fails (e.g., due to AuthN/AuthZ failure or an integration failure), the connection will not be made.

 **Note**

If authorization fails on \$connect, the connection will not be established, and the client will receive a 401 or 403 response.

Setting up an integration for \$connect is optional. You should consider setting up a \$connect integration if:

- You want to enable clients to specify subprotocols by using the Sec-WebSocket-Protocol field. For example code, see [Set up a \\$connect route that requires a WebSocket subprotocol](#).
- You want to be notified when clients connect.
- You want to throttle connections or control who connects.
- You want your backend to send messages back to clients using a callback URL.
- You want to store each connection ID and other information into a database (for example, Amazon DynamoDB).

Passing connection information from the \$connect route

You can use both proxy and non-proxy integrations to pass information from the \$connect route to a database or other AWS service.

To pass connection information using a proxy integration

You can access the connection information from a Lambda proxy integration in the event. Use another AWS service or AWS Lambda function to post to the connection.

The following Lambda function shows how to use the requestContext object to log the connection ID, domain name, stage name, and query strings.

Node.js

```
export const handler = async(event, context) => {
  const connectId = event["requestContext"]["connectionId"]
  const domainName = event["requestContext"]["domainName"]
  const stageName = event["requestContext"]["stage"]
  const qs = event['queryStringParameters']
  console.log('Connection ID: ', connectId, 'Domain Name: ', domainName, 'Stage
Name: ', stageName, 'Query Strings: ', qs )
  return {"statusCode" : 200}
};
```

Python

```
import json
import logging
logger = logging.getLogger()
logger.setLevel("INFO")
```

```
def lambda_handler(event, context):
    connectId = event["requestContext"]["connectionId"]
    domainName = event["requestContext"]["domainName"]
    stageName = event["requestContext"]["stage"]
    qs = event['queryStringParameters']
    connectionInfo = {
        'Connection ID': connectId,
        'Domain Name': domainName,
        'Stage Name': stageName,
        'Query Strings': qs}
    logging.info(connectionInfo)
    return {"statusCode": 200}
```

To pass connection information using a non-proxy integration

- You can access the connection information with a non-proxy integration. Set up the integration request and provide a WebSocket API request template. The following [Velocity Template Language \(VTL\)](#) mapping template provides an integration request. This request sends the following details to a non-proxy integration:
 - Connection ID
 - Domain name
 - Stage name
 - Path
 - Headers
 - Query strings

This request sends the connection ID, domain name, stage name, paths, headers, and query strings to a non-proxy integration.

```
{
    "connectionId": "$context.connectionId",
    "domain": "$context.domainName",
    "stage": "$context.stage",
    "params": "$input.params()"
}
```

For more information about setting up data transformations, see [the section called “Data transformations”](#).

To complete the integration request, set StatusCode : 200 for the integration response. To learn more about setting up an integration response, see [Set up an integration response using the API Gateway console](#).

The \$disconnect route

The \$disconnect route is executed after the connection is closed.

The connection can be closed by the server or by the client. As the connection is already closed when it is executed, \$disconnect is a best-effort event. API Gateway will try its best to deliver the \$disconnect event to your integration, but it cannot guarantee delivery.

The backend can initiate disconnection by using the @connections API. For more information, see [the section called “Use @connections commands in your backend service”](#).

Invoke your backend integration with the \$default Route and custom routes in API Gateway

The following section describes how to invoke your backend integration using either the \$default route or a custom route for a WebSocket API.

Topics

- [Using routes to process messages](#)
- [The \\$default route](#)
- [Custom routes](#)
- [Using API Gateway WebSocket API integrations to connect to your business logic](#)
- [Important differences between WebSocket APIs and REST APIs](#)

Using routes to process messages

In API Gateway WebSocket APIs, messages can be sent from the client to your backend service and vice versa. Unlike HTTP's request/response model, in WebSocket the backend can send messages to the client without the client taking any action.

Messages can be JSON or non-JSON. However, only JSON messages can be routed to specific integrations based on message content. Non-JSON messages are passed through to the backend by the \$default route.

Note

API Gateway supports message payloads up to 128 KB with a maximum frame size of 32 KB. If a message exceeds 32 KB, you must split it into multiple frames, each 32 KB or smaller. If a larger message (or frame) is received, the connection is closed with code 1009. Currently binary payloads are not supported. If a binary frame is received, the connection is closed with code 1003. However, it is possible to convert binary payloads to text. See [the section called “Binary media types”](#).

With WebSocket APIs in API Gateway, JSON messages can be routed to execute a specific backend service based on message content. When a client sends a message over its WebSocket connection, this results in a *route request* to the WebSocket API. The request will be matched to the route with the corresponding route key in API Gateway. You can set up a route request for a WebSocket API in the API Gateway console, by using the AWS CLI, or by using an AWS SDK.

Note

In the AWS CLI and AWS SDKs, you can create routes before or after you create integrations. Currently the console does not support reuse of integrations, so you must create the route first and then create the integration for that route.

You can configure API Gateway to perform validation on a route request before proceeding with the integration request. If the validation fails, API Gateway fails the request without calling your backend, sends a "Bad request body" gateway response similar to the following to the client, and publishes the validation results in CloudWatch Logs:

```
{"message" : "Bad request body", "connectionId": "{connectionId}", "messageId": "{messageId}"}
```

This reduces unnecessary calls to your backend and lets you focus on the other requirements of your API.

You can also define a route response for your API's routes to enable two-way communication. A route response describes what data will be sent to your client upon completion of a particular route's integration. It is not necessary to define a response for a route if, for example, you want a client to send messages to your backend without receiving a response (one-way communication). However, if you don't provide a route response, API Gateway won't send any information about the result of your integration to your clients.

The \$default route

Every API Gateway WebSocket API can have a `$default` route. This is a special routing value that can be used in the following ways:

- You can use it together with defined route keys, to specify a "fallback" route (for example, a generic mock integration that returns a particular error message) for incoming messages that don't match any of the defined route keys.
- You can use it without any defined route keys, to specify a proxy model that delegates routing to a backend component.
- You can use it to specify a route for non-JSON payloads.

Custom routes

If you want to invoke a specific integration based on message content, you can do so by creating a custom route.

A custom route uses a route key and integration that you specify. When an incoming message contains a JSON property, and that property evaluates to a value that matches the route key value, API Gateway invokes the integration. (For more information, see [the section called “Overview of WebSocket APIs”](#).)

For example, suppose you wanted to create a chat room application. You might start by creating a WebSocket API whose route selection expression is `$request.body.action`. You could then define two routes: `joinroom` and `sendmessage`. A client app might invoke the `joinroom` route by sending a message such as the following:

```
{"action":"joinroom","roomname":"developers"}
```

And it might invoke the `sendmessage` route by sending a message such as the following:

```
{"action": "sendmessage", "message": "Hello everyone"}
```

Using API Gateway WebSocket API integrations to connect to your business logic

After setting up a route for an API Gateway WebSocket API, you must specify the integration you'd like to use. As with a route, which can have a route request and a route response, an integration can have an *integration request* and an *integration response*. An *integration request* contains the information expected by your backend in order to process the request that came from your client. An *integration response* contains the data that your backend returns to API Gateway, and that may be used to construct a message to send to the client (if a route response is defined).

For more information about setting up integrations, see [the section called “Integrations”](#).

Important differences between WebSocket APIs and REST APIs

Integrations for WebSocket APIs are similar to integrations for REST APIs, except for the following differences:

- Currently, in the API Gateway console you must create a route first and then create an integration as that route's target. However, in the API and CLI, you can create routes and integrations independently, in any order.
- You can use a single integration for multiple routes. For example, if you have a set of actions that closely relate to each other, you might want all of those routes to go to a single Lambda function. Rather than defining the details of the integration multiple times, you can specify it once and assign it to each of the related routes.

Note

Currently the console does not support reuse of integrations, so you must create the route first and then create the integration for that route.

In the AWS CLI and AWS SDKs, you can reuse an integration by setting the route's target to a value of "integrations/*{integration-id}*", where *{integration-id}* is the unique ID of the integration to be associated with the route.

- API Gateway provides multiple [selection expressions](#) you can use in your routes and integrations. You don't need to rely on the content type to select an input template or output mapping. As with route selection expressions, you can define a selection expression to be evaluated by

API Gateway to choose the right item. All of them will fall back to the \$default template if a matching template is not found.

- In integration requests, the template selection expression supports `$request.body.<json_path_expression>` and static values.
- In integration responses, the template selection expression supports `$request.body.<json_path_expression>`, `$integration.response.statusCode`, `$integration.response.header.<headerName>`, and static values.

In the HTTP protocol, in which requests and responses are sent synchronously; communication is essentially one-way. In the WebSocket protocol, communication is two-way. Responses are asynchronous and are not necessarily received by the client in the same order as the client's messages were sent. In addition, the backend can send messages to the client.

 **Note**

For a route that is configured to use AWS_PROXY or LAMBDA_PROXY integration, communication is one-way, and API Gateway will not pass the backend response through to the route response automatically. For example, in the case of LAMBDA_PROXY integration, the body that the Lambda function returns will not be returned to the client. If you want the client to receive integration responses, you must define a route response to make two-way communication possible.

WebSocket selection expressions

API Gateway uses selection expressions as a way to evaluate request and response context and produce a key. The key is then used to select from a set of possible values, typically provided by you, the API developer. The exact set of supported variables will vary depending on the particular expression. Each expression is discussed in more detail below.

For all of the expressions, the language follows the same set of rules:

- A variable is prefixed with "\$".
- Curly braces can be used to explicitly define variable boundaries, e.g., `"${request.body.version}-beta"`.
- Multiple variables are supported, but evaluation occurs only once (no recursive evaluation).

- A dollar sign (\$) can be escaped with "\\". This is most useful when defining an expression that maps to the reserved \$default key, e.g., "\\\$default".
- In some cases, a pattern format is required. In this case, the expression should be wrapped with forward slashes ("/"), e.g. "/2\\d\\d/" to match 2XX status codes.

Topics

- [Route response selection expressions](#)
- [API key selection expressions](#)
- [API mapping selection expressions](#)
- [WebSocket selection expression summary](#)

Route response selection expressions

A [route response](#) is used for modeling a response from the backend to the client. For WebSocket APIs, a route response is optional. When defined, it signals to API Gateway that it should return a response to a client upon receiving a WebSocket message.

Evaluation of the *route response selection expression* produces a route response key. Eventually, this key will be used to choose from one of the [RouteResponses](#) associated with the API. However, currently only the \$default key is supported.

API key selection expressions

This expression is evaluated when the service determines the given request should proceed only if the client provides a valid [API key](#).

Currently the only two supported values are \$request.header.x-api-key and \$context.authorizer.usageIdentifierKey.

API mapping selection expressions

This expression is evaluated to determine which API stage is selected when a request is made using a custom domain.

Currently, the only supported value is \$request.basepath.

WebSocket selection expression summary

The following table summarizes the use cases for selection expressions in WebSocket APIs:

Selection expression	Evaluates to key for	Notes	Example use case
Api.RouteSelectionExpression	Route.RouteKey	\$default is supported as a catch-all route.	Route is WebSocket supported as a based on the context of a client request.
Route.ModelSelectionExpression	Key for Route.RequestModels	Optional If provided for non-proxy integration, model validation occurs.	Perform request validation dynamically within the same route.
Integration.Templa	Key for Integration.RequestTemplates	Optional	Manipulate the

Selection expression	Evaluates to key for	Notes	Example use case
teSelectionExpression	<p>May be provided for non-proxy integrations on to the manipulated request. e incoming payloads</p> <p><code> \${request.body.\$Path}</code> and static values are supported.</p> <p><code>\$default</code> is supported as a catch-all.</p>		

Selection expression	Evaluates to key for	Notes	Example use case
Integration.IntegrationResponseSelectionExpression	IntegrationResponse.IntegrationResponseKey	Optional May be provided for non-proxy integration. Acts as a pattern match for error message (from Lambda) or status codes (from HTTP integrations). \$default is required for non-proxy	Manipulate the response from the backend. Choose the action to occur based on the dynamic response message of the backend (e.g., handling certain errors distinctl y).

Selection expression	Evaluates to key for	Notes	Example use case
		integrations to act as the catch-all for successful responses.	

Selection expression	Evaluates to key for	Notes	Example use case
IntegrationResponseTemplateSelectionExpression	Key for <code>IntegrationResponse.Responses[Template]</code> for dynamic non-proxy integration response. \${default} is supported. •	Optional May be for non- proxy integrati on. \$default is suppo rted. •	In some cases, a dynamic property of the integrati on. may dictate different transform ations within the same route and associated integration.

Selection expression	Evaluates to key for	Notes	Example use case
			<p>er.headerName} , \${integration.response.multivalueheader.headerName} , and static values are supported . \$default is supported as a catch-all.</p>

Selection expression	Evaluates to key for	Notes	Example use case
Route.RouteResponseSelectionExpression	RouteResponse.RouteResponseKey	Should be provided to initiate two-way communication for a WebSocket route.	Currently, this value is restricted to \$default only.
RouteResponse.ModeSelectionExpression	Key for RouteResponse.RequestModels	Currently unsupported.	

Develop WebSocket APIs in API Gateway

This section provides details about API Gateway capabilities that you need while you're developing your API Gateway APIs.

As you're developing your API Gateway API, you decide on a number of characteristics of your API. These characteristics depend on the use case of your API. For example, you might want to only allow certain clients to call your API, or you might want it to be available to everyone. You might want an API call to execute a Lambda function, make a database query, or call an application.

Topics

- [Create WebSocket APIs in API Gateway](#)
- [IP address types for WebSocket APIs in API Gateway](#)
- [Create routes for WebSocket APIs in API Gateway](#)
- [Control and manage access to WebSocket APIs in API Gateway](#)
- [Integrations for WebSocket APIs in API Gateway](#)
- [Request validation for WebSocket APIs in API Gateway](#)
- [Data transformations for WebSocket APIs in API Gateway](#)
- [Binary media types for WebSocket APIs in API Gateway](#)
- [Invoke WebSocket APIs](#)

Create WebSocket APIs in API Gateway

You can create a WebSocket API in the API Gateway console, by using the AWS CLI [create-api](#) command, or by using the `CreateApi` command in an AWS SDK. The following procedures show how to create a new WebSocket API.

 **Note**

WebSocket APIs only support TLS 1.2 and TLS 1.3. Earlier TLS versions are not supported.

Create a WebSocket API using AWS CLI commands

The following [create-api](#) command creates an API with the `$request.body.action` route selection expression:

```
aws apigatewayv2 --region us-east-1 create-api --name "myWebSocketApi3" --protocol-type WEBSOCKET --route-selection-expression '$request.body.action'
```

The output looks like the following:

```
{  
    "ApiKeySelectionExpression": "$request.header.x-api-key",  
    "Name": "myWebSocketApi3",  
    "CreatedDate": "2018-11-15T06:23:51Z",  
    "ProtocolType": "WEBSOCKET",  
    "RouteSelectionExpression": "'$request.body.action'",  
    "ApiId": "aabbcdddee"  
}
```

Create a WebSocket API using the API Gateway console

You can create a WebSocket API in the console by choosing the WebSocket protocol and giving the API a name.

Important

Once you have created the API, you cannot change the protocol you have chosen for it. There is no way to convert a WebSocket API into a REST API or vice versa.

To create a WebSocket API using the API Gateway console

1. Sign in to the API Gateway console and choose **Create API**.
2. Under **WebSocket API**, choose **Build**. Only Regional endpoints are supported.
3. For **API name**, enter the name of your API.
4. For **Route selection expression**, enter a value. For example, `$request.body.action`.

For more information about route selection expressions, see [the section called “”](#).

5. Do one of the following:
 - Choose **Create blank API** to create an API with no routes.
 - Choose **Next** to attach routes to your API.

You can attach routes after you create your API.

IP address types for WebSocket APIs in API Gateway

When you create an API, you specify the type of IP addresses that can invoke your API. You can choose IPv4 to resolve IPv4 addresses to invoke your API, or you can choose dualstack to allow

both IPv4 and IPv6 addresses to invoke your API. We recommend that you set the IP address type to dualstack to alleviate IP space exhaustion or for your security posture. For more information about the benefits of a dualstack IP address type, see [IPv6 on AWS](#).

Considerations for IP address types

The following considerations might impact your use of IP address types:

- The default IP address type for all WebSocket APIs is IPv4.
- If you change the IP address type for an existing API from IPv4 to dualstack, confirm that any policies controlling access to your APIs have been updated to account for IPv6 calls. When you change the IP address type, the change takes effect immediately.
- Your API can be mapped to a custom domain name with a different IP address type than your API. If you disable your default API endpoint, this might affect how callers can invoke your API.

Change the IP address type of an WebSocket API

You can change the IP address type by updating the API's configuration. You can update the API's configuration by using the AWS Management Console, the AWS CLI, CloudFormation, or an AWS SDK. If you change the API's IP address type, you don't redeploy your API for the changes to take effect.

AWS Management Console

To change the IP address type of a WebSocket API

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose a WebSocket API.
3. Choose **API settings**, and then choose **Edit**.
4. For IP address type, select either **IPv4** or **Dualstack**.
5. Choose **Save**.

The change to your API's configuration will take effect immediately.

AWS CLI

The following [update-api](#) command updates an API to have an IP address type of dualstack:

```
aws apigatewayv2 update-api \
--api-id abcd1234 \
--ip-address-type dualstack
```

The output will look like the following:

```
{
  "ApiEndpoint": "https://abcd1234.execute-api.us-east-1.amazonaws.com",
  "ApiId": "abcd1234",
  "ApiKeySelectionExpression": "$request.header.x-api-key",
  "CreatedDate": "2025-02-04T22:20:20+00:00",
  "DisableExecuteApiEndpoint": false,
  "Name": "My-WebSocket-API",
  "ProtocolType": "WEBSOCKET",
  "RouteSelectionExpression": "$request.method $request.path",
  "Tags": {},
  "NotificationUris": [],
  "IpAddressType": "dualstack"
}
```

Create routes for WebSocket APIs in API Gateway

In your WebSocket API, incoming JSON messages are directed to backend integrations based on routes that you configure. (Non-JSON messages are directed to a `$default` route that you configure.)

A *route* includes a *route key*, which is the value that is expected once a *route selection expression* is evaluated. The `routeSelectionExpression` is an attribute defined at the API level. It specifies a JSON property that is expected to be present in the message payload. For more information about route selection expressions, see [the section called “”](#).

For example, if your JSON messages contain an `action` property and you want to perform different actions based on this property, your route selection expression might be `${request.body.action}`. Your routing table would specify which action to perform by matching the value of the `action` property against the custom route key values that you have defined in the table.

There are three predefined routes that can be used: `$connect`, `$disconnect`, and `$default`. In addition, you can create custom routes.

- API Gateway calls the `$connect` route when a persistent connection between the client and a WebSocket API is being initiated.
- API Gateway calls the `$disconnect` route when the client or the server disconnects from the API.
- API Gateway calls a custom route after the route selection expression is evaluated against the message if a matching route is found; the match determines which integration is invoked.
- API Gateway calls the `$default` route if the route selection expression cannot be evaluated against the message or if no matching route is found.

Route selection expressions

A *route selection expression* is evaluated when the service is selecting the route to follow for an incoming message. The service uses the route whose `routeKey` exactly matches the evaluated value. If none match and a route with the `$default` route key exists, that route is selected. If no routes match the evaluated value and there is no `$default` route, the service returns an error. For WebSocket-based APIs, the expression should be of the form `$request.body.{path_to_body_element}`.

For example, suppose you are sending the following JSON message:

```
{  
    "service" : "chat",  
    "action" : "join",  
    "data" : {  
        "room" : "room1234"  
    }  
}
```

You might want to select your API's behavior based on the `action` property. In that case, you might define the following route selection expression:

```
$request.body.action
```

In this example, `request.body` refers to your message's JSON payload, and `.action` is a [JSONPath](#) expression. You can use any JSON path expression after `request.body`, but keep in mind that the result will be stringified. For example, if your JSONPath expression returns an array of two elements, that will be presented as the string "[item1, item2]". For this reason, it's a good practice to have your expression evaluate to a value and not an array or an object.

You can simply use a static value, or you can use multiple variables. The following table shows examples and their evaluated results against the preceding payload.

Expression	Evaluated result	Description
\$request.body.action	join	An unwrapped variable
\${request.body.action}	join	A wrapped variable
\${request.body.service}/\${request.body.action}	chat/join	Multiple variables with static values
\${request.body.action}-\${request.body.invalidPath}	join-	If the JSONPath is not found, the variable is resolved as "".
action	action	Static value
\\$default	\$default	Static value

The evaluated result is used to find a route. If there is a route with a matching route key, the route is selected to process the message. If no matching route is found, then API Gateway tries to find the \$default route if available. If the \$default route is not defined, then API Gateway returns an error.

Set up routes for a WebSocket API in API Gateway

When you first create a new WebSocket API, there are three predefined routes: \$connect, \$disconnect, and \$default. You can create them by using the console, API, or AWS CLI. If desired, you can create custom routes. For more information, see [the section called “Overview of WebSocket APIs”](#).

 **Note**

In the CLI, you can create routes before or after you create integrations, and you can reuse the same integration for multiple routes.

Create a route using the API Gateway console

To create a route using the API Gateway console

1. Sign in to the API Gateway console, choose the API, and choose **Routes**.
2. Choose **Create route**
3. For **Route key**, enter the route key name. You can create the predefined routes (\$connect, \$disconnect, and \$default), or a custom route.

 **Note**

When you create a custom route, do not use the \$ prefix in the route key name. This prefix is reserved for predefined routes.

4. Select and configure the integration type for the route. For more information, see [the section called “Set up a WebSocket API integration request using the API Gateway console”](#).

Create a route using the AWS CLI

The following [create-route](#) command creates a route:

```
aws apigatewayv2 --region us-east-1 create-route --api-id aabbcccddee --route-key $default
```

The output will look like a following:

```
{  
    "ApiKeyRequired": false,  
    "AuthorizationType": "NONE",  
    "RouteKey": "$default",  
    "RouteId": "1122334"  
}
```

Specify route request settings for \$connect

When you set up the \$connect route for your API, the following optional settings are available to enable authorization for your API. For more information, see [the section called “The \\$connect route”](#).

- **Authorization:** If no authorization is needed, you can specify NONE. Otherwise, you can specify:
 - AWS_IAM to use standard AWS IAM policies to control access to your API.
 - CUSTOM to implement authorization for an API by specifying a Lambda authorizer function that you have previously created. The authorizer can reside in your own AWS account or a different AWS account. For more information about Lambda authorizers, see [Use API Gateway Lambda authorizers](#).

Note

In the API Gateway console, the CUSTOM setting is visible only after you have set up an authorizer function as described in [the section called “Configure a Lambda authorizer \(console\)”](#).

Important

The **Authorization** setting is applied to the entire API, not just the \$connect route. The \$connect route protects the other routes, because it is called on every connection.

- **API key required:** You can optionally require an API key for an API's \$connect route. You can use API keys together with usage plans to control and track access to your APIs. For more information, see [the section called "Usage plans"](#).

Set up the \$connect route request using the API Gateway console

To set up the \$connect route request for a WebSocket API using the API Gateway console:

1. Sign in to the API Gateway console, choose the API, and choose **Routes**.
2. Under **Routes**, choose \$connect, or create a \$connect route by following [the section called "Create a route using the API Gateway console"](#).
3. In the **Route request settings** section, choose **Edit**.
4. For **Authorization**, select an authorization type.
5. To require an API for the \$connect route, select **Require API key**.
6. Choose **Save changes**.

Set up route responses for WebSocket APIs in API Gateway

WebSocket routes can be configured for two-way or one-way communication. API Gateway will not pass the backend response through to the route response, unless you set up a route response.

Note

You can only define the \$default route response for WebSocket APIs. You can use an integration response to manipulate the response from a backend service. For more information, see [the section called "Overview of integration responses"](#).

You can configure route responses and response selection expressions by using the API Gateway console or the AWS CLI or an AWS SDK.

For more information about route response selection expressions, see [the section called ""](#).

Topics

- [Set up a route response using the API Gateway console](#)
- [Set up a route response using the AWS CLI](#)

Set up a route response using the API Gateway console

After you have created a WebSocket API and attached a proxy Lambda function to the default route, you can set up route response using the API Gateway console:

1. Sign in to the API Gateway console, choose a WebSocket API with a proxy Lambda function integration on the \$default route.
2. Under **Routes**, choose the \$default route.
3. Choose **Enable two-way communication**.
4. Choose **Deploy API**.
5. Deploy your API to a stage.

Use the following [wscat](#) command to connect to your API. For more information about wscat, see the section called “[Use wscat to connect to a WebSocket API and send messages to it](#)”.

```
wscat -c wss://api-id.execute-api.us-east-2.amazonaws.com/test
```

Press the enter button to call the default route. The body of your Lambda function should return.

Set up a route response using the AWS CLI

The following [create-route-response](#) command creates a route response for the \$default route. You can identify the API ID and route ID by using the [get-apis](#) and [get-routes](#) commands.

```
aws apigatewayv2 create-route-response \
  --api-id aabbccddeee \
  --route-id 1122334 \
  --route-response-key '$default'
```

The output will look like the following:

```
{
  "RouteResponseId": "abcdef",
  "RouteResponseKey": "$default"
}
```

Set up a \$connect route that requires a WebSocket subprotocol

Clients can use the Sec-WebSocket-Protocol field to request a [WebSocket subprotocol](#) during the connection to your WebSocket API. You can set up an integration for the \$connect route to allow connections only if a client requests a subprotocol that your API supports.

The following example Lambda function returns the Sec-WebSocket-Protocol header to clients. The function establishes a connection to your API only if the client specifies the myprotocol subprotocol.

For an CloudFormation template that creates this example API and Lambda proxy integration, see [ws-subprotocol.yaml](#).

```
export const handler = async (event) => {
  if (event.headers != undefined) {
    const headers = toLowerCaseProperties(event.headers);

    if (headers['sec-websocket-protocol'] != undefined) {
      const subprotocolHeader = headers['sec-websocket-protocol'];
      const subprotocols = subprotocolHeader.split(',');

      if (subprotocols.indexOf('myprotocol') >= 0) {
        const response = {
          statusCode: 200,
          headers: {
            "Sec-WebSocket-Protocol" : "myprotocol"
          }
        };
        return response;
      }
    }
  }

  const response = {
    statusCode: 400
  };

  return response;
};

function toLowerCaseProperties(obj) {
  var wrapper = {};
  for (var key in obj) {
```

```
        wrapper[key.toLowerCase()] = obj[key];
    }
    return wrapper;
}
```

You can use [wscat](#) to test that your API allows connections only if a client requests a subprotocol that your API supports. The following commands use the `-s` flag to specify subprotocols during the connection.

The following command attempts a connection with an unsupported subprotocol. Because the client specified the `chat1` subprotocol, the Lambda integration returns a 400 error, and the connection is unsuccessful.

```
wscat -c wss://api-id.execute-api.region.amazonaws.com/beta -s chat1
error: Unexpected server response: 400
```

The following command includes a supported subprotocol in the connection request. The Lambda integration allows the connection.

```
wscat -c wss://api-id.execute-api.region.amazonaws.com/beta -s chat1,myprotocol
connected (press CTRL+C to quit)
```

To learn more about invoking WebSocket APIs, see [Invoke WebSocket APIs](#).

Control and manage access to WebSocket APIs in API Gateway

API Gateway supports multiple mechanisms for controlling and managing access to your WebSocket API.

You can use the following mechanisms for authentication and authorization:

- **Standard AWS IAM roles and policies** offer flexible and robust access controls. You can use IAM roles and policies for controlling who can create and manage your APIs, as well as who can invoke them. For more information, see [Control access to WebSocket APIs with IAM authorization](#).
- **IAM tags** can be used together with IAM policies to control access. For more information, see [Using tags to control access to API Gateway REST API resources](#).
- **Lambda authorizers** are Lambda functions that control access to APIs. For more information, see [Control access to WebSocket APIs with AWS Lambda REQUEST authorizers](#).

To improve your security posture, we recommend that you configure an authorizer for the \$connect route on all your WebSocket APIs. You might need to do this to comply with various compliance frameworks. For more information, see [Amazon API Gateway controls](#) in the *AWS Security Hub User Guide*.

Topics

- [Control access to WebSocket APIs with IAM authorization](#)
- [Control access to WebSocket APIs with AWS Lambda REQUEST authorizers](#)

Control access to WebSocket APIs with IAM authorization

IAM authorization in WebSocket APIs is similar to that for [REST APIs](#), with the following exceptions:

- The execute-api action supports ManageConnections in addition to existing actions (Invoke, InvalidateCache). ManageConnections controls access to the @connections API.
- WebSocket routes use a different ARN format:

```
arn:aws:execute-api:region:account-id:api-id/stage-name/route-key
```

- The @connections API uses the same ARN format as REST APIs:

```
arn:aws:execute-api:region:account-id:api-id/stage-name/POST/@connections
```

Important

When you use [IAM authorization](#), you must sign requests with [Signature Version 4 \(SigV4\)](#).

For example, you could set up the following policy to the client. This example allows everyone to send a message (Invoke) for all routes except for a secret route in the prod stage and prevents everyone from sending a message back to connected clients (ManageConnections) for all stages.

JSON

```
{  
  "Version": "2012-10-17",
```

```
"Statement": [
    {
        "Effect": "Allow",
        "Action": [
            "execute-api:Invoke"
        ],
        "Resource": [
            "arn:aws:execute-api:us-east-1:111122223333:api-id/prod/*"
        ]
    },
    {
        "Effect": "Deny",
        "Action": [
            "execute-api:Invoke"
        ],
        "Resource": [
            "arn:aws:execute-api:us-east-1:111122223333:api-id/prod/secret"
        ]
    },
    {
        "Effect": "Deny",
        "Action": [
            "execute-api:ManageConnections"
        ],
        "Resource": [
            "arn:aws:execute-api:us-east-1:111122223333:api-id/*"
        ]
    }
]
```

Control access to WebSocket APIs with AWS Lambda REQUEST authorizers

A Lambda authorizer function in WebSocket APIs is similar to that for [REST APIs](#), with the following exceptions:

- You can only use a Lambda authorizer function for the \$connect route.
- You cannot use path variables (`event.pathParameters`), because the path is fixed.
- `event.methodArn` is different from its REST API equivalent, because it has no HTTP method. In the case of \$connect, `methodArn` ends with "\$connect":

```
arn:aws:execute-api:region:account-id:api-id/stage-name/$connect
```

- The context variables in `event.requestContext` are different from those for REST APIs.

The following example shows an input to a REQUEST authorizer for a WebSocket API:

```
{  
    "type": "REQUEST",  
    "methodArn": "arn:aws:execute-api:us-east-1:123456789012:abcdef123/default/  
$connect",  
    "headers": {  
        "Connection": "upgrade",  
        "content-length": "0",  
        "HeaderAuth1": "headerValue1",  
        "Host": "abcdef123.execute-api.us-east-1.amazonaws.com",  
        "Sec-WebSocket-Extensions": "permessage-deflate; client_max_window_bits",  
        "Sec-WebSocket-Key": "...",  
        "Sec-WebSocket-Version": "13",  
        "Upgrade": "websocket",  
        "X-Amzn-Trace-Id": "...",  
        "X-Forwarded-For": "...",  
        "X-Forwarded-Port": "443",  
        "X-Forwarded-Proto": "https"  
    },  
    "multiValueHeaders": {  
        "Connection": [  
            "upgrade"  
        ],  
        "content-length": [  
            "0"  
        ],  
        "HeaderAuth1": [  
            "headerValue1"  
        ],  
        "Host": [  
            "abcdef123.execute-api.us-east-1.amazonaws.com"  
        ],  
        "Sec-WebSocket-Extensions": [  
            "permessage-deflate; client_max_window_bits"  
        ],  
        "Sec-WebSocket-Key": [  
            "..."  
        ]  
    }  
}
```

```
],
  "Sec-WebSocket-Version": [
    "13"
  ],
  "Upgrade": [
    "websocket"
  ],
  "X-Amzn-Trace-Id": [
    "..."
  ],
  "X-Forwarded-For": [
    "..."
  ],
  "X-Forwarded-Port": [
    "443"
  ],
  "X-Forwarded-Proto": [
    "https"
  ]
},
"queryStringParameters": {
  "QueryString1": "queryValue1"
},
"multiValueQueryStringParameters": {
  "QueryString1": [
    "queryValue1"
  ]
},
"stageVariables": {},
"requestContext": {
  "routeKey": "$connect",
  "eventType": "CONNECT",
  "extendedRequestId": "...",
  "requestTime": "19/Jan/2023:21:13:26 +0000",
  "messageDirection": "IN",
  "stage": "default",
  "connectedAt": 1674162806344,
  "requestTimeEpoch": 1674162806345,
  "identity": {
    "sourceIp": "..."
  },
  "requestId": "...",
  "domainName": "abcdef123.execute-api.us-east-1.amazonaws.com",
  "connectionId": "..."
}
```

```
        "apiId": "abcdef123"
    }
}
```

The following example Lambda authorizer function is a WebSocket version of the Lambda authorizer function for REST APIs in [the section called “Additional examples of Lambda authorizer functions”](#):

Node.js

```
// A simple REQUEST authorizer example to demonstrate how to use request
// parameters to allow or deny a request. In this example, a request is
// authorized if the client-supplied HeaderAuth1 header and QueryString1 query
// parameter
// in the request context match the specified values of
// of 'headerValue1' and 'queryValue1' respectively.
export const handler = function(event, context, callback) {
    console.log('Received event:', JSON.stringify(event, null, 2));

    // Retrieve request parameters from the Lambda function input:
    var headers = event.headers;
    var queryStringParameters = event.queryStringParameters;
    var stageVariables = event.stageVariables;
    var requestContext = event.requestContext;

    // Parse the input for the parameter values
    var tmp = event.methodArn.split(':');
    var apiGatewayArnTmp = tmp[5].split('/');
    var awsAccountId = tmp[4];
    var region = tmp[3];
    var ApiId = apiGatewayArnTmp[0];
    var stage = apiGatewayArnTmp[1];
    var route = apiGatewayArnTmp[2];

    // Perform authorization to return the Allow policy for correct parameters and
    // the 'Unauthorized' error, otherwise.
    var authResponse = {};
    var condition = {};
    conditionIpAddress = {};

    if (headers.HeaderAuth1 === "headerValue1"
        && queryStringParameters.QueryString1 === "queryValue1") {
        callback(null, generateAllow('me', event.methodArn));
    }
}
```

```
    } else {
        callback(null, generateDeny('me', event.methodArn));
    }
}

// Helper function to generate an IAM policy
var generatePolicy = function(principalId, effect, resource) {
    // Required output:
    var authResponse = {};
    authResponse.principalId = principalId;
    if (effect && resource) {
        var policyDocument = {};
        policyDocument.Version = '2012-10-17'          // default version
        policyDocument.Statement = [];
        var statementOne = {};
        statementOne.Action = 'execute-api:Invoke'; // default action
        statementOne.Effect = effect;
        statementOne.Resource = resource;
        policyDocument.Statement[0] = statementOne;
        authResponse.policyDocument = policyDocument;
    }
    // Optional output with custom properties of the String, Number or Boolean type.
    authResponse.context = {
        "stringKey": "stringval",
        "numberKey": 123,
        "booleanKey": true
    };
    return authResponse;
}

var generateAllow = function(principalId, resource) {
    return generatePolicy(principalId, 'Allow', resource);
}

var generateDeny = function(principalId, resource) {
    return generatePolicy(principalId, 'Deny', resource);
}
```

Python

```
# A simple REQUEST authorizer example to demonstrate how to use request
# parameters to allow or deny a request. In this example, a request is
```

```
# authorized if the client-supplied HeaderAuth1 header and QueryString1 query
# parameter
# in the request context match the specified values of
# of 'headerValue1' and 'queryValue1' respectively.

import json


def lambda_handler(event, context):
    print(event)

    # Retrieve request parameters from the Lambda function input:
    headers = event['headers']
    queryStringParameters = event['queryStringParameters']
    stageVariables = event['stageVariables']
    requestContext = event['requestContext']

    # Parse the input for the parameter values
    tmp = event['methodArn'].split(':')
    apiGatewayArnTmp = tmp[5].split('/')
    awsAccountId = tmp[4]
    region = tmp[3]
    ApiId = apiGatewayArnTmp[0]
    stage = apiGatewayArnTmp[1]
    route = apiGatewayArnTmp[2]

    # Perform authorization to return the Allow policy for correct parameters
    # and the 'Unauthorized' error, otherwise.

    authResponse = {}
    condition = []
    condition['IpAddress'] = []

    if (headers['HeaderAuth1'] ==
        "headerValue1" and queryStringParameters["QueryString1"] ==
        "queryValue1"):
        response = generateAllow('me', event['methodArn'])
        print('authorized')
        return json.loads(response)
    else:
        response = generateDeny('me', event['methodArn'])
        print('unauthorized')
        return json.loads(response)
```

```
# Help function to generate IAM policy

def generatePolicy(principalId, effect, resource):
    authResponse = {}
    authResponse['principalId'] = principalId
    if (effect and resource):
        policyDocument = {}
        policyDocument['Version'] = '2012-10-17'
        policyDocument['Statement'] = []
        statementOne = {}
        statementOne['Action'] = 'execute-api:Invoke'
        statementOne['Effect'] = effect
        statementOne['Resource'] = resource
        policyDocument['Statement'] = [statementOne]
        authResponse['policyDocument'] = policyDocument

        authResponse['context'] = {
            "stringKey": "stringval",
            "numberKey": 123,
            "booleanKey": True
        }

    authResponse_JSON = json.dumps(authResponse)

    return authResponse_JSON

def generateAllow(principalId, resource):
    return generatePolicy(principalId, 'Allow', resource)

def generateDeny(principalId, resource):
    return generatePolicy(principalId, 'Deny', resource)
```

To configure the preceding Lambda function as a REQUEST authorizer function for a WebSocket API, follow the same procedure as for [REST APIs](#).

To configure the \$connect route to use this Lambda authorizer in the console, select or create the \$connect route. In the **Route request settings** section, choose **Edit**. Select your authorizer in the **Authorization** dropdown menu, and then choose **Save changes**.

To test the authorizer, you need to create a new connection. Changing authorizer in \$connect doesn't affect the already connected client. When you connect to your WebSocket API, you need to provide values for any configured identity sources. For example, you can connect by sending a valid query string and header using wscat as in the following example:

```
wscat -c 'wss://myapi.execute-api.us-east-1.amazonaws.com/beta?  
QueryString1=queryValue1' -H HeaderAuth1:headerValue1
```

If you attempt to connect without a valid identity value, you'll receive a 401 response:

```
wscat -c wss://myapi.execute-api.us-east-1.amazonaws.com/beta  
error: Unexpected server response: 401
```

Integrations for WebSocket APIs in API Gateway

After setting up an API route, you must integrate it with an endpoint in the backend. A backend endpoint is also referred to as an integration endpoint and can be a Lambda function, an HTTP endpoint, or an AWS service action. The API integration has an integration request and an integration response.

In this section, you can learn how to set up integration requests and integration responses for your WebSocket API.

Topics

- [Set up a WebSocket API integration request in API Gateway](#)
- [Set up a WebSocket API integration response in API Gateway](#)

Set up a WebSocket API integration request in API Gateway

Setting up an integration request involves the following:

- Choosing a route key to integrate to the backend.
- Specifying the backend endpoint to invoke. WebSocket APIs support the following integration types:
 - AWS_PROXY
 - AWS
 - HTTP_PROXY

- HTTP
- MOCK

For more information about integration types, see [IntegrationType](#) in the API Gateway V2 REST API.

- Configuring how to transform the route request data, if necessary, into integration request data by specifying one or more request templates.

Set up a WebSocket API integration request using the API Gateway console

To add an integration request to a route in a WebSocket API using the API Gateway console

1. Sign in to the API Gateway console, choose the API, and choose **Routes**.
2. Under **Routes**, choose the route.
3. Choose the **Integration request** tab, and then in the **Integration request settings** section, choose **Edit**.
4. For **Integration type**, select one of the following:
 - Choose **Lambda function** only if your API will be integrated with an AWS Lambda function that you have already created in this account or in another account.

To create a new Lambda function in AWS Lambda, to set a resource permission on the Lambda function, or to perform any other Lambda service actions, choose **AWS Service** instead.

5. If you chose **Lambda function**, do the following:
 - a. For **Use Lambda proxy integration**, choose the check box if you intend to use [Lambda proxy integration](#) or [cross-account Lambda proxy integration](#).

- b. For **Lambda function**, specify the function in one of the following ways:
 - If your Lambda function is in the same account, enter the function name and then select the function from the dropdown list.
-  **Note**

The function name can optionally include its alias or version specification, as in HelloWorld, HelloWorld:1, or HelloWorld:alpha.
- If the function is in a different account, enter the ARN for the function.
 - c. To use the default timeout value of 29 seconds, keep **Default timeout** turned on. To set a custom timeout, choose **Default timeout** and enter a timeout value between 50 and 29000 milliseconds.
 6. If you chose **HTTP**, follow the instructions in step 4 of [the section called “Set up integration request using the console”](#).
 7. If you chose **Mock**, proceed to the **Request Templates** step.
 8. If you chose **AWS service**, follow the instructions in step 6 of [the section called “Set up integration request using the console”](#).
 9. If you chose **VPC link**, do the following:
 - a. For **VPC proxy integration**, choose the check box if you want your requests to be proxied to your VPCLink's endpoint.
 - b. For **HTTP method**, choose the HTTP method type that most closely matches the method in the HTTP backend.
 - c. From the **VPC link** dropdown list, select a VPC link. You can select [Use Stage Variables] and enter `${stageVariables.vpcLinkId}` in the text box below the list.

You can define the `vpcLinkId` stage variable after deploying the API to a stage and set its value to the ID of the VpcLink.
 - d. For **Endpoint URL**, enter the URL of the HTTP backend you want this integration to use.
 - e. To use the default timeout value of 29 seconds, keep **Default timeout** turned on. To set a custom timeout, choose **Default timeout** and enter a timeout value between 50 and 29000 milliseconds.
 10. Choose **Save changes**.

11. Under **Request templates**, do the following:

- a. To enter a **Template selection expression**, under **Request templates**, choose **Edit**.
- b. Enter a **Template selection expression**. Use an expression that API Gateway looks for in the message payload. If it is found, it is evaluated, and the result is a template key value that is used to select the data mapping template to be applied to the data in the message payload. You create the data mapping template in the next step. Choose **Edit** to save your changes.
- c. Choose **Create template** to create the data mapping template. For **Template key**, enter a template key value that is used to select the data mapping template to be applied to the data in the message payload. Then, enter a mapping template. Choose **Create template**.

For information about template selection expressions, see [the section called “Template selection expressions”](#).

Set up an integration request using the AWS CLI

You can set up an integration request for a route in a WebSocket API by using the AWS CLI as in the following example, which creates a mock integration:

1. Create a file named `integration-params.json`, with the following contents:

```
{"PassthroughBehavior": "WHEN_NO_MATCH", "TimeoutInMillis": 29000,  
"ConnectionType": "INTERNET", "RequestTemplates": {"application/json":  
"\\"statusCode\\":200}"}, "IntegrationType": "MOCK"}
```

2. Use the following [create-integration](#) command to create the mock integration.

```
aws apigatewayv2 --region us-east-1 create-integration --api-id aabbccddeee --cli-  
input-json file://integration-params.json
```

The output will look like the following:

```
{  
    "PassthroughBehavior": "WHEN_NO_MATCH",  
    "TimeoutInMillis": 29000,  
    "ConnectionType": "INTERNET",  
    "IntegrationResponseSelectionExpression": "${response.statusCode}",  
    "RequestTemplates": {
```

```
        "application/json": "{\"statusCode\":200}"  
    },  
    "IntegrationId": "0abcdef",  
    "IntegrationType": "MOCK"  
}
```

Alternatively, you can set up an integration request for a proxy integration by using the AWS CLI.

1. Create a Lambda function in the Lambda console and give it a basic Lambda execution role.
2. Use the following [create-integration](#) command to create the integration.

```
aws apigatewayv2 create-integration --api-id aabbccdde --integration-type  
AWS_PROXY --integration-method POST --integration-uri arn:aws:apigateway:us-  
east-1:lambda:path/2015-03-31/functions/arn:aws:lambda:us-  
east-1:123412341234:function:simpleproxy-echo-e2e/invocations
```

The output will look like the following:

```
{  
    "PassthroughBehavior": "WHEN_NO_MATCH",  
    "IntegrationMethod": "POST",  
    "TimeoutInMillis": 29000,  
    "ConnectionType": "INTERNET",  
    "IntegrationUri": "arn:aws:apigateway:us-east-1:lambda:path/2015-03-31/functions/  
arn:aws:lambda:us-east-1:123412341234:function:simpleproxy-echo-e2e/invocations",  
    "IntegrationId": "abcdefg",  
    "IntegrationType": "AWS_PROXY"  
}
```

Input format of a Lambda function for proxy integration for WebSocket APIs

In Lambda proxy integration, API Gateway maps the entire client request to the input event parameter of the backend Lambda function. The following example shows the structure of the input event from the \$connect route and the input event from the \$disconnect route that API Gateway sends to a Lambda proxy integration.

Input from the \$connect route

```
{
```

```
headers: {
    Host: 'abcd123.execute-api.us-east-1.amazonaws.com',
    'Sec-WebSocket-Extensions': 'permessage-deflate; client_max_window_bits',
    'Sec-WebSocket-Key': '...',
    'Sec-WebSocket-Version': '13',
    'X-Amzn-Trace-Id': '...',
    'X-Forwarded-For': '192.0.2.1',
    'X-Forwarded-Port': '443',
    'X-Forwarded-Proto': 'https'
},
multiValueHeaders: {
    Host: [ 'abcd123.execute-api.us-east-1.amazonaws.com' ],
    'Sec-WebSocket-Extensions': [ 'permessage-deflate; client_max_window_bits' ],
    'Sec-WebSocket-Key': [ '...' ],
    'Sec-WebSocket-Version': [ '13' ],
    'X-Amzn-Trace-Id': [ '...' ],
    'X-Forwarded-For': [ '192.0.2.1' ],
    'X-Forwarded-Port': [ '443' ],
    'X-Forwarded-Proto': [ 'https' ]
},
requestContext: {
    routeKey: '$connect',
    eventType: 'CONNECT',
    extendedRequestId: 'ABCD1234=',
    requestTime: '09/Feb/2024:18:11:43 +0000',
    messageDirection: 'IN',
    stage: 'prod',
    connectedAt: 1707502303419,
    requestTimeEpoch: 1707502303420,
    identity: { sourceIp: '192.0.2.1' },
    requestId: 'ABCD1234=',
    domainName: 'abcd1234.execute-api.us-east-1.amazonaws.com',
    connectionId: 'AAAA1234=',
    apiId: 'abcd1234'
},
isBase64Encoded: false
}
```

Input from the \$disconnect route

```
{
  headers: {
```

```
        Host: 'abcd1234.execute-api.us-east-1.amazonaws.com',
        'x-api-key': '',
        'X-Forwarded-For': '',
        'x-restapi': ''
    },
    multiValueHeaders: {
        Host: [ 'abcd1234.execute-api.us-east-1.amazonaws.com' ],
        'x-api-key': [ '' ],
        'X-Forwarded-For': [ '' ],
        'x-restapi': [ '' ]
    },
    requestContext: {
        routeKey: '$disconnect',
        disconnectStatusCode: 1005,
        eventType: 'DISCONNECT',
        extendedRequestId: 'ABCD1234=',
        requestTime: '09/Feb/2024:18:23:28 +0000',
        messageDirection: 'IN',
        disconnectReason: 'Client-side close frame status not set',
        stage: 'prod',
        connectedAt: 1707503007396,
        requestTimeEpoch: 1707503008941,
        identity: { sourceIp: '192.0.2.1' },
        requestId: 'ABCD1234=',
        domainName: 'abcd1234.execute-api.us-east-1.amazonaws.com',
        connectionId: 'AAAA1234=',
        apiId: 'abcd1234'
    },
    isBase64Encoded: false
}
```

Set up a WebSocket API integration response in API Gateway

The following section provides a brief overview of integration responses for WebSocket API and how to set up an integration response for a WebSocket API.

Topics

- [Overview of integration responses](#)
- [Integration responses for two-way communication](#)
- [Set up an integration response using the API Gateway console](#)

- [Set up an integration response using the AWS CLI](#)

Overview of integration responses

API Gateway's integration response is a way of modeling and manipulating the response from a backend service. There are some differences in setup of a REST API versus a WebSocket API integration response, but conceptually the behavior is the same.

WebSocket routes can be configured for two-way or one-way communication.

- When a route is configured for two-way communication, an integration response allows you to configure transformations on the returned message payload, similar to integration responses for REST APIs.
- If a route is configured for one-way communication, then regardless of any integration response configuration, no response will be returned over the WebSocket channel after the message is processed.

API Gateway will not pass the backend response through to the route response, unless you set up a route response. To learn about setting up a route response, see [the section called "Set up WebSocket API route responses"](#).

Integration responses for two-way communication

Integrations can be divided into *proxy* integrations and *non-proxy* integrations.

Important

For *proxy integrations*, API Gateway automatically passes the backend output to the caller as the complete payload. There is no integration response.

For *non-proxy integrations*, you must set up at least one integration response:

- Ideally, one of your integration responses should act as a catch-all when no explicit choice can be made. This default case is represented by setting an integration response key of \$default.
- In all other cases, the integration response key functions as a regular expression. It should follow a format of "/expression/".

For non-proxy HTTP integrations:

- API Gateway will attempt to match the HTTP status code of the backend response. The integration response key will function as a regular expression in this case. If a match cannot be found, then `$default` is chosen as the integration response.
- The template selection expression, as described above, functions identically. For example:
 - `/2\d\d/`: Receive and transform successful responses
 - `/4\d\d/`: Receive and transform bad request errors
 - `$default`: Receive and transform all unexpected responses

For more information about template selection expressions, see [the section called “Template selection expressions”](#).

Set up an integration response using the API Gateway console

To set up a route integration response for a WebSocket API using the API Gateway console:

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose your WebSocket API and choose your route.
3. Choose the **Integration request** tab, and then in the **Integration response settings** section, choose **Create integration response**.
4. For **Response key**, enter a value that will be found in the response key in the outgoing message after evaluating the response selection expression. For instance, you can enter `/4\d\d/` to receive and transform bad request errors or enter `$default` to receive and transform all responses that match the template selection expression.
5. For **Template selection expression**, enter a selection expression to evaluate the outgoing message.
6. Choose **Create response**.
7. You can also define a mapping template to configure transformations of your returned message payload. Choose **Create template**.
8. Enter a key name. If you are choosing the default template selection expression, enter `\$default`.
9. For **Response template**, enter your mapping template in the code editor.
10. Choose **Create template**.
11. Choose **Deploy API** to deploy your API.

Use the following [wscat](#) command to connect to your API. For more information about wscat, see the section called “[Use wscat to connect to a WebSocket API and send messages to it](#)”.

```
wscat -c wss://api-id.execute-api.us-east-2.amazonaws.com/test
```

When you call your route, the returned message payload should return.

Set up an integration response using the AWS CLI

The following [create-integration-response](#) command creates a \$default integration response:

```
aws apigatewayv2 create-integration-response \
--api-id vaz7da96z6 \
--integration-id a1b2c3 \
--integration-response-key '$default'
```

Request validation for WebSocket APIs in API Gateway

You can configure API Gateway to perform validation on a route request before proceeding with the integration request. If the validation fails, API Gateway fails the request without calling your backend, sends a "Bad request body" gateway response to the client, and publishes the validation results in CloudWatch Logs. Using validation this way reduces unnecessary calls to your API backend.

Model selection expressions

You can use a model selection expression to dynamically validate requests within the same route. Model validation occurs if you provide a model selection expression for either proxy or non-proxy integrations. You might need to define the \$default model as a fallback when no matching model is found. If there is no matching model and \$default isn't defined, the validation fails. The selection expression looks like Route.ModelSelectionExpression and evaluates to the key for Route.RequestModels.

When you define a route for a WebSocket API, you can optionally specify a *model selection expression*. This expression is evaluated to select the model to be used for body validation when a request is received. The expression evaluates to one of the entries in a route's [requestmodels](#).

A model is expressed as a [JSON schema](#) and describes the data structure of the request body. The nature of this selection expression enables you to dynamically choose the model to validate

against at runtime for a particular route. For information about how to create a model, see [the section called “Data models for REST APIs”](#).

Set up request validation using the API Gateway console

The following example shows you how to set up request validation on a route.

First, you create a model, and then you create a route. Next, you configure request validation on the route you just created. Lastly, you deploy and test your API. To complete this tutorial, you need a WebSocket API with `$request.body.action` as the route selection expression and an integration endpoint for your new route.

You also need `wscat` to connect to your API. For more information, see [the section called “Use `wscat` to connect to a WebSocket API and send messages to it”](#).

To create a model

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose a WebSocket API.
3. In the main navigation pane, choose **Models**.
4. Choose **Create model**.
5. For **Name**, enter `emailModel`.
6. For **Content type**, enter `application/json`.
7. For **Model schema**, enter the following model:

```
{  
  "$schema": "http://json-schema.org/draft-04/schema#",  
  "type" : "object",  
  "required" : [ "address"],  
  "properties" : {  
    "address": {  
      "type": "string"  
    }  
  }  
}
```

This model requires that the request contains an email address.

8. Choose **Save**.

In this step, you create a route for your WebSocket API.

To create a route

1. In the main navigation pane, choose **Routes**.
2. Choose **Create route**.
3. For **Route key**, enter **sendMessage**.
4. Choose an integration type and specify an integration endpoint. For more information see [the section called “Integrations”](#).
5. Choose **Create route**.

In this step, you set up request validation for the sendMessage route.

To set up request validation

1. On the **Route request** tab, under **Route request settings**, choose **Edit**.
2. For **Model selection expression**, enter `${request.body.messageType}`.

API Gateway uses the messageType property to validate the incoming request.

3. Choose **Add request model**.
4. For **Model key**, enter **email**.
5. For **Model**, choose **emailModel**.

API Gateway validates incoming messages with the messageType property set to email against this model.

Note

If API Gateway can't match the model selection expression to a model key, then it selects the \$default model. If there is no \$default model, then the validation fails. For production APIs, we recommend that you create a \$default model.

6. Choose **Save changes**.

In this step, you deploy and test your API.

To deploy and test your API

1. Choose **Deploy API**.
2. Choose the desired stage from the dropdown list or enter the name of a new stage.
3. Choose **Deploy**.
4. In the main navigation pane, choose **Stages**.
5. Copy your API's WebSocket URL. The URL should look like `wss://abcdef123.execute-api.us-east-2.amazonaws.com/production`.
6. Open a new terminal and run the **wscat** command with the following parameters.

```
wscat -c wss://abcdef123.execute-api.us-west-2.amazonaws.com/production
```

```
Connected (press CTRL+C to quit)
```

7. Use the following command to test your API.

```
{"action": "sendMessage", "messageType": "email"}
```

```
{"message": "Invalid request body", "connectionId": "ABCD1=234",  
"requestId": "EFGH="}
```

API Gateway will fail the request.

Use the next command to send a valid request to your API.

```
{"action": "sendMessage", "messageType": "email", "address":  
"mary_major@example.com"}
```

Data transformations for WebSocket APIs in API Gateway

In API Gateway, a WebSocket API's method request can take a payload in a different format from the corresponding integration request payload, as required in the backend. Similarly, the backend may return an integration response payload different from the method response payload, as expected by the frontend.

API Gateway lets you use mapping template transformations to map the payload from a method request to the corresponding integration request and from an integration response to the corresponding method response. You create a mapping template and You specify a template selection expression to determine which template to use to perform the necessary data transformations.

You can use data mappings to map data from a [route request](#) to a backend integration. To learn more, see [the section called “Data mapping”](#).

Mapping templates and models

A *mapping template* is a script expressed in [Velocity Template Language \(VTL\)](#) and applied to the payload using [JSONPath expressions](#). For more information about API Gateway mapping templates, see [Mapping template transformations for REST APIs in API Gateway](#).

The payload can have a *data model* according to the [JSON schema draft 4](#). You do not have to define a model to create a mapping template. However, a model can help you create a template because API Gateway generates a template blueprint based on a provided model. For more information about API Gateway models, see [Data models for REST APIs](#).

Template selection expressions

To transform a payload with a mapping template, you specify a WebSocket API template selection expression in an [integration request](#) or [integration response](#). This expression is evaluated to determine the input or output template (if any) to use to transform either the request body into the integration request body (via an input template) or the integration response body to the route response body (via an output template).

`Integration.TemplateSelectionExpression` supports `${request.body.jsonPath}` and static values.

`IntegrationResponse.TemplateSelectionExpression` supports
 `${request.body.jsonPath}, ${integration.response.statusCode},`
 `${integration.response.header.headerName},`
 `${integration.response.multivalueheader.headerName},` and static values.

Integration response selection expressions

When you [set up an integration response](#) for a WebSocket API, you can optionally specify an integration response selection expression. This expression determines what

[IntegrationResponse](#) should be selected when an integration returns. The value of this expression is currently restricted by API Gateway, as defined below. Realize that this expression is only relevant for *non-proxy integrations*; a proxy integration simply passes the response payload back to the caller without modeling or modification.

Unlike the other preceding selection expressions, this expression currently supports a *pattern-matching* format. The expression should be wrapped with forward slashes.

Currently the value is fixed depending on the [integrationType](#):

- For Lambda-based integrations, it is `$integration.response.body.errorMessage`.
- For HTTP and MOCK integrations, it is `$integration.response.statusCode`.
- For HTTP_PROXY and AWS_PROXY, the expression isn't utilized because you're requesting that the payload pass through to the caller.

Set up data mapping for WebSocket APIs in API Gateway

Data mapping enables you to map data from a [route request](#) to a backend integration.

Note

Data mapping for WebSocket APIs isn't supported in the AWS Management Console. You must use the AWS CLI, AWS CloudFormation, or an SDK to configure data mapping.

Topics

- [Map route request data to integration request parameters](#)
- [Examples](#)

Map route request data to integration request parameters

Integration request parameters can be mapped from any defined route request parameters, the request body, [context or stage](#) variables, and static values.

The following table shows integration request data mapping expressions. In the table, **PARAM_NAME** is the name of a route request parameter of the given parameter type. It must match the regular expression `'^[\a-zA-Z0-9._$-]+$'`. **JSONPath_EXPRESSION** is a JSONPath expression for a JSON field of the request body.

Mapped data source	Mapping expression
Request query string (supported only for the \$connect route)	route.request.querystring. <i>PARAM_NAME</i>
Request header (supported only for the \$connect route)	route.request.header. <i>PARAM_NAME</i>
Multi-value request query string (supported only for the \$connect route)	route.request.multivaluequerystring. <i>PARAM_NAME</i>
Multi-value request header (supported only for the \$connect route)	route.request.multivalueheader. <i>PARAM_NAME</i>
Request body	route.request.body. <i>JSONPath_EXPRESSION</i>
Stage variables	stageVariables. <i>VARIABLE_NAME</i>
Context variables	context. <i>VARIABLE_NAME</i> that must be one of the supported context variables .
Static value	' <i>STATIC_VALUE</i> '. The <i>STATIC_VALUE</i> is a string literal and must be enclosed in single quotes.

When you create a data mapping, using the AWS CLI make sure to follow the correct format for using literals with strings in the AWS CLI. For more information, see [Using quotation marks and literals with strings in the AWS CLI](#) in the *AWS Command Line Interface User Guide*.

Examples

The following AWS CLI examples configure data mappings. For an example CloudFormation template, see [websocket-data-mapping.yaml](#).

Map a client's connectionId to a header in an integration request

The following [update-integration](#) command maps a client's connectionId to a connectionId header in the request to a backend integration:

```
aws apigatewayv2 update-integration \
--integration-id abc123 \
--api-id a1b2c3d4 \
--request-parameters
'integration.request.header.connectionId'='context.connectionId'
```

Map a query string parameter to a header in an integration request

The following example maps an authToken query string parameter to an authToken header in the integration request.

1. Use the following [update-route](#) command to add the authToken query string parameter to the route's request parameters.

```
aws apigatewayv2 update-route --route-id 0abcdef \
--api-id a1b2c3d4 \
--request-parameters '{"route.request.querystring.authToken": {"Required": false}}'
```

2. Use the following [update-integration](#) command to map the query string parameter to the authToken header in the request to the backend integration.

```
aws apigatewayv2 update-integration \
--integration-id abc123 \
--api-id a1b2c3d4 \
--request-parameters
'integration.request.header.authToken'='route.request.querystring.authToken'
```

3. (Optional) If necessary, use the following [delete-route-request-parameter](#) to delete the authToken query string parameter from the route's request parameters.

```
aws apigatewayv2 delete-route-request-parameter \
--route-id 0abcdef \
--api-id a1b2c3d4 \
--request-parameter-key 'route.request.querystring.authToken'
```

WebSocket API mapping template reference for API Gateway

This section summarizes the set of variables that are currently supported for WebSocket APIs in API Gateway.

Parameter	Description
\$context.connectionId	A unique ID for the connection that can be used to make a callback to the client.
\$context.connectedAt	The Epoch -formatted connection time.
\$context.domainName	A domain name for the WebSocket API. This can be used to make a callback to the client (instead of a hard-coded value).
\$context.eventType	The event type: CONNECT, MESSAGE, or DISCONNECT .
\$context.messageId	A unique server-side ID for a message. Available only when the \$context.eventType is MESSAGE.
\$context.routeKey	The selected route key.
\$context.requestId	Same as \$context.extendedRequestId .
\$context.extendedRequestId	An automatically generated ID for the API call, which contains more useful information for debugging/troubleshooting.
\$context.apiId	The identifier API Gateway assigns to your API.
\$context.authorizer.principalId	The principal user identification associated with the token sent by the client and returned from an API Gateway Lambda authorizer (formerly known as a custom authorizer) Lambda function.
\$context.authorizer. <i>property</i>	The stringified value of the specified key-value pair of the context map returned from an API Gateway Lambda authorizer function. For example, if the authorizer returns the following context map:

Parameter	Description
	<pre data-bbox="850 234 1127 424"> "context" : { "key": "value", "numKey": 1, "boolKey": true } </pre>
	<p>calling <code>\$context.authorizer.key</code> returns the "value" string, calling <code>\$context.authorizer.numKey</code> returns the "1" string, and calling <code>\$context.authorizer.boolKey</code> returns the "true" string.</p>
<code>\$context.error.messageString</code>	<p>The quoted value of <code>\$context.error.message</code>, namely "<code>\$context.error.message</code>".</p>
<code>\$context.error.validationErrorMessage</code>	<p>A string containing a detailed validation error message.</p>
<code>\$context.identity.accountId</code>	<p>The AWS account ID associated with the request.</p>
<code>\$context.identity.apiKey</code>	<p>The API owner key associated with key-enabled API request.</p>
<code>\$context.identity.apiKeyId</code>	<p>The API key ID associated with the key-enabled API request</p>
<code>\$context.identity.caller</code>	<p>The principal identifier of the caller making the request.</p>

Parameter	Description
\$context.identity.cognitoAuthenticationProvider	<p>A comma-separated list of all the Amazon Cognito authentication providers used by the caller making the request. Available only if the request was signed with Amazon Cognito credentials.</p> <p>For example, for an identity from an Amazon Cognito user pool, <code>cognito-idp.<i>region</i>.amazonaws.com/ <i>user_pool_id</i></code>, <code>cognito-idp.<i>region</i>.amazonaws.com/ <i>user_pool_id</i> :CognitoSignIn: <i>token subject claim</i></code></p> <p>For information about the available Amazon Cognito authentication providers, see Using Federated Identities in the Amazon Cognito Developer Guide.</p>
\$context.identity.cognitoAuthenticationType	<p>The Amazon Cognito authentication type of the caller making the request. Available only if the request was signed with Amazon Cognito credentials. Possible values include <code>authenticated</code> for authenticated identities and <code>unauthenticated</code> for unauthenticated identities.</p>
\$context.identity.cognitoIdentityId	<p>The Amazon Cognito identity ID of the caller making the request. Available only if the request was signed with Amazon Cognito credentials.</p>
\$context.identity.cognitoIdentityPoolId	<p>The Amazon Cognito identity pool ID of the caller making the request. Available only if the request was signed with Amazon Cognito credentials.</p>

Parameter	Description
\$context.identity.sourceIp	The source IP address of the immediate TCP connection making the request to API Gateway endpoint.
\$context.identity.user	The principal identifier of the user making the request.
\$context.identity.userAgent	The User Agent of the API caller.
\$context.identity.userArn	The Amazon Resource Name (ARN) of the effective user identified after authentication.
\$context.requestTime	The CLF -formatted request time (dd/MMM/yy yy:HH:mm:ss +-hhmm).
\$context.requestTimeEpoch	The Epoch -formatted request time, in milliseconds.
\$context.stage	The deployment stage of the API call (for example, Beta or Prod).
\$context.status	The response status.
\$input.body	Returns the raw payload as a string.
\$input.json(x)	<p>This function evaluates a JSONPath expression and returns the results as a JSON string.</p> <p>For example, <code>\$input.json('\$.pets')</code> will return a JSON string representing the pets structure.</p> <p>For more information about JSONPath, see JSONPath or JSONPath for Java.</p>

Parameter	Description
<p><code>\$input.path(x)</code></p> <p>Takes a JSONPath expression string (x) and returns a JSON object representation of the result. This allows you to access and manipulate elements of the payload natively in Apache Velocity Template Language (VTL).</p> <p>For example, if the expression <code>\$input.path('\$.pets')</code> returns an object like this:</p> <pre data-bbox="850 642 1165 1311">[{ "id": 1, "type": "dog", "price": 249.99 }, { "id": 2, "type": "cat", "price": 124.99 }, { "id": 3, "type": "fish", "price": 0.99 }]</pre> <p><code>\$input.path('\$.pets').count()</code> would return "3".</p> <p>For more information about JSONPath, see JSONPath or JSONPath for Java.</p>	
<p><code>\$stageVariables. <variable_name></code></p> <p><code>\$stageVariables[' <variable_name> ']</code></p>	<p><code><variable_name></code> represents a stage variable name.</p> <p><code><variable_name></code> represents any stage variable name.</p>

Parameter	Description
<code> \${stageVariables['<variable_name>']}</code>	<code><variable_name></code> represents any stage variable name.
<code>\$util.escapeJavaScript()</code>	Escapes the characters in a string using JavaScript string rules.

 **Note**

This function will turn any regular single quotes (') into escaped ones (\ '). However, the escaped single quotes are not valid in JSON. Thus, when the output from this function is used in a JSON property, you must turn any escaped single quotes (\ ') back to regular single quotes ('). This is shown in the following example:

```
$util.escapeJavaScript( $data).replaceAll("\\'", "'")
```

Parameter	Description
\$util.parseJson()	<p>Takes "stringified" JSON and returns an object representation of the result. You can use the result from this function to access and manipulate elements of the payload natively in Apache Velocity Template Language (VTL). For example, if you have the following payload:</p>
	<pre>{"errorMessage": "{\"key1\": \"var1\", \"key2\": {\"arr\": [1, 2, 3]}}"} </pre>
	<p>and use the following mapping template</p> <pre>#set (\$errorMessageObj = \$util.parseJson(\$input.path('\$.errorMessage'))) { "errorMessageObjKey2ArrVal" : \$errorMessageObj.key2.arr[0] }</pre>
	<p>You will get the following output:</p> <pre>{ "errorMessageObjKey2ArrVal" : 1 }</pre>
\$util.urlEncode()	Converts a string into "application/x-www-form-urlencoded" format.
\$util.urlDecode()	Decodes an "application/x-www-form-urlencoded" string.
\$util.base64Encode()	Encodes the data into a base64-encoded string.

Parameter	Description
<code>\$util.base64Decode()</code>	Decodes the data from a base64-encoded string.

Binary media types for WebSocket APIs in API Gateway

API Gateway WebSocket APIs don't currently support binary frames in incoming message payloads. If a client app sends a binary frame, API Gateway rejects it and disconnects the client with code 1003.

There is a workaround for this behavior. If the client sends a text-encoded binary data (e.g., base64) as a text frame, you can set the integration's `contentHandlingStrategy` property to `CONVERT_TO_BINARY` to convert the payload from base64-encoded string to binary.

To return a route response for a binary payload in non-proxy integrations, you can set the integration response's `contentHandlingStrategy` property to `CONVERT_TO_TEXT` to convert the payload from binary to base64-encoded string.

Invoke WebSocket APIs

After you've deployed your WebSocket API, client applications can connect to it and send messages to it—and your backend service can send messages to connected client applications:

- You can use `wscat` to connect to your WebSocket API and send messages to it to simulate client behavior. See [the section called “Use wscat to connect to a WebSocket API and send messages to it”](#).
- You can use the `@connections` API from your backend service to send a callback message to a connected client, get connection information, or disconnect the client. See [the section called “Use @connections commands in your backend service”](#).
- A client application can use its own WebSocket library to invoke your WebSocket API.

Use `wscat` to connect to a WebSocket API and send messages to it

The `wscat` utility is a convenient tool for testing a WebSocket API that you have created and deployed in API Gateway. You can install and use `wscat` as follows:

1. Download `wscat` from <https://www.npmjs.com/package/wscat>.

2. Install wscat by running the following command:

```
npm install -g wscat
```

3. To connect to your API, run the wscat command as shown in the following example. Note that this example assumes that the Authorization setting is NONE.

```
wscat -c wss://aabbccdde.execute-api.us-east-1.amazonaws.com/test/
```

You need to replace *aabbccdde* with the actual API ID, which is displayed in the API Gateway console or returned by the AWS CLI [create-api](#) command.

In addition, if your API is in a Region other than us-east-1, you need to substitute the correct Region.

4. To test your API, enter a message such as the following while connected:

```
{"jsonpath-expression":"route-key"}
```

where *jsonpath-expression* is a JSONPath expression and *route-key* is a route key for the API. For example:

```
{"action":"action1"}  
{"message":"test response body"}
```

For more information about JSONPath, see [JSONPath](#) or [JSONPath for Java](#).

5. To disconnect from your API, enter `ctrl-C`.

Use @connections commands in your backend service

Your backend service can use the following WebSocket connection HTTP requests to send a callback message to a connected client, get connection information, or disconnect the client.

⚠ Important

These requests use [IAM authorization](#), so you must sign them with [Signature Version 4 \(SigV4\)](#). To do this, you can use the API Gateway Management API. For more information, see [ApiGatewayManagementApi](#).

In the following command, you need to replace `{api-id}` with the actual API ID, which is displayed in the API Gateway console or returned by the AWS CLI [create-api](#) command. You must establish the connection before using this command.

To send a callback message to the client, use:

```
POST https://{api-id}.execute-api.us-east-1.amazonaws.com/{stage}/  
@connections/{connection_id}
```

You can test this request by using [Postman](#) or by calling [awscurl](#) as in the following example:

```
awscurl --service execute-api -X POST -d "hello world" https://{prefix}.execute-api.us-east-1.amazonaws.com/{stage}@connections/{connection_id}
```

You need to URL-encode the command as in the following example:

```
awscurl --service execute-api -X POST -d "hello world" https://aabbcccddee.execute-api.us-east-1.amazonaws.com/prod/%40connections/R0oXAdfD0kwCH6w%3D
```

To get the latest connection status of the client, use:

```
GET https://{api-id}.execute-api.us-east-1.amazonaws.com/{stage}/  
@connections/{connection_id}
```

To disconnect the client, use:

```
DELETE https://{api-id}.execute-api.us-east-1.amazonaws.com/{stage}/  
@connections/{connection_id}
```

You can dynamically build a callback URL by using the `$context` variables in your integration. For example, if you use Lambda proxy integration with a Node.js Lambda function, you can build the URL and send a message to a connected client as follows:

```
import {  
    ApiGatewayManagementApiClient,  
    PostToConnectionCommand,  
} from "@aws-sdk/client-apigatewaymanagementapi";
```

```
export const handler = async (event) => {
  const domain = event.requestContext.domainName;
  const stage = event.requestContext.stage;
  const connectionId = event.requestContext.connectionId;
  const callbackUrl = `https://${domain}/${stage}`;
  const client = new ApiGatewayManagementApiClient({ endpoint: callbackUrl });

  const requestParams = {
    ConnectionId: connectionId,
    Data: "Hello!",
  };

  const command = new PostToConnectionCommand(requestParams);

  try {
    await client.send(command);
  } catch (error) {
    console.log(error);
  }

  return {
    statusCode: 200,
  };
};
```

If you use a custom domain name for your WebSocket API, remove the `stage` variable from your function code.

When sending a callback message, your Lambda function must have permission to call the API Gateway Management API. You might receive an error that contains `GoneException` if you post a message before the connection is established, or after the client has disconnected.

Publish WebSocket APIs for customers to invoke

Simply creating and developing an API Gateway API doesn't automatically make it callable by your users. To make it callable, you must deploy your API to a stage. In addition, you might want to customize the URL that your users will use to access your API. You can give it a domain that is consistent with your brand or is more memorable than the default URL for your API.

In this section, you can learn how to deploy your API and customize the URL that you provide to users to access it.

Note

To augment the security of your API Gateway APIs, the execute-api.
`{region}.amazonaws.com` domain is registered in the [Public Suffix List \(PSL\)](#). For further security, we recommend that you use cookies with a __Host- prefix if you ever need to set sensitive cookies in the default domain name for your API Gateway APIs. This practice will help to defend your domain against cross-site request forgery attempts (CSRF). For more information see the [Set-Cookie](#) page in the Mozilla Developer Network.

Topics

- [Create stages for WebSocket APIs in API Gateway](#)
- [Deploy WebSocket APIs in API Gateway](#)
- [Security policy for WebSocket APIs in API Gateway](#)
- [Custom domain names for WebSocket APIs in API Gateway](#)

Create stages for WebSocket APIs in API Gateway

An API stage is a logical reference to a lifecycle state of your API (for example, dev, prod, beta, or v2). API stages are identified by their API ID and stage name, and they're included in the URL you use to invoke the API. Each stage is a named reference to a deployment of the API and is made available for client applications to call.

A deployment is a snapshot of your API configuration. After you deploy an API to a stage, it's available for clients to invoke. You must deploy an API for changes to take effect.

Stage variables

Stage variables are key-value pairs that you can define for a stage of a WebSocket API. They act like environment variables and can be used in your API setup.

For example, you can define a stage variable, and then set its value as an HTTP endpoint for an HTTP proxy integration. Later, you can reference the endpoint by using the associated stage variable name. By doing this, you can use the same API setup with a different endpoint at each stage. Similarly, you can use stage variables to specify a different AWS Lambda function integration for each stage of your API.

Note

Stage variables are not intended to be used for sensitive data, such as credentials. To pass sensitive data to integrations, use an AWS Lambda authorizer. You can pass sensitive data to integrations in the output of the Lambda authorizer. To learn more, see [the section called “Lambda authorizer response format”](#).

Examples

To use a stage variable to customize the HTTP integration endpoint, you must first set the name and value of the stage variable (for example, `url1`) with a value of `example.com`. Next, set up an HTTP proxy integration. Instead of entering the endpoint's URL, you can tell API Gateway to use the stage variable value, `http://${stageVariables.url1}`. This value tells API Gateway to substitute your stage variable `$[]` at runtime, depending on the stage of your API.

You can reference stage variables in a similar way to specify a Lambda function name or an AWS role ARN.

When specifying a Lambda function name as a stage variable value, you must configure the permissions on the Lambda function manually. The following [add-permission](#) command adds the required permissions:

```
aws lambda add-permission --function-name arn:aws:lambda:XXXXXX:your-lambda-function-name --source-arn arn:aws:execute-api:us-east-1:YOUR_ACCOUNT_ID:api_id/*/* /HTTP_METHOD/resource --principal apigateway.amazonaws.com --statement-id apigateway-access --action lambda:InvokeFunction
```

API Gateway stage variables reference

HTTP integration URIs

You can use a stage variable as part of an HTTP integration URI, as shown in the following examples.

- A full URI without protocol – `http://${stageVariables.<variable_name>}`
- A full domain – `http://${stageVariables.<variable_name>}/resource/operation`
- A subdomain – `http://${stageVariables.<variable_name>}.example.com/resource/operation`

- A path – `http://example.com/${stageVariables.<variable_name>}/bar`
- A query string – `http://example.com/foo?q=${stageVariables.<variable_name>}`

Lambda functions

You can use a stage variable in place of a Lambda function name or alias, as shown in the following examples.

- `arn:aws:apigateway:<region>:lambda:path/2015-03-31/functions/arn:aws:lambda:<region>:<account_id>:function:${stageVariables.<function_variable_name>}/invocations`
- `arn:aws:apigateway:<region>:lambda:path/2015-03-31/functions/arn:aws:lambda:<region>:<account_id>:function:<function_name>:${stageVariables.<version_variable_name>}/invocations`

 **Note**

To use a stage variable for a Lambda function, the function must be in the same account as the API. Stage variables don't support cross-account Lambda functions.

AWS integration credentials

You can use a stage variable as part of an AWS user or role credential ARN, as shown in the following example.

- `arn:aws:iam::<account_id>:${stageVariables.<variable_name>}`

Deploy WebSocket APIs in API Gateway

After creating your WebSocket API, you must deploy it to make it available for your users to invoke.

To deploy an API, you create an [API deployment](#) and associate it with a [stage](#). Each stage is a snapshot of the API and is made available for client apps to call.

Important

Every time you update an API, you must redeploy it. Changes to anything other than stage settings require a redeployment, including modifications to the following resources:

- Routes
- Integrations
- Authorizers

By default you are limited to 10 stages for each API. We recommend that you re-use stages for your deployments.

To call a deployed WebSocket API, the client sends a message to the API's URL. The URL is determined by the API's hostname and stage name.

Note

API Gateway will support payloads up to 128 KB with a maximum frame size of 32 KB. If a message exceeds 32 KB, it must be split into multiple frames, each 32 KB or smaller.

Using the API's default domain name, the URL of (for example) a WebSocket API in a given stage (`{stageName}`) is in the following format:

```
wss://{api-id}.execute-api.{region}.amazonaws.com/{stageName}
```

To make the WebSocket API's URL more user-friendly, you can create a custom domain name (e.g., `api.example.com`) to replace the default host name of the API. The configuration process is the same as for REST APIs. For more information, see [the section called “Custom domain names”](#).

Stages enable robust version control of your API. For example, you can deploy an API to a test stage and a prod stage, and use the test stage as a test build and use the prod stage as a stable build. After the updates pass the test, you can promote the test stage to the prod stage. The promotion can be done by redeploying the API to the prod stage. For more details about stages, see [the section called “Set up a stage”](#).

Topics

- [Create a WebSocket API deployment using the AWS CLI](#)
- [Create a WebSocket API deployment using the API Gateway console](#)

Create a WebSocket API deployment using the AWS CLI

The following [create-deployment](#) command creates a deployment:

```
aws apigatewayv2 --region us-east-1 create-deployment --api-id aabbcccddee
```

The output will look like the following:

```
{  
    "DeploymentId": "fedcba",  
    "DeploymentStatus": "DEPLOYED",  
    "CreatedDate": "2018-11-15T06:49:09Z"  
}
```

The deployed API is not callable until you associate the deployment with a stage. You can create a new stage or reuse a stage that you have previously created.

The following [create-stage](#) command creates a new stage and associates it with the deployment:

```
aws apigatewayv2 --region us-east-1 create-stage --api-id aabbcccddee --deployment-id  
fedcba --stage-name test
```

The output looks like the following:

```
{  
    "StageName": "test",  
    "CreatedDate": "2018-11-15T06:50:28Z",  
    "DeploymentId": "fedcba",  
    "DefaultRouteSettings": {  
        "MetricsEnabled": false,  
        "ThrottlingBurstLimit": 5000,  
        "DataTraceEnabled": false,  
        "ThrottlingRateLimit": 10000.0  
    },  
    "LastUpdatedDate": "2018-11-15T06:50:28Z",  
    "StageVariables": {},  
    "RouteSettings": {}
```

{}

You can also reuse an existing stage by updating the stage's deploymentId property with the newly created deployment ID (*deployment-id*). The following [update-stage](#) command updates the stage's deployment ID:

```
aws apigatewayv2 update-stage --region region \  
  --api-id api-id \  
  --stage-name stage-name \  
  --deployment-id deployment-id
```

Create a WebSocket API deployment using the API Gateway console

To use the API Gateway console to create a deployment for a WebSocket API:

1. Sign in to the API Gateway console and choose the API.
2. Choose **Deploy API**.
3. Choose the desired stage from the dropdown list or enter the name of a new stage.

Security policy for WebSocket APIs in API Gateway

API Gateway enforces a security policy of TLS_1_2 for all WebSocket API endpoints.

A *security policy* is a predefined combination of minimum TLS version and cipher suites offered by Amazon API Gateway. The TLS protocol addresses network security problems such as tampering and eavesdropping between a client and server. When your clients establish a TLS handshake to your API through the custom domain, the security policy enforces the TLS version and cipher suite options your clients can choose to use. This security policy accepts TLS 1.2 and TLS 1.3 traffic and rejects TLS 1.0 traffic.

Supported TLS protocols and ciphers for WebSocket APIs

The following table describes the supported TLS protocols for WebSocket APIs.

TLS protocols	TLS_1_2 security policy
TLSv1.3	Yes
TLSv1.2	Yes

The following table describes the TLS ciphers that are available for the TLS 1_2 security policy for WebSocket APIs.

TLS ciphers	TLS_1_2 security policy
TLS_AES_128_GCM_SHA256	Yes
TLS_AES_256_GCM_SHA384	Yes
TLS_CHACHA20_POLY1305_SHA256	Yes
ECDHE-ECDSA-AES128-GCM-SHA256	Yes
ECDHE-RSA-AES128-GCM-SHA256	Yes
ECDHE-ECDSA-AES128-SHA256	Yes
ECDHE-RSA-AES128-SHA256	Yes
ECDHE-ECDSA-AES256-GCM-SHA384	Yes

TLS ciphers	TLS_1_2 security policy
ECDHE-RSA-AES256-GCM-SHA384	Yes
ECDHE-ECDSA-AES256-SHA384	Yes
ECDHE-RSA-AES256-SHA384	Yes
AES128-GCM-SHA256	Yes
AES128-SHA256	Yes
AES256-GCM-SHA384	Yes
AES256-SHA256	Yes

OpenSSL and RFC cipher names

OpenSSL and IETF RFC 5246, use different names for the same ciphers. For a list of the cipher names, see [the section called “OpenSSL and RFC cipher names”](#).

Information about REST APIs and HTTP APIs

For more information about REST APIs and HTTP APIs, see [the section called “Choose a security policy”](#) and [the section called “Security policy for HTTP APIs in API Gateway”](#).

Custom domain names for WebSocket APIs in API Gateway

Custom domain names are simpler and more intuitive URLs that you can provide to your API users.

After deploying your API, you (and your customers) can invoke the API using the default base URL of the following format:

`https://api-id.execute-api.region.amazonaws.com/stage`

where *api-id* is generated by API Gateway, *region* is the AWS Region, and *stage* is specified by you when deploying the API.

The hostname portion of the URL, *api-id*.execute-api.*region*.amazonaws.com refers to an API endpoint. The default API endpoint name is randomly generated, difficult to recall, and not user-friendly.

With custom domain names, you can set up your API's hostname, and choose a base path (for example, myservice) to map the alternative URL to your API. For example, a more user-friendly API base URL can become:

`https://api.example.com/myservice`

Considerations

The following considerations might impact your use of a custom domain name.

- If you map a custom domain name to a WebSocket API, you can't map it to a REST API or an HTTP API.
- Only Regional custom domain names are supported.
- For the minimum TLS version, only TLS 1.2 is supported.
- You must create or update your DNS provider's resource record to map to your API endpoint. Without such a mapping, API requests bound for the custom domain name cannot reach API Gateway.
- You can support an almost infinite number of domain names without exceeding the default quota by using a wildcard certificate. For more information, see [the section called "Wildcard custom domain names"](#).

Prerequisites

The following are prerequisites for a custom domain name.

Register a domain name

You must have a registered internet domain name in order to set up custom domain names for your APIs. You can register your internet domain name using [Amazon Route 53](#) or using a third-

party domain registrar of your choice. Your custom domain name can be the name of a subdomain or the root domain (also known as the "zone apex") of a registered internet domain.

Your domain name must follow the [RFC 1035](#) specification and can have a maximum of 63 octets per label and 255 octets in total.

Certificates for custom domain names

Before setting up a custom domain name for an API, you must have an SSL/TLS certificate ready in ACM. If ACM is not available in the AWS Region where you are creating your custom domain name, you must import a certificate to API Gateway in that Region.

To import an SSL/TLS certificate, you must provide the PEM-formatted SSL/TLS certificate body, its private key, and the certificate chain for the custom domain name.

Each certificate stored in ACM is identified by its ARN. With certificates issued by ACM, you do not have to worry about exposing any sensitive certificate details, such as the private key. To use an AWS managed certificate for a domain name, you simply reference its ARN.

If your application uses certificate pinning, sometimes known as SSL pinning, to pin an ACM certificate, the application might not be able to connect to your domain after AWS renews the certificate. For more information, see [Certificate pinning problems](#) in the *AWS Certificate Manager User Guide*.

Wildcard custom domain names

With wildcard custom domain names, you can support an almost infinite number of domain names without exceeding the [default quota](#). For example, you could give each of your customers their own domain name, *customername*.api.example.com.

To create a wildcard custom domain name, specify a wildcard (*) as the first subdomain of a custom domain that represents all possible subdomains of a root domain.

For example, the wildcard custom domain name *.example.com results in subdomains such as a.example.com, b.example.com, and c.example.com, which all route to the same domain.

Wildcard custom domain names support distinct configurations from API Gateway's standard custom domain names. For example, in a single AWS account, you can configure *.example.com and a.example.com to behave differently.

You can use the `$context.domainName` and `$context.domainPrefix` context variables to determine the domain name that a client used to call your API. To learn more about context variables, see [Variables for data transformations for API Gateway](#).

To create a wildcard custom domain name, you must provide a certificate issued by ACM that has been validated using either the DNS or the email validation method.

 **Note**

You can't create a wildcard custom domain name if a different AWS account has created a custom domain name that conflicts with the wildcard custom domain name. For example, if account A has created `a.example.com`, then account B can't create the wildcard custom domain name `*.example.com`.

If account A and account B share an owner, you can contact the [AWS Support Center](#) to request an exception.

Next steps for custom domain names

To set up a custom domain name for an HTTP API, you use documentation from the REST API section of the API Gateway Developer Guide.

First, specify a certificate for your custom domain name. For more information, see [the section called "Get certificates ready in AWS Certificate Manager"](#). Next, you create a Regional custom domain name. For more information, see [the section called "Set up a Regional custom domain name"](#).

Map API stages to a custom domain name for WebSocket APIs

You use API mappings to connect API stages to a custom domain name. After you create a domain name and configure DNS records, you use API mappings to send traffic to your APIs through your custom domain name.

An API mapping specifies an API, a stage, and optionally a path to use for the mapping. For example, you can map the production stage of an API to `wss://api.example.com/orders`.

Before you create an API mapping, you must have an API, a stage, and a custom domain name. To learn more about creating a custom domain name, see [the section called "Set up a Regional custom domain name"](#).

Restrictions

- In an API mapping, the custom domain name and mapped APIs must be in the same AWS account.
- API mappings must contain only letters, numbers, and the following characters: \$-_.+!*'().
- The maximum length for the path in an API mapping is 300 characters.
- You can't map WebSocket APIs to the same custom domain name as an HTTP API or REST API.
- If you create an API mappings with multiple levels, API Gateway converts all header names to lowercase.

Create an API mapping

To create an API mapping, you must first create a custom domain name, API, and stage. For information about creating a custom domain name, see [the section called “Set up a Regional custom domain name”](#).

AWS Management Console

To create an API mapping

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose **Custom domain names**.
3. Select a custom domain name that you've already created.
4. Choose **API mappings**.
5. Choose **Configure API mappings**.
6. Choose **Add new mapping**.
7. Enter an **API**, a **Stage**, and optionally a **Path**.
8. Choose **Save**.

AWS CLI

The following [create-api-mapping](#) command creates an API mapping. In this example, API Gateway sends requests to api.example.com/v1 to the specified API and stage.

```
aws apigatewayv2 create-api-mapping \
```

```
--domain-name api.example.com \
--api-mapping-key v1 \
--api-id a1b2c3d4 \
--stage test
```

CloudFormation

The following CloudFormation example creates an API mapping.

```
MyApiMapping:
  Type: 'AWS::ApiGatewayV2::ApiMapping'
  Properties:
    DomainName: api.example.com
    ApiMappingKey: 'v1'
    ApiId: !Ref MyApi
    Stage: !Ref MyStage
```

IP address types for custom domain names for WebSocket APIs

When you create an custom domain name, you specify the type of IP addresses that can invoke your domain. You can choose IPv4 to resolve IPv4 addresses to invoke your domain, or you can choose dualstack to allow both IPv4 and IPv6 addresses to invoke your domain. We recommend that you set the IP address type to dualstack to alleviate IP space exhaustion or for your security posture. For more information about the benefits of a dualstack IP address type, see [IPv6 on AWS](#).

Considerations for IP address types

The following considerations might impact your use of IP address types.

- The default IP address type for API Gateway custom domain names is IPv4.
- Your custom domain name doesn't need to have the same IP address type for all APIs mapped to it. If you disable your default API endpoint, this might affect how callers can invoke your API.

Change the IP address type of custom domain name

You can change the IP address type by updating the domain name's endpoint configuration. You can update the endpoint configuration by using the AWS Management Console, the AWS CLI, CloudFormation, or an AWS SDK.

AWS Management Console

To change the IP address type of a custom domain name

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose a public custom domain name.
3. Choose **Endpoint configuration**.
4. For IP address type, select either **IPv4** or **Dualstack**.
5. Choose **Save**.

AWS CLI

The following [update-domain-name](#) command updates an API to have an IP address type of dualstack:

```
aws apigatewayv2 update-domain-name \
--domain-name dualstack.example.com \
--domain-name-configurations CertificateArn=arn:aws:acm:us-
east-1:111122223333:certificate/abcd1234-5678-abc,IpAddressType=dualstack
```

The output will look like the following:

```
{
    "ApiMappingSelectionExpression": "$request.basepath",
    "DomainName": "dualstack.example.com",
    "DomainNameConfigurations": [
        {
            "ApiGatewayDomainName": "d-abcd1234.execute-api.us-
east-1.amazonaws.com",
            "CertificateArn": "arn:aws:acm:us-east-1:111122223333:certificate/
abcd1234-5678-abc",
            "DomainNameStatus": "AVAILABLE",
            "EndpointType": "REGIONAL",
            "HostedZoneId": "Z3LQWSYCGH4ADY",
            "SecurityPolicy": "TLS_1_2",
            "IpAddressType": "dualstack"
        }
    ],
    "Tags": {}
}
```

Disable the default endpoint for WebSocket APIs

By default, clients can invoke your API by using the execute-api endpoint that API Gateway generates for your API. To ensure that clients can access your API only by using a custom domain name, disable the default execute-api endpoint. When you disable the default endpoint, it affects all stages of an API.

The following procedure shows how to disable the default endpoint for a WebSocket API.

AWS Management Console

1. Sign in to the API Gateway console at <https://console.aws.amazon.com/apigateway>.
2. Choose an WebSocket API.
3. Choose **API settings**.
4. On **API details**, choose **Edit**.
5. For **Default endpoint**, select **Inactive**.
6. Choose **Save changes**.
7. On the main navigation pane, choose **Routes**.
8. Choose **Deploy**, and then redeploy your API or create a new stage for the change to take effect.

AWS CLI

The following [update-api](#) command disables the default endpoint for an WebSocket API:

```
aws apigatewayv2 update-api \
--api-id abcdef123 \
--disable-execute-api-endpoint
```

After you disable the default endpoint, you must deploy your API for the change to take effect.

The following AWS CLI command creates a deployment.

```
aws apigatewayv2 create-deployment \
--api-id abcdef123 \
--stage-name dev
```

Protect your WebSocket APIs in API Gateway

API Gateway provides a number of ways to protect your API from certain threats, like malicious users or spikes in traffic. You can protect your API using strategies like generating SSL certificates or setting throttling targets. For more information about generating SSL certificates, see [the section called "Client certificates"](#). The rest of this section covers setting throttling targets.

You can configure throttling for your APIs to help protect them from being overwhelmed by too many requests. Throttles are applied on a best-effort basis and should be thought of as targets rather than guaranteed request ceilings.

API Gateway throttles requests to your API using the token bucket algorithm, where a token counts for a request. Specifically, API Gateway examines the rate and a burst of request submissions against all APIs in your account, per Region. In the token bucket algorithm, a burst can allow predefined overrun of those limits, but other factors can also cause limits to be overrun in some cases.

When request submissions exceed the steady-state request rate and burst limits, API Gateway begins to throttle requests. Clients may receive 429 Too Many Requests error responses at this point. Upon catching such exceptions, the client can resubmit the failed requests in a way that is rate limiting.

As an API developer, you can set the target limits for individual API stages or routes to improve overall performance across all APIs in your account.

Account-level throttling per Region

By default, API Gateway limits the steady-state requests per second (RPS) across all APIs within an AWS account, per Region. It also limits the burst (that is, the maximum bucket size) across all APIs within an AWS account, per Region. In API Gateway, the burst limit represents the target maximum number of concurrent request submissions that API Gateway will fulfill before returning 429 Too Many Requests error responses. For more information on throttling quotas, see [Quotas and important notes](#).

Per-account limits are applied to all APIs in an account in a specified Region. The account-level rate limit can be increased upon request - higher limits are possible with APIs that have shorter timeouts and smaller payloads. To request an increase of account-level throttling limits per Region, contact the [AWS Support Center](#). For more information, see [Quotas and important notes](#). Note that these limits can't be higher than the AWS throttling limits.

Route-level throttling

You can set route-level throttling to override the account-level request throttling limits for a specific stage or for individual routes in your API. The default route throttling limits can't exceed account-level rate limits.

You can configure route-level throttling by using the AWS CLI. The following [update-stage](#) command configures custom throttling for the specified stage and route of an API:

```
aws apigatewayv2 update-stage \
  --api-id a1b2c3d4 \
  --stage-name dev \
  --route-settings '{"messages": \
    {"ThrottlingBurstLimit":100, "ThrottlingRateLimit":2000}}'
```

Monitor WebSocket APIs in API Gateway

You can use CloudWatch metrics and CloudWatch Logs to monitor WebSocket APIs. By combining logs and metrics, you can log errors and monitor your API's performance.

Note

API Gateway might not generate logs and metrics in the following cases:

- 413 Request Entity Too Large errors
- Excessive 429 Too Many Requests errors
- 400 series errors from requests sent to a custom domain that has no API mapping
- 500 series errors caused by internal failures

Topics

- [Monitor WebSocket API execution with CloudWatch metrics](#)
- [Configure logging for WebSocket APIs in API Gateway](#)

Monitor WebSocket API execution with CloudWatch metrics

You can use [Amazon CloudWatch](#) metrics to monitor WebSocket APIs. The configuration is similar to that used for REST APIs. For more information, see [Monitor REST API execution with Amazon CloudWatch metrics](#).

The following metrics are supported for WebSocket APIs:

Metric	Description
ConnectCount	The number of messages sent to the \$connect route integration.
MessageCount	The number of messages sent to the WebSocket API, either from or to the client.
IntegrationError	The number of requests that return a 4XX/5XX response from the integration.
ClientError	The number of requests that have a 4XX response returned by API Gateway before the integration is invoked.
ExecutionError	Errors that occurred when calling the integration.
IntegrationLatency	The time difference between API Gateway sending the request to the integration and API Gateway receiving the response from the integration. Suppressed for callbacks and mock integrations.

You can use the dimensions in the following table to filter API Gateway metrics.

Dimension	Description
Apild	Filters API Gateway metrics for an API with the specified API ID.
Apild, Stage	Filters API Gateway metrics for an API stage with the specified API ID and stage ID.
Apild, Method, Resource, Stage	<p>Filters API Gateway metrics for an API method with the specified API ID, stage ID, resource path, and route ID.</p> <p>API Gateway will not send these metrics unless you have explicitly enabled detailed CloudWatch metrics. You can do this by calling the UpdateStage action of the API Gateway V2 REST API to update the <code>detailedMetricsEnabled</code> property to <code>true</code>. Alternatively, you can call the update-stage AWS CLI command to update the <code>DetailedMetricsEnabled</code> property to <code>true</code>. Enabling such metrics will incur additional charges to your account. For pricing information, see Amazon CloudWatch Pricing.</p>

Configure logging for WebSocket APIs in API Gateway

You can enable logging to write logs to CloudWatch Logs. There are two types of API logging in CloudWatch: execution logging and access logging. In execution logging, API Gateway manages the CloudWatch Logs. The process includes creating log groups and log streams, and reporting to the log streams any caller's requests and responses.

To improve your security posture, we recommend that you use execution logging at the ERROR or INFO level. You might need to do this to comply with various compliance frameworks. For more information, see [Amazon API Gateway controls](#) in the *AWS Security Hub User Guide*.

In access logging, you, as an API developer, want to log who has accessed your API and how the caller accessed the API. You can create your own log group or choose an existing log group that could be managed by API Gateway. To specify the access details, you select \$context variables (expressed in a format of your choosing) and choose a log group as the destination.

For instructions on how to set up CloudWatch logging, see [the section called “Set up CloudWatch API logging using the API Gateway console”](#).

When you specify the **Log Format**, you can choose which context variables to log. The following variables are supported.

Parameter	Description
\$context.apiId	The identifier API Gateway assigns to your API.
\$context.authorize.error	The authorization error message.
\$context.authorize.latency	The authorization latency in ms.
\$context.authorize.status	The status code returned from an authorization attempt.
\$context.authorizer.error	The error message returned from an authorizer.
\$context.authorizer.integrationLatency	The Lambda authorizer latency in ms.

Parameter	Description
\$context.authorizer.integrationStatus	The status code returned from a Lambda authorizer.
\$context.authorizer.latency	The authorizer latency in ms.
\$context.authorizer.requestId	The AWS endpoint's request ID.
\$context.authorizer.status	The status code returned from an authorizer.
\$context.authorizer.principalId	The principal user identification that is associated with the token sent by the client and returned from an API Gateway Lambda authorizer Lambda function. (A Lambda authorizer was formerly known as a custom authorizer.)
\$context.authorizer. <i>property</i>	<p>The stringified value of the specified key-value pair of the context map returned from an API Gateway Lambda authorizer function. For example, if the authorizer returns the following context map:</p> <pre data-bbox="856 1214 1476 1531"> "context" : { "key": "value", "numKey": 1, "boolKey": true } </pre> <p>calling \$context.authorizer.key returns the "value" string, calling \$context.authorizer.numKey returns the "1" string, and calling \$context.authorizer.boolKey returns the "true" string.</p>

Parameter	Description
\$context.authenticate.error	The error message returned from an authentication attempt.
\$context.authenticate.latency	The authentication latency in ms.
\$context.authenticate.status	The status code returned from an authentication attempt.
\$context.connectedAt	The Epoch -formatted connection time.
\$context.connectionId	A unique ID for the connection that can be used to make a callback to the client.
\$context.domainName	A domain name for the WebSocket API. This can be used to make a callback to the client (instead of a hardcoded value).
\$context.error.message	A string that contains an API Gateway error message.
\$context.error.messageString	The quoted value of \$context.error.message , namely "\$context.error.message" .
\$context.error.responseType	The error response type.
\$context.error.validationErrorString	A string that contains a detailed validation error message.
\$context.eventType	The event type: CONNECT, MESSAGE, or DISCONNECT .
\$context.extendedRequestId	Equivalent to \$context.requestId .
\$context.identity.accountId	The AWS account ID associated with the request.

Parameter	Description
\$context.identity.apiKey	The API owner key associated with key-enabled API request.
\$context.identity.apiKeyId	The API key ID associated with the key-enabled API request
\$context.identity.caller	The principal identifier of the caller that signed the request. Supported for routes that use IAM authorization.
\$context.identity.cognitoAuthenticationProvider	<p>A comma-separated list of all the Amazon Cognito authentication providers used by the caller making the request. Available only if the request was signed with Amazon Cognito credentials.</p>
	<p>For example, for an identity from an Amazon Cognito user pool, <code>cognito-idp.<i>region</i>.amazonaws.com/ <i>user_pool_id</i></code>, <code>cognito-idp. <i>region</i>.amazonaws.com/ <i>user_pool_id</i></code>:CognitoSignIn: <i>token subject claim</i></p>
	<p>For information about the available Amazon Cognito authentication providers, see Using Federated Identities in the Amazon Cognito Developer Guide.</p>
\$context.identity.cognitoAuthenticationType	The Amazon Cognito authentication type of the caller making the request. Available only if the request was signed with Amazon Cognito credentials. Possible values include <code>authenticated</code> for authenticated identities and <code>unauthenticated</code> for unauthenticated identities.

Parameter	Description
\$context.identity.cognitoId entityId	The Amazon Cognito identity ID of the caller making the request. Available only if the request was signed with Amazon Cognito credentials.
\$context.identity.cognitoId entityPoolId	The Amazon Cognito identity pool ID of the caller making the request. Available only if the request was signed with Amazon Cognito credentials.
\$context.identity.principalOrgId	The AWS organization ID . Supported for routes that use IAM authorization.
\$context.identity.sourceIp	The source IP address of the TCP connection making the request to API Gateway.
\$context.identity.user	The principal identifier of the user that will be authorized against resource access. Supported for routes that use IAM authorization.
\$context.identity.userAgent	The user agent of the API caller.
\$context.identity.userArn	The Amazon Resource Name (ARN) of the effective user identified after authentication.
\$context.integration.error	The error message returned from an integration.
\$context.integration.integrationStatus	For Lambda proxy integration, the status code returned from AWS Lambda, not from the backend Lambda function code.
\$context.integration.latency	The integration latency in ms. Equivalent to \$context.integrationLatency .
\$context.integration.requestId	The AWS endpoint's request ID. Equivalent to \$context.awsEndpointRequestId .

Parameter	Description
\$context.integration.status	The status code returned from an integration. For Lambda proxy integrations, this is the status code that your Lambda function code returns. Equivalent to <code>\$context.integrationStatus</code> .
\$context.integrationLatency	The integration latency in ms, available for access logging only.
\$context.messageId	A unique server-side ID for a message. Available only when the <code>\$context.eventType</code> is MESSAGE.
\$context.requestId	Same as <code>\$context.extendedRequestId</code> .
\$context.requestTime	The CLF -formatted request time (dd/MMM/yy yy:HH:mm:ss +-hhmm).
\$context.requestTimeEpoch	The Epoch -formatted request time, in milliseconds.
\$context.routeKey	The selected route key.
\$context.stage	The deployment stage of the API call (for example, beta or prod).
\$context.status	The response status.
\$context.waf.error	The error message returned from AWS WAF.
\$context.waf.latency	The AWS WAF latency in ms.
\$context.waf.status	The status code returned from AWS WAF.

Examples of some commonly used access log formats are shown in the API Gateway console and are listed as follows.

- CLF ([Common Log Format](#)):

```
$context.identity.sourceIp $context.identity.caller \
identity.user [$context.requestTime] "$context.eventType $context.routeKey
$context.connectionId" \
$context.status $context.requestId
```

The continuation characters (\) are meant as a visual aid. The log format must be a single line. You can add a newline character (\n) at the end of the log format to include a newline at the end of each log entry.

- JSON:

```
{
  "requestId": "$context.requestId", \
  "ip": "$context.identity.sourceIp", \
  "caller": "$context.identity.caller", \
  "user": "$context.identity.user", \
  "requestTime": "$context.requestTime", \
  "eventType": "$context.eventType", \
  "routeKey": "$context.routeKey", \
  "status": "$context.status", \
  "connectionId": "$context.connectionId"
}
```

The continuation characters (\) are meant as a visual aid. The log format must be a single line. You can add a newline character (\n) at the end of the log format to include a newline at the end of each log entry.

- XML:

```
<request id="$context.requestId"> \
<ip>$context.identity.sourceIp</ip> \
<caller>$context.identity.caller</caller> \
<user>$context.identity.user</user> \
<requestTime>$context.requestTime</requestTime> \
<eventType>$context.eventType</eventType> \
<routeKey>$context.routeKey</routeKey> \
<status>$context.status</status> \
<connectionId>$context.connectionId</connectionId> \
</request>
```

The continuation characters (\) are meant as a visual aid. The log format must be a single line. You can add a newline character (\n) at the end of the log format to include a newline at the end of each log entry.

- CSV (comma-separated values):

```
$context.identity.sourceIp,$context.identity.caller, \
$context.identity.user,$context.requestTime,$context.eventType, \
$context.routeKey,$context.connectionId,$context.status, \
$context.requestId
```

The continuation characters (\) are meant as a visual aid. The log format must be a single line. You can add a newline character (\n) at the end of the log format to include a newline at the end of each log entry.

API Gateway Amazon Resource Name (ARN) reference

The following tables list the Amazon Resource Names (ARNs) for API Gateway resources. To learn more about using ARNs in AWS Identity and Access Management policies, see [How Amazon API Gateway works with IAM](#) and [Control access to a REST API with IAM permissions](#).

HTTP API and WebSocket API resources

Resource	ARN
AccessLogSettings	arn: <i>partition</i> :apigateway: <i>region</i> ::/apis/ <i>api-id</i> /stages/ <i>stage-name</i> /accesslogsettings
Api	arn: <i>partition</i> :apigateway: <i>region</i> ::/apis/ <i>api-id</i>
Apis	arn: <i>partition</i> :apigateway: <i>region</i> ::/apis
Authorizer	arn: <i>partition</i> :apigateway: <i>region</i> ::/apis/ <i>api-id</i> /authorizers/ <i>id</i>
Authorizers	arn: <i>partition</i> :apigateway: <i>region</i> ::/apis/ <i>api-id</i> /authorizers
Cors	arn: <i>partition</i> :apigateway: <i>region</i> ::/apis/ <i>api-id</i> /cors
Deployment	arn: <i>partition</i> :apigateway: <i>region</i> ::/apis/ <i>api-id</i> /deployments/ <i>id</i>

Resource	ARN
Deployments	arn: <i>partition</i> :apigateway ay: <i>region</i> ::/apis/ <i>api-id</i> /deployments
ExportedAPI	arn: <i>partition</i> :apigateway ay: <i>region</i> ::/apis/ <i>api-id</i> /exports/ <i>specification</i>
Integration	arn: <i>partition</i> :apigateway ay: <i>region</i> ::/apis/ <i>api-id</i> /integrations/ <i>integration-id</i>
Integrations	arn: <i>partition</i> :apigateway ay: <i>region</i> ::/apis/ <i>api-id</i> /integrations
IntegrationResponse	arn: <i>partition</i> :apigateway ay: <i>region</i> ::/apis/ <i>api-id</i> /integrationresponses/ <i>integration-response</i>
IntegrationResponses	arn: <i>partition</i> :apigateway ay: <i>region</i> ::/apis/ <i>api-id</i> /integrationresponses
Model	arn: <i>partition</i> :apigateway ay: <i>region</i> ::/apis/ <i>api-id</i> /models/ <i>id</i>
Models	arn: <i>partition</i> :apigateway ay: <i>region</i> ::/apis/ <i>api-id</i> /models
ModelTemplate	arn: <i>partition</i> :apigateway ay: <i>region</i> ::/apis/ <i>api-id</i> /models/ <i>id</i> /template

Resource	ARN
Route	arn: <i>partition</i> :apigateway ay: <i>region</i> ::/apis/ <i>api-id</i> /routes/ <i>id</i>
Routes	arn: <i>partition</i> :apigateway ay: <i>region</i> ::/apis/ <i>api-id</i> /routes
RouteRequestParameter	arn: <i>partition</i> :apigateway ay: <i>region</i> ::/apis/ <i>api-id</i> /routes/ <i>id</i> /requestparameters/ <i>key</i>
RouteResponse	arn: <i>partition</i> :apigateway ay: <i>region</i> ::/apis/ <i>api-id</i> /routes/ <i>id</i> /routeresponses/ <i>id</i>
RouteResponses	arn: <i>partition</i> :apigateway ay: <i>region</i> ::/apis/ <i>api-id</i> /routes/ <i>id</i> /routeresponses
RouteSettings	arn: <i>partition</i> :apigateway ay: <i>region</i> ::/apis/ <i>api-id</i> /stages/ <i>stage-name</i> /routesettings/ <i>route-key</i>
Stage	arn: <i>partition</i> :apigateway ay: <i>region</i> ::/apis/ <i>api-id</i> /stages/ <i>stage-name</i>
Stages	arn: <i>partition</i> :apigateway ay: <i>region</i> ::/apis/ <i>api-id</i> /stages
VpcLink	arn: <i>partition</i> :apigateway ay: <i>region</i> ::/vpclinks/ <i>vpclink-id</i>
VpcLinks	arn: <i>partition</i> :apigateway ay: <i>region</i> ::/vpclinks

REST API resources

Resource	ARN
Account	arn: <i>partition</i> :apigateway ay: <i>region</i> ::/account
ApiKey	arn: <i>partition</i> :apigateway ay: <i>region</i> ::/apikeys/ <i>id</i>
ApiKeys	arn: <i>partition</i> :apigateway ay: <i>region</i> ::/apikeys
Authorizer	arn: <i>partition</i> :apigateway ay: <i>region</i> ::/restapis/ <i>api-id</i> / authorizers/ <i>id</i>
Authorizers	arn: <i>partition</i> :apigateway ay: <i>region</i> ::/restapis/ <i>api-id</i> / authorizers
ClientCertificate	arn: <i>partition</i> :apigateway ay: <i>region</i> ::/clientcertificates/ <i>id</i>
ClientCertificates	arn: <i>partition</i> :apigateway ay: <i>region</i> ::/clientcertificates
Deployment	arn: <i>partition</i> :apigateway ay: <i>region</i> ::/restapis/ <i>api-id</i> / deployments/ <i>id</i>
Deployments	arn: <i>partition</i> :apigateway ay: <i>region</i> ::/restapis/ <i>api-id</i> / deployments

Resource	ARN
DocumentationPart	arn: <i>partition</i> :apigatew ay: <i>region</i> ::/restapis/ <i>api-id</i> / documentation/parts/ <i>id</i>
DocumentationParts	arn: <i>partition</i> :apigatew ay: <i>region</i> ::/restapis/ <i>api-id</i> / documentation/parts
DocumentationVersion	arn: <i>partition</i> :apigatew ay: <i>region</i> ::/restapis/ <i>api-id</i> / documentation/versions/ <i>version</i>
DocumentationVersions	arn: <i>partition</i> :apigatew ay: <i>region</i> ::/restapis/ <i>api-id</i> / documentation/versions
GatewayResponse	arn: <i>partition</i> :apigatew ay: <i>region</i> ::/restapis/ <i>api-id</i> / gatewayresponses/ <i>response-type</i>
GatewayResponses	arn: <i>partition</i> :apigatew ay: <i>region</i> ::/restapis/ <i>api-id</i> / gatewayresponses
Integration	arn: <i>partition</i> :apigatew ay: <i>region</i> ::/restapis/ <i>api-id</i> / resources/ <i>resource-id</i> /methods/ <i>http-method</i> /integration
IntegrationResponse	arn: <i>partition</i> :apigatew ay: <i>region</i> ::/restapis/ <i>api-id</i> / resources/ <i>resource-id</i> /methods/ <i>http-method</i> /integration/respo nses/ <i>status-code</i>

Resource	ARN
Method	<code>arn:partition :apigatew ay: region:::/restapis/ <i>api-id</i>/ resources/ <i>resource-id</i> /methods/ <i>http-method</i></code>
MethodResponse	<code>arn:partition :apigatew ay: region:::/restapis/ <i>api-id</i>/ resources/ <i>resource-id</i> /methods/ <i>http-method</i> /responses/ <i>status-co de</i></code>
Model	<code>arn:partition :apigatew ay: region:::/restapis/ <i>api-id</i>/ models/<i>model-name</i></code>
Models	<code>arn:partition :apigatew ay: region:::/restapis/ <i>api-id</i>/ models</code>
RequestValidator	<code>arn:partition :apigatew ay: region:::/restapis/ <i>api-id</i>/ requestvalidators/ <i>id</i></code>
RequestValidators	<code>arn:partition :apigatew ay: region:::/restapis/ <i>api-id</i>/ requestvalidators</code>
Resource	<code>arn:partition :apigatew ay: region:::/restapis/ <i>api-id</i>/ resources/ <i>id</i></code>
Resources	<code>arn:partition :apigatew ay: region:::/restapis/ <i>api-id</i>/ resources</code>

Resource	ARN
RestApi	arn: <i>partition</i> :apigateway ay: <i>region</i> ::/restapis/ <i>api-id</i>
RestApis	arn: <i>partition</i> :apigateway ay: <i>region</i> ::/restapis
Stage	arn: <i>partition</i> :apigateway ay: <i>region</i> ::/restapis/ <i>api-id</i> / stages/ <i>stage-name</i>
Stages	arn: <i>partition</i> :apigateway ay: <i>region</i> ::/restapis/ <i>api-id</i> / stages
Tags	arn: <i>partition</i> :apigateway ay: <i>region</i> ::/tags/ <i>url-encoded-</i> <i>resource-arn</i>
Template	arn: <i>partition</i> :apigateway ay: <i>region</i> ::/restapis/models/ <i>model-name</i> /template
UsagePlan	arn: <i>partition</i> :apigateway ay: <i>region</i> ::/usageplans/ <i>usageplan</i> - <i>id</i>
UsagePlans	arn: <i>partition</i> :apigateway ay: <i>region</i> ::/usageplans
UsagePlanKey	arn: <i>partition</i> :apigateway ay: <i>region</i> ::/usageplans/ <i>usageplan</i> - <i>id</i> /keys/ <i>id</i>
UsagePlanKeys	arn: <i>partition</i> :apigateway ay: <i>region</i> ::/usageplans/ <i>usageplan</i> - <i>id</i> /keys

Resource	ARN
VpcLink	arn: <i>partition</i> :apigateway ay: <i>region</i> ::/vpclinks/ <i>vpclink-id</i>
VpcLinks	arn: <i>partition</i> :apigateway ay: <i>region</i> ::/vpclinks

Domain names resources

Resource	ARN
ApiMapping	arn: <i>partition</i> :apigateway ay: <i>region</i> ::/domainnames/ <i>domain-name</i> /apimappings/ <i>id</i>
ApiMappings	arn: <i>partition</i> :apigateway ay: <i>region</i> ::/domainnames/ <i>domain-name</i> /apimappings
BasePathMapping	arn: <i>partition</i> :apigateway ay: <i>region</i> ::/domainnames/ <i>domain-name</i> /basepathmappings/ <i>basepath</i>
BasePathMappings	arn: <i>partition</i> :apigateway ay: <i>region</i> ::/domainnames/ <i>domain-name</i> /basepathmappings
DomainName	arn: <i>partition</i> :apigateway ay: <i>region</i> ::/domainnames/ <i>domain-name</i>
DomainNameAccessAssociation	arn: <i>partition</i> :apigateway ay: <i>region:account-id</i> ::/domainnameaccessassociations/domainname/ <i>domain-name</i> /vpcesource/ <i>vpce-source-id</i>

Resource	ARN
DomainNameAccessAssociations	arn: <i>partition</i> :apigatew ay: <i>region:account-id</i> :/domainn ameaccessassociations
DomainNames	arn: <i>partition</i> :apigatew ay: <i>region</i> ::/domainnames
RoutingRule	arn: <i>partition</i> :apigatew ay: <i>region:account-id</i> :/domainn ames/ <i>domain-name</i> /routingr ules/ <i>routing-rule-id</i>

execute-api (HTTP APIs, WebSocket APIs, and REST APIs)

Resource	ARN
WebSocket API endpoint	arn: <i>partition</i> :execute- api: <i>region:account-id</i> :api- <i>id/stage/route-key</i>
HTTP API and REST API endpoint *	arn: <i>partition</i> :execute- api: <i>region:account-id</i> :api- <i>id/stage/http-method/resource- path</i>
Lambda authorizer **	arn: <i>partition</i> :execute- api: <i>region:account-id</i> :api- <i>id/authorizers/authorizer-id</i>

* The ARN for the \$default route endpoint for HTTP APIs is arn:*partition*:execute-
api:*region:account-id:api-id/*/\$default*.

** This ARN is applicable only when setting the SourceArn condition in the [resource policy](#) for a Lambda authorizer function. For an example, see [the section called "Create a Lambda authorizer"](#).

OpenAPI extensions for API Gateway

The API Gateway extensions support the AWS-specific authorization and API Gateway-specific API integrations for REST APIs and HTTP APIs. In this section, we describe the API Gateway extensions to the OpenAPI specification.

Tip

To understand how the API Gateway extensions are used in an application, you can use the API Gateway console to create a REST API or HTTP API and export it to an OpenAPI definition file. For more information on how to export an API, see [Export a REST API from API Gateway](#) and [Export HTTP APIs from API Gateway](#).

Topics

- [x-amazon-apigateway-any-method object](#)
- [x-amazon-apigateway-cors object](#)
- [x-amazon-apigateway-api-key-source property](#)
- [x-amazon-apigateway-auth object](#)
- [x-amazon-apigateway-authorizer object](#)
- [x-amazon-apigateway-authtype property](#)
- [x-amazon-apigateway-binary-media-types property](#)
- [x-amazon-apigateway-documentation object](#)
- [x-amazon-apigateway-endpoint-access-mode](#)
- [x-amazon-apigateway-endpoint-configuration object](#)
- [x-amazon-apigateway-gateway-responses object](#)
- [x-amazon-apigateway-gateway-responses.gatewayResponse object](#)
- [x-amazon-apigateway-gateway-responses.responseParameters object](#)
- [x-amazon-apigateway-gateway-responses.responseTemplates object](#)
- [x-amazon-apigateway-importexport-version](#)
- [x-amazon-apigateway-integration object](#)
- [x-amazon-apigateway-integrations object](#)

- [x-amazon-apigateway-integration.requestTemplates object](#)
- [x-amazon-apigateway-integration.requestParameters object](#)
- [x-amazon-apigateway-integration.responses object](#)
- [x-amazon-apigateway-integration.response object](#)
- [x-amazon-apigateway-integration.responseTemplates object](#)
- [x-amazon-apigateway-integration.responseParameters object](#)
- [x-amazon-apigateway-integration.tlsConfig object](#)
- [x-amazon-apigateway-minimum-compression-size](#)
- [x-amazon-apigateway-policy](#)
- [x-amazon-apigateway-request-validator property](#)
- [x-amazon-apigateway-requestValidators object](#)
- [x-amazon-apigateway-requestValidators.requestValidator object](#)
- [x-amazon-apigateway-security-policy](#)
- [x-amazon-apigateway-tag-value property](#)

x-amazon-apigateway-any-method object

Specifies the [OpenAPI Operation Object](#) for the API Gateway catch-all ANY method in an [OpenAPI Path Item Object](#). This object can exist alongside other Operation objects and will catch any HTTP method that wasn't explicitly declared.

The following table lists the properties extended by API Gateway. For the other OpenAPI Operation properties, see the OpenAPI specification.

Property name	Type	Description
isDefaultRoute	Boolean	Specifies whether a route is the \$default route. Supported only for HTTP APIs. To learn more, see Create routes for HTTP APIs in API Gateway .

Property name	Type	Description
x-amazon-apigateway-integration	x-amazon-apigateway-integration object	Specifies the integration of the method with the backend. This is an extended property of the OpenAPI Operation object. The integration can be of type AWS, AWS_PROXY , HTTP, HTTP_PROXY , or MOCK.

x-amazon-apigateway-any-method examples

The following example integrates the ANY method on a proxy resource, {proxy+}, with a Lambda function, TestSimpleProxy.

```
"/{proxy+}": {
  "x-amazon-apigateway-any-method": {
    "produces": [
      "application/json"
    ],
    "parameters": [
      {
        "name": "proxy",
        "in": "path",
        "required": true,
        "type": "string"
      }
    ],
    "responses": {},
    "x-amazon-apigateway-integration": {
      "uri": "arn:aws:apigateway:us-east-1:lambda:path/2015-03-31/functions/
arn:aws:lambda:us-east-1:123456789012:function:TestSimpleProxy/invocations",
      "httpMethod": "POST",
      "type": "aws_proxy"
    }
  }
}
```

The following example creates a \$default route for an HTTP API that integrates with a Lambda function, HelloWorld.

```
"/$default": {  
    "x-amazon-apigateway-any-method": {  
        "isDefaultRoute": true,  
        "x-amazon-apigateway-integration": {  
            "type": "AWS_PROXY",  
            "httpMethod": "POST",  
            "uri": "arn:aws:apigateway:us-east-1:lambda:path/2015-03-31/functions/  
arn:aws:lambda:us-east-1:123456789012:function:HelloWorld/invocations",  
            "timeoutInMillis": 1000,  
            "connectionType": "INTERNET",  
            "payloadFormatVersion": 1.0  
        }  
    }  
}
```

x-amazon-apigateway-cors object

Specifies the cross-origin resource sharing (CORS) configuration for an HTTP API. The extension applies to the root-level OpenAPI structure. To learn more, see [Configure CORS for HTTP APIs in API Gateway](#).

Property name	Type	Description
allowOrigins	Array	Specifies the allowed origins.
allowCredentials	Boolean	Specifies whether credentials are included in the CORS request.
exposeHeaders	Array	Specifies the headers that are exposed.
maxAge	Integer	Specifies the number of seconds that the browser should cache preflight request results.
allowMethods	Array	Specifies the allowed HTTP methods.

Property name	Type	Description
allowHeaders	Array	Specifies the allowed headers.

x-amazon-apigateway-cors example

The following is an example CORS configuration for an HTTP API.

```
"x-amazon-apigateway-cors": {  
    "allowOrigins": [  
        "https://www.example.com"  
    ],  
    "allowCredentials": true,  
    "exposeHeaders": [  
        "x-apigateway-header",  
        "x-amz-date",  
        "content-type"  
    ],  
    "maxAge": 3600,  
    "allowMethods": [  
        "GET",  
        "OPTIONS",  
        "POST"  
    ],  
    "allowHeaders": [  
        "x-apigateway-header",  
        "x-amz-date",  
        "content-type"  
    ]  
}
```

x-amazon-apigateway-api-key-source property

Specify the source to receive an API key to throttle API methods that require a key. This API-level property is a `String` type. For more information about configuring a method to require an API key, see [the section called “Configure a method to use API keys with an OpenAPI definition”](#).

Specify the source of the API key for requests. Valid values are:

- `HEADER` for receiving the API key from the `X-API-Key` header of a request.

- AUTHORIZER for receiving the API key from the UsageIdentifierKey from a Lambda authorizer (formerly known as a custom authorizer).

x-amazon-apigateway-api-key-source example

The following example sets the X-API-Key header as the API key source.

OpenAPI 2.0

```
{  
  "swagger" : "2.0",  
  "info" : {  
    "title" : "Test1"  
  },  
  "schemes" : [ "https" ],  
  "basePath" : "/import",  
  "x-amazon-apigateway-api-key-source" : "HEADER",  
  .  
  .  
  .  
}
```

OpenAPI 3.0.1

```
{  
  "openapi" : "3.0.1",  
  "info" : {  
    "title" : "Test1"  
  },  
  "servers" : [ {  
    "url" : "/{basePath}",  
    "variables" : {  
      "basePath" : {  
        "default" : "import"  
      }  
    }  
  } ],  
  "x-amazon-apigateway-api-key-source" : "HEADER",  
  .  
  .  
  .  
}
```

```
}
```

x-amazon-apigateway-auth object

Defines an authorization type to be applied for authorization of method invocations in API Gateway.

Property name	Type	Description
type	string	Specifies the authorization type. Specify "NONE" for open access. Specify "AWS_IAM" to use IAM permissions. Values are case insensitive.

x-amazon-apigateway-auth example

The following example sets the authorization type for an API method.

OpenAPI 3.0.1

```
{
  "openapi": "3.0.1",
  "info": {
    "title": "openapi3",
    "version": "1.0"
  },
  "paths": {
    "/protected-by-iam": {
      "get": {
        "x-amazon-apigateway-auth": {
          "type": "AWS_IAM"
        }
      }
    }
  }
}
```

x-amazon-apigateway-authorizer object

Defines a Lambda authorizer, Amazon Cognito user pool, or JWT authorizer to be applied for authorization of method invocations in API Gateway. This extension applies to the security definition in [OpenAPI 2](#) and the security scheme in [OpenAPI 3](#).

Property name	Type	Description
type	string	<p>The type of the authorizer. This is a required property.</p> <p>For REST APIs, specify token for an authorizer with the caller identity embedded in an authorization token. Specify request for an authorizer with the caller identity contained in request parameters. Specify cognito_user_pools for an authorizer that uses an Amazon Cognito user pool to control access to your API.</p> <p>For HTTP APIs, specify request for a Lambda authorizer with the caller identity contained in request parameters. Specify jwt for a JWT authorizer.</p>
authorizerUri	string	<p>The Uniform Resource Identifier (URI) of the authorizer Lambda function. The syntax is as follows:</p> <div style="border: 1px solid #ccc; padding: 5px; width: fit-content;"><code>"arn:aws:apigateway:us-east-1:lambda</code></div>

Property name	Type	Description
		<pre>:path/2015-03-31/ functions/ arn:aws:lambda:us- east-1: <i>account-id</i> :function: <i>auth_function_name</i> /invocations"</pre>
authorizerCredentials	string	<p>The credentials required for invoking the authorizer, if any, in the form of an ARN of an IAM execution role. For example, "arn:aws:iam::<i>account-id</i> :<i>IAM_role</i>".</p>
authorizerPayloadFormatVersion	string	<p>For HTTP APIs, specifies the format of the data that API Gateway sends to a Lambda authorizer, and how API Gateway interprets the response from Lambda. To learn more, see the section called "Payload format version".</p>

Property name	Type	Description
enableSimpleResponses	Boolean	For HTTP APIs, specifies whether a request authorizer returns a Boolean value or an IAM policy. Supported only for authorizers with an <code>authorizerPayloadFormatVersion</code> of 2.0. If enabled, the Lambda authorizer function returns a Boolean value. To learn more, see the section called "Lambda function response for format 2.0" .
identitySource	string	A comma-separated list of mapping expressions of the request parameters as the identity source. Applicable for the authorizer of the request and jwt type only.
jwtConfiguration	Object	Specifies the issuer and audiences for a JWT authorizer. To learn more, see JWTConfiguration in the API Gateway Version 2 API Reference. Supported only for HTTP APIs.
identityValidationExpression	string	A regular expression for validating the token as the incoming identity. For example, <code>^x-[a-z]+</code> . Supported only for TOKEN authorizers for REST APIs.

Property name	Type	Description
authorizerResultTtlInSeconds	string	The number of seconds during which authorizer result is cached.
providerARNs	An array of string	A list of the Amazon Cognito user pool ARNs for the COGNITO_USER_POOLS .

x-amazon-apigateway-authorizer examples for REST APIs

The following OpenAPI security definitions example specifies a Lambda authorizer of the "token" type and named test-authorizer.

```

"securityDefinitions" : {
    "test-authorizer" : {
        "type" : "apiKey", // Required and the value must be
        "apiKey" for an API Gateway API.
        "name" : "Authorization", // The name of the header containing
        the authorization token.
        "in" : "header", // Required and the value must be
        "header" for an API Gateway API.
        "x-amazon-apigateway-authType" : "custom", // Specifies the authorization
        mechanism for the client.
        "x-amazon-apigateway-authorizer" : { // An API Gateway Lambda authorizer
            "type" : "token", // Required property and the value
            must "token"
            "authorizerUri" : "arn:aws:apigateway:us-east-1:lambda:path/2015-03-31/
            functions/arn:aws:lambda:us-east-1:account-id:function:function-name/invocations",
            "authorizerCredentials" : "arn:aws:iam::account-id:role",
            "identityValidationExpression" : "^x-[a-z]+",
            "authorizerResultTtlInSeconds" : 60
        }
    }
}

```

The following OpenAPI operation object snippet sets the GET /http to use the preceding Lambda authorizer.

```
"/http" : {
    "get" : {
        "responses" : { },
        "security" : [ {
            "test-authorizer" : [ ]
        }],
        "x-amazon-apigateway-integration" : {
            "type" : "http",
            "responses" : {
                "default" : {
                    "statusCode" : "200"
                }
            },
            "httpMethod" : "GET",
            "uri" : "http://api.example.com"
        }
    }
}
```

The following OpenAPI security definitions example specifies a Lambda authorizer of the "request" type, with a single header parameter (auth) as the identity source. The securityDefinitions is named request_authorizer_single_header.

```
"securityDefinitions": {
    "request_authorizer_single_header" : {
        "type" : "apiKey",
        "name" : "auth", // The name of a single header or query parameter
as the identity source.
        "in" : "header", // The location of the single identity source
request parameter. The valid value is "header" or "query"
        "x-amazon-apigateway-authType" : "custom",
        "x-amazon-apigateway-authorizer" : {
            "type" : "request",
            "identitySource" : "method.request.header.auth", // Request parameter mapping
expression of the identity source. In this example, it is the 'auth' header.
            "authorizerCredentials" : "arn:aws:iam::123456789012:role/AWSepIntegTest-CS-
LambdaRole",
        }
    }
}
```

```
        "authorizerUri" : "arn:aws:apigateway:us-east-1:lambda:path/2015-03-31/
functions/arn:aws:lambda:us-east-1:123456789012:function:APIGateway-Request-
Authorizer:vtwo/invocations",
        "authorizerResultTtlInSeconds" : 300
    }
}
}
```

The following OpenAPI security definitions example specifies a Lambda authorizer of the "request" type, with one header (HeaderAuth1) and one query string parameter QueryString1 as the identity sources.

```
"securityDefinitions": {
    "request_authorizer_header_query" : {
        "type" : "apiKey",
        "name" : "Unused",           // Must be "Unused" for multiple identity sources
or non header or query type of request parameters.
        "in" : "header",           // Must be "header" for multiple identity sources
or non header or query type of request parameters.
        "x-amazon-apigateway-authtype" : "custom",
        "x-amazon-apigateway-authorizer" : {
            "type" : "request",
            "identitySource" : "method.request.header.HeaderAuth1,
method.request.querystring.QueryString1",   // Request parameter mapping expressions
of the identity sources.
            "authorizerCredentials" : "arn:aws:iam::123456789012:role/AWSepIntegTest-CS-
LambdaRole",
            "authorizerUri" : "arn:aws:apigateway:us-east-1:lambda:path/2015-03-31/
functions/arn:aws:lambda:us-east-1:123456789012:function:APIGateway-Request-
Authorizer:vtwo/invocations",
            "authorizerResultTtlInSeconds" : 300
        }
    }
}
```

The following OpenAPI security definitions example specifies an API Gateway Lambda authorizer of the "request" type, with a single stage variable (stage) as the identity source.

```
"securityDefinitions": {
    "request_authorizer_single_stagevar" : {
        "type" : "apiKey",

```

```
"name" : "Unused", // Must be "Unused", for multiple identity sources  
or non header or query type of request parameters.  
"in" : "header", // Must be "header", for multiple identity sources  
or non header or query type of request parameters.  
"x-amazon-apigateway-authtype" : "custom",  
"x-amazon-apigateway-authorizer" : {  
    "type" : "request",  
    "identitySource" : "stageVariables.stage", // Request parameter mapping  
expression of the identity source. In this example, it is the stage variable.  
    "authorizerCredentials" : "arn:aws:iam::123456789012:role/AWSepIntegTest-CS-  
LambdaRole",  
    "authorizerUri" : "arn:aws:apigateway:us-east-1:lambda:path/2015-03-31/  
functions/arn:aws:lambda:us-east-1:123456789012:function:APIGateway-Request-  
Authorizer:vtwo/invocations",  
    "authorizerResultTtlInSeconds" : 300  
}  
}  
}
```

The following OpenAPI security definition example specifies an Amazon Cognito user pool as an authorizer.

```
"securityDefinitions": {  
    "cognito-pool": {  
        "type": "apiKey",  
        "name": "Authorization",  
        "in": "header",  
        "x-amazon-apigateway-authtype": "cognito_user_pools",  
        "x-amazon-apigateway-authorizer": {  
            "type": "cognito_user_pools",  
            "providerARNs": [  
                "arn:aws:cognito-idp:us-east-1:123456789012:userpool/us-east-1_ABC123"  
            ]  
        }  
    }  
}
```

The following OpenAPI operation object snippet sets the GET /http to use the preceding Amazon Cognito user pool as an authorizer, with no custom scopes.

```
"/http" : {  
    "get" : {
```

```
    "responses" : { },
    "security" : [ {
        "cognito-pool" : [ ]
    } ],
    "x-amazon-apigateway-integration" : {
        "type" : "http",
        "responses" : {
            "default" : {
                "statusCode" : "200"
            }
        },
        "httpMethod" : "GET",
        "uri" : "http://api.example.com"
    }
}
}
```

x-amazon-apigateway-authorizer examples for HTTP APIs

The following OpenAPI 3.0 example creates a JWT authorizer for an HTTP API that uses Amazon Cognito as an identity provider, with the Authorization header as an identity source.

```
"securitySchemes": {
    "jwt-authorizer-oauth": {
        "type": "oauth2",
        "x-amazon-apigateway-authorizer": {
            "type": "jwt",
            "jwtConfiguration": {
                "issuer": "https://cognito-idp.region.amazonaws.com/userPoolId",
                "audience": [
                    "audience1",
                    "audience2"
                ],
                "identitySource": "$request.header.Authorization"
            }
        }
    }
}
```

The following OpenAPI 3.0 example produces the same JWT authorizer as the previous example. However, this example uses the OpenAPI `openIdConnectUrl` property to automatically detect the issuer. The `openIdConnectUrl` must be fully formed.

```
"securitySchemes": {  
    "jwt-authorizer-autofind": {  
        "type": "openIdConnect",  
        "openIdConnectUrl": "https://cognito-idp.region.amazonaws.com/userPoolId/.well-known/openid-configuration",  
        "x-amazon-apigateway-authorizer": {  
            "type": "jwt",  
            "jwtConfiguration": {  
                "audience": [  
                    "audience1",  
                    "audience2"  
                ],  
                "identitySource": "$request.header.Authorization"  
            }  
        }  
    }  
}
```

The following example creates a Lambda authorizer for an HTTP API. This example authorizer uses the Authorization header as its identity source. The authorizer uses the 2.0 payload format version, and returns Boolean value, because enableSimpleResponses is set to true.

```
"securitySchemes" : {  
    "lambda-authorizer" : {  
        "type" : "apiKey",  
        "name" : "Authorization",  
        "in" : "header",  
        "x-amazon-apigateway-authorizer" : {  
            "type" : "request",  
            "identitySource" : "$request.header.Authorization",  
            "authorizerUri" : "arn:aws:apigateway:us-west-2:lambda:path/2015-03-31/functions/  
arn:aws:lambda:us-west-2:123456789012:function:function-name/invocations",  
            "authorizerPayloadFormatVersion" : "2.0",  
            "authorizerResultTtlInSeconds" : 300,  
            "enableSimpleResponses" : true  
        }  
    }  
}
```

x-amazon-apigateway-authtype property

For REST APIs, this extension can be used to define a custom type of a Lambda authorizer. In this case, the value is free-form. For example, an API may have multiple Lambda authorizers that use different internal schemes. You can use this extension to identify the internal scheme of a Lambda authorizer.

More commonly, in HTTP APIs and REST APIs, it can also be used as a way to define IAM authorization across several operations that share the same security scheme. In this case, the term `awsSigv4` is a reserved term, along with any term prefixed by `aws`.

This extension applies to the `apiKey` type security scheme in [OpenAPI 2](#) and [OpenAPI 3](#).

x-amazon-apigateway-authtype example

The following OpenAPI 3 example defines IAM authorization across multiple resources in a REST API or HTTP API:

```
{
  "openapi" : "3.0.1",
  "info" : {
    "title" : "openapi3",
    "version" : "1.0"
  },
  "paths" : {
    "/operation1" : {
      "get" : {
        "responses" : {
          "default" : {
            "description" : "Default response"
          }
        },
        "security" : [ {
          "sigv4Reference" : [ ]
        } ]
      }
    },
    "/operation2" : {
      "get" : {
        "responses" : {
          "default" : {
            "description" : "Default response"
          }
        }
      }
    }
  }
}
```

```
        },
      ],
    "security" : [ {
      "sigv4Reference" : [ ]
    } ]
  }
},
"components" : {
  "securitySchemes" : {
    "sigv4Reference" : {
      "type" : "apiKey",
      "name" : "Authorization",
      "in" : "header",
      "x-amazon-apigateway-authtype": "awsSigv4"
    }
  }
}
}
```

The following OpenAPI 3 example defines a Lambda authorizer with a custom scheme for a REST API:

```
{
  "openapi" : "3.0.1",
  "info" : {
    "title" : "openapi3 for REST API",
    "version" : "1.0"
  },
  "paths" : {
    "/protected-by-lambda-authorizer" : {
      "get" : {
        "responses" : {
          "200" : {
            "description" : "Default response"
          }
        },
        "security" : [ {
          "myAuthorizer" : [ ]
        } ]
      }
    }
  }
},
```

```
"components" : {  
    "securitySchemes" : {  
        "myAuthorizer" : {  
            "type" : "apiKey",  
            "name" : "Authorization",  
            "in" : "header",  
            "x-amazon-apigateway-authorizer" : {  
                "identitySource" : "method.request.header.Authorization",  
                "authorizerUri" : "arn:aws:apigateway:us-east-1:lambda:path/2015-03-31/  
functions/arn:aws:lambda:us-east-1:account-id:function:function-name/invocations",  
                "authorizerResultTtlInSeconds" : 300,  
                "type" : "request",  
                "enableSimpleResponses" : false  
            },  
            "x-amazon-apigateway-authtype": "Custom scheme with corporate claims"  
        }  
    }  
},  
"x-amazon-apigateway-importexport-version" : "1.0"  
}
```

See also

[authorizer.authType](#)

x-amazon-apigateway-binary-media-types property

Specifies the list of binary media types to be supported by API Gateway, such as application/octet-stream and image/jpeg. This extension is a JSON array. It should be included as a top-level vendor extension to the OpenAPI document.

x-amazon-apigateway-binary-media-types example

The following example shows the encoding lookup order of an API.

```
"x-amazon-apigateway-binary-media-types": [ "application/octet", "image/jpeg" ]
```

x-amazon-apigateway-documentation object

Defines the documentation parts to be imported into API Gateway. This object is a JSON object containing an array of the DocumentationPart instances.

Property name	Type	Description
documentationParts	Array	An array of the exported or imported DocumentationPart instances.
version	String	The version identifier of the snapshot of the exported documentation parts.

x-amazon-apigateway-documentation example

The following example of the API Gateway extension to OpenAPI defines DocumentationParts instances to be imported to or exported from an API in API Gateway.

```
{
  ...
  "x-amazon-apigateway-documentation": {
    "version": "1.0.3",
    "documentationParts": [
      {
        "location": {
          "type": "API"
        },
        "properties": {
          "description": "API description",
          "info": {
            "description": "API info description 4",
            "version": "API info version 3"
          }
        }
      },
      {
        ...
        // Another DocumentationPart instance
      }
    ]
  }
}
```

x-amazon-apigateway-endpoint-access-mode

Specifies a the endpoint access mode for a REST API or custom domain name. To learn more about endpoint access mode, see [Endpoint access mode](#).

x-amazon-apigateway-endpoint-access-mode example

The following example specifies the endpoint access mode to strict.

```
"x-amazon-apigateway-endpoint-access-mode": "STRICT"
```

x-amazon-apigateway-endpoint-configuration object

Specifies details of the endpoint configuration for an API. This extension is an extended property of the [OpenAPI Operation](#) object. This object should be present in [top-level vendor extensions](#) for Swagger 2.0. For OpenAPI 3.0, it should be present under the vendor extensions of the [Server object](#).

Property name	Type	Description
disableExecuteApiEndpoint	Boolean	Specifies whether clients can invoke your API by using the default execute-api endpoint. By default, clients can invoke your API with the default https:// <code>{api_id}</code> .execute-api. <code>{region}</code> .amazonaws.com endpoint. To require that clients use a custom domain name to invoke your API, specify true.
vpcEndpointIds	An array of String	A list of VpcEndpoint identifiers against which to create Route 53 alias records for a REST API. It is only supported

Property name	Type	Description
		for REST APIs the PRIVATE endpoint type.
ipAddressType	string	The IP address types that can invoke an HTTP API. Use <code>ipv4</code> to allow IPv4 address types to invoke an HTTP API. Use <code>dualstack</code> to allow IPv4 and IPv6 address types to invoke an HTTP API. It is only supported for HTTP APIs.

x-amazon-apigateway-endpoint-configuration examples

The following example associates specified VPC endpoints to the REST API.

```
"x-amazon-apigateway-endpoint-configuration": {
    "vpcEndpointIds": ["vpce-0212a4ababd5b8c3e", "vpce-01d622316a7df47f9"]
}
```

The following example disables the default endpoint for an API.

```
"x-amazon-apigateway-endpoint-configuration": {
    "disableExecuteApiEndpoint": true
}
```

The following example sets the IP address type to dualstack for an HTTP API.

```
"x-amazon-apigateway-endpoint-configuration": {
    "ipAddressType": "dualstack"
}
```

x-amazon-apigateway-gateway-responses object

Defines the gateway responses for an API as a string-to-[GatewayResponse](#) map of key-value pairs. The extension applies to the root-level OpenAPI structure.

Property name	Type	Description
<i>responseType</i>	x-amazon-apigateway-gateway-responses.gatewayResponse	A <code>GatewayResponse</code> for the specified <i>responseT</i> ype .

x-amazon-apigateway-gateway-responses example

The following API Gateway extension to OpenAPI example defines a [GatewayResponses](#) map that contains two [GatewayResponse](#) instances—one for the `DEFAULT_4XX` type and another for the `INVALID_API_KEY` type.

```
{  
  "x-amazon-apigateway-gateway-responses": {  
    "DEFAULT_4XX": {  
      "responseParameters": {  
        "gatewayresponse.header.Access-Control-Allow-Origin": "'domain.com'"  
      },  
      "responseTemplates": {  
        "application/json": "{\"message\": test 4xx b }"  
      }  
    },  
    "INVALID_API_KEY": {  
      "statusCode": "429",  
      "responseTemplates": {  
        "application/json": "{\"message\": test forbidden }"  
      }  
    }  
  }  
}
```

x-amazon-apigateway-gateway-responses.gatewayResponse object

Defines a gateway response of a given response type, including the status code, any applicable response parameters, or response templates.

Property name	Type	Description
<i>responseParameters</i>	x-amazon-apigateway-gateway-responses.responseParameters	Specifies the GatewayResponse parameters, namely the header parameters. The parameter values can take any incoming request parameter value or a static custom value.
<i>responseTemplates</i>	x-amazon-apigateway-gateway-responses.responseTemplates	Specifies the mapping templates of the gateway response. The templates are not processed by the VTL engine.
<i>statusCode</i>	string	An HTTP status code for the gateway response.

x-amazon-apigateway-gateway-responses.gatewayResponse example

The following example of the API Gateway extension to OpenAPI defines a [GatewayResponse](#) to customize the INVALID_API_KEY response to return the status code of 456, the incoming request's api-key header value, and a "Bad api-key" message.

```
"INVALID_API_KEY": {
    "statusCode": "456",
    "responseParameters": {
        "gatewayresponse.header.api-key": "method.request.header.api-key"
    },
    "responseTemplates": {
        "application/json": "{\"message\": \"Bad api-key\"}"
    }
}
```

x-amazon-apigateway-gateway-responses.responseParameters object

Defines a string-to-string map of key-value pairs to generate gateway response parameters from the incoming request parameters or using literal strings. Supported only for REST APIs.

Property name	Type	Description
gatewayresponse. <i>param-position</i> . <i>param-name</i>	string	<i>param-position</i> can be header, path, or querystring . For more information, see Parameter mapping for REST APIs in API Gateway .

x-amazon-apigateway-gateway-responses.responseParameters example

The following OpenAPI extensions example shows a [GatewayResponse](#) response parameter mapping expression to enable CORS support for resources on the *.example.domain domains.

```
"responseParameters": {
    "gatewayresponse.header.Access-Control-Allow-Origin": '*.{example.domain}',
    "gatewayresponse.header.from-request-header" : method.request.header.Accept,
    "gatewayresponse.header.from-request-path" : method.request.path.petId,
    "gatewayresponse.header.from-request-query" : method.request.querystring.qname
}
```

x-amazon-apigateway-gateway-responses.responseTemplates object

Defines [GatewayResponse](#) mapping templates, as a string-to-string map of key-value pairs, for a given gateway response. For each key-value pair, the key is the content type. For example, "application/json" and the value is a stringified mapping template for simple variable substitutions. A GatewayResponse mapping template isn't processed by the [Velocity Template Language \(VTL\)](#) engine.

Property name	Type	Description
<code>content-type</code>	string	A <code>GatewayResponse</code> body mapping template supporting only simple variable substitution to customize a gateway response body.

x-amazon-apigateway-gateway-responses.responseTemplates example

The following OpenAPI extensions example shows a [GatewayResponse](#) mapping template to customize an API Gateway-generated error response into an app-specific format.

```
"responseTemplates": {
    "application/json": "{ \"message\": $context.error.messageString, \"type\": $context.error.responseType, \"statusCode\": '488' }"
}
```

The following OpenAPI extensions example shows a [GatewayResponse](#) mapping template to override an API Gateway-generated error response with a static error message.

```
"responseTemplates": {
    "application/json": "{ \"message\": 'API-specific errors' }"
}
```

x-amazon-apigateway-importexport-version

Specifies the version of the API Gateway import and export algorithm for HTTP APIs. Currently, the only supported value is `1.0`. To learn more, see [exportVersion](#) in the *API Gateway Version 2 API Reference*.

x-amazon-apigateway-importexport-version example

The following example sets the import and export version to `1.0`.

```
{
```

```
"openapi": "3.0.1",
"x-amazon-apigateway-importexport-version": "1.0",
"info": { ...
```

x-amazon-apigateway-integration object

Specifies details of the backend integration used for this method. This extension is an extended property of the [OpenAPI Operation](#) object. The result is an [API Gateway integration](#) object.

Property name	Type	Description
cacheKeyParameters	An array of string	A list of request parameters whose values are to be cached.
cacheNamespace	string	An API-specific tag group of related cached parameters.
connectionId	string	The ID of a VpcLink for the private integration.
connectionType	string	The integration connection type. The valid value is "VPC_LINK" for private integration or "INTERNET" , otherwise.
credentials	string	For AWS IAM role-based credentials, specify the ARN of an appropriate IAM role. If unspecified, credentials default to resource-based permissions that must be added manually to allow the API to access the resource. For more information, see

Property name	Type	Description
		<p>Granting Permissions Using a Resource Policy.</p> <p>Note: When using IAM credentials, make sure that AWS STS Regional endpoints are enabled for the Region where this API is deployed for best performance.</p>
contentHandling	string	<p>Request payload encoding conversion types. Valid values are 1) CONVERT_TO_TEXT , for converting a binary payload into a base64-encoded string or converting a text payload into a utf-8-encoded string or passing through the text payload natively without modification, and 2) CONVERT_TO_BINARY , for converting a text payload into a base64-decoded blob or passing through a binary payload natively without modification.</p>
httpMethod	string	<p>The HTTP method used in the integration request. For Lambda function invocations, the value must be POST.</p>

Property name	Type	Description
integrationSubtype	string	Specifies the integration subtype for an AWS service integration. Supported only for HTTP APIs. For supported integration subtypes, see the section called "AWS service integrations reference".
integrationTarget	string	The ALB or NLB listener to send the request to. Supported only for private integrations that use VPC links V2. For more information, see the section called "VPC links V2".
passthroughBehavior	string	Specifies how a request payload of unmapped content type is passed through the integration request without modification. Supported values are <code>when_no_templates</code> , <code>when_no_match</code> , and <code>never</code> . For more information, see Integration.passthroughBehavior .

Property name	Type	Description
payloadFormatVersion	string	<p>Specifies the format of the payload sent to an integration. Required for HTTP APIs. For HTTP APIs, supported values for Lambda proxy integrations are 1.0 and 2.0. For all other integrations, 1.0 is the only supported value.</p> <p>To learn more, see the section called “AWS Lambda integrations” and the section called “AWS service integrations reference”.</p>

Property name	Type	Description
<code>requestParameters</code>	x-amazon-apigateway-integration.requestParameters object	<p>For REST APIs, specifies mappings from method request parameters to integration request parameters. Supported request parameters are <code>querystring</code>, <code>path</code>, <code>header</code>, and <code>body</code>.</p> <p>For HTTP APIs, request parameters are a key-value map specifying parameters that are passed to AWS_PROXY integrations with a specified <code>integrationSubtype</code>. You can provide static values, or map request data, stage variables, or context variables that are evaluated at runtime. To learn more, see the section called "AWS service integrations".</p>
<code>requestTemplates</code>	x-amazon-apigateway-integration.requestTemplates object	Mapping templates for a request payload of specified MIME types.
<code>responses</code>	x-amazon-apigateway-integration.responses object	Defines the method's responses and specifies desired parameter mappings or payload mappings from integration responses to method responses.

Property name	Type	Description
responseTransferMode	string	The response transfer mode of the integration. Use BUFFERED to have API Gateway wait to receive the complete response before beginning transmission. Use STREAM to have API Gateway send partial responses back to the client as they become available. To learn more, see the section called “Stream the integration response for your proxy integrations” .
timeoutInMillis	integer	Integration timeouts between 50 ms and 29,000 ms.

Property name	Type	Description
type	string	<p>The type of integration with the specified backend. Valid values are:</p> <ul style="list-style-type: none">• <code>http</code> or <code>http_proxy</code>, for integration with an HTTP backend.• <code>aws_proxy</code>, for integration with AWS Lambda functions.• <code>aws</code>, for integration with AWS Lambda functions or other AWS services, such as Amazon DynamoDB, Amazon Simple Notification Service, or Amazon Simple Queue Service.• <code>mock</code>, for integration with API Gateway without invoking any backend. <p>For more information about the integration types, see integration:type.</p>
tlsConfig	the section called “x-amazon-apigateway-integration.tlsConfig”	Specifies the TLS configuration for an integration.

Property name	Type	Description
uri	string	The endpoint URI of the backend. For integrations of the aws type, this is an ARN value. For the HTTP integration, this is the URL of the HTTP endpoint including the https or http scheme.

x-amazon-apigateway-integration examples

For HTTP APIs, you can define integrations in the components section of your OpenAPI definition. To learn more, see [x-amazon-apigateway-integrations object](#).

```
"x-amazon-apigateway-integration": {
    "$ref": "#/components/x-amazon-apigateway-integrations/integration1"
}
```

The following example creates an integration with a Lambda function. For demonstration purposes, the sample mapping templates shown in requestTemplates and responseTemplates of the examples below are assumed to apply to the following JSON-formatted payload: { "name":"value_1", "key":"value_2", "redirect": {"url" :"..."} } to generate a JSON output of { "stage":"value_1", "user-id":"value_2" } or an XML output of <stage>value_1</stage>.

```
"x-amazon-apigateway-integration" : {
    "type" : "aws",
    "uri" : "arn:aws:apigateway:us-east-1:lambda:path/2015-03-31/functions/
arn:aws:lambda:us-east-1:012345678901:function:HelloWorld/invocations",
    "httpMethod" : "POST",
    "credentials" : "arn:aws:iam::012345678901:role/apigateway-invoke-lambda-exec-
role",
    "requestTemplates" : {
        "application/json" : "#set ($root=$input.path('$')) { \"stage\":
\"$root.name\", \"user-id\": \"$root.key\" }",
        "application/xml" : "#set ($root=$input.path('$')) <stage>$root.name</
stage> "
    }
}
```

```
},
"requestParameters" : {
    "integration.request.path.stage" : "method.request.querystring.version",
    "integration.request.querystring.provider" :
"method.request.querystring.vendor"
},
"cacheNamespace" : "cache namespace",
"cacheKeyParameters" : [],
"responses" : {
    "2\\d{2}" : {
        "statusCode" : "200",
        "responseParameters" : {
            "method.response.header.requestId" : "integration.response.header.cid"
        },
        "responseTemplates" : {
            "application/json" : "#set ($root=$input.path('$')) { \"stage\": \"$root.name\", \"user-id\": \"$root.key\" }",
            "application/xml" : "#set ($root=$input.path('$')) <stage>$root.name</stage>"
        }
    },
    "302" : {
        "statusCode" : "302",
        "responseParameters" : {
            "method.response.header.Location" :
"integration.response.body.redirect.url"
        }
    },
    "default" : {
        "statusCode" : "400",
        "responseParameters" : {
            "method.response.header.test-method-response-header" : "'static value'"
        }
    }
}
}
```

Note that double quotes ("") for the JSON string in the mapping templates must be string-escaped (\").

x-amazon-apigateway-integrations object

Defines a collection of integrations. You can define integrations in the components section of your OpenAPI definition, and reuse the integrations for multiple routes. Supported only for HTTP APIs.

Property name	Type	Description
<i>integration</i>	x-amazon-apigateway-integration object	A collection of integration objects.

x-amazon-apigateway-integrations example

The following example creates an HTTP API that defines two integrations, and references the integrations by using `$ref": "#/components/x-amazon-apigateway-integrations/integration-name.`

```
{
  "openapi": "3.0.1",
  "info":
  {
    "title": "Integrations",
    "description": "An API that reuses integrations",
    "version": "1.0"
  },
  "servers": [
  {
    "url": "https://example.com/{basePath}",
    "description": "The production API server",
    "variables":
    {
      "basePath":
      {
        "default": "example/path"
      }
    }
  }],
  "paths":
  {
    "/":
    {
      "get": {
        "responses": {
          "200": {
            "description": "Success response"
          }
        }
      }
    }
  }
}
```

```
"get":  
  {  
    "x-amazon-apigateway-integration":  
      {  
        "$ref": "#/components/x-amazon-apigateway-integrations/integration1"  
      }  
    }  
  },  
"/pets":  
{  
  "get":  
    {  
      "x-amazon-apigateway-integration":  
        {  
          "$ref": "#/components/x-amazon-apigateway-integrations/integration1"  
        }  
    }  
  },  
"/checkout":  
{  
  "get":  
    {  
      "x-amazon-apigateway-integration":  
        {  
          "$ref": "#/components/x-amazon-apigateway-integrations/integration2"  
        }  
    }  
  }  
},  
"components": {  
  "x-amazon-apigateway-integrations":  
  {  
    "integration1":  
      {  
        "type": "aws_proxy",  
        "httpMethod": "POST",  
        "uri": "arn:aws:apigateway:us-east-2:lambda:path/2015-03-31/functions/  
arn:aws:lambda:us-east-2:123456789012:function:my-function/invocations",  
        "passthroughBehavior": "when_no_templates",  
        "payloadFormatVersion": "1.0"  
      },  
    "integration2":  
  }
```

```

    {
        "type": "aws_proxy",
        "httpMethod": "POST",
        "uri": "arn:aws:apigateway:us-east-2:lambda:path/2015-03-31/functions/
arn:aws:lambda:us-east-2:123456789012:function:example-function/invocations",
        "passthroughBehavior": "when_no_templates",
        "payloadFormatVersion" : "1.0"
    }
}
}
}

```

x-amazon-apigateway-integration.requestTemplates object

Specifies mapping templates for a request payload of the specified MIME types.

Property name	Type	Description
<i>MIME type</i>	string	An example of the MIME type is application/json . For information about creating a mapping template, see the section called “Mapping template transformations” .

x-amazon-apigateway-integration.requestTemplates example

The following example sets mapping templates for a request payload of the application/json and application/xml MIME types.

```

"requestTemplates" : {
    "application/json" : "#set ($root=$input.path('$')) { \"stage\": \"$root.name\",
\"user-id\": \"$root.key\" }",
    "application/xml" : "#set ($root=$input.path('$')) <stage>$root.name</stage> "
}

```

x-amazon-apigateway-integration.requestParameters object

For REST APIs, specifies mappings from named method request parameters to integration request parameters. The method request parameters must be defined before being referenced.

For HTTP APIs, specifies parameters that are passed to AWS_PROXY integrations with a specified `integrationSubtype`.

Property name	Type	Description
<code>integration.request.<i>param-type</i>.<param-name></code>	string	For REST APIs, the value is typically a predefined method request parameter of the <code>method.request</code> . <i>param-type</i> can be <code>querystring</code> , <code>path</code> , <code>header</code> , or <code>body</code> . However, <code>\$context.VARIABLE_NAME</code> , <code>\$stageVariables.VARIABLE_NAME</code> , and <code>STATIC_VALUE</code> are also valid. For the body parameter, the <code><param-name></code> is a JSON path expression without the <code>\$. </code> prefix.
<i>parameter</i>	string	For HTTP APIs, request parameters are a key-value map specifying parameters that are passed to AWS_PROXY integrations with a specified <code>integrationSubtype</code> . You can

Property name	Type	Description
		provide static values, or map request data, stage variables , or context variables that are evaluated at runtime. To learn more, see the section called "AWS service integrations" .

x-amazon-apigateway-integration.requestParameters example

The following request parameter mappings example translates a method request's query (version), header (x-user-id), and path (service) parameters to the integration request's query (stage), header (x-userid), and path parameters (op), respectively.

 **Note**

If you're creating resources through OpenAPI or CloudFormation, static values should be enclosed in single quotes.

To add this value from the console, enter application/json in the box, without quotation marks.

```
"requestParameters" : {  
    "integration.request.querystring.stage" : "method.request.querystring.version",  
    "integration.request.header.x-userid" : "method.request.header.x-user-id",  
    "integration.request.path.op" : "method.request.path.service"  
},
```

x-amazon-apigateway-integration.responses object

Defines the method's responses and specifies parameter mappings or payload mappings from integration responses to method responses.

Property name	Type	Description
<i>Response status pattern</i>	x-amazon-apigateway-integration.response object	<p>Either a regular expression used to match the integration response to the method response, or default to catch any response that you haven't configured. For HTTP integrations, the regex applies to the integration response status code. For Lambda invocations, the regex applies to the errorMessage field of the error information object returned by AWS Lambda as a failure response body when the Lambda function execution throws an exception.</p> <div style="border: 1px solid #ccc; padding: 10px; margin-top: 10px;"><p>Note The <i>Response status pattern</i> property name refers to a response status code or regular expression describing a group of response status codes. It does not correspond to any identifier of an IntegrationResponses resource in the API Gateway REST API.</p></div>

x-amazon-apigateway-integration.responses example

The following example shows a list of responses from 2xx and 302 responses. For the 2xx response, the method response is mapped from the integration response's payload of the application/json or application/xml MIME type. This response uses the supplied mapping templates. For the 302 response, the method response returns a Location header whose value is derived from the redirect.url property on the integration response's payload.

```
"responses" : {  
    "2\\d{2}" : {  
        "statusCode" : "200",  
        "responseTemplates" : {  
            "application/json" : "#set ($root=$input.path('$')) { \"stage\": \"$root.name\", \"$user-id\": \"$root.key\" }",  
            "application/xml" : "#set ($root=$input.path('$')) <stage>$root.name</stage>"  
        },  
        "302" : {  
            "statusCode" : "302",  
            "responseParameters" : {  
                "method.response.header.Location": "integration.response.body.redirect.url"  
            }  
        }  
    }  
}
```

x-amazon-apigateway-integration.response object

Defines a response and specifies parameter mappings or payload mappings from the integration response to the method response.

Property name	Type	Description
statusCode	string	HTTP status code for the method response; for example, "200". This must

Property name	Type	Description
		correspond to a matching response in the OpenAPI Operation responses field.
<code>responseTemplates</code>	x-amazon-apigateway-integration.responseTemplates object	Specifies MIME type-specific mapping templates for the response's payload.
<code>responseParameters</code>	x-amazon-apigateway-integration.responseParameters object	Specifies parameter mappings for the response. Only the <code>header</code> and <code>body</code> parameters of the integration response can be mapped to the <code>header</code> parameters of the method.
<code>contentHandling</code>	<code>string</code>	Response payload encoding conversion types. Valid values are 1) <code>CONVERT_TO_TEXT</code> , for converting a binary payload into a base64-encoded string or converting a text payload into a utf-8-encoded string or passing through the text payload natively without modification, and 2) <code>CONVERT_TO_BINARY</code> , for converting a text payload into a base64-decoded blob or passing through a binary payload natively without modification.

x-amazon-apigateway-integration.response example

The following example defines a 302 response for the method that derives a payload of the application/json or application/xml MIME type from the backend. The response uses the supplied mapping templates and returns the redirect URL from the integration response in the method's Location header.

```
{  
    "statusCode" : "302",  
    "responseTemplates" : {  
        "application/json" : "#set ($root=$input.path('$')) { \\\"stage\\\": \\\"$root.name\\\", \\\"user-id\\\": \\\"$root.key\\\" }",  
        "application/xml" : "#set ($root=$input.path('$')) <stage>$root.name</stage> "  
    },  
    "responseParameters" : {  
        "method.response.header.Location": "integration.response.body.redirect.url"  
    }  
}
```

x-amazon-apigateway-integration.responseTemplates object

Specifies mapping templates for a response payload of the specified MIME types.

Property name	Type	Description
<i>MIME type</i>	string	Specifies a mapping template to transform the integration response body to the method response body for a given MIME type. For information about creating a mapping template, see the section called “Mapping template transformations” .

Property name	Type	Description
		An example of the <i>MIME type</i> is application/json.

x-amazon-apigateway-integration.responseTemplate example

The following example sets mapping templates for a request payload of the application/json and application/xml MIME types.

```
"responseTemplates" : {
    "application/json" : "#set ($root=$input.path('$')) { \"stage\": \"$root.name\",
\"user-id\": \"$root.key\" }",
    "application/xml" : "#set ($root=$input.path('$')) <stage>$root.name</stage> "
}
```

x-amazon-apigateway-integration.responseParameters object

Specifies mappings from integration method response parameters to method response parameters. You can map header, body, or static values to the header type of the method response. Supported only for REST APIs.

Property name	Type	Description
method.response.header. <i><param-name></i>	string	The named parameter value can be derived from the header and body types of the integration response parameters.

x-amazon-apigateway-integration.responseParameters example

The following example maps body and header parameters of the integration response to two header parameters of the method response.

```
"responseParameters" : {  
    "method.response.header.Location" : "integration.response.body.redirect.url",  
    "method.response.header.x-user-id" : "integration.response.header.x-userid"  
}
```

x-amazon-apigateway-integration.tlsConfig object

Specifies the TLS configuration for an integration.

Property name	Type	Description
insecureSkipVerification	Boolean	Supported only for REST APIs. Specifies whether or not API Gateway skips verification that the certificate for an integration endpoint is issued by a supported certificate authority . This isn't recommended, but it enables you to use certificates that are signed by private certificate authorities, or certificates that are self-signed. If enabled, API Gateway still performs basic certificate validation, which includes checking the certificate's expiration date, hostname, and presence of a root

Property name	Type	Description
		<p>certificate authority. The root certificate belonging to the private authority must satisfy the following constraints:</p> <ul style="list-style-type: none">• x509 extension keyUsage must have keyCertSign .• x509 extension basicConstraints must have CA:TRUE. <p>Supported only for HTTP and HTTP_PROXY integrations.</p> <div style="border: 1px solid #f0e68c; padding: 10px; margin-top: 10px;"><p>⚠️ Warning</p><p>Enabling <code>insecureSslVerification</code> isn't recommended, especially for integrations with public HTTPS endpoints. If you enable <code>insecureSslVerification</code>, you increase the risk of man-in-the-middle attacks.</p></div>

Property name	Type	Description
serverNameToVerify	string	Supported only for HTTP API private integrations. If you specify a server name, API Gateway uses it to verify the hostname on the integration's certificate. The server name is also included in the TLS handshake to support Server Name Indication (SNI) or virtual hosting.

x-amazon-apigateway-integration.tlsConfig examples

The following OpenAPI 3.0 example enables `insecureSkipVerification` for a REST API HTTP proxy integration.

```
"x-amazon-apigateway-integration": {
  "uri": "http://petstore-demo-endpoint.execute-api.com/petstore/pets",
  "responses": {
    "default": {
      "statusCode": "200"
    }
  },
  "passthroughBehavior": "when_no_match",
  "httpMethod": "ANY",
  "tlsConfig" : {
    "insecureSkipVerification" : true
  }
  "type": "http_proxy",
}
```

The following OpenAPI 3.0 example specifies a `serverNameToVerify` for an HTTP API private integration.

```
"x-amazon-apigateway-integration" : {
  "payloadFormatVersion" : "1.0",
  "connectionId" : "abc123",
```

```
"type" : "http_proxy",
"httpMethod" : "ANY",
"uri" : "arn:aws:elasticloadbalancing:us-west-2:123456789012:listener/app/my-load-balancer/50dc6c495c0c9188/0467ef3c8400ae65",
"connectionType" : "VPC_LINK",
"tlsConfig" : {
    "serverNameToVerify" : "example.com"
}
}
```

x-amazon-apigateway-minimum-compression-size

Specifies the minimum compression size for a REST API. To enable compression, specify an integer between 0 and 10485760. To learn more, see [Payload compression for REST APIs in API Gateway](#).

x-amazon-apigateway-minimum-compression-size example

The following example specifies a minimum compression size of 5242880 bytes for a REST API.

```
"x-amazon-apigateway-minimum-compression-size": 5242880
```

x-amazon-apigateway-policy

Specifies a resource policy for a REST API. To learn more about resource policies, see [Control access to a REST API with API Gateway resource policies](#). For resource policy examples, see [API Gateway resource policy examples](#).

x-amazon-apigateway-policy example

The following example specifies a resource policy for a REST API. The resource policy denies (blocks) incoming traffic to an API from a specified source IP address block. On import, "execute-api:/*" is converted to arn:aws:execute-api:*region:account-id:api-id*/*, using the current Region, your AWS account ID, and the current REST API ID.

```
"x-amazon-apigateway-policy": {
    "Version": "2012-10-17",
    "Statement": [
        {
            "Effect": "Allow",
```

```
        "Principal": "*",
        "Action": "execute-api:Invoke",
        "Resource": [
            "execute-api:/*"
        ],
    },
{
    "Effect": "Deny",
    "Principal": "*",
    "Action": "execute-api:Invoke",
    "Resource": [
        "execute-api:/*"
    ],
    "Condition" : {
        "IpAddress": {
            "aws:SourceIp": "192.0.2.0/24"
        }
    }
}
]
```

x-amazon-apigateway-request-validator property

Specifies a request validator, by referencing a [*request_validator_name*](#) of the [x-amazon-apigateway-requestValidators object](#) map, to enable request validation on the containing API or a method. The value of this extension is a JSON string.

This extension can be specified at the API level or at the method level. The API-level validator applies to all of the methods unless it is overridden by the method-level validator.

x-amazon-apigateway-request-validator example

The following example applies the basic request validator at the API level while applying the parameter-only request validator on the POST /validation request.

OpenAPI 2.0

```
{
    "swagger": "2.0",
    "x-amazon-apigateway-requestValidators" : {
```

```

"basic" : {
    "validateRequestBody" : true,
    "validateRequestParameters" : true
},
"params-only" : {
    "validateRequestBody" : false,
    "validateRequestParameters" : true
}
},
"x-amazon-apigateway-request-validator" : "basic",
"paths": {
    "/validation": {
        "post": {
            "x-amazon-apigateway-request-validator" : "params-only",
            ...
        }
    }
}
}

```

x-amazon-apigateway-requestValidators object

Defines the supported request validators for the containing API as a map between a validator name and the associated request validation rules. This extension applies to a REST API.

Property name	Type	Description
<i>request_validator_name</i>	x-amazon-apigateway-requestValidators.requestValidator object	<p>Specifies the validation rules consisting of the named validator. For example:</p> <div style="border: 1px solid #ccc; padding: 10px; margin-top: 10px;"> <pre> "basic" : { "validate RequestBody" : true, "validate RequestParameters" : true }, </pre> </div> <p>To apply this validator to a specific method, reference</p>

Property name	Type	Description
		the validator name (basic) as the value of the x-amazon-apigateway-request-validator property .

x-amazon-apigateway-requestValidators example

The following example shows a set of request validators for an API as a map between a validator name and the associated request validation rules.

OpenAPI 2.0

```
{  
  "swagger": "2.0",  
  ...  
  "x-amazon-apigateway-requestValidators" : {  
    "basic" : {  
      "validateRequestBody" : true,  
      "validateRequestParameters" : true  
    },  
    "params-only" : {  
      "validateRequestBody" : false,  
      "validateRequestParameters" : true  
    }  
  },  
  ...  
}
```

x-amazon-apigateway-requestValidators.requestValidator object

Specifies the validation rules of a request validator as part of the [x-amazon-apigateway-requestValidators object](#) map definition.

Property name	Type	Description
validateRequestBody	Boolean	Specifies whether to validate the request body (true) or not (false).
validateRequestParameters	Boolean	Specifies whether to validate the required request parameters (true) or not (false).

x-amazon-apigateway-request-validation.example

The following example shows a parameter-only request validator:

```
"params-only": {  
    "validateRequestBody" : false,  
    "validateRequestParameters" : true  
}
```

x-amazon-apigateway-security-policy

Specifies a security policy for a REST API. If you create a security policy that starts with "SecurityPolicy_ ", you must also set the [endpoint access mode](#). To learn more about security policies, see [Security policies for REST APIs in API Gateway](#).

x-amazon-apigateway-security-policy.example

The following example specifies SecurityPolicy_TLS13_1_3_2025_0 for a REST API.

```
"x-amazon-apigateway-security-policy": "SecurityPolicy_TLS13_1_3_2025_09"
```

x-amazon-apigateway-tag-value property

Specifies the value of an [AWS tag](#) for an HTTP API. You can use the x-amazon-apigateway-tag-value property as part of the root-level [OpenAPI tag object](#) to specify AWS tags for an HTTP API. If you specify a tag name without the x-amazon-apigateway-tag-value property, API Gateway creates a tag with an empty string for a value.

To learn more about tagging, see [Tagging your API Gateway resources](#).

Property name	Type	Description
name	String	Specifies the tag key.
x-amazon-apigateway-tag-value	String	Specifies the tag value.

x-amazon-apigateway-tag-value example

The following example specifies two tags for an HTTP API:

- "Owner": "Admin"
- "Prod": ""

```
"tags": [
  {
    "name": "Owner",
    "x-amazon-apigateway-tag-value": "Admin"
  },
  {
    "name": "Prod"
  }
]
```

Security in Amazon API Gateway

Cloud security at AWS is the highest priority. As an AWS customer, you benefit from a data center and network architecture that is built to meet the requirements of the most security-sensitive organizations.

Security is a shared responsibility between AWS and you. The [shared responsibility model](#) describes this as security *of* the cloud and security *in* the cloud:

- **Security of the cloud** – AWS is responsible for protecting the infrastructure that runs AWS services in the AWS Cloud. AWS also provides you with services that you can use securely. Third-party auditors regularly test and verify the effectiveness of our security as part of the [AWS Compliance Programs](#). To learn about the compliance programs that apply to Amazon API Gateway, see [AWS services in scope by compliance program](#).
- **Security in the cloud** – Your responsibility is determined by the AWS service that you use. You are also responsible for other factors including the sensitivity of your data, your company's requirements, and applicable laws and regulations.

This documentation helps you understand how to apply the shared responsibility model when using API Gateway. The following topics show you how to configure API Gateway to meet your security and compliance objectives. You also learn how to use other AWS services that help you to monitor and secure your API Gateway resources.

For more information, see [Security Overview of Amazon API Gateway](#).

Topics

- [Data protection in Amazon API Gateway](#)
- [Identity and access management for Amazon API Gateway](#)
- [Logging and monitoring in Amazon API Gateway](#)
- [Compliance validation for Amazon API Gateway](#)
- [Resilience in Amazon API Gateway](#)
- [Infrastructure security in Amazon API Gateway](#)
- [Vulnerability analysis in Amazon API Gateway](#)
- [Security best practices in Amazon API Gateway](#)

Data protection in Amazon API Gateway

The AWS [shared responsibility model](#) applies to data protection in Amazon API Gateway. As described in this model, AWS is responsible for protecting the global infrastructure that runs all of the AWS Cloud. You are responsible for maintaining control over your content that is hosted on this infrastructure. You are also responsible for the security configuration and management tasks for the AWS services that you use. For more information about data privacy, see the [Data Privacy FAQ](#). For information about data protection in Europe, see the [AWS Shared Responsibility Model and GDPR](#) blog post on the [AWS Security Blog](#).

For data protection purposes, we recommend that you protect AWS account credentials and set up individual users with AWS IAM Identity Center or AWS Identity and Access Management (IAM). That way, each user is given only the permissions necessary to fulfill their job duties. We also recommend that you secure your data in the following ways:

- Use multi-factor authentication (MFA) with each account.
- Use SSL/TLS to communicate with AWS resources. We require TLS 1.2 and recommend TLS 1.3.
- Set up API and user activity logging with AWS CloudTrail. For information about using CloudTrail trails to capture AWS activities, see [Working with CloudTrail trails](#) in the *AWS CloudTrail User Guide*.
- Use AWS encryption solutions, along with all default security controls within AWS services.
- Use advanced managed security services such as Amazon Macie, which assists in discovering and securing sensitive data that is stored in Amazon S3.
- If you require FIPS 140-3 validated cryptographic modules when accessing AWS through a command line interface or an API, use a FIPS endpoint. For more information about the available FIPS endpoints, see [Federal Information Processing Standard \(FIPS\) 140-3](#).

We strongly recommend that you never put confidential or sensitive information, such as your customers' email addresses, into tags or free-form text fields such as a **Name** field. This includes when you work with API Gateway or other AWS services using the console, API, AWS CLI, or AWS SDKs. Any data that you enter into tags or free-form text fields used for names may be used for billing or diagnostic logs. If you provide a URL to an external server, we strongly recommend that you do not include credentials information in the URL to validate your request to that server.

Data encryption in Amazon API Gateway

Data protection refers to protecting data while in transit (as it travels to and from API Gateway) and at rest (while it is stored in AWS).

Data encryption at rest in Amazon API Gateway

If you choose to enable caching for a REST API, you can enable cache encryption. To learn more, see [Cache settings for REST APIs in API Gateway](#).

For more information about data protection, see the [AWS Shared Responsibility Model and GDPR](#) blog post on the *AWS Security Blog*.

Encryption and decryption of your certificate's private key

When you create a custom domain name for private APIs, your ACM certificate and private key are encrypted using an AWS managed KMS key that has the alias **aws/acm**. You can view the key ID with this alias in the AWS KMS console under **AWS managed keys**.

API Gateway does not directly access your ACM resources. It uses AWS TLS Connection Manager to secure and access the private keys for your certificate. When you use your ACM certificate to create an API Gateway custom domain name for private APIs, API Gateway associates your certificate with AWS TLS Connection Manager. This is done by creating a grant in AWS KMS against your AWS Managed Key with the prefix **aws/acm**. A grant is a policy instrument that allows TLS Connection Manager to use KMS keys in cryptographic operations. The grant allows the grantee principal (TLS Connection Manager) to call the specified grant operations on the KMS key to decrypt your certificate's private key. TLS Connection Manager then uses the certificate and the decrypted (plaintext) private key to establish a secure connection (SSL/TLS session) with clients of API Gateway services. When the certificate is disassociated from an API Gateway custom domain name for private APIs, the grant is retired.

If you want to remove access to the KMS key, we recommend that you replace or delete the certificate from the service using the AWS Management Console or the `update-service` command in the AWS CLI.

Encryption context for API Gateway

An [encryption context](#) is an optional set of key-value pairs that contain contextual information about what your private key might be used for. AWS KMS binds the encryption context to the encrypted data and uses it as additional authenticated data to support authenticated encryption.

When your TLS keys are used with API Gateway and TLS Connection manager, the name of your API Gateway service is included in the encryption context used to encrypt your key at rest. You can verify which API Gateway custom domain name your certificate and private key are being used for by viewing the encryption context in your CloudTrail logs as shown in the next section, or by looking at the **Associated Resources** tab in the ACM console.

To decrypt data, the same encryption context is included in the request. API Gateway uses the same encryption context in all AWS KMS cryptographic operations, where the key is `aws:apigateway:arn` and the value is the Amazon Resource Name (ARN) of the API Gateway `PrivateDomainName` resource.

The following example shows the encryption context in the output of an operation such as `CreateGrant`.

```
"constraints": {  
  "encryptionContextEquals": {  
    "aws:acm:arn": "arn:aws:acm:us-west-2:859412291086:certificate/9177097a-f0ae-4be1-93b1-19f911ea4f88",  
    "aws:apigateway:arn": "arn:aws:apigateway:us-west-2:859412291086:/domainnames/denytest-part1.pdx.sahig.people.aws.dev+cbaeumzjhg"  
  }  
},  
"operations": [  
  "Decrypt"  
],  
"granteePrincipal": "tlsconnectionmanager.amazonaws.com"
```

Data encryption in transit in Amazon API Gateway

The APIs created with Amazon API Gateway expose HTTPS endpoints only. API Gateway doesn't support unencrypted (HTTP) endpoints.

API Gateway manages the certificates for default `execute-api` endpoints. If you configure a custom domain name, [you specify the certificate for the domain name](#). As a best practice, don't [pin certificates](#).

For greater security, you can choose a minimum Transport Layer Security (TLS) protocol version to be enforced for your API Gateway custom domain. WebSocket APIs and HTTP APIs support only TLS 1.2. To learn more, see [Choose a security policy for your custom domain in API Gateway](#).

You can also set up a Amazon CloudFront distribution with a custom SSL certificate in your account and use it with Regional APIs. You can then configure the security policy for the CloudFront distribution with TLS 1.1 or higher based on your security and compliance requirements.

For more information about data protection, see [Protect your REST APIs in API Gateway](#) and the [AWS Shared Responsibility Model and GDPR](#) blog post on the [AWS Security Blog](#).

Internet traffic privacy

Using Amazon API Gateway, you can create private REST APIs that can be accessed only from your Amazon Virtual Private Cloud (VPC). The VPC uses an [interface VPC endpoint](#), which is an endpoint network interface that you create in your VPC. Using [resource policies](#), you can allow or deny access to your API from selected VPCs and VPC endpoints, including across AWS accounts. Each endpoint can be used to access multiple private APIs. You can also use Direct Connect to establish a connection from an on-premises network to Amazon VPC and access your private API over that connection. In all cases, traffic to your private API uses secure connections and does not leave the Amazon network; it is isolated from the public internet. To learn more, see [the section called "Private REST APIs"](#).

Identity and access management for Amazon API Gateway

AWS Identity and Access Management (IAM) is an AWS service that helps an administrator securely control access to AWS resources. IAM administrators control who can be *authenticated* (signed in) and *authorized* (have permissions) to use API Gateway resources. IAM is an AWS service that you can use with no additional charge.

Topics

- [Audience](#)
- [Authenticating with identities](#)
- [Managing access using policies](#)
- [How Amazon API Gateway works with IAM](#)
- [Amazon API Gateway identity-based policy examples](#)
- [Amazon API Gateway resource-based policy examples](#)
- [Troubleshooting Amazon API Gateway identity and access](#)
- [Using service-linked roles for API Gateway](#)

Audience

How you use AWS Identity and Access Management (IAM) differs based on your role:

- **Service user** - request permissions from your administrator if you cannot access features (see [Troubleshooting Amazon API Gateway identity and access](#))
- **Service administrator** - determine user access and submit permission requests (see [How Amazon API Gateway works with IAM](#))
- **IAM administrator** - write policies to manage access (see [Amazon API Gateway identity-based policy examples](#))

Authenticating with identities

Authentication is how you sign in to AWS using your identity credentials. You must be authenticated as the AWS account root user, an IAM user, or by assuming an IAM role.

You can sign in as a federated identity using credentials from an identity source like AWS IAM Identity Center (IAM Identity Center), single sign-on authentication, or Google/Facebook credentials. For more information about signing in, see [How to sign in to your AWS account](#) in the [AWS Sign-In User Guide](#).

For programmatic access, AWS provides an SDK and CLI to cryptographically sign requests. For more information, see [AWS Signature Version 4 for API requests](#) in the [IAM User Guide](#).

AWS account root user

When you create an AWS account, you begin with one sign-in identity called the AWS account *root user* that has complete access to all AWS services and resources. We strongly recommend that you don't use the root user for everyday tasks. For tasks that require root user credentials, see [Tasks that require root user credentials](#) in the [IAM User Guide](#).

IAM users and groups

An [IAM user](#) is an identity with specific permissions for a single person or application. We recommend using temporary credentials instead of IAM users with long-term credentials. For more information, see [Require human users to use federation with an identity provider to access AWS using temporary credentials](#) in the [IAM User Guide](#).

An [IAM group](#) specifies a collection of IAM users and makes permissions easier to manage for large sets of users. For more information, see [Use cases for IAM users](#) in the *IAM User Guide*.

IAM roles

An [IAM role](#) is an identity with specific permissions that provides temporary credentials. You can assume a role by [switching from a user to an IAM role \(console\)](#) or by calling an AWS CLI or AWS API operation. For more information, see [Methods to assume a role](#) in the *IAM User Guide*.

IAM roles are useful for federated user access, temporary IAM user permissions, cross-account access, cross-service access, and applications running on Amazon EC2. For more information, see [Cross account resource access in IAM](#) in the *IAM User Guide*.

Managing access using policies

You control access in AWS by creating policies and attaching them to AWS identities or resources. A policy defines permissions when associated with an identity or resource. AWS evaluates these policies when a principal makes a request. Most policies are stored in AWS as JSON documents. For more information about JSON policy documents, see [Overview of JSON policies](#) in the *IAM User Guide*.

Using policies, administrators specify who has access to what by defining which **principal** can perform **actions** on what **resources**, and under what **conditions**.

By default, users and roles have no permissions. An IAM administrator creates IAM policies and adds them to roles, which users can then assume. IAM policies define permissions regardless of the method used to perform the operation.

Identity-based policies

Identity-based policies are JSON permissions policy documents that you attach to an identity (user, group, or role). These policies control what actions identities can perform, on which resources, and under what conditions. To learn how to create an identity-based policy, see [Define custom IAM permissions with customer managed policies](#) in the *IAM User Guide*.

Identity-based policies can be *inline policies* (embedded directly into a single identity) or *managed policies* (standalone policies attached to multiple identities). To learn how to choose between managed and inline policies, see [Choose between managed policies and inline policies](#) in the *IAM User Guide*.

Resource-based policies

Resource-based policies are JSON policy documents that you attach to a resource. Examples include IAM *role trust policies* and Amazon S3 *bucket policies*. In services that support resource-based policies, service administrators can use them to control access to a specific resource. You must [specify a principal](#) in a resource-based policy.

Resource-based policies are inline policies that are located in that service. You can't use AWS managed policies from IAM in a resource-based policy.

Access control lists (ACLs)

Access control lists (ACLs) control which principals (account members, users, or roles) have permissions to access a resource. ACLs are similar to resource-based policies, although they do not use the JSON policy document format.

Amazon S3, AWS WAF, and Amazon VPC are examples of services that support ACLs. To learn more about ACLs, see [Access control list \(ACL\) overview](#) in the *Amazon Simple Storage Service Developer Guide*.

Other policy types

AWS supports additional policy types that can set the maximum permissions granted by more common policy types:

- **Permissions boundaries** – Set the maximum permissions that an identity-based policy can grant to an IAM entity. For more information, see [Permissions boundaries for IAM entities](#) in the *IAM User Guide*.
- **Service control policies (SCPs)** – Specify the maximum permissions for an organization or organizational unit in AWS Organizations. For more information, see [Service control policies](#) in the *AWS Organizations User Guide*.
- **Resource control policies (RCPs)** – Set the maximum available permissions for resources in your accounts. For more information, see [Resource control policies \(RCPs\)](#) in the *AWS Organizations User Guide*.
- **Session policies** – Advanced policies passed as a parameter when creating a temporary session for a role or federated user. For more information, see [Session policies](#) in the *IAM User Guide*.

Multiple policy types

When multiple types of policies apply to a request, the resulting permissions are more complicated to understand. To learn how AWS determines whether to allow a request when multiple policy types are involved, see [Policy evaluation logic](#) in the *IAM User Guide*.

How Amazon API Gateway works with IAM

Before you use IAM to manage access to API Gateway, you should understand what IAM features are available to use with API Gateway. To get a high-level view of how API Gateway and other AWS services work with IAM, see [AWS Services That Work with IAM](#) in the *IAM User Guide*.

Topics

- [API Gateway identity-based policies](#)
- [API Gateway resource-based policies](#)
- [Authorization based on API Gateway tags](#)
- [API Gateway IAM roles](#)

API Gateway identity-based policies

With IAM identity-based policies, you can specify which actions and resources are allowed or denied as well as the conditions under which actions are allowed or denied. API Gateway supports specific actions, resources, and condition keys. For more information about the API Gateway-specific actions, resources, and condition keys, see [Actions, resources, and condition keys for Amazon API Gateway Management](#) and [Actions, resources, and condition keys for Amazon API Gateway Management V2](#). For information about all of the elements that you use in a JSON policy, see [IAM JSON Policy Elements Reference](#) in the *IAM User Guide*.

The following example shows an identity-based policy that allows a user to create or update only private REST APIs. For more examples, see [the section called “Identity-based policy examples”](#).

JSON

```
{  
    "Version": "2012-10-17",  
    "Statement": [  
        {
```

```
        "Sid": "ScopeToPrivateApis",
        "Effect": "Allow",
        "Action": [
            "apigateway:PATCH",
            "apigateway:POST",
            "apigateway:PUT"
        ],
        "Resource": [
            "arn:aws:apigateway:us-east-1::/restapis",
            "arn:aws:apigateway:us-east-1::/restapis/??????????"
        ],
        "Condition": {
            "ForAllValues:StringEqualsIfExists": {
                "apigateway:Request/EndpointType": "PRIVATE",
                "apigateway:Resource/EndpointType": "PRIVATE"
            }
        }
    },
    {
        "Sid": "AllowResourcePolicyUpdates",
        "Effect": "Allow",
        "Action": [
            "apigateway:UpdateRestApiPolicy"
        ],
        "Resource": [
            "arn:aws:apigateway:us-east-1::/restapis/*"
        ]
    }
]
```

Actions

The Action element of a JSON policy describes the actions that you can use to allow or deny access in a policy.

Policy actions in API Gateway use the following prefix before the action: apigateway:. Policy statements must include either an Action or NotAction element. API Gateway defines its own set of actions that describe tasks that you can perform with this service.

The API-managing Action expression has the format `apigateway:action`, where `action` is one of the following API Gateway actions: **GET**, **POST**, **PUT**, **DELETE**, **PATCH** (to update resources), or *****, which is all of the previous actions.

Some examples of the Action expression include:

- **apigateway:*** for all API Gateway actions.
- **apigateway:GET** for just the GET action in API Gateway.

To specify multiple actions in a single statement, separate them with commas as follows:

```
"Action": [  
    "apigateway:action1",  
    "apigateway:action2"]
```

For information about HTTP verbs to use for specific API Gateway operations, see [Amazon API Gateway Version 1 API Reference](#) (REST APIs) and [Amazon API Gateway Version 2 API Reference](#) (WebSocket and HTTP APIs).

For more information, see [the section called “Identity-based policy examples”](#).

Resources

Administrators can use AWS JSON policies to specify who has access to what. That is, which **principal** can perform **actions** on what **resources**, and under what **conditions**.

The Resource JSON policy element specifies the object or objects to which the action applies. As a best practice, specify a resource using its [Amazon Resource Name \(ARN\)](#). For actions that don't support resource-level permissions, use a wildcard (*) to indicate that the statement applies to all resources.

```
"Resource": "*"
```

API Gateway resources have the following ARN format:

```
arn:aws:apigateway:region::resource-path-specifier
```

For example, to specify a REST API with the id `api-id` and its sub-resources, such as authorizers in your statement, use the following ARN:

```
"Resource": "arn:aws:apigateway:us-east-2::/restapis/api-id/*"
```

To specify all REST APIs and sub-resources that belong to a specific account, use the wildcard (*):

```
"Resource": "arn:aws:apigateway:us-east-2::/restapis/*"
```

For a list of API Gateway resource types and their ARNs, see [API Gateway Amazon Resource Name \(ARN\) reference](#).

Condition keys

Administrators can use AWS JSON policies to specify who has access to what. That is, which **principal** can perform **actions** on what **resources**, and under what **conditions**.

The Condition element specifies when statements execute based on defined criteria. You can create conditional expressions that use [condition operators](#), such as equals or less than, to match the condition in the policy with values in the request. To see all AWS global condition keys, see [AWS global condition context keys](#) in the *IAM User Guide*.

API Gateway defines its own set of condition keys and also supports using some global condition keys. For a list of API Gateway condition keys, see [Condition Keys for Amazon API Gateway](#) in the *IAM User Guide*. For information about which actions and resources you can use with a condition key, see [Actions Defined by Amazon API Gateway](#).

For information about tagging, including attribute-based access control, see [Tagging](#).

Examples

For examples of API Gateway identity-based policies, see [Amazon API Gateway identity-based policy examples](#).

API Gateway resource-based policies

Resource-based policies are JSON policy documents that specify what actions a specified principal can perform on the API Gateway resource and under what conditions. API Gateway supports resource-based permissions policies for REST APIs. You use resource policies to control who can invoke a REST API. For more information, see [the section called “Use API Gateway resource policies”](#).

Examples

For examples of API Gateway resource-based policies, see [API Gateway resource policy examples](#).

Authorization based on API Gateway tags

You can attach tags to API Gateway resources or pass tags in a request to API Gateway. To control access based on tags, you provide tag information in the [condition element](#) of a policy using the `apigateway:ResourceTag/key-name`, `aws:RequestTag/key-name`, or `aws:TagKeys` condition keys. For more information about tagging API Gateway resources, see [the section called "Attribute-based access control"](#).

For examples of identity-based policies for limiting access to a resource based on the tags on that resource, see [Using tags to control access to API Gateway REST API resources](#).

API Gateway IAM roles

An [IAM role](#) is an entity within your AWS account that has specific permissions.

Using temporary credentials with API Gateway

You can use temporary credentials to sign in with federation, assume an IAM role, or to assume a cross-account role. You obtain temporary security credentials by calling AWS STS API operations such as [AssumeRole](#) or [GetFederationToken](#).

API Gateway supports using temporary credentials.

Service-linked roles

[Service-linked roles](#) allow AWS services to access resources in other services to complete an action on your behalf. Service-linked roles appear in your IAM account and are owned by the service. An IAM administrator can view but not edit the permissions for service-linked roles.

API Gateway supports service-linked roles. For information about creating or managing API Gateway service-linked roles, see [Using service-linked roles for API Gateway](#).

Service roles

A service can assume a [service role](#) on your behalf. A service role allows the service to access resources in other services to complete an action on your behalf. Service roles appear in your IAM account and are owned by the account, so an administrator can change the permissions for this role. However, doing so might break the functionality of the service.

API Gateway supports service roles.

Amazon API Gateway identity-based policy examples

By default, IAM users and roles don't have permission to create or modify API Gateway resources. They also can't perform tasks using the AWS Management Console, AWS CLI, or AWS SDKs. An IAM administrator must create IAM policies that grant users and roles permission to perform specific API operations on the specified resources they need. The administrator must then attach those policies to the IAM users or groups that require those permissions.

For information about how to create IAM policies, see [Creating Policies on the JSON Tab](#) in the *IAM User Guide*. For information about the actions, resources, and conditions specific to API Gateway, see [Actions, resources, and condition keys for Amazon API Gateway Management](#) and [Actions, resources, and condition keys for Amazon API Gateway Management V2](#).

Topics

- [Policy best practices](#)
- [Allow users to view their own permissions](#)
- [Simple read permissions](#)
- [Create only REQUEST or JWT authorizers](#)
- [Require that the default execute-api endpoint is disabled](#)
- [Allow users to create or update only private REST APIs](#)
- [Require that API routes have authorization](#)
- [Prevent a user from creating or updating a VPC link](#)
- [Example policies for using routing rules](#)

Policy best practices

Identity-based policies determine whether someone can create, access, or delete API Gateway resources in your account. These actions can incur costs for your AWS account. When you create or edit identity-based policies, follow these guidelines and recommendations:

- **Get started with AWS managed policies and move toward least-privilege permissions** – To get started granting permissions to your users and workloads, use the *AWS managed policies* that grant permissions for many common use cases. They are available in your AWS account. We recommend that you reduce permissions further by defining AWS customer managed policies

that are specific to your use cases. For more information, see [AWS managed policies](#) or [AWS managed policies for job functions](#) in the *IAM User Guide*.

- **Apply least-privilege permissions** – When you set permissions with IAM policies, grant only the permissions required to perform a task. You do this by defining the actions that can be taken on specific resources under specific conditions, also known as *least-privilege permissions*. For more information about using IAM to apply permissions, see [Policies and permissions in IAM](#) in the *IAM User Guide*.
- **Use conditions in IAM policies to further restrict access** – You can add a condition to your policies to limit access to actions and resources. For example, you can write a policy condition to specify that all requests must be sent using SSL. You can also use conditions to grant access to service actions if they are used through a specific AWS service, such as CloudFormation. For more information, see [IAM JSON policy elements: Condition](#) in the *IAM User Guide*.
- **Use IAM Access Analyzer to validate your IAM policies to ensure secure and functional permissions** – IAM Access Analyzer validates new and existing policies so that the policies adhere to the IAM policy language (JSON) and IAM best practices. IAM Access Analyzer provides more than 100 policy checks and actionable recommendations to help you author secure and functional policies. For more information, see [Validate policies with IAM Access Analyzer](#) in the *IAM User Guide*.
- **Require multi-factor authentication (MFA)** – If you have a scenario that requires IAM users or a root user in your AWS account, turn on MFA for additional security. To require MFA when API operations are called, add MFA conditions to your policies. For more information, see [Secure API access with MFA](#) in the *IAM User Guide*.

For more information about best practices in IAM, see [Security best practices in IAM](#) in the *IAM User Guide*.

Allow users to view their own permissions

This example shows how you might create a policy that allows IAM users to view the inline and managed policies that are attached to their user identity. This policy includes permissions to complete this action on the console or programmatically using the AWS CLI or AWS API.

```
{  
    "Version": "2012-10-17",  
    "Statement": [  
        {  
            "Sid": "ViewOwnUserInfo",  
            "Effect": "Allow",  
            "Action": "iam:GetUser",  
            "Resource": "arn:aws:iam::  
                EXAMPLE-AWS-ACCOUNT-ID:user/  
                EXAMPLE-IAM-USER-NAME  
        }  
    ]  
}
```

```
        "Effect": "Allow",
        "Action": [
            "iam:GetUserPolicy",
            "iam>ListGroupsForUser",
            "iam>ListAttachedUserPolicies",
            "iam>ListUserPolicies",
            "iam GetUser"
        ],
        "Resource": ["arn:aws:iam::*:user/${aws:username}"]
    },
    {
        "Sid": "NavigateInConsole",
        "Effect": "Allow",
        "Action": [
            "iam:GetGroupPolicy",
            "iam:GetPolicyVersion",
            "iam:GetPolicy",
            "iam>ListAttachedGroupPolicies",
            "iam>ListGroupPolicies",
            "iam>ListPolicyVersions",
            "iam>ListPolicies",
            "iam>ListUsers"
        ],
        "Resource": "*"
    }
]
}
```

Simple read permissions

This example policy gives a user permission to get information about all of the resources of an HTTP or WebSocket API with the identifier of a123456789 in the AWS Region of us-east-1. The resource `arn:aws:apigateway:us-east-1::/apis/a123456789/*` includes all sub-resources of the API such as authorizers and deployments.

JSON

```
{
    "Version": "2012-10-17",
    "Statement": [
        {
            "Effect": "Allow",
```

```
    "Action": [
        "apigateway:GET"
    ],
    "Resource": [
        "arn:aws:apigateway:::/apis/a123456789/*"
    ]
}
]
```

Create only REQUEST or JWT authorizers

This example policy allows a user to create APIs with only REQUEST or JWT authorizers, including through [import](#). In the Resource section of the policy, arn:aws:apigateway:us-east-1::/apis/?????????? requires that resources have a maximum of 10 characters, which excludes sub-resources of an API. This example uses ForAllValues in the Condition section because users can create multiple authorizers at once by importing an API.

JSON

```
{
    "Version": "2012-10-17",
    "Statement": [
        {
            "Sid": "OnlyAllowSomeAuthorizerTypes",
            "Effect": "Allow",
            "Action": [
                "apigateway:PUT",
                "apigateway:POST",
                "apigateway:PATCH"
            ],
            "Resource": [
                "arn:aws:apigateway:us-east-1::apis",
                "arn:aws:apigateway:us-east-1::apis/??????????",
                "arn:aws:apigateway:us-east-1::apis/*/authorizers",
                "arn:aws:apigateway:us-east-1::apis/*/authorizers/*"
            ],
            "Condition": {
                "ForAllValues:StringEqualsIfExists": {
                    "apigateway:Request/AuthorizerType": [
                        "REQUEST",
                        "JWT"
                    ]
                }
            }
        }
    ]
}
```

```
        "JWT"
    ]
}
}
]
}
```

Require that the default execute-api endpoint is disabled

This example policy allows users to create, update or import an API, with the requirement that `DisableExecuteApiEndpoint` is true. When `DisableExecuteApiEndpoint` is true, clients can't use the default execute-api endpoint to invoke an API.

We use the `BoolIfExists` condition to handle a call to update an API that doesn't have the `DisableExecuteApiEndpoint` condition key populated. When a user attempts to create or import an API, the `DisableExecuteApiEndpoint` condition key is always populated.

Because the `apis/*` resource also captures sub resources such as authorizers or methods, we explicitly scope it to just APIs with a Deny statement.

JSON

```
{
  "Version": "2012-10-17",
  "Statement": [
    {
      "Sid": "DisableExecuteApiEndpoint",
      "Effect": "Allow",
      "Action": [
        "apigateway:PATCH",
        "apigateway:POST",
        "apigateway:PUT"
      ],
      "Resource": [
        "arn:aws:apigateway:us-east-1::/apis",
        "arn:aws:apigateway:us-east-1::/apis/*"
      ],
      "Condition": {
        "BoolIfExists": {
          "apigateway:Request/DisableExecuteApiEndpoint": true
        }
      }
    }
  ]
}
```

```
        }
    },
},
{
    "Sid": "ScopeDownToJustApis",
    "Effect": "Deny",
    "Action": [
        "apigateway:PATCH",
        "apigateway:POST",
        "apigateway:PUT"
    ],
    "Resource": [
        "arn:aws:apigateway:us-east-1::/apis/*/*"
    ]
}
]
```

Allow users to create or update only private REST APIs

This example policy uses condition keys to require that a user creates only PRIVATE APIs, and to prevent updates that might change an API from PRIVATE to another type, such as REGIONAL.

We use `ForAllValues` to require that every `EndpointType` added to an API is PRIVATE. We use a resource condition key to allow any update to an API as long as it's PRIVATE. `ForAllValues` applies only if a condition key is present.

We use the non-greedy matcher (?) to explicitly match against API IDs to prevent allowing non-API resources such as authorizers.

JSON

```
{
    "Version": "2012-10-17",
    "Statement": [
        {
            "Sid": "ScopePutToPrivateApis",
            "Effect": "Allow",
            "Action": [
                "apigateway:PUT"
            ],
            "Condition": {
                "StringEquals": {
                    "aws:SecureTransport": "TLSv1.2"
                }
            }
        }
    ]
}
```

```
"Resource": [
    "arn:aws:apigateway:us-east-1::/restapis",
    "arn:aws:apigateway:us-east-1::/restapis/??????????"
],
"Condition": {
    "ForAllValues:StringEquals": {
        "apigateway:Resource/EndpointType": "PRIVATE"
    }
}
},
{
    "Sid": "ScopeToPrivateApis",
    "Effect": "Allow",
    "Action": [
        "apigateway:DELETE",
        "apigateway:PATCH",
        "apigateway:POST"
    ],
    "Resource": [
        "arn:aws:apigateway:us-east-1::/restapis",
        "arn:aws:apigateway:us-east-1::/restapis/??????????"
    ],
    "Condition": {
        "ForAllValues:StringEquals": {
            "apigateway:Request/EndpointType": "PRIVATE",
            "apigateway:Resource/EndpointType": "PRIVATE"
        }
    }
},
{
    "Sid": "AllowResourcePolicyUpdates",
    "Effect": "Allow",
    "Action": [
        "apigateway:UpdateRestApiPolicy"
    ],
    "Resource": [
        "arn:aws:apigateway:us-east-1::/restapis/*"
    ]
}
]
```

Require that API routes have authorization

This policy causes attempts to create or update a route (including through [import](#)) to fail if the route has no authorization. ForAnyValue evaluates to false if the key is not present, such as when a route is not being created or updated. We use ForAnyValue because multiple routes can be created through import.

JSON

```
{
    "Version": "2012-10-17",
    "Statement": [
        {
            "Sid": "AllowUpdatesOnApisAndRoutes",
            "Effect": "Allow",
            "Action": [
                "apigateway:POST",
                "apigateway:PATCH",
                "apigateway:PUT"
            ],
            "Resource": [
                "arn:aws:apigateway:us-east-1::apis",
                "arn:aws:apigateway:us-east-1::apis/??????????",
                "arn:aws:apigateway:us-east-1::apis/*/routes",
                "arn:aws:apigateway:us-east-1::apis/*/routes/*"
            ]
        },
        {
            "Sid": "DenyUnauthorizedRoutes",
            "Effect": "Deny",
            "Action": [
                "apigateway:POST",
                "apigateway:PATCH",
                "apigateway:PUT"
            ],
            "Resource": [
                "arn:aws:apigateway:us-east-1::apis",
                "arn:aws:apigateway:us-east-1::apis/*"
            ],
            "Condition": {
                "ForAnyValue:StringEqualsIgnoreCase": {
                    "apigateway:Request/RouteAuthorizationType": "NONE"
                }
            }
        }
    ]
}
```

```
        }
    }
}
]
```

Prevent a user from creating or updating a VPC link

This policy prevents a user from creating or updating a VPC link. A VPC link enables you to expose resources within an Amazon VPC to clients outside of the VPC.

JSON

```
{
    "Version": "2012-10-17",
    "Statement": [
        {
            "Sid": "DenyVPCLink",
            "Effect": "Deny",
            "Action": [
                "apigateway:POST",
                "apigateway:PUT",
                "apigateway:PATCH"
            ],
            "Resource": [
                "arn:aws:apigateway:us-east-1:::vpclinks",
                "arn:aws:apigateway:us-east-1:::vpclinks/*"
            ]
        }
    ]
}
```

Example policies for using routing rules

The following example policies show how to use the `RoutingRule` condition keys to control how users can route traffic from their custom domain names to their REST APIs. You can use these examples to create fine-grained policies for what kind of routing rules users can make. For more information, see [the section called “Routing rules”](#).

Prevent a user from changing how a custom domain name routes a request

This policy prevents a user from creating or updating a BasePathMapping, ApiMapping or RoutingRule. All of these resources might change how a custom domain name routes requests to APIs.

JSON

```
{  
    "Version": "2012-10-17",  
    "Statement": [  
        {  
            "Sid": "DenyAccessBasePathMappingsApiMappingsRoutingRules",  
            "Effect": "Deny",  
            "Action": "apigateway:*",  
            "Resource": [  
                "arn:aws:apigateway:us-east-1::/domainnames/example.com/basepathmappings/*",  
                "arn:aws:apigateway:us-east-1::/domainnames/example.com/apimappings/*",  
                "arn:aws:apigateway:us-east-1:111122223333:/domainnames/example.com/routingrules/*"  
            ]  
        }  
    ]  
}
```

Allow a user to update a routing rule for certain priorities

This policy allows a user to only update a routing rule to a priority between 1001 and 2000. You can use this rule to separate your production rules from lower priority rules and then allow users to modify lower priority rules without impacting production rules.

JSON

```
{  
    "Version": "2012-10-17",  
    "Statement": [  
        {  
            "Sid": "UpdatingRoutingRulePriorityBetween1001And2000",  
            "Effect": "Allow",  
            "Action": "apigateway:PUT",  
            "Resource": "arn:aws:apigateway:us-east-1:111122223333:/restapis/  
            "/routes/{id}/operations/{operationId}/x-amazon-apigateway-routing-rule",  
            "Condition": "StringEquals(apigateway:path, /v1/categories/{category})"  
        }  
    ]  
}
```

```
"Action": "apigateway:UpdateRoutingRule",
"Resource": "arn:aws:apigateway:us-east-1:111122223333:/domainnames/
example.com/routingrules/*",
"Condition": {
    "NumericGreaterThanOrEqualTo": {
        "apigateway:Resource/Priority": 1001,
        "apigateway:Request/Priority": 1001
    },
    "NumericLessThanOrEqualTo": {
        "apigateway:Resource/Priority": 2000,
        "apigateway:Request/Priority": 2000
    }
}
]
```

Allow a user to update a routing rule or base path mapping for a certain base path value

This policy allows a user to only update a base path mapping for any base path that starts with `orders` or update a routing rule matching a base path that starts with `orders`. In this policy, a user can update a base path mapping or routing rule for `orders/create` or `orders123`, but not `payment/orders`.

JSON

```
{
    "Version": "2012-10-17",
    "Statement": [
        {
            "Sid": "AllowUpdateRoutingRuleUnderPathOrders",
            "Effect": "Allow",
            "Action": "apigateway:UpdateRoutingRule",
            "Resource": "arn:aws:apigateway:us-east-1:111122223333:/domainnames/
example.com/routingrules/*",
            "Condition": {
                "ForAllValues:StringLike": {
                    "apigateway:Request/ConditionBasePaths": ["orders*"],
                    "apigateway:Resource/ConditionBasePaths": ["orders*"]
                },
                "Null": {}
            }
        }
    ]
}
```

```
        "apigateway:Request/ConditionBasePaths": "false",
        "apigateway:Resource/ConditionBasePaths": "false"
    }
}
]
}
```

Allow a user to update the routing mode to specific values

This policy allows a user to only update the routing mode to API_MAPPING_ONLY and ROUTING_RULE_THEN_API_MAPPING. For more information about routing mode, see [the section called "Set the routing mode for your custom domain name"](#).

JSON

```
{
    "Version": "2012-10-17",
    "Statement": [
        {
            "Sid": "AllowUpdateRoutingModeToAnythingWithApiMapping",
            "Effect": "Allow",
            "Action": ["apigateway:PATCH"],
            "Resource": "arn:aws:apigateway:us-east-1:::domainnames/example.com",
            "Condition": {
                "StringLike": {
                    "apigateway:Request/RequestMethod": "*API_MAPPING*"
                }
            }
        ]
    }
}
```

Amazon API Gateway resource-based policy examples

For resource-based policy examples, see [the section called "API Gateway resource policy examples"](#).

Troubleshooting Amazon API Gateway identity and access

Use the following information to help you diagnose and fix common issues that you might encounter when working with API Gateway and IAM.

Topics

- [I am not authorized to perform an action in API Gateway](#)
- [I am not authorized to perform iam:PassRole](#)
- [I want to allow people outside of my AWS account to access my API Gateway resources](#)

I am not authorized to perform an action in API Gateway

If you receive an error that you're not authorized to perform an action, your policies must be updated to allow you to perform the action.

The following example error occurs when the mateojackson IAM user tries to use the console to view details about a fictional *my-example-widget* resource but doesn't have the fictional apigateway:*GetWidget* permissions.

```
User: arn:aws:iam::123456789012:user/mateojackson is not authorized to perform:  
apigateway:GetWidget on resource: my-example-widget because no identity-based policy  
allows the GetWidget action
```

In this case, the policy for the mateojackson user must be updated to allow access to the *my-example-widget* resource by using the apigateway:*GetWidget* action.

If you need help, contact your AWS administrator. Your administrator is the person who provided you with your sign-in credentials.

I am not authorized to perform iam:PassRole

If you receive an error that you're not authorized to perform the iam:PassRole action, your policies must be updated to allow you to pass a role to API Gateway.

Some AWS services allow you to pass an existing role to that service instead of creating a new service role or service-linked role. To do this, you must have permissions to pass the role to the service.

The following example error occurs when an IAM user named `marymajor` tries to use the console to perform an action in API Gateway. However, the action requires the service to have permissions that are granted by a service role. Mary does not have permissions to pass the role to the service.

```
User: arn:aws:iam::123456789012:user/marymajor is not authorized to perform:  
    iam:PassRole
```

In this case, Mary's policies must be updated to allow her to perform the `iam:PassRole` action.

If you need help, contact your AWS administrator. Your administrator is the person who provided you with your sign-in credentials.

I want to allow people outside of my AWS account to access my API Gateway resources

You can create a role that users in other accounts or people outside of your organization can use to access your resources. You can specify who is trusted to assume the role. For services that support resource-based policies or access control lists (ACLs), you can use those policies to grant people access to your resources.

To learn more, consult the following:

- To learn whether API Gateway supports these features, see [How Amazon API Gateway works with IAM](#).
- To learn how to provide access to your resources across AWS accounts that you own, see [Providing access to an IAM user in another AWS account that you own](#) in the *IAM User Guide*.
- To learn how to provide access to your resources to third-party AWS accounts, see [Providing access to AWS accounts owned by third parties](#) in the *IAM User Guide*.
- To learn how to provide access through identity federation, see [Providing access to externally authenticated users \(identity federation\)](#) in the *IAM User Guide*.
- To learn the difference between using roles and resource-based policies for cross-account access, see [Cross account resource access in IAM](#) in the *IAM User Guide*.

Using service-linked roles for API Gateway

Amazon API Gateway uses AWS Identity and Access Management (IAM) [service-linked roles](#). A service-linked role is a unique type of IAM role that is linked directly to API Gateway. Service-linked

roles are predefined by API Gateway and include all the permissions that the service requires to call other AWS services on your behalf.

A service-linked role makes setting up API Gateway easier because you don't have to manually add the necessary permissions. API Gateway defines the permissions of its service-linked roles, and unless defined otherwise, only API Gateway can assume its roles. The defined permissions include the trust policy and the permissions policy, and that permissions policy cannot be attached to any other IAM entity.

You can delete a service-linked role only after first deleting the related resources. This protects your API Gateway resources because you can't inadvertently remove permission to access the resources.

For information about other services that support service-linked roles, see [AWS Services That Work with IAM](#) and look for the services that have Yes in the **Service-Linked Role** column. Choose a Yes with a link to view the service-linked role documentation for that service.

Service-linked role permissions for API Gateway

API Gateway uses the service-linked role named **AWSServiceRoleForAPIGateway** – Allows API Gateway to access Elastic Load Balancing, Amazon Data Firehose, and other service resources on your behalf.

The AWSServiceRoleForAPIGateway service-linked role trusts the following services to assume the role:

- ops.apigateway.amazonaws.com

The role permissions policy allows API Gateway to complete the following actions on the specified resources:

JSON

```
{  
    "Version": "2012-10-17",  
    "Statement": [  
        {  
            "Effect": "Allow",  
            "Action": [  
                "elasticloadbalancing:AddListenerCertificates",  
                "elasticloadbalancing:DescribeListenerCertificates",  
                "elasticloadbalancing:ListListeners",  
                "elasticloadbalancing:ListLoadBalancers",  
                "elasticloadbalancing:RemoveListenerCertificates"  
            ]  
        }  
    ]  
}
```

```
        "elasticloadbalancing:RemoveListenerCertificates",
        "elasticloadbalancing:ModifyListener",
        "elasticloadbalancing:DescribeListeners",
        "elasticloadbalancing:DescribeLoadBalancers",
        "xray:PutTraceSegments",
        "xray:PutTelemetryRecords",
        "xray:GetSamplingTargets",
        "xray:GetSamplingRules",
        "logs>CreateLogDelivery",
        "logs:GetLogDelivery",
        "logs:UpdateLogDelivery",
        "logs>DeleteLogDelivery",
        "logs>ListLogDeliveries",
        "servicediscovery:DiscoverInstances"
    ],
    "Resource": [
        "*"
    ]
},
{
    "Effect": "Allow",
    "Action": [
        "firehose:DescribeDeliveryStream",
        "firehose:PutRecord",
        "firehose:PutRecordBatch"
    ],
    "Resource": "arn:aws:firehose:*:*:deliverystream/amazon-apigateway-*"
},
{
    "Effect": "Allow",
    "Action": [
        "acm:DescribeCertificate",
        "acm:GetCertificate"
    ],
    "Resource": "arn:aws:acm:*:*:certificate/*"
},
{
    "Effect": "Allow",
    "Action": "ec2>CreateNetworkInterfacePermission",
    "Resource": "arn:aws:ec2:*:*:network-interface/*"
},
{
    "Effect": "Allow",
    "Action": "ec2>CreateTags",
```

```
"Resource": "arn:aws:ec2::::network-interface/*",
"Condition": {
    "ForAllValues:StringEquals": [
        "aws:TagKeys": [
            "Owner",
            "VpcLinkId"
        ]
    }
},
{
    "Effect": "Allow",
    "Action": [
        "ec2:ModifyNetworkInterfaceAttribute",
        "ec2:DeleteNetworkInterface",
        "ec2:AssignPrivateIpAddresses",
        "ec2>CreateNetworkInterface",
        "ec2:DeleteNetworkInterfacePermission",
        "ec2:DescribeNetworkInterfaces",
        "ec2:DescribeAvailabilityZones",
        "ec2:DescribeNetworkInterfaceAttribute",
        "ec2:DescribeVpcs",
        "ec2:DescribeNetworkInterfacePermissions",
        "ec2:UnassignPrivateIpAddresses",
        "ec2:DescribeSubnets",
        "ec2:DescribeRouteTables",
        "ec2:DescribeSecurityGroups"
    ],
    "Resource": "*"
},
{
    "Effect": "Allow",
    "Action": "servicediscovery:GetNamespace",
    "Resource": "arn:aws:servicediscovery::::namespace/*"
},
{
    "Effect": "Allow",
    "Action": "servicediscovery:GetService",
    "Resource": "arn:aws:servicediscovery::::service/*"
}
]
```

You must configure permissions to allow an IAM entity (such as a user, group, or role) to create, edit, or delete a service-linked role. For more information, see [Service-Linked Role Permissions](#) in the *IAM User Guide*.

Creating a service-linked role for API Gateway

You don't need to manually create a service-linked role. When you create an API, custom domain name, or VPC link in the AWS Management Console, the AWS CLI, or the AWS API, API Gateway creates the service-linked role for you.

If you delete this service-linked role, and then need to create it again, you can use the same process to recreate the role in your account. When you create an API, custom domain name, or VPC link, API Gateway creates the service-linked role for you again.

Editing a service-linked role for API Gateway

API Gateway does not allow you to edit the `AWSServiceRoleForAPIGateway` service-linked role. After you create a service-linked role, you can't change the name of the role because various entities might reference the role. However, you can edit the description of the role using IAM. For more information, see [Editing a Service-Linked Role](#) in the *IAM User Guide*.

Deleting a service-linked role for API Gateway

If you no longer need to use a feature or service that requires a service-linked role, we recommend that you delete that role. That way you don't have an unused entity that is not actively monitored or maintained. However, you must clean up the resources for your service-linked role before you can manually delete it.

Note

If the API Gateway service is using the role when you try to delete the resources, then the deletion might fail. If that happens, wait for a few minutes and try the operation again.

To delete API Gateway resources used by the `AWSServiceRoleForAPIGateway`

1. Open the API Gateway console at <https://console.aws.amazon.com/apigateway/>.
2. Navigate to the API, custom domain name, or VPC link that uses the service-linked role.

3. Use the console to delete the resource.
4. Repeat the procedure to delete all APIs, custom domain names, or VPC links that use the service-linked role.

To manually delete the service-linked role using IAM

Use the IAM console, the AWS CLI, or the AWS API to delete the `AWSServiceRoleForAPIGateway` service-linked role. For more information, see [Deleting a Service-Linked Role](#) in the *IAM User Guide*.

Supported Regions for API Gateway service-linked roles

API Gateway supports using service-linked roles in all of the Regions where the service is available. For more information, see [AWS Service Endpoints](#).

API Gateway updates to AWS managed policies

View details about updates to AWS managed policies for API Gateway since this service began tracking these changes. For automatic alerts about changes to this page, subscribe to the RSS feed on the API Gateway [Document history](#) page.

Change	Description	Date
Added acm:GetCertificate support to the <code>AWSServiceRoleForAPIGateway</code> policy.	The <code>AWSServiceRoleForAPIGateway</code> policy now includes permission to call the ACM <code>GetCertificate</code> API action.	July 12, 2021
API Gateway started tracking changes	API Gateway started tracking changes for its AWS managed policies.	July 12, 2021

Logging and monitoring in Amazon API Gateway

Monitoring is an important part of maintaining the reliability, availability, and performance of API Gateway and your AWS solutions. You should collect monitoring data from all of the parts of your

AWS solution so that you can more easily debug a multi-point failure if one occurs. AWS provides several tools for monitoring your API Gateway resources and responding to potential incidents:

Amazon CloudWatch Logs

To help debug issues related to request execution or client access to your API, you can enable CloudWatch Logs to log API calls. For more information, see [the section called “CloudWatch logs”](#).

Amazon CloudWatch Alarms

Using CloudWatch alarms, you watch a single metric over a time period that you specify. If the metric exceeds a given threshold, a notification is sent to an Amazon Simple Notification Service topic or AWS Auto Scaling policy. CloudWatch alarms do not invoke actions when a metric is in a particular state. Rather the state must have changed and been maintained for a specified number of periods. For more information, see [the section called “CloudWatch metrics”](#).

Access Logging to Firehose

To help debug issues related to client access to your API, you can enable Firehose to log API calls. For more information, see [the section called “Firehose”](#).

AWS CloudTrail

CloudTrail provides a record of actions taken by a user, role, or an AWS service in API Gateway. Using the information collected by CloudTrail, you can determine the request that was made to API Gateway, the IP address from which the request was made, who made the request, when it was made, and additional details. For more information, see [the section called “Working with CloudTrail”](#).

AWS X-Ray

X-Ray is an AWS service that gathers data about the requests that your application serves, and uses it to construct a service map that you can use to identify issues with your application and opportunities for optimization. For more information, see [the section called “Set up AWS X-Ray”](#).

AWS Config

AWS Config provides a detailed view of the configuration of AWS resources in your account. You can see how resources are related, get a history of configuration changes, and see how

relationships and configurations change over time. You can use AWS Config to define rules that evaluate resource configurations for data compliance. AWS Config rules represent the ideal configuration settings for your API Gateway resources. If a resource violates a rule and is flagged as noncompliant, AWS Config can alert you using an Amazon Simple Notification Service (Amazon SNS) topic. For details, see [the section called “Working with AWS Config”](#).

Logging Amazon API Gateway API calls using AWS CloudTrail

Amazon API Gateway is integrated with [AWS CloudTrail](#), a service that provides a record of actions taken by a user, role, or an AWS service. CloudTrail captures all REST API calls for API Gateway service as events. The calls captured include calls from the API Gateway console and code calls to the API Gateway service APIs. Using the information collected by CloudTrail, you can determine the request that was made to API Gateway, the IP address from which the request was made, when it was made, and additional details.

 **Note**

[TestInvokeAuthorizer](#) and [TestInvokeMethod](#) are not logged in CloudTrail.

Every event or log entry contains information about who generated the request. The identity information helps you determine the following:

- Whether the request was made with root user or user credentials.
- Whether the request was made on behalf of an IAM Identity Center user.
- Whether the request was made with temporary security credentials for a role or federated user.
- Whether the request was made by another AWS service.

CloudTrail is active in your AWS account when you create the account and you automatically have access to the CloudTrail **Event history**. The CloudTrail **Event history** provides a viewable, searchable, downloadable, and immutable record of the past 90 days of recorded management events in an AWS Region. For more information, see [Working with CloudTrail Event history](#) in the [AWS CloudTrail User Guide](#). There are no CloudTrail charges for viewing the **Event history**.

For an ongoing record of events in your AWS account past 90 days, create a trail or a [CloudTrail Lake](#) event data store.

CloudTrail trails

A *trail* enables CloudTrail to deliver log files to an Amazon S3 bucket. All trails created using the AWS Management Console are multi-Region. You can create a single-Region or a multi-Region trail by using the AWS CLI. Creating a multi-Region trail is recommended because you capture activity in all AWS Regions in your account. If you create a single-Region trail, you can view only the events logged in the trail's AWS Region. For more information about trails, see [Creating a trail for your AWS account](#) and [Creating a trail for an organization](#) in the *AWS CloudTrail User Guide*.

You can deliver one copy of your ongoing management events to your Amazon S3 bucket at no charge from CloudTrail by creating a trail, however, there are Amazon S3 storage charges. For more information about CloudTrail pricing, see [AWS CloudTrail Pricing](#). For information about Amazon S3 pricing, see [Amazon S3 Pricing](#).

CloudTrail Lake event data stores

CloudTrail Lake lets you run SQL-based queries on your events. CloudTrail Lake converts existing events in row-based JSON format to [Apache ORC](#) format. ORC is a columnar storage format that is optimized for fast retrieval of data. Events are aggregated into *event data stores*, which are immutable collections of events based on criteria that you select by applying [advanced event selectors](#). The selectors that you apply to an event data store control which events persist and are available for you to query. For more information about CloudTrail Lake, see [Working with AWS CloudTrail Lake](#) in the *AWS CloudTrail User Guide*.

CloudTrail Lake event data stores and queries incur costs. When you create an event data store, you choose the [pricing option](#) you want to use for the event data store. The pricing option determines the cost for ingesting and storing events, and the default and maximum retention period for the event data store. For more information about CloudTrail pricing, see [AWS CloudTrail Pricing](#).

API Gateway management events in CloudTrail

[Management events](#) provide information about management operations that are performed on resources in your AWS account. These are also known as control plane operations. By default, CloudTrail logs management events.

Amazon API Gateway logs all API Gateway actions as management events, except for [TestInvokeAuthorizer](#) and [TestInvokeMethod](#). For a list of the Amazon API Gateway actions that API Gateway logs to CloudTrail, see the [Amazon API Gateway API Reference](#).

API Gateway event example

An event represents a single request from any source and includes information about the requested API operation, the date and time of the operation, request parameters, and so on. CloudTrail log files aren't an ordered stack trace of the public API calls, so events don't appear in any specific order.

The following example shows a CloudTrail event that demonstrates the API Gateway `GetResource` action:

```
{  
    Records: [  
        {  
            eventVersion: "1.03",  
            userIdentity: {  
                type: "Root",  
                principalId: "AKIAI44QH8DHBEEXAMPLE",  
                arn: "arn:aws:iam::123456789012:root",  
                accountId: "123456789012",  
                accessKeyId: "AKIAIOSFODNN7EXAMPLE",  
                sessionContext: {  
                    attributes: {  
                        mfaAuthenticated: "false",  
                        creationDate: "2015-06-16T23:37:58Z"  
                    }  
                }  
            },  
            eventTime: "2015-06-17T00:47:28Z",  
            eventSource: "apigateway.amazonaws.com",  
            eventName: "GetResource",  
            awsRegion: "us-east-1",  
            sourceIPAddress: "203.0.113.11",  
            userAgent: "example-user-agent-string",  
            requestParameters: {  
                restApiId: "3rbEXAMPLE",  
                resourceId: "5tfEXAMPLE",  
                template: false  
            },  
            responseElements: null,  
            requestID: "6d9c4bfc-148a-11e5-81b6-7577cEXAMPLE",  
            eventID: "4d293154-a15b-4c33-9e0a-ff5eeEXAMPLE",  
            readOnly: true,  
            eventType: "AwsApiCall",  
        }  
    ]  
}
```

```
        recipientAccountId: "123456789012"
    },
    ... additional entries ...
]
}
```

For information about CloudTrail record contents, see [CloudTrail record contents](#) in the *AWS CloudTrail User Guide*.

Monitoring API Gateway API configuration with AWS Config

You can use [AWS Config](#) to record configuration changes made to your API Gateway API resources and send notifications based on resource changes. Maintaining a configuration change history for API Gateway resources is useful for operational troubleshooting, audit, and compliance use cases.

AWS Config can track changes to:

- **API stage configuration**, such as:
 - cache cluster settings
 - throttle settings
 - access log settings
 - the active deployment set on the stage
- **API configuration**, such as:
 - endpoint configuration
 - version
 - protocol
 - tags

In addition, the AWS Config Rules feature enables you to define configuration rules and automatically detect, track, and alert violations to these rules. By tracking changes to these resource configuration properties, you can also author change-triggered AWS Config rules for your API Gateway resources, and test your resource configurations against best practices.

You can enable AWS Config in your account by using the AWS Config console or the AWS CLI. Select the resource types for which you want to track changes. If you previously configured AWS Config to record all resource types, then these API Gateway resources will be automatically recorded in your account. Support for Amazon API Gateway in AWS Config is available in all AWS

public regions and AWS GovCloud (US). For the full list of supported Regions, see [Amazon API Gateway Endpoints and Quotas](#) in the AWS General Reference.

Topics

- [Supported resource types](#)
- [Setting up AWS Config](#)
- [Configuring AWS Config to record API Gateway resources](#)
- [Viewing API Gateway configuration details in the AWS Config console](#)
- [Evaluating API Gateway resources using AWS Config rules](#)

Supported resource types

The following API Gateway resource types are integrated with AWS Config and are documented in [AWS Config Supported AWS Resource Types and Resource Relationships](#):

- AWS::ApiGatewayV2::Api (WebSocket and HTTP API)
- AWS::ApiGateway::RestApi (REST API)
- AWS::ApiGatewayV2::Stage (WebSocket and HTTP API stage)
- AWS::ApiGateway::Stage (REST API stage)

For more information about AWS Config, see the [AWS Config Developer Guide](#). For pricing information, see the [AWS Config pricing information page](#).

Important

If you change any of the following API properties after the API is deployed, you *must redeploy* the API to propagate the changes. Otherwise, you'll see the attribute changes in the AWS Config console, but the previous property settings will still be in effect; the API's runtime behavior will be unchanged.

- **AWS::ApiGateway::RestApi** – binaryMediaTypes, minimumCompressionSize, apiKeySource
- **AWS::ApiGatewayV2::Api** – apiKeySelectionExpression

Setting up AWS Config

To initially set up AWS Config, see the following topics in the [AWS Config Developer Guide](#).

- [Setting Up AWS Config with the Console](#)
- [Setting Up AWS Config with the AWS CLI](#)

Configuring AWS Config to record API Gateway resources

By default, AWS Config records configuration changes for all supported types of regional resources that it discovers in the region in which your environment is running. You can customize AWS Config to record changes only for specific resource types, or changes to global resources.

To learn about regional vs. global resources and learn how to customize your AWS Config configuration, see [Selecting which Resources AWS Config Records](#).

Viewing API Gateway configuration details in the AWS Config console

You can use the AWS Config console to look for API Gateway resources and get current and historical details about their configurations. The following procedure shows how to find information about an API Gateway API.

To find an API Gateway resource in the AWS config console

1. Open the [AWS Config console](#).
2. Choose **Resources**.
3. On the **Resource inventory** page, choose **Resources**.
4. Open the **Resource type** menu, scroll to APIGateway or APIGatewayV2, and then choose one or more of the API Gateway resource types.
5. Choose **Look up**.
6. Choose a resource ID in the list of resources that AWS Config displays. AWS Config displays configuration details and other information about the resource you selected.
7. To see the full details of the recorded configuration, choose **View Details**.

To learn more ways to find a resource and view information on this page, see [Viewing AWS Resource Configurations and History](#) in the AWS Config Developer Guide.

Evaluating API Gateway resources using AWS Config rules

You can create AWS Config rules, which represent the ideal configuration settings for your API Gateway resources. You can use predefined [AWS Config Managed Rules](#), or define custom rules. AWS Config continuously tracks changes to the configuration of your resources to determine whether those changes violate any of the conditions in your rules. The AWS Config console shows the compliance status of your rules and resources.

If a resource violates a rule and is flagged as noncompliant, AWS Config can alert you using an [Amazon Simple Notification Service Developer Guide](#) (Amazon SNS) topic. To programmatically consume the data in these AWS Config alerts, use an Amazon Simple Queue Service (Amazon SQS) queue as the notification endpoint for the Amazon SNS topic.

To learn more about setting up and using rules, see [Evaluating Resources with Rules](#) in the [AWS Config Developer Guide](#).

Compliance validation for Amazon API Gateway

To learn whether an AWS service is within the scope of specific compliance programs, see [AWS services in Scope by Compliance Program](#) and choose the compliance program that you are interested in. For general information, see [AWS Compliance Programs](#).

You can download third-party audit reports using AWS Artifact. For more information, see [Downloading Reports in AWS Artifact](#).

Your compliance responsibility when using AWS services is determined by the sensitivity of your data, your company's compliance objectives, and applicable laws and regulations. For more information about your compliance responsibility when using AWS services, see [AWS Security Documentation](#).

Resilience in Amazon API Gateway

The AWS global infrastructure is built around AWS Regions and Availability Zones. AWS Regions provide multiple physically separated and isolated Availability Zones, which are connected with low-latency, high-throughput, and highly redundant networking. With Availability Zones, you can design and operate applications and databases that automatically fail over between zones without interruption. Availability Zones are more highly available, fault tolerant, and scalable than traditional single or multiple data center infrastructures.

As a fully managed Regional service, API Gateway operates in multiple Availability Zones in each Region, using the redundancy of Availability Zones to minimize infrastructure failure as a category of availability risk. API Gateway is designed to automatically recover from the failure of an Availability Zone.

For more information about AWS Regions and Availability Zones, see [AWS Global Infrastructure](#).

To prevent your APIs from being overwhelmed by too many requests, API Gateway throttles requests to your APIs. Specifically, API Gateway sets a limit on a steady-state rate and a burst of request submissions against all APIs in your account. You can configure custom throttling for your APIs. To learn more, see [Throttle requests to your REST APIs for better throughput in API Gateway](#).

You can use Route 53 health checks to control DNS failover from an API Gateway API in a primary region to an API Gateway API in a secondary region. For an example, see [the section called “DNS failover”](#).

Infrastructure security in Amazon API Gateway

As a managed service, Amazon API Gateway is protected by AWS global network security. For information about AWS security services and how AWS protects infrastructure, see [AWS Cloud Security](#). To design your AWS environment using the best practices for infrastructure security, see [Infrastructure Protection](#) in *Security Pillar AWS Well-Architected Framework*.

You use AWS published API calls to access API Gateway through the network. Clients must support the following:

- Transport Layer Security (TLS). We require TLS 1.2 and recommend TLS 1.3.
- Cipher suites with perfect forward secrecy (PFS) such as DHE (Ephemeral Diffie-Hellman) or ECDHE (Elliptic Curve Ephemeral Diffie-Hellman). Most modern systems such as Java 7 and later support these modes.

You can call these API operations from any network location, but API Gateway does support resource-based access policies, which can include restrictions based on the source IP address. You can also use resource-based policies to control access from specific Amazon Virtual Private Cloud (Amazon VPC) endpoints or specific VPCs. Effectively, this isolates network access to a given API Gateway resource from only the specific VPC within the AWS network.

Vulnerability analysis in Amazon API Gateway

Configuration and IT controls are a shared responsibility between AWS and you, our customer. For more information, see the AWS [shared responsibility model](#).

Security best practices in Amazon API Gateway

API Gateway provides a number of security features to consider as you develop and implement your own security policies. The following best practices are general guidelines and don't represent a complete security solution. Because these best practices might not be appropriate or sufficient for your environment, treat them as helpful considerations rather than prescriptions.

Implement least privilege access

Use IAM policies to implement least privilege access for creating, reading, updating, or deleting API Gateway APIs. To learn more, see [Identity and access management for Amazon API Gateway](#). API Gateway offers several options to control access to APIs that you create. To learn more, see [Control and manage access to REST APIs in API Gateway](#), [Control and manage access to WebSocket APIs in API Gateway](#), and [Control access to HTTP APIs with JWT authorizers in API Gateway](#).

Implement logging

Use CloudWatch Logs or Amazon Data Firehose to log requests to your APIs. To learn more, see [Monitor REST APIs in API Gateway](#), [Configure logging for WebSocket APIs in API Gateway](#), and [Configure logging for HTTP APIs in API Gateway](#).

Implement Amazon CloudWatch alarms

Using CloudWatch alarms, you watch a single metric over a time period that you specify. If the metric exceeds a given threshold, a notification is sent to an Amazon Simple Notification Service topic or AWS Auto Scaling policy. CloudWatch alarms do not invoke actions when a metric is in a particular state. Rather, the state must have changed and been maintained for a specified number of periods. For more information, see [the section called "CloudWatch metrics"](#).

Enable AWS CloudTrail

CloudTrail provides a record of actions taken by a user, role, or an AWS service in API Gateway. Using the information collected by CloudTrail, you can determine the request that was made to API Gateway, the IP address from which the request was made, who made the request, when it

was made, and additional details. For more information, see [the section called “Working with CloudTrail”](#).

Enable AWS Config

AWS Config provides a detailed view of the configuration of AWS resources in your account. You can see how resources are related, get a history of configuration changes, and see how relationships and configurations change over time. You can use AWS Config to define rules that evaluate resource configurations for data compliance. AWS Config rules represent the ideal configuration settings for your API Gateway resources. If a resource violates a rule and is flagged as noncompliant, AWS Config can alert you using an Amazon Simple Notification Service (Amazon SNS) topic. For details, see [the section called “Working with AWS Config”](#).

Use AWS Security Hub CSPM

Monitor your usage of API Gateway as it relates to security best practices by using [AWS Security Hub CSPM](#). Security Hub CSPM uses *security controls* to evaluate resource configurations and *security standards* to help you comply with various compliance frameworks. For more information about using Security Hub CSPM to evaluate API Gateway resources, see [Amazon API Gateway controls](#) in the [AWS Security Hub User Guide](#).

Tagging your API Gateway resources

A *tag* is a metadata label that you assign or that AWS assigns to an AWS resource. Each tag has two parts:

- A *tag key* (for example, CostCenter, Environment, or Project). Tag keys are case sensitive.
- An optional field known as a *tag value* (for example, 111122223333 or Production). Omitting the tag value is the same as using an empty string. Like tag keys, tag values are case-sensitive.

Tags help you do the following:

- Control access to your resources based on the tags that are assigned to them. You control access by specifying tag keys and values in the conditions for an AWS Identity and Access Management (IAM) policy. For more information about tag-based access control, see [Controlling Access Using Tags](#) in the *IAM User Guide*.
- Track your AWS costs. You activate these tags on the AWS Billing and Cost Management dashboard. AWS uses the tags to categorize your costs and deliver a monthly cost allocation report to you. For more information, see [Use Cost Allocation Tags](#) in the [AWS Billing User Guide](#).
- Identify and organize your AWS resources. Many AWS services support tagging, so you can assign the same tag to resources from different services to indicate that the resources are related. For example, you could assign the same tag to an API Gateway stage that you assign to a CloudWatch Events rule.

For tips on using tags, see the whitepaper [AWS Tagging Strategies](#).

The following sections provide more information about tags for Amazon API Gateway.

Topics

- [API Gateway resources that can be tagged](#)
- [Using tags to control access to API Gateway REST API resources](#)

API Gateway resources that can be tagged

Tags can be set on the following HTTP API or WebSocket API resources in the [Amazon API Gateway V2 API](#):

- Api
- DomainName
- Stage
- VpcLink

In addition, tags can be set on the following REST API resources in the [Amazon API Gateway V1 API](#):

- ApiKey
- ClientCertificate
- DomainName
- DomainNameAccessAssociation
- RestApi
- Stage
- UsagePlan
- VpcLink

Tags cannot be set directly on other resources. However, in the [Amazon API Gateway V1 API](#), child resources inherit the tags that are set on parent resources. For example:

- If a tag is set on a RestApi resource, that tag is inherited by the following child resources of that RestApi for [Attribute-based access control](#):
 - Authorizer
 - Deployment
 - Documentation
 - GatewayResponse
 - Integration
 - Method
 - Model
 - Resource
 - ResourcePolicy
 - Setting

- Stage
- If a tag is set on a DomainName, that tag is inherited by any BasePathMapping, ApiMapping, and RoutingRule resources under it.
- If a tag is set on a UsagePlan, that tag is inherited by any UsagePlanKey resources under it.

 **Note**

Tag inheritance applies only to [attribute-based access control](#). For example, you can't use inherited tags to monitor costs in AWS Cost Explorer. To use tags for cost allocation, we recommend that you create tags on child resources, such as the Stage resource. API Gateway doesn't return inherited tags when you call [GetTags](#) for a resource.

Tag inheritance in the Amazon API Gateway V1 API

Previously it was only possible to set tags on stages. Now that you can also set them on other resources, a Stage can receive a tag two ways:

- The tag can be set directly on the Stage.
- The stage can inherit the tag from its parent RestApi.

If a stage receives a tag both ways, the tag that was set directly on the stage takes precedence. For example, suppose a stage inherits the following tags from its parent REST API:

```
{  
  'foo': 'bar',  
  'x':'y'  
}
```

Suppose it also has the following tags set on it directly:

```
{  
  'foo': 'bar2',  
  'hello': 'world'  
}
```

The net effect would be for the stage to have the following tags, with the following values:

```
{  
  'foo': 'bar2',  
  'hello': 'world'  
  'x':'y'  
}
```

Tag restrictions and usage conventions

The following restrictions and usage conventions apply to using tags with API Gateway resources:

- Each resource can have a maximum of 50 tags.
- For each resource, each tag key must be unique, and each tag key can have only one value.
- The maximum tag key length is 128 Unicode characters in UTF-8.
- The maximum tag value length is 256 Unicode characters in UTF-8.
- Allowed characters for keys and values are letters, numbers, spaces representable in UTF-8, and the following characters: . : + = @ _ / - (hyphen). Amazon EC2 resources allow any characters.
- Tag keys and values are case-sensitive. As a best practice, decide on a strategy for capitalizing tags, and consistently implement that strategy across all resource types. For example, decide whether to use Costcenter, costcenter, or CostCenter, and use the same convention for all tags. Avoid using similar tags with inconsistent case treatment.
- The aws : prefix is prohibited for tags; it's reserved for AWS use. You can't edit or delete tag keys or values with this prefix. Tags with this prefix do not count against your tags per resource limit.

Using tags to control access to API Gateway REST API resources

Conditions in AWS Identity and Access Management policies are part of the syntax that you use to specify permissions to API Gateway resources. For details about specifying IAM policies, see [the section called “Use IAM permissions”](#). In API Gateway, resources can have tags, and some actions can include tags. When you create an IAM policy, you can use tag condition keys to control:

- Which users can perform actions on an API Gateway resource, based on tags that the resource already has.
- Which tags can be passed in an action's request.
- Whether specific tag keys can be used in a request.

Using tags for attribute-based access control can allow for finer control than API-level control, as well as more dynamic control than resource-based access control. IAM policies can be created that allow or disallow an operation based on tags provided in the request (request tags), or tags on the resource that is being operated on (resource tags). In general, resource tags are for resources that already exist. Request tags are for when you're creating new resources.

For the complete syntax and semantics of tag condition keys, see [Controlling Access Using Tags](#) in the *IAM User Guide*.

The following examples demonstrate how to specify tag conditions in policies for API Gateway users.

Limit actions based on resource tags

The following example policy grants users permission to perform all actions on all resources, as long as those resources don't have the tag Environment with a value of prod.

JSON

```
{  
    "Version": "2012-10-17",  
    "Statement": [  
        {  
            "Effect": "Allow",  
            "Action": "apigateway:*",  
            "Resource": "*"  
        },  
        {  
            "Effect": "Deny",  
            "Action": [  
                "apigateway:/*"  
            ],  
            "Resource": "*",  
            "Condition": {  
                "StringEquals": {  
                    "aws:ResourceTag/Environment": "prod"  
                }  
            }  
        }  
    ]  
}
```

Allow actions based on resource tags

The following example policy allows users to perform all actions on API Gateway resources, as long as the resources have the tag Environment with a value of Development. The Deny statement prevents the user from changing the value of the Environment tag.

JSON

```
{  
    "Version": "2012-10-17",  
    "Statement": [  
        {  
            "Sid": "ConditionallyAllow",  
            "Effect": "Allow",  
            "Action": [  
                "apigateway:*"  
            ],  
            "Resource": [  
                "arn:aws:apigateway:*:::"  
            ],  
            "Condition": {  
                "StringEquals": {  
                    "aws:ResourceTag/Environment": "Development"  
                }  
            }  
        },  
        {  
            "Sid": "AllowTagging",  
            "Effect": "Allow",  
            "Action": [  
                "apigateway:*"  
            ],  
            "Resource": [  
                "arn:aws:apigateway:*::/tags/*"  
            ]  
        },  
        {  
            "Sid": "DenyChangingTag",  
            "Effect": "Deny",  
            "Action": [  
                "apigateway:*"  
            ],  
            "Condition": {  
                "StringNotEquals": {  
                    "aws:ResourceTag/Environment": "Development"  
                }  
            }  
        }  
    ]  
}
```

```
"Resource": [  
    "arn:aws:apigateway:*:::/tags/*"  
,  
    "Condition": {  
        "ForAnyValue:StringEquals": {  
            "aws:TagKeys": "Environment"  
        }  
    }  
,  
]  
}
```

Deny tagging operations

The following example policy allows a user to perform all API Gateway actions, except for changing tags.

JSON

```
{  
    "Version": "2012-10-17",  
    "Statement": [  
        {  
            "Effect": "Allow",  
            "Action": [  
                "apigateway:*"  
,  
                "Resource": [  
                    "*"  
,  
                    {"  
                        "Effect": "Deny",  
                        "Action": [  
                            "apigateway:*"  
,  
                            "Resource": "arn:aws:apigateway:*:::/tags*"  
                        ]  
                    ]  
                ]  
        }  
    ]  
}
```

Allow tagging operations

The following example policy allows a user to get all API Gateway resources, and change tags for those resources. To get the tags for a resource, the user must have GET permissions for that resource. To update the tags for a resource, the user must have PATCH permissions for that resource.

JSON

```
{  
    "Version": "2012-10-17",  
    "Statement": [  
        {  
            "Effect": "Allow",  
            "Action": [  
                "apigateway:GET",  
                "apigateway:PUT",  
                "apigateway:POST",  
                "apigateway:DELETE"  
            ],  
            "Resource": [  
                "arn:aws:apigateway:*:::/tags/*"  
            ]  
        },  
        {  
            "Effect": "Allow",  
            "Action": [  
                "apigateway:GET",  
                "apigateway:PATCH"  
            ],  
            "Resource": [  
                "arn:aws:apigateway:*::*"  
            ]  
        }  
    ]  
}
```

API references

Amazon API Gateway provides APIs for creating and deploying your own HTTP and WebSocket APIs. In addition, API Gateway APIs are available in standard AWS SDKs.

If you are using a language for which an AWS SDK exists, you may prefer to use the SDK rather than using the API Gateway REST APIs directly. The SDKs make authentication simpler, integrate easily with your development environment, and provide easy access to API Gateway commands.

Here's where to find the AWS SDKs and API Gateway REST API reference documentation:

- [Tools for Amazon Web Services](#)
- [Amazon API Gateway REST API Reference](#)
- [Amazon API Gateway WebSocket and HTTP API Reference](#)

API Gateway service endpoints

An endpoint is a URL that serves as an entry point for an AWS web service. API Gateway supports the following endpoint types:

- [the section called “IPv4 endpoints”](#)
- [Dualstack endpoints](#) (support both IPv4 and IPv6)
- [FIPS endpoints](#)

When you make a request, you can specify the endpoint to use. If you do not specify an endpoint, the IPv4 endpoint is used by default. To use a different endpoint type, you must specify it in your request. For examples of how to do this, see [the section called “Specifying endpoints”](#). For a table of available endpoints, see [Amazon API Gateway endpoints](#).

IPv4 endpoints

IPv4 endpoints support IPv4 traffic only. IPv4 endpoints are available for all Regions.

If you specify the general endpoint, `apigateway.amazonaws.com`, we use the endpoint for `us-east-1`. To use a different Region, specify its associated endpoint. For example, if you specify `apigateway.us-east-2.amazonaws.com` as the endpoint, we direct your request to the `us-east-2` endpoint.

IPv4 endpoint names use the following naming convention:

- `apigateway.region.amazonaws.com`

For example, the IPv4 endpoint name for the eu-west-1 Region is `apigateway.eu-west-1.amazonaws.com`.

Dualstack (IPv4 and IPv6) endpoints

Dualstack endpoints support both IPv4 and IPv6 traffic. When you make a request to a dualstack endpoint, the endpoint URL resolves to an IPv6 or an IPv4 address, depending on the protocol used by your network and client.

Dual-stack endpoint names use the following naming convention:

- `apigateway.region.api.aws`

For example, the dual-stack endpoint name for the eu-west-1 Region is `apigateway.eu-west-1.api.aws`.

Specifying endpoints

The following examples show how to specify an endpoint for the us-east-2 Region using the AWS CLI for apigateway.

- **Dualstack**

```
aws apigateway get-rest-apis --region us-east-2 --endpoint-url https://apigateway.us-east-2.api.aws
```

- **IPv4**

```
aws apigateway get-rest-apis --region us-east-2 --endpoint-url https://apigateway.us-east-2.amazonaws.com
```

The following examples show how to specify an endpoint for the us-east-2 Region using the AWS CLI for apigatewayv2.

- **Dualstack**

```
aws apigatewayv2 get/apis --region us-east-2 --endpoint-url https://apigateway.us-east-2.api.aws
```

- **IPv4**

```
aws apigatewayv2 get/apis --region us-east-2 --endpoint-url https://apigateway.us-east-2.amazonaws.com
```

Using IPv6 addresses in IAM policies

If you use any IAM user policies or API Gateway resource policies to control access to API Gateway or any API Gateway APIs, confirm that your policies are updated to include IPv6 address ranges. Policies that aren't updated to handle IPv6 addresses might impact client's access to API Gateway when they start using the dualstack endpoint. For more information about managing access permissions with IAM, see [Identity and access management for Amazon API Gateway](#)

IAM policies that filter IP addresses use [IP Address Condition Operators](#). The following identity policy allows IP addresses in the 54.240.143.* range to get information about all of the resources of an HTTP or WebSocket API with the identifier of a123456789. Any IP addresses outside of this range will be denied access information about all of the resources in the API. Since all IPv6 addresses are outside of the allowed range, this policy prevents IPv6 addresses from being able to access information about the API.

JSON

```
{  
    "Version": "2012-10-17",  
    "Statement": [  
        {  
            "Sid": "IPAllow",  
            "Effect": "Allow",  
            "Principal": "*",  
            "Action": "apigateway:GET",  
            "Resource": "arn:aws:apigateway:us-east-1::/apis/a123456789/*",  
            "Condition": {  
                "IpAddress": {"aws:SourceIp": "54.240.143.0/24"}  
            }  
        }  
    ]  
}
```

```
]  
}
```

You can modify the API policy's Condition element to allow both IPv4 (54.240.143.0/24) and IPv6 (2001:DB8:1234:5678::/64) address ranges as shown in the following example. You can use the same type of Condition block shown in the example to update both your IAM user policies and API Gateway resource policies.

```
"Condition": {  
    "IpAddress": {  
        "aws:SourceIp": [  
            "54.240.143.0/24",  
            "2001:DB8:1234:5678::/64"  
        ]  
    }  
}
```

Amazon API Gateway quotas

The following quotas apply for all Amazon API Gateway API types.

API Gateway account-level quotas, per Region

The following quotas apply per account, per Region in Amazon API Gateway.

Resource or operation	Default quota	Can be increased
Throttle quota per account, per Region across HTTP APIs, REST APIs, WebSocket APIs, and WebSocket callback APIs	10,000 requests per second (RPS) with an additional burst capacity provided by the token bucket algorithm , using a maximum bucket capacity of 5,000 requests. *	Yes
Throttle quota without access control per account per Region for a portal	250,000 requests per second	No

* For the following Regions, the default throttle quota is 2500 RPS and the default burst quota is 1250 RPS: Africa (Cape Town), Europe (Milan), Asia Pacific (Jakarta), Middle East (UAE), Asia Pacific

(Hyderabad), Asia Pacific (Melbourne), Europe (Spain), Europe (Zurich), Israel (Tel Aviv), Canada West (Calgary), Asia Pacific (Malaysia), Asia Pacific (Thailand), and Mexico (Central).

API Gateway quotas for creating, deploying and managing an API

The following fixed quotas apply to creating, deploying, and managing an API in API Gateway, using the AWS CLI, the API Gateway console, or the API Gateway REST API and its SDKs. These quotas can't be increased.

Action	Default quota	Can be increased
CreateApiKey	5 requests per second per account	No
CreateDeployment	1 request every 5 seconds per account	No
CreateDocumentationVersion	1 request every 20 seconds per account	No
CreateDomainName	1 request every 30 seconds per account	No
CreateResource	5 requests per second per account	No
CreateRestApi for Regional or private API	1 request every 3 seconds per account	No
CreateRestApi for edge-optimized API	1 request every 30 seconds per account	No
CreateVpcLink (V2)	1 request every 15 seconds per account	No
DeleteApiKey	5 requests per second per account	No

Action	Default quota	Can be increased
DeleteDomainName	1 request every 30 seconds per account	No
DeleteResource	5 requests per second per account	No
DeleteRestApi	1 request every 30 seconds per account	No
GetResources	5 requests every 2 seconds per account	No
DeleteVpcLink (V2)	1 request every 30 seconds per account	No
ImportDocumentationParts	1 request every 30 seconds per account	No
ImportRestApi for Regional or private API	1 request every 3 seconds per account	No
ImportRestApi for edge-optimized API	1 request every 30 seconds per account	No
PutRestApi	1 request per second per account	No
UpdateAccount	1 request every 20 seconds per account	No
UpdateDomainName	1 request every 30 seconds per account	No
UpdateUsagePlan	1 request every 20 seconds per account	No
Create Portal	1 request every 3 seconds	No

Action	Default quota	Can be increased
Update Portal	2 requests per minute	No
Get Portal	10 requests per second	No
List Portals	10 requests per second	No
Publish Portal	2 requests per minute	No
DeletePortal	2 requests per minute	No
PreviewPortal	1 request every 3 seconds	No
DisablePortal	2 requests per minute	No
GetPortalProduct	10 requests per second	No
ListPortalProduct	5 requests per second	No
CreatePortalProduct	2 requests per second	No
UpdatePortalProduct	0.5 requests per second	No
DeletePortalProduct	1 request per second	No
PutPortalProductSharingPolicy	1 request every 3 seconds	No
GetPortalProductSharingPolicy	10 requests per second	No
DeletePortalProductSharingPolicy	1 request every 3 seconds	No
CreateProductRestEndpointPage	1 request every 3 seconds	No
GetProductRestEndpointPage	10 requests per second	No

Action	Default quota	Can be increased
UpdateProductRestEndpointPage	1 request every 3 seconds	No
DeleteProductRestEndpointPage	1 request every 3 seconds	No
ListProductRestEndpointPages	10 requests per second	No
CreateProductPage	1 request every 3 seconds	No
GetProductPage	10 requests per second	No
UpdateProductPage	1 request every 3 seconds	No
DeleteProductPage	1 request every 3 seconds	No
ListProductPages	10 requests per second	No
Other operations	No quota up to the total account quota.	No
Total operations	10 requests per second with a burst quota of 40 requests per second.	No

Quotas for configuring and running a REST API in API Gateway

The following quotas apply to configuring and running a REST API in Amazon API Gateway. If the quota is per-API, it can only be increased on specific APIs, not for all the APIs in an account.

For information about account-level quotas see [Quotas and important notes](#).

Resource or operation	Default quota	Can be increased
Public custom domain names per account per Region	120	Yes
Private custom domain names per account per Region	50	Yes
Regional APIs per Region	600	No
Edge-optimized APIs per Region	120	No
Private APIs per account per Region	600	No
Domain name access associations per account	100	Yes
Multi-level API mappings per domain	200	No
Routing rules per domain	50	Yes
Length, in characters, of the URL for an edge-optimized API	8192	No
Length, in characters, of the	10240	No

Resource or operation	Default quota	Can be increased
URL for a Regional API		
Length, in characters, of the URL for a private API	8192	No
Length, in characters, of API Gateway resource policy	8192	Yes
API keys per account per Region	10000	No
Client certificates per account per Region	60	Yes
Authorizers per API (AWS Lambda and Amazon Cognito)	10	Yes To increase this quota, contact the AWS Support Center

Resource or operation	Default quota	Can be increased
Documentation parts per API	2000	Yes To increase this quota, contact the AWS Support Center
Resources per API	300	Yes
Stages per API	10	Yes
Stage variables per stage	100	No
Length, in characters, of the key in a stage variable	64	No
Length, in characters, of the value in a stage variable	512	No
Usage plans per account per Region	300	Yes
Usage plans per API key	10	Yes

Resource or operation	Default quota	Can be increased
VPC links per account per Region	20	Yes
API caching TTL	300 seconds by default and configurable between 0 and 3600 by an API owner.	Not for the upper bound (3600)
Cached response size	1048576 Bytes. Cache data encryption may increase the size of the item that is being cached.	No
Integration timeout for Regional APIs	50 milliseconds - 29 seconds for all integration types, including Lambda, Lambda proxy, HTTP, HTTP proxy, and AWS integrations.	Yes *
Integration timeout for edge-optimized APIs	50 milliseconds - 29 seconds for all integration types, including Lambda, Lambda proxy, HTTP, HTTP proxy, and AWS integrations.	No
Integration timeout for private APIs	50 milliseconds - 29 seconds for all integration types, including Lambda, Lambda proxy, HTTP, HTTP proxy, and AWS integrations.	Yes *
Total combined size of all header values, including header names, values, any line terminators, and whitespaces	10240 Bytes	No

Resource or operation	Default quota	Can be increased
Total combined size of all header values for a private API	8000 Bytes	No
Payload size	10 MB	No
Tags per stage	50	No
#iterations in a #foreach ... #end loop in mapping templates	1000	No
Maximum mapping template size	300 KB	No
Access log template size	3 KB	No
Method ARN length	1600 bytes. If your method contains a path parameter and a client uses a value that exceeds the ARN length, your API will return a 414 Request URI too long response.	No

Resource or operation	Default quota	Can be increased
Method-level throttling settings for a stage in a usage plan	20	Yes To increase this quota, contact the AWS Support Center
Model size per API	400 KB	No
Number of certificates in a truststore	1,000 certificates up to 1 MB total object size.	No
Idle connection timeout	310 seconds	No
Maximum API definition file size when using restapi:import or restapi:put	6 MB	No

* You can't set the integration timeout to less than 50 milliseconds. You can raise the integration timeout to greater than 29 seconds, but this might require a reduction in your Region-level throttle quota for your account.

Best practices to reduce your quotas

The following best practices might help reduce your current number of resources to avoid increasing your quota. Make sure that these suggestions work for your API's architecture.

APIs per Region

To reduce the number of APIs per Region, export any unused APIs and then delete them from API Gateway. For more information, see [the section called “Export a REST API”](#).

Stages per API

To reduce the number of stages per API, split up your API into multiple APIs.

Resources per API

Use {proxy+} paths to reduce the number of resources. For more information, see [the section called “Set up proxy integrations with a proxy resource”](#).

API mappings

To reduce the number of API mappings for a custom domain name, use API mappings with single levels, such as /prod. API mappings with a single level doesn't count towards the API mappings quota.

Authorizers per API

To reduce the number of authorizers per API, reuse authorizers across API methods.

Documentation parts per API

To reduce the number of documentation parts per API, use ignore=documentation when you import your API. For more information, see [the section called “Import API documentation”](#).

You can also use content inheritance to allow some documentation parts to inherit content from an API entity of a more general specification. For more information, see [the section called “Representation of API documentation in API Gateway”](#).

Length, in characters, of API Gateway resource policy

To reduce the length of a resource policy, use AWS WAFV2 to protect your API. For more information, see [the section called “AWS WAF”](#).

If your policy contains IP addresses, you can also use ranges instead of specific values to define IP addresses.

Usage plans per API key

To reduce the number of usage plans per API key, use one API key per usage plan, and associate your usage plan with multiple APIs. We don't recommend sharing one API key across multiple usage plans.

Quotas for configuring and running an HTTP API in API Gateway

The following quotas apply to configuring and running an HTTP API in Amazon API Gateway. If the quota is per-API, it can only be increased on specific APIs, not for all the APIs in an account. For information about account-level quotas see [Quotas and important notes](#)

Resource or operation	Default quota	Can be increased
Routes per API	300	Yes
Integrations per API	300	No
Maximum integration timeout	30 seconds	No
Stages per API	10	Yes
Multi-level API mappings per domain	200 API mappings. This limit doesn't include API mapping with single levels, such as /prod.	No
Tags per stage	50	No
Total combined size of request line and header values	10240 bytes	No
Payload size	10 MB	No
Custom domains per account per Region	120	Yes
Access log template size	3 KB	No

Resource or operation	Default quota	Can be increased
Amazon CloudWatch Logs log entry	1 MB	No
Authorizers per API	10	Yes To increase this quota, contact the AWS Support Center
Audiences per authorizer	50	No
Scopes per route	10	No
Timeout for JSON Web Key Set endpoint	1500 ms	No
Response size from JSON Web Key Set endpoint	150000 bytes	No
Timeout for OpenID Connect discovery endpoint	1500 ms	No
Timeout for Lambda authorizer response	10000 ms	No

Resource or operation	Default quota	Can be increased
VPC links per account per Region	10	Yes
Subnets per VPC link	10	Yes
Stage variables per stage	100	No
Length, in characters, of the key in a stage variable	64	No
Length, in characters, of the value in a stage variable	512	No

Best practices to reduce your quotas

The following best practices might help reduce your current number of resources to avoid increasing your quota. Make sure that these suggestions work for your API's architecture.

APIs per Region

To reduce the number of APIs per Region, export any unused APIs and then delete them from API Gateway. For more information, see [the section called "Export"](#).

Stages per API

To reduce the number of stages per API, split up your API into multiple APIs.

Authorizers per API

To reduce the number of authorizers per API, reuse authorizers across API methods.

Quotas for configuring portals in API Gateway

The following quotas apply to creating portals in API Gateway. For more information, see [API Gateway portals](#).

Resource or operation	Default quota	Can be increased
Portals per account	15	Yes
Portal products per portal	200	Yes
Portal products per account	2000	Yes
Product REST endpoint pages per portal product	40	Yes
Product pages per portal product	40	Yes
Logo size	200 KB	No
Documentation page size per product REST endpoint page	32,000 characters	No
Custom page size for product pages	32,000 characters	No
Custom domain names per portal	1	No
Authorizers per portal	1	No

Quotas for configuring and running a WebSocket in API Gateway

The following quotas apply to configuring and running a WebSocket API in Amazon API Gateway. If the quota is per-API, it can only be increased on specific APIs, not for all the APIs in an account. For information about account-level quotas see [Quotas and important notes](#)

Resource or operation	Default quota	Can be increased
New connections per second per account (across all WebSocket APIs) per Region	500	Yes
Concurrent connections	Not applicable *	Not applicable
AWS Lambda authorizers per API	10	Yes To increase this quota, contact the AWS Support Center
AWS Lambda authorizer result size	8 KB	No
Routes per API	300	Yes

Resource or operation	Default quota	Can be increased
Integrations per API	300	Yes To increase this quota, contact the AWS Support Center
Integration timeout	50 milliseconds - 29 seconds for all integration types, including Lambda, Lambda proxy, HTTP, HTTP proxy, and AWS integrations.	No
Stages per API	10	Yes
WebSocket frame size	32 KB	No
Message payload size	128 KB **	No
Maximum mapping template size	300 KB	No
Connection duration for WebSocket API	2 hours	No
Idle Connection Timeout	10 minutes	No

Resource or operation	Default quota	Can be increased
Length, in characters, of the URL for a WebSocket API	4096	No
Access log template size	3 KB	No

* API Gateway doesn't enforce a quota on concurrent connections. The maximum number of concurrent connections is determined by the rate of new connections per second and maximum connection duration of two hours. For example, with the default quota of 500 new connections per second, if clients connect at the maximum rate over two hours, API Gateway can serve up to 3,600,000 concurrent connections.

** Because of the WebSocket frame-size quota of 32 KB, a message larger than 32 KB must be split into multiple frames, each 32 KB or smaller. This applies to `@connections` commands. If a larger message (or larger frame size) is received, the connection is closed with code 1009.

Amazon API Gateway important notes

The following section details notes that might impact your use of API Gateway.

Topics

- [Amazon API Gateway important notes for HTTP APIs](#)
- [Amazon API Gateway important notes for HTTP and WebSocket APIs](#)
- [Amazon API Gateway important notes for REST and WebSocket APIs](#)
- [Amazon API Gateway important notes for WebSocket APIs](#)
- [Amazon API Gateway important notes for REST APIs](#)

Amazon API Gateway important notes for HTTP APIs

- HTTP APIs translate incoming `X-Forwarded-`* headers into a standard `Forwarded` header and will append the egress IP, Host, and protocol.

- API Gateway adds the Content-type header to your request if there is no payload and the Content-Length is 0.

Amazon API Gateway important notes for HTTP and WebSocket APIs

- Signature Version 4A is not officially supported by Amazon API Gateway for HTTP and WebSocket APIs.

Amazon API Gateway important notes for REST and WebSocket APIs

- API Gateway does not support sharing a custom domain name across REST and WebSocket APIs.
- Stage names can only contain alphanumeric characters, hyphens, and underscores. Maximum length is 128 characters.
- The /ping and /sping paths are reserved for the service health check. Use of these for API root-level resources with custom domains will fail to produce the expected result.
- API Gateway currently limits log events to 1024 bytes. Log events larger than 1024 bytes, such as request and response bodies, will be truncated by API Gateway before submission to CloudWatch Logs.
- CloudWatch Metrics currently limits dimension names and values to 255 valid XML characters. (For more information, see the [CloudWatch User Guide](#).) Dimension values are a function of user-defined names, including API name, label (stage) name, and resource name. When choosing these names, be careful not to exceed CloudWatch Metrics limits.
- The maximum size of a mapping template is 300 KB.

Amazon API Gateway important notes for WebSocket APIs

- API Gateway supports message payloads up to 128 KB with a maximum frame size of 32 KB. If a message exceeds 32 KB, you must split it into multiple frames, each 32 KB or smaller. If a larger message is received, the connection is closed with code 1009.

Amazon API Gateway important notes for REST APIs

- The plain text pipe character (|) and the curly brace character ({ or }) are not supported for any request URL query string and must be URL-encoded.

- The semicolon character (;) is not supported for any request URL query string and results in the data being split.
- REST APIs decode URL-encoded request parameters before passing them to backend integrations. For UTF-8 request parameters, REST APIs decode the parameters and then pass them as unicode to backend integrations. REST APIs URL-encode the percent character (%) before passing it to backend integrations.
- When using the API Gateway console to test an API, you may get an "unknown endpoint errors" response if a self-signed certificate is presented to the backend, the intermediate certificate is missing from the certificate chain, or any other unrecognizable certificate-related exceptions thrown by the backend.
- For an API [Resource](#) or [Method](#) entity with a private integration, you should delete it after removing any hard-coded reference of a [VpcLink](#). Otherwise, you have a dangling integration and receive an error stating that the VPC link is still in use even when the Resource or Method entity is deleted. This behavior does not apply when the private integration references VpcLink through a stage variable.
- The following backends may not support SSL client authentication in a way that's compatible with API Gateway:
 - [NGINX](#)
 - [Heroku](#)
- API Gateway supports most of the [OpenAPI 2.0 specification](#) and the [OpenAPI 3.0 specification](#), with the following exceptions:
 - Path segments can only contain alphanumeric characters, underscores, hyphens, periods, commas, colons, and curly braces. Path parameters must be separate path segments. For example, "resource/{path_parameter_name}" is valid; "resource{path_parameter_name}" is not.
 - Model names can only contain alphanumeric characters.
 - For input parameters, only the following attributes are supported: name, in, required, type, description. Other attributes are ignored.
 - The securitySchemes type, if used, must be apiKey. However, OAuth 2 and HTTP Basic authentication are supported via [Lambda authorizers](#); the OpenAPI configuration is achieved via [vendor extensions](#).
 - The deprecated field is not supported and is dropped in exported APIs.
 - API Gateway models are defined using [JSON schema draft 4](#), instead of the JSON schema used by OpenAPI.

- The `discriminator` parameter is not supported in any schema object.
- The `example` tag is not supported.
- The `nullable` field is not supported.
- `exclusiveMinimum` is not supported by API Gateway.
- The `maxItems` and `minItems` tags are not included in [simple request validation](#). To work around this, update the model after import before doing validation.
- For OpenAPI 3.0, you can't have a `oneOf`, `anyOf`, or `allOf` that uses `$ref` to a definition within the same schema. You can either directly input your schema or define a separate API Gateway model resource. For more information, see [the section called "Creating more complex models"](#).
- `oneOf` is not supported for OpenAPI 2.0 or SDK generation.
- The `readOnly` field is not supported.
- `$ref` cannot be used to reference other files.
- Response definitions of the "500": {"\$ref": "#/responses/UnexpectedError"} form is not supported in the OpenAPI document root. To work around this, replace the reference by the inline schema.
- Numbers of the `Int32` or `Int64` type are not supported. An example is shown as follows:

```
"elementId": {  
    "description": "Working Element Id",  
    "format": "int32",  
    "type": "number"  
}
```

- Decimal number format type ("format": "decimal") is not supported in a schema definition.
- In method responses, schema definition must be of an object type and cannot be of primitive types. For example, "schema": { "type": "string"} is not supported. However, you can work around this using the following object type:

```
"schema": {  
    "$ref": "#/definitions/StringResponse"  
}  
  
"definitions": {  
    "StringResponse": {
```

```

    "type": "string"
}
}

```

- API Gateway doesn't use root level security defined in the OpenAPI specification. Hence security needs to be defined at an operation level to be appropriately applied.
- The default keyword is not supported.
- API Gateway enacts the following restrictions and limitations when handling methods with either Lambda integration or HTTP integration.
 - Header names and query parameters are processed in a case-sensitive way.
 - The following table lists the headers that may be dropped, remapped, or otherwise modified when sent to your integration endpoint or sent back by your integration endpoint. In this table:
 - Remapped means that the header name is changed from *<string>* to X-Amzn-Remapped-*<string>*.

Remapped Overwritten means that the header name is changed from *<string>* to X-Amzn-Remapped-*<string>* and the value is overwritten.

Header name	Request (http/http_proxy /lambda)	Response (http/http_proxy /lambda)
Age	Passthrough	Passthrough
Accept	Passthrough	Dropped/ Passthrough/ Passthrough
Accept-Charset	Passthrough	Passthrough

Header name	Request (http/http_proxy /lambda)	Response (http/http_proxy /lambda)
Accept-Encoding	Passthrough	Passthrough
Authorization	Passthrough *	Remapped
Connection	Passthrough/Passthrough/Dropped	Remapped
Content-Encoding	Passthrough/Dropped/Passthrough	Passthrough
Content-Length	Passthrough (generated based on body)	Passthrough
Content-MD5	Dropped	Remapped
Content-Type	Passthrough	Passthrough
Date	Passthrough	Remapped Overwritten
Expect	Dropped	Dropped
Host	Overwritten to the integration endpoint	Dropped
Max-Forwards	Dropped	Remapped
Pragma	Passthrough	Passthrough
Proxy-Authorenticate	Dropped	Dropped

Header name	Request (<code>http/http_proxy /lambda</code>)	Response (<code>http/http_proxy /lambda</code>)
Range	Passthrough	Passthrough
Referer	Passthrough	Passthrough
Server	Dropped	Remapped Overwritten
TE	Dropped	Dropped
Transfer-Encoding	Dropped/Dropped/Exception	Dropped
Trailer	Dropped	Dropped
Upgrade	Dropped	Dropped
User-Agent	Passthrough	Remapped
Via	Dropped/Dropped/Passthrough	Passthrough/ Dropped/ Dropped
Warn	Passthrough	Passthrough
WWW-Authenticate	Dropped	Remapped

* The Authorization header is dropped if it contains a [Signature Version 4](#) signature or if AWS_IAM authorization is used.

- The Android SDK of an API generated by API Gateway uses the `java.net.HttpURLConnection` class. This class will throw an unhandled exception, on devices running Android 4.4 and earlier, for a 401 response resulted from remapping of the `WWW-Authenticate` header to `X-Amzn-Remapped-WWW-Authenticate`.
- Unlike API Gateway-generated Java, Android and iOS SDKs of an API, the JavaScript SDK of an API generated by API Gateway does not support retries for 500-level errors.
- The test invocation of a method uses the default content type of `application/json` and ignores specifications of any other content types.
- When sending requests to an API by passing the `X-HTTP-Method-Override` header, API Gateway overrides the method. So in order to pass the header to the backend, the header needs to be added to the integration request.
- When a request contains multiple media types in its `Accept` header, API Gateway only honors the first `Accept` media type. In the situation where you cannot control the order of the `Accept` media types and the media type of your binary content is not the first in the list, you can add the first `Accept` media type in the `binaryMediaTypes` list of your API, API Gateway will return your content as binary. For example, to send a JPEG file using an `` element in a browser, the browser might send `Accept: image/webp, image/*, */*; q=0.8` in a request. By adding `image/webp` to the `binaryMediaTypes` list, the endpoint will receive the JPEG file as binary.
- Customizing the default gateway response for `413 REQUEST_TOO_LARGE` isn't currently supported.
- API Gateway includes a `Content-Type` header for all integration responses. By default, the content type is `application/json`.

Document history

The following table describes the important changes to the documentation since the last release of Amazon API Gateway. For notification about updates to this documentation, you can subscribe to an RSS feed by choosing the RSS button in the top menu panel.

- **Latest documentation update:** December 02, 2025

Change	Description	Date
<u>Add an API Gateway REST API as a target for Amazon Bedrock AgentCore Gateway</u>	API Gateway now supports adding a REST API as a target for Amazon Bedrock AgentCore Gateway. For more information, see <u>Add an API Gateway REST API as a target for Amazon Bedrock AgentCore Gateway</u> .	December 2, 2025
<u>Private integration with Application Load Balancer</u>	API Gateway now supports private integrations with Application Load Balancers for REST APIs. For more information, see <u>Private integrations for REST APIs</u> .	November 21, 2025
<u>Security policies for REST APIs and custom domain names</u>	API Gateway now supports enhanced TLS security policies on REST APIs and custom domain names. For more information, see <u>Security policies for REST APIs in API Gateway</u> .	November 19, 2025
<u>Response streaming for REST APIs</u>	API Gateway REST APIs now support progressively streaming response payloads	November 19, 2025

to clients as they become available. For more information, see [Stream the integration response for your proxy integrations](#).

[Developer portals](#)

API Gateway now supports portals, which are a centralized location for your customers to discover and test your APIs and portal products which represent a service or functionality that you want to share. For more information, see [API Gateway portals](#).

November 19, 2025

[SIGv4a for REST APIs](#)

API Gateway now supports using Signature Version 4a for REST APIs. For more information, see [API Gateway permissions model for invoking an API](#).

August 19, 2025

[Routing rules for REST APIs](#)

API Gateway now supports routing rules for REST APIs using custom domain names. You can dynamically route incoming requests based on HTTP header values, URL base paths, or a combination of both. For more information, see [Send traffic to your APIs through your custom domain name](#).

June 3, 2025

<u>Added support for dual-stack (IPv4 and IPv6) endpoints</u>	API Gateway now supports dual-stack endpoints for REST, HTTP, and WebSocket APIs, and custom domain names. For more information, see IP address types .	March 28, 2025
<u>Custom domain names for private APIs</u>	Added support for custom domain names for private APIs. For more information, see Custom domain names for private APIs .	November 21, 2024
<u>Added support for TLS 1.3</u>	API Gateway now supports TLS 1.3 on Regional REST APIs, HTTP APIs, and WebSocket APIs. For more information, see Choosing a security policy for your custom domain in API Gateway .	February 15, 2024
<u>REST API and WebSocket API console updates</u>	Updated console information for REST APIs and WebSocket APIs.	December 10, 2023
<u>Documentation update</u>	Updated conceptual information and created new tutorials for data transformations and request validation topics for API Gateway REST APIs. For more information, see Use request validation in API Gateway and Setting up data transformations for REST API .	June 22, 2023

<u>Configure DNS failover for a multi-Region API Gateway</u>	Added support to use Amazon Route 53 health checks to control DNS failover from an API Gateway REST API in a primary AWS Region to one in a secondary Region. For more information, see <u>Configure custom health checks for DNS failover</u> .	October 31, 2022
<u>Documentation update</u>	Updated core feature summaries for REST API and HTTP API APIs. For more information, see <u>Choosing between REST API and HTTP API APIs</u> .	May 31, 2022
<u>Managed policy update</u>	Added acm:GetCertificate support to the AWSServiceRoleForAPIGateway policy. For more information, see <u>Using service-linked roles for API Gateway</u> .	July 12, 2021
<u>Parameter mapping for HTTP APIs</u>	Added support for parameter mapping for HTTP APIs. For more information, see <u>Transforming API requests and responses</u> .	January 7, 2021
<u>Disable the default endpoint for a REST API</u>	Added support for disabling the default endpoint for REST APIs. For more information, see <u>Disabling the default endpoint for a REST API</u> .	October 29, 2020

<u>Mutual TLS authentication</u>	Added support for mutual TLS authentication for REST APIs and HTTP APIs. For more information, see <u>Configuring mutual TLS authentication for a REST API</u> and <u>Configuring mutual TLS authentication for an HTTP API</u> .	September 17, 2020
<u>HTTP API AWS Lambda authorizers</u>	Added support for AWS Lambda authorizers for HTTP APIs. For more information, see <u>Working with AWS Lambda authorizers for HTTP APIs</u> .	September 9, 2020
<u>HTTP API AWS service integrations</u>	Added support for AWS service integrations for HTTP APIs. For more information, see <u>Working with AWS service integrations for HTTP APIs</u> .	August 20, 2020
<u>HTTP API wildcard custom domains</u>	Added support for wildcard custom domain names for HTTP APIs. For more information, see <u>Wildcard custom domain names</u> .	August 10, 2020
<u>Serverless developer portal improvements</u>	Added user management to the administrator panel and support for exporting API definitions. For more information, see <u>Use the serverless developer portal to catalog your API Gateway APIs</u> .	June 25, 2020

<u>WebSocket API Sec-WebS</u> <u>ocket-Protocol support</u>	Added support for the Sec-WebSocket-Protocol field. For more information, see <u>Setting up a \$connect route that requires a WebSocket subprotocol.</u>	June 16, 2020
<u>HTTP API export</u>	Added support for exporting OpenAPI 3.0 definitions of HTTP APIs. For more information, see <u>Exporting an HTTP API from API Gateway</u> .	April 20, 2020
<u>Security documentation</u>	Added security documentation. For more information, see <u>Security in Amazon API Gateway</u> .	March 31, 2020
<u>Reorganized documentation</u>	Reorganized the developer guide.	March 12, 2020
<u>HTTP API general availability</u>	Released HTTP APIs in general availability. For more information, see <u>Working with HTTP APIs</u> .	March 12, 2020
<u>HTTP API logging</u>	Added support for \$context.integrationErrorMessage in HTTP API logs. For more information, see <u>HTTP API Logging Variables</u> .	February 26, 2020
<u>AWS variables for OpenAPI import</u>	Added support for AWS variables in OpenAPI definitions. For more information, see <u>AWS Variables for OpenAPI Import</u> .	February 17, 2020

<u>HTTP APIs</u>	Released HTTP APIs in beta. For more information, see <u>HTTP APIs</u> .	December 4, 2019
<u>Wildcard custom domain names</u>	Added support for wildcard custom domain names. For more information, see <u>Wildcard Custom Domain Names</u> .	October 21, 2019
<u>Amazon Data Firehose logging</u>	Added support for Amazon Data Firehose as a destination for access logging data. For more information, see <u>Using Amazon Data Firehose as a Destination for API Gateway Access Logging</u> .	October 15, 2019
<u>Route53 aliases for invoking private APIs</u>	Added support for additional Route53 alias DNS records for invoking private APIs. For more information, see <u>Accessing Your Private API Using Route53 Alias</u> .	September 18, 2019
<u>Tag-based access control for WebSocket APIs</u>	Added support for tag-based access control for WebSocket APIs. For more information, see <u>API Gateway Resources That Can Be Tagged</u> .	June 27, 2019

<u>TLS version selection for custom domains</u>	Added support for Transport Layer Security (TLS) version selection for APIs that are deployed to custom domains. See the note in <u>Choose a Minimum TLS Version for a Custom Domain in API Gateway</u> .	June 20, 2019
<u>VPC endpoint policies for private APIs</u>	Added support for improving the security of private APIs by attaching endpoint policies to interface VPC endpoints . For more information, see <u>Use VPC Endpoint Policies for Private APIs in API Gateway</u> .	June 4, 2019
<u>Documentation updated</u>	Rewrote <u>Getting Started with Amazon API Gateway</u> . Moved tutorials to <u>Amazon API Gateway Tutorials</u> .	May 29, 2019
<u>Tag-based access control for REST APIs</u>	Added support for tag-based access control for REST APIs. For more information, see <u>Using Tags with IAM Policies to Control Access to API Gateway Resources</u> .	May 23, 2019

<u>Documentation updated</u>	Rewrote 6 topics: What Is Amazon API Gateway? , Tutorial: Build an API with HTTP Proxy Integration , Tutorial: Create a Calc REST API with Three Non-Proxy Integrations , API Gateway Mapping Template and Access Logging Variable Reference , Use API Gateway Lambda Authorizers , and Enable CORS for an API Gateway REST API Resource .	April 5, 2019
<u>Serverless developer portal improvements</u>	Added administrator panel and other improvements to make it easier to publish APIs in the Amazon API Gateway developer portal. For more information, see Use a Developer Portal to Catalog Your APIs .	March 28, 2019
<u>Support for AWS Config</u>	Added support for AWS Config. For more information, see Monitoring API Gateway API Configuration with AWS Config .	March 20, 2019
<u>Support for CloudFormation</u>	Added API Gateway V2 API to the CloudFormation template reference. For more information, see Amazon API Gateway V2 Resource Types Reference .	February 7, 2019

Support for WebSocket APIs	Added support for WebSocket APIs. For more information, see Creating a WebSocket API in Amazon API Gateway .	December 18, 2018
Serverless developer portal available through AWS Serverless Application Repository	The Amazon API Gateway developer portal serverless application is now available from the AWS Serverless Application Repository (in addition to GitHub). For more information, see Use a Developer Portal to Catalog Your API Gateway APIs .	November 16, 2018
Support for AWS WAF	Added support for AWS WAF (Web Application Firewall). For more information, see Control Access to an API Using AWS WAF .	November 5, 2018
Serverless developer portal	Amazon API Gateway now provides a fully customizable developer portal as a serverless application that you can deploy for publishing your API Gateway APIs. For more information, see Use a Developer Portal to Catalog Your API Gateway APIs .	October 29, 2018

<u>Support for multi-value headers and query string parameters</u>	Amazon API Gateway now supports multiple headers and query string parameters that have the same name. For more information, see <u>Support for Multi-Value Headers and Query String Parameters</u> .	October 4, 2018
<u>OpenAPI support</u>	Amazon API Gateway now supports OpenAPI 3.0 as well as OpenAPI (Swagger) 2.0.	September 27, 2018
<u>Documentation updated</u>	Added a new topic: <u>How Amazon API Gateway Resource Policies Affect Authorization Workflow</u> .	September 27, 2018
<u>Active AWS X-Ray integration</u>	You can now use AWS X-Ray to trace and analyze latencies in user requests as they travel through your APIs to the underlying services. For more information, see <u>Trace API Gateway API Execution with AWS X-Ray</u> .	September 6, 2018

Caching improvements

Only GET methods will have caching enabled by default when you enable caching for an API stage. This helps to ensure the safety of your API. You can enable caching for other methods by overriding method settings. For more information, see [Enable API Caching to Enhance Responsiveness](#).

Service limits revised

Several limits have been revised: Increased number of APIs per account. Increased API rate limits for Create/Import/Deploy APIs. Corrected some rates from per minute to per second. For more information, see [Limits](#).

Overriding API request and response parameters and headers

Added support for overriding request headers, query strings, and paths, as well as response headers and status codes. For more information, see [Use a Mapping Template to Override an API's Request and Response Parameters and Headers](#).

August 20, 2018

July 13, 2018

July 12, 2018

<u>Method-level throttling for usage plans</u>	Added support for setting default per-method throttling limits, as well as setting throttling limits for individual API methods in usage plan settings. These settings are in addition to the existing account-level throttling and default method-level throttling limits that you can set in stage settings. For more information, see <u>Throttle API Requests for Better Throughput</u> .	July 11, 2018
--	---	---------------

<u>API Gateway Developer Guide update notifications now available through RSS</u>	The HTML version of the API Gateway Developer Guide now supports an RSS feed of updates that are documented on this Document History page. The RSS feed includes updates made June 27, 2018, and later. Previously announced updates are still available on this page. Use the RSS button in the top menu panel to subscribe to the feed.	June 27, 2018
---	--	---------------

Earlier updates

The following table describes important changes in each release of the *API Gateway Developer Guide* before June 27, 2018.

Change	Description	Date changed
Private APIs	Added support for private APIs , which you expose via interface VPC endpoints . Traffic to your private APIs does not leave the Amazon network; it is isolated from the public internet.	June 14, 2018
Cross-Account Lambda Authorizers and Integrations and Cross-Account Amazon Cognito User Pool Authorizers	Use an AWS Lambda function from a different AWS account as a Lambda authorizer function or as an API integration backend. Or use an Amazon Cognito user pool as an authorizer. The other account can be in any region where Amazon API Gateway is available. For more information, see the section called “Configure a cross-account Lambda authorizer” , the section called “Tutorial : Create a REST API with a cross-account Lambda proxy integration” , and the section called “Configure cross-account Amazon Cognito authorizer for a REST API” .	April 2, 2018
Resource Policies for APIs	Use API Gateway resource policies to enable users from a different AWS account to securely access your API or to allow the API to be invoked only from specified source IP address ranges or CIDR blocks. For more information, see the section called “Use API Gateway resource policies” .	April 2, 2018
Tagging for API Gateway resources	Tag an API stage with up to 50 tags for cost allocation of API requests and caching in API Gateway. For more information see the section called “Set up tags” .	December 19, 2017
Payload compression and decompression	Enable calling your API with compressed payloads using one of the supported content codings. The compressed payloads are subject to mapping if a body-mapping template is specified. For more information, see the section called “Content encoding” .	December 19, 2017
API key sourced from a custom authorizer	Return an API key from a custom authorizer to API Gateway to apply a usage plan for API methods that	December 19, 2017

Change	Description	Date changed
	require the key. For more information, see the section called “Choose an API key source in API Gateway” .	
Authorization with OAuth 2 scopes	Enable authorization of method invocation by using OAuth 2 scopes with the COGNITO_USER_POOLS authorizer. For more information, see the section called “Use Amazon Cognito user pool as authorizer for a REST API” .	December 14, 2017
Private Integration and VPC Link	Create an API with the API Gateway private integration to provide clients with access to HTTP/HTTPS resources in an Amazon VPC from outside of the VPC through a VpcLink resource. For more information, see the section called “Tutorial: Create a REST API with a private integration” and the section called “Set up a private integration” .	November 30, 2017
Deploy a Canary for API testing	Add a canary release to an existing API deployment to test a newer version of the API while keeping the current version in operation on the same stage. You can set a percentage of stage traffic for the canary release and enable canary-specific execution and access logged in separate CloudWatch Logs logs. For more information, see the section called “Set up a canary release deployment” .	November 28, 2017
Access Logging	Log client access to your API with data derived from \$context variables in a format of your choosing. For more information, see the section called “CloudWatch logs” .	November 21, 2017
Ruby SDK of an API	Generate a Ruby SDK for your API and use it to invoke your API methods. For more information, see the section called “Generate the Ruby SDK of an API in API Gateway” and the section called “Use a Ruby SDK generated by API Gateway for a REST API” .	November 20, 2017

Change	Description	Date changed
Regional API endpoint	Specify a regional API endpoint to create an API for non-mobile clients. A non-mobile client, such as an EC2 instance, runs in the same AWS Region where the API is deployed. As with an edge-optimized API, you can create a custom domain name for a regional API. For more information, see the section called "API Gateway endpoint types" and the section called "Set up a Regional custom domain name" .	November 2, 2017
Custom request authorizer	Use custom request authorizer to supply user-authenticating information in request parameters to authorize API method calls. The request parameters include headers and query string parameters as well as stage and context variables. For more information, see Use API Gateway Lambda authorizers .	September 15, 2017
Customizing gateway responses	Customize API Gateway-generated gateway responses to API requests that failed to reach the integration backend. A customized gateway message can provide the caller with API-specific custom error messages, including returning needed CORS headers, or can transform the gateway response data to a format of an external exchange. For more information, see Setting up gateway responses to customize error responses .	June 6, 2017
Mapping Lambda custom error properties to method response headers	Map individual custom error properties returned from Lambda to the method response header parameters using the <code>integration.response.body</code> parameter, relying API Gateway to deserialize the stringified custom error object at run time. For more information, see Handle custom Lambda errors in API Gateway .	June 6, 2017

Change	Description	Date changed
Throttling limits increase	<p>Increase the account-level steady-state request rate limit to 10,000 requests per second (rps) and the burst limit to 5000 concurrent requests. For more information, see Throttle requests to your REST APIs for better throughput in API Gateway.</p>	June 6, 2017
Validating method requests	<p>Configure basic request validators on the API level or method levels so that API Gateway can validate incoming requests. API Gateway verifies that required parameters are set and not blank, and verifies that the format of applicable payloads conforms to the configured model. For more information, see Request validation for REST APIs in API Gateway.</p>	April 11, 2017
Integrating with ACM	<p>Use ACM Certificates for your API's custom domain names. You can create a certificate in AWS Certificate Manager or import an existing PEM-formatted certificate into ACM. You then refer to the certificate's ARN when setting a custom domain name for your APIs. For more information, see Custom domain name for public REST APIs in API Gateway.</p>	March 9, 2017
Generating and calling a Java SDK of an API	<p>Let API Gateway generate the Java SDK for your API and use the SDK to call the API in your Java client. For more information, see Use a Java SDK generated by API Gateway for a REST API.</p>	January 13, 2017
Integrating with AWS Marketplace	<p>Sell your API in a usage plan as a SaaS product through AWS Marketplace. Use AWS Marketplace to extend the reach of your API. Rely on AWS Marketplace for customer billing on your behalf. Let API Gateway handle user authorization and usage metering. For more information, see Sell your APIs as SaaS.</p>	December 1, 2016

Change	Description	Date changed
Enabling Documentation Support for your API	Add documentation for API entities in DocumentationPart resources in API Gateway. Associate a snapshot of the collection DocumentationPart instances with an API stage to create a DocumentationVersion . Publish API documentation by exporting a documentation version to an external file, such as a Swagger file. For more information, see Documentation for REST APIs in API Gateway .	December 1, 2016
Updated custom authorizer	A customer authorizer Lambda function now returns the caller's principal identifier. The function also can return other information as key-value pairs of the context map and an IAM policy. For more information, see Output from an API Gateway Lambda authorizer .	December 1, 2016
Supporting binary payloads	Set binaryMediaTypes on your API to support binary payloads of a request or response. Set the contentHandling property on an Integration or IntegrationOnResponse to specify whether to handle a binary payload as the native binary blob, as a Base64-encoded string, or as a passthrough without modifications. For more information, see Binary media types for REST APIs in API Gateway .	November 17, 2016
Enabling a proxy integration with an HTTP or Lambda backend through a proxy resource of an API.	Create a proxy resource with a greedy path parameter of the form {proxy+} and the catch-all ANY method. The proxy resource is integrated with an HTTP or Lambda backend using the HTTP or Lambda proxy integration, respectively. For more information, see Set up a proxy integration with a proxy resource .	September 20, 2016

Change	Description	Date changed
Extending selected APIs in API Gateway as product offerings for your customers by providing one or more usage plans.	Create a usage plan in API Gateway to enable selected API clients to access specified API stages at agreed-up on request rates and quotas. For more information, see Usage plans and API keys for REST APIs in API Gateway .	August 11, 2016
Enabling method-level authorization with a user pool in Amazon Cognito	Create a user pool in Amazon Cognito and use it as your own identity provider. You can configure the user pool as a method-level authorizer to grant access for users who are registered with the user pool. For more information, see Control access to REST APIs using Amazon Cognito user pools as an authorizer .	July 28, 2016
Enabling Amazon CloudWatch metrics and dimensions under the AWS/ApiGateway namespace.	The API Gateway metrics are now standardized under the CloudWatch namespace of AWS/ApiGateway . You can view them in both the API Gateway console and the Amazon CloudWatch console. For more information, see Amazon API Gateway dimensions and metrics .	July 28, 2016
Enabling certificate rotation for a custom domain name	Certificate rotation allows you to upload and renew an expiring certificate for a custom domain name. For more information, see Rotate a certificate imported into ACM .	April 27, 2016
Documenting changes for the updated Amazon API Gateway console.	Learn how to create and set up an API using the updated API Gateway console. For more information, see Tutorial: Create a REST API by importing an example and Tutorial: Create a REST API with an HTTP non-proxy integration .	April 5, 2016

Change	Description	Date changed
Enabling the Import API feature to create a new or update an existing API from external API definitions.	With the Import API features, you can create a new API or update an existing one by uploading an external API definition expressed in Swagger 2.0 with the API Gateway extensions. For more information about the Import API, see Develop REST APIs using OpenAPI in API Gateway .	April 5, 2016
Exposing the <code>\$input.body</code> variable to access the raw payload as string and the <code>\$util.parseJson()</code> function to turn a JSON string into a JSON object in a mapping template.	For more information about <code>\$input.body</code> and <code>\$util.parseJson()</code> , see Variables for data transformations for API Gateway .	April 5, 2016
Enabling client requests with method-level cache invalidation, and improving request throttling management.	Flush API stage-level cache and invalidate individual cache entry. For more information, see Flush the API stage cache in API Gateway and Invalidate an API Gateway cache entry . Improve the console experience for managing API request throttling. For more information, see Throttle requests to your REST APIs for better throughput in API Gateway .	March 25, 2016
Enabling and calling API Gateway API using custom authorization	Create and configure an AWS Lambda function to implement custom authorization. The function returns an IAM policy document that grants the Allow or Deny permissions to client requests of an API Gateway API. For more information, see Use API Gateway Lambda authorizers .	February 11, 2016

Change	Description	Date changed
Importing and exporting API Gateway API using a Swagger definition file and extensions	<p>Create and update your API Gateway API using the Swagger specification with the API Gateway extensions.</p> <p>Import the Swagger definitions using the API Gateway Importer. Export an API Gateway API to a Swagger definition file using the API Gateway console or API Gateway Export API. For more information, see Develop REST APIs using OpenAPI in API Gateway and Export a REST API from API Gateway.</p>	December 18, 2015
Mapping request or response body or body's JSON fields to request or response parameters.	<p>Map method request body or its JSON fields into integration request's path, query string, or headers. Map integration response body or its JSON fields into request response's headers. For more information, see Parameter mapping examples for REST APIs in API Gateway.</p>	December 18, 2015
Working with Stage Variables in Amazon API Gateway	<p>Learn how to associate configuration attributes with a deployment stage of an API in Amazon API Gateway. For more information, see Use stage variables for a REST API in API Gateway.</p>	November 5, 2015
How to: Enable CORS for a Method	<p>It is now easier to enable cross-origin resource sharing (CORS) for methods in Amazon API Gateway. For more information, see CORS for REST APIs in API Gateway.</p>	November 3, 2015
How to: Use Client Side SSL Authentication	<p>Use Amazon API Gateway to generate SSL certificates that you can use to authenticate calls to your HTTP backend. For more information, see Generate and configure an SSL certificate for backend authentication in API Gateway.</p>	September 22, 2015
Mock integration of methods	<p>Learn how to mock-integrate an API with Amazon API Gateway. This feature enables developers to generate API responses from API Gateway directly without the need for a final integration backend beforehand.</p>	September 1, 2015

Change	Description	Date changed
Amazon Cognito Identity support	<p>Amazon API Gateway has expanded the scope of the \$context variable so that it now returns information about Amazon Cognito Identity when requests are signed with Amazon Cognito credentials. In addition, we have added a \$util variable for escaping characters in JavaScript and encoding URLs and strings. For more information, see Variables for data transformations for API Gateway.</p>	August 28, 2015
Swagger integration	<p>Use the Swagger import tool on GitHub to import Swagger API definitions into Amazon API Gateway. Learn more about OpenAPI extensions for API Gateway to create and deploy APIs and methods using the import tool. With the Swagger importer tool you can also update existing APIs.</p>	July 21, 2015
Mapping Template Reference	<p>Read about the \$input parameter and its functions in the Variables for data transformations for API Gateway.</p>	July 18, 2015
Initial public release	<p>This is the initial public release of the <i>API Gateway Developer Guide</i>.</p>	July 9, 2015