IF2130 – Organisasi dan Arsitektur Komputer

sumber: Greg Kesden, CMU 15-213, 2012

Machine-Level Programming: Basics
Achmad Imam Kistijantoro
Anggrahita Bayu Sasmita
Rahmat Mulyawan
Infall Syafalni

Dasar Bahasa Pemrograman Level Mesin

- Sejarah arsitektur dan prosesor Intel
- C, assembly, machine code
- Assembly Basics: Registers, operands, move
- Intro to x86-64



Intel x86 Processors

- Totally dominate laptop/desktop/server market
- Evolutionary design
 - Backwards compatible up until 8086, introduced in 1978
 - Added more features as time goes on
- Complex instruction set computer (CISC)
 - Many different instructions with many different formats
 - ▶ But, only small subset encountered with Linux programs
 - Hard to match performance of Reduced Instruction Set Computers (RISC)
 - But, Intel has done just that!
 - In terms of speed. Less so for low power.



Intel x86 Evolution: Milestones

	Name	Date	Transistors	MHz	
•	8086	1978	29K	5-10	
	First 16-bit In	itel processor. Ba	asis for IBM PC & D	OOS	
	► IMB address	space			
•	386	1985	275K	16-33	
	First 32 bit In	itel processor, re	eferred to as IA32		
	Added "flat addressing", capable of running Unix				
•	Pentium 4	2004	125M	2800-3800	
	First 64-bit In	itel processor, ref	ferred to as x86-64		
•	Core 2	2006	291M	1060-3500	
	First multi-core Intel processor				
	Core i7	2008	73 I M	1700-3900	
	▶ Four cores				

Intel x86 Processors, cont.

Machine Evolution

▶ 386	1985	0.3M
Pentium	1993	3.IM
▶ Pentium/MMX	1997	4.5M
PentiumPro	1995	6.5M
Pentium III	1999	8.2M
Pentium 4	2001	42M
Core 2 Duo	2006	291M
Core i7	2008	73 I M

Integrated Memory Controller - 3 Ch DDR3
Core 0 Core 1 Core 2 Core 3
P Shared L3 Cache

Added Features

- Instructions to support multimedia operations
- Instructions to enable more efficient conditional operations
- Transition from 32 bits to 64 bits
- More cores



x86 Clones: Advanced Micro Devices (AMD)

Historically

- AMD has followed just behind Intel
- A little bit slower, a lot cheaper

▶ Then

- Recruited top circuit designers from Digital Equipment Corp. and other downward trending companies
- Built Opteron: tough competitor to Pentium 4
- Developed x86-64, their own extension to 64 bits



Intel's 64-Bit

- ▶ Intel Attempted Radical Shift from IA32 to IA64
 - Totally different architecture (Itanium)
 - Executes IA32 code only as legacy
 - Performance disappointing
- AMD Stepped in with Evolutionary Solution
 - x86-64 (now called "AMD64")
- Intel Felt Obligated to Focus on IA64

intinya intel gagal buat represent amd 64 trus dia ngeclone amd 64 ini dan distandarin jadi em64t

- Hard to admit mistake or that AMD is better
- 2004: Intel Announces EM64T extension to IA32
 - Extended Memory 64-bit Technology
 - Almost identical to x86-64!
- All but low-end x86 processors support x86-64
 - But, lots of code still runs in 32-bit mode



Our Coverage

- ► IA32
 - ▶ The traditional x86
 - ▶ shark> gcc -m32 hello.c
- ×86-64
 - The emerging standard
 - shark> gcc hello.c
 - ▶ shark> gcc -m64 hello.c
- Presentation
 - ▶ Book presents IA32 in Sections 3.1—3.12
 - Covers x86-64 in 3.13
 - We will cover both simultaneously



Today: Machine Programming I: Basics

- History of Intel processors and architectures
- ▶ C, assembly, machine code
- Assembly Basics: Registers, operands, move
- Intro to x86-64



Definitions

- Architecture: (also ISA: instruction set architecture) The parts of a processor design that one needs to understand to write assembly code.
 - Examples: instruction set specification, registers.
- Microarchitecture: Implementation of the architecture.
 - Examples: cache sizes and core frequency.

x86-64 atau em64t


Example ISAs (Intel): x86, IA

ada perubahan arsitektur antargenerasi intel



Assembly Programmer's View

(yg terlihat dr prosesor)



Programmer-Visible State

- PC: Program counter
 - Address of next instruction
 - ▶ Called "EIP" (IA32) or "RIP" (x86-64)
- ▶ Register file kaya storage gt
 - ▶ Heavily used program data
- Condition codes
 - Store status information about most recent arithmetic operation
 - Used for conditional branching


Memory

- Byte addressable array
- Code and user data
- Stack to support procedures



Turning C into Object Code

- Code in files p1.c p2.c
- ▶ Compile with command: gcc -01 p1.c p2.c -o p
 - ▶ Use basic optimizations (-01)
 - ▶ Put resulting binary in file p



executable langsung pake -o



Compiling Into Assembly

C Code

```
int sum(int x, int y)
{
  int t = x+y;
  return t;
}
```

Generated IA32 Assembly

```
pushl %ebp nilai ebp disimpan ke memori (ebp[0])
  movl %esp,%ebp
  movl 12(%ebp),%eax output disimpan di operan kedua yaitu %eax
  popl %ebp
  ret
```

movl pindah data addl tambah data I = 4 byte, 32 bit q = 8 byte, 64 bit b = 2 byte, 16 bit w = 1 byte, 8 bit

Obtain with command

/usr/local/bin/gcc -O1 -S code.c

Produces file code . s

stack -> area di antara ebp dan esp esp

nilai t disimpan di eax

ebp+4 isinya return address setelah proses assembly

esp = extended stack pointer sp defaultnya 16, kalo 32 byte jadinya esp alias diextend

ebp = extended base pointer



Assembly Characteristics: Data Types

- "Integer" data of 1, 2, or 4 bytes
 - Data values
 - Addresses (untyped pointers)
- ▶ Floating point data of 4, 8, or 10 bytes

f add = untuk penjumlahan floating point

- No aggregate types such as arrays or structures
 - Just contiguously allocated bytes in memory



Assembly Characteristics: Operations

- Perform arithmetic function on register or memory data
- ▶ Transfer data between memory and register
 - Load data from memory into register
 - Store register data into memory
- Transfer control
 - Unconditional jumps to/from procedures
 - Conditional branches



Object Code

Code for sum

menandakan address 0×401040 <sum>: 0x55addres 040 0x89041 0xe5042 $0 \times 8 h$ dst 0×45 $0 \times 0 c$ 0×0.3 0×45 0x08

0x5d

fungsi red ()xc3

- Total of 11 bytes
- Each instruction1, 2, or 3 bytes
- Starts at address 0x401040

Assembler

- ▶ Translates .s into .o
- Binary encoding of each instruction
- Nearly-complete image of executable code
- Missing linkages between code in different files

Linker

- Resolves references between files
- Combines with static run-time libraries
 - ▶ E.g., code for malloc, printf
- Some libraries are dynamically linked
 - Linking occurs when program begins execution



Machine Instruction Example

int
$$t = x+y$$
;

addl 8(%ebp),%eax

Similar to expression:

$$x += y$$

4(%ebp) -> return address setelah execute sum

More precisely:

```
int eax;
int *ebp;
eax = ebp[3]
eax += ebp[2]
ebp 12
```

0x80483ca: 03 45 08

perintah addl 8(%ebp), %eax

C Code

- Add two signed integers
- Assembly
 - Add 2 4-byte integers
 - "Long" words in GCC parlance
 - Same instruction whether signed or unsigned
 - Operands:

x: Register %eax

y: Memory **M**[%**e**b**p**+8]

t: Register %eax

☐ Return function value in %eax

Object Code

- ▶ 3-byte instruction
- Stored at address 0x80483ca

Disassembling Object Code

Disassembled

```
080483c4 <sum>:
80483c4: 55
                   push
                          %ebp
80483c5: 89 e5
                          %esp, %ebp
                   mov
80483c7: 8b 45 0c mov
                          0xc(%ebp), %eax
80483ca: 03 45 08 add
                          0x8(%ebp), %eax
80483cd: 5d
                          %ebp
                   pop
80483ce: c3
                   ret
```

Disassembler

```
objdump -d p
```

- Useful tool for examining object code
- Analyzes bit pattern of series of instructions
- Produces approximate rendition of assembly code
- ▶ Can be run on either a .out (complete executable) or .o file



Alternate Disassembly

Object

0x401040: 0x55 0x89 0xe5 0x8b 0x45 0x0c 0x03 0x45 0x08 0x45

Disassembled

```
Dump of assembler code for function sum:
0x080483c4 < sum + 0>:
                        push
                                %ebp
0x080483c5 < sum + 1>:
                                %esp, %ebp
                        mov
0x080483c7 < sum + 3>:
                                0xc(%ebp), %eax
                        mov
0 \times 080483ca <sum+6>: add
                                0x8(%ebp), %eax
0x080483cd < sum + 9>:
                     pop
                                %ebp
0x080483ce < sum + 10>:
                     ret
```

- Within gdb Debugger gdb p disassemble sum
 - Disassemble procedurex/11xb sum
 - Examine the II bytes starting at sum



What Can be Disassembled?

```
% objdump -d WINWORD.EXE
WINWORD.EXE: file format pei-i386
No symbols in "WINWORD.EXE".
Disassembly of section .text:
30001000 <.text>:
30001000: 55
                     push %ebp
30001001: 8b ec
                     mov %esp, %ebp
30001003: 6a ff push $0xffffffff
30001005: 68 90 10 00 30 push $0x30001090
3000100a: 68 91 dc 4c 30 push
                              $0x304cdc91
```

- Anything that can be interpreted as executable code
- Disassembler examines bytes and reconstructs assembly
- source

Today: Machine Programming I: Basics


- History of Intel processors and architectures
- C, assembly, machine code
- Assembly Basics: Registers, operands, move
- Intro to x86-64



Integer Registers (IA32)

al, cl, dl, ah, ch masing" 1 byte

Origin (mostly obsolete)



accumulate

counter

data

base

source index

destination index

stack pointer

base pointer

oit virtual registers

16-bit virtual registers (backwards compatibility)

Moving Data: IA32

- Moving Data mov1 Source, Dest:
- Operand Types
 - Immediate: Constant integer data konstanta 400 heksa
 - Example: \$0x400, \$-533 konstanta -533
 - Like C constant, but prefixed with \\$'
 - ▶ Encoded with 1, 2, or 4 bytes
 - **Register:** One of 8 integer registers
 - Example: %eax, %edx
 - But %esp and %ebp reserved for special use
 - Others have special uses for particular instructions eax buat return value
 - Memory: 4 consecutive bytes of memory at address given by register
 - Simplest example: (%eax)
 - Various other "address modes"

%eax %ecx %edx %ebx %esi %edi

%esp

%ebp

gabole perpindahan yang 22nya memori ga disediain



mov1 Operand Combinations

Source Dest Src,Dest C Analog
$$\begin{cases} Imm & \begin{cases} Reg & mov1 & \$0x4, \$eax & temp = 0x4; \\ Mem & mov1 & \$-147, (\$eax) & *p = -147; \end{cases}$$
 movl
$$\begin{cases} Reg & mov1 & \$eax, \$edx & temp2 = temp1; \\ Mem & mov1 & \$eax, (\$edx) & *p = temp; \end{cases}$$

Cannot do memory-memory transfer with a single instruction



Simple Memory Addressing Modes

- Normal (R) Mem[Reg[R]]
 - ▶ Register R specifies memory address
 - Aha! Pointer dereferencing in C

```
movl (%ecx), %eax
```

- Displacement D(R) Mem[Reg[R]+D]
 - Register R specifies start of memory region
 - Constant displacement D specifies offset

```
movl 8 (%ebp), %edx
```



Using Simple Addressing Modes

```
void swap(int *xp, int *yp)
{
  int t0 = *xp;
  int t1 = *yp;
  *xp = t1;
  *yp = t0;
}
```

kalau ada () itu berarti akses memori % itu register, semua yg tanpa () itu akses register

```
swap:
  pushl %ebp
                             Set
  movl %esp, %ebp
                             Up
  pushl %ebx
          nilai address
  movl 8(%ebp), %edx
  movl 12(%ebp), %ecx
  mov1 *_{xp}(%edx), %ebx **
                             Body
  movl *yp(%ecx), %eax to
  movl %eax, (%edx)
  movl %ebx, (%ecx)
  popl %ebx
                             Finish
  popl %ebp
  ret
```



Using Simple Addressing Modes

```
void swap(int *xp, int *yp)
{
  int t0 = *xp;
  int t1 = *yp;
  *xp = t1;
  *yp = t0;
}
```

```
swap:
  pushl %ebp
                           Set
  movl %esp, %ebp
                           Up
  pushl %ebx
  movl 8(%ebp), %edx
  movl 12(%ebp), %ecx
  movl (%edx), %ebx
                           Body
  movl (%ecx), %eax
  movl %eax, (%edx)
  movl %ebx, (%ecx)
  popl %ebx
  popl %ebp
                           Finish
  ret
```




Understanding Swap


```
void swap(int *xp, int *yp)
{
  int t0 = *xp;
  int t1 = *yp;
  *xp = t1;
  *yp = t0;
}
```


Offset	•	Stack (in memory)
12	Ур	
8	хр	
4	Rtn adr	
0	Old %ebp	← %ebp
-4	Old %ebx	← %esp

Register	Value
%edx	хр
%ecx	УР
%ebx	t0
%eax	t1


```
movl 8(%ebp), %edx # edx = xp
movl 12(%ebp), %ecx # ecx = yp
movl (%edx), %ebx # ebx = *xp (t0)
movl (%ecx), %eax # eax = *yp (t1)
movl %eax, (%edx) # *xp = t1
movl %ebx, (%ecx) # *yp = t0
```







Address **Understanding Swap** 123 0×124 456 0x120 0x11c %eax 0x118 Offset %edx 0x1240x114 12 0×120 Уþ 0x110 %ecx 0×120 0x124 хр 0x10c 123 %ebx 4 Rtn adr 0x108 %esi %ebp 0x104 %edi **-**4 0x100 %esp movl 8(%ebp), %edx # edx = xp%ebp 0x104 movl 12(\$ebp), \$ecx #ecx = ypmovl (%edx), %ebx # ebx = *xp (t0) movl (%ecx), %eax # eax = *yp (t1) movl %eax, (%edx) # *xp = t1 movl %ebx, (%ecx) # *yp = t0





Address **Understanding Swap** 0×124 456 456 0x120 0x11c %eax 456 0x118 Offset %edx 0x124 0×114 12 0×120 Уþ 0x110 %ecx 0×120 0x124 хр 0x10c 123 %ebx 4 Rtn adr 0x108 %esi %ebp 0x104 %edi **-**4 0×100 %esp movl 8(%ebp), %edx # edx = xp%ebp 0x104 movl 12(\$ebp), \$ecx #ecx = ypmovl (%edx), %ebx # ebx = *xp (t0) movl (%ecx), %eax # eax = *yp (t1) movl %eax, (%edx) # *xp = t1

movl %ebx, (%ecx) # *yp = t0



Address **Understanding Swap** 0×124 456 123 0x120 0x11c %eax 456 0x118 Offset %edx 0x124 0×114 12 0×120 Уþ 0x110 %ecx 0×120 0x124 хр 0x10c 123 %ebx 4 Rtn adr 0x108 %esi %ebp 0x104 %edi **-**4 0×100 %esp movl 8(%ebp), %edx # edx = xp%ebp 0x104 movl 12(\$ebp), \$ecx #ecx = ypmovl (%edx), %ebx # ebx = *xp (t0) movl (%ecx), %eax # eax = *yp (t1) movl %eax, (%edx) # *xp = t1

movl %ebx, (%ecx) # *yp = t0



Complete Memory Addressing Modes

Most General Form

$$D(Rb,Ri,S)$$
 $Mem[Reg[Rb]+S*Reg[Ri]+D]$

- D: Constant "displacement" 1, 2, or 4 bytes
- Rb: Base register: Any of 8 integer registers
- ▶ Ri: Index register: Any, except for %esp
 - ▶ Unlikely you'd use %ebp, either
- S: Scale: 1, 2, 4, or 8 (why these numbers?)

Special Cases

(Rb,Ri)	Mem[Reg[Rb]+Reg[Ri]]
D(Rb,Ri)	Mem[Reg[Rb]+Reg[Ri]+D]
(Rb,Ri,S)	Mem[Reg[Rb]+S*Reg[Ri]]

Today: Machine Programming I: Basics

- History of Intel processors and architectures
- C, assembly, machine code
- Assembly Basics: Registers, operands, move
- Intro to x86-64



Data Representations: IA32 + x86-64

Sizes of C Objects (in Bytes)

C Data Type	Generic 32-bit	Intel IA32	x86-64
unsigned	4	4	4
▶ int	4	4	4
▶ long int	4	4	8
> char	I	1	I
> short	2	2	2
▶ float	4	4	4
double	8	8	8
long double	8	10/12	10/16
≻ char *	4	4	8
□ Or any other pointer			



x86-64 Integer Registers

4 byte

%rax	%eax	%r8	%r8d
%rbx	%ebx	% r9	%r9d
%rcx	%ecx	%r10	%r10d
%rdx	%edx	%r11	%r11d
%rsi	%esi	%r12	%r12d
%rdi	%edi	%r13	%r13d
%rsp	%esp	% r14	%r14d
%rbp	%ebp	% r15	%r15d

Extend existing registers. Add 8 new ones.

Make %ebp/%rbp general purpose

Instructions

Long word 1 (4 Bytes)

☐ Quad word q (8 Bytes)

- New instructions:
 - > mov1 → movq
 - addl → addq
 - ▶ sall → salq
 - etc.
- ▶ 32-bit instructions that generate 32-bit results
 - Set higher order bits of destination register to 0
 - Example: add1

32-bit code for swap

```
void swap(int *xp, int *yp)
{
  int t0 = *xp;
  int t1 = *yp;
  *xp = t1;
  *yp = t0;
}
```

```
swap:
  pushl %ebp
                          Set
  movl %esp, %ebp
                          Up
  pushl %ebx
  movl 8(%ebp), %edx
  movl
        12(%ebp), %ecx
  movl (%edx), %ebx
                          Body
  movl (%ecx), %eax
  movl %eax, (%edx)
  movl %ebx, (%ecx)
  popl %ebx
  popl %ebp
                          Finish
  ret
```



64-bit code for swap

swap:

```
void swap(int *xp, int *yp)
{
  int t0 = *xp;
  int t1 = *yp;
  *xp = t1;
  *yp = t0;
}
```

```
    Set
Up

movl (%rdi), %edx
movl (%rsi), %eax
movl %eax, (%rdi)
movl %edx, (%rsi)

Finish

Set
Up

Body

Body

Finish

Finish
```

- Operands passed in registers (why useful?)
 - First (xp) in %rdi, second (yp) in %rsi
 - 64-bit pointers
- No stack operations required
- ▶ 32-bit data
 - ▶ Data held in registers %eax and %edx
 - movl operation



64-bit code for long int swap

```
swap 1:
                                                        Set
void swap(long *xp, long *yp)
                                       (%rdi), %rdx
                              movq
 long t0 = *xp;
                                       (%rsi), %rax
                              movq
 long t1 = *yp;
                                                        Body
                                       %rax, (%rdi)
                              movq
 *xp = t1;
                                       %rdx, (%rsi)
 *yp = t0;
                              movq
                              ret
```

- ▶ 64-bit data
 - ▶ Data held in registers %rax and %rdx
 - movq operation
 - "q" stands for quad-word



Machine Programming I: Summary

- History of Intel processors and architectures
 - Evolutionary design leads to many quirks and artifacts
- C, assembly, machine code
 - Compiler must transform statements, expressions, procedures into low-level instruction sequences
- Assembly Basics: Registers, operands, move
 - The x86 move instructions cover wide range of data movement forms
- Intro to x86-64
 - A major departure from the style of code seen in IA32

