
一.主从复制(replication)的概念

当master(主)库的数据发生变化的时候,变化会实时的同步到slave(从)库。(从3.5的版本开始)

二.主从同步有什么好处?

- (1)水平扩展数据库的负载能力。
- (2)容错,高可用。Failover(失败切换)/High Availability
- (3)数据备份



三.实现过程

- 3.1 在master机器上,主从同步事件会被写到特殊的log文件中(binary-log);在slave机器上,slave读取主从同步事件,并根据读取的事件变化,在slave库上做相应的更改。
 - 3.2 在master机器上,主从同步事件会被写到特殊的log文件中(binary-log);

主从同步事件有3种形式:statement、row、mixed。

statement: 会将对数据库操作的sql语句写入到binlog中。

row: 会将每一条数据的变化写入到binlog中。

mixed: statement与row的混合。Mysql决定什么时候写statement格式的,什么时候写row格式的binlog

3.3在master机器上的操作

当master上的数据发生改变的时候,该事件(insert、update、delete)变化会按照顺序写入到binlog中。

binlog dump线程


当slave连接到master的时候,master机器会为slave开启binlog dump线程。当master 的 binlog发生变化的时候,binlog dump 线程会通知slave,并将相应的binlog内容发送给slave。

3.4在slave机器上的操作

当主从同步开启的时候,slave上会创建2个线程(I/O线程 / SQL线程)。

I/O线程: 该线程连接到master机器,master机器上的binlog dump线程会将binlog的内容发送给该I/O线程。该I/O线程接收到binlog内容后,再将内容写入到本地的relay log(中继日志)。

SQL线程 : 该线程读取1/0线程写入的relay log。并且根据relay log的内容对slave数据库做相应的操作。



```
四.配置主从命令(这里应用的是mysq18.0版本,且ip为 192.168.100.135 | 192.168.100.136 两台机器)
     1. 确保从数据库与主数据库里的数据一致
     2. 在主数据库里创建一个同步账户授权给从数据库使用
     3. 配置主数据库(修改配置文件)与开启binlog日志
     4. 配置从数据库(修改配置文件)
     5. 配置从节点
  MySQL8.0新加了很多功能,其中在用户管理中增加了角色的管理,默认的密码加密方式也做了调整,由之前的sha1改为了sha2,同时加上
5.7的禁用用户和用户 过期的设置,这样方面用户的管理和权限的管理,也增加了用户的安全性。
  4.1 mysql> show variables like "%binlog_format%";
     | Variable_name | Value |
     +-----
     | binlog_format | ROW |
     1 row in set, 1 warning (0.03 sec)`
     默认新版本中的复制模式默认都是行级别;
  4.2查看binlog日志所在位置.(8.0版本默认是开启binlog的状态)
     查看binlog是否开启,以及当前server_id(注意server_id代表当前实例的唯一标识,不能与其他实例相同);
     mysql> show variables like "%log_bin%";
     +-----
     | Variable_name
                              | Value
     +-----
     | log_bin
                              ON
     | log_bin_basename
                             D:\mysql8.0.19\mysql-8.0.19-winx64\data\binlog
                           | D:\mysql8.0.19\mysql-8.0.19-winx64\data\binlog.index |
     | log_bin_index
     | log_bin_trust_function_creators | OFF
     | log_bin_use_v1_row_events
                              OFF
     | sql_log_bin
                              ON
     6 rows in set, 1 warning (0.00 sec)
  4.3查看当前数据库的server_id
     mysql> show variables like "%server_id%";
     +-----
     | Variable_name | Value |
     +----+
     server_id | 1
     | server_id_bits | 32
     2 rows in set, 1 warning (0.00 sec)
  4.4创建用于专门主从复制用的用户.(主库创建)
     create user "repl"@"192.168.100.%" identified by "mysql";
     从库所在服务器链接一下.链接成功,给用户授权.
     grant replication slave on *.* to "repl"@"192.168.15.%";
     查看权限
     show grants for "repl"@"192.168.100.%";
  4.5将主数据库中的数据进行mysqldump备份,
     1.直接进行数据库备份 添加参数 --all-databases -master-data=2 --single-transaction 参数
        参数说明:
           --all-databases #表示将所有的数据库全部进行数据备份
           -master-data=2 #将当前数据库中文件的binlog节点信息注释到备份文件中.
           --single-transaction #会在备份的时候添加一个瞬时的锁定,为数据库创建一个快照,然后再备份过程中不会对数据的写入
造成影响.
     语句如下:
       (1)备份所有数据库:
           mysqldump --all-databases --master-data=2 --single-transaction -u root -p -P 3306 > ./dbdump.db
       (2)备份单个数据库:
           mysqldump -h127.0.0.1 -uroot -p -P 3306 php45 > d:/backupfile.sql
           Enter password: ****
```

```
(3)同时备份多个MySQL数据库
          mysqldump -h127.0.0.1 -uroot -ppass --databases php45 php46 > ./multibackupfile.sql
     2.还原sql到数据库
       还原MySQL数据库的命令。还原当前备份名为backupfile.sql的数据库
       mysql -h127.0.0.1 -uroot -p -P 3306 数据库名 < backupfile.sql (将已经备份好的数据全部恢复到数据库中,有则覆盖无
则添加)
 4.6修改加密方式(caching_sha2_password)
    mysql8.0重置了加密放置
       mysql> select user,host,plugin from mysql.user;
        +----+
                     host
        user
                             plugin
       +-----
        | mysql.infoschema | localhost | caching_sha2_password |
        | mysql.session | localhost | caching_sha2_password |
                   | localhost | caching_sha2_password |
| localhost | caching_sha2_password |
        mysql.sys
        *----
     (1)修改加密方式(对于一些配置不是支持的很好),配置文件中修改
        default_authentication_plugin=mysql_native_password
        修改后从起mysq1服务
       mysql> create user "slave1"@"192.168.100.%" identified by "mysql";
       Query OK, 0 rows affected (0.02 sec)
       mysql> select user,host,plugin from mysql.user;
       *-----
                | host | plugin
       +----+
                | 192.168.100.% | mysql_native_password | |
        | mysql.infoschema | localhost | caching_sha2_password |
        | mysql.session | localhost | caching_sha2_password |
        | mysql.sys | localhost | caching_sha2_password |
                    | localhost | caching_sha2_password |
        root
        *----
       5 rows in set (0.00 sec)
     (2)或者直接手动定义加密方式
       mysql> create user "slave1"@"192.168.100.%" identified with mysql_native_password by "mysql";
       FLUSH PRIVILEGES; #刷新权限
 4.7 进行用户授权
     查看权限:
    mysql> show grants for 'slave1'@'192.168.100.%';
     +-----
     | Grants for slave1@192.168.100.%
     +-----
    | GRANT USAGE ON *.* TO `slave1`@`192.168.100.%` |
     1 row in set (0.00 sec)
     (1)为username@localhost用户赋予超级用户权限:
       grant all privileges on *.* to 'slave1'@'192.168.100.%' with grant option;
     (2)grant: 授权
        (1)all privileges:所有的权限
       (2)on *.*: 在哪个数据库的那个表
       (3)to username@localhost: 对哪个用户的哪个主机
       (4)with grant option: 是不是 将username用户自己本身的权限赋给其他账户
       MySQL8.0的用户授权和之前有所区别,老版本的常用授权语句在8.0中会报错:
        --MySQL8.0之前版本:
          GRANT ALL ON *.* TO `root`@`127.0.0.1` IDENTIFIED BY 'passowrd' WITH GRANT OPTION;
```

```
--MySQL8.0版本:
          --创建账号密码
             CREATE USER `root'@`127.0.0.1` IDENTIFIED BY 'passowrd';
          --授予权限
             GRANT ALL ON *.* TO `root'@`127.0.0.1` WITH GRANT OPTION;
          --删除权限
             REVOKE all privileges ON databasename.tablename FROM 'username'@'host';
             ALTER USER 'root'@'localhost' IDENTIFIED WITH mysql_native_password BY 'password';
      (3)普通用户权限添加如下:
      grant usage, select, insert, update, delete, create temporary tables, execute on php45.* to 'slave1'@'192.168.100.%';
//此时没有with grant option 表示不给其他用户赋权限
      flush privileges;
         usage: 无权限,当你想创建一个没有权限的用户时候,指定usage
         view:视图的权限(mysql8.0+赋权限出错)ERROR 3619 (HY000): Illegal privilege level specified for VIEW
         create temporary tables:创建临时表的权限
         excute: 执行的权限
         REPLICATION SLAVE ON: 主从的权限
五.开始配置
   /*创建账号sql:
  create user 'username'@'localhost' identified by 'password';
  授权grant [权限] on 数据库名.数据表名 to 'username'@'localhost' identified by 'password';
  5.1(主机配置)
      mysql> CREATE USER 'slave1'@'192.168.100.%' IDENTIFIED WITH mysql_native_password BY 'slave1';
      Query OK, 0 rows affected (0.04 sec)
      mysql> select user,host from mysql.user;
      mysql> GRANT REPLICATION SLAVE ON *.* TO 'slave1'@'192.168.100.%';
      Query OK, 0 rows affected, 1 warning (0.00 sec)
      对于MySQL的主从复制来说最重要的主要就是binlog日志,所以我们就需要开启binlog日志,并设置server-id的值。需要重启服务器
之后才生效 二进制日志,也 就是我们常说的binlog。
      mysql> show variables like "%log_bin%";
                                    Value
      | Variable name
      | log_bin
                                   /usr/local/mysql/data/binlog
      | log_bin_basename
                                    | /usr/local/mysql/data/binlog.index |
      log_bin_index
      | log_bin_trust_function_creators | OFF
      | log_bin_use_v1_row_events | OFF
      | sql_log_bin
                                    ON
      6 rows in set (0.03 sec)
      1. 增量备份(不是所有数据备份,而是最近的写操作)
      2. 用于MySQL主从复制
   主要就是下配置文件中添加如下配置
      log-bin=mysql-bin //开启二进制文件
      server-id=1 //这里自己随意定义
   重启mysql服务: service mysql restart
```

```
查看当前的binlog日志以及节点,方便配置从服务器
   mysql> show master status;
                  | Position | Binlog_Do_DB | Binlog_Ignore_DB | Executed_Gtid_Set |
   +-----
   | mysql-bin.000001 | 155 |
   +-----
   1 row in set (0.00 sec)
   5.2从机配置
      修改配置文件,开启二进制
      log-bin=mysql-bin
      server-id = 2 ////一定不能和主机重复
      relay_log = /usr/local/mysql/data/mysql-relay-bin
      relay_log-index = /usr/local/mysql/data/mysql-relay-bin.index
      log_slave_updates = 1
      read_only = 1
      指定主节点的ip,端口,用户
      change master to master_host='192.168.81.132',--主服务器的ip
      master_port=3306,--端口
      master_user='slave1',--用户名
      master_password='slave1',--密码
      master_log_file='mysql- bin.000001',--指定主服务器的binlog日志
      master_log_pos=155; -- 目前日志的节点
   完整命令:
      mysql> change master to master host='192.168.100.143', master port=3306, master user='slave1',
master_password='slave1',master_log_file='mysql-bin.000001',master_log_pos=155;
      Query OK, 0 rows affected, 2 warnings (0.03 sec)
change master to master_host='192.168.100.143', master_port=3306, master_user='slave1', master_password='slave1',
master_log_file='mysql-bin.000001',master_log_pos=322;
   开启从服务器:
      mysql> start slave;
      Query OK, 0 rows affected (0.01 sec)
  查看状态:
   mysql> show slave status\G;
      Slave_IO_State:
      Master_Host: 192.168.100.143
      Master User: slave1
      Master_Port: 3306
      Connect_Retry: 60
      Master_Log_File: mysql-bin.000001
      Read_Master_Log_Pos: 155
      Relay_Log_File: localhost-relay-bin.000001
      Relay_Log_Pos: 4
      Relay_Master_Log_File: mysql-bin.000001
      Slave_IO_Running: Yes
      Slave_SQL_Running: Yes
      如果出现错误:
      stop slave;
      reset slave all;
      从新查看主机的binlog日志(show master status),看是否填错了
```