PHYS 253: Thermal Physics

W.R.YCH.

Fall 2026

Abstract

Contents

1 Introduction **1**
1.1 Course Information 1

2 Temperature **1**
2.1 Basic Concepts 1
2.1.1 State Functions 1
2.1.2 Adiabatic and Diathermal Walls 2
2.2 Equilibrium State 2
2.2.1 The Zeroth Law of Thermodynamics 2
2.2.2 Temperature 3
2.2.3 Thermodynamic Equilibrium 3
2.2.4 PV Diagrams 3
2.3 Equations of State 4
2.4 Scales of Temperature 5
2.4.1 The Gas Thermometer 5
2.4.2 Absolute Zero 5

3 Reversible Processes and Work **5**
3.1 Reversible Processes 5
3.1.1 Isothermal Compression 6
3.1.2 Thermal Expansion 6
3.1.3 Bulk Modulus 7
3.2 Work 7
3.2.1 Free Expansion 8
3.3 Other Kinds of Work 8
3.4 Calculating Work in a Reversible Process 8

4 The First Law of Thermodynamics **8**
4.1 The Work of Thompson and Joule 8
4.2 The First Law of Thermodynamics 9
4.2.1 Internal Energy 9
4.2.2 Heat 10
4.3 Heat Capacity 10
4.3.1 Other Heat Capacities 11
4.3.2 Calorimetry 11
4.3.3 Latent Heat 12
4.4 Kinetic Theory of Gases 12
4.4.1 Pressure and Temperature of an Ideal Gas 12
4.4.2 Equipartition of Energy 12
4.4.3 Counting Quadratic Degrees of Freedom 12
4.4.4 Frozen-Out Degrees of Freedom 12
4.4.5 Heat Capacities from Equipartition 12
4.5 Ideal Gases and the First Law 12
4.5.1 Internal Energy of an Ideal Gas 13

4.5.2 Isothermal Processes . . . 13
4.5.3 Adiabatic Processes . . . 13
4.6 Rates of Processes . . . 13
4.6.1 Heat Conduction . . . 13
4.6.2 Viscosity . . . 13
4.6.3 Diffusion . . . 13

5 The Second Law of Thermodynamics 13
5.1 Carnot Cycles . . . 13
5.1.1 Thermodynamic Cycles . . . 13
5.1.2 The Carnot Cycle . . . 13
5.2 Efficiency of an Engine . . . 13
5.3 Statements of the Second Law . . . 13
5.3.1 The Kelvin–Planck Statement . . . 13
5.3.2 The Clausius Statement . . . 13
5.3.3 Equivalence of the Two Statements . . . 13
5.4 Carnot's Theorem . . . 13
5.5 The Thermodynamic Temperature Scale . . . 13
5.6 Engines and Refrigerators . . . 13
5.6.1 Refrigerators . . . 13
5.6.2 Heat Pumps . . . 13
5.6.3 Internal Combustion Engines . . . 13
5.6.4 The Steam Engine . . . 13

6 Entropy 14
6.1 The Clausius Inequality . . . 14
6.2 Entropy . . . 16
6.3 The Principle of Increasing Entropy . . . 17
6.3.1 Entropy and the Arrow of Time . . . 18
6.4 Entropy–Temperature Diagrams . . . 18
6.5 The Thermodynamic Identity . . . 19
6.6 Other Examples of Entropy Calculations . . . 19
6.6.1 Free Expansion of an Ideal Gas . . . 19
6.6.2 Entropy of an Ideal Gas in General . . . 20
6.6.3 Entropy Change of the Universe when Heating Water . . . 20

7 Statistical Mechanics 21
7.1 Introduction to Probability and Statistics . . . 21
7.1.1 The Multiplicity Function . . . 22
7.2 Microscopic View of Entropy . . . 22
7.2.1 The Two-State Paramagnet . . . 22
7.2.2 The Einstein Solid . . . 23
7.2.3 Interacting Systems . . . 24
7.2.4 Large Systems . . . 26
7.2.5 Thermodynamic Limit . . . 27
7.2.6 Entropy as Multiplicity . . . 27

7.2.7 Maxwell's Demon 28
7.3 Ideal Gases 29
7.3.1 Multiplicity of an Ideal Gas 29
7.3.2 Entropy of an Ideal Gas 30
7.3.3 Entropy of Mixing 31

8 The Thermodynamic Potentials and the Maxwell Relations 31
8.1 Thermodynamic Potentials 31
8.2 Internal Energy 31
8.3 Enthalpy 31
8.4 Helmholtz Function 31
8.4.1 Maximum Work 31
8.4.2 Equilibrium at Constant Volume 31
8.5 Gibbs Function 31
8.5.1 Equilibrium at Constant Pressure 31
8.5.2 Useful Work 31
8.6 The Thermodynamic Square 31
8.7 Example Using a Maxwell Relation 31

A Proofs 32
A.1 Inexact differentials 32
A.2 Multiplicity of a Large Einstein Solid 32

B Useful Links 32

1 Introduction

1.1 Course Information

The textbook is *An Introduction to Thermal Physics* by Daniel V. Schroeder. Grading is divided as follows:

- 10% problem sets (~ 6, submitted as handwritten PDF scans)[1]
- 50% two midterms
- 40% final exam

2 Temperature

2.1 Basic Concepts

Definition 1 (System)**.** *A system is the part of the universe under study.*

Definition 2 (Surroundings)**.** *The surroundings are everything outside the system that can interact with it.*

Definition 3 (Boundary)**.** *The boundary, or also named partition, is the wall separating the system from its surroundings.*

Definition 4 (Closed System)**.** *A closed system exchanges energy but not matter with its surroundings.*

Definition 5 (Equilibrium State)**.** *An equilibrium state is one in which all the bulk physical properties of the system (i.e pressure, volume...) are uniform throughout the system and do not change with time.*

2.1.1 State Functions

Definition 6 (State Function)**.** *A state function is a property of a system that depends only on its current equilibrium state, not on how that state was reached. Its change between two states is therefore path independent.*

Example 1. *Pressure P, volume V, and temperature T are state functions; heat Q and work W are not.*

Remark 1 (State Property)**.** *State functions are also called state properties, since they describe the state itself.*

Remark 2 (State Variables)**.** *The state variables are the state functions that are easily measured and allow the specification of an equilibrium state, e.g. P, V, T. For a simple fluid, only two are independent, the third being fixed by the equation of state.*

[1] Only one or two problems on each assignment are marked for submission and grading.

2.1.2 Adiabatic and Diathermal Walls

Definition 7 (Mechanical Interaction)**.** *A mechanical interaction is an exchange of energy between the system and its surroundings as work, e.g. through a moving boundary.*

Example 2. *A piston pushing a gas (system) in a cylinder.*

Definition 8 (Adiabatic Wall)**.** *An adiabatic (or adiathermal) wall allows only mechanical interactions: no heat can pass through it.*

Definition 9 (Diathermal Wall)**.** *A diathermal wall allows thermal interaction: heat can pass through it.*

Definition 10 (Thermal Contact)**.** *Two systems are in thermal contact when separated by a diathermal wall.*

Example 3 (Testing a Wall)**.** *A rigid cylinder contains two gases separated by a rigid wall; a piston compresses the second gas. Since the first gas cannot do or receive work, its pressure can only change if heat crosses the wall (at fixed volume, a change in T shows up as a change in P). If its pressure stays constant, the wall is adiabatic; otherwise it is diathermal.*

2.2 Equilibrium State

Returning to Example 3, if the two gases are put into thermal contact, after a time their pressures and volumes stop changing: each gas has reached an equilibrium state.

Definition 11 (Thermal Equilibrium)**.** *Two systems in thermal contact are in thermal equilibrium when no further changes occur in their state variables.*

2.2.1 The Zeroth Law of Thermodynamics

Law 1 (Zeroth Law of Thermodynamics)**.** *If systems A and B are each in thermal equilibrium with a third system C, then A and B are in thermal equilibrium with each other.*




Figure 1: If A and B are in thermal equilibrium upon contact, as are A and C, then so are B and C.

2.2.2 Temperature

Definition 12 (Temperature)**.** *Temperature is the property that tells whether two systems are in thermal equilibrium: they are if and only if they have the same temperature T.*

2.2.3 Thermodynamic Equilibrium

Definition 13 (Thermodynamic Equilibrium)**.** *Systems in thermodynamic equilibrium must meet the following conditions:*

- *Thermal equilibrium, with no heat flow (uniform temperature).*
- *Mechanical equilibrium, with no unbalanced forces acting.*
- *Chemical equilibrium, with no net chemical reaction occurring.*
- *Diffusive equilibrium, with no flow of matter from one system to another.*

2.2.4 PV Diagrams

Definition 14 (PV Diagram)**.** *A PV diagram is a plot of pressure versus volume, on which each equilibrium state of a gas, such as the gases in Example 3, is a single point (P, V).*




Figure 2: The four basic processes on a PV diagram: isobaric (constant P), isochoric (constant V), isothermal (constant T, PV = const for an ideal gas) and adiabatic (no heat exchanged, steeper than an isotherm).

Definition 15 (Isobar)**.** *An isobar is the curve on a PV diagram joining all states with the same pressure, a horizontal line.*

Definition 16 (Isochore)**.** *An isochore is the curve on a PV diagram joining all states with the same volume, a vertical line.*

Definition 17 (Adiabat)**.** *An adiabat is the curve on a PV diagram followed by a system undergoing a reversible adiabatic process (no heat exchanged). It is steeper than an isotherm, since compression raises the temperature.*

Definition 18 (Isotherm)**.** *An isotherm is the curve on a PV diagram joining all states with the same temperature.*

Remark 3. *To trace an isotherm, put a gas in state (P, V) in thermal equilibrium with a reference system, then separate them and push the piston to reach a new state (P', V'). If (P', V') is also in thermal equilibrium with the unchanged reference system, the zeroth law says both states have the same temperature, so they lie on the same isotherm (Figure 3).*

Example 4 (Same Isotherm)**.** *For an ideal gas, $T = \frac{PV}{nR}$, so two states lie on the same isotherm if and only if $PV = P'V'$. For one mole in the states $(100\ kPa, 24.9\ L)$ and $(200\ kPa, 12.45\ L)$,*

$$PV = P'V' = 2490\ J \implies T = \frac{2490\ J}{(1\ mol)(8.31\ J/(mol\ K))} \approx 300\ K,$$

so both states lie on the $300\ K$ isotherm, and two identical gases in these states would be in thermal equilibrium.

2.3 Equations of State

Definition 19 (Equation of State)**.** *An equation of state is a functional relationship between the state variables of a system in equilibrium, which leaves only two of them independent.*

Example 5. *For a gas, an equation of state is*

$$f(P, V, T) = 0.$$

Example 6. *For an ideal gas (where there are no intermolecular attractions and the molecules themselves have no volume), the equation of state is determined empirically*[2] *to be*

$$PV = nRT, \tag{1}$$

where n is the number of moles present and $R = 8.314\ J/(mol\ K)$ is the universal gas constant.

[2] Determined from experiment and observation rather than derived from theory.

It follows from Equation (1) that the isotherms for an ideal gas are a family of hyperbolae, as shown in Figure 3.




Figure 3: The isotherms for an ideal gas. They form a family of hyperbolae $P = \frac{nRT}{V}$.

2.4 Scales of Temperature

2.4.1 The Gas Thermometer

2.4.2 Absolute Zero

3 Reversible Processes and Work

Definition 20 (Process)**.** *A process is the mechanism of bringing about a change in a system from one equilibrium state to another.*

Example 7. *Pushing the piston and compressing the second gas in Example 3 is a process.*

Definition 21 (End Points)**.** *The end points of a process are its initial and final equilibrium states.*

3.1 Reversible Processes

Definition 22 (Reversible Process)**.** *A process is reversible if, after it occurs, both the system and its surroundings can be returned to their original states.*

Definition 23 (Quasistatic Process)**.** *A quasistatic process is one that can be thought of as a succession of equilibrium states.*

Remark 4. *Reversible processes are quasistatic processes in which no dissipative forces, such as friction, are present.*

3.1.1 Isothermal Compression

Definition 24 (Reservoir)**.** *A reservoir (or heat or thermal reservoir) is a system so large that it can absorb or release heat without any significant change in temperature.*

Example 8 (Reversible Isothermal Compression)**.** *A gas in contact with a reservoir at T is compressed from (P_1, V_1) to (P_2, V_2) by infinitesimal pushes on a frictionless piston, re-equilibrating at T each time. It passes only through equilibrium states, tracing an isotherm (Figure 3).*

Example 9 (Irreversible Compression)**.** *Pushing the piston in suddenly causes turbulence and finite gradients: the intermediate stages have no well-defined P or T, so the process cannot be plotted on a PV diagram.*

Remark 5. *In a reversible process there are never finite pressure or temperature differences, within the system or with the surroundings, so its direction can be reversed by an infinitesimal change in external conditions.*

3.1.2 Thermal Expansion

Definition 25 (Linear Coefficient of Thermal Expansion)**.** *For a small increase in temperature ΔT at constant tension F, the increase in length of a solid bar of length L is $\Delta L = \alpha L \Delta T$, where*

$$\alpha = \frac{1}{L}\left(\frac{\partial L}{\partial T}\right)_F \tag{2}$$

is the linear coefficient of thermal expansion, in units of K^{-1}.

Definition 26 (Volume Coefficient of Thermal Expansion)**.** *For a small increase in temperature ΔT at constant pressure P, the increase in volume of a solid or liquid of volume V is $\Delta V = \beta V \Delta T$, where in the limit as ΔT approaches zero,*

$$\beta = \frac{1}{V}\left(\frac{\partial V}{\partial T}\right)_P \tag{3}$$

is the volume coefficient of thermal expansion, in units of K^{-1}.

Remark 6. *Slow thermal expansion is reversible: cooling by ΔT undoes the volume change from heating by ΔT.*

Remark 7. *For solid material, α and β are related*

$$\beta \approx 3\alpha.$$

3.1.3 Bulk Modulus

Definition 27 (Isothermal Bulk Modulus)**.** *The bulk modulus of a solid or fluid is the stress (pressure increase) divided by the fractional volume decrease, at constant temperature:*

$$B = -V\left(\frac{\partial P}{\partial V}\right)_T \equiv \frac{1}{\kappa}, \tag{4}$$

where κ is the isothermal compressibility and the negative sign ensures that B stays positive.

3.2 Work

Proposition 1 (Reversible Work)**.** *The work done on a fluid in a reversible process from V_1 to V_2 is*

$$W = -\int_{V_1}^{V_2} P\,dV, \tag{5}$$

or, for an infinitesimal change,

$$\delta W = -P dV. \tag{6}$$

Proof. A gas in the equilibrium state (P_1, V_1) is compressed to (P_2, V_2) by increasing the external force on a frictionless piston of area A, so that $F = PA$. If the force is increased infinitesimally so that the piston moves in by dx, the volume changes by $dV = -A\,dx$, and the work done on the gas is

$$\delta W = F\,dx = PA\,dx = -P\,dV.$$

The minus sign is necessary because during compression the volume decreases, while the work done on the gas is positive. □

Remark 8 (Quasistatic Piston, Irreversible Process)**.** *$\delta W = -PdV$ also holds for irreversible processes in which the piston itself moves quasistatically (no finite pressure drop across it), even if irreversibility occurs elsewhere, e.g. a slow chemical reaction releasing gas, or gas slowly leaking through a small hole.*

Remark 9 (Work as an Area)**.** *The magnitude of the work in a reversible process is the area under its path on a PV diagram (Figure 2), so it depends on the path. For a cycle, the enclosed area is the magnitude of the net work, with a sign set by the direction of the cycle.*

Example 10 (Isothermal Work on an Ideal Gas)**.** *Along an isotherm, $P = \frac{nRT}{V}$, so*

$$W = -\int_{V_1}^{V_2} \frac{nRT}{V}\,dV = -nRT\ln\frac{V_2}{V_1},$$

negative for an expansion ($V_2 > V_1$) and positive for a compression.

Remark 10 (Sign Convention for Work)**.** *In this course, W is the work done on the system by its surroundings: positive for compression, negative for expansion.*

3.2.1 Free Expansion

Definition 28 (Free Expansion)**.** *Free expansion is the expansion of a gas into a vacuum, with no external pressure applied.*

- *The process is irreversible;*
- *There is no temperature change;*
- *No heat enters the system, since the walls are adiabatic;*
- *No work is done, since there is no external pressure;*

3.3 Other Kinds of Work

Definition 29 (Work on an Extensible Wire)**.** *The work done on a wire under tension F when it is stretched by an infinitesimal length dL is*

$$\delta W = F\,dL, \tag{7}$$

positive for an extension ($dL > 0$), consistent with the sign convention for work.

Remark 11. *Work also includes other energy transfers, such as magnetizing a material or running a current through a resistor.*

3.4 Calculating Work in a Reversible Process

Remark 12 (Method)**.** *To find the change in one state function given the changes in two others, write the equation of state for the wanted one in terms of the other two; since a reversible process is a succession of equilibrium states, it holds at every step.*

Example 11 (Work on a Compressible Fluid)**.** *For a fluid taken reversibly from (P_1, T_1) to (P_2, T_2), write $V = V(P, T)$:*

$$dV = \left(\frac{\partial V}{\partial P}\right)_T dP + \left(\frac{\partial V}{\partial T}\right)_P dT = -\frac{V}{B}\,dP + \beta V\,dT,$$

where $B = -V\left(\frac{\partial P}{\partial V}\right)_T$ and $\beta = \frac{1}{V}\left(\frac{\partial V}{\partial T}\right)_P$, so

$$W = -\int P\,dV = \int_{P_1}^{P_2} \frac{PV}{B}\,dP - \int_{T_1}^{T_2} P\beta V\,dT.$$

4 The First Law of Thermodynamics

4.1 The Work of Thompson and Joule

Joseph Black, professor of medicine at the University of Glasgow, discovered the following principle:

Principle 1 (Black's Principle of Calorimetry)**.** *When two bodies are put in thermal contact, the heat lost by one is equal to the heat gained by the other.*

This suggested that heat was a conserved substance, called caloric.

Definition 30 (Caloric)**.** *Caloric is a hypothetical weightless, invisible fluid, once believed to be heat itself, conserved and flowing from hotter to colder bodies.*

Then came Benjamin Thompson, working in the arsenal in Munich, who noticed while boring cannons that friction produced seemingly unlimited heat:

Principle 2 (Thompson's Observation)**.** *Heat is not a finite substance such as caloric, and there is a direct relation between the work done and the heat produced.*

About 50 years later, James Joule finished the job with a careful series of experiments, using a tub containing a paddle wheel rotated by weights falling outside the tub. The water inside was stirred (irreversibly, because of turbulence), raising its temperature between two equilibrium states. The walls of the tub were insulating, so the work was performed under adiabatic conditions.

Definition 31 (Adiabatic Work)**.** *Adiabatic work is work done on a system enclosed by adiabatic (thermally insulating) walls, so that no heat is exchanged with the surroundings.*

Joule found:

Result 1 (Mechanical Equivalent of Heat)**.** 4.2 *kJ of work is required to raise the temperature of* 1 *kg of water by* 1 *K.*

Result 2 (Adiabatic Work)**.** *No matter how the adiabatic work is performed, the same amount of work is required to take a system between the same two equilibrium states.*

This second result is exactly the First Law of Thermodynamics, stated in the next subsection.

4.2 The First Law of Thermodynamics

Law 2 (First Law of Thermodynamics)**.** *If a thermally isolated system is brought from one equilibrium state to another, the work necessary to achieve this change is independent of the process used.*

4.2.1 Internal Energy

By Law 2, the adiabatic work (Definition 31) depends only on the end states, whether the process is reversible or not, so it defines a state function:

Definition 32 (Internal Energy)**.** *The internal energy U is the state function satisfying*

$$W_{adiabatic} = U_2 - U_1.$$

Remark 13. *U is the kinetic and potential energy of the individual molecules (random motion, mutual attraction), not of the object as a whole.*

4.2.2 Heat

Remark 14. *If the system is not thermally isolated, the work between two equilibrium states depends on the path and generally differs from the adiabatic work.*

The difference between ΔU and W is called heat Q.

$$\Delta U = W + Q. \tag{8}$$

Definition 33 (Heat)**.** *Heat Q is the nonmechanical exchange of energy between the system and the surroundings due to their temperature difference, flowing spontaneously from the hotter to the colder one.*

Remark 15 (Sign convention for Heat)**.** *Heat Q is positive when it enters the system and is negative when it leaves the system.*

Remark 16 (Differential Form)**.** *For an infinitesimal process, the first law takes the form*

$$dU = \delta W + \delta Q. \tag{9}$$

The δ are used to indicate that their integrals are in general path dependent (inexact differentials[3]).

To see why non-adiabatic work is an inexact differential, see Appendix A.1.

Remark 17. *For a compressible fluid, where $\delta W = -P dV$ for an infinitesimal reversible process, the first law becomes*

$$dU = -P\,dV + \delta Q,$$

or

$$\delta Q = dU + P\,dV \quad \textit{(reversible)}. \tag{10}$$

4.3 Heat Capacity

Definition 34 (Heat Capacity)**.** *The heat capacity C of a system is the heat needed per unit temperature rise, in the limit of an infinitesimally small rise, for heat added reversibly:*

$$C = \lim_{\Delta T \to 0} \frac{Q}{\Delta T} = \frac{\delta Q}{dT}. \tag{11}$$

Remark 18. *Heat capacities are measured with irreversible heating, but this agrees with the definition as long as the system re-equilibrates much faster than it is heated, so no significant temperature or pressure gradients form.*

[3] Exactness, including the test $\left(\frac{\partial M}{\partial y}\right)_x = \left(\frac{\partial N}{\partial x}\right)_y$, is treated in detail in my Math 325 notes, in the section "First-Order Scalar Equation".

Definition 35 (Specific Heat)**.** *The specific heat c is the heat capacity per unit mass*

$$c = \frac{1}{m}\frac{\delta Q}{dT}. \tag{12}$$

Remark 19. *Lower case c is used consistently for specific heat, whether per unit mass, per mole, or another definite quantity.*

4.3.1 Other Heat Capacities

Remark 20. *Since Q depends on the path, there is a different heat capacity for each path between the same end temperatures. The two most useful are at constant volume and at constant pressure.*

Definition 36 (Heat capacity at constant volume)**.** *For an infinitesimal isochoric reversible process, Equation (10) gives $\delta Q_V = dU$, thus the heat capacity at constant volume is given*

$$C_V = \frac{\delta Q_V}{dT} = \left(\frac{\partial U}{\partial T}\right)_V. \tag{13}$$

Definition 37 (Enthalpy)**.** *Let's define a new state function, the enthalpy H, as*

$$H = U + PV. \tag{14}$$

Proposition 2 (Heat capacity at constant pressure)**.** *For an infinitesimal isobaric reversible process, the heat capacity at constant pressure is given*

$$C_P = \frac{\delta Q_P}{dT} = \left(\frac{\partial H}{\partial T}\right)_P, \tag{15}$$

where H is the enthalpy.

Proof. For an infinitesimal process $dH = dU + PdV + VdP$, using the infinitesimal form of the first law Equation (10)

$$dH = \delta Q + VdP.$$

For a reversible, isobaric process

$$dH = \delta Q_P.$$

□

4.3.2 Calorimetry

If c is nearly constant over the temperature range, Equation (12) integrates to

$$Q = mc\,\Delta T. \tag{16}$$

Example 12 (Specific Heat of Water)**.** *It takes* 4186 *J to heat* 1 *kg of water from* $20^\circ C$ *to* $21^\circ C$*, so* $c = \frac{Q}{m\,\Delta T} = 4186$ *J/(kg K).*

Definition 38 (Calorimetry)**.** *Calorimetry is the measurement of an unknown specific heat by heat exchange with a standard substance of known specific heat, usually water, in a thermally insulated container.*

Example 13 (Specific Heat of a Metal)**.** *A metal of mass* m_m *at* T_m *is placed in water of mass* m_w *at* T_w*, and both reach* T_f*. By Black's principle, the heat lost by the metal equals the heat gained by the water:*

$$m_m c_m (T_m - T_f) = m_w c_w (T_f - T_w) \implies c_m = \frac{m_w c_w (T_f - T_w)}{m_m (T_m - T_f)}.$$

4.3.3 Latent Heat

Remark 21. *During a phase transformation at constant pressure, heat is absorbed or released with no change in temperature, so the heat capacity* $\frac{\delta Q}{dT}$ *is not defined (it would be infinite).*

Definition 39 (Latent Heat)**.** *The latent heat* L *is the heat per unit mass absorbed during a phase transformation at constant temperature and pressure:*

$$L = \frac{Q}{m}\left[\frac{J}{kg}\right]. \tag{17}$$

It is called the latent heat of fusion L_f *for melting and of vaporization* L_v *for boiling.*

Remark 22. *Since the transformation occurs at constant pressure,* $Q = \Delta H$ *(Equation (15)), so the latent heat is the enthalpy change per unit mass.*

4.4 Kinetic Theory of Gases

4.4.1 Pressure and Temperature of an Ideal Gas

4.4.2 Equipartition of Energy

4.4.3 Counting Quadratic Degrees of Freedom

4.4.4 Frozen-Out Degrees of Freedom

4.4.5 Heat Capacities from Equipartition

4.5 Ideal Gases and the First Law

An ideal gas obeys the equation of state $PV = nRT$ (Equation (1)). As a consequence of this equation of state, the internal energy is a function of temperature alone:

$$U = U(T). \tag{18}$$

4.5.1 Internal Energy of an Ideal Gas
4.5.2 Isothermal Processes
4.5.3 Adiabatic Processes
4.6 Rates of Processes
4.6.1 Heat Conduction
4.6.2 Viscosity
4.6.3 Diffusion
5 The Second Law of Thermodynamics
5.1 Carnot Cycles
5.1.1 Thermodynamic Cycles
5.1.2 The Carnot Cycle
5.2 Efficiency of an Engine
5.3 Statements of the Second Law
5.3.1 The Kelvin–Planck Statement
5.3.2 The Clausius Statement
5.3.3 Equivalence of the Two Statements
5.4 Carnot's Theorem
5.5 The Thermodynamic Temperature Scale
5.6 Engines and Refrigerators
5.6.1 Refrigerators
5.6.2 Heat Pumps
5.6.3 Internal Combustion Engines
5.6.4 The Steam Engine

6 Entropy

As previously mentioned, Sadi Carnot was the first to recognize that heat flowing from hot to cold can be used to produce work, but never all of it. The explanation behind this limit is entropy. The second law of thermodynamics can be restated in terms of entropy:

Law 3 (The Second Law of Thermodynamics (Entropy Formulation))**.** *the entropy of an isolated system never decreases with time. As a result, isolated systems evolve toward a thermodynamic equilibrium state where the entropy is maximized.*

6.1 The Clausius Inequality




Figure 4: Clausius' thought experiment: Carnot engines route all heat exchanged by the gas through a single reservoir at T_0.

Could an engine run on heat drawn from the surrounding air alone, without burning fuel?

Remark 23 (Clausius' Thought Experiment)**.** *Consider Figure 4. Heat $\delta Q_1 \frac{T_0}{T_1}$ flows from the principal reservoir (PR) at T_0 (e.g. the surrounding air) to an auxiliary reservoir at T_0. A Carnot engine takes this heat, transforms part of it into work, and transfers the rest, δQ_1, to an auxiliary reservoir at the gas's temperature T_1, which passes it to the gas, changing its state from (P_1, V_1, T_1) to (P_2, V_2, T_2). Each auxiliary reservoir gives exactly what it receives, so it ends unchanged. This continues until the gas is back at its original state. The question is whether heat from a single reservoir can thus be fully converted into work, with no other effect on the surroundings.*




Figure 5: The composite system exchanges heat only with the reservoir at T_0.

After a full cycle, everything in the composite system (Figure 5) is back to its original state, so $\Delta U = 0$ and the first law gives

$$W = Q = T_0 \sum_i \frac{\delta Q_i}{T_i}, \tag{19}$$

where $W = \sum_i \delta W_i$ is the total work done by the composite system (the opposite of our usual sign convention) and Q the heat drawn from T_0. A positive $W = Q$ is forbidden by:

Law 4 (Kelvin Statement of the Second Law of Thermodynamics)**.** *No process is possible whose sole result is the absorption of heat from a reservoir and the conversion of this heat into work.*

Hence $W = Q \leq 0$, and since $T_0 > 0$, taking the steps infinitesimal gives:

Law 5 (Clausius Inequality)**.** *For any cyclic process,*

$$\oint \frac{\delta Q}{T_{surr}} \leq 0, \tag{20}$$

where T_{surr} is the temperature of the auxiliary reservoirs supplying δQ_i (not of the system). If the cycle is reversible, $T_{surr} = T_{sys}$ and running it in reverse gives $\oint \frac{\delta Q}{T_{surr}} \geq 0$, so equality holds if and only if the cycle is reversible.

Remark 24. *Physically, an engine needs a hot source and a colder sink: a car takes heat from burning fuel, turns part of it into work, and dumps the rest into the colder air. With only one reservoir, there is nowhere to dump heat, so no net work is possible.*

6.2 Entropy

Suppose a system is taken along a reversible path Route_1 from an initial state i to a final state f and then back again to the initial state along another reversible path Route_2, completing a reversible cycle. Since the cycle is reversible, the Clausius inequality holds with equality:

$$\oint \frac{\delta Q_{\text{Route}}}{T} = \int_{i,\ \text{Route}_1}^{f} \frac{\delta Q_{\text{Route}}}{T} + \int_{f,\ \text{Route}_2}^{i} \frac{\delta Q_{\text{Route}}}{T} = 0,$$

therefore

$$\int_{i,\ \text{Route}_1}^{f} \frac{\delta Q_{\text{Route}}}{T} = -\int_{f,\ \text{Route}_2}^{i} \frac{\delta Q_{\text{Route}}}{T}.$$

Since Route_2 is reversible, traversing it from i to f instead flips the sign of every δQ, so $\int_{f,\ \text{Route}_2}^{i} = -\int_{i,\ \text{Route}_2}^{f}$ and

$$\int_{i,\ \text{Route}_1}^{f} \frac{\delta Q_{\text{Route}}}{T} = \int_{i,\ \text{Route}_2}^{f} \frac{\delta Q_{\text{Route}}}{T}.$$

The integral is the same along any reversible path between i and f, so it is path independent (depends only on the end states) and defines a state function.

Definition 40 (Entropy)**.** *The entropy S is the state function defined by*

$$\Delta S = S_f - S_i = \int_i^f \frac{\delta Q_{rev}}{T}, \tag{21}$$

where the integral is taken along any reversible path[4]*, for which $T_{sys} = T_{surr}$. Only entropy differences (ΔS) are defined, in units of J/K, using absolute temperature T in Kelvin. For an infinitesimal reversible process*

$$dS = \frac{\delta Q_{rev}}{T}. \tag{22}$$

Remark 25 (Entropy Change in Irreversible Processes)**.** *Since S is a state function, ΔS for an irreversible process equals ΔS along any reversible process between the same end states.*

Example 14 (Entropy Change of Heating Water)**.** *Consider heating water from T_i to T_f, isobarically, through a series of reservoirs, each at $T + dT$ when the water is at T. The heat entering the water reversibly at each step is*

$$\delta Q_{rev} = C_P\, dT,$$

[4]Irreversibility comes from the temperature gap between system and source. The source must be at $T + dT$ hotter than the system at every moment.

where C_P is the water's heat capacity at constant pressure. Hence, the entropy change of the water is

$$dS = \frac{\delta Q_{rev}}{T} = \frac{C_P\, dT}{T},$$

or, for constant C_P,

$$\Delta S = C_P \int_{T_i}^{T_f} \frac{dT}{T} = C_P \ln \frac{T_f}{T_i}. \tag{23}$$

Definition 41 (Isentropic)**.** *A process is isentropic if the entropy of the system stays constant, $dS = 0$ at every step.*

Remark 26 (Isentropic Conditions)**.** *A process that is both adiabatic ($\delta Q = 0$) and reversible is isentropic, since $dS = \frac{\delta Q_{rev}}{T} = 0$. An adiabatic but irreversible process increases the system's entropy.*

6.3 The Principle of Increasing Entropy

Proposition 3 (Clausius Inequality for a Process)**.** *For any process between equilibrium states i and f,*

$$\int_i^f \frac{\delta Q}{T_{surr}} \le \Delta S, \qquad \textit{or, infinitesimally,} \qquad \frac{\delta Q}{T_{surr}} \le dS,$$

where the equality holds if the process is reversible, and then $T = T_{surr}$.[5]

Proof. Consider a cycle consisting of an irreversible path i to f followed by a reversible path f to i. The Clausius inequality gives

$$\int_i^f \frac{\delta Q}{T_{\text{surr}}} + \int_{\substack{f\\R}}^{i} \frac{\delta Q}{T_{\text{surr}}} \le 0 \implies \int_i^f \frac{\delta Q}{T_{\text{surr}}} \le -\int_{\substack{f\\R}}^{i} \frac{\delta Q}{T_{\text{surr}}} = \int_{\substack{i\\R}}^{f} \frac{\delta Q}{T} = \Delta S,$$

where the last equality is the definition of entropy, since the path is reversible. □

For an isolated system $\delta Q = 0$, so $\Delta S \ge 0$:

Law 6 (Principle of Increasing Entropy)**.** *The entropy of a thermally isolated system increases in any irreversible process and is constant in a reversible process; it never decreases.*

Remark 27. *Applied to the universe (system plus surroundings), a process can occur spontaneously only if the total entropy increases or stays the same. The principle applies to net changes of the entire system: the entropy of a part of a composite system, or of a non-isolated system, can decrease.*

[5] Here δQ is the actual heat, not the heat of the imaginary reversible process used to calculate dS.




Figure 6: Although the entropy of a thermally isolated system can only increase or stay constant, the entropy of a part of the system can decrease.

Example 15. *Consider Figure 6, a system consisting of two subsystems which can exchange heat, the whole system being enclosed by adiabatic walls. If initially $T_A > T_B$, a small heat Q naturally flows from subsystem A to subsystem B. This reduces the entropy of subsystem A, $\Delta S_A = -\frac{Q}{T_A}$, while increasing the entropy of subsystem B, $\Delta S_B = \frac{Q}{T_B}$. But the total change is*

$$\Delta S = Q\left(\frac{1}{T_B} - \frac{1}{T_A}\right) > 0,$$

since $T_A > T_B$, so the entropy of the whole system increases.

Since the entropy of an isolated system can only increase, spontaneous changes continue until no further increase is possible, so equilibrium is reached when S is maximum.

Proposition 4 (Principle of Entropy Maximization)**.** *For a system that is thermally isolated from the surroundings, S tends to its maximum, whilst for a system that is totally isolated (thermally and mechanically), S tends to its maximum with U remaining constant.*

6.3.1 Entropy and the Arrow of Time

Remark 28 (Entropy and the Arrow of Time)**.** *Most physical laws are unchanged by replacing t with $-t$ (e.g. $F = m\frac{d^2\vec{r}}{dt^2}$), so they allow processes to run backward as well as forward. Yet a smashed teacup never reassembles itself: by the principle of increasing entropy (Law 6), the broken pieces have higher entropy than the unbroken cup. Entropy increase thus gives time its direction.*

6.4 Entropy–Temperature Diagrams

Remark 29. *The thermodynamic state of a system can be specified by any pair of independent state variables, for example on a PV diagram or a TS diagram.*

Remark 30 (Reversible Adiabats and Isotherms)**.** *By Equation (22), a reversible adiabatic process is isentropic, so on a TS diagram (with T vertical) it is a vertical line, while a reversible isothermal process is a horizontal line.*




Figure 7: TS diagram for a Carnot cycle: a rectangle of two isotherms and two adiabats.

Remark 31 (Area of a TS Cycle)**.** *Since $\delta Q_{rev} = T\,dS$, the area enclosed by a reversible cycle on a TS diagram is the net heat absorbed, $\oint T\,dS$, which by the first law equals the net work done by the system.*

6.5 The Thermodynamic Identity

Combining the first and second laws gives the most important equation in thermodynamics.

Proposition 5 (Thermodynamic Identity)**.** *The thermodynamic identity, or central equation of thermodynamics, states that for any process between equilibrium states,*

$$dU = T\,dS - P\,dV. \tag{24}$$

Proof. For a reversible process, substitute $\delta W = -PdV$ (Equation (6)) and $\delta Q = T\,dS$ (Equation (22)) into the first law (Equation (9)). Since the result involves only state functions, it holds between any two neighbouring equilibrium states, so for irreversible processes too. □

Remark 32. *The whole of thermodynamics is dependent on this equation, just as the whole of mechanics is dependent on Newton's laws.*

6.6 Other Examples of Entropy Calculations

6.6.1 Free Expansion of an Ideal Gas

Free expansion (Definition 28) is irreversible, so to apply Equation (21) we imagine a reversible isothermal expansion between the same end states, e.g. letting the gas expand slowly in thermal contact with a reservoir at T. Since T is constant, $dU = C_V\,dT = 0$ for an ideal gas, so the first law and $PV = nRT$ give

$$dS = \frac{\delta Q_{\text{rev}}}{T} = \frac{dU + P\,dV}{T} = \frac{nR}{V}\,dV \implies \Delta S = nR\int_{V_i}^{V_f}\frac{dV}{V} = nR\ln\frac{V_f}{V_i},$$

which gives $\Delta S = nR \ln 2$ when the volume doubles.

Remark 33. *Although $Q = 0$ in the actual free expansion, $\Delta S > 0$, as expected for an adiabatic irreversible process.*

6.6.2 Entropy of an Ideal Gas in General

For an ideal gas, $U = U(T)$, since there are no intermolecular forces, so $dU = C_V\, dT$. The thermodynamic identity (Equation (24)) and the ideal gas law (Equation (1)) give

$$T\, dS = C_V\, dT + P\, dV = C_V\, dT + \frac{nRT}{V}\, dV.$$

Dividing by nT and using molar quantities, $s = S/n$, $c_v = C_V/n$ and $v = V/n$,

$$ds = \frac{c_v}{T}\, dT + \frac{R}{v}\, dv.$$

For constant c_v, integrating from a reference state (T_0, v_0), usually taken at standard temperature and pressure ($T_0 = 273.15$ K, $P_0 = 101.325$ kPa), gives

$$s = c_v \ln \frac{T}{T_0} + R \ln \frac{v}{v_0} + s_0, \tag{25}$$

where s_0 is the molar entropy of the reference state, which cancels when entropy differences are taken.

6.6.3 Entropy Change of the Universe when Heating Water

Example 16 (Single-Stage Heating)**.** *Heating water from $T_i = 293$ K on a reservoir at $T_f = 373$ K, the reservoir loses $Q = C_P(T_f - T_i)$ at constant temperature T_f, so*

$$\Delta S_{universe} = \Delta S_{water} + \Delta S_{reservoir},$$

where ΔS_{water} comes from Equation (23), so

$$\Delta S_{universe} = C_P \left[\ln \frac{T_f}{T_i} - \frac{T_f - T_i}{T_f} \right] = C_P(0.241 - 0.214) = 0.027\, C_P > 0.$$

The water's entropy gain only slightly exceeds the reservoir's loss, but no choice of parameters makes the total negative.

Example 17 (Two-Stage Heating)**.** *Heating in two stages, first on a reservoir at 323 K, then at 373 K, leaves ΔS_{water} unchanged (same end states), while*

$$\Delta S_{universe} = C_P \left[\ln \frac{373}{293} - \frac{323 - 293}{323} - \frac{373 - 323}{373} \right] = 0.014\, C_P,$$

about half.

Remark 34. *More stages bring the process closer to reversibility.*

Example 18 (Reversible Heating with a Carnot Engine)**.** *An infinitesimal Carnot engine runs between the reservoir at $T_f = 373\ K$ and the water at T, with cycles so small that only differential heat and work are exchanged per cycle. To deliver $\delta Q_2 = C_P\, dT$ to the water, it draws $\delta Q_1 = \frac{T_f}{T}\, \delta Q_2$ from the reservoir and outputs work δW. Then*

$$\Delta S_{reservoir} = -\int_{T_i}^{T_f} \frac{\delta Q_1}{T_f} = -\int_{T_i}^{T_f} \frac{C_P\, dT}{T} = -C_P \ln \frac{T_f}{T_i} = -\Delta S_{water},$$

so $\Delta S_{universe} = 0$, as it must be for a reversible process.

7 Statistical Mechanics

Remark 35. *Many thermodynamic processes happen in one direction but never the reverse, because every irreversible process increases the total entropy. Classical thermodynamics states this but does not explain why; statistical mechanics does.*

Definition 42 (Statistical Thermodynamics)**.** *Statistical thermodynamics is the study of how systems store energy, by counting all the ways that energy can be arranged among their constituents.*

Definition 43 (Combinatorics)**.** *Combinatorics is the mathematics of counting ways of arranging things.*

7.1 Introduction to Probability and Statistics

Definition 44 (Microstate)**.** *A microstate is a specific configuration of the particles in a system.*

Definition 45 (Macrostate)**.** *A macrostate is a description of the system in terms of macroscopic properties, such as temperature, pressure, and volume. Different macrostates can be distinguished by a measurement, while different microstates of the same macrostate cannot.*

Definition 46 (Multiplicity)**.** *The multiplicity Ω of a macrostate is the number of microstates corresponding to it. For N two-state particles, the multiplicity of the macrostate with n particles in one of the two states is the binomial coefficient*

$$\Omega(N, n) = \binom{N}{n} = \frac{N!}{n!(N-n)!}. \tag{26}$$

Example 19 (Three Coins)**.** *Flipping three distinguishable fair coins gives $2^3 = 8$ equally probable microstates (e.g. HHT). The macrostate is the number of heads: $\Omega(3) = 1$ (HHH), while $\Omega(2) = 3$ (HHT, HTH, THH). Knowing the microstate gives the macrostate, but not the reverse.*

Definition 47 (Probability of a macrostate)**.** *Assuming all microstates are equally probable, the probability of a macrostate is its multiplicity divided by the total number of microstates:*

$$P(n) = \frac{\Omega(n)}{\sum_i \Omega(i)}. \tag{27}$$

Proposition 6 (Total Amount of Microstates)**.** *There are $N+1$ macrostates and 2^N microstates in total:*

$$\sum_{n=0}^{N} \binom{N}{n} = 2^N. \tag{28}$$

7.1.1 The Multiplicity Function

Definition 48 (Mean of a Binomial Distribution)**.** *For N independent trials, each succeeding with probability p, the mean number of successes is*

$$\bar{n} = Np.$$

Definition 49 (Variance of a Binomial Distribution)**.** *The variance measures the spread of a distribution around its mean, $\sigma^2 = \overline{(n-\bar{n})^2}$. For a binomial distribution,*

$$\sigma^2 = Np(1-p).$$

Definition 50 (Standard Deviation)**.** *The standard deviation is the square root of the variance,*

$$\sigma = \sqrt{Np(1-p)}.$$

For fair coins, $p = \frac{1}{2}$, so $\bar{n} = \frac{N}{2}$, $\sigma^2 = \frac{N}{4}$, and the standard deviation normalized to the number of coins is

$$\frac{\sigma}{N} = \frac{1}{2\sqrt{N}}.$$

Remark 36. *The normalized multiplicity function gets narrower as N increases, becoming sharply peaked at $n = \frac{N}{2}$.*

7.2 Microscopic View of Entropy

7.2.1 The Two-State Paramagnet

Definition 51 (Paramagnet)**.** *A paramagnet is a material whose constituent particles act like tiny magnetic dipoles, due to 'unpaired' electrons or atomic nuclei, which tend to align parallel to any externally applied magnetic field and do not interact significantly with neighbouring dipoles.*

Definition 52 (Dipoles)**.** *Here, dipoles are the individual magnetic particles, which can be single electrons, groups of electrons in an atom, or atomic nuclei.*

Remark 37 (Two-State Paramagnet)**.** *Quantum mechanics limits the projection of each dipole onto the axis defined by $\vec{B}$ to only two states:*

- *Up state: aligned with $\vec{B}$.*
- *Down state: anti-aligned with $\vec{B}$.*

Definition 53 (M-Meter)**.** *An M-meter measures the magnetization M of the material, proportional to $N_\uparrow - N_\downarrow$, the paramagnet's analogue of a "heads meter" for coins.*

Remark 38. *In zero (or weak) $\vec{B}$, the up/down state of each dipole is effectively an independent 50/50 'coin toss', so we expect to measure $M = 0$ ($N_\uparrow = N_\downarrow = \frac{N}{2}$).*

This system has one macrostate for each possible value of $N_\uparrow$, from 0 to N. The multiplicity of each macrostate is

$$\Omega(N_\uparrow) = \binom{N}{N_\uparrow} = \frac{N!}{N_\uparrow!\, N_\downarrow!}.$$

7.2.2 The Einstein Solid

Consider a collection of microscopic systems that can each store any number of energy "units", all of the same size.

Definition 54 (Quantum Harmonic Oscillator)**.** *A quantum harmonic oscillator is a particle in a potential $\frac{1}{2}k_s x^2$, where k_s is the "spring constant".*

Remark 39. *Its allowed energies are equally spaced by hf, where $h = 6.63 \times 10^{-34}$ J s is Planck's constant and $f = \frac{1}{2\pi}\sqrt{\frac{k_s}{m}}$ is its natural frequency.*

Example 20. *Examples of quantum oscillators include the vibrational motions of diatomic and polyatomic gas molecules, and the oscillation of atoms in a solid.*

Definition 55 (Einstein Solid)**.** *An Einstein solid is a model of a solid as a collection of N identical, independent quantum harmonic oscillators. Each atom oscillates in three independent directions, so N oscillators correspond to $N/3$ atoms.*




Figure 8: Schematic of an Einstein solid: atoms connected by springs.

Proposition 7 (Multiplicity of an Einstein Solid)**.** *The multiplicity of an Einstein solid with N oscillators and q units of energy is*

$$\Omega(N,q) = \binom{q+N-1}{q} = \frac{(q+N-1)!}{q!\,(N-1)!}. \tag{29}$$

Proof. Represent each energy unit by a dot and separate the N oscillators by $N-1$ dividers[6], e.g. $\bullet|\ \bullet\bullet|\,|\bullet$ for $N=4$, $q=4$. Each microstate is an arrangement of q dots and $N-1$ lines, so Ω is the number of ways to choose which q of the $q+N-1$ symbols are dots. □

Example 21 (Three Oscillators)**.** *For $N=3$, with energy in units of hf,*

$$\Omega(3,0)=1, \qquad \Omega(3,1)=3, \qquad \Omega(3,2)=6, \qquad \Omega(3,3)=10.$$

7.2.3 Interacting Systems

Consider two Einstein solids, A and B, that can exchange energy. They are weakly coupled: energy flows between them much more slowly than within each solid.

Remark 40. *On short time scales, U_A and U_B are effectively fixed, and a macrostate of the combined system is specified by them. On longer time scales, energy flows between the solids and U_A, U_B change, with only U_A+U_B fixed.*

Since the two solids are independent, for each of the Ω_A microstates of A there are Ω_B microstates of B, so the multiplicity of a macrostate of the combined system is

$$\Omega_{\text{total}} = \Omega_A\,\Omega_B. \tag{30}$$

Example 22 (Two Solids of Three Oscillators)**.** *For $N_A=N_B=3$ and $q_A+q_B=6$, there are seven macrostates, $q_A=0,1,\ldots,6$[7] (Table 1). The most likely is $q_A=q_B=3$, the energy shared equally.*

q_A	Ω_A	q_B	Ω_B	$\Omega_{\text{total}}=\Omega_A\Omega_B$
0	1	6	28	28
1	3	5	21	63
2	6	4	15	90
3	10	3	10	100
4	15	2	6	90
5	21	1	3	63
6	28	0	1	28
			Total	$462=\binom{6+6-1}{6}$

Table 1: Macrostates of two Einstein solids with $N_A=N_B=3$ sharing $q=6$ units of energy.

[6] The lines/dividers are just a bookkeeping trick to mark where one oscillator's energy ends and the next one's begins.

[7] q_A can be anything from 0 to 6, as long as q_B makes up the rest: $q_B=6-q_A$. So $q_A=6$ just means solid A has all the energy and $q_B=0$.

Principle 3 (Fundamental Assumption of Statistical Mechanics)**.** *In an isolated system in thermal equilibrium, all accessible microstates are equally probable.*[8]

Principle 4 (Principle of Detailed Balance)**.** *At the microscopic level, we expect that any process that would take the system from state X to state Y is reversible, so that the system can just as easily go from state Y to state X.*

Remark 41. *If we invoke the fundamental assumption for our system of two small Einstein solids (Example 22), we can immediately conclude that, while all 462 microstates are equally probable, some macrostates are more probable than others.*

Example 23. *The chance of finding the system in the fourth macrostate (with three energy units in each solid) is 100/462, while the chance of finding it in the first macrostate (with all the energy in solid B) is only 28/462.*

Remark 42. *If all the energy is in solid B initially, and we wait a while, chances are we'll find the energy distributed more evenly later on because the macrostates associated with a more even sharing of the total energy between A and B are more probable (they are associated with a larger number of the equally probable microstates; their multiplicity is larger)*

Example 24. *Take two Einstein solids with* $N_A = 300$*,* $N_B = 200$ *and* $q_{total} = 100$*, giving* 101 *macrostates. What matters is not that the multiplicities are large, but that their ratios are: the most likely macrostate,* $q_A = 60$*, is more than* 10^{33} *times more probable than the least likely,* $q_A = 0$*. With* $\Omega_{total}(all) = 9.3 \times 10^{115}$*, the probability of* $q_A = 60$ *is about* 7%*, of* $q_A < 30$ *or* $q_A > 90$ *less than one in a million, and of* $q_A < 10$ *less than* 10^{-20}*. Since the universe is about* 4×10^{17} *s old, you would need to check the system a hundred times per second for the age of the universe to have a decent chance of ever seeing* $q_A < 10$*.*

Remark 43. *Suppose the system in Example 24 starts with* q_A *much less than* 60*, e.g. all the energy in solid B. After the energy has had time to rearrange itself, we are almost certain to find that energy has flowed from B to A. The system is irreversible: energy flows spontaneously from B to A, but essentially never back.*

Remark 44. *This is the physical explanation of the spontaneous flow of heat: it is a probabilistic phenomenon.*

Principle 5 (Law of Increase of Multiplicity)**.** *The spontaneous flow of energy stops when a system is at, or very near, its most likely macrostate, the one with the greatest multiplicity.*

Remark 45. *Principle 5 is a version of the second law of thermodynamics. It is not a fundamental law, just a very strong statement about probabilities.*

[8] Assume that the interactions among oscillators are strong enough to allow the exchange of energy, but too weak to have much effect on the energy levels themselves.

7.2.4 Large Systems

Remark 46 (Stirling's Approximation)**.** *For $N \gg 1$, factorials are evaluated with Stirling's approximation:*

$$N! \approx N^N e^{-N}\sqrt{2\pi N}, \qquad \ln N! \approx N\ln N - N. \tag{31}$$

Proposition 8 (Multiplicity of a Large Einstein Solid)**.** *For an Einstein solid with $N \gg 1$ and $q \gg N$ (many more energy units than oscillators, the "high-temperature" limit),*

$$\Omega(N,q) \approx \left(\frac{eq}{N}\right)^N. \tag{32}$$

The proof of this proposition can be seen in Appendix A.2.

Remark 47. *For two large interacting Einstein solids with $N_A = N_B = N$, the multiplicity of any macrostate is*

$$\Omega = \Omega_A\Omega_B = \left(\frac{eq_A}{N}\right)^N\left(\frac{eq_B}{N}\right)^N = \left(\frac{e}{N}\right)^{2N}(q_Aq_B)^N. \tag{33}$$

Remark 48. *Graphing Equation (33) shows a very sharp peak at $q_A = \frac{q}{2}$, where $q = q_A + q_B$, i.e. the energy shared equally. The height of this peak is*

$$\Omega_{\max} = \left(\frac{e}{N}\right)^{2N}\left(\frac{q}{2}\right)^{2N}.$$

To see the shape near the peak, set

$$q_A = \frac{q}{2} + x, \qquad q_B = \frac{q}{2} - x,$$

with $|x| \ll q$. Plugging into Equation (33),

$$\Omega = \left(\frac{e}{N}\right)^{2N}\left[\left(\frac{q}{2}\right)^2 - x^2\right]^N.$$

Taking the logarithm and using $\ln(1-\epsilon) \approx -\epsilon$ for $\epsilon = \left(\frac{2x}{q}\right)^2 \ll 1$,

$$\ln\left[\left(\frac{q}{2}\right)^2 - x^2\right] = \ln\left(\frac{q}{2}\right)^2 + \ln\left[1 - \left(\frac{2x}{q}\right)^2\right] \approx \ln\left(\frac{q}{2}\right)^2 - \left(\frac{2x}{q}\right)^2,$$

so, exponentiating,

Remark 49. *The multiplicity's peak becomes a Gaussian:*

$$\Omega \approx \Omega_{\max}\, e^{-N(2x/q)^2}.$$

Remark 50. *The peak falls to $\frac{1}{e}$ of its maximum when $N\left(\frac{2x}{q}\right)^2 = 1$, i.e. at*

$$x = \frac{q}{2\sqrt{N}}, \qquad \frac{x}{q} = \frac{1}{2\sqrt{N}}.$$

7.2.5 Thermodynamic Limit

Remark 51. *Typical fluctuations in the energy are only about $\frac{1}{\sqrt{N}}$ times the most likely value, $\frac{q}{2}$. For $N \sim 10^{20}$, seeing a one-standard-deviation fluctuation would require measuring a solid's energy to ten significant figures, so fluctuations away from the most likely macrostate are unmeasurable.*

Once a large system reaches thermal equilibrium, we can therefore assume it is in its most likely macrostate.

Definition 56 (Thermodynamic Limit)**.** *The thermodynamic limit is reached when a system is large enough that measurable fluctuations away from the most likely macrostate never occur.*

7.2.6 Entropy as Multiplicity

From the discussion of large systems above:

Proposition 9 (Equilibrium Macrostate)**.** *Any large system in equilibrium will be found in the macrostate with the greatest multiplicity, aside from fluctuations normally too small to measure.*

Multiplicities are huge numbers, so it is easier to work with their logarithm, which also turns the product $\Omega_A \Omega_B$ of a combined system into a sum.

Definition 57 (Entropy)**.** *In statistical thermodynamics, entropy is defined as*

$$S \equiv k \ln \Omega, \tag{34}$$

where $k = 1.381 \times 10^{-23}$ J/K is Boltzmann's constant, which gives S its units since Ω is dimensionless.

Thus entropy is a measure of multiplicity, and the Law of Increase of Multiplicity becomes: entropy tends to increase.

Example 25 (Entropy of a Large Einstein Solid)**.** *For an Einstein solid with $q \gg N$, Equation (32) gives*

$$S = k \ln \left(\frac{eq}{N}\right)^N = Nk \left[\ln \frac{q}{N} + 1\right].$$

For $N = 10^{22}$ and $q = 10^{24}$, $S \approx 0.77$ J/K.

Remark 52 (Entropy as Disorder)**.** *Entropy is often described as disorder. This works for a deck of cards: shuffling increases entropy, since the "sorted" macrostate has multiplicity 1 while a "random shuffle" macrostate has a much higher one. But it fails elsewhere: crushed ice looks more disorderly than the same amount of water, yet water has much higher entropy, since its molecules can move freely and have far more microstates. Entropy is best thought of as multiplicity, not disorder.*

Proposition 10 (Entropy of a Composite System)**.** *If the macrostates of systems A and B are specified separately, the total entropy of the composite system is the sum of their entropies:*

$$S_{total} = S_A + S_B. \tag{35}$$

Proof. By Equations (30) and (34),

$$S_{\text{total}} = k \ln \Omega_{\text{total}} = k \ln(\Omega_A \Omega_B) = k \ln \Omega_A + k \ln \Omega_B = S_A + S_B.$$

□

Remark 53. *For small N, the energy split between A and B fluctuates, so Ω_{total} must be summed over all possible splits, $\Omega_{total} = \sum \Omega_A \Omega_B$. In the thermodynamic limit, the most likely split dominates this sum, $\Omega_{total} \approx \Omega_{A,\max} \Omega_{B,\max}$, so each subsystem has a well-defined entropy and $S_{total} = S_A + S_B$ holds.*

Since the natural logarithm is a monotonically[9] increasing function of its argument, a macrostate with higher multiplicity also has higher entropy. Any large system in equilibrium is therefore in its macrostate of greatest entropy, and by extension:

Law 7 (Second Law of Thermodynamics (Statistical Form))**.** *Spontaneous, irreversible processes increase the total entropy, i.e. the total multiplicity, of the universe.*

7.2.7 Maxwell's Demon

In 1867, Maxwell noted that the speed distribution of gas molecules might provide a way to defeat the second law: could an agent intervening at the microscopic level reduce entropy?

Remark 54 (Maxwell's Demon)**.** *A vessel of gas is divided into two parts, A and B, by a wall with a small hole. A being (Maxwell's demon) who can see individual molecules opens and closes the hole so that only fast molecules pass from A to B, and only slow ones from B to A. Without doing work, it would raise the temperature of B and lower that of A, contradicting the second law.*

Remark 55. *The second law survives once the demon itself is included. To sort molecules, it must remember their speeds; with a finite memory, it must keep erasing old data, and erasing information always releases entropy (at least $k \ln 2$ per bit, Landauer's principle). This outweighs the entropy it removes from the gas, linking entropy to information.*

Remark 56 (Entropy and Information)**.** *Knowing only the macrostate, we don't know which of its Ω microstates the system is in. Finding out would take $\log_2 \Omega$ yes/no answers (bits), so*

$$S = k \ln \Omega = (k \ln 2) \log_2 \Omega :$$

[9] Meaning it always increases.

entropy measures this missing information about the microstate.[10]

7.3 Ideal Gases

Remark 57. *An ideal gas has its multiplicity depend on its volume as well as its totl energy and number of particles. When the gases interact, they can often expand and contract and even exchange molecules in addtion to exchanging energy.*

7.3.1 Multiplicity of an Ideal Gas

Consider a single gas atom with kinetic energy U in a container of volume V.

Definition 58 (Momentum Space)**.** *Momentum space is an imaginary space whose axes are p_x, p_y, p_z; each point corresponds to a momentum vector of the particle.*

The multiplicity should be proportional to V, since twice the volume offers twice as many positions, and to the number of allowed momentum vectors:

$$\Omega_1 \propto V \cdot V_p,$$

where V_p is the "volume" of accessible momentum space and the subscript 1 is for a single molecule. Since the kinetic energy is

$$U = \frac{1}{2}m\left(v_x^2 + v_y^2 + v_z^2\right) = \frac{1}{2m}\left(p_x^2 + p_y^2 + p_z^2\right),$$

the allowed momenta satisfy $p_x^2 + p_y^2 + p_z^2 = 2mU$: a sphere in momentum space of radius $\sqrt{2mU}$, so V_p is the surface area of this sphere.

To count microstates we need quantum mechanics.

Principle 6 (Heisenberg Uncertainty Principle)**.** *A particle's wavefunction is spread out in both position and momentum space; the narrower it is in one, the wider it must be in the other:*

$$(\Delta x)(\Delta p_x) \approx h, \tag{36}$$

where h is Planck's constant.

The number of independent wavefunctions is therefore finite when the available position and momentum space are limited. In one dimension, there are $\frac{L}{\Delta x}$ distinct position states and $\frac{L_p}{\Delta p_x}$ distinct momentum states, so

$$\Omega_1 = \frac{L}{\Delta x} \cdot \frac{L_p}{\Delta p_x} = \frac{LL_p}{h}.$$

[10] Not covered in this course; this connection is developed in information theory (Shannon entropy).

In three dimensions, lengths become volumes:

$$\Omega_1 = \frac{V V_p}{h^3}. \tag{37}$$

For N molecules, the total kinetic energy is the sum over all $3N$ momentum components:

$$\sum_{i=1}^{N} \left(p_{ix}^2 + p_{iy}^2 + p_{iz}^2\right) = 2mU,$$

the surface of a $3N$-dimensional "hypersphere" of radius $\sqrt{2mU}$ in momentum space. Since interchanging two identical molecules does not give a distinct state, counting them as distinguishable overcounts by $N!$, so

$$\Omega_N = \frac{1}{N!}\frac{V^N}{h^{3N}} \times (\text{area of momentum hypersphere}). \tag{38}$$

Remark 58 (Area of a Hypersphere)**.** *The surface area of a d-dimensional hypersphere of radius r is*

$$A = \frac{2\pi^{d/2}}{\left(\frac{d}{2}-1\right)!}\, r^{d-1}.$$

Proposition 11 (Multiplicity of a Monatomic Ideal Gas)**.** *For $N \gg 1$ indistinguishable molecules of mass m with total energy U in volume V,*

$$\Omega_N \approx \frac{1}{N!}\frac{V^N}{h^{3N}}\frac{\pi^{3N/2}}{\left(\frac{3N}{2}\right)!}\left(\sqrt{2mU}\right)^{3N}, \tag{39}$$

so that

$$\Omega(U, V, N) = f(N)\, V^N U^{3N/2}. \tag{40}$$

Proof. Substitute the hypersphere area with $d = 3N$ and $r = \sqrt{2mU}$ into Equation (38), dropping factors that are negligible next to Ω for large N. □

7.3.2 Entropy of an Ideal Gas

Proposition 12 (Sackur–Tetrode Equation)**.** *The entropy of a monatomic ideal gas of N molecules of mass m, with energy U in volume V, is*

$$S = Nk\left[\ln\left(\frac{V}{N}\left(\frac{4\pi mU}{3Nh^2}\right)^{3/2}\right) + \frac{5}{2}\right]. \tag{41}$$

Proof. Take the logarithm of Equation (39), apply Stirling's approximation (Equation (31)) to $N!$ and $\left(\frac{3N}{2}\right)!$, and drop factors that are merely large. □

Remark 59. *At fixed U and N, $\Delta S = Nk \ln \frac{V_f}{V_i}$, the same result as the classical free expansion calculation.*

7.3.3 Entropy of Mixing

8 The Thermodynamic Potentials and the Maxwell Relations

8.1 Thermodynamic Potentials

8.2 Internal Energy

8.3 Enthalpy

8.4 Helmholtz Function

8.4.1 Maximum Work

8.4.2 Equilibrium at Constant Volume

8.5 Gibbs Function

8.5.1 Equilibrium at Constant Pressure

8.5.2 Useful Work

8.6 The Thermodynamic Square

8.7 Example Using a Maxwell Relation

A Proofs

A.1 Inexact differentials

Proof. For work, $\delta W = -P dV$. Take two paths between the same states (P_1, V_1) and (P_2, V_2), with $P_1 \neq P_2$. Along path A, expand at P_1, then change pressure at constant V_2 (no work):

$$W_A = -P_1(V_2 - V_1).$$

Along path B, change pressure at constant V_1 (no work), then expand at P_2:

$$W_B = -P_2(V_2 - V_1).$$

Same end states, but $W_A \neq W_B$. In general, for an ideal gas write $\delta W = M\,dV + N\,dT$ with $M = -\frac{nRT}{V}$ and $N = 0$. Exactness would require $\left(\frac{\partial M}{\partial T}\right)_V = \left(\frac{\partial N}{\partial V}\right)_T$, but

$$\left(\frac{\partial M}{\partial T}\right)_V = -\frac{nR}{V} \neq 0 = \left(\frac{\partial N}{\partial V}\right)_T,$$

so no function $W(V, T)$ satisfies $dW = \delta W$. Since dU is exact, $\delta Q = dU - \delta W$ is then inexact too. □

A.2 Multiplicity of a Large Einstein Solid

Proof. Start from the exact formula, Equation (29):

$$\Omega(N, q) = \frac{(q + N - 1)!}{q!\,(N - 1)!} \approx \frac{(q + N)!}{q!\,N!},$$

since replacing $N - 1$ by N changes Ω only by a factor of order N, negligible compared to the huge number Ω. Taking the logarithm and using Stirling's approximation, Equation (31),

$$\ln \Omega \approx (q + N) \ln(q + N) - q \ln q - N \ln N,$$

since the linear terms cancel. As $N/q \ll 1$, the Taylor expansion $\ln(1 + x) \approx x$ for $|x| \ll 1$ gives

$$\ln(q + N) = \ln q + \ln\left(1 + \frac{N}{q}\right) \approx \ln q + \frac{N}{q}.$$

Substituting,

$$\ln \Omega \approx N \ln \frac{q}{N} + N + \frac{N^2}{q} \approx N \ln \frac{q}{N} + N,$$

since $\frac{N^2}{q} \ll N$. Exponentiating, $\Omega \approx e^{N \ln(q/N)}\, e^N = \left(\frac{eq}{N}\right)^N$. □

B Useful Links