Front pant pattern example

Curves pass through the calculated measurement stations. Values match the built-in test draft.

WAIST 32″	SEAT 40″	BAND 1.5″	DEPTH 12″
TOTAL LENGTH 42″	HEM 8″	FRONT RISE 12.5″	FABRIC WIDTH 30″



FRONT PANEL

Calculated dimensions, inches

Waist-edge allocation	7.75″
Seat width	10″
Width to crotch point	12.25″
Crotch to knee / point 1	12″
Point 1 width	7.65″
Point 1 to point 2	9″
Point 2 width	7.2″
Point 2 to hem	9″
Hem width	7.2″
Panel outseam height	40.5″
Cutting envelope width	13.375″

LEVELS FROM WAIST ATTACHMENT

Seat level	7.875″
Crotch level	10.5″
Leg span	30″
Knee below crotch	12″
Point 1 to point 2	9″
Point 2 to hem	9″

LEG SHARE
45%

FRONT RISE
12.5″ curved-seam reference, not vertical depth.

CUT WIDTH
12.25″ max + 5/8″ in + 1/2″ out.

CUTTING ALLOWANCES

Waist 1/2″ · Inseam 5/8″ · Outseams 1/2″

Front rise straight 1/4″ · curved 1/2″

Hem turn-up 1″ · all allowances outside lines

Curves are illustrative between measured stations. Check final seam length and fit on your draft.

Back pant pattern example

Curves pass through the calculated measurement stations. Values match the built-in test draft.

WAIST 32″	SEAT 40″	BAND 1.5″	DEPTH 12″
TOTAL LENGTH 42″	HEM 8″	FRONT RISE 12.5″	FABRIC WIDTH 30″



BACK PANEL

Calculated dimensions, inches

Waist-edge allocation	8.25″
Seat width	10″
Width to crotch point	14.5″
Seat offset reference	1.125″
Crotch to knee / point 1	12″
Point 1 width	9.35″
Point 1 to point 2	9″
Point 2 width	8.8″
Point 2 to hem	9″
Hem width	8.8″
Panel outseam height	40.5″
Cutting envelope width	15.625″

LEVELS FROM WAIST ATTACHMENT

Seat level	7.875″
Crotch level	10.5″
Leg span	30″
Knee below crotch	12″
Point 1 to point 2	9″
Point 2 to hem	9″

LEG SHARE
55%

FORK FORMULA
Q = 40 ÷ 8 – 0.5 = 4.5″; offset = Q ÷ 4.

FRONT RISE
12.5″ curved-seam reference, not vertical depth.

CUT WIDTH
14.5″ max + 5/8″ in + 1/2″ out.

CUTTING ALLOWANCES

Waist 1/2″ · Inseam 5/8″ · Outseams 1/2″

Front rise straight 1/4″ · curved 1/2″

Hem turn-up 1″ · all allowances outside lines

Curves are illustrative between measured stations. Check final seam length and fit on your draft.