Example pattern worksheet

Calculator example values, with front and back panel references.

INPUTS & SHARED LEVELS

Waist target	**32″**
Full seat target	**40″**
Band height	**1.5″**
Vertical crotch depth	**12″**
Total length, includes band	**42″**
Flat hem opening, one hem	**8″**
Curved front-rise target	**12.5″**
Fabric width, selvedge to selvedge	**30″**
Front / back leg share	**45% / 55%**
Seat level below band	**7.875″**
Crotch level below band	**10.5″**
Knee position below crotch	**12″**
Point 1 to point 2	**9″**
Point 2 to hem	**9″**
Cut length with waist + hem allowances	**42″**

FRONT PANEL



Reference sketch

FRONT STITCHING-LINE VALUES

Waist edge allocation	**7.75″**
Seat width	**10″**
Width to crotch point	**12.25″**
Crotch → knee / point 1	**12″**
Point 1 width	**7.65″**
Point 1 → point 2	**9″**
Point 2 width	**7.2″**
Point 2 → hem	**9″**
Hem width	**7.2″**
Cutting envelope width	**13.375″**

Blank knee width uses hem + ½″. Front values preserve the 45% leg share.

Sketch proportions are illustrative.

Back panel & finish

Matching back values from the same 32″ waist / 40″ seat example.

BACK STITCHING-LINE VALUES

Waist edge allocation	**8.25″**
Seat width	**10″**
Width to crotch point	**14.5″**
Seat offset reference	**1.125″**
Crotch → knee / point 1	**12″**
Point 1 width	**9.35″**
Point 1 → point 2	**9″**
Point 2 width	**8.8″**
Point 2 → hem	**9″**
Hem width	**8.8″**
Cutting envelope width	**15.625″**
Panel outseam height	**40.5″**

BACK PANEL



CUTTING ALLOWANCES USED BY THE CALCULATOR

Inseam ■″ · Waist ½″ · Front outseam ½″ · Back outseam ½″

Front rise straight ¼″ · Front rise curve ½″ · Hem turn-up 1″

Allowances sit outside stitching-line targets. Curves and seam matching still need a manual draft check. This worksheet is a measurement example, not a tiled cutting pattern.

For the example proportions: Q = 40 ÷ 8 – 0.5 = 4.5″. Front extension = 2.25″. Back extension = 4.5″.

Front waist 7.75″ + back waist 8.25″, two of each, totals 32″ before manual shaping.