





USER GUIDE

Fairpot

Split shared expenses fairly — in any currency.

Record a bill with all its receipts, see what each person owes in the expense's currency and in your home currency, and send everyone the split in one tap.



Version 0.5.2 · iPhone and iPad
October 2026

Contents

1 Welcome to Fairpot

What it does and how it thinks

2 First launch: the Terms of Use

Accepting the terms unlocks the app

3 Finding your way around

The three screens

4 Recording an expense

Description, people, currency and receipts

5 Exchange rates

Where rates come from and how they are locked

6 Saving

What “Saved” really means

7 Sharing a split

Send everyone what they owe

8 History

Look back, share again, edit or delete

9 Summary

Totals by category, month and year

10 Settings

Help, home currency, payment methods and categories

11 Backup and restore

Keep a copy outside the app

12 Terms and privacy

What Fairpot keeps, and where

13 Troubleshooting

Common questions, quick answers

14 Quick reference

Everything on one page

Welcome to Fairpot

What it does and how it thinks

Fairpot is for the moments when one person pays and everyone else owes a share: a dinner out, groceries for a weekend at the cottage, gas for a road trip, a hotel room on holiday.

About the pictures

Every picture is a real Fairpot screen. Orange numbered dots point to the parts described beside it. The example data — a dinner in Makati for four people, paid in Philippine pesos — is invented for this guide, and so are the payment details shown.

The ideas behind it

An expense is one shared bill. It has a description, a date, the number of people splitting it and a currency.

Receipts are the parts of an expense. A restaurant bill might have food, drinks and a tip — each a receipt with its own category, amount and, if you like, a photo.

People splitting is everyone who shares the bill, including you. Fairpot divides the total evenly between them.

Two currencies. Each expense is recorded in the currency you paid in. Fairpot also shows every amount in your **home currency** (Canadian dollars unless you change it), so totals and summaries always add up in one currency.

Private by design

Fairpot has no account, no sign-in, no advertising and no tracking. Everything you enter is kept only on your device. The only thing Fairpot downloads is a table of exchange rates, once a day.


Fairpot is free

There are no fees, subscriptions or in-app purchases.

First launch: the Terms of Use

Accepting the terms unlocks the app

The very first time you open Fairpot, it shows its Terms of Use. Nothing else starts until you accept them — not even the exchange-rate download.



1 The title

Fairpot Terms of Use, shown in large text.

2 Version and date

The version of the terms and when it took effect.

3 What is asked of you

You must accept the terms to use Fairpot.

4 The terms

Eleven short sections. Scroll down to read them all.

Accepting

Fairpot.

9. Changes to these terms

We may change these terms in a later version of Fairpot. If we do, Fairpot will show you the new terms and ask you to accept them before you can continue using it.

10. Governing law

These terms are governed by the laws of the Province of Ontario and the federal laws of Canada that apply there, except where the law of the place you live requires otherwise.

11. Contact

Questions about Fairpot or these terms: willyros01@gmail.com



I have read and agree to the Fairpot Terms of Use.

By tapping Accept, you agree to these terms. If you decline, Fairpot stays locked.

2

Decline

3

Accept

1

I have read and agree

Tick this box first. The Accept button stays grey until you do.

2

Decline

Fairpot stays locked. See below.

3


Accept

Saves your acceptance and opens the app.

Saved properly

Your acceptance is saved like any other change: it counts only once it is safely stored. If it cannot be saved, a message says so and Fairpot stays locked, so you can try again.

If you decline




1 Read the terms again

Fairpot cannot be used without accepting the terms. You can close the app, or tap this button to go back to the terms.

Once accepted, the terms are not shown again — unless a later version of Fairpot changes them. You can read them at any time from the Summary screen (Chapter 12).

Finding your way around

The three screens



1 The rate badge

Top right on every screen: the rate in use for the current currency and where it came from. Tap it to type your own rate (Chapter 5).

2 The tab bar

New records an expense. **History** lists the ones you saved. **Summary** shows totals and holds the settings.

Fairpot opens on the **New** screen, ready for an expense. The page title changes to History or Summary as you move between tabs.

Pinch to zoom

On iPhone and iPad you can pinch to enlarge any screen, and pinch again to zoom back out.

Recording an expense

Description, people, currency and receipts

This chapter follows one example from start to finish: dinner in Makati for four people, paid in Philippine pesos, with a total of ₱4,530 across three receipts.

1. Describe the expense

Fairpot

51 PHP = 0.02403 CAD
live rate · 2026-10-01
Rates By Exchange Rate API

Description

1Dinner in Makati

Date10/01/2026

2

People splitting34

Currency of this expense4PHP Philippine Peso

Receipts

Food3200

Change photo

Delete receipt

Beverages980

Add photo

Delete receipt

Tip350

Add photo

Delete receipt

+ Add another receipt


New

History

Summary

- 1 **Description**
A short name you will recognise later, such as “Dinner in Makati”.
- 2 **Date**
Today, unless you change it.
- 3 **People splitting**
Tap – or + or type the number. Count everyone who shares the bill, including yourself.
- 4 **Currency of this expense**
The currency you paid in. Tap to choose another (below).
- 5 **Rate badge**
Now shows the peso rate: 1 PHP = 0.02403 CAD, downloaded today.

2. Choose the currency



1 Search

Type a code (PHP) or part of a name (peso). The list narrows as you type.

2 Pick one

Tap a currency to use it. Currencies you used recently are listed first next time.

3. Add the receipts

The screenshot shows the 'Receipts' screen in the Fairpot app. It features three receipt entries, each with a category dropdown, an amount input field, a photo thumbnail, and a 'Delete receipt' button. A '+ Add another receipt' button is at the bottom of the list. Below the list is a summary section showing the total of 3 receipts (₱4,530.00), the current rate (1 PHP = 0.02403 CAD), the total in Canadian Dollars (C\$108.84), and the amount divided between 4 people (₱1,132.50 / person). The bottom navigation bar has three icons: 'New', 'History', and 'Summary'.

Category	Amount
Food	200
Beverages	980
Tip	350

Item	Amount
Food	₱3,200.00
Beverages	₱980.00
Tip	₱350.00
Total of 3 receipts	₱4,530.00
Rate (tap to change)	1 PHP = 0.02403 CAD
In Canadian Dollar	C\$108.84
Divided between	4 people

₱1,132.50 / person
≈ C\$27.21 / person
live rate · 2026-10-01

1 Category

Choose from the pull-down. The list is alphabetical and you can add your own (Chapter 10).

2 Amount

In the expense currency. Decimals follow the currency: two for pesos and dollars, none for yen.

3 Photo

A thumbnail of the attached receipt photo. Tap it to see it full size; tap the small × to remove it.

4 Add photo

Take a picture of the receipt or pick one from your photo library.

5 Delete receipt

Removes that receipt from the expense.

6 + Add another receipt

Adds a row. The example has Food ₱3,200, Beverages ₱980 and Tip ₱350.

4. Check the shares

The screenshot shows the Fairpot app interface for checking shares. At the top, there are options to 'Change photo' and 'Delete receipt'. Below this, there are three receipt entries: 'Beverages' (980), 'Tip' (350), and a '+ Add another receipt' button. Each entry has an 'Add photo' button and a 'Delete receipt' link. The bottom section shows a summary of the bill: 'Food' (P3,200.00), 'Beverages' (P980.00), and 'Tip' (P350.00). The total is P4,530.00. It then shows the conversion to Canadian dollars: '1 PHP = 0.02403 CAD', resulting in C\$108.84. The bill is divided between 4 people, resulting in P1,132.50 / person (approx C\$27.21 / person). At the bottom, there are 'Share' and 'Save' buttons. The bottom navigation bar has 'New', 'History', and 'Summary' options.

1 Rate (tap to change)

The rate used to convert to your home currency. Tap it to type the rate you actually paid.

2 Each person pays

The share in the expense currency, with the home-currency amount underneath.

3 Share

Send the split before or after saving (Chapter 7).

4 Save

Stores the expense with its receipts, photos and rate (Chapter 6).

How the numbers are worked out

Food + Beverages + Tip

$\text{P}3,200 + \text{P}980 + \text{P}350 = \text{P}4,530.00$

Divided between 4 people

P1,132.50 each

In Canadian dollars at 1 PHP = 0.02403 CAD

≈ C\$27.21 each

Whole bill in Canadian dollars

C\$108.84

Include yourself

“People splitting” counts everyone who shares the bill — including you. For a dinner for four, enter 4.

Exchange rates

Where rates come from and how they are locked

Fairpot converts every expense into your home currency so that totals and summaries add up.

Where the rates come from

Once a day Fairpot downloads a table of exchange rates from the free ExchangeRate-API service (credited under the rate badge). The badge and the result box say which kind of rate is in use:

Label	Meaning
live rate	Downloaded today.
last downloaded rate	You are offline; Fairpot uses the most recent table it has and shows its date.
approximate built-in rate	Used only before the very first download.
your own rate	You typed it in.
rate saved with this expense	The rate locked in when the expense was saved.

Rates are locked when you save

An expense keeps the rate it was saved with, so its home-currency amount never drifts. Editing it later keeps the same rate — unless you change its currency.

Using your own rate

Your card or bank may have used a different rate. Tap **Rate (tap to change)** in the result box, or the rate badge, and type how many units of your home currency one unit of the expense currency cost. Fairpot confirms with a short message and labels it “your own rate”.

Expenses on an earlier date

The free rate service only has today's rates. If you date an expense in the past, Fairpot warns you that the rate is today's and suggests tapping the rate to enter the one you actually paid.

Same currency as home

When an expense is in your home currency, no conversion is needed and no rate is shown.

Saving

What “Saved” really means

Tap **Save** on the New screen. Fairpot works like a careful database:

A save counts only once it is written. The expense, its receipts and photos are saved together as one change. Fairpot then reads the saved data back, and only then shows “Expense saved”.

If anything goes wrong, nothing changes. A message says what was not saved and why. Your previous data is untouched, and the form keeps everything you typed so you can try again.

While saving, the button reads “Saving...” and cannot be tapped twice.

Editing works the same way

Updates, deletes, settings, categories and payment methods are all saved this way.


If Fairpot warns about its storage

If the saved data cannot be read safely when Fairpot starts, it shows a warning and refuses every save, so it can never overwrite your real data with an empty list. Restore your latest backup (Chapter 11) or contact us.

Sharing a split

Send everyone what they owe

Tap **Share** on the New screen, or on any expense in History.



1 The message

Exactly what the other people will receive: each receipt, the total, each share and how to pay you.

2 Include my payment details

Adds the payment methods you saved (Chapter 10). Untick to leave them out.

3 Attach receipt photos

Shown when receipts have photos. Sends the photos along with the message.

4 Share...

Opens the iPhone share sheet: Messages, WhatsApp, Mail and so on.

5 Copy to clipboard

Copies the message so you can paste it anywhere.

What people receive

Dinner in Makati – 2026-10-01

Food	₱3,200.00
Beverages	₱980.00
Tip	₱350.00
TOTAL	₱4,530.00 (≈ C\$108.84)

Split 4 ways: ₱1,132.50 each (≈ C\$27.21 each)

Send your share to Willy:

Interac e-Transfer: willy@example.com

GCash: 0917 000 0000


Rate: 1 PHP = 0.02403 CAD (2026-10-01)

No payment methods yet?

Fairpot reminds you in the share window and points you to the Summary screen to add them.

History

Look back, share again, edit or delete



1 The expense

Description, date, people and receipt count, with the total in its own currency and in your home currency.

2 Each person

The share per person, in green.

3 Details

Opens the full breakdown (right).

4 Share


Sends the split again.

5 Edit

Opens the expense on the New screen for changes. Tap Update to save, or Cancel editing.

6 Delete

Removes the expense with its receipts and photos, after you confirm.




The details show every receipt, the totals, the people, each share, the rate used and its source. A thumbnail of each receipt photo is shown; tap it to see it full size.

Deleting cannot be undone

Save a backup first (Chapter 11) if you might want the expense back.

Summary

Totals by category, month and year



- 1 This year by category**
Totals in your home currency, largest first.
- 2 Bars**
Show each category's share of the year at a glance.
- 3 By month and by year**
Number of expenses and totals per period, with the categories and currencies involved.


All summary amounts are in your home currency, using each expense's locked rate.

Settings

Help, home currency, payment methods and categories


Settings sit below the totals on the Summary screen.

Help



- 1 Open the User Guide**
Opens this guide and the Quick Start on the Cuberoot Systems website.

Home currency



- 1 Your home currency**
Every total, summary and share message is also shown in it.
- 2 Change**
Pick another currency. Fairpot asks you to confirm. Expenses already saved keep their own rates.

Where people can pay you

Where people can pay you

Offered every time you share a split. Add as many ways to pay as you like. Kept only on this device and in your backup file.

Your name (optional)

1

Willy

Payment methods

2

Interac e-Transfer

Willy@example.com

Remove

GCash

0917 000 0000

Remove

Add a method

3

PayPal

Interac e-Transfer

GCash

Maya

4

PayPal

Wise

Revolut

Venmo

Zelle

Bank transfer

5

Email, phone number or account

6

Add payment method

1 Your name

Optional. Used in “Send your share to ...”.

2 Saved methods

Each with a Remove button.

3 Add a method

Type the name of the method, or —

4 Tap a suggestion

Fills in a common name: Interac e-Transfer, GCash, Maya, PayPal, Wise and more.

5 Account

The email, phone number or account people should pay.

6 Add payment method

Saves it. Add as many as you like.

Receipt categories

Receipt categories

Shown alphabetically in the pull-down on every receipt. Add as many of your own as you like.

1

verages

built in

Fees

built in

Food

built in

Gifts

built in

Groceries

built in

Lodging

built in

Other

built in

Shopping

built in

Tip

built in

Transport

built in

Utilities

built in

2

New category

Add

- 1

The list


Built-in categories are marked; your own can be removed.
- 2

New category

Type a name (up to 24 characters) and tap Add.

Backup and restore

Keep a copy outside the app



1 Save backup

Saves everything — expenses, receipt photos, categories, payment methods and settings — as one file. Choose **Save to Files** on the share sheet.

2 Load backup

Opens a backup file and restores it, after you confirm.

Good to know

Backups travel. A backup includes its photos, so it restores on another iPhone or iPad.

Restore is all or nothing. Loading a backup replaces your current expenses. If any part cannot be saved, nothing is restored.

Split It backups from the older web app load too.


Reminders. Under the New screen Fairpot reminds you when your last backup is 30 or more days old, or when you have 5 or more expenses and no backup yet.

Your data lives only on this device

If you delete Fairpot or lose your device, anything not in a backup is gone. Save a backup now and then.

Terms and privacy

What Fairpot keeps, and where



1 Accepted

The version of the terms you accepted, and the date.

2 Read the terms

Shows the full Terms of Use. Tap Close to return.

The terms in brief

Fairpot is free and provided as is. You check every amount and rate before relying on it. Fairpot does not move money. You keep your own backups. To the fullest extent the law allows, the developer accepts no liability for losses from using it. The full text is in the app and on the Cuberoot Systems website.

Privacy

Fairpot collects no personal information. Expenses, photos, payment details and settings are stored only in Fairpot's private storage on your device. The daily rate download contains no personal information. Camera and photo access is used only when you attach a receipt photo.

Troubleshooting

Common questions, quick answers

Question	Answer
Fairpot only shows the Terms of Use.	Tick "I have read and agree", then tap Accept. If a message says the acceptance was not saved, close and reopen Fairpot and try again.
The rate says "last downloaded rate".	You are offline or the rate service did not answer. New rates arrive the next time Fairpot is online.
The share in my home currency looks wrong.	Check the rate in the result box. Tap it to enter the rate your bank actually used.
I see a warning about an earlier date.	Free rates are today's only. Tap the rate and enter the one you paid.
A message says something was NOT saved.	Nothing was changed and your typing is kept. Try again; if it repeats, restart Fairpot.
Payment details are missing from my message.	Add payment methods on the Summary screen, and keep "Include my payment details" ticked.
A backup will not load.	Only Fairpot and Split It backup files can be loaded. Choose the file you saved with Save backup.
The screen is enlarged.	Pinch with two fingers to zoom back out.
I moved to a new phone.	On the old one, Save backup to Files (iCloud Drive). On the new one, Load backup.

Still stuck? Email willyros01@gmail.com.

Quick reference

Everything on one page

To...	Do this
Record an expense	New → description, date, people, currency → receipts → Save
Add a receipt photo	 Add photo on the receipt row
Change the currency	Tap the currency button → search → tap one
Use your own rate	Tap “Rate (tap to change)” or the rate badge
Send the split	Share → Share... (or Copy to clipboard)
Fix a saved expense	History → Edit → change → Update
Delete an expense	History → Delete → confirm
See totals	Summary
Change home currency	Summary → Home currency → Change
Add a payment method	Summary → tap a suggestion or type a name → account → Add payment method
Add a category	Summary → Receipt categories → New category → Add
Back up	Summary → Save backup → Save to Files
Restore	Summary → Load backup → choose the file → confirm
Read the terms	Summary → Terms of use → Read the terms
Open this guide	Summary → Help → Open the User Guide