CHAPTER 8

EDITING SCREEN VIEW MENU

The View menu includes commands for previewing your printed document onscreen, turning on and off the display of command tags and other screen elements, and opening, switching, and sizing windows.

```
View

Preview                    ^OP

Command Tags               ^OD
Block Highlighting         ^KH

Open/Switch Window         ^OK
Change Window Size...      ^OM

Screen Settings...         ^OB
```

PREVIEW

Pull-down: ***ALT + V, P***
Classic: ***^OP***

Displays the document onscreen exactly as it will appear printed.



When you start Preview, you see the current page onscreen, with columns, headers, footers, footnotes, fonts, line spacing, and so on. At the top of the screen is the Preview menu bar. The commands on the Preview menus let you move around in your document and change your view of the document. You can view another page, choose a different view of a page or pages, scan a range of pages, and display a grid for checking page alignment. You can also prepare faxes for transmission.

The Preview commands are described below.

Go to

Pull-down: ***ALT + V, P, G***
Classic: ***^OPG***

Previews another page.



To display the first, last, next, or previous page, choose the appropriate option. To preview a specific page, choose Specified Page, type the page number and press Enter. Preview goes to the specified physical page and ignores any page number commands you may have set. If Preview is displaying more than one page, the page you specify will be the first page at the top of the screen.

View

Pull-down: ***ALT + V, P, V***
Classic: ***^OPV***

Previews the document from any of several perspectives.



Entire Page Displays the entire current page, the same view as when you first choose Preview.

Facing Pages Zooms out and displays two pages next to each other, the way pages look in a book or newsletter.

Multiple Pages Zooms out and displays four to ten pages, depending on your monitor and the page size. It is good for looking at the overall layout of a short document, or a section of a longer one.

Thumbnail Display Zooms out and displays ten or more pages, depending on your monitor and the page size. It's good for looking at the overall layout of a document. Press ^PgDn or ^PgUp to see the next set or the previous set of pages. Press ^Home or ^End to see the first or last page of a document. To zoom in on a specific page, use the direction keys to move the highlighting to the page number, and then choose the magnification.

TIP *You can quickly change the magnification by using the Plus (+) or Minus (–) keys on the numeric keypad. For example, if you're viewing the thumbnail display, press + to see the multiple pages display. If you're viewing the entire page display, press – to see facing pages.*

2x Zoom Zooms in and makes the page appear twice as large. You can then use the direction keys to move the display window to a different part of the page. For example, press the Down Arrow key or ^X to move down a few lines, or press PgDn or ^C to move down a full screen. Use ^PgDn to move to the next page.

4x Zoom Zooms in and makes the page appear four times as large. You can use the same commands as you can with 2x Zoom.

Adjust Window Lets you move to a different part of the page. When you choose this command, WordStar displays a small picture of the page with a box outlining the current window display. Use the direction keys to move the box to the area of the page you want to see. (To move the box more quickly, use the Shift key with the direction keys.) When the box is where you want it, press Enter to return to the page. The area you selected appears on the screen.

TIP *To adjust the window display without choosing View and Adjust Window, press Insert to display the box, and use the direction keys to move it. When you stop moving the box, WordStar returns you to the page.*

OPTIONS

Pull-down: ***ALT + V, P, O***
Classic: ***^OPO***

Scans the document, displays a grid to check the alignment of text, and prepares faxes for transmission.

These options are described below.

Automatic Scan Shows successive portions of the document until you press Esc.

TIP *To locate a portion of your document quickly, scan the document in thumbnail display, then press Esc when you see the page you want. Move the highlighting to that page number and choose a View command to preview, or press Alt+1 or choose Return to Editing and then Current page to exit Preview and edit that page.*

Scan Range Scans a specified range of pages. After you choose Scan range, you specify the page numbers where you want the scan to start and stop.

Fax Files for Entire Document Creates a .PCX file for each page of the document. You can send these files through a fax board using the software that came with the board. The resulting page printed by the fax machine at its destination looks exactly like the previewed page. If you did not start Preview from the Fax dialog box, WordStar prompts you for a five-letter name for the first fax file. The default name is F*nnn*P*mmm*.PCX, where *nnn* is a document number and *mmm* is the page number, assigned sequentially. The default resolution is used (high resolution unless you've changed the value for FAX_RES in the FONTID.CTL file).

When you choose this command, an entire view of each page is displayed in Preview as its .PCX file is created, and the .PCX filename is displayed at the top of the screen. When all the .PCX files are created, Preview displays the entire page view of the last page for which a .PCX file was created. The .PCX files are created in the WS\FAX directory. (The fax directory is a subdirectory of the directory that contains the FONTID.CTL file. If it doesn't already exist when you create fax files, WordStar creates it.)

You can also create fax files using the Fax→File command. For more information on creating fax files, see "Fax" in "Opening Screen File Menu."

Fax Files for Range Creates fax files for a specified range of pages. After you choose this command, you specify the page numbers where you want the range to begin and end. For more information on creating fax files, see the information above on the previous command, Fax Files for Entire Document. If you want to create fax files for several ranges, just use this command as many times as necessary.

IMPORTANT *When you specify the range of pages, you must specify the physical page numbers, even if you've reassigned page numbers. For example, if you have a three-page document with no page number on the first page, and the second and third pages numbered 1 and 2, you must specify 2-3 to print the last two pages. If you're not sure about the physical page numbers, you can check them using Preview. Preview displays the physical page numbers at the top of the screen or, if more than one page is displayed, above each page.*

Grid Display On/Off Displays a grid across the page. Grid display is useful for making sure your text is properly aligned.

EXIT

Pull-down: ***ALT + V, P, E***
Classic: ***^OPE***

Exits Preview and returns you to the editing screen.

You can choose to return to the page you're currently viewing or to the original page you were editing when you chose Preview.

To return to the page you're currently viewing, choose Current Page or press Alt+1. If you're in a view that displays more than one page, you return to the page whose number is highlighted. To return to the page you were editing before you chose Preview, choose Original Page or press Alt+2.

PREVIEW FILES

Preview creates CRT directories containing screen font files (.CRT) and graphics files (.G*n*$, where *n* is a number) in your WordStar directory. WordStar may create a number of CRT directories, depending on your monitor(s) and on the page size and orientation.

The .CRT files are created when you preview a document with fonts that you haven't previewed before. Each time you see the message *Building preview font,* WordStar is creating a .CRT file.

The .G*n*$ files are created when you use the zoom commands in Preview with graphics (.PIX) files.

Each time you preview a document that contains a new Inset graphic, a .WSG file is created. This file contains specific graphics information that is needed for Preview. The .WSG files are stored in the directory that contains your .PIX files. To save disk space, you can delete the .WSG files when you're finished with them (use the DOS DEL command).

To save disk space, you may want to delete the .CRT and .G*n*$ files and the CRT directories periodically, especially if they contain files for fonts and graphics that you are no longer using. You can delete these files and directories individually by using the DOS DEL and RD commands, or you can delete them all at once by using the DELCRT.EXE program, which is in your WordStar directory. At the DOS prompt in the WordStar directory, type **delcrt** and press Enter. DELCRT.EXE deletes all of the .CRT files, .Gn$ files, and CRT directories from your WordStar directory. (Note that DELCRT deletes only those .CRT files with eight digits in the filename (*nnnnnnnn*.CRT).

PREVIEW ADVISORIES

Keep these points in mind when you use Preview:

- Preview works only on monitors with graphics capability.
- Preview can't run with two windows open, unless you are have at least 80K (5 pages) of EMS memory available.
- If the appearance of fonts (especially large fonts) is blocky, WordStar may need more memory while creating fonts. If less than 512K is available when you start WordStar, you can remove memory-resident programs or use WSCHANGE settings to make more memory available, and then run the DELCRT program to delete the blocky fonts. Then start WordStar and use Preview again. You can also improve these fonts by creating .WSF files for

large fonts using smaller symbol sets. For more information on .WSF files, see the *Installing and Customizing* booklet.

- If an Inset graphic is too compressed (for example, if a very large graphic is reduced to a small size for printing), it won't be displayed correctly in Preview.

- Preview does not support text mode .PIX files. If you want to preview a page with a text mode pix file, you must first convert the .PIX file to graphics mode, which may affect the appearance of the printed page. For more information, see "Converting a text screen to graphics" in the "Inset" section of the *Companion Programs* manual.

- If you often start WordStar from ProFinder™, you may want to redefine the + and – ProFinder hot keys. Otherwise, you won't be able to use the + and – keys as zoom keys in Preview. For more information, see "Setting the Configuration Options" in the "ProFinder" section of the *Companion Programs* manual.

COMMAND TAGS

Pull-down: ***ALT + V, C***
Classic: ***^OD***

Turns display of WordStar command tags on and off.

WordStar command tags, such as **^B** for bold and **<COURIER 10>** for a font change, are normally displayed onscreen. However, they take up space and may make text appear out of alignment. Choose View→Command Tags, or use the ^OD classic command, to remove these tags from the screen while you edit, or to display them again. The commands remain in effect even when the tags aren't displayed.

It's a good idea to turn Command Tags display on before you mark a block to see what commands you're including in the block. For example, if bold text begins at the beginning of the block, be sure to include the tag that begins bold in the block.

View→Command Tags can also turn on and off the display of dot commands, soft space characters, and the flag column at the right of the screen. You can specify whether or not to include each of these elements in Command Tags by

choosing View→Screen Settings, or ^OB. If display of dot commands is off and you type a dot in column 1, the new dot command disappears after you press Enter. For more information, see "Screen Settings" in this chapter.

You can turn Command Tags display on and off with a mouse by clicking the [*] button in the style bar.

You can use WSCHANGE (DBAB) to turn the default setting for Command Tags on or off and to change which elements are turned on and off when you choose Command Tags.

BLOCK HIGHLIGHTING

Pull-down: ***ALT + V, B***
Classic: ***^KH***

Turns block highlighting (and display of block markers) on and off.

You can use this command to hide the block markers and highlighting, and to turn them on again. If you hide a block or a marker, and then mark a new block beginning or end, block highlighting is turned on again.

At all help levels except 0, you can hide the marked block as a safety measure. At these levels, WordStar won't move, copy, erase, or write blocks when the markers are hidden.

You can delete block markers, rather than hiding them, by pressing ^K<.

OPEN/SWITCH WINDOW

Pull-down: ***ALT + V, O***
Classic: ***^OK***

Opens a window so that you can look at two documents at once, or at two parts of the same document. If two windows are already open, moves the cursor to the other window.

Follow these steps to open a window or move the cursor to the other window:

1 Choose View→Open/Switch Window, or use the ^OK classic command.

2 In the Open dialog box, specify the name of the file to open. You can open either an existing file or a new one.

A filename can have up to eight characters and an optional extension of up to three characters. Type a period between the filename and the extension. Don't use spaces between the characters. Filenames can include letters, numbers, and these symbols:

$ & # ! % ' ` ( ) { } - _ ~ @

Note: Files with the extensions .COM, .EXE, .OVR, .SYS, .DCT, .CRT, .WSF, .PDF, .DCC, .INF, .PRD, .WSM, and .$?? (where ? can be any character) do not appear in the WordStar filenames lists, so don't use them to name your text files. You can change this list of filename extensions using WSCHANGE (CEC).

3 Press F10 or choose OK.

The screen splits in half. The cursor is located in the new file on the bottom half of the screen.

You can edit in either window. To move the cursor to the other window, use this command or choose File→Open/Switch, or use the ^OK classic command.

The title bar shows a [1] when the cursor is in the top window and a [2] when the cursor is in the bottom window. It also shows the name of the file where the cursor is currently located. You can use a mouse to switch to the other window by clicking this number.

The file in the second window is always opened as a document if the file in the first window is a document, or as a nondocument if the file in the first window is a nondocument. If you want to be able to open a document and a nondocument at the same time, use WSCHANGE (DCGG) to turn on the prompt that asks you whether to open a document or a nondocument when you open a second window.

TIP *If you want to see how the document you're editing looked before you made your most recent editing changes, you can open a second window on the same document. The second window shows the version that you saved last, in protected mode because you can't make changes to both copies.*

Keep these points in mind when working with two windows:

- To change the sizes of the windows, choose View→Change Window Size, or use the ^OM classic command. You can also press ^– (hyphen) to enlarge the current window one line at a time. For more information, see "Change Window Size" in this chapter.

- You can mark blocks in both windows at once. To copy a block between windows, choose Edit→Copy→Block from Other Window, or press ^KA. To move a block between windows, choose Edit→Move→Block from Other Window, or press ^KG. For more information, see "Copy" and "Move" in "Editing Screen Edit Menu."

- You cannot edit notes or macros when you have a document in the second window.

CHANGE WINDOW SIZE

Pull-down: ***ALT + V, W***
Classic: ***^OM***

Changes the number of lines displayed in a window.

When you open a second window, each window takes up half the screen. Follow these steps to change the window size:

1. Choose View→Change Window Size, or use the ^OM classic command.

2. In the Change Window Size dialog box, choose Full Screen or Half Screen or specify the number of lines you want for the current window.

   If you choose Full Screen, each window takes up the full screen, and the screen flips from one file to the other when you move the cursor between windows.

3. Press F10 or choose OK.

You can specify a default window size in WSCHANGE (DCGH).

Note: You can press ^– (hyphen) to enlarge the current window one line at a time.

SCREEN SETTINGS

Pull-down: ***ALT + V, S***
Classic: ***^OB***

Determines which screen elements are displayed during editing.

You can use this command to turn on and off the display of several screen elements and to decide which elements to turn on and off using View→Command Tags (or ^OD). Follow these steps:

1. Choose View→Screen Settings, or use the ^OB classic command.
2. In the Screen Settings dialog box, change any options you want. The options are described below.

```
                    Screen Settings

Dot Commands:                    Display On Screen:     OK
 o  Always On
 ◆  Display with Command Tags    [X] Scroll Bar         Cancel

Flag Column:                     [X] Style Bar
 o  Always On
 ◆  Display with Command Tags    [X] Status Line

Soft Space Dots:                 [X] Ruler Line
 o  Always On
 ◆  Always Off                   [X] Classic Commands on
 o  Display with Command Tags        Pull-down Menus
```

Dot Commands Dot commands can be always displayed or turned on and off with Command Tags (the default). If display of dot commands is off and you type a dot in column one, the new dot command disappears after you press Enter. You can change the default in WSCHANGE (DBAE).

Flag Column The flag column at the right of the screen can be always displayed or turned on and off with Command Tags (the default). You can change the default in WSCHANGE (DBAC).

Soft Space Dots The spaces that WordStar inserts when it justifies text to make the line end at the right margin are called soft spaces. WordStar can display soft spaces as small dots. These dots can be always displayed, never displayed (the default), or turned on and off with Command Tags. You can change the default in WSCHANGE (DBAD).

Scroll Bar This option turns on and off the display of the vertical scroll bar at the right of the screen. The scroll bar is especially useful for mouse users. The default is scroll bar display on. You can change the default in WSCHANGE (DBAJ).

Style Bar This option turns on and off the display of the style bar. The style bar displays information about current settings, and allows easy access to these settings using a mouse. The default is style bar display on. You can change the default in WSCHANGE (DBAG).

Status Line This option turns on and off the display of the status line. The status line displays information about the current editing status. The default is status line display on. You can change the default or move the status line to the top of the screen using WSCHANGE (DBAI or DBA2B).

Ruler Line This option turns on and off the display of the ruler line at the top of the screen. The ruler line shows the margins and tab stops that currently apply to your text. The default is ruler line display on. You can change the default in WSCHANGE (DBAH). You can still make changes to the ruler when it's not displayed. For more information on ruler lines, see "Ruler Line" in "Editing Screen Layout Menu."

Classic Commands on Pull-down Menus This option turns on and off the display of classic commands on the pull-down menus. If you use the classic commands, this display is useful as a reminder and to determine the related pull-down commands. The default is classic commands on. You can change the default in WSCHANGE (DBAK).

3 Press F10 or choose OK.

For more information on these screen elements, see "Screens and Dialog Boxes" in "WordStar Basics" in this manual.