APPENDIX C

MACRO KEYSTROKES

This appendix describes the keystroke conventions used for the WordStar macro system, and provides a table of all the keystrokes that the macro system recognizes. For more information about macros, see "Macros" in "Utilities Menu."

THE KEY( ) FUNCTION

The Key( ) macro function provides keystrokes to the application. The argument of Key( ) is a keystroke string. For example, "Good Morning!{Enter}" is a valid keystroke string, and to have it typed into WordStar you'd include the statement KEY("Good Morning!{Enter}") in a macro. For guidelines for entering keystrokes in the Key( ) function, see "The Macro Language" in "Macros" in "Editing Screen Utilities Menu."

TYPES OF KEYSTROKES

A keystroke is defined as the act of either pressing a single key or pressing a number of keys at the same time. Keystrokes generate codes that are interpreted in one of two ways:

- A keystroke can be an alphanumeric character, a punctuation mark, or symbol such as **A**, **;**, or ‡. These are all called characters.

- A keystroke can be a command to perform an action such as delete a character, move the cursor up one line, or start a new line. These keystrokes are called application defined keystrokes.

The Key( ) function provides both types of keystrokes. The first type of keystroke is represented in the keystroke string by simply entering the character. The second type of keystroke is represented by a description as shown in the table. Generally, the keystroke description is the same as the one that appears on the key cap on the US keyboard. It is usually enclosed in braces ({ }). (To enter an actual { or }, you double the character, for example, { { .)

A keyboard may contain more than one key that has the same general meaning. To differentiate between keys with similar meanings, the following conventions are used:

- Characters and descriptions enclosed in square brackets represent keys on the numeric key pad, for example, [Enter]. Some of these keys are only available on enhanced keyboards.

- Descriptions enclosed in parentheses represent the cursor and edit pad keys on enhanced keyboards, for example, (UP) and (Del).

Combining these conventions leads to keystroke descriptions like {Enter}, {[Enter]}, and {(UP)}.

SHIFTED KEY DESCRIPTIONS

Keyboards have three types of keys that can be used with other keys, the Shift key, the Control key (Ctrl), and the Alt key. Some non-US keyboards also have a fourth key, the right Alt key (AltGr), which is used to generate additional alphanumeric symbols. These keys are represented in macros enclosed in braces with the accompanying key, for example, {Ctrl C}, {Alt A}, and {Shift F1}.

For alphabetic characters, punctuation marks, and other symbols, don't indicate the Shift key required to generate the keystroke; just enter the character as

you normally would. For example, {Shift a} does not produce A. This is also true for the AltGr shift key, which is used to generate characters, not instructions. For example, on a German keyboard, don't represent / as {AltGr ß}.

KEYSTROKES IN RECORDED MACROS

When a recorded macro is translated into a macro source file, keystrokes from enhanced keyboards are translated into the equivalent keystrokes from unenhanced keyboards. For example, {(UP)} becomes {UP}. The same is true for numbers and symbols on the numeric keypad; for example, {[1]} becomes 1.

If a specific keystroke is required, you can edit the macro and enter the extended or numeric keypad description. When the macro is compiled, the indicated scan code and character combination are used.

Note: When you execute a macro, it provides keystrokes to WordStar in the same general way that the BIOS keyboard i/o service does. WordStar often performs additional processing on a keystroke prior to acting on it. For example, if you press ^K^Q while recording (without taking your finger off of the control key before pressing Q), the macro file shows {CTRL K}{CTRL Q}. During playback, the WordStar editor takes the same action as if the source file contained {CTRL K}Q.

KEYSTROKES NOT IN THE TABLE

The table in this appendix shows the standard keystrokes based on the US keyboard in code page 437. Other keyboards and code pages can produce different keystroke codes. When a recorded macro is translated into a macro source file, all recognizable codes are translated into US keyboard equivalents. These equivalents may be particular keys or extended characters.

To enter a specific keystroke not in the table, enter it in {*xxx,yyy*} format, where *xxx* is the high byte and *yyy* is the low byte of the decimal value of the code.

Any unrecognized keystroke code is translated into this same format when a recording is translated into source code.

THE WORDSTAR MACRO US KEYSTROKE TABLE

The following table shows the valid keystrokes for WordStar macros.

- The first column of the table shows the character or description associated with each keystroke.
- The second column shows the hexadecimal value of the code returned by BIOS Interrupt 16H for each keystroke. This is called the keystroke code. The high byte is usually called the scan code, and the low byte is usually called the ASCII code. For text and punctuation keystrokes, the ASCII code (low byte) is the number associated with the character.
- The third column shows the decimal values of the high and low byte of the keystroke code.
- The fourth column indicates if the particular keystroke is available only on an enhanced keyboard. It also shows keystrokes that are specific to WordStar.

The last part of the table includes all the extended characters (those with decimal codes 1 to 31 and 128 to 255). The characters shown in the table are those displayed on the screen for the IBM symbol set for code page 437. (If you're using a different code page, different characters are displayed on the screen. The characters that are printed depend on the symbol set for the font you use for printing.) You can enter extended characters in several ways. For more information, see "Extended Character" in "Insert Menu."

KEYSTROKE DESCRIPTION	HEX	DECIMAL	NOTE
{BACKTAB}	0F 00	015 000	
{BKSP}	0E 08	014 008	
{DEL}	53 00	083 000	
{(DEL)}	53 E0	083 224	Enhanced keyboard
{DOWN}	50 00	080 000	
{(DOWN)}	50 E0	080 224	Enhanced keyboard
{END}	4F 00	079 000	
{(END)}	4F E0	079 224	Enhanced keyboard
{ENTER}	1C 0D	028 013	
{[ENTER]}	E0 0D	224 013	Enhanced keyboard
{ESC}	01 1B	001 027	
{HOME}	47 00	071 000	
{(HOME)}	47 E0	071 224	Enhanced keyboard
{INSERT}	52 00	082 000	
{(INSERT)}	52 E0	082 224	Enhanced keyboard
{LEFT}	4B 00	075 000	
{(LEFT)}	4B E0	075 224	Enhanced keyboard
{PGDN}	51 00	081 000	
{(PGDN)}	51 E0	081 224	Enhanced keyboard
{PGUP}	49 00	073 000	
{(PGUP)}	49 E0	073 224	Enhanced keyboard
{RIGHT}	4D 00	077 000	
{(RIGHT)}	4D E0	077 224	Enhanced keyboard
{TAB}	0F 09	015 009	
{([5])}	4C 00	076 000	Enhanced keyboard
{UP}	48 00	072 000	
{(UP)}	48 E0	072 224	Enhanced keyboard
space	39 20	057 032	
!	02 21	002 033	
"	28 22	040 034	
#	04 23	004 035	
$	05 24	005 036	
%	06 25	006 037	
&	08 26	008 038	
'	28 27	040 039	
(	0A 28	010 040	
)	0B 29	011 041	
*	09 2A	009 042	
{[*]}	37 2A	055 042	

KEYSTROKE DESCRIPTION	HEX	DECIMAL	NOTE
+	0D 2B	013 043	
{[+]}	4E 2B	078 043	
,	33 2C	051 044	
-	0C 2D	012 045	
{[-]}	4A 2D	074 045	
.	34 2E	052 046	
{[.]}	53 2E	083 046	
/	35 2F	053 047	
{[/]}	E0 2F	224 047	Enhanced keyboard
:	27 3A	039 058	
;	27 3B	039 059	
<	33 3C	051 060	
=	0D 3D	013 061	
>	34 3E	052 062	
?	35 3F	053 063	
@	03 40	003 064	
[	1A 5B	026 091	
\	2B 5C	043 092	
]	1B 5D	027 093	
^	07 5E	007 094	
_	0C 5F	012 095	
`	29 60	041 096	
{	1A 7B	026 123	
|	2B 7C	043 124	
}	1B 7D	027 125	
~	29 7E	041 126	
n/a	00 7F	000 127	
0	0B 30	011 048	
{[0]}	52 30	082 048	
1	02 31	002 049	
{[1]}	4F 31	079 049	
2	03 32	003 050	
{[2]}	50 32	080 050	
3	04 33	004 051	
{[3]}	51 33	081 051	
4	05 34	005 052	
{[4]}	4B 34	075 052	
5	06 35	006 053	
{[5]}	4C 35	076 053	

KEYSTROKE DESCRIPTION	HEX	DECIMAL	NOTE
6	07 36	007 054	
{[6]}	4D 36	077 054	
7	08 37	008 055	
{[7]}	47 37	071 055	
8	09 38	009 056	
{[8]}	48 38	072 056	
9	0A 39	010 057	
{[9]}	49 39	073 057	
A	1E 41	030 065	
B	30 42	048 066	
C	2E 43	046 067	
D	20 44	032 068	
E	12 45	018 069	
F	21 46	033 070	
G	22 47	034 071	
H	23 48	035 072	
I	17 49	023 073	
J	24 4A	036 074	
K	25 4B	037 075	
L	26 4C	038 076	
M	32 4D	050 077	
N	31 4E	049 078	
O	18 4F	024 079	
P	19 50	025 080	
Q	10 51	016 081	
R	13 52	019 082	
S	1F 53	031 083	
T	14 54	020 084	
U	16 55	022 085	
V	2F 56	047 086	
W	11 57	017 087	
X	2D 58	045 088	
Y	15 59	021 089	
Z	2C 5A	044 090	
a	1E 61	030 097	
b	30 62	048 098	
c	2E 63	046 099	
d	20 64	032 100	
e	12 65	018 101	

KEYSTROKE DESCRIPTION	HEX	DECIMAL	NOTE
f	21 66	033 102	
g	22 67	034 103	
h	23 68	035 104	
i	17 69	023 105	
j	24 6A	036 106	
k	25 6B	037 107	
l	26 6C	038 108	
m	32 6D	050 109	
n	31 6E	049 110	
o	18 6F	024 111	
p	19 70	025 112	
q	10 71	016 113	
r	13 72	019 114	
s	1F 73	031 115	
t	14 74	020 116	
u	16 75	022 117	
v	2F 76	047 118	
w	11 77	017 119	
x	2D 78	045 120	
y	15 79	021 121	
z	2C 7A	044 122	
{CTRL+BKSP}	0E 7F	014 127	
{CTRL+BREAK}	00 00	000 000	
{CTRL+DEL}	93 00	147 000	Enhanced keyboard
{CTRL+(DEL)}	93 E0	147 224	Enhanced keyboard
{CTRL+DOWN}	91 00	145 000	Enhanced keyboard
{CTRL+(DOWN)}	91 E0	145 224	Enhanced keyboard
{CTRL+END}	75 00	117 000	
{CTRL+(END)}	75 E0	117 224	Enhanced keyboard
{CTRL+ENTER}	1C 0A	028 010	
{CTRL+[ENTER]}	E0 0A	224 010	Enhanced keyboard
{CTRL+HOME}	77 00	119 000	
{CTRL+(HOME)}	77 E0	119 224	Enhanced keyboard
{CTRL+INSERT}	92 00	146 000	Enhanced keyboard
{CTRL+(INSERT)}	92 E0	146 224	Enhanced keyboard
{CTRL+LEFT}	73 00	115 000	
{CTRL+(LEFT)}	73 E0	115 224	Enhanced keyboard
{CTRL+PGDN}	76 00	118 000	
{CTRL+(PGDN)}	76 E0	118 224	Enhanced keyboard

KEYSTROKE DESCRIPTION	HEX	DECIMAL	NOTE
{CTRL+PGUP}	84 00	132 000	
{CTRL+(PGUP)}	84 E0	132 224	Enhanced keyboard
{CTRL+PRTSC}	72 00	114 000	
{CTRL+RIGHT}	74 00	116 000	
{CTRL+(RIGHT)}	74 E0	116 224	Enhanced keyboard
{CTRL+TAB}	94 00	148 000	Enhanced keyboard
{CTRL+UP}	8D 00	141 000	Enhanced keyboard
{CTRL+(UP)}	8D E0	141 224	Enhanced keyboard
{CTRL+'}	C1 00	193 000	WordStar keystroke
{CTRL+[*]}	96 00	150 000	Enhanced keyboard
{CTRL+[+]}	90 00	144 000	Enhanced keyboard
{CTRL+,}	C3 00	195 000	WordStar keystroke
{CTRL+-}	0C 1F	012 031	
{CTRL+[-]}	8E 00	142 000	Enhanced keyboard
{CTRL+.}	C4 00	196 000	WordStar keystroke
{CTRL+/}	C5 00	197 000	WordStar keystroke
{CTRL+[/]}	95 00	149 000	Enhanced keyboard
{CTRL+;}	C2 00	194 000	WordStar keystroke
{CTRL+[}	1A 1B	026 027	
{CTRL+\}	2B 1C	043 028	
{CTRL+]}	1B 1D	027 029	
{CTRL+`}	C0 00	192 000	WordStar keystroke
{CTRL+0}	CD 00	205 000	WordStar keystroke
{CTRL+1}	C6 00	198 000	WordStar keystroke
{CTRL+2}	03 00	003 000	
{CTRL+3}	C7 00	199 000	WordStar keystroke
{CTRL+4}	C8 00	200 000	WordStar keystroke
{CTRL+5}	C9 00	201 000	WordStar keystroke
{CTRL+[5]}	8F 00	143 000	Enhanced keyboard
{CTRL+6}	07 1E	007 030	
{CTRL+7}	CA 00	202 000	WordStar keystroke
{CTRL+8}	CB 00	203 000	WordStar keystroke
{CTRL+9}	CC 00	204 000	WordStar keystroke
{CTRL+A}	1E 01	030 001	
{CTRL+B}	30 02	048 002	
{CTRL+C}	2E 03	046 003	
{CTRL+D}	20 04	032 004	
{CTRL+E}	12 05	018 005	
{CTRL+F}	21 06	033 006	

KEYSTROKE DESCRIPTION	HEX	DECIMAL	NOTE
{CTRL+G}	22 07	034 007	
{CTRL+H}	23 08	035 008	
{CTRL+I}	17 09	023 009	
{CTRL+J}	24 0A	036 010	
{CTRL+K}	25 0B	037 011	
{CTRL+L}	26 0C	038 012	
{CTRL+M}	32 0D	050 013	
{CTRL+N}	31 0E	049 014	
{CTRL+O}	18 0F	024 015	
{CTRL+P}	19 10	025 016	
{CTRL+Q}	10 11	016 017	
{CTRL+R}	13 12	019 018	
{CTRL+S}	1F 13	031 019	
{CTRL+T}	14 14	020 020	
{CTRL+U}	16 15	022 021	
{CTRL+V}	2F 16	047 022	
{CTRL+W}	11 17	017 023	
{CTRL+X}	2D 18	045 024	
{CTRL+Y}	15 19	021 025	
{CTRL+Z}	2C 1A	044 026	
{ALT+BKSP}	0E 00	014 000	Enhanced keyboard
{ALT+(DEL)}	A3 00	163 000	Enhanced keyboard
{ALT+(DOWN)}	A0 00	160 000	Enhanced keyboard
{ALT+(END)}	9F 00	159 000	Enhanced keyboard
{ALT+ENTER}	1C 00	028 000	Enhanced keyboard
{ALT+[ENTER]}	A6 00	166 000	Enhanced keyboard
{ALT+ESC}	01 00	001 000	Enhanced keyboard
{ALT+(HOME)}	97 00	151 000	Enhanced keyboard
{ALT+(INSERT)}	A2 00	162 000	Enhanced keyboard
{ALT+(LEFT)}	9B 00	155 000	Enhanced keyboard
{ALT+(PGDN)}	A1 00	161 000	Enhanced keyboard
{ALT+(PGUP)}	99 00	153 000	Enhanced keyboard
{ALT+(RIGHT)}	9D 00	157 000	Enhanced keyboard
{ALT+TAB}	A5 00	165 000	Enhanced keyboard
{ALT+(UP)}	98 00	152 000	Enhanced keyboard
{ALT+'}	28 00	040 000	Enhanced keyboard
{ALT+[*]}	37 00	055 000	Enhanced keyboard
{ALT+[+]}	4E 00	078 000	Enhanced keyboard
{ALT+,}	33 00	051 000	Enhanced keyboard

KEYSTROKE DESCRIPTION	HEX	DECIMAL	NOTE
{ALT+-}	82 00	130 000	
{ALT+[-]}	4A 00	074 000	Enhanced keyboard
{ALT+.}	34 00	052 000	Enhanced keyboard
{ALT+/}	35 00	053 000	Enhanced keyboard
{ALT+[/]}	A4 00	164 000	Enhanced keyboard
{ALT+;}	27 00	039 000	Enhanced keyboard
{ALT+=}	83 00	131 000	
{ALT+[}	1A 00	026 000	Enhanced keyboard
{ALT+\}	2B 00	043 000	Enhanced keyboard
{ALT+]}	1B 00	027 000	Enhanced keyboard
{ALT+'}	29 00	041 000	Enhanced keyboard
{ALT+0}	81 00	129 000	
{ALT+1}	78 00	120 000	
{ALT+2}	79 00	121 000	
{ALT+3}	7A 00	122 000	
{ALT+4}	7B 00	123 000	
{ALT+5}	7C 00	124 000	
{ALT+6}	7D 00	125 000	
{ALT+7}	7E 00	126 000	
{ALT+8}	7F 00	127 000	
{ALT+9}	80 00	128 000	
{ALT+A}	1E 00	030 000	
{ALT+B}	30 00	048 000	
{ALT+C}	2E 00	046 000	
{ALT+D}	20 00	032 000	
{ALT+E}	12 00	018 000	
{ALT+F}	21 00	033 000	
{ALT+G}	22 00	034 000	
{ALT+H}	23 00	035 000	
{ALT+I}	17 00	023 000	
{ALT+J}	24 00	036 000	
{ALT+K}	25 00	037 000	
{ALT+L}	26 00	038 000	
{ALT+M}	32 00	050 000	
{ALT+N}	31 00	049 000	
{ALT+O}	18 00	024 000	
{ALT+P}	19 00	025 000	
{ALT+Q}	10 00	016 000	
{ALT+R}	13 00	019 000	

KEYSTROKE DESCRIPTION	HEX	DECIMAL	NOTE
{ALT+S}	1F 00	031 000	
{ALT+T}	14 00	020 000	
{ALT+U}	16 00	022 000	
{ALT+V}	2F 00	047 000	
{ALT+W}	11 00	017 000	
{ALT+X}	2D 00	045 000	
{ALT+Y}	15 00	021 000	
{ALT+Z}	2C 00	044 000	
{F1}	3B 00	059 000	
{F2}	3C 00	060 000	
{F3}	3D 00	061 000	
{F4}	3E 00	062 000	
{F5}	3F 00	063 000	
{F6}	40 00	064 000	
{F7}	41 00	065 000	
{F8}	42 00	066 000	
{F9}	43 00	067 000	
{F10}	44 00	068 000	
{F11}	85 00	133 000	Enhanced keyboard
{F12}	86 00	134 000	Enhanced keyboard
{SHIFT+F1}	54 00	084 000	
{SHIFT+F2}	55 00	085 000	
{SHIFT+F3}	56 00	086 000	
{SHIFT+F4}	57 00	087 000	
{SHIFT+F5}	58 00	088 000	
{SHIFT+F6}	59 00	089 000	
{SHIFT+F7}	5A 00	090 000	
{SHIFT+F8}	5B 00	091 000	
{SHIFT+F9}	5C 00	092 000	
{SHIFT+F10}	5D 00	093 000	
{SHIFT+F11}	87 00	135 000	Enhanced keyboard
{SHIFT+F12}	88 00	136 000	Enhanced keyboard
{CTRL+F1}	5E 00	094 000	
{CTRL+F2}	5F 00	095 000	
{CTRL+F3}	60 00	096 000	
{CTRL+F4}	61 00	097 000	
{CTRL+F5}	62 00	098 000	
{CTRL+F6}	63 00	099 000	
{CTRL+F7}	64 00	100 000	

KEYSTROKE DESCRIPTION	HEX	DECIMAL	NOTE
{CTRL+F8}	65 00	101 000	
{CTRL+F9}	66 00	102 000	
{CTRL+F10}	67 00	103 000	
{CTRL+F11}	89 00	137 000	Enhanced keyboard
{CTRL+F12}	8A 00	138 000	Enhanced keyboard
{ALT+F1}	68 00	104 000	
{ALT+F2}	69 00	105 000	
{ALT+F3}	6A 00	106 000	
{ALT+F4}	6B 00	107 000	
{ALT+F5}	6C 00	108 000	
{ALT+F6}	6D 00	109 000	
[ALT+F7}	6E 00	110 000	
{ALT+F8}	6F 00	111 000	
{ALT+F9}	70 00	112 000	
{ALT+F10}	71 00	113 000	
{ALT+F11}	8B 00	139 000	Enhanced keyboard
{ALT+F12}	8C 00	140 000	Enhanced keyboard

EXTENDED CHARACTERS

CHARACTER	HEX	DEC
☺	00 01	000 001
☻	00 02	000 002
♥	00 03	000 003
♦	00 04	000 004
♣	00 05	000 005
♠	00 06	000 006
•	00 07	000 007
◘	00 08	000 008
○	00 09	000 009
◙	00 0A	000 010
♂	00 0B	000 011
♀	00 0C	000 012
♪	00 0D	000 013
♫	00 0E	000 014
✲	00 0F	000 015
►	00 10	000 016
◄	00 11	000 017
↕	00 12	000 018
‼	00 13	000 019

CHARACTER	HEX	DECIMAL	NOTE
¶	00 14	000 020	
§	00 15	000 021	
▬	00 16	000 022	
↨	00 17	000 023	
↑	00 18	000 024	
↓	00 19	000 025	
→	00 1A	000 026	
←	00 1B	000 027	
∟	00 1C	000 028	
↔	00 1D	000 029	
▲	00 1E	000 030	
▼	00 1F	000 031	
Ç	00 80	000 128	
ü	00 81	000 129	
é	00 82	000 130	
â	00 83	000 131	
ä	00 84	000 132	
à	00 85	000 133	
å	00 86	000 134	
ç	00 87	000 135	
ê	00 88	000 136	
ë	00 89	000 137	
è	00 8A	000 138	
ï	00 8B	000 139	
î	00 8C	000 140	
ì	00 8D	000 141	
Ä	00 8E	000 142	
Å	00 8F	000 143	
É	00 90	000 144	
æ	00 91	000 145	
Æ	00 92	000 146	
ô	00 93	000 147	
ö	00 94	000 148	
ò	00 95	000 149	
û	00 96	000 150	
ù	00 97	000 151	
ÿ	00 98	000 152	
Ö	00 99	000 153	
Ü	00 9A	000 154	

CHARACTER	HEX	DECIMAL	NOTE
¢	00 9B	000 155	
£	00 9C	000 156	
¥	00 9D	000 157	
₧	00 9E	000 158	
ƒ	00 9F	000 159	
á	00 A0	000 160	
í	00 A1	000 161	
ó	00 A2	000 162	
ú	00 A3	000 163	
ñ	00 A4	000 164	
Ñ	00 A5	000 165	
ª	00 A6	000 166	
º	00 A7	000 167	
¿	00 A8	000 168	
⌐	00 A9	000 169	
¬	00 AA	000 170	
½	00 AB	000 171	
¼	00 AC	000 172	
¡	00 AD	000 173	
«	00 AE	000 174	
»	00 AF	000 175	
	00 B0	000 176	
░	00 B1	000 177	
▒	00 B2	000 178	
│	00 B3	000 179	
┤	00 B4	000 180	
╡	00 B5	000 181	
╢	00 B6	000 182	
╖	00 B7	000 183	
╕	00 B8	000 184	
╣	00 B9	000 185	
║	00 BA	000 186	
╗	00 BB	000 187	
╝	00 BC	000 188	
╜	00 BD	000 189	
╛	00 BE	000 190	
┐	00 BF	000 191	
└	00 C0	000 192	
┴	00 C1	000 193	

CHARACTER	HEX	DECIMAL	NOTE
┬	00 C2	000 194	
├	00 C3	000 195	
─	00 C4	000 196	
┼	00 C5	000 197	
╞	00 C6	000 198	
╟	00 C7	000 199	
╚	00 C8	000 200	
╔	00 C9	000 201	
╩	00 CA	000 202	
╦	00 CB	000 203	
╠	00 CC	000 204	
═	00 CD	000 205	
╬	00 CE	000 206	
╧	00 CF	000 207	
╨	00 D0	000 208	
╤	00 D1	000 209	
╥	00 D2	000 210	
╙	00 D3	000 211	
╘	00 D4	000 212	
╒	00 D5	000 213	
╓	00 D6	000 214	
╫	00 D7	000 215	
╪	00 D8	000 216	
┘	00 D9	000 217	
┌	00 DA	000 218	
█	00 DB	000 219	
▄	00 DC	000 220	
▌	00 DD	000 221	
▐	00 DE	000 222	
▀	00 DF	000 223	
α	00 E0	000 224	
β	00 E1	000 225	
Γ	00 E2	000 226	
π	00 E3	000 227	
Σ	00 E4	000 228	
σ	00 E5	000 229	
µ	00 E6	000 230	
τ	00 E7	000 231	
Φ	00 E8	000 232	

CHARACTER	HEX	DECIMAL	NOTE
Θ	00 E9	000 233	
Ω	00 EA	000 234	
δ	00 EB	000 235	
∞	00 EC	000 236	
ϕ	00 ED	000 237	
ε	00 EE	000 238	
∩	00 EF	000 239	
≡	00 F0	000 240	
±	00 F1	000 241	
≥	00 F2	000 242	
≤	00 F3	000 243	
⌠	00 F4	000 244	
⌡	00 F5	000 245	
÷	00 F6	000 246	
≈	00 F7	000 247	
°	00 F8	000 248	
●	00 F9	000 249	
•	00 FA	000 250	
√	00 FB	000 251	
η	00 FC	000 252	
²	00 FD	000 253	
■	00 FE	000 254	
	00 FF	000 255	