

Looking after the Redcliffe Advisory website

This guide is for whoever looks after the website day to day. You do not need any **technical knowledge**. Everything is done in a web browser by clicking and typing. Nothing you do by following this guide can break the design.

This same guide is available inside the website's dashboard, under **Website guide** in the left-hand menu, so you never need to find this file again.

In a hurry? Jump to the worked examples: [changing the Summit agenda](#), [changing or adding photographs](#), [announcing something](#), [adding speakers](#), [the Register button](#), [sponsors and collaborators](#), [writing an article](#) and [Karina's LinkedIn posts](#).

1. Logging in

The website is hosted by **Hostinger**, and it runs on **WordPress**. WordPress is the program you use to edit the website. You will only ever need two addresses:

Where	Address	What it is for
Hostinger	https://hpanel.hostinger.com	Backups, the domain name, and the button that takes you into WordPress
WordPress	<code>https://your-website-address/wp-admin</code>	Editing the website: words, pictures, pages, enquiries

The easy way in:

1. Go to <https://hpanel.hostinger.com> and log in with the Hostinger account.
2. Click **Websites** in the left-hand menu.
3. Next to the website, click the **WP Admin** button.

That opens the WordPress dashboard without asking for another password.

The direct way in: go to `https://your-website-address/wp-admin` and enter the WordPress username and password. If you have forgotten the password, click **Lost your password?** on that screen and follow the email.

You should see: the WordPress dashboard, with a dark menu down the left-hand side. Near the top of that menu, just under **Dashboard**, is **Website guide**, which is this document.

2. The places you will use

Almost everything you do lives in one of these places in the left-hand menu.

I want to...	Go to
Change any words or any photograph already on the website: a headline, a date, a name, a paragraph, the announcement strip, the footer	Appearance → Customize
Change the Summit agenda (times, sessions, speakers, the note at the bottom)	Pages → Agenda → Edit
Add something new to a page: a new section of text, a speaker, a new photograph, a gallery, a quotation	Pages
Add, change or remove a sponsor or collaborator (name, logo, which group it is in)	Sponsors
Write and publish an article for the Articles page	Posts → Add New
Read the messages sent through the contact form	Enquiries

The rest of this guide walks through each one.

3. Changing words and pictures that are already there

Every piece of text on the website and every photograph can be changed. There are two ways to find the thing you want to change; both end in the same place.

The quick way: click the pencil

1. In the left-hand menu, click **Appearance**, then **Customize**. The website appears on the right, with a small blue **pencil** next to every piece of text and in the corner of every photograph.
2. Use the website on the right as normal to get to the page you want (click the menu, scroll down). The pencils come with you.
3. Click the pencil next to the words you want to change. A box with those words opens on the left.
4. Type your change. The website on the right updates as you type.
5. Click the blue **Publish** button at the top when you are happy.

The other way: find it in the list

1. In **Appearance** → **Customize**, click **Redcliffe Advisory** on the left.
2. Click the page you want, for example **Summit page**. Every piece of text on that page is listed, in the order it appears on the page, followed by the photographs and the switches for hiding whole sections.
3. Change the text in a box, or click **Select image** under a photograph.
4. Click **Publish**.

Top of every page holds the announcement strip and the logo; **Bottom of every page** holds the footer.

Four useful things to know:

- **Clearing a box puts the original wording back.** Nothing can be left blank by accident.
- **A little formatting is allowed** in the boxes. `<em>word</em>` makes a word italic and blue, as in the headlines; `<br />` starts a new line. Otherwise just type plainly.
- **Each page has switches** to show or hide whole sections of the page (for example, hiding the testimonials on the homepage). Untick the box and click **Publish**.
- **Nothing changes on the live website until you click Publish.** If you get in a muddle, close the Customizer (the × at the top left) without publishing and nothing has happened.

The one exception: the programme on the **Agenda** page is not in the Customizer. It is edited under **Pages**, because it grows and changes. See [section 15](#).

4. Adding a new section to a page

Every page has room underneath its designed part for as many new sections as you like. This is where you add news, a new photograph, a gallery of pictures from an event, a quotation, a list of speakers, or anything else.

1. In the left-hand menu, click **Pages**.
2. Hover over the page you want to add to, and click **Edit**.
3. You will see a mostly empty page with the page's name at the top. **That is normal.** The designed part of the page is not shown here. A blue note at the top reminds you that whatever you add here appears at the **bottom** of the page on the website. (The Agenda page is different: it shows the whole programme.)
4. Click the **+** button in the middle of the page (or the blue **+** at the top left).
5. Click the **Patterns** tab, then choose **Redcliffe Advisory** from the list. You will see ready-made sections that match the design of the website:

Pattern	What it gives you
Heading and text	A small label, a large heading and a few paragraphs, like the sections already on the site
Photograph with caption	One big photograph with a line of text underneath
Text beside a photograph	A photograph on one side, heading and text on the other
Photo gallery	A grid of photographs
Quotation	A large quotation with the name of the person who said it
Two columns of text	Two short pieces of text side by side
Button	A button that links to another page
Speaker	A photograph, a name, a role and a line about one speaker
Agenda: a time slot	One line of the Summit programme (Agenda page)
Agenda: part of the day	A small heading such as <i>Afternoon</i> (Agenda page)

- Click the one you want. It appears on the page filled with example text and pictures.
- Click on any text and type over it. Click on any picture and press **Replace** to swap it for one of your own (see the next section).
- Click the blue **Update** button at the top right.
- Click **View page** in the message that appears, and scroll to the bottom of the page to see your new section on the live website.

You can add as many sections as you like. Press **+** again to add another underneath.

To move a section up or down: click on it, then use the **up and down arrows** in the small toolbar that appears above it.

To remove a section: click on it, click the **three dots** at the right-hand end of its toolbar, and choose **Delete**. Then click **Update**.

To undo a mistake: press the **undo arrow** at the very top left of the editor (or press Ctrl+Z, or Cmd+Z on a Mac). If you have already clicked Update, see [Undoing a published change](#).

5. Adding or replacing a photograph

A photograph that is part of the design

The portrait on the homepage, the Summit pictures, the six photographs in the Summit gallery, the logo: all of these are changed in **Appearance** → **Customize**. Either click the **pencil** in the corner of the photograph, or find it in the list for that page. Then:

1. Click **Select image**.
2. Click **Upload files** and choose a photograph from your computer, or click **Media Library** to use one that is already on the website.
3. Click the blue **Choose image** button at the bottom right.
4. The website on the right shows the new photograph. Click **Publish**.

To go back to the original photograph, click **Remove** under it and **Publish**.

The Summit gallery photographs each have a **caption** box in the same list, so you can change the words underneath a picture at the same time.

A photograph in a new section

Any picture in a pattern from section 4 can be replaced:

1. Click on the picture.
2. In the toolbar above it, click **Replace**.
3. Choose **Upload** to use a photograph from your computer, or **Open Media Library** to use one that is already on the website.
4. Once the picture is in place, click **Update** at the top right.

To add a picture on its own, press **+**, type **Image**, and choose the **Image** block. Then click **Upload**.

A few tips about photographs

- **Size:** photographs straight from a phone or camera are fine. WordPress makes smaller copies automatically. Very large files (over 10 MB) may be refused; if so, email the picture to yourself first, choosing a smaller size.
- **Shape:** the design uses landscape (wider than tall) photographs in most places. Portrait photographs work but may be cropped. The Summit gallery has one wide picture, one tall one and one full-width one; the names in the Customizer say which is which.
- **Describe the picture:** after adding a picture, there is a box on the right called **Alternative text**. Type a short description, such as "Karina Robinson speaking at Mansion House". This is read aloud to visitors who cannot see the picture, and helps Google.

- **All pictures are kept** under **Media** in the left-hand menu. You can reuse any of them on any page.
-
-

6. The menu along the top

1. In the left-hand menu, click **Appearance**, then **Menus**.
2. Drag items up and down to reorder them, or click the small arrow on an item to rename or remove it.
3. To add a page to the menu, tick it in the **Pages** box on the left and click **Add to Menu**.
4. Click **Save Menu**.

The dark blue **Enquire** button at the end of the menu is just an ordinary link with a special marking. If it ever stops looking like a button: click the arrow on that item, find the box called **CSS Classes** and type `cta` into it, then **Save Menu**. (If you cannot see a CSS Classes box, click **Screen Options** at the very top right of the screen and tick **CSS Classes**.)

7. Enquiries from the contact form

Every message sent through the Contact page is saved on the website **and** emailed to you.

- **To read messages:** click **Enquiries** in the left-hand menu. Each one shows the sender's name, email address and topic. Click a name to read the full message.
- **To reply:** press **Reply** on the email you received. It goes straight back to the person who wrote it.
- **To change which email address receives the messages:** go to **Appearance** → **Customize** → **Redcliffe Advisory** → **Contact page**, change the address under **Send enquiries to**, and click **Publish**.

If a message is listed under Enquiries but no email arrived, check your spam folder first. If emails never arrive, see [If something looks wrong](#). The messages are safe under Enquiries either way.

8. Undoing a published change

Every time you click **Update** on a page, WordPress keeps the old version.

1. Open the page under **Pages** → **Edit**.
2. On the right-hand side, under **Page**, click **Revisions**.
3. Drag the slider at the top to go back in time. The screen shows what changed.
4. Click **Restore This Revision**, then **Update**.

Changes made in **Appearance** → **Customize** do not keep old versions, but clearing a box always puts the original wording back, and **Remove** under a photograph puts the original photograph back.

If the whole website needs to go back to an earlier day, use a Hostinger backup — see the next section.

9. Backups

Hostinger takes a copy of the whole website automatically, **once a week**. You do not need to do anything for this to happen.

To see your backups:

1. Log in at <https://hpanel.hostinger.com> and click **Websites**.
2. Click **Dashboard** next to the website.
3. In the left-hand menu, click **Files**, then **Backups**. The **Latest backup** date is shown at the top.

To go back to a backup:

1. On the same **Backups** screen, click **View backups**.
2. Choose the date you want, click **Restore** and confirm.

This puts the whole website back exactly as it was on that day, including any messages, pages and pictures added since. Use it only when something has gone badly wrong.

Backups you take yourself (before a big change) are not included in the current hosting plan; Hostinger offers them as an upgrade on the Backups screen. Without one, the safety net is the weekly copy plus the page **Revisions** described in section 8.

10. Keeping the website up to date

WordPress itself gets small updates from time to time. Hostinger installs these for you automatically. You do not need to do anything.

If you ever see a number in a red circle next to **Updates** in the left-hand menu, it is safe to click **Updates** and then **Update Now**.

Do not install extra plugins or themes unless someone technical has asked you to. The website does not need any, and each one is a possible way for things to go wrong.

11. Putting a new version of the design live

Sometimes a designer or developer will give you a new version of the website's design. It always arrives as **one file** called `redcliffe-advisory.zip`. You do not unzip it. To put it live:

1. Save the zip file somewhere you can find it, such as your Desktop.
2. In WordPress, click **Appearance**, then **Themes**.
3. Click **Add New Theme** at the top (on some versions it says **Add New**).
4. Click **Upload Theme**.
5. Click **Choose File**, pick `redcliffe-advisory.zip`, and click **Install Now**.
6. WordPress notices that the design is already installed and shows you a comparison of the two versions. Click **Replace active with uploaded**.
7. Wait a few seconds.

You should see: a message saying the theme was installed successfully. Open the website and check it looks right.

What is kept: all your words, pictures, extra sections, the agenda, menu changes and enquiries. A new version of the design never touches those.

If you are unsure whether to do this: check the date of the latest weekly backup first (section 9). If anything looks wrong afterwards, that backup can be restored.

12. Pointing redcliffeadvisory.com at the website

Until this is done, the website lives at its temporary Hostinger address (ending in `.hostingersite.com`), and the public still sees the old website. Do this only once you are happy with the new one.

1. Log in at <https://hpanel.hostinger.com>.
2. Click **Websites**, then **Dashboard** next to the website.

3. At the top of the dashboard there is a red note saying *Every website needs a domain*. Click its **Connect domain** button.
4. On the screen *What domain do you want to connect to this site?*, type `redcliffeadvisory.com` and click **Next**.
5. Hostinger will tell you what to do next. If the domain is already with Hostinger, it connects on its own. If it is with another company, Hostinger shows you two or three settings (called **nameservers** or **DNS records**) to enter at that company. That company's support desk can do this for you if you send them the settings.
6. Once connected, Hostinger sets up the padlock (HTTPS) automatically. There is nothing to buy.

It can take anywhere from a few minutes to a day for the change to show everywhere. If in doubt, the **Agent** button at the bottom right of hPanel opens Hostinger's help chat, which will check it for you.

Afterwards, in WordPress go to **Settings** → **General** and make sure both address boxes show `https://www.redcliffeadvisory.com`.

Old links to the Summit page — including every past `...summit-2025` and `...summit-2026` address — start forwarding to the current Summit page automatically once the domain is connected. There is nothing to set up.

13. If something looks wrong

What you see	What it means	What to do
A change does not appear on the website	It was not published	Customizer: click Publish . Page: click Update
A change appears for you but not for someone else	Their browser is showing an old copy	Ask them to press Ctrl+F5 (Cmd+Shift+R on a Mac). If it persists, in WordPress hover LiteSpeed Cache in the top bar and click Purge All , or in hPanel open the site's Dashboard and click Clear cache
A new section appears but looks unstyled	The browser is showing an old copy	Press Ctrl+F5, then Purge All as above
Pages look plain, with no colours or fonts	The design is not switched on	Appearance → Themes → click Activate on Redcliffe Advisory

What you see	What it means	What to do
The menu at the top is empty	The menu was unassigned	Appearance → Menus → at the bottom tick Primary menu → Save Menu
A menu link goes to the homepage	That page was deleted	Pages → Trash → hover the page → Restore . Never delete the nine main pages
The homepage shows a list of blog posts	The front page setting changed	Settings → Reading → <i>Your homepage displays: A static page</i> → Homepage: Home → Save Changes
The Articles page shows a list of blog posts instead of the designed page	The "Posts page" setting is pointing at it	Settings → Reading → set Posts page to — Select — → Save Changes
A post you added does not appear on the Articles page	It is still a Draft	Open Posts , click the post, then Publish (top right)
An article should link to another website but opens on this site instead	The External web address box was left empty	Open the post, find Where this article appears on the right, paste the address, Update
The Register button on the Summit page goes to the wrong place, or its wording is wrong	The old address or wording is still saved	Appearance → Customize → Summit page: Register button text and Registration page address , then Publish (section 19)
The Register button has disappeared	The Registration page address was cleared, which hides the button	Appearance → Customize → Summit page → Registration page address , paste the booking link, Publish
The two buttons at the bottom of the Agenda page point to the wrong place or say the wrong thing	Their wording and addresses are kept in the Customizer	Appearance → Customize → Agenda page , change First closing button and Second closing button , Publish (section 15)
A sponsor you added is not on the Summit page	It is still a Draft , or the browser or the site is showing an old copy	Sponsors : the sponsor must say Published and show a tier. Then press Ctrl+F5; if it is still missing, hPanel → site Dashboard → Clear cache

What you see	What it means	What to do
A logo looks the wrong colour or sits on the wrong tile	The website's automatic tile choice is not right for this logo	Sponsors → click the sponsor → Tile colour → choose White tile or Dark blue tile → Update (section 20)
Karina's LinkedIn posts do not show on the homepage	The feed is loaded from LinkedIn's partner service and can be slow or blocked by an ad-blocker	Wait a few seconds and scroll down; try without an ad-blocker. If it never shows, see section 22
The Agenda page shows the old programme, not what you typed	The page has not been updated, or the browser is showing an old copy	Open Pages → Agenda → Edit and click Update ; then Ctrl+F5
A block on the Agenda page says "unexpected or invalid content"	Something was pasted in that the editor does not understand	Click Attempt recovery . If that does not help, click the three dots on that block, choose Delete , and add a fresh Agenda: a time slot
Enquiries arrive in WordPress but no email comes	Email sending is off	Check spam first. Then ask Hostinger's help chat (the Agent button in hPanel) to "enable email sending from WordPress". The messages are safe under Enquiries in the meantime
A photograph you uploaded is not showing	The change was not published	Reopen where you changed it and click Publish (Customizer) or Update (page)
"The uploaded file exceeds the maximum size"	The picture is very large	Email the picture to yourself choosing a smaller size, then upload that
You cannot log in	Wrong password, or the WordPress user changed	Use WP Admin from https://hpanel.hostinger.com , which does not need the WordPress password

Nothing in this guide can break the design. If an edit goes wrong, delete the section or clear the box, and the original comes back.

14. Getting help

- **Hostinger** answers questions about logging in, backups, the domain name, email and anything about the hosting itself. Click the **Agent** button at the bottom right of <https://hpanel.hostinger.com> to open its help chat, 24 hours a day.
 - **The design and the theme file** come from whoever built the website. Ask them for a new `redcliffe-advisory.zip` if the design itself needs to change, and follow section 11 to put it live.
-

15. Example: updating the 2026 Summit agenda

The programme for The City Quantum & AI Summit lives on the **Agenda** page. It is a list of time slots, each with a time, a title and a short description, grouped under headings such as *Morning* and *Afternoon*. You change it the way you would change a document.

Before you start: log in (section 1), click **Pages** in the left-hand menu, hover over **Agenda** and click **Edit**. You will see the programme exactly as it appears on the website, with a blue note at the top. Close the note with its ✕. (The first time, WordPress may show a short *Welcome to the editor* tour; close it with its ✕ too.)

Changing the time, title or description of a session

1. Click on the words you want to change, for example the title *Keynote — the state of quantum & AI*.
2. Delete the old words and type the new ones. To make a word italic and blue (as in *opening address*), select it and press Ctrl+I (Cmd+I on a Mac).
3. Click the blue **Update** button at the top right.
4. Click **View page** in the message that appears, or open the website and go to **Summit** → **Agenda**, to see the change live.

Times work the same way: click **09.45**, type **10.00**, click **Update**.

Adding a session

1. Click on the session **above** where the new one should go, so it is highlighted.
2. Click the blue **+** at the top left of the screen.
3. Click the **Patterns** tab, click **Redcliffe Advisory**, and click **Agenda: a time slot**. A new slot appears underneath the one you highlighted, filled with example words.

4. Click each part of it and type: the time, the title, then the description (who is speaking, and what the session is about).
5. Click **Update**.

If the slot appeared in the wrong place, click on it and use the **up and down arrows** in the small toolbar above it to move it.

A quicker way for a similar session: click on an existing slot, click the **three dots** in its toolbar, choose **Duplicate**, and then change the copy.

Removing a session

1. Click on the slot you want to remove, so it is highlighted. Make sure the whole slot is highlighted (a thin blue outline around the time and the title together). If only the title is highlighted, press **Escape** and then click the slot's left-hand edge, or use the arrow above the toolbar that says **Select parent block** until the outline covers the whole slot.
2. Click the **three dots** at the right-hand end of the toolbar and choose **Delete**.
3. Click **Update**.

Adding a new part of the day (for example, *Evening*)

1. Click on the last session of the previous part, so it is highlighted.
2. Click the blue **+** at the top left, then **Patterns** → **Redcliffe Advisory** → **Agenda: part of the day**. A small heading appears.
3. Click the heading and type its name, for example **Evening**.
4. Add sessions under it as described above.
5. Click **Update**.

Changing a speaker's name in the agenda

Speakers are mentioned in the description of each session. Click the description, change the name, click **Update**. If the speaker line-up has its own section on the Summit page, see [section 18](#).

Changing the date, venue or theme

- **On the Agenda page**, the three facts at the top of the programme (Date, Venue, Theme) are part of the same editor. Click **7 October 2026**, type the new date, click **Update**.
- **Everywhere else** (the Summit page, the homepage, the announcement strip at the top, the footer) the date is ordinary text: go to **Appearance** → **Customize**, click the **pencil** next to each mention, change it, and click **Publish**. The quickest way to find every mention is to click **Redcliffe Advisory** → **Summit page** in the Customizer, where each piece of text is listed with its wording as the label.

Changing the note at the bottom

The italic note under the programme is ordinary text in the same editor. Click and type, then **Update**.

Changing the two buttons at the bottom of the programme

The two buttons under the programme (by default *Register here* and *Back to the Summit*) are set in the Customizer, not in the page editor, so they can never be broken by accident:

1. **Appearance** → **Customize** → **Agenda page**.
2. Under **First closing button: text**, type what the button should say, for example *Reserve your spot*. Its address is in **First closing button: address**. Leave that empty to use the registration page address you set for the Register button (section 19), or paste a different web address.
3. Do the same for the **Second closing button**. Leave its address empty to send people back to the Summit page.
4. To hide a button, clear its text. Click **Publish**.

If you would rather start again

Nothing you do here is final. Under **Page** → **Revisions** on the right-hand side you can go back to any earlier version of the agenda (section 8).

16. Example: changing and adding photographs

Swapping one of the six Summit gallery photographs

The Summit page has a gallery of six photographs under *From the floor*. To replace, say, the third one with a photograph from this year's reception:

1. Have the new photograph saved on your computer (a JPEG from a phone or camera is fine).
2. In the left-hand menu, click **Appearance**, then **Customize**.
3. On the website on the right, click **Summit** in the menu, scroll down to the gallery and click the **pencil** in the corner of the third photograph. (Or, on the left, click **Redcliffe Advisory**, then **Summit page**, and scroll down to **Gallery photo 3**.)
4. Click **Select image**, then **Upload files**, then **Select Files**, and pick the photograph on your computer.

5. While it uploads, fill in **Alt Text** on the right with a short description, such as "Guests at the Summit reception, Mansion House".
6. Click the blue **Choose image** button at the bottom right.
7. The website on the right shows the new photograph in place. Find **Gallery photo 3 caption** in the same list on the left and type the words that appear under the picture.
8. Click **Publish** at the top.

Do the same for any of the six. **To put the original photograph back**, click **Remove** under it and **Publish**.

Replacing the portrait on the homepage

1. **Appearance** → **Customize**. On the homepage on the right, click the **pencil** in the corner of the portrait (or **Redcliffe Advisory** → **Homepage** → **Portrait photograph**).
2. **Select image** → **Upload files**, choose the new portrait, fill in **Alt Text**, click **Choose image**.
3. Check it looks right on the right-hand side, then click **Publish**.

The portrait is shown taller than it is wide, so choose a photograph in that shape; WordPress will crop a landscape one to fit.

Adding a set of new photographs from an event

New photographs that are not replacing an existing one go in a new section on whichever page suits (usually the Summit page):

1. **Pages** → hover over **Summit** → **Edit**. Close the blue note.
2. Click the **+** in the middle of the page → **Patterns** tab → **Redcliffe Advisory** → **Heading and text**. Type a label such as **Summit 2026**, a heading such as **The day in pictures**, and a sentence or two. (If you do not want words, skip this step.)
3. Click below that section, press **+** again → **Patterns** → **Redcliffe Advisory** → **Photo gallery**. Three example photographs appear.
4. Click on the first example photograph, click **Replace** in its toolbar, choose **Upload** and pick your photograph. Repeat for the other two.
5. To add more photographs to the gallery, click on the gallery (its outline should surround all the pictures), then click the **+** at the end of the gallery, or use the **Add** button in the right-hand panel, and upload more. You can add as many as you like; they arrange themselves in rows of three.
6. Click **Update** at the top right, then **View page**. Scroll to the bottom of the Summit page to see the gallery live.

For one big photograph with a caption use **Photograph with caption** instead of **Photo gallery**, and type the caption in the box under the picture.

To change the order of photographs in a gallery, click one and use the left and right arrows in its toolbar. To remove one, click it and press the **Delete** key on your keyboard.

Changing the logo

Appearance → **Customize** → **Redcliffe Advisory** → **Top of every page**, then **Select image** under the logo. Use a picture with a transparent or white background, wider than it is tall. Click **Publish**.

17. Example: making an announcement

The thin strip across the very top of every page (currently *7 October 2026 · See the agenda*) is the place for short announcements: a date change, a new speaker, "registration now open".

1. **Appearance** → **Customize**. Click the **pencil** at the very top of the page next to the strip's words, or click **Redcliffe Advisory** → **Top of every page**.
2. **Announcement text** is the message. **Announcement link text** is the short link at the end of it. Type your announcement, keeping it to one line.
3. The strip links to the Agenda page unless you say otherwise. To send visitors somewhere else (a registration form, a news article), paste the address into **Announcement link goes to**. Clear the box to go back to the Agenda.
4. Click **Publish**. The strip changes on every page at once.

For a longer announcement, add a **Heading and text** section to the homepage under **Pages** → **Home** → **Edit** (section 4), and mention it in the strip.

To take the strip away altogether, untick the switch for it at the bottom of the **Top of every page** list, and **Publish**.

18. Example: adding the speakers

As speakers are confirmed, add them to the Summit page, one section per person:

1. **Pages** → hover over **Summit** → **Edit**. Close the blue note.
2. Click **+** → **Patterns** → **Redcliffe Advisory** → **Heading and text**. Type the label **Speakers** · **2026** and a heading such as **Who is speaking**. Delete the example paragraphs if you do

not need them (click one, three dots, **Delete**).

3. Click below it, press **+** → **Patterns** → **Redcliffe Advisory** → **Speaker**. A photograph, a name, a role line and a short paragraph appear.
4. Click the photograph → **Replace** → **Upload**, and choose the speaker's picture (a square or portrait head-and-shoulders photograph looks best).
5. Click the name and type the speaker's name; click the role line and type their title and organisation; click the paragraph and type a sentence about them or their session.
6. For the next speaker, click on the one you just made, click the **three dots** in its toolbar and choose **Duplicate**, then change the copy. Or press **+** and choose **Speaker** again.
7. Click **Update**, then **View page**. The speakers appear at the bottom of the Summit page, under the designed part.

If a speaker drops out, open the page, click their section, three dots, **Delete**, then **Update**.

To mention a speaker in the programme as well, change the description of their session on the Agenda page (section 15).

19. Example: the Register button

Beside **See the 2026 agenda** in the Summit page's opening section there is a second button, **Register**, that sends people straight to wherever booking happens: Cvent, Eventbrite, a form, anywhere. The first button under the programme on the Agenda page sends people to the same place.

1. **Appearance** → **Customize** → **Summit page**.
2. Find **Register button text** and type what the button should say, for example *Register* or *Reserve your place*.
3. Find **Registration page address** and paste the booking link.
4. Click **Publish**.

The website always uses the current address, so nothing else needs to change. **Clear the address and the Register button disappears**, which is useful between events; paste a new one and it comes back.

Access in the same opening section is ordinary text again. If it still holds a long web address from an earlier version, change it to a short phrase such as *Open to all* or *By invitation*, then **Publish**.

20. Example: sponsors and collaborators

Every sponsor and collaborator is kept under **Sponsors** in the left-hand menu, one entry for each organisation. The Summit page shows them automatically, grouped under a heading for each level (a **tier**): Gold Sponsor, Dinner Sponsor, Silver Sponsor, Bronze Sponsors, Collaborators and Partners. Each logo sits in a tile of the same shape, and the website works out the rest: it trims the empty space around a logo, fits it inside its tile without stretching or cutting it, chooses a white or a dark blue tile so that the logo can be seen, puts as many logos on a row as fit the screen, and stacks them on a phone. **You never have to resize or crop a logo.**

Adding one sponsor

1. **Sponsors** → **Add sponsor**.
2. Type the organisation's **name** at the top.
3. In the **About this sponsor** box, open the **Tier** list and choose the level (Gold Sponsor, Collaborators, and so on).
4. On the right, in the **Logo** box, click **Choose the logo** and pick the file from the Media Library, or **Upload** a new one.
5. Optionally, fill in **Website address** (the logo then links there) and, for Partners, **A few words about the role**.
6. Click **Publish**. Once a logo is chosen, **How the logo will look** at the bottom of the **About this sponsor** box shows the finished tile.

A PNG with a transparent background is best, but any image works. **Tile colour** is set to **Automatic**; change it only if a logo looks wrong: **White tile** for dark or coloured logos, **Dark blue tile** for white logos.

Adding many logos in one go

Sponsors → **Add several logos** lists pictures in the Media Library that are not yet sponsors. Tick the ones you want, choose their tier, check the names the website guessed from the file names, and click **Add the ticked logos as sponsors**.

Logos you placed on the Summit page yourself

If you placed logos directly on the Summit page in the page editor, the **Add several logos** screen has a section at the top, **Logos already on your Summit page**. Each logo is listed under the heading you gave it, with a suggested name and tier. Check them, then click **Move these logos into Sponsors**. They become ordinary sponsors and are taken off the page so they are not shown twice. WordPress keeps the earlier version of the page, which you can

bring back under **Pages** → **Summit** → **Revisions** if you change your mind. Until you do this, logos placed by hand still show, but they are not arranged for you.

Changing the order, the tier, or removing a sponsor

- **Order inside a tier:** open the sponsor and set **Order in its tier** on the right (10, 20, 30...). Smaller numbers come first; the same number falls into alphabetical order.
- **Move a sponsor to another tier:** open it and choose a different **Tier** in the **About this sponsor** box.
- **Remove a sponsor:** hover over it in the list and click **Trash**.
- **Hide it for now:** open it, change **Status** to **Draft**, and **Update**.

Tiers

Sponsors → **Tiers** shows the six levels. For each you can change:

Setting	What it does
Name	The heading above the logos
Position on the page	A number: smaller comes first (Gold 10, Dinner 20, Silver 30...). Leave gaps so a new tier can go between
Logo size	From Small (fits the most across the page) to Largest (for one or two headline sponsors)
Show names	Writes the organisation's name under each logo. Partners have this on by default

To add a level such as *Media partner*, fill in the **Add a tier** form on the left (name, position, size) and click the button at its foot. A tier with no sponsors is never shown on the website.

Where they appear

On the Summit page, in the blue **Collaborators · 2026** band. Its heading and introduction are ordinary text you can change in **Appearance** → **Customize** → **Summit page**. The original list of example names in that band is replaced by your sponsors as soon as the first one is published, so the two never appear together; if every sponsor is removed, the example names come back. To hide the whole band, untick **Show: Collaborators** on the same Customizer page.

If a new sponsor does not show: check that its status says **Published** and that a tier is chosen. If the site has a cache, press Ctrl+F5, or in hPanel open the site's **Dashboard** and click **Clear cache** (section 13).

21. Example: writing an article

Articles are written the ordinary WordPress way, under **Posts**, not on the Articles page itself. As soon as one is published, it appears there automatically, newest first, and the three already on the site are already showing this way.

1. **Posts** → **Add New**.
2. Type the title, then write the piece in the body underneath, exactly like the page editor (section 4) — headings, paragraphs, photographs and quotations all work the same way.
3. On the right, under **Excerpt**, type one or two sentences summarising it — this is what shows on the Articles page. If left empty, WordPress uses the opening of the piece instead.
4. Under **Categories**, tick one (**Karina's Column**, for example) — its name is the small label shown above the title on the card. Add a new category by typing its name and clicking **Add new category**. Under **Tags**, type any tags you want (for example *quantum*); they are shown with the article.
5. Under **Featured image**, set a photograph — this is the picture shown on the card and, for the article at the top, the large photograph.
6. **Author and date**. Every article shows **Karina Robinson** and the month and year it was published, for example *Karina Robinson · September 2026*. You do not have to do anything. If someone else wrote the piece, find **Author and link** on the right and type their name in **Written by**; leave it empty for Karina. The month and year come from the date of publication; to backdate a piece, click the date next to **Publish** in the right-hand panel and choose an earlier one.
7. If the piece was written for somewhere else — The Quantum Insider, LSE, a partner site — type that page's web address into **Published elsewhere? Web address** in the same **Author and link** box. The card then sends readers straight there instead of to a page on this site; leave it empty for an article people read here.
8. Click **Publish** (top right).

To change the default author for the whole site (for example, if Karina is replaced by someone else), go to **Appearance** → **Customize** → **Articles page** → **Author shown on articles**, type the name, and **Publish**.

Long articles are laid out for comfortable reading: a narrow column of text, and quotations set in the middle with extra space on each side. The **Headings** in the editor (Heading 1, 2 and 3) all line up with the text. Use **Quote** for a quotation; the website centres it for you.

The Articles page shows the ten newest articles, the newest one large at the top. Older ones are on **Page 2** and so on, and the small buttons above the list filter by category.

To edit or unpublish an article later, open **Posts**, click it, make the change, and **Update**. Moving it to **Trash** removes its card from the Articles page.

If the **Articles** page ever has no posts on it, it shows the original designed content instead, so it can never look empty.

22. Example: Karina's LinkedIn posts

The homepage has a section, **Karina's recent posts**, that shows her most recent LinkedIn posts, live. New posts appear on the website by themselves a little after Karina publishes them on LinkedIn; **there is nothing for you to update**.

Only the first few posts show at first, so the page stays short. **Show more posts** opens the rest. A **Follow Karina on LinkedIn** link sits underneath.

To change any of it, go to **Appearance** → **Customize** → **Homepage**:

To change...	Find...
The wording of the Show more posts button	LinkedIn “show more” button text
The wording of the follow link	LinkedIn link text
Where the follow link goes (or remove it)	LinkedIn profile address (clear it to remove the link)
Hide the whole section	Untick Show: Karina's LinkedIn posts
The feed itself	LinkedIn posts feed number (SociableKit) — leave this alone unless the feed is replaced

The posts come from a service called SociableKit, connected to Karina's public LinkedIn profile. **If the posts stop showing**, the SociableKit subscription may have lapsed or the feed was deleted; the rest of the homepage is not affected. Ask whoever manages that SociableKit account, and if the feed number changes, paste the new number into **LinkedIn posts feed number**.