

Tanium Appliance User Guide

8 August 2025

Table of Contents

D. C	. O DI. IC OI I	
Reference: Tanii ir	n Core Plattorm Cl	1
Notor Cricc. Tarriar	II OOIC I IALIOIIII OLI	



2025H1 PDF



2024H2PDF



2024H1PDF



PDF archive

Reference: Tanium Core Platform command-line interface in an Appliance deployment

In special cases, such as troubleshooting specific issues with assistance from Tanium Support, you might use the command-line interface (CLI) on Tanium Core Platform Servers to configure platform settings.



- Typically, you change platform settings through Tanium Console or the TanOS menu. For more information, see Tanium Console User Guide: Managing Tanium Core Platform settings and Manage Tanium Core Platform settings on Tanium Appliances.
- For details about the TanOS CLI, which is separate from the Tanium Core Platform CLI, see Reference: TanOS command line interface.



- · Contact Tanium Support for guidance before you create, edit, or delete platform settings.
- You must be granted read-write shell access before using this CLI. See Request read-write restricted shell or full shell access.

The following table lists the locations where the CLI programs reside. For descriptions of the settings that you can edit, see Deployment-related settings reference.

CLI executables on Tanium Appliances

Component	CLI program location
Tanium Server	/opt/Tanium/TaniumServer/TaniumServer
Tanium Module Server	/opt/Tanium/TaniumModuleServer/ TaniumModuleServer
Tanium Zone Server	/opt/Tanium/TaniumZoneServer/ZoneServer
TDownloader: Tanium Server	/opt/Tanium/TaniumServer/TaniumTDownloader

Component	CLI program location
TDownloader: Module Server	/opt/Tanium/TaniumModuleServer/
TDOWTHOAder: Module Server	TaniumTDownloader

CLI examples

The following examples show how to use the CLI.

Display help

```
cmd-prompt>./TaniumServer --help
Usage: TaniumServer [options] <command> [<args>]
General Options:
 -h [ --help ]
                      Print this help message
 -v [ --version ]
                      Print the version
 --verbose
                       Verbose output
Service Options:
  -i
                       Install the service
                       Uninstall the service
  -11
                       Start the service
  -s
                       Stop the service
  -е
Internal Tanium Options - DO NOT USE:
  -d
                       Run without daemonizing
Commands:
 config
                       Manage configuration
 clean-downloads
                       Clean the downloads catalog
 database
                       Manages a database
 global-settings
                       Manages global settings
 license
                       Manages Deployment License
 pki
                       Manages PKI
  registration-secret Manages Client registration secrets
  server-registrations Manages Server registration requests
                       Test an HSM configuration
  test-hsm
  trust-module-certs Add trusted Module Server certificates
For help on a specific command run `TaniumServer COMMAND -h`
```

Display config help

```
cmd-prompt>./TaniumServer config --help
Usage: TaniumServer config <action> [<key>] [<value>]
Actions:
 config list
                                     List all keys and non-protected values
 config list-protected
                                    List all keys and values
  config get <key>
                                    Print non-protected config value
  config get-protected <key>
                                    Print config value
  config set <key> <value>
                                     Set config value and try to guess type
 config set-string <key> <value>
                                    Set string value
  config set-protected <key> <value> Set protected string value
  config set-number <key> <value>
                                      Set numeric value (in decimal or hex notation)
  config remove <key>
                                      Remove config value
```

Example: List configuration settings

When displaying the current settings, note that the CLI output displays (protected) instead of the actual value for settings that are designated as protected, which means they are sensitive in the security sense.

```
cmd-prompt>./TaniumServer config list
Keys:
  - AddressMask: 16777215
  - ConsoleSettingsJSON: C:\Program Files\Tanium\Tanium Server\http\config\console.json
  - DBUserDomain: tam.local
  - DBUserName: taniumsvc
  - LogPath: C:\Program Files\Tanium\Tanium Server\Logs
  - LogVerbosityLevel: 1
  - Logs:
   - Logs.MiniDumpMessages:
      - Logs.MiniDumpMessages.FilterRegex: .*Begin MiniDumper.*
      - Logs.MiniDumpMessages.LogVerbosityLevel: 1
  - ModuleServer: tms1.tam.local, TMS1.tam.local:17477
  - ModuleServerPort: 17477
  - PGDLLPath: C:\Program Files\Tanium\Tanium Server\postgres\bin
  - PKIDatabasePassword: (protected)
  - PGRoot: C:\Program Files\Tanium\Tanium Server\postgres
  - Path: C:\Program Files\Tanium\Tanium Server
  - ProxyPassword: (protected)
  - ProxyPort:
  - ProxyServer:
```

```
- ProxyType: NONE
- ProxyUserid:
- SQLConnectionString: postgres:localhost@dbname=postgres port=5432
- ServerName: 0.0.0.0
- ServerPort: 17472
- ServerSOAPPort: 443
- TrustedCertPath: C:\Program Files\Tanium\Tanium Server\Certs\installedcacert.crt
- TrustedModuleServerCertsPath: C:\Program Files\Tanium\Tanium Server\trusted-module-servers.crt
- Version: 7.7.3.8207
```

Example: Set configuration values

```
cmd-prompt>./TaniumServer config set BypassProxyHostList host1.example.com,192.168.0.1
cmd-prompt>./TaniumServer config get BypassProxyHostList
host1.example.com,192.168.0.1
```

Example: Set configuration values

```
cmd-prompt>./TaniumTDownloader config set ProxyServer 192.168.0.2
cmd-prompt>./TaniumTDownloader config get ProxyServer
192.168.0.2
```

Example: Configure global settings

Example: Add an administrator user

Last updated: 8/1/2025 3:54 PM | Feedback