TopogrElow

TensorFlow API r1.4

tf.layers.conv3d

```
conv3d(
    inputs,
    filters,
    kernel_size,
    strides=(1, 1, 1),
    padding='valid',
    data_format='channels_last',
    dilation_rate=(1, 1, 1),
    activation=None,
    use_bias=True,
    kernel initializer=None.
   bias_initializer=tf.zeros_initializer(),
    kernel_regularizer=None,
    bias_regularizer=None,
    activity_regularizer=None,
    kernel_constraint=None,
    bias_constraint=None,
    trainable=True,
    name=None,
    reuse=None
)
```

Defined in tensorflow/python/layers/convolutional.py.

Functional interface for the 3D convolution layer.

This layer creates a convolution kernel that is convolved (actually cross-correlated) with the layer input to produce a tensor of outputs. If **use_bias** is True (and a **bias_initializer** is provided), a bias vector is created and added to the outputs. Finally, if **activation** is not **None**, it is applied to the outputs as well.

Arguments:

- inputs: Tensor input.
- filters: Integer, the dimensionality of the output space (i.e. the number of filters in the convolution).
- kernel_size: An integer or tuple/list of 3 integers, specifying the depth, height and width of the 3D convolution window. Can be a single integer to specify the same value for all spatial dimensions.
- strides: An integer or tuple/list of 3 integers, specifying the strides of the convolution along the depth, height and width. Can be a single integer to specify the same value for all spatial dimensions. Specifying any stride value != 1 is incompatible with specifying any dilation_rate value != 1.
- padding: One of "valid" or "same" (case-insensitive).
- data_format: A string, one of channels_last (default) or channels_first. The ordering of the dimensions in the
 inputs. channels_last corresponds to inputs with shape (batch, depth, height, width, channels) while
 channels_first corresponds to inputs with shape (batch, channels, depth, height, width).
- dilation_rate: An integer or tuple/list of 3 integers, specifying the dilation rate to use for dilated convolution. Can be a single integer to specify the same value for all spatial dimensions. Currently, specifying any dilation_rate value!= 1 is incompatible with specifying any stride value!= 1.
- activation: Activation function. Set it to None to maintain a linear activation.

- use_bias: Boolean, whether the layer uses a bias.
- kernel_initializer: An initializer for the convolution kernel.
- bias_initializer: An initializer for the bias vector. If None, no bias will be applied.
- kernel_regularizer: Optional regularizer for the convolution kernel.
- bias_regularizer: Optional regularizer for the bias vector.
- activity_regularizer: Optional regularizer function for the output.
- kernel_constraint: Optional projection function to be applied to the kernel after being updated by an Optimizer
 (e.g. used to implement norm constraints or value constraints for layer weights). The function must take as input the
 unprojected variable and must return the projected variable (which must have the same shape). Constraints are not
 safe to use when doing asynchronous distributed training.
- bias_constraint: Optional projection function to be applied to the bias after being updated by an Optimizer.
- trainable: Boolean, if True also add variables to the graph collection GraphKeys.TRAINABLE_VARIABLES (see tf.Variable).
- name: A string, the name of the layer.
- reuse: Boolean, whether to reuse the weights of a previous layer by the same name.

Returns:

Output tensor.

Except as otherwise noted, the content of this page is licensed under the Creative Commons Attribution 3.0 License, and code samples are licensed under the Apache 2.0 License. For details, see our Site Policies. Java is a registered trademark of Oracle and/or its affiliates.

Last updated November 2, 2017.

