TencorFlow

TensorFlow API r1.4

tf.feature_column.embedding_column

```
embedding_column(
    categorical_column,
    dimension,
    combiner='mean',
    initializer=None,
    ckpt_to_load_from=None,
    tensor_name_in_ckpt=None,
    max_norm=None,
    trainable=True
)
```

Defined in tensorflow/python/feature_column.py.

_DenseColumn that converts from sparse, categorical input.

Use this when your inputs are sparse, but you want to convert them to a dense representation (e.g., to feed to a DNN).

Inputs must be a _CategoricalColumn created by any of the categorical_column_* function. Here is an example embedding of an identity column for a DNN model:

```
video_id = categorical_column_with_identity(
    key='video_id', num_buckets=1000000, default_value=0)
columns = [embedding_column(video_id, 9),...]
features = tf.parse_example(..., features=make_parse_example_spec(columns))
dense_tensor = input_layer(features, columns)
```

Args:

- categorical_column: A _CategoricalColumn created by a categorical_column_with_* function. This column produces the sparse IDs that are inputs to the embedding lookup.
- dimension: An integer specifying dimension of the embedding, must be > 0.
- combiner: A string specifying how to reduce if there are multiple entries in a single row. Currently 'mean', 'sqrtn' and 'sum' are supported, with 'mean' the default. 'sqrtn' often achieves good accuracy, in particular with bag-of-words columns. Each of this can be thought as example level normalizations on the column. For more information, see tf.embedding_lookup_sparse.
- initializer: A variable initializer function to be used in embedding variable initialization. If not specified, defaults to tf.truncated_normal_initializer with mean 0.0 and standard deviation 1/sqrt(dimension).
- ckpt_to_load_from: String representing checkpoint name/pattern from which to restore column weights. Required if tensor_name_in_ckpt is not None.
- tensor_name_in_ckpt: Name of the **Tensor** in **ckpt_to_load_from** from which to restore the column weights. Required if **ckpt_to_load_from** is not **None**.
- max_norm: If not None, embedding values are l2-normalized to this value.
- trainable: Whether or not the embedding is trainable. Default is True.

Returns:

_DenseColumn that converts from sparse input.

Raises:

- ValueError: if dimension not > 0.
- ValueError: if exactly one of ckpt_to_load_from and tensor_name_in_ckpt is specified.
- ValueError: if initializer is specified and is not callable.

Except as otherwise noted, the content of this page is licensed under the Creative Commons Attribution 3.0 License, and code samples are licensed under the Apache 2.0 License. For details, see our Site Policies. Java is a registered trademark of Oracle and/or its affiliates.

Last updated November 2, 2017.

