TopogrElow

TensorFlow API r1.4

tf.contrib.layers.legacy_fully_connected

```
legacy_fully_connected(
x,
num_output_units,
activation_fn=None,
weight_init=initializers.xavier_initializer(),
bias_init=tf.zeros_initializer(),
name=None,
weight_collections=(ops.GraphKeys.WEIGHTS,),
bias_collections=(ops.GraphKeys.BIASES,),
output_collections=(ops.GraphKeys.ACTIVATIONS,),
trainable=True,
weight_regularizer=None,
bias_regularizer=None
```

Defined in tensorflow/contrib/layers/python/layers/layers.py.

Adds the parameters for a fully connected layer and returns the output.

A fully connected layer is generally defined as a matrix multiply: y = f(w * x + b) where f is given by activation_fn. If activation_fn is None, the result of y = w * x + b is returned.

If x has shape [\(\text{dim}0, \text{dim}_1, ..., \text{dim}_n\)] with more than 2 dimensions (n > 1), then we repeat the matrix multiply along the first dimensions. The result r is a tensor of shape [\(\text{dim}_0, ..., \text{dim}_n\)], where \((r_{i_0}, ..., i_{n-1}, k) = \sum_{0 \le j \le n} (r_{i_0}, ..., i_{n-1}, j) \cdot (r_{i_0}, ..., j)

This op creates w and optionally b. Bias (b) can be disabled by setting bias_init to None.

The variable creation is compatible with **tf.variable_scope** and so can be reused with **tf.variable_scope** or **tf.make_template**.

Most of the details of variable creation can be controlled by specifying the initializers (weight_init and bias_init) and in which collections to place the created variables (weight_collections and bias_collections; note that the variables are always added to the VARIABLES collection). The output of the layer can be placed in custom collections using output_collections. The collections arguments default to WEIGHTS, BIASES and ACTIVATIONS, respectively.

A per layer regularization can be specified by setting weight_regularizer and bias_regularizer, which are applied to the weights and biases respectively, and whose output is added to the REGULARIZATION_LOSSES collection.

Args:

- x: The input Tensor.
- num_output_units: The size of the output.
- activation_fn: Activation function, default set to None to skip it and maintain a linear activation.
- weight_init: An optional weight initialization, defaults to xavier_initializer.
- bias_init: An initializer for the bias, defaults to 0. Set to None in order to disable bias.
- name: The name for this operation is used to name operations and to find variables. If specified it must be unique for

this scope, otherwise a unique name starting with "fully_connected" will be created. See **tf.variable_scope** for details.

- weight_collections: List of graph collections to which weights are added.
- bias_collections: List of graph collections to which biases are added.
- output_collections: List of graph collections to which outputs are added.
- trainable: If True also add variables to the graph collection GraphKeys.TRAINABLE_VARIABLES (see tf. Variable).
- weight_regularizer: A regularizer like the result of 11_regularizer or 12_regularizer. Used for weights.
- bias_regularizer: A regularizer like the result of 11_regularizer or 12_regularizer. Used for biases.

Returns:

The output of the fully connected layer.

Raises:

• ValueError: If x has rank less than 2 or if its last dimension is not set.

Except as otherwise noted, the content of this page is licensed under the Creative Commons Attribution 3.0 License, and code samples are licensed under the Apache 2.0 License. For details, see our Site Policies. Java is a registered trademark of Oracle and/or its affiliates.

Last updated November 2, 2017.

