### TancarFlow

TensorFlow API r1.4

tf.decode\_csv

```
decode_csv(
    records,
    record_defaults,
    field_delim=',',
    use_quote_delim=True,
    name=None,
    na_value=''
)
```

Defined in tensorflow/python/ops/parsing\_ops.py.

See the guides: Inputs and Readers > Converting, Reading data > Reading from files, Strings > Conversion

Convert CSV records to tensors. Each column maps to one tensor.

RFC 4180 format is expected for the CSV records. (https://tools.ietf.org/html/rfc4180) Note that we allow leading and trailing spaces with int or float field.

# Args:

- records: A Tensor of type string. Each string is a record/row in the csv and all records should have the same format.
- record\_defaults: A list of Tensor objects with types from: float32, int32, int64, string. One tensor per
  column of the input record, with either a scalar default value for that column or empty if the column is required.
- field\_delim: An optional string. Defaults to ",". char delimiter to separate fields in a record.
- use\_quote\_delim: An optional **bool**. Defaults to **True**. If false, treats double quotation marks as regular characters inside of the string fields (ignoring RFC 4180, Section 2, Bullet 5).
- name: A name for the operation (optional).
- na\_value: Additional string to recognize as NA/NaN.

# Returns:

A list of Tensor objects. Has the same type as record\_defaults. Each tensor will have the same shape as records.

Except as otherwise noted, the content of this page is licensed under the Creative Commons Attribution 3.0 License, and code samples are licensed under the Apache 2.0 License. For details, see our Site Policies. Java is a registered trademark of Oracle and/or its affiliates.

Last updated November 2, 2017.

## **Stay Connected**

Blog

GitHub

Twitter

# Support Issue Tracker Release Notes Stack Overflow English Terms | Privacy