TopogrElow

TensorFlow API r1.4

tf.keras.layers.Layer

Contents
Class Layer
Properties
activity_regularizer
dtype

Class Layer

Inherits From: Layer

Defined in tensorflow/python/keras/_impl/keras/engine/topology.py.

Abstract base layer class.

Properties

```
name: String, must be unique within a model.
input_spec: List of InputSpec class instances
    each entry describes one required input:
        - ndim
        - dtype
    A layer with `n` input tensors must have
    an `input_spec` of length `n`.
trainable: Boolean, whether the layer weights
    will be updated during training.
uses_learning_phase: Whether any operation
    of the layer uses `K.in_training_phase()`
    or `K.in_test_phase()`.
input_shape: Shape tuple. Provided for convenience,
    but note that there may be cases in which this
    attribute is ill-defined (e.g. a shared layer
    with multiple input shapes), in which case
    requesting `input_shape` will raise an Exception.
    Prefer using `layer.get_input_shape_for(input_shape)`,
    or `layer.get_input_shape_at(node_index)`.
output_shape: Shape tuple. See above.
inbound_nodes: List of nodes.
outbound_nodes: List of nodes.
input, output: Input/output tensor(s). Note that if the layer is used
    more than once (shared layer), this is ill-defined
    and will raise an exception. In such cases, use
    `layer.get_input_at(node_index)`.
input_mask, output_mask: Same as above, for masks.
trainable_weights: List of variables.
non_trainable_weights: List of variables.
weights: The concatenation of the lists trainable_weights and
   non_trainable_weights (in this order).
```

Methods

```
call(x, mask=None): Where the layer's logic lives.
__call__(x, mask=None): Wrapper around the layer logic (`call`).
    If x is a Keras tensor:
        - Connect current layer with last layer from tensor:
            `self._add_inbound_node(last_layer)`
        - Add layer to tensor history
   If layer is not built:
        - Build from inputs shape
get_weights()
set_weights(weights)
get_config()
count_params()
_compute_output_shape(input_shape)
compute_mask(x, mask)
get_input_at(node_index)
get_output_at(node_index)
get_input_shape_at(node_index)
get_output_shape_at(node_index)
get_input_mask_at(node_index)
get_output_mask_at(node_index)
```

Class Methods

```
from_config(config)
```

Internal methods:

```
build(input_shape)
_add_inbound_node(layer, index=0)
```

Properties

activity_regularizer

Optional regularizer function for the output of this layer.

dtype

graph

input

Retrieves the input tensor(s) of a layer.

Only applicable if the layer has exactly one input, i.e. if it is connected to one incoming layer.

Returns:

Input tensor or list of input tensors.

Raises:

AttributeError: if the layer is connected to more than one incoming layers.

Raises:

- RuntimeError: If called in Eager mode.
- AttributeError: If no inbound nodes are found.

input_mask

Retrieves the input mask tensor(s) of a layer.

Only applicable if the layer has exactly one inbound node, i.e. if it is connected to one incoming layer.

Returns:

Input mask tensor (potentially None) or list of input mask tensors.

Raises:

• AttributeError: if the layer is connected to more than one incoming layers.

input_shape

Retrieves the input shape(s) of a layer.

Only applicable if the layer has exactly one input, i.e. if it is connected to one incoming layer, or if all inputs have the same shape.

Returns:

Input shape, as an integer shape tuple (or list of shape tuples, one tuple per input tensor).

Raises:

- AttributeError: if the layer has no defined input_shape.
- RuntimeError: if called in Eager mode.

losses

name

non_trainable_variables

non_trainable_weights

output

Retrieves the output tensor(s) of a layer.

Only applicable if the layer has exactly one output, i.e. if it is connected to one incoming layer.

Output tensor or list of output tensors.

Raises:

- AttributeError: if the layer is connected to more than one incoming layers.
- RuntimeError: if called in Eager mode.

output_mask

Retrieves the output mask tensor(s) of a layer.

Only applicable if the layer has exactly one inbound node, i.e. if it is connected to one incoming layer.

Returns:

Output mask tensor (potentially None) or list of output mask tensors.

Raises:

• AttributeError: if the layer is connected to more than one incoming layers.

output_shape

Retrieves the output shape(s) of a layer.

Only applicable if the layer has one output, or if all outputs have the same shape.

Returns:

Output shape, as an integer shape tuple (or list of shape tuples, one tuple per output tensor).

Raises:

- AttributeError: if the layer has no defined output shape.
- RuntimeError: if called in Eager mode.

scope_name

trainable_variables

trainable_weights

updates

variables

Returns the list of all layer variables/weights.

Returns:

A list of variables.

weights

Returns the list of all layer variables/weights.

Returns:

A list of variables.

Methods

```
__init__
```

```
__init__(**kwargs)
```

__call__

```
__call__(
   inputs,
   **kwargs
)
```

Wrapper around self.call(), for handling internal references.

If a Keras tensor is passed: - We call self._add_inbound_node(). - If necessary, we **build** the layer to match the shape of the input(s). - We update the _keras_history of the output tensor(s) with the current layer. This is done as part of _add_inbound_node().

Arguments:

- inputs: Can be a tensor or list/tuple of tensors.
- **kwargs: Additional keyword arguments to be passed to call().

Returns:

Output of the layer's call method.

Raises:

• ValueError: in case the layer is missing shape information for its build call.

__deepcopy__

```
__deepcopy__(memo)
```

add_loss

```
add_loss(
   losses,
   inputs=None
)
```

Add loss tensor(s), potentially dependent on layer inputs.

Some losses (for instance, activity regularization losses) may be dependent on the inputs passed when calling a layer. Hence, when reusing a same layer on different inputs **a** and **b**, some entries in **layer.losses** may be dependent on **a** and some on **b**. This method automatically keeps track of dependencies.

The **get_losses_for** method allows to retrieve the losses relevant to a specific set of inputs.

Arguments:

- losses: Loss tensor, or list/tuple of tensors.
- inputs: Optional input tensor(s) that the loss(es) depend on. Must match the inputs argument passed to the __call__ method at the time the losses are created. If None is passed, the losses are assumed to be unconditional, and will apply across all dataflows of the layer (e.g. weight regularization losses).

Raises:

• RuntimeError: If called in Eager mode.

add_update

```
add_update(
    updates,
    inputs=None
)
```

Add update op(s), potentially dependent on layer inputs.

Weight updates (for instance, the updates of the moving mean and variance in a BatchNormalization layer) may be dependent on the inputs passed when calling a layer. Hence, when reusing a same layer on different inputs **a** and **b**, some entries in **layer.updates** may be dependent on **a** and some on **b**. This method automatically keeps track of dependencies.

The **get_updates_for** method allows to retrieve the updates relevant to a specific set of inputs.

This call is ignored in Eager mode.

Arguments:

- updates: Update op, or list/tuple of update ops.
- inputs: Optional input tensor(s) that the update(s) depend on. Must match the inputs argument passed to the __call__ method at the time the updates are created. If None is passed, the updates are assumed to be unconditional, and will apply across all dataflows of the layer.

add_variable

```
add_variable(
   name,
   shape,
   dtype=None,
   initializer=None,
   regularizer=None,
   trainable=True,
   constraint=None
)
```

Adds a new variable to the layer, or gets an existing one; returns it.

Arguments:

- name: variable name.
- shape: variable shape.
- dtype: The type of the variable. Defaults to self.dtype or float32.
- initializer: initializer instance (callable).
- regularizer: regularizer instance (callable).
- trainable: whether the variable should be part of the layer's "trainable_variables" (e.g. variables, biases) or "non_trainable_variables" (e.g. BatchNorm mean, stddev).
- constraint : constraint instance (callable).

Returns:

The created variable.

Raises:

• RuntimeError: If called in Eager mode with regularizers.

add_weight

```
add_weight(
   name,
   shape,
   dtype=None,
   initializer=None,
   regularizer=None,
   trainable=True,
   constraint=None
)
```

Adds a weight variable to the layer.

Arguments:

- name: String, the name for the weight variable.
- shape: The shape tuple of the weight.
- dtype: The dtype of the weight.
- initializer: An Initializer instance (callable).

- regularizer: An optional Regularizer instance.
- trainable: A boolean, whether the weight should be trained via backprop or not (assuming that the layer itself is also trainable).
- constraint : An optional Constraint instance.

The created weight variable.

apply

```
apply(
   inputs,
   *args,
   **kwargs
)
```

Apply the layer on a input.

This simply wraps self.__call__.

Arguments:

- inputs: Input tensor(s).
- *args: additional positional arguments to be passed to self.call.
- **kwargs: additional keyword arguments to be passed to self.call.

Returns:

Output tensor(s).

build

```
build(_)
```

Creates the variables of the layer.

call

```
call(
   inputs,
   **kwargs
)
```

This is where the layer's logic lives.

Arguments:

- inputs: Input tensor, or list/tuple of input tensors.
- **kwargs : Additional keyword arguments.

A tensor or list/tuple of tensors.

compute_mask

```
compute_mask(
   inputs,
   mask=None
)
```

Computes an output mask tensor.

Arguments:

- inputs: Tensor or list of tensors.
- mask: Tensor or list of tensors.

Returns:

None or a tensor (or list of tensors, one per output tensor of the layer).

count_params

```
count_params()
```

Count the total number of scalars composing the weights.

Returns:

An integer count.

Raises:

• ValueError: if the layer isn't yet built (in which case its weights aren't yet defined).

from_config

```
@classmethod
from_config(
    cls,
    config
)
```

Creates a layer from its config.

This method is the reverse of <code>get_config</code>, capable of instantiating the same layer from the config dictionary. It does not handle layer connectivity (handled by Container), nor weights (handled by <code>set_weights</code>).

Arguments:

config: A Python dictionary, typically the output of get_config.

A layer instance.

get_config

get_config()

Returns the config of the layer.

A layer config is a Python dictionary (serializable) containing the configuration of a layer. The same layer can be reinstantiated later (without its trained weights) from this configuration.

The config of a layer does not include connectivity information, nor the layer class name. These are handled by **Container** (one layer of abstraction above).

Returns:

Python dictionary.

get_input_at

get_input_at(node_index)

Retrieves the input tensor(s) of a layer at a given node.

Arguments:

• node_index: Integer, index of the node from which to retrieve the attribute. E.g. node_index=0 will correspond to the first time the layer was called.

Returns:

A tensor (or list of tensors if the layer has multiple inputs).

Raises:

• RuntimeError: If called in Eager mode.

get_input_mask_at

get_input_mask_at(node_index)

Retrieves the input mask tensor(s) of a layer at a given node.

Arguments:

• node_index: Integer, index of the node from which to retrieve the attribute. E.g. node_index=0 will correspond to the first time the layer was called.

Returns:

A mask tensor (or list of tensors if the layer has multiple inputs).

get_input_shape_at

```
get_input_shape_at(node_index)
```

Retrieves the input shape(s) of a layer at a given node.

Arguments:

• node_index: Integer, index of the node from which to retrieve the attribute. E.g. node_index=0 will correspond to the first time the layer was called.

Returns:

A shape tuple (or list of shape tuples if the layer has multiple inputs).

Raises:

RuntimeError: If called in Eager mode.

get_losses_for

```
get_losses_for(inputs)
```

Retrieves losses relevant to a specific set of inputs.

Arguments:

• inputs: Input tensor or list/tuple of input tensors. Must match the inputs argument passed to the __call__
method at the time the losses were created. If you pass inputs=None, unconditional losses are returned, such as weight regularization losses.

Returns:

List of loss tensors of the layer that depend on inputs.

Raises:

• RuntimeError: If called in Eager mode.

get_output_at

```
get_output_at(node_index)
```

Retrieves the output tensor(s) of a layer at a given node.

Arguments:

• node_index: Integer, index of the node from which to retrieve the attribute. E.g. node_index=0 will correspond to the

first time the layer was called.

Returns:

A tensor (or list of tensors if the layer has multiple outputs).

Raises:

• RuntimeError: If called in Eager mode.

get_output_mask_at

```
get_output_mask_at(node_index)
```

Retrieves the output mask tensor(s) of a layer at a given node.

Arguments:

• node_index: Integer, index of the node from which to retrieve the attribute. E.g. node_index=0 will correspond to the first time the layer was called.

Returns:

A mask tensor (or list of tensors if the layer has multiple outputs).

get_output_shape_at

```
get_output_shape_at(node_index)
```

Retrieves the output shape(s) of a layer at a given node.

Arguments:

• node_index: Integer, index of the node from which to retrieve the attribute. E.g. node_index=0 will correspond to the first time the layer was called.

Returns:

A shape tuple (or list of shape tuples if the layer has multiple outputs).

Raises:

• RuntimeError: If called in Eager mode.

get_updates_for

```
get_updates_for(inputs)
```

Retrieves updates relevant to a specific set of inputs.

Arguments:

• inputs: Input tensor or list/tuple of input tensors. Must match the inputs argument passed to the __call__ method at the time the updates were created. If you pass inputs=None, unconditional updates are returned.

Returns:

List of update ops of the layer that depend on inputs.

Raises:

• RuntimeError: If called in Eager mode.

get_weights

```
get_weights()
```

Returns the current weights of the layer.

Returns:

Weights values as a list of numpy arrays.

set_weights

set_weights(weights)

Sets the weights of the layer, from Numpy arrays.

Arguments:

• weights: a list of Numpy arrays. The number of arrays and their shape must match number of the dimensions of the weights of the layer (i.e. it should match the output of get_weights).

Raises:

ValueError: If the provided weights list does not match the layer's specifications.

Except as otherwise noted, the content of this page is licensed under the Creative Commons Attribution 3.0 License, and code samples are licensed under the Apache 2.0 License. For details, see our Site Policies. Java is a registered trademark of Oracle and/or its affiliates.

Last updated November 2, 2017.

Stay Connected

Blog

GitHub

Twitter

Support Issue Tracker Release Notes Stack Overflow English Terms | Privacy