TensorFlow

tf.contrib.learn.DNNLinearCombinedEstimator

Contents

Class DNNLinearCombinedEstimator

Properties

config

model_dir

Class DNNLinearCombinedEstimator

Inherits From: Estimator

Defined in tensorflow/contrib/learn/python/learn/estimators/dnn_linear_combined.py.

An estimator for TensorFlow Linear and DNN joined training models.



★ Note: New users must set fix_global_step_increment_bug=True when creating an estimator.

Input of fit, train, and evaluate should have following features, otherwise there will be a KeyError: if weight_column_name is not None, a feature with key=weight_column_name whose value is a Tensor . for each column in dnn_feature_columns + linear_feature_columns: - if column is a SparseColumn, a feature with key=column.name whose value is a SparseTensor . - if column is a WeightedSparseColumn, two features: the first with key the id column name, the second with key the weight column name. Both features' value must be a SparseTensor . - if column is a RealValuedColumn, a feature with key=column.name whose value is a Tensor`.

Propertie	es
-----------	----

config

model_dir

Methods

__init__

```
__init__(
    head.
    model_dir=None,
    linear_feature_columns=None,
    linear_optimizer=None,
    _joint_linear_weights=False,
    dnn_feature_columns=None,
    dnn_optimizer=None,
    dnn_hidden_units=None,
    dnn_activation_fn=None,
    dnn_dropout=None,
    gradient_clip_norm=None,
    config=None,
    feature_engineering_fn=None,
    embedding_lr_multipliers=None,
    fix_global_step_increment_bug=False,
    input_layer_partitioner=None
)
```

Initializes a DNNLinearCombinedEstimator instance. (deprecated arguments)

SOME ARGUMENTS ARE DEPRECATED. They will be removed after 2017-04-15. Instructions for updating: Please set fix_global_step_increment_bug=True and update training steps in your pipeline. See pydoc for details.



Note: New users must set fix_global_step_increment_bug=True when creating an estimator.

Args:

- head: A _Head object.
- model_dir: Directory to save model parameters, graph and etc. This can also be used to load checkpoints from the
 directory into a estimator to continue training a previously saved model.
- linear_feature_columns: An iterable containing all the feature columns used by linear part of the model. All items in the set should be instances of classes derived from FeatureColumn.
- linear_optimizer: An instance of tf.Optimizer used to apply gradients to the linear part of the model. If None, will use a FTRL optimizer.
- _joint_linear_weights: If True will use a single (possibly partitioned) variable to store all weights for the linear
 model. More efficient if there are many columns, however requires all columns are sparse and have the 'sum'
 combiner.
- dnn_feature_columns: An iterable containing all the feature columns used by deep part of the model. All items in the set should be instances of classes derived from FeatureColumn.
- dnn_optimizer: An instance of tf.Optimizer used to apply gradients to the deep part of the model. If None, will use an Adagrad optimizer.
- dnn_hidden_units: List of hidden units per layer. All layers are fully connected.
- dnn_activation_fn: Activation function applied to each layer. If None, will use tf.nn.relu.
- dnn_dropout: When not None, the probability we will drop out a given coordinate.
- gradient_clip_norm: A float > 0. If provided, gradients are clipped to their global norm with this clipping ratio. See tf.clip_by_global_norm for more details.
- config: RunConfig object to configure the runtime settings.
- feature_engineering_fn: Feature engineering function. Takes features and labels which are the output of input_fn and returns features and labels which will be fed into the model.
- embedding_lr_multipliers: Optional. A dictionary from EmbeddingColumn to a float multiplier. Multiplier will be
 used to multiply with learning rate for the embedding variables.

- fix_global_step_increment_bug: If False, the estimator needs two fit steps to optimize both linear and dnn parts.
 If True, this bug is fixed. New users must set this to True, but the default value is False for backwards compatibility.
- input_layer_partitioner: Optional. Partitioner for input layer.

Raises:

• ValueError: If both linear_feature_columns and dnn_features_columns are empty at the same time.

evaluate

```
evaluate(
    x=None,
    y=None,
    input_fn=None,
    feed_fn=None,
    batch_size=None,
    steps=None,
    metrics=None,
    name=None,
    checkpoint_path=None,
    hooks=None,
    log_progress=True
)
```

See Evaluable . (deprecated arguments)

SOME ARGUMENTS ARE DEPRECATED. They will be removed after 2016-12-01. Instructions for updating: Estimator is decoupled from Scikit Learn interface by moving into separate class SKCompat. Arguments x, y and batch_size are only available in the SKCompat class, Estimator will only accept input_fn. Example conversion: est = Estimator(...) -> est = SKCompat(Estimator(...))

Raises:

ValueError: If at least one of x or y is provided, and at least one of input_fn or feed_fn is provided. Or if
metrics is not None or dict.

export

```
export(
    export_dir,
    input_fn=export._default_input_fn,
    input_feature_key=None,
    use_deprecated_input_fn=True,
    signature_fn=None,
    prediction_key=None,
    default_batch_size=1,
    exports_to_keep=None,
    checkpoint_path=None
)
```

Exports inference graph into given dir. (deprecated)

THIS FUNCTION IS DEPRECATED. It will be removed after 2017-03-25. Instructions for updating: Please use Estimator.export_savedmodel() instead.

Args:

- export_dir: A string containing a directory to write the exported graph and checkpoints.
- input_fn: If use_deprecated_input_fn is true, then a function that given Tensor of Example strings, parses it into features that are then passed to the model. Otherwise, a function that takes no argument and returns a tuple of (features, labels), where features is a dict of string key to Tensor and labels is a Tensor that's currently not used (and so can be None).
- input_feature_key: Only used if use_deprecated_input_fn is false. String key into the features dict returned by input_fn that corresponds to a the raw Example strings Tensor that the exported model will take as input. Can only be None if you're using a custom signature_fn that does not use the first arg (examples).
- use_deprecated_input_fn: Determines the signature format of input_fn.
- signature_fn: Function that returns a default signature and a named signature map, given **Tensor** of **Example** strings, **dict** of **Tensor** s for features and **Tensor** or **dict** of **Tensor** s for predictions.
- prediction_key: The key for a tensor in the predictions dict (output from the model_fn) to use as the
 predictions input to the signature_fn. Optional. If None, predictions will pass to signature_fn without filtering.
- default_batch_size: Default batch size of the Example placeholder.
- exports_to_keep: Number of exports to keep.
- checkpoint_path: the checkpoint path of the model to be exported. If it is **None** (which is default), will use the latest checkpoint in export_dir.

Returns:

The string path to the exported directory. NB: this functionality was added ca. 2016/09/25; clients that depend on the return value may need to handle the case where this function returns None because subclasses are not returning a value.

export_savedmodel

```
export_savedmodel(
    export_dir_base,
    serving_input_fn,
    default_output_alternative_key=None,
    assets_extra=None,
    as_text=False,
    checkpoint_path=None,
    graph_rewrite_specs=(GraphRewriteSpec((tag_constants.SERVING,), ()),)
)
```

Exports inference graph as a SavedModel into given dir.

Args:

- export_dir_base: A string containing a directory to write the exported graph and checkpoints.
- serving_input_fn: A function that takes no argument and returns an InputFn0ps.
- default_output_alternative_key: the name of the head to serve when none is specified. Not needed for single-headed models.
- assets_extra: A dict specifying how to populate the assets.extra directory within the exported SavedModel. Each key should give the destination path (including the filename) relative to the assets.extra directory. The corresponding value gives the full path of the source file to be copied. For example, the simple case of copying a single file without renaming it is specified as {'my_asset_file.txt': '/path/to/my_asset_file.txt'}.
- as_text: whether to write the SavedModel proto in text format.

- checkpoint_path: The checkpoint path to export. If None (the default), the most recent checkpoint found within the model directory is chosen.
- graph_rewrite_specs: an iterable of GraphRewriteSpec. Each element will produce a separate MetaGraphDef
 within the exported SavedModel, tagged and rewritten as specified. Defaults to a single entry using the default
 serving tag ("serve") and no rewriting.

Returns:

The string path to the exported directory.

Raises:

• ValueError: if an unrecognized export_type is requested.

fit

```
fit(
    x=None,
    y=None,
    input_fn=None,
    steps=None,
    batch_size=None,
    monitors=None,
    max_steps=None
)
```

See Trainable. (deprecated arguments)

SOME ARGUMENTS ARE DEPRECATED. They will be removed after 2016-12-01. Instructions for updating: Estimator is decoupled from Scikit Learn interface by moving into separate class SKCompat. Arguments x, y and batch_size are only available in the SKCompat class, Estimator will only accept input_fn. Example conversion: est = Estimator(...) -> est = SKCompat(Estimator(...))

Raises:

- ValueError: If x or y are not None while input_fn is not None.
- ValueError: If both steps and max_steps are not None.

get_params

```
get_params(deep=True)
```

Get parameters for this estimator.

Args:

deep: boolean, optional

If True, will return the parameters for this estimator and contained subobjects that are estimators.

Returns:

params: mapping of string to any Parameter names mapped to their values.

get_variable_names

```
get_variable_names()
```

Returns list of all variable names in this model.

Returns:

List of names.

get_variable_value

```
get_variable_value(name)
```

Returns value of the variable given by name.

Args:

name: string, name of the tensor.

Returns:

Numpy array - value of the tensor.

partial_fit

```
partial_fit(
    x=None,
    y=None,
    input_fn=None,
    steps=1,
    batch_size=None,
    monitors=None
)
```

Incremental fit on a batch of samples. (deprecated arguments)

SOME ARGUMENTS ARE DEPRECATED. They will be removed after 2016-12-01. Instructions for updating: Estimator is decoupled from Scikit Learn interface by moving into separate class SKCompat. Arguments x, y and batch_size are only available in the SKCompat class, Estimator will only accept input_fn. Example conversion: est = Estimator(...) -> est = SKCompat(Estimator(...))

This method is expected to be called several times consecutively on different or the same chunks of the dataset. This either can implement iterative training or out-of-core/online training.

This is especially useful when the whole dataset is too big to fit in memory at the same time. Or when model is taking long time to converge, and you want to split up training into subparts.

Args:

- x: Matrix of shape [n_samples, n_features...]. Can be iterator that returns arrays of features. The training input samples for fitting the model. If set, input_fn must be None.
- y: Vector or matrix [n_samples] or [n_samples, n_outputs]. Can be iterator that returns array of labels. The training

label values (class labels in classification, real numbers in regression). If set, input_fn must be None.

- input_fn: Input function. If set, x, y, and batch_size must be None.
- steps: Number of steps for which to train model. If None, train forever.
- batch_size: minibatch size to use on the input, defaults to first dimension of x. Must be None if input_fn is provided.
- monitors: List of BaseMonitor subclass instances. Used for callbacks inside the training loop.

Returns:

```
self, for chaining.
```

Raises:

• ValueError: If at least one of x and y is provided, and input_fn is provided.

predict

```
predict(
    x=None,
    input_fn=None,
    batch_size=None,
    outputs=None,
    as_iterable=True
)
```

Returns predictions for given features. (deprecated arguments)

SOME ARGUMENTS ARE DEPRECATED. They will be removed after 2016-12-01. Instructions for updating: Estimator is decoupled from Scikit Learn interface by moving into separate class SKCompat. Arguments x, y and batch_size are only available in the SKCompat class, Estimator will only accept input_fn. Example conversion: est = Estimator(...) -> est = SKCompat(Estimator(...))

Args:

- x: Matrix of shape [n_samples, n_features...]. Can be iterator that returns arrays of features. The training input samples for fitting the model. If set, input_fn must be None.
- input_fn: Input function. If set, x and 'batch_size' must be None.
- batch_size: Override default batch size. If set, 'input_fn' must be 'None'.
- outputs: list of str, name of the output to predict. If None, returns all.
- as_iterable: If True, return an iterable which keeps yielding predictions for each example until inputs are exhausted.
 Note: The inputs must terminate if you want the iterable to terminate (e.g. be sure to pass num_epochs=1 if you are using something like read_batch_features).

Returns:

A numpy array of predicted classes or regression values if the constructor's **model_fn** returns a **Tensor** for **predictions** or a **dict** of numpy arrays if **model_fn** returns a **dict**. Returns an iterable of predictions if as_iterable is True.

Raises:

• ValueError: If x and input_fn are both provided or both None.

set_params

set_params(**params)

Set the parameters of this estimator.

The method works on simple estimators as well as on nested objects (such as pipelines). The former have parameters of the form **<component>__<parameter>** so that it's possible to update each component of a nested object.

Args:

**params : Parameters.

Returns:

self

Raises:

• ValueError: If params contain invalid names.

Except as otherwise noted, the content of this page is licensed under the Creative Commons Attribution 3.0 License, and code samples are licensed under the Apache 2.0 License. For details, see our Site Policies. Java is a registered trademark of Oracle and/or its affiliates.

Last updated November 2, 2017.

