TopogrElow

TensorFlow API r1.4

tf.contrib.layers.sparse_column_with_vocabulary_file

```
sparse_column_with_vocabulary_file(
    column_name,
    vocabulary_file,
    num_oov_buckets=0,
    vocab_size=None,
    default_value=-1,
    combiner='sum',
    dtype=tf.string
)
```

Defined in tensorflow/contrib/layers/python/layers/feature_column.py.

See the guide: Layers (contrib) > Feature columns

Creates a _SparseColumn with vocabulary file configuration.

Use this when your sparse features are in string or integer format, and you have a vocab file that maps each value to an integer ID. output_id = LookupIdFromVocab(input_feature_string)

Args:

- column_name: A string defining sparse column name.
- vocabulary_file: The vocabulary filename.
- num_oov_buckets: The number of out-of-vocabulary buckets. If zero all out of vocabulary features will be ignored.
- vocab_size: Number of the elements in the vocabulary.
- default_value: The value to use for out-of-vocabulary feature values. Defaults to -1.
- combiner: A string specifying how to reduce if the sparse column is multivalent. Currently "mean", "sqrtn" and "sum" are supported, with "sum" the default. "sqrtn" often achieves good accuracy, in particular with bag-of-words columns.
 - "sum": do not normalize features in the column
 - "mean": do l1 normalization on features in the column
 - "sqrtn": do l2 normalization on features in the column For more information: tf.embedding_lookup_sparse.
- dtype: The type of features. Only string and integer types are supported.

Returns:

A _SparseColumn with vocabulary file configuration.

Raises:

- ValueError: vocab_size is not defined.
- ValueError: dtype is neither string nor integer.

Stay Connected	
Blog	
GitHub	
Twitter	
Support	
Issue Tracker	
Release Notes	
Stack Overflow	
English	
Terms Privacy	