TancarFlow

TensorFlow Al

tf.contrib.kfac.loss_functions.NegativeLogProbLoss

Contents

Class NegativeLogProbLoss

Properties

fisher_factor_inner_shape

fisher_factor_inner_static_shape

Class NegativeLogProbLoss

Inherits From: LossFunction

Defined in tensorflow/contrib/kfac/python/ops/loss_functions.py.

Abstract base class for loss functions that are negative log probs.

Properties

fisher_factor_inner_shape

The shape of the tensor returned by multiply_fisher_factor.

fisher_factor_inner_static_shape

Static version of fisher_factor_inner_shape.

hessian_factor_inner_shape

The shape of the tensor returned by multiply_hessian_factor.

hessian_factor_inner_static_shape

Static version of hessian_factor_inner_shape.

inputs

params

Methods

__init__

```
__init__(
   targets=None,
   seed=None
)
```

evaluate

```
evaluate()
```

Evaluate the loss function.

evaluate_on_sample

```
evaluate_on_sample(seed=None)
```

multiply_fisher

```
multiply_fisher(vector)
```

Right-multiply a vector by the Fisher.

Args:

vector: The vector to multiply. Must be the same shape(s) as the 'inputs' property.

Returns:

The vector right-multiplied by the Fisher. Will be of the same shape(s) as the 'inputs' property.

multiply_fisher_factor

```
multiply_fisher_factor(vector)
```

Right-multiply a vector by a factor B of the Fisher.

Here the 'Fisher' is the Fisher information matrix (i.e. expected outer- product of gradients) with respect to the parameters of the underlying probability distribtion (whose log-prob defines the loss). Typically this will be block-diagonal across different cases in the batch, since the distribution is usually (but not always) conditionally iid across different cases.

Note that B can be any matrix satisfying B * B^T = F where F is the Fisher, but will agree with the one used in the other methods of this class.

Args:

vector: The vector to multiply. Must be of the shape given by the 'fisher_factor_inner_shape' property.

Returns:

The vector right-multiplied by B. Will be of the same shape(s) as the 'inputs' property.

multiply_fisher_factor_replicated_one_hot

multiply_fisher_factor_replicated_one_hot(index)

Right-multiply a replicated-one-hot vector by a factor B of the Fisher.

Here the 'Fisher' is the Fisher information matrix (i.e. expected outer- product of gradients) with respect to the parameters of the underlying probability distribtion (whose log-prob defines the loss). Typically this will be block-diagonal across different cases in the batch, since the distribution is usually (but not always) conditionally iid across different cases.

A 'replicated-one-hot' vector means a tensor which, for each slice along the batch dimension (assumed to be dimension 0), is 1.0 in the entry corresponding to the given index and 0 elsewhere.

Note that B can be any matrix satisfying B * B^T = H where H is the Fisher, but will agree with the one used in the other methods of this class.

Args:

• index: A tuple representing in the index of the entry in each slice that is 1.0. Note that len(index) must be equal to the number of elements of the 'fisher_factor_inner_shape' tensor minus one.

Returns:

The vector right-multiplied by B. Will be of the same shape(s) as the 'inputs' property.

multiply_fisher_factor_transpose

multiply_fisher_factor_transpose(vector)

Right-multiply a vector by the tranpose of a factor B of the Fisher.

Here the 'Fisher' is the Fisher information matrix (i.e. expected outer- product of gradients) with respect to the parameters of the underlying probability distribtion (whose log-prob defines the loss). Typically this will be block-diagonal across different cases in the batch, since the distribution is usually (but not always) conditionally iid across different cases.

Note that B can be any matrix satisfying $B * B^T = F$ where F is the Fisher, but will agree with the one used in the other methods of this class.

Args:

• vector: The vector to multiply. Must be the same shape(s) as the 'inputs' property.

Returns:

The vector right-multiplied by B^T. Will be of the shape given by the 'fisher_factor_inner_shape' property.

multiply_hessian

multiply_hessian(vector)

Right-multiply a vector by the Hessian.

Here the 'Hessian' is the Hessian matrix (i.e. matrix of 2nd-derivatives) of the loss function with respect to its inputs.

Args:

vector: The vector to multiply. Must be the same shape(s) as the 'inputs' property.

Returns:

The vector right-multiplied by the Hessian. Will be of the same shape(s) as the 'inputs' property.

multiply_hessian_factor

multiply_hessian_factor(vector)

Right-multiply a vector by a factor B of the Hessian.

Here the 'Hessian' is the Hessian matrix (i.e. matrix of 2nd-derivatives) of the loss function with respect to its inputs. Typically this will be block-diagonal across different cases in the batch, since the loss function is typically summed across cases.

Note that B can be any matrix satisfying B * B^T = H where H is the Hessian, but will agree with the one used in the other methods of this class.

Args:

vector: The vector to multiply. Must be of the shape given by the 'hessian_factor_inner_shape' property.

Returns:

The vector right-multiplied by B. Will be of the same shape(s) as the 'inputs' property.

multiply_hessian_factor_replicated_one_hot

multiply_hessian_factor_replicated_one_hot(index)

Right-multiply a replicated-one-hot vector by a factor B of the Hessian.

Here the 'Hessian' is the Hessian matrix (i.e. matrix of 2nd-derivatives) of the loss function with respect to its inputs. Typically this will be block-diagonal across different cases in the batch, since the loss function is typically summed across cases.

A 'replicated-one-hot' vector means a tensor which, for each slice along the batch dimension (assumed to be dimension 0), is 1.0 in the entry corresponding to the given index and 0 elsewhere.

Note that B can be any matrix satisfying $B * B^T = H$ where H is the Hessian, but will agree with the one used in the other methods of this class.

Args:

• index: A tuple representing in the index of the entry in each slice that is 1.0. Note that len(index) must be equal to the number of elements of the 'hessian_factor_inner_shape' tensor minus one.

Returns:

The vector right-multiplied by B^T. Will be of the same shape(s) as the 'inputs' property.

multiply_hessian_factor_transpose

multiply_hessian_factor_transpose(vector)

Right-multiply a vector by the tranpose of a factor B of the Hessian.

Here the 'Hessian' is the Hessian matrix (i.e. matrix of 2nd-derivatives) of the loss function with respect to its inputs. Typically this will be block-diagonal across different cases in the batch, since the loss function is typically summed across cases.

Note that B can be any matrix satisfying $B * B^T = H$ where H is the Hessian, but will agree with the one used in the other methods of this class.

Args:

vector: The vector to multiply. Must be the same shape(s) as the 'inputs' property.

Returns:

The vector right-multiplied by BAT. Will be of the shape given by the 'hessian_factor_inner_shape' property.

sample

sample(seed)

Except as otherwise noted, the content of this page is licensed under the Creative Commons Attribution 3.0 License, and code samples are licensed under the Apache 2.0 License. For details, see our Site Policies. Java is a registered trademark of Oracle and/or its affiliates.

Last updated November 2, 2017.

