### TancarFlow

TensorFlow API r1.4

tf.contrib.legacy\_seq2seq.tied\_rnn\_seq2seq

```
tied_rnn_seq2seq(
    encoder_inputs,
    decoder_inputs,
    cell,
    loop_function=None,
    dtype=tf.float32,
    scope=None
)
```

Defined in tensorflow/contrib/legacy\_seq2seq/python/ops/seq2seq.py.

RNN sequence-to-sequence model with tied encoder and decoder parameters.

This model first runs an RNN to encode encoder\_inputs into a state vector, and then runs decoder, initialized with the last encoder state, on decoder\_inputs. Encoder and decoder use the same RNN cell and share parameters.

# Args:

- encoder\_inputs: A list of 2D Tensors [batch\_size x input\_size].
- decoder\_inputs: A list of 2D Tensors [batch\_size x input\_size].
- cell: tf.nn.rnn\_cell.RNNCell defining the cell function and size.
- loop\_function: If not None, this function will be applied to i-th output in order to generate i+1-th input, and decoder\_inputs will be ignored, except for the first element ("GO" symbol), see rnn\_decoder for details.
- dtype: The dtype of the initial state of the rnn cell (default: tf.float32).
- scope: VariableScope for the created subgraph; default: "tied\_rnn\_seq2seq".

# Returns:

A tuple of the form (outputs, state), where: outputs: A list of the same length as decoder\_inputs of 2D Tensors with shape [batch\_size x output\_size] containing the generated outputs. state: The state of each decoder cell in each time-step. This is a list with length len(decoder\_inputs) – one item for each time-step. It is a 2D Tensor of shape [batch\_size x cell.state\_size].

Except as otherwise noted, the content of this page is licensed under the Creative Commons Attribution 3.0 License, and code samples are licensed under the Apache 2.0 License. For details, see our Site Policies. Java is a registered trademark of Oracle and/or its affiliates.

Last updated November 2, 2017.

# **Stay Connected**

Blog

GitHub

Twitter

# Support Issue Tracker Release Notes Stack Overflow English Terms | Privacy