## TopogrElow

TensorFlow API r1.4

## tf.nn.sampled\_softmax\_loss

```
sampled_softmax_loss(
    weights,
    biases,
    labels,
    inputs,
    num_sampled,
    num_classes,
    num_true=1,
    sampled_values=None,
    remove_accidental_hits=True,
    partition_strategy='mod',
    name='sampled_softmax_loss'
)
```

Defined in tensorflow/python/ops/nn\_impl.py.

See the guide: Neural Network > Candidate Sampling

Computes and returns the sampled softmax training loss.

This is a faster way to train a softmax classifier over a huge number of classes.

This operation is for training only. It is generally an underestimate of the full softmax loss.

A common use case is to use this method for training, and calculate the full softmax loss for evaluation or inference. In this case, you must set **partition\_strategy="div"** for the two losses to be consistent, as in the following example:

```
if mode == "train":
    loss = tf.nn.sampled_softmax_loss(
        weights=weights,
        biases=biases,
        labels=labels,
        inputs=inputs,
        ...,
        partition_strategy="div")
elif mode == "eval":
    logits = tf.matmul(inputs, tf.transpose(weights))
    logits = tf.nn.bias_add(logits, biases)
    labels_one_hot = tf.one_hot(labels, n_classes)
    loss = tf.nn.softmax_cross_entropy_with_logits(
        labels=labels_one_hot,
        logits=logits)
```

See our Candidate Sampling Algorithms Reference

Also see Section 3 of Jean et al., 2014 (pdf) for the math.

## Args:

- weights: A Tensor of shape [num\_classes, dim], or a list of Tensor objects whose concatenation along dimension 0 has shape [num\_classes, dim]. The (possibly-sharded) class embeddings.
- biases: A Tensor of shape [num\_classes]. The class biases.

- labels: A **Tensor** of type **int64** and shape **[batch\_size, num\_true]**. The target classes. Note that this format differs from the **labels** argument of **nn.softmax\_cross\_entropy\_with\_logits**.
- inputs: A Tensor of shape [batch\_size, dim]. The forward activations of the input network.
- num\_sampled: An int. The number of classes to randomly sample per batch.
- num\_classes: An int. The number of possible classes.
- num\_true: An int. The number of target classes per training example.
- sampled\_values: a tuple of (sampled\_candidates, true\_expected\_count, sampled\_expected\_count) returned by a
   \*\_candidate\_sampler function. (if None, we default to log\_uniform\_candidate\_sampler)
- remove\_accidental\_hits: A bool. whether to remove "accidental hits" where a sampled class equals one of the target classes. Default is True.
- partition\_strategy: A string specifying the partitioning strategy, relevant if len(weights) > 1. Currently "div" and "mod" are supported. Default is "mod". See tf.nn.embedding\_lookup for more details.
- name: A name for the operation (optional).

## Returns:

A batch\_size 1-D tensor of per-example sampled softmax losses.

Except as otherwise noted, the content of this page is licensed under the Creative Commons Attribution 3.0 License, and code samples are licensed under the Apache 2.0 License. For details, see our Site Policies. Java is a registered trademark of Oracle and/or its affiliates.

Last updated November 2, 2017.

