TopogrElow

TensorFlow API r1.4

tf.keras.layers.ConvLSTM2D

Contents
Class ConvLSTM2D
Properties
activity_regularizer
dtype

Class ConvLSTM2D

Defined in tensorflow/python/keras/_impl/keras/layers/convolutional_recurrent.py.

Convolutional LSTM.

It is similar to an LSTM layer, but the input transformations and recurrent transformations are both convolutional.

Arguments:

- filters: Integer, the dimensionality of the output space (i.e. the number output of filters in the convolution).
- kernel_size: An integer or tuple/list of n integers, specifying the dimensions of the convolution window.
- strides: An integer or tuple/list of n integers, specifying the strides of the convolution. Specifying any stride value!= 1 is incompatible with specifying any **dilation_rate** value!= 1.
- padding: One of "valid" or "same" (case-insensitive).
- data_format: A string, one of channels_last (default) or channels_first. The ordering of the dimensions in the inputs. channels_last corresponds to inputs with shape (batch, time, ..., channels) while channels_first corresponds to inputs with shape (batch, time, channels, ...). It defaults to the image_data_format value found in your Keras config file at ~/.keras/keras.json. If you never set it, then it will be "channels_last".
- dilation_rate: An integer or tuple/list of n integers, specifying the dilation rate to use for dilated convolution.

 Currently, specifying any dilation_rate value!= 1 is incompatible with specifying any strides value!= 1.
- activation: Activation function to use. If you don't specify anything, no activation is applied (ie. "linear" activation:
 a(x) = x).
- recurrent_activation: Activation function to use for the recurrent step.
- use_bias: Boolean, whether the layer uses a bias vector.
- kernel_initializer: Initializer for the kernel weights matrix, used for the linear transformation of the inputs..
- recurrent_initializer: Initializer for the recurrent_kernel weights matrix, used for the linear transformation of the recurrent state..
- bias_initializer: Initializer for the bias vector.
- unit_forget_bias: Boolean. If True, add 1 to the bias of the forget gate at initialization. Use in combination with bias_initializer="zeros". This is recommended in Jozefowicz et al.
- kernel_regularizer: Regularizer function applied to the kernel weights matrix.
- recurrent_regularizer: Regularizer function applied to the recurrent_kernel weights matrix.

- bias_regularizer: Regularizer function applied to the bias vector.
- activity_regularizer: Regularizer function applied to the output of the layer (its "activation")...
- kernel_constraint: Constraint function applied to the kernel weights matrix.
- recurrent_constraint: Constraint function applied to the recurrent_kernel weights matrix.
- bias_constraint: Constraint function applied to the bias vector.
- return_sequences: Boolean. Whether to return the last output in the output sequence, or the full sequence.
- go_backwards: Boolean (default False). If True, rocess the input sequence backwards.
- stateful: Boolean (default False). If True, the last state for each sample at index i in a batch will be used as initial state for the sample of index i in the following batch.
- dropout: Float between 0 and 1. Fraction of the units to drop for the linear transformation of the inputs.
- recurrent_dropout: Float between 0 and 1. Fraction of the units to drop for the linear transformation of the recurrent state.

Input shape: -if data_format='channels_first' 5D tensor with shape: (samples, time, channels, rows, cols) -if data_format='channels_last' 5D tensor with shape: (samples, time, rows, cols, channels)

Output shape: -if return_sequences -if data_format='channels_first' 5D tensor with shape: (samples, time, filters, output_row, output_col) -if data_format='channels_last' 5D tensor with shape: (samples, time, output_row, output_col, filters) - else - if data_format = 'channels_first' 4D tensor with shape: (samples, filters, output_row, output_col) - if data_format='channels_last' 4D tensor with shape: (samples, output_row, output_col, filters) where o_row and o_col depend on the shape of the filter and the padding

Raises:

ValueError: in case of invalid constructor arguments.

References: - Convolutional LSTM Network: A Machine Learning Approach for Precipitation Nowcasting The current implementation does not include the feedback loop on the cells output

Properties

activity_regularizer

Optional regularizer function for the output of this layer.

dtype

graph

input

Retrieves the input tensor(s) of a layer.

Only applicable if the layer has exactly one input, i.e. if it is connected to one incoming layer.

Returns:

Input tensor or list of input tensors.

Raises:

• AttributeError: if the layer is connected to more than one incoming layers.

Raises:

RuntimeError: If called in Eager mode.

AttributeError: If no inbound nodes are found.

input_mask

Retrieves the input mask tensor(s) of a layer.

Only applicable if the layer has exactly one inbound node, i.e. if it is connected to one incoming layer.

Returns:

Input mask tensor (potentially None) or list of input mask tensors.

Raises:

• AttributeError: if the layer is connected to more than one incoming layers.

input_shape

Retrieves the input shape(s) of a layer.

Only applicable if the layer has exactly one input, i.e. if it is connected to one incoming layer, or if all inputs have the same shape.

Returns:

Input shape, as an integer shape tuple (or list of shape tuples, one tuple per input tensor).

Raises:

- AttributeError: if the layer has no defined input_shape.
- RuntimeError: if called in Eager mode.

losses

name

non_trainable_variables

non_trainable_weights

output

Retrieves the output tensor(s) of a layer.

Only applicable if the layer has exactly one output, i.e. if it is connected to one incoming layer.

Returns:

Output tensor or list of output tensors.

Raises:

- AttributeError: if the layer is connected to more than one incoming layers.
- RuntimeError: if called in Eager mode.

output_mask

Retrieves the output mask tensor(s) of a layer.

Only applicable if the layer has exactly one inbound node, i.e. if it is connected to one incoming layer.

Returns:

Output mask tensor (potentially None) or list of output mask tensors.

Raises:

• AttributeError: if the layer is connected to more than one incoming layers.

output_shape

Retrieves the output shape(s) of a layer.

Only applicable if the layer has one output, or if all outputs have the same shape.

Returns:

Output shape, as an integer shape tuple (or list of shape tuples, one tuple per output tensor).

Raises:

- AttributeError: if the layer has no defined output shape.
- RuntimeError: if called in Eager mode.

scope_name

trainable_variables

trainable_weights

updates

variables

Returns the list of all layer variables/weights.

Returns:

A list of variables.

weights

Returns the list of all layer variables/weights.

Returns:

A list of variables.

Methods

__init__

```
__init__(
   filters,
   kernel_size,
   strides=(1, 1),
   padding='valid',
   data_format=None,
   dilation_rate=(1, 1),
   activation='tanh',
    recurrent_activation='hard_sigmoid',
   use_bias=True,
   kernel_initializer='glorot_uniform',
    recurrent_initializer='orthogonal',
   bias_initializer='zeros',
   unit_forget_bias=True,
   kernel_regularizer=None,
    recurrent_regularizer=None,
   bias_regularizer=None,
   activity_regularizer=None,
   kernel_constraint=None,
    recurrent_constraint=None,
   bias_constraint=None,
    return_sequences=False,
   go_backwards=False,
    stateful=False,
   dropout=0.0,
    recurrent_dropout=0.0,
    **kwargs
```

__call__

```
__call__(
   inputs,
   initial_state=None,
   **kwargs
)
```

__deepcopy__

```
__deepcopy__(memo)
```

add_loss

```
add_loss(
   losses,
   inputs=None
)
```

Add loss tensor(s), potentially dependent on layer inputs.

Some losses (for instance, activity regularization losses) may be dependent on the inputs passed when calling a layer. Hence, when reusing a same layer on different inputs **a** and **b**, some entries in **layer.losses** may be dependent on **a** and some on **b**. This method automatically keeps track of dependencies.

The get_losses_for method allows to retrieve the losses relevant to a specific set of inputs.

Arguments:

- losses: Loss tensor, or list/tuple of tensors.
- inputs: Optional input tensor(s) that the loss(es) depend on. Must match the inputs argument passed to the __call__ method at the time the losses are created. If None is passed, the losses are assumed to be unconditional, and will apply across all dataflows of the layer (e.g. weight regularization losses).

Raises:

• RuntimeError: If called in Eager mode.

add_update

```
add_update(
    updates,
    inputs=None
)
```

Add update op(s), potentially dependent on layer inputs.

Weight updates (for instance, the updates of the moving mean and variance in a BatchNormalization layer) may be dependent on the inputs passed when calling a layer. Hence, when reusing a same layer on different inputs **a** and **b**, some entries in **layer.updates** may be dependent on **a** and some on **b**. This method automatically keeps track of dependencies.

The get_updates_for method allows to retrieve the updates relevant to a specific set of inputs.

This call is ignored in Eager mode.

Arguments:

- updates: Update op, or list/tuple of update ops.
- inputs: Optional input tensor(s) that the update(s) depend on. Must match the inputs argument passed to the __call__ method at the time the updates are created. If None is passed, the updates are assumed to be unconditional, and will apply across all dataflows of the layer.

add_variable

```
add_variable(
   name,
   shape,
   dtype=None,
   initializer=None,
   regularizer=None,
   trainable=True,
   constraint=None
)
```

Adds a new variable to the layer, or gets an existing one; returns it.

Arguments:

- name: variable name.
- shape: variable shape.
- dtype: The type of the variable. Defaults to self.dtype or float32.
- initializer: initializer instance (callable).
- regularizer: regularizer instance (callable).
- trainable: whether the variable should be part of the layer's "trainable_variables" (e.g. variables, biases) or "non_trainable_variables" (e.g. BatchNorm mean, stddev).
- constraint : constraint instance (callable).

Returns:

The created variable.

Raises:

• RuntimeError: If called in Eager mode with regularizers.

add_weight

```
add_weight(
   name,
   shape,
   dtype=None,
   initializer=None,
   regularizer=None,
   trainable=True,
   constraint=None
)
```

Adds a weight variable to the layer.

Arguments:

- name: String, the name for the weight variable.
- shape: The shape tuple of the weight.
- dtype: The dtype of the weight.
- initializer: An Initializer instance (callable).

- regularizer: An optional Regularizer instance.
- trainable: A boolean, whether the weight should be trained via backprop or not (assuming that the layer itself is also trainable).
- constraint: An optional Constraint instance.

Returns:

The created weight variable.

apply

```
apply(
   inputs,
   *args,
   **kwargs
)
```

Apply the layer on a input.

This simply wraps self.__call__.

Arguments:

- inputs: Input tensor(s).
- *args: additional positional arguments to be passed to self.call.
- **kwargs: additional keyword arguments to be passed to self.call.

Returns:

Output tensor(s).

build

```
build(input_shape)
```

call

```
call(
   inputs,
   mask=None,
   training=None,
   initial_state=None
)
```

compute_mask

```
compute_mask(
   inputs,
   mask
)
```

count_params

```
count_params()
```

Count the total number of scalars composing the weights.

Returns:

An integer count.

Raises:

• ValueError: if the layer isn't yet built (in which case its weights aren't yet defined).

from_config

```
from_config(
   cls,
   config
)
```

Creates a layer from its config.

This method is the reverse of <code>get_config</code>, capable of instantiating the same layer from the config dictionary. It does not handle layer connectivity (handled by Container), nor weights (handled by <code>set_weights</code>).

Arguments:

• config: A Python dictionary, typically the output of get_config.

Returns:

A layer instance.

get_config

```
get_config()
```

get_constants

```
get_constants(
   inputs,
   training=None
)
```

get_initial_state

```
get_initial_state(inputs)
```

get_input_at

get_input_at(node_index)

Retrieves the input tensor(s) of a layer at a given node.

Arguments:

• node_index: Integer, index of the node from which to retrieve the attribute. E.g. node_index=0 will correspond to the first time the layer was called.

Returns:

A tensor (or list of tensors if the layer has multiple inputs).

Raises:

• RuntimeError: If called in Eager mode.

get_input_mask_at

```
get_input_mask_at(node_index)
```

Retrieves the input mask tensor(s) of a layer at a given node.

Arguments:

• node_index: Integer, index of the node from which to retrieve the attribute. E.g. node_index=0 will correspond to the first time the layer was called.

Returns:

A mask tensor (or list of tensors if the layer has multiple inputs).

get_input_shape_at

```
get_input_shape_at(node_index)
```

Retrieves the input shape(s) of a layer at a given node.

Arguments:

• node_index: Integer, index of the node from which to retrieve the attribute. E.g. node_index=0 will correspond to the first time the layer was called.

Returns:

A shape tuple (or list of shape tuples if the layer has multiple inputs).

Raises:

• RuntimeError: If called in Eager mode.

get_losses_for

```
get_losses_for(inputs)
```

Retrieves losses relevant to a specific set of inputs.

Arguments:

• inputs: Input tensor or list/tuple of input tensors. Must match the inputs argument passed to the __call__ method at the time the losses were created. If you pass inputs=None, unconditional losses are returned, such as weight regularization losses.

Returns:

List of loss tensors of the layer that depend on inputs.

Raises:

• RuntimeError: If called in Eager mode.

get_output_at

```
get_output_at(node_index)
```

Retrieves the output tensor(s) of a layer at a given node.

Arguments:

• node_index: Integer, index of the node from which to retrieve the attribute. E.g. node_index=0 will correspond to the first time the layer was called.

Returns:

A tensor (or list of tensors if the layer has multiple outputs).

Raises:

• RuntimeError: If called in Eager mode.

get_output_mask_at

```
get_output_mask_at(node_index)
```

Retrieves the output mask tensor(s) of a layer at a given node.

Arguments:

• node_index: Integer, index of the node from which to retrieve the attribute. E.g. node_index=0 will correspond to the first time the layer was called.

Returns:

A mask tensor (or list of tensors if the layer has multiple outputs).

get_output_shape_at

```
get_output_shape_at(node_index)
```

Retrieves the output shape(s) of a layer at a given node.

Arguments:

• node_index: Integer, index of the node from which to retrieve the attribute. E.g. node_index=0 will correspond to the first time the layer was called.

Returns:

A shape tuple (or list of shape tuples if the layer has multiple outputs).

Raises:

• RuntimeError: If called in Eager mode.

get_updates_for

```
get_updates_for(inputs)
```

Retrieves updates relevant to a specific set of inputs.

Arguments:

• inputs: Input tensor or list/tuple of input tensors. Must match the inputs argument passed to the __call_ method at the time the updates were created. If you pass inputs=None, unconditional updates are returned.

Returns:

List of update ops of the layer that depend on inputs.

Raises:

• RuntimeError: If called in Eager mode.

get_weights

```
get_weights()
```

Returns the current weights of the layer.

Returns:

Weights values as a list of numpy arrays.

input_conv

```
input_conv(
    x,
    w,
    b=None,
    padding='valid'
)
```

preprocess_input

```
preprocess_input(
   inputs,
   training=None
)
```

reccurent_conv

```
reccurent_conv(
    x,
    w
)
```

reset_states

```
reset_states()
```

set_weights

```
set_weights(weights)
```

Sets the weights of the layer, from Numpy arrays.

Arguments:

• weights: a list of Numpy arrays. The number of arrays and their shape must match number of the dimensions of the weights of the layer (i.e. it should match the output of get_weights).

Raises:

• ValueError: If the provided weights list does not match the layer's specifications.

step

```
step(
   inputs,
   states
)
```

Except as otherwise noted, the content of this page is licensed under the Creative Commons Attribution 3.0 License, and code samples are licensed under the Apache 2.0 License. For details, see our Site Policies. Java is a registered trademark of Oracle and/or its affiliates.

Last updated November 2, 2017.

Stay Connected		
Blog		
GitHub		
Twitter		
Support		
Issue Tracker		
Release Notes		
Stack Overflow		
English		
Terms Privacy		