#### TencorFlow

TensorFlow API r1.4

# tf.contrib.lookup.TextFileStringTableInitializer

```
Contents
Class TextFileStringTableInitializer
Properties
key_dtype
value_dtype
Methods
__init__
initialize
```

# Class TextFileStringTableInitializer

Inherits From: TextFileInitializer

Defined in tensorflow/python/ops/lookup\_ops.py.

Table initializer for int64 IDs to string tables from a text file.

# **Properties**

## key\_dtype

The expected table key dtype.

## value\_dtype

The expected table value dtype.

## Methods

## \_\_init\_\_

```
__init__(
    filename,
    key_column_index=TextFileIndex.LINE_NUMBER,
    value_column_index=TextFileIndex.WHOLE_LINE,
    vocab_size=None,
    delimiter='\t',
    name='text_file_string_table_init'
)
```

Constructs an initializer for an id-to-string table from a text file.

It populates a table that its key and value types are int64 and string, respectively. It generates one key-value pair per line. The content of the key and value are specified by **key\_column\_index** and **value\_column\_index**.

• TextFileIndex.LINE\_NUMBER means use the line number starting from zero, expects data type int64.

- TextFileIndex.WHOLE\_LINE means use the whole line content, expects data type string.
- A value >= 0 means use the index (starting at zero) of the split line based on delimiter.

## Args:

- filename: The filename of the text file to be used for initialization. The path must be accessible from wherever the graph is initialized (eg. trainer or eval workers). The filename may be a scalar **Tensor**.
- key\_column\_index: The column index from the text file to get the keys from. The default is 0 that represents the whole line content.
- value\_column\_index: The column index from the text file to get the values from. The default is to use the line number, starting from zero.
- vocab\_size: The number of elements in the file, if known.
- delimiter: The delimiter to separate fields in a line.
- name: Optional name for the op.

#### Raises:

• TypeError: when the filename is empty, or when the table key and value data types do not match the expected data types.

#### initialize

initialize(table)

Initializes the table from a text file.

# Args:

• table: The table to be initialized.

## Returns:

The operation that initializes the table.

#### Raises:

TypeError: when the keys and values data types do not match the table key and value data types.

Except as otherwise noted, the content of this page is licensed under the Creative Commons Attribution 3.0 License, and code samples are licensed under the Apache 2.0 License. For details, see our Site Policies. Java is a registered trademark of Oracle and/or its affiliates.

Last updated November 2, 2017.

#### **Stay Connected**

Blog

GitHub

Twitter

# Support Issue Tracker Release Notes Stack Overflow English Terms | Privacy