hq.dreamifno.biz 설정

```
우선, 루트인증기관에서 CN=vpn.dreaminfo.biz 인증서 발급.
root@hq:~# apt-get install openvpn
root@ha:~#
                 CD
                        /usr/share/doc/openypn/examples/sample-config-files/server.conf.gz
/etc/openvpn
(위 경로를 외우기 어렵다면 "find / -name server.conf.gz"으로 gz파일이 위치한 경로를 알아낸 다음
openvpn디렉터리로 옮겨준다.)
root@hq:~# cd/etc/openvpn
root@hq:/etc/openvpn# gunzip server.conf.gz
root@hq:/etc/openvpn# mkdir ./crts
root@hq:/etc/openvpn# scp root@ca.worldsign.org:/certs/hq.dreaminfo.biz.* ./crts/
hq.dreaminfo.biz.crt
hq.dreaminfo.biz.csr
root@hq:/etc/openvpn# openssl dhparam -out ./crts/dh1024.pem 1024
root@hq:/etc/openvpn# vim server.conf
    ;dev tap
    dev tun1
 78 ca /etc/ssl/certs/worldsign–CA.pem
 79 c<mark>e</mark>rt /etc/openvpn/crts/hq.dreaminfo.biz.crt
 80 k<mark>e</mark>y /etc/openvpn/crts/hq.dreaminfo.biz.key
   # Diffie hellman parameters.
 83 # Generate your own with:
         openss1 dhparam -out dh1024.pem 1024
   # Substitute 2048 for 1024 if you are using
 86 # 2048 bit keys.
    dh /etc/openvpn/crts/dh1024.pem
95 # ethernet bridging. See the man page for more info.
<mark>96 s</mark>erver 192.168.0.8 255.255.255.248
 136 push "route 192.168.0.0 255.255.25
137 push "route 192.168.1.0 255.255.255.0
138 push "route 172.16.0.0 255.255.255.0'
 195 # DNS servers provided by opendns.com.
 196 push "dhcp-option DNS 172.16.0.1"
```

197 ;push "dhcp-option DNS 208.67.220.220

251 # enable it in the client config file.
252 ; comp-lzo
299 # category will be output to the log.
300 ; mute 20
301 plugin /usr/lib/openvpn/openvpn-plugin-auth-pam.so login
302 client-cert-not-required

root@hq:~# systemctl restart openvpn

root@hq:~# systemctl status openvpn@server.service // 에러 없이 정상적으로 작동해야 함.

root@hq:~# netstat -nl | grep 1194 //1194 포트가 정상적으로 작동해야 함. 1194번이 안 올라왔으면 머신을 재 부팅하던가 인증서 유효기간 확인 및 cdp 정상 접근 확인. 정상적이라면 재부팅 후 1194번 올라옴.

Remote.worldsign.org 설정

openvpn GUI 패키지 설치



