
Module VII

Low-Level Memory Management

Location Low-Level Of Memory ManagementIn The Hierarchy



• Process manager uses memory manager to allocate space for a process

- Process manager uses memory manager to allocate space for a process
- Memory manager uses device manager to page or swap to disk

- Process manager uses memory manager to allocate space for a process
- Memory manager uses device manager to page or swap to disk
- Device manager uses process manager to block and restart processes when they request I/O

- Process manager uses memory manager to allocate space for a process
- Memory manager uses device manager to page or swap to disk
- Device manager uses process manager to block and restart processes when they request I/O
- Solution: divide memory manager into two parts

Two Types Of Memory Management

- Low-level memory manager
 - Manages memory within the kernel address space
 - Allocates address spaces for processes
 - Treats memory as a single, exhaustible resource
 - Positioned in the hierarchy below process manager
- High-level memory manager
 - Manages pages within address space
 - Positioned in the hierarchy above device manager
 - Divides memory into abstract resources

Conceptual Uses Of A Low-Level Memory Manager

- Allocation of stack space for a process
 - Performed by the process manager
 - Primitives needed to allocate and free stack space
- Allocation of heap storage
 - Performed by device manager (buffers) and other system facilities
 - Primitives needed to allocate and free heap space

Xinu Low-Level Memory Manager

Two functions control allocation of stack storage

```
addr = getstk(numbytes);
freestk(addr, numbytes);
```

• Two functions control allocation of heap storage

```
addr = getmem(numbytes);
freemem(addr, numbytes);
```

- Memory is allocated until none remains
- Only *getmem/freemem* are intended for use by application processes; *getstk/freestk* are restricted to the OS

Possible Allocation Strategies

- Stack and heap
 - Allocated from same free area
 - Allocated from separate free areas
- Single free list within an area
 - First-fit
 - Best-fit
 - Circular list with roving pointer
- Multiple free lists within an area
 - By exact size (static / dynamic)
 - By range

Possible Allocation Strategies (continued)

- Hierarchical data structure (tree)
 - Binary size allocation
 - Other
- FIFO cache with above methods


Practical Considerations

- Sharing
 - Stack cannot be shared
 - Multiple processes may share access to a heap
- Persistence
 - Stack object is associated with one process
 - Heap object may persist longer than the process that created it
- Stack objects tend to be uniform size

Xinu Low-Level Allocation

- One free area
- Single free list used for both heap and stack allocation
 - Ordered by increasing address
 - Singly-linked
 - Initialized at system startup to contain *all* free memory
- Allocation policy
 - Heap: first-fit
 - Stack: last-fit
 - Results in two conceptual pools

Result Of Xinu Allocation Policy



- First-fit allocates heap from lowest free address
- Last-fit allocates stack from highest free memory
- Uniform stack object size means higher probability of reuse and lower probability of fragmentation

Memory Protection And Stack Overflow

- If memory management hardware supports protection
 - Assign a unique protection key to each process stack
 - Set the processor protection key during context switch
 - Hardware will raise an exception if a process attempts to access another process's stack
- If no hardware protection is available
 - Mark the top of each stack with a reserved value
 - Check the value when scheduling
 - Provides partial protection against overflow

Memory Allocation Granularity


- Facts
 - Memory is byte addressable
 - Some hardware requires alignment
 - * For process stack
 - * For I/O buffers
 - * For pointers
 - Free memory blocks are kept on free list
 - One cannot allocate / free individual bytes
- Solution: choose a minimum granularity and round all requests

Example Code To Round Memory Requests

```
/* excerpt from memory.h */
* roundmb, truncmb - Round or truncate address to memory block size
* /
#define roundmb(x) (char *)( (7 + (uint32)(x)) & (~7))
#define truncmb(x) (char *)( ((uint32)(x)) & (~7) )
                 /* See roundmb & truncmb
struct memblk {
                                                             */
      struct memblk *mnext; /* Ptr to next free memory blk */
      uint32 mlength;
                                /* Size of blk (includes memblk)*/
extern struct memblk memlist; /* Head of free memory list
                      /* Start of heap
extern void *minheap;
                                                             * /
extern void *maxheap; /* Highest valid heap address
```

- Note the efficient implementation
 - The size of *memblk* is chosen to be a power of 2
 - Bit manipulation is used for rounding and truncation

Illustration Of Xinu Free List



- Free memory blocks are used to store list pointers
- Items on the list are ordered by increasing address
- All allocations rounded to size of struct *memblk*
- The length in *memlist* counts total free memory bytes

Allocation Technique

- Round up the request to a multiple of memory blocks
- Walk the free memory list
- Choose either
 - First free block that is large enough (getmem)
 - Last free block that is large enough (getstk)
- If a free block is larger than the request, extract a piece for the request and leave the part that is left over on the free list
- Invariant used during search:
 - *curr* points to a node on the free list (or *NULL*)
 - prev points to the previous node (or memlist)

Xinu Getmem (part 1)

```
/* getmem.c - getmem */
#include <xinu.h>
* getmem - Allocate heap storage, returning lowest word address
*/
char
   *getmem(
      uint32 nbytes /* Size of memory requested
                                                      * /
      intmask mask; /* Saved interrupt mask
                                                      * /
      struct memblk *prev, *curr, *leftover;
     mask = disable();
      if (nbytes == 0) {
            restore(mask);
            return (char *)SYSERR;
```

Xinu Getmem (part 2)

```
prev = &memlist;
curr = memlist.mnext;
while (curr != NULL) {
                                        /* Search free list
                                                                 * /
        if (curr->mlength == nbytes) { /* Block is exact match */
                prev->mnext = curr->mnext;
                memlist.mlength -= nbytes;
                restore(mask);
                return (char *)(curr);
        } else if (curr->mlength > nbytes) { /* Split big block */
                leftover = (struct memblk *)((uint32) curr +
                                nbytes);
                prev->mnext = leftover;
                leftover->mnext = curr->mnext;
                leftover->mlength = curr->mlength - nbytes;
                memlist.mlength -= nbytes;
                restore(mask);
                return (char *)(curr);
                                        /* Move to next block */
        } else {
                prev = curr;
                curr = curr->mnext;
restore(mask);
return (char *)SYSERR;
```

Deallocation Technique

- Round size to a multiple of memory blocks
- Walk the free list, using *next* to point to a block on the free list, and *prev* to point to the previous block (or *memlist*)
- Stop when the address of the block being freed lies between *prev* and *next*
- Either
 - Coalesce with the previous block if new block is contiguous
 - Add the new block to the free list
- Coalesce with the next block, if the result of the above is adjacent with the next block

Xinu Freemem (part 1)

```
/* freemem.c - freemem */
#include <xinu.h>
* freemem - Free a memory block, returning the block to the free list
* /
syscall freemem(
        char *blkaddr, /* Pointer to memory block
       uint32 nbytes /* Size of block in bytes
      intmask mask; /* Saved interrupt mask
                                                          * /
      struct memblk *next, *prev, *block;
      uint32 top;
      mask = disable();
      if ((nbytes == 0) | ((uint32) blkaddr < (uint32) minheap)
                      ((uint32) blkaddr > (uint32) maxheap)) {
            restore(mask);
            return SYSERR;
      block = (struct memblk *)blkaddr;
```

Xinu Freemem (part 2)

```
/* Walk along free list */
prev = &memlist;
next = memlist.mnext;
while ((next != NULL) && (next < block)) {
        prev = next;
        next = next->mnext;
if (prev == &memlist) { /* Compute top of previous block*/
        top = (uint32) NULL;
} else {
        top = (uint32) prev + prev->mlength;
/* Ensure new block does not overlap previous or next blocks
                                                                * /
if (((prev != &memlist) && (uint32) block < top)
       ((next != NULL) && (uint32) block+nbytes>(uint32)next)) {
        restore(mask);
        return SYSERR;
memlist.mlength += nbytes;
```

Xinu Freemem (part 3)

```
/* Either coalesce with previous block or add to free list */
if (top == (uint32) block) { /* Coalesce with previous block */
        prev->mlength += nbytes;
        block = prev;
                                /* Link into list as new node
} else {
        block->mnext = next;
        block->mlength = nbytes;
        prev->mnext = block;
/* Coalesce with next block if adjacent */
if (((uint32) block + block->mlength) == (uint32) next) {
        block->mlength += next->mlength;
        block->mnext = next->mnext;
restore(mask);
return OK;
```

Operating Systems – Module 7 Spring, 2017

Xinu Getstk (part 1)

```
/* getstk.c - getstk */
#include <xinu.h>
* getstk - Allocate stack memory, returning highest word address
* /
char
      *getstk(
       uint32 nbytes /* Size of memory requested
                                                           * /
                          /* Saved interrupt mask
      intmask mask;
      struct memblk *prev, *curr; /* Walk through memory list
      struct memblk *fits, *fitsprev; /* Record block that fits
      mask = disable();
      if (nbytes == 0) {
             restore(mask);
             return (char *)SYSERR;
      prev = &memlist;
      curr = memlist.mnext;
      fits = NULL;
```

Xinu Getstk (part 2)

```
/* Scan entire list
while (curr != NULL) {
       if (curr->mlength >= nbytes) { /* Record block address */
               fits = curr; /* when request fits */
               fitsprev = prev;
       prev = curr;
       curr = curr->mnext;
if (fits == NULL) {
                                       /* No block was found
       restore(mask);
       return (char *)SYSERR;
if (nbytes == fits->mlength) {
                                      /* Block is exact match */
       fitsprev->mnext = fits->mnext;
                                       /* Remove top section */
} else {
       fits->mlength -= nbytes;
       fits = (struct memblk *)((uint32)fits + fits->mlength);
memlist.mlength -= nbytes;
restore(mask);
return (char *)((uint32) fits + nbytes - sizeof(uint32));
```


Xinu Freestk

- Implemented as an inline function
- Technique: convert address from the highest address in block being freed to the lowest address in the block, and call *freemem*

Module VIII

High-level Memory Management

Location Of High-level Memory ManagementIn The Hierarchy



Our Approach To Memory Management (Review)

- Divide memory manager into two pieces
- Low-level piece
 - A basic facility
 - Provides functions for stack and heap allocation
 - Treats memory as exhaustible resource
- High-level piece
 - Accommodates other memory uses
 - Assumes both operating system modules and sets of applications need dynamic memory allocation
 - Prevents exhaustion

Motivation For Memory Partitioning

- Competition exists for kernel memory
- Many subsystems in the operaing system
 - Allocate blocks of memory
 - Have needs that change dynamically
- Examples
 - Disk subsystem allocates buffers for disk blocks
 - Network subsystem allocates packet buffers
- Interaction among subsystems can be subtle and complex

Managing Memory

- Conflicting philosophies and tradeoffs
 - Protecting information
 - Sharing information
- Extreme examples
 - Xinu has much sharing; little protection
 - Original Unix[™] had much protection; little sharing

The Concept Of Subsystem Isolation

- An OS designer desires
 - Predictable behavior
 - Provable assertions (e.g., "network traffic will never deprive the disk driver of buffers")
- The reality
 - Subsystems are designed independently; there is no global policy or guarantee about their memory use
 - If one subsystem allocates memory excessively, anothers can e deprived
- Conclusions
 - We must not treat memory as a single, global resource
 - We need a way to isolate subsystems

Providing Abstract Memory Resources

Assertion: to be able to make guarantees about subsystem behavior, one must partition memory into abstract resources with each resource dedicated to one subsystem.

A Few Examples Of Memory Resources

- Disk buffers
- Network buffers
- Message storage
- Inter-process communication buffers (e.g., Unix pipes)

Notes:

- * Each subsystem should operate safely and independently
- * An OS may defines separate sets of buffers for each network interface (e.g., Wi-Fi and Ethernet)

Xinu High-level Memory Manager

- Partitions memory into set of *buffer pools*
- Each pool is created once and persists until system shuts down
- At pool creation, we fix the
 - Size of buffers in the pool
 - Number of buffers in the pool
- Once a pool has been created, buffer allocation and release
 - Is dynamic
 - Uses a synchronous interface

Virtual Memory

Definition Of Virtual Memory

- Abstraction of physical memory
- Provides separation from underlying hardware details
- Primarily applied to applications (user processes)
- Allows applications to run independent of
 - Physical memory size
 - Position in physical memory
- Many mechanisms have been proposed and used

General Approach

- Heavyweight process
 - Lives in an isolated address space
 - All addresses are virtual
- Operating system
 - Establishes policies
 - Provides support for virtual address space creation
 - Configures the hardware
- Underlying hardware
 - Dynamically translates from virtual address to physical address
 - Provides support to help OS make policy decisions

Virtual Address Space

- Can be smaller than physical memory
 - * A 32-bit computer with more than 2^{32} bytes (four GB) of memory
- Can be larger than the physical memory
 - * A 64-bit computer with less than 2^{64} bytes (16 million terabytes) of memory
- Historic note: on early computers, physical memory was larger. Then virtual memory was larger until physical memory caught up. Now 64-bit architectures mean virtual memory is once again larger than physical memory.

Multiplexing Virtual Address Spaces Onto Physical Memory

• General idea

- Store a complete copy of each process's address space on secondary storage
- Move items to main memory as needed
- Write items back to disk to create space in memory for other items

Questions

- How much of a process's address space should reside in memory?
- When should items be loaded into memory?
- When should items be written back to disk?

General Approaches

- Swapping
 - Transfer an entire address space (complete process image)
- Segmentation
 - Divide the image into large segments
 - Transfer segments as needed
- Paging
 - Divide image into small, fixed-size pieces
 - Transfer individual pieces as needed

General Approaches (continued)

- Segmentation with paging
 - Divide an image into large segments
 - Further subdivide segments into fixed-size pages
- Note: simple paging has emerged as the most popular


Hardware Support For Paging

- Page tables
 - One page table per process
 - Storage location depends on hardware
 - * Kernel memory
 - * MMU hardware (on some systems)
- Page table base register
 - Internal to the processor
 - Contains the address of current process's page table
 - Must be changed during a context switch

Hardware Support For Paging (continued)

- Page table length register
 - Internal to the processor
 - Specifies the number of entries in the current page table
 - Determines the size of the virtual address space
 - Can be changed during context switch if the size of the virtual address space differs among processes

Illustration Of VM Hardware Registers



• Only one page table is active at given time


Address Translation

- Is performed by memory management hardware
- Must be applied to *every* memory reference
- Hardware translates from process's virtual address to corresponding physical memory address

Address Translation With Paging

- For now, we will assume
 - The operating system is not paged
 - The physical memory area beyond the operating system kernel is used for paging
 - The page size is 4 Kbytes
- Think of the physical memory area use for paging as a giant array of *frames*, where each frame can hold one page (i.e. a frame is 4K bytes)

Illustration Of Address Translation



- Page table entry contains physical frame address
- Choosing the page size to be a power of 2 eliminates division and modulus

In Practice

- Some hardware offers separate page tables for text, data, and stack
 - Disadvantage: complexity
 - Advantage: independent policies
- The size of virtual space may be limited to physical memory size
- The kernel address space can also be virtual (but it hasn't worked well in practice)

Demand Paging

- Keep the process image on secondary storage
- Treat main memory as cache of recently-referenced pages
- Allocate space in the cache dynamically as needed
- Move pages between the secondary store and main memory on demand (when referenced)

The Importance Of Hardware Support For Virtual Memory

- Every memory reference must be translated from a virtual address to a physical address
 - Instructions must be translated as well as data (to accommodate branching)
 - Indirect addresses that are generated at runtime must be translated
- Hardware support is essential
 - For efficiency
 - For recovery if a fault occurs
 - To record which pages are being used

In Practice

- A single instruction may reference many pages
 - Instruction fetch
 - Operand fetch
 - Indirect reference resolution
 - Memory copy instructions on CISC hardware
- Special-purpose hardware speeds page lookup
 - Translation Look-aside Buffer (TLB)
 - Implemented with T-CAM
 - TLB caches most recent address translations

In Practice (continued)

- VM mappings change during context switch
 - Some hardware requires OS to flush TLB
 - Other hardware uses tags to distinguish among address spaces
 - * Tag assigned by OS
 - * Typically, a process ID
- Can page tables be paged?
 - On some hardware, yes
 - Extremely inefficient (impractical)

Bits That Record Page Status

- Part of the page table entry for each page
- Understood by hardware
- Use Bit
 - Set by the hardware whenever page referenced
 - Applies to all fetch and store operations
- Modify Bit
 - Set by the hardware when a store operation occurs
- Presence Bit
 - Set by the OS to indicate that the page currently resident in memory
 - Tested by the hardware when the page is referenced

Questions For OS Designers

- Which VM policies are most effective?
- Which pages from which address spaces should be in memory at any time?
- Should some pages be locked in memory? (If so, which ones?)
- How does a VM policy interact with other policies (e.g., scheduling?)
- Should high-priority processes/threads have guarantees about the number of resident pages?
- If a system supports libraries that are shared among many processes, which paging policy applies?

A Critical Trade-off For Demand Paging

- Paging overhead and latency for given process can be reduced by giving the process more physical memory (more frames)
- Processor utilization and overall throughput are increased by increasing level of multitasking (concurrent processes)
- Extremes
 - Paging is minimized when the current process has maximal memory
 - Throughput is maximized when all ready processes are resident
- What is the best choice?

Terminology

- Reference string: a list of page references emitted by a process
- Resident set: the subset of process's pages currently present in main memory
- Page: a fixed size piece of process's address space
- Frame: a "slot" in main memory exactly the size of a page
- Dirty: a page that has been modified since it was last written to secondary store
- Page fault: an error that occurs when a referenced page is not present

Page Replacement

- Hardware
 - Detects a page fault because a referenced page is not resident
 - Raises an exception
- Operating system
 - Receives the exception
 - Allocates a frame
 - Retrieves the needed page, and allows other processes to execute while page is being fetched
 - Allows the blocked process to continue once the page arrives

Frame Allocation

- A frame must be allocated when a page fault occurs
- Allocation is trivial if free (unfilled) frames exist
- Allocation is difficult if all frames are currently used
- A policy is needed because operating system must
 - Select one of the resident pages and save a copy on disk
 - Mark the page table to indicate the page is no longer resident
 - Load the needed page into the frame
 - Set the appropriate page table entry
 - Return from the page fault to restart the operation
- Question: which frame should be selected when all are in use?

Choosing A Frame

- Competition can be
 - Global: consider frames from all processes when choosing
 - Local: choose a frame within the same process that caused the page fault
- Possible selection policies
 - Least Recently Used (LRU)
 - Least Frequently Used (LFU)
 - First In First Out (FIFO)

Example Page Replacement Algorithms

- We will consider three examples
 - Belady's optimal page replacement algorithm
 - Global clock (second chance algorithm)
 - Working set algorithm

Belady's Optimal Algorithm

- Chooses a page that will be referenced farthest in the future
- Provably optimal
- Totally impractical (of theoretical interest only)
- Useful for comparison of other algorithms
- Corollary: increasing the physical memory size does not always decrease the rate of page faults (known as Belady's Anomaly).

Global Clock Algorithm

- Originated in the MULTICS operating system
- Allows processes to compete with one another (hence the term *global*)
- Relatively low overhead
- Widely implemented (the most popular practical method)

Global Clock Paradigm

- Clock algorithm is activated when a page fault occurs
- Searches frames in memory, and selects a frame to use
- Gives a frame containing a referenced page a "second chance" before reclaiming
- Gives a frame containing a modified page a "third chance" before reclaiming
- In the worst case: the clock sweeps through all frames twice before reclaiming one
- Does *not* require external data structure other than standard page table bits

Operation Of The Global Clock

- Uses a global pointer that picks up where it left off previously
 - Sweeps slowly through all frames in memory
 - Starts moving when a frame is needed
 - Stops moving once a frame has been selected
- During the sweep, the algorithm checks *Use* and *Modify* bits of each frame
- Reclaims the frame if Use / Modify bits are (0,0)
- Changes (1,0) into (0,0) and bypasses the frame
- Changes (1,1) into (1,0) and bypasses the frame
- The algorithm keeps a copy of the actual modified bit to know whether page is dirty

In Practice

- The global clock always reclaims a small set of frames when one is needed
- The reclaimed frames are cached for subsequent references
- Advantage: collecting multiple frames avoids running the clock frequently

Level Of Multitasking

- If too many processes are running
 - Each process will not have many frames
 - Paging activity will be high
 - Throughput will be low
- If too few processes are running, paging activity is low, but
 - The processor will not have a process to run while other processes wait for I/O
 - Throughput will be low

Load Balancing

- Refers to adjusting the number of processes that compete for frames
- Goal is to maximize throughput
- Works best in systems that have
 - A steady, predictable workload
 - A large set of available processes
- Is performed in cooperation with, and response to, the global clock
- Multitasking level (number of active processes) is
 - Decreased when page faults are frequent
 - Increased when paging level is low

Difficulties In Load Balancing

- Choosing thresholds
- Collecting measurements
- Anticipating paging activity
- It is easy to overreact

Working Set Algorithm

- More theory
- Finer level of assessment
- Definition

Let δ be the size of a window on a reference string measured in page references. A process's working set at time i, w(i), consists of the set of pages in the δ references immediately preceding time i.

• Note: a working set is a set in the mathematical sense — it does not contain duplicates

Working Set Example For $\delta = 12$

time 3 2 5 3 8 3 27 3 6 27 2 11 5 1 2 w(2) = 3, 2w(3) = 3, 2, 5w(4) = 3, 2, 5w(6) = 3, 2, 5, 8(8) = 3, 2, 5, 8, 27(9) = 3, 2, 5, 8, 27, 6w(10) = 3, 2, 5, 8, 27, 6w(11) = 3, 2, 5, 8, 27, 6w(12) = 3, 2, 5, 8, 27, 6, 11w(13) = 3, 2, 5, 8, 27, 6, 11w(14) = 3, 2, 5, 8, 27, 6, 11, 1w(15) = 3, 2, 5, 8, 27, 6, 11, 1

Working Set Terminology

- Working set size: number of pages in the process's working set
- Resident set size: number of pages of process currently resident
- Note: both resident and working sets vary over time

Working Set Replacement Policy

Allocate to each process a resident set size equal to the process's working set size

Level Of Multitasking Under Working Set

- Level of multitasking
 - Is adjusted dynamically
 - Is a function of current working set sizes and memory size
- Idea: compare the sum of the working set sizes, W, and frames, F
 - Reduce multitasking when

Increase multitasking when

Assessment Of Working Set Model

Pros

- Simulation shows it performs well
- It uses paging performance as a way to balance load

Cons

- Need both a minimum and maximum bound on resident set size
- Difficult (impossible) to capture the needed information
 - * Working set must be recomputed on each memory reference
 - * Even a hardware solution is inadequate

Virtual memory was once the most important research topic in operating systems. What changed? Why did the topic fade? Has the problem been solved completely?

Summary

- We considered two forms of high-level memory management
- Inside the kernel
 - Define a set of abstract resources
 - Firewalling memory used by each prevents interference
 - Mechanism uses buffer pools
 - Buffer referenced by single address
- Outside the kernel
 - Swapping, segmentation, or paging

Summary (continued)

- Demand paging
 - Fixed size pages
 - Brought into memory when referenced
- Algorithms
 - Belady's algorithm (theoretical)
 - Global clock (widely used and practical)
- Working set (theoretical) relates paging to load balancing

