Qtile Documentation

Release 0.1.dev50+g42203cb

Aldo Cortesi

GETTING STARTED

1	Installation	3
2	Running Qtile as a Wayland Compositor	11
3	Troubleshooting	15
4	Entry points	17
5	Default Config File	37
6	The config file	43
7	Built-in Layouts	71
8	Built-in Widgets	93
9	Built-in Hooks	205
10	Built-in Extensions	217
11	Keybindings in images	223
12	Window stacking	227
13	Architecture	229
14	Interfaces	237
15	Commands API	241
16	Hacking on Qtile	403
17	Contributing	409
18	Frequently Asked Questions	421
19	How to create a widget	427
20	How to create a layout	441
21	Using git	455
22	License	459

23 Changelog	461
Index	485

Qtile is a full-featured, hackable tiling window manager written and configured in Python. It's available both as an X11 window manager and also as *a Wayland compositor*.

This documentation is designed to help you *install* and *configure* Qtile. Once it's up and running you'll probably want to start adding your own *customisations* to have it running exactly the way you want.

You'll find a lot of what you need within these docs but, if you still have some questions, you can find support in the following places:

IRC

irc://irc.oftc.net:6667/qtile

Discord

https://discord.gg/ehh233wCrC (Bridged with IRC)

Q&A

https://github.com/qtile/qtile/discussions/categories/q-a

Mailing List

https://groups.google.com/group/qtile-dev

GETTING STARTED 1

2 GETTING STARTED

CHAPTER

ONE

INSTALLATION

1.1 Distro Guides

Below are the preferred installation methods for specific distros. If you are running something else, please see *Installing From Source*.

1.1.1 Installing on Arch Linux

Stable versions of Qtile are currently packaged for Arch Linux. To install this package, run:

```
pacman -S qtile
```

Please see the ArchWiki for more information on Qtile.

1.1.2 Installing on Fedora 40 or later

Both Qtile X11 and Wayland stable versions can be installed via the DNF Package Manager.

If you want to pick a specific version(Such as the wayland version) then double-click Tab after "qtile".

dnf install qtile

1.1.3 Installing on Funtoo

Latest versions of Qtile are available on Funtoo. To install it, run:

```
emerge -av x11-wm/qtile
```

You can also install the development version from GitHub:

```
echo "x11-wm/qtile-9999 **" >> /etc/portage/package.accept_keywords emerge -av qtile
```

Customize

You can customize your installation with the following useflags:

- dbus
- · widget-khal-calendar
- · widget-imap
- · widget-keyboardkbdd
- · widget-launchbar
- · widget-mpd
- · widget-mpris
- widget-wlan

The dbus useflag is enabled by default. Disable it only if you know what it is and know you don't use/need it.

All widget-* useflags are disabled by default because these widgets require additional dependencies while not everyone will use them. Enable only widgets you need to avoid extra dependencies thanks to these useflags.

Visit Funtoo Qtile documentation for more details on Qtile installation on Funtoo.

1.1.4 Installing on Ubuntu or Debian

Newer versions of Debian-based distros (Debian >= 13, Ubuntu >= 25.04) have Qtile packages. Exact versions for each distro release can be found either on packages.debian.org or packages.ubuntu.com

Older Releases

Ubuntu and Debian >=11 comes with the necessary packages for installing Qtile. Starting from a minimal Debian installation, the following packages are required:

```
sudo apt install xserver-xorg xinit
sudo apt install libpangocairo-1.0-0
sudo apt install uv # if your distro doesn't have uv, try:
# curl -LsSf https://astral.sh/uv/install.sh | sh
```

Either Qtile can then be downloaded from the package index or the Github repository can be used, see *Installing From Source*:

```
uv tool install qtile
```

1.1.5 Installing on Slackware

Qtile is available on the SlackBuilds.org as:

Package Name	Description
qtile	stable branch (release)

Using slpkg (third party package manager)

The easy way to install Qtile is with slpkg. For example:

```
slpkg -s sbo qtile
```

Manual installation

Download dependencies first and install them. The order in which you need to install is:

- · pycparser
- cffi
- · futures
- · python-xcffib
- trollius
- cairocffi
- qtile

Please see the HOWTO for more information on SlackBuild Usage HOWTO.

1.1.6 Installing on FreeBSD

Otile is available via FreeBSD Ports. It can be installed with

```
pkg install qtile
```

1.1.7 Installing on NixOS

Qtile is available in the NixOS repos. To set qtile as your window manager, include this in your configuration.nix file:

```
services.xserver.windowManager.qtile.enable = true;
```

Other options for qtile can be declared within the services.xserver.windowManager.qtile attribute set.

You may add extra packages in the qtile python environment by putting them in the extraPackages list.

```
services.xserver.windowManager.qtile = {
  enable = true;
  extraPackages = python3Packages: with python3Packages; [
    qtile-extras
  ];
};
```

The Qtile package creates desktop files for both X11 and Wayland, to use one of the backends choose the right session in your display manager.

The configuration file can be changed from its default location (\$XDG_CONFIG/qtile/config.py) by setting the config-File attribute:

1.1. Distro Guides 5

```
qtile = {
  enable = true;
  configFile = ./my_qtile_config.py;
};
```

Note: Some options may change over time, please refer to see all the options for the latest stable: search.nixos.org if you have any doubt

Home manager

If you are using home-manager, you can copy your qtile configuration by using the following:

```
xdg.configFile."qtile/config.py".source = ./my_qtile_config.py;
```

or, if you have a directory containing multiple python files:

```
xdg.configFile."qtile" = {
  source = ./src;
  recursive = true;
};
```

Flake

Qtile also has a flake in the repository. This can be used for the following use cases:

- Run a bleeding edge version of Qtile by using it as an overlay in your flake config
- Hack on Qtile with a Nix develop shell

Note that flakes are an experimental NixOS feature but they are already widely used. This section is meant for users that already use flakes.

To run a bleeding edge version of Qtile with the flake, add the Qtile repo to your inputs and define the overlay. An example flake is the following:

```
description = "A very basic flake";
inputs = {
    nixpkgs.url = "github:nixos/nixpkgs?ref=nixos-unstable";

    qtile-flake = {
        url = "github:qtile/qtile";
        inputs.nixpkgs.follows = "nixpkgs";
    };
};

outputs = { self, nixpkgs, qtile-flake }: {
    nixosConfigurations.demo = nixpkgs.lib.nixosSystem {
        system = "x86_64-linux";
        modules = [
```

(continues on next page)

```
(_: { nixpkgs.overlays = [ qtile-flake.overlays.default ]; })
    ({ config, pkgs, lib, ...}: {
        services.xserver = {
            enable = true;
            windowManager.qtile.enable = true;
        };

    # make qtile X11 the default session
        services.displayManager.defaultSession = lib.mkForce "qtile";

    # rest of your NixOS config
        })
     ];
    };
};
```

This flake can also be tested with a vm:

```
sudo nixos-rebuild build-vm --flake .#demo
```

Gives you a script to run that runs Qemu to test your config. For this to work you have to set a user with a password.

To hack on Qtile with Nix, simply run *nix develop* in a checkout of the repo. In the development shell, there are a few useful things:

- qtile-run-tests-wayland: Run all Wayland tests
- qtile-run-tests-x11: Run all X11 tests

1.1.8 Running from systemd

This case will cover automatic login to Qtile after booting the system without using display manager. It logins in virtual console and init X by running through session.

Automatic login to virtual console

To get login into virtual console as an example edit *getty* service by running *systemctl edit getty*@tty1 and add instructions to /etc/systemd/system/getty@tty1.service.d/override.conf:

```
[Service]
ExecStart=
ExecStart=-/usr/bin/agetty --autologin username --noclear %I $TERM
```

username should be changed to current user name.

Check more for other examples.

1.1. Distro Guides 7

Autostart X session

After login X session should be started. That can be done by .bash_profile if bash is used or .zprofile in case of zsh. Other shells can be adjusted by given examples.

```
if systemctl -q is-active graphical.target && [[ ! $DISPLAY && $XDG_VTNR -eq 1 ]]; then
  exec startx
fi
```

And to start Qtile itself .xinitrc should be fixed:

```
# some apps that should be started before Qtile, ex.
#
#
    [[ -f ~/.Xresources ]] && xrdb -merge ~/.Xresources
#
    ~/.fehbg &
    nm-applet &
   blueman-applet &
#
#
    dunst &
#
# or
#
    source ~/.xsession
exec qtile start
```

1.2 Installing From Source

1.2.1 Python interpreters

We aim to always support the last three versions of CPython, the reference Python interpreter. We usually support the latest stable version of PyPy as well. You can check the versions and interpreters we currently run our test suite against in our tox configuration file.

There are not many differences between versions aside from Python features you may or may not be able to use in your config. PyPy should be faster at runtime than any corresponding CPython version under most circumstances, especially for bits of Python code that are run many times. CPython should start up faster than PyPy and has better compatibility for external libraries.

1.2.2 Core Dependencies

Here are Qtile's core runtime dependencies and the package names that provide them in Ubuntu. Note that Qtile can run with one of two backends -- X11 and Wayland -- so only the dependencies of one of these is required.

Dependency	Ubuntu Package	Needed for
Core Dependencies		
CFFI	python3-cffi	Bars and popups
cairocffi	python3-cairocffi	Drawing on bars and popups
libpangocairo	libpangocairo-1.0-0	Writing on bars and popups
dbus-fast		Sending notifications with dbus (optional).
X11		
X server	xserver-xorg	X11 backends
xcffib	python3-xcffib	required for X11 backend
Wayland		
wlroots	libwlroots-dev	Wayland backend (see below)
pywlroots		python bindings for the wlroots library
pywayland		python bindings for the wayland library
python-xkbcommon		required for wayland backeds

1.2.3 Qtile

With the dependencies in place, you can now install the stable version of qtile from PyPI:

```
uv tool install qtile
```

Or with sets of dependencies:

```
    uv tool install qtile[wayland]
    # for Wayland dependencies

    uv tool install qtile[widgets]
    # for all widget dependencies

    uv tool install qtile[all]
    # for all dependencies
```

Or install qtile-git with:

```
git clone https://github.com/qtile/qtile.git
cd qtile
uv tool install .
uv tool install --reinstall .[wayland] # reinstall with wayland deps
```

1.3 Starting Qtile

There are several ways to start Qtile. The most common way is via an entry in your X session manager's menu. The default Qtile behavior can be invoked by creating a qtile.desktop file in /usr/share/xsessions.

A second way to start Qtile is a custom X session. This way allows you to invoke Qtile with custom arguments, and also allows you to do any setup you want (e.g. special keyboard bindings like mapping caps lock to control, setting your desktop background, etc.) before Qtile starts. If you're using an X session manager, you still may need to create a custom.desktop file similar to the qtile.desktop file above, but with Exec=/etc/X11/xsession. Then, create your own ~/.xsession. There are several examples of user defined xsession s in the qtile-examples repository.

If there is no display manager such as SDDM, LightDM or other and there is need to start Qtile directly from ~/. xinitrc do that by adding exec qtile start at the end.

In very special cases, ex. Qtile crashing during session, then suggestion would be to start through a loop to save running applications:

1.3. Starting Qtile 9

```
while true; do
    qtile
done
```

1.4 Wayland

Qtile can be run as a Wayland compositor rather than an X11 window manager. For this, Qtile uses whoots, a compositor library which is undergoing fast development. Be aware that some distributions package outdated versions of whoots. More up-to-date distributions such as Arch Linux may package pywayland, pywhoots and python-xkbcommon. Also note that we may not have yet caught up with the latest whoots release ourselves.

Note: We currently support whoots>=0.17.0,<0.18.0, pywhoots>=0.17.0,<0.18.0 and pywayland >= 0.4.17.

With the Wayland dependencies in place, Qtile can be run either from a TTY, or within an existing X11 or Wayland session where it will run inside a nested window:

```
qtile start -b wayland
```

See the Wayland page for more information on running Qtile as a Wayland compositor.

Similar to the xsession example above, a wayland session file can be used to start qtile from a login manager. To use this, you should create a qtile-wayland.desktop file in /usr/share/wayland-sessions.

1.5 udev rules

Qtile has widgets that support managing various kinds of hardware (LCD backlight, keyboard backlight, battery charge thresholds) via the kernel's exposed sysfs endpoints. However, to make this work, Qtile needs permission to write to these files. There is a udev rules file at /resources/99-qtile.rules in the tree, which users installing from source will want to install at /etc/udev/rules.d/ on their system. By default, this rules file changes the group of the relevant files to the sudo group, and changes the file mode to be g+w (i.e. writable by all members of the sudo group). The theory here is that most systems qtile is installed on will also have the primary user in the sudo group. However, you can change this to whatever you like with the --group argument; see the sample udev rules.

Note that this file invokes Qtile's hidden udev from udevd, so udevd will need qtile in its \$PATH. For distro packaging this shouldn't be a problem, since /usr/bin is typically in udev's path. Alternatively, users can install from source using uv, which will do all the right \$PYTHONPATH setup etc., so you only need to change the path to the final executable in the udev rules:

```
# copy the in-tree udev rules file to the right place to make udev see it,
# and change the rules to point at our wrapper script above.
sed "s,qtile,$HOME/.local/bin/qtile,g" ./resources/99-qtile.rules | sudo tee /etc/udev/
→rules.d/99-qtile.rules
```

CHAPTER

TWO

RUNNING QTILE AS A WAYLAND COMPOSITOR

Some functionality may not yet be implemented in the Wayland compositor. Please see the Wayland To Do List discussion for the current state of development. Also checkout the unresolved Wayland-specific issues and *troubleshooting* for tips on how to debug Wayland problems.

Note: We currently support whoots>=0.17.0,<0.18.0 and pywhoots>=0.17.0,<0.18.0.

2.1 Backend-Specific Configuration

If you want your config file to work with different backends but want some options set differently per backend, you can check the name of the current backend in your config as follows:

```
from libqtile import qtile

if qtile.core.name == "x11":
    term = "urxvt"

elif qtile.core.name == "wayland":
    term = "foot"
```

2.2 Running X11-Only Programs

Qtile supports XWayland but requires that *wlroots* and *pywlroots* were built with XWayland support, and that XWayland is installed on the system from startup. XWayland will be started the first time it is needed.

2.2.1 XWayland windows sometimes don't receive mouse events

There is currently a known bug (https://github.com/qtile/qtile/issues/3675) which causes pointer events (hover/click/scroll) to propagate to the wrong window when switching focus.

2.3 Input Device Configuration

2.3.1 InputConfig

class libqtile.backend.wayland.InputConfig(**config: Any)

This is used to configure input devices. An instance of this class represents one set of settings that can be applied to an input device.

To use this, define a dictionary called wl_input_rules in your config. The keys are used to match input devices, and the values are instances of this class with the desired settings. For example:

```
from libqtile.backend.wayland import InputConfig

wl_input_rules = {
    "1267:12377:ELAN1300:00 04F3:3059 Touchpad": InputConfig(left_handed=True),
    "*": InputConfig(left_handed=True, pointer_accel=True),
    "type:keyboard": InputConfig(kb_options="ctrl:nocaps,compose:ralt"),
}
```

When a input device is being configured, the most specific matching key in the dictionary is found and the corresponding settings are used to configure the device. Unique identifiers are chosen first, then "type:X", then "*"

The command qtile cmd-obj -o core -f get_inputs can be used to get information about connected devices, including their identifiers.

Options default to None, leave a device's default settings intact. For information on what each option does, see the documenation for libinput: https://wayland.freedesktop.org/libinput/doc/latest/configuration.html. Note that devices often only support a subset of settings.

This tries to mirror how Sway configures libinput devices. For more information check out sway-input(5): https://man.archlinux.org/man/sway-input.5#LIBINPUT_CONFIGURATION

Keyboards, managed by xkbcommon, are configured with the options prefixed by kb_. X11's helpful XKB guide may be useful for figuring out the syntax for some of these settings.

Configuration options

key	default	description
accel_profile	None	'adaptive' or 'flat'
click_method	None	<pre>'none', 'button_areas' or 'clickfinger'</pre>
drag	None	True or False
drag_lock	None	True or False
dwt	None	True or False
kb_layout	None	Keyboard layout i.e. XKB_DEFAULT_LAYOUT
kb_options	None	Keyboard options i.e. XKB_DEFAULT_OPTIONS
kb_repeat_delay	600	Keyboard delay in milliseconds before repeating
kb_repeat_rate	25	Keyboard key repeats made per second
kb_variant	None	Keyboard variant i.e. XKB_DEFAULT_VARIANT
left_handed	None	True or False
middle_emulation	None	True or False
natural_scroll	None	True or False
<pre>pointer_accel</pre>	None	A float between -1 and 1.
scroll_button	None	'disable', 'Button[1-3,8,9]' or a keycode
scroll_method	None	<pre>'none', 'two_finger', 'edge', or 'on_button_down'</pre>
tap	None	True or False
tap_button_map	None	'lrm' or 'lmr'

If you want to change keyboard configuration during runtime, you can use the core's *set_keymap* command (see below).

2.4 Core Commands

See the Wayland backend section in the API Commands documentation.

2.4. Core Commands

0.1.dev50+g42		

CHAPTER

THREE

TROUBLESHOOTING

3.1 So something has gone wrong... what do you do?

When Qtile is running, it logs error messages (and other messages) to its log file. This is found at ~/.local/share/qtile/qtile.log. This is the first place to check to see what is going on. If you are getting unexpected errors from normal usage or your configuration (and you're not doing something wacky) and believe you have found a bug, then please report a bug.

If you are *hacking on Qtile* and you want to debug your changes, this log is your best friend. You can send messages to the log from within libqtile by using the logger:

```
from libqtile.log_utils import logger

logger.warning("Your message here")
logger.warning(variable_you_want_to_print)

try:
    # some changes here that might error
except Exception:
    logger.exception("Uh oh!")
```

logger.warning is convenient because its messages will always be visibile in the log. logger.exception is helpful because it will print the full traceback of an error to the log. By sticking these amongst your changes you can look more closely at the effects of any changes you made to Qtile's internals.

3.2 X11: Capturing an xtrace

Occasionally, a bug will be low level enough to require an xtrace of Qtile's conversations with the X server. To capture one of these, create an xinitro or similar file with:

```
exec xtrace qtile >> ~/qtile.log
```

This will put the xtrace output in Qtile's logfile as well. You can then demonstrate the bug, and paste the contents of this file into the bug report.

Note that xtrace may be named x11trace on some platforms, for example, on Fedora and Arch.

3.3 Debugging in Wayland

To get incredibly verbose output of communications between clients and the server, you can set WAYLAND_DEBUG=1 in the environment before starting the process. This applies to the server itself, so be aware that running qtile with this set will generate lots of output for Qtile and all clients that it launches. If you're including this output with a bug report please try to cut out just the relevant portions.

If you're hacking on Qtile and would like this debug log output for it rather than any clients, it can be helpful to run the helper script at scripts/wephyr in the source from an existing session. You can then run clients from another terminal using the WAYLAND_DISPLAY value printed by Qtile, so that the debug logs printed by Qtile are only the server's.

If you suspect a client may be responsible for a bug, it can be helpful to look at the issue trackers for other compositors, such as sway. Similarly if you're hacking on Qtile's internals and think you've found an unexpected quirk it may be helpful to search the issue tracker for wlroots.

CHAPTER

FOUR

ENTRY POINTS

Qtile uses a subcommand structure; various subcommands are listed below. Additionally, two other commands available in the scripts/ section of the repository are also documented below.

4.1 qtile start

This is the entry point for the window manager, and what you should run from your .xsession or similar. This will make an attempt to detect if qtile is already running and fail if it is. See qtile start --help for more details.

4.2 qtile shell

The Qtile command shell is a command-line shell interface that provides access to the full complement of Qtile command functions. The shell features command name completion, and full command documentation can be accessed from the shell itself. The shell uses GNU Readline when it's available, so the interface can be configured to, for example, obey VI keybindings with an appropriate .inputrc file. See the GNU Readline documentation for more information.

4.2.1 Navigating the Object Graph

The shell presents a filesystem-like interface to the command graph - the builtin "cd" and "ls" commands act like their familiar shell counterparts:

```
> ls
layout/ widget/ screen/ bar/ window/ group/
> cd screen
layout/ window/ bar/ widget/
> cd ..
/
> ls
layout/ widget/ screen/ bar/ window/ group/
```

If you try to access an object that has no "default" value then you will see an error message:

```
> ls
layout/ widget/ screen/ bar/ window/ group/
(continues on next page)
```

```
> cd bar
Item required for bar
> ls bar
bar[bottom]/
> cd bar/bottom
bar['bottom']> ls
screen/ widget/
```

Please refer to *Navigating the command graph* for a summary of which objects need a specified selector and the type of selector required. Using 1s will show which selectors are available for an object. Please see below for an explanation about how Qtile displays shell paths.

Alternatively, the items() command can be run on the parent object to show which selectors are available. The first value shows whether a selector is optional (False means that a selector is required) and the second value is a list of selectors:

```
> ls
layout/ widget/ screen/ bar/ window/ group/
> items(bar)
(False, ['bottom'])
```

4.2.2 Displaying the shell path

Note that the shell provides a "short-hand" for specifying node keys (as opposed to children). The following is a valid shell path:

```
> cd group/4/window/31457314
```

The command prompt will, however, always display the Python node path that should be used in scripts and key bindings:

```
group['4'].window[31457314]>
```

4.2.3 Live Documentation

The shell help command provides the canonical documentation for the Qtile API:

```
> cd layout/1
layout[1]> help
help command -- Help for a specific command.

Builtins
=======
cd exit help ls q quit

Commands for this object
```

(continues on next page)

add delete doc commands current down get_info items next previous shuffle_down shuffle_up rotate toggle_split up layout[1]> help previous previous() Focus previous stack.

4.3 qtile migrate

qtile migrate is a tool to help users update their configs to reflect any breaking changes/deprecations introduced in later versions.

The tool can automatically apply updates but it can also be used to highlight impacted lines, allowing users to update their configs manually.

The tool can take a number of options when running:

Argu- ment	Description	Default
-c, config	Sets the path to the config file	~/.config/qtile/config.py
list-m	Lists all the available migrations that can be run by the tool.	n/a
info ID	Show more detail about the migration implement by ID.	n/a
	Only runs migrations relating to changes implemented after release VERSION.	Not set (i.e. runs all migrations).
-r ID, run-mi ID	Run selected migrations identified by ID. Comma separated list if using multiple values.	Not set (i.e. runs all migrations).
yes	Automatically apply changes without asking user for confirmation.	Not set (i.e. users will need to confirm application of changes).
show-d	When used withyes will cause diffs to still be shown for information purposes only.	Not set.
no-col	Disables colour output for diff.	Not set
lint	Outputs linting lines showing location of changes. No changes are made to the config.	Not set.

4.3. qtile migrate

4.3.1 Available migrations

The following migrations are currently available.

ID	Changes troduced version	in- after	Summary
UpdateBitcoin	0.18.0		Updates BitcoinTicker to CryptoTicker.
<i>UpdateBluetoothArgs</i>	0.23.0		Updates Bluetooth argument signature.
<i>UpdateKeychordArgs</i>	0.21.0		Updates KeyChord argument signature.
<i>UpdateStocktickerArgs</i>	0.22.1		Updates StockTicker argument signature.
<i>UpdateWidgetboxArgs</i>	0.20.0		Updates WidgetBox argument signature.
<i>UpdateWlanArgs</i>	0.31.0		Updates Wlan argument signature.
MatchListRegex	0.23.0		Updates Match objects using lists
ModuleRenames	0.18.1		Updates certain deprecated libqtile. module names.
RemoveCmdPrefix	0.22.1		Removes cmd_ prefix from method calls and definitions.
RenamePacmanWidget	0.16.1		Changes deprecated Pacman widget name to CheckUpdates.
RenameCurrentLayoutIcon	0.32.0		Removed CurrentLayoutIcon widget.
RenameWindowNameHook	0.16.1		Changes window_name_changed hook name.
RenameThreadedPollText	0.16.1		Replaces ThreadedPollText with ThreadPoolText.
RenameTileMaster	0.16.1		Changes masterWindows argument to master_length.
RenameUnspecified	0.25.0		Drops UNSPECIFIED argument
<i>UpdateMonadArgs</i>	0.17.0		Updates new_at_current keyword argument in Monad layouts.
<i>UpdateTogroupArgs</i>	0.18.1		Updates groupName keyword argument to group_name.

4.3.2 Running migrations

Assuming your config file is in the default location, running qtile migrate is sufficent to start the migration process. Let's say you had a config file with the following contents:

```
import libqtile.command_client

keys = [
    KeyChord(
        [mod],
        "x",
        [Key([], "Up", lazy.layout.grow()), Key([], "Down", lazy.layout.shrink())],
        mode="Resize layout",
    )
]

qtile.cmd_spawn("alacritty")
```

Running qtile migrate will run each available migration and, where the migration would result in changes, a diff will be shown and you will be asked whether you wish to apply the changes.

```
--- original
+++ modified
@@ -5,7 +5,8 @@

[mod],
    "x",
    [Key([], "Up", lazy.layout.grow()), Key([], "Down", lazy.layout.shrink())],
-    mode="Resize layout",
+    name="Resize layout",
+    mode=True,
    )
]

Apply changes? (y)es, (n)o, (s)kip file, (q)uit.
```

You will see from the output above that you are shown the name of the migration being applied and its purpose, along with the changes that will be implemented.

If you select quit the migration will be stopped and any applied changes will be reversed.

Once all migrations have been run on a file, you will then be asked whether you want to save changes to the file:

```
Save all changes to config.py? (y)es, (n)o.
```

At the end of the migration, backups of your original config will still be in your config folder. NB these will be overwritten if you re-run qtile migrate.

4.3.3 Linting

If you don't want the script to modify your config directly, you can use the --lint option to show you where changes are required.

Running qtile migrate --lint on the same config as shown above will result in the following output:

```
config.py:
[Ln 1, Col 7]: The 'libqtile.command_*' modules have been moved to 'libqtile.command.*'...

(ModuleRenames)
[Ln 8, Col 8]: The use of mode='mode name' for KeyChord is deprecated. Use mode=True and...

value='mode name'. (UpdateKeychordArgs)
[Ln 12, Col 6]: Use of 'cmd_' prefix is deprecated. 'cmd_spawn' should be replaced with

'spawn' (RemoveCmdPrefix)
```

4.3.4 Explanations of migrations

The table below provides more detail of the available migrations.

4.3. qtile migrate 21

UpdateBitcoin

```
Migration introduced after version 0.18.0
```

The BitcoinTicker widget has been renamed CryptoTicker. In addition, the format keyword argument is removed during this migration as the available fields for the format have changed.

The removal only happens on instances of BitcoinTracker. i.e. running qtile migrate on the following code:

```
BitcoinTicker(format="...")
CryptoTicker(format="...")
```

will return:

```
CryptoTicker()
CryptoTicker(format="...")
```

UpdateBluetoothArgs

```
Migration introduced after version 0.23.0
```

The Bluetooth widget previously accepted a hci keyword argument. This has been deprecated following a major overhaul of the widget and should be replaced with a keyword argument named device.

For example:

```
widget.Bluetooth(hci="/dev_XX_XX_XX_XXX_XX")
```

should be changed to:

```
widget.Bluetooth(device="/dev_XX_XX_XX_XX_XX")
```

UpdateKeychordArgs

```
Migration introduced after version 0.21.0
```

Previously, users could make a key chord persist by setting the *mode* to a string representing the name of the mode. For example:

```
keys = [
    KeyChord(
        [mod],
        "x",
        [
             Key([], "Up", lazy.layout.grow()),
             Key([], "Down", lazy.layout.shrink())
        ],
        mode="Resize layout",
        (continues on next page)
```

```
]
```

This will now result in the following warning message in the log file:

```
The use of `mode` to set the KeyChord name is deprecated. Please use `name='Resize Layout
→'` instead.
'mode' should be a boolean value to set whether the chord is persistent (True) or not."
```

To remove the error, the config should be amended as follows:

```
keys = [
    KeyChord(
        [mod],
        "x",
        [
             Key([], "Up", lazy.layout.grow()),
             Key([], "Down", lazy.layout.shrink())
        ],
        name="Resize layout",
        mode=True,
    )
]
```

Note: The formatting of the inserted argument may not correctly match your own formatting. You may this to run a tool like black after applying this migration to tidy up your code.

UpdateStocktickerArgs

```
Migration introduced after version 0.22.1
```

The StockTicker widget had a keyword argument called function. This needs to be renamed to func to prevent clashes with the function() method of CommandObject.

For example:

```
widget.StockTicker(function="TIME_SERIES_INTRADAY")
```

should be changed to:

```
widget.StockTicker(func="TIME_SERIES_INTRADAY")
```

4.3. qtile migrate 23

UpdateWidgetboxArgs

Migration introduced after version 0.20.0

The WidgetBox widget allowed a position argument to set the contents of the widget. This behaviour is deprecated and, instead, the contents should be specified with a keyword argument called widgets.

For example:

should be changed to:

```
widget.WidgetBox(
    widgets=[
        widget.Systray(),
        widget.Volume(),
    ]
)
```

UpdateWlanArgs

Migration introduced after version 0.31.0

The Wlan widget previously accepted a ethernet_message keyword argument. This has been deprecated and should be replaced with a keyword argument named ethernet_message_format.

For example:

```
widget.Wlan(ethernet_message="eth")
```

should be changed to:

```
widget.Wlan(ethernet_message_format="eth")
```

MatchListRegex

Migration introduced after version 0.23.0

The use of lists in Match objects is deprecated and should be replaced with a regex.

For example:

```
Match(wm_class=["one", "two"])
```

should be changed to:

```
Match(wm_class=re.compile(r"^(one|two)$"))
```

ModuleRenames

Migration introduced after version 0.18.1

libqtile.window module was moved to libqtile.backend.x11.window.

RemoveCmdPrefix

Migration introduced after version 0.22.1

The cmd_ prefix was used to identify methods that should be exposed to qtile's command API. This has been deprecated and so calls no longer require the prefix.

For example:

```
qtile.cmd_spawn("vlc")
```

would be replaced with:

```
qtile.spawn("vlc")
```

Where users have created their own widgets with methods using this prefix, the syntax has also changed:

For example:

```
class MyWidget(libqtile.widget.base._Widget):
    def cmd_my_command(self):
        pass
```

Should be updated as follows:

```
from libqtile.command.base import expose_command

class MyWidget(libqtile.widget.base._Widget):
    @expose_command
    def my_command(self):
        pass
```

4.3. qtile migrate 25

RenamePacmanWidget

Migration introduced after version 0.16.1

The Pacman widget has been renamed to CheckUpdates.

This is because the widget supports multiple package managers.

Example:

Should be updated as follows:

RenameCurrentLayoutlcon

Migration introduced after version 0.32.0

The CurrentLayoutIcon widget's functionality has been merged with CurrentLayout.

Example:

```
widgets=[
    widget.CurrentLayoutIcon(),
    ...
],
```

Should be updated as follows:

```
widgets=[
    widget.CurrentLayout(icon_first=True),
    ...
],
```

RenameWindowNameHook

```
Migration introduced after version 0.16.1
```

The window_name_changed hook has been replaced with client_name_updated.

Example:

```
@hook.subscribe.window_name_changed
def my_func(window):
    ...
```

Should be updated as follows:

```
@hook.subscribe.client_name_updated
def my_func(window):
    ...
```

RenameThreadedPollText

```
Migration\ introduced\ after\ version \quad \  0.16.1
```

The ThreadedPollText class needs to replied with ThreadPoolText.

This is because the ThreadPoolText class can do everything that the ThreadedPollText does so the redundant code was removed.

Example:

```
from libqtile import widget

class MyPollingWidget(widget.base.ThreadedPollText):
    ...
```

Should be updated as follows:

```
from libqtile import widget

class MyPollingWidget(widget.base.ThreadPoolText):
    ...
```

4.3. qtile migrate 27

RenameTileMaster

Migration introduced after version 0.16.1

To be consistent with other layouts, the masterWindows property of the Tile layout was renamed to master_length. Configs using the masterWindows argument when configuring the layout should replace this.

RenameUnspecified

Migration introduced after version 0.25.0

The UNSPECIFIED object was removed in favor of using the zero values (or None) to leave behavior unspecified. That is:

font=UNSPECIFIED -> fontsNone fontsize=UNSPECIFIED -> fontsize=0 fontshadow=UNSPECIFIED -> fontshadow=""

UpdateMonadArgs

Migration introduced after version 0.17.0

Replaces the new_at_current=True|False argument in Monad* layouts with new_client_position to be consistent with other layouts.

new_at_current=True is replaced with new_client_position="before_current and new_at_current=False is replaced with new_client_position="after_current".

UpdateTogroupArgs

Migration introduced after version 0.18.1

To be consistent with codestyle, the groupName argument in the togroup command needs to be changed to group_name.

The following code:

lazy.window.togroup(groupName="1")

 $will \ result \ in \ a \ warning \ in \ your \ log file: \ \textbf{Window.togroup's groupName is deprecated;} \ use \ group_name.$

The code should be updated to:

lazy.window.togroup(group_name="1")

4.4 qtile cmd-obj

This is a simple tool to expose quile.command functionality to shell. This can be used standalone or in other shell scripts.

4.4.1 How it works

qtile cmd-obj works by selecting a command object and calling a specified function of that object.

As per *Architecture*, Qtile's command graph has seven nodes: layout, window, group, bar, widget, screen, and a special root node. These are the objects that can be accessed via qtile cmd-obj.

Running the command against a selected object without a function (-f) will run the help command and list the commands available to the object. Commands shown with an asterisk ("*") require arguments to be passed via the -a flag.

Selecting an object

With the exception of cmd, all objects need an identifier so the correct object can be selected. Refer to *Navigating the command graph* for more information.

Note: You will see from the graph on *Architecture* that certain objects can be accessed from other objects. For example, qtile cmd-obj -o group term layout will list the commands for the current layout on the term group.

Information on functions

Running a function with the -i flag will provide additional detail about that function (i.e. what it does and what arguments it expects).

Passing arguments to functions

Arguments can be passed to a function by using the -a flag. For example, to change the label for the group named "1" to "A", you would run qtile cmd-obj -o group 1 -f set_label -a A.

Warning: It is not currently possible to pass non-string arguments to functions via qtile cmd-obj. Doing so will result in an error.

4.4.2 Examples:

Output of qtile cmd-obj -h

4.4. qtile cmd-obj 29

(continues on next page)

```
optional arguments:
 -h, --help
                        show this help message and exit
  --object OBJ_SPEC [OBJ_SPEC ...], -o OBJ_SPEC [OBJ_SPEC ...]
                        Specify path to object (space separated). If no
                        --function flag display available commands.
 --function FUNCTION, -f FUNCTION
                        Select function to execute.
 --args ARGS [ARGS ...], -a ARGS [ARGS ...]
                        Set arguments supplied to function.
                        With both --object and --function args prints
 --info, -i
                        documentation for function.
Examples:
qtile cmd-obj
qtile cmd-obj -o root # same as above, root node is default
qtile cmd-obj -o root -f prev_layout -i
qtile cmd-obj -o root -f prev_layout -a 3 # prev_layout on group 3
qtile cmd-obj -o group 3 -f focus_back
qtile cmd-obj -o widget textbox -f update -a "New text"
qtile cmd-obj -f restart # restart qtile
```

Output of qtile cmd-obj -o group 3

```
-o group 3 -f commands
                                  Returns a list of possible commands for this object
-o group 3 -f doc
                                * Returns the documentation for a specified command name
-o group 3 -f eval
                                * Evaluates code in the same context as this function
-o group 3 -f focus_back
                                  Focus the window that had focus before the current one.
⇔got it.
-o group 3 -f focus_by_name
                                * Focus the first window with the given name. Do nothing_
\rightarrow if the name is
-o group 3 -f function
                                * Call a function with current object as argument
                                  Returns a dictionary of info for this group
-o group 3 -f info
-o group 3 -f info_by_name
                                * Get the info for the first window with the given name_
→without giving it
-o group 3 -f items
                                * Returns a list of contained items for the specified_
→name
-o group 3 -f next_window
                                  Focus the next window in group.
-o group 3 -f prev_window
                                  Focus the previous window in group.
-o group 3 -f set_label
                                * Set the display name of current group to be used in_
→GroupBox widget.
-o group 3 -f setlayout
-o group 3 -f switch_groups
                                * Switch position of current group with name
-o group 3 -f toscreen
                                * Pull a group to a specified screen.
-o group 3 -f unminimize_all
                                  Unminimise all windows in this group
```

Output of qtile cmd-obj -o root

```
* Add a dgroup rule, returns rule_id needed to remove it
-o root -f add_rule
-o root -f addgroup
                                 * Add a group with the given name
-o root -f commands
                                   Returns a list of possible commands for this object
-o root -f critical
                                   Set log level to CRITICAL
-o root -f debug
                                   Set log level to DEBUG
-o root -f delgroup
                                 * Delete a group with the given name
                                 * Display table of key bindings
-o root -f display_kb
                                 * Returns the documentation for a specified command name
-o root -f doc
-o root -f error
                                   Set log level to ERROR
-o root -f eval
                                 * Evaluates code in the same context as this function
-o root -f findwindow
                                 * Launch prompt widget to find a window of the given_

→ name

-o root -f focus_by_click
                                 * Bring a window to the front
-o root -f function
                                 * Call a function with current object as argument
-o root -f get_info
                                   Prints info for all groups
-o root -f get_state
                                   Get pickled state for restarting gtile
                                  Returns any content arbitrarily set in the self.test_
-o root -f get_test_data

→data attribute.
-o root -f groups
                                  Return a dictionary containing information for all_
→ groups
-o root -f hide_show_bar
                                 * Toggle visibility of a given bar
-o root -f info
                                   Set log level to INFO
-o root -f internal_windows
                                   Return info for each internal window (bars, for_
→example)
-o root -f items
                                 * Returns a list of contained items for the specified_
→name
-o root -f list_widgets
                                   List of all addressible widget names
-o root -f next_layout
                                 * Switch to the next layout.
-o root -f next_screen
                                   Move to next screen
-o root -f next_urgent
                                   Focus next window with urgent hint
-o root -f pause
                                   Drops into pdb
-o root -f prev_layout
                                 * Switch to the previous layout.
-o root -f prev_screen
                                   Move to the previous screen
-o root -f qtile_info
                                   Returns a dictionary of info on the Qtile instance
                                 * Execute a Qtile command using the client syntax
-o root -f qtilecmd
-o root -f remove_rule
                                 * Remove a dgroup rule by rule_id
-o root -f restart
                                   Restart gtile
-o root -f run_extension
                                 * Run extensions
-o root -f run_external
                                 * Run external Python script
-o root -f screens
                                   Return a list of dictionaries providing information.
→on all screens
-o root -f shutdown
                                   Quit Qtile
-o root -f simulate_keypress
                                 * Simulates a keypress on the focused window.
                                 * Run cmd in a shell.
-o root -f spawn
-o root -f spawncmd
                                 * Spawn a command using a prompt widget, with tab-
→completion.
                                   Return "OK" if Qtile is running
-o root -f status
                                 * Switch position of groupa to groupb
-o root -f switch_groups
-o root -f switchgroup
                                 * Launch prompt widget to switch to a given group to.
→the current screen
-o root -f sync
                                   Sync the X display. Should only be used for.
```

(continues on next page)

4.4. qtile cmd-obj

```
→development
-o root -f to_layout_index
                                  * Switch to the layout with the given index in self.
→layouts.
-o root -f to_screen
                                  * Warp focus to screen n, where n is a 0-based screen_
\rightarrownumber
-o root -f togroup
                                  * Launch prompt widget to move current window to a.
⊸given group
-o root -f tracemalloc_dump
                                    Dump tracemalloc snapshot
-o root -f tracemalloc_toggle
                                    Toggle tracemalloc status
-o root -f warning
                                    Set log level to WARNING
-o root -f windows
                                    Return info for each client window
```

4.5 qtile repl

Creates a REPL (Read-Evaluate-Print-Loop) client with access to the qtile internals.

The client requires the prompt_toolkit library to work.

The client has support for code completion, multiline input and input history.

Running qtile repl will start the server with access to the qtile instance. However, users can add extra items to the REPL's environment by starting the REPL server from their config before launching the client e.g.:

This will add all variables from a user's config to the REPL environment, allowing users to trigger their own functions etc.

The REPL server runs on port 41414. This is hardcoded for now but we expect to make changes to qtile's wire format in the future.

4.6 qtile run-cmd

Run a command applying rules to the new windows, ie, you can start a window in a specific group, make it floating, intrusive, etc.

The Windows must have NET WM PID.

```
# run xterm floating on group "test-group"
qtile run-cmd -g test-group -f xterm
```

4.7 qtile top

qtile top is a top-like tool to measure memory usage of Qtile's internals.

Note: To use qtile top you need to have tracemalloc enabled. You can do this by setting the environmental variable PYTHONTRACEMALLOC=1 before starting qtile. Alternatively, you can force start tracemalloc but you will lose early traces:

```
>>> from libqtile.command.client import InteractiveCommandClient
>>> i=InteractiveCommandClient()
>>> i.eval("import tracemalloc;tracemalloc.start()")
```

4.8 dqtile-cmd

A Rofi/dmenu interface to qtile-cmd. Accepts all arguments of qtile-cmd.

4.8.1 Examples:

Output of dqtile-cmd -o cmd

dmenu:			
Alt-1 C-u Esc	Go back to menu. Clear input	show '	function help (if -f is present)
-o cmd	-f add_rule	*	Add a dgroup rule, returns rule_id needed to remove it
-o cmd	-f addgroup	*	Add a group with the given name
-o cmd	-f commands		Returns a list of possible commands for this object
-o cmd	-f critical		Set log level to CRITICAL
-o cmd	-f debug		Set log level to DEBUG
-o cmd	-f delgroup	*	Delete a group with the given name
-o cmd	-f display_kb	*	Display table of key bindings
-o cmd	-f doc	*	Returns the documentation for a specified command name
-o cmd	-f error		Set log level to ERROR
-o cmd	-f eval	*	Evaluates code in the same context as this function
-o cmd	-f findwindow	*	Launch prompt widget to find a window of the given name
-o cmd	-f focus_by_click	*	Bring a window to the front
-o cmd	-f function	*	Call a function with current object as argument
-o cmd	-f get_info		Prints info for all groups
-o cmd	-f get_state		Get pickled state for restarting qtile

4.7. qtile top 33

Output of dqtile-cmd -h

```
dqtile-cmd
   A Rofi/dmenu interface to qtile-cmd. Excepts all arguments of qtile-cmd
    (see below).
usage: dqtile-cmd [-h] [--object OBJ_SPEC [OBJ_SPEC ...]]
                  [--function FUNCTION] [--args ARGS [ARGS ...]] [--info]
Simple tool to expose qtile.command functionality to shell.
optional arguments:
  -h, --help
                        show this help message and exit
  --object OBJ_SPEC [OBJ_SPEC ...], -o OBJ_SPEC [OBJ_SPEC ...]
                        Specify path to object (space separated). If no
                        --function flag display available commands.
  --function FUNCTION, -f FUNCTION
                        Select function to execute.
  --args ARGS [ARGS ...], -a ARGS [ARGS ...]
                        Set arguments supplied to function.
  --info, -i
                        With both --object and --function args prints
                        documentation for function.
Examples:
dqtile-cmd
dqtile-cmd -o cmd
dqtile-cmd -o cmd -f prev_layout -i
dqtile-cmd -o cmd -f prev_layout -a 3 # prev_layout on group 3
dqtile-cmd -o group 3 -f focus_back
If both rofi and dmenu are present rofi will be selected as default, to change this us --
→force-dmenu as the first argument.
```

4.9 iqshell

In addition to the standard qtile shell shell interface, we provide a kernel capable of running through Jupyter that hooks into the qshell client. The command structure and syntax is the same as qshell, so it is recommended you read that for more information about that.

4.9.1 Dependencies

In order to run iqshell, you must have ipykernel and jupyter_console. You can install the dependencies when you are installing qtile by running:

```
$ pip install qtile[ipython]
```

Otherwise, you can just install these two packages separately, either through PyPI or through your distribution package manager.

4.9.2 Installing and Running the Kernel

Once you have the required dependencies, you can run the kernel right away by running:

```
$ python3 -m libqtile.interactive.iqshell_kernel
```

However, this will merely spawn a kernel instance, you will have to run a separate frontend that connects to this kernel.

A more convenient way to run the kernel is by registering the kernel with Jupyter. To register the kernel itself, run:

```
$ python3 -m libqtile.interactive.iqshell_install
```

If you run this as a non-root user, or pass the --user flag, this will install to the user Jupyter kernel directory. You can now invoke the kernel directly when starting a Jupyter frontend, for example:

```
$ jupyter console --kernel qshell
```

The iqshell script will launch a Jupyter terminal console with the qshell kernel.

4.9.3 iqshell vs qtile shell

One of the main drawbacks of running through a Jupyter kernel is the frontend has no way to query the current node of the kernel, and as such, there is no way to set a custom prompt. In order to query your current node, you can call pwd.

This, however, enables many of the benefits of running in a Jupyter frontend, including being able to save, run, and re-run code cells in frontends such as the Jupyter notebook.

The Jupyter kernel also enables more advanced help, text completion, and introspection capabilities (however, these are currently not implemented at a level much beyond what is available in the standard qtile shell).

4.9. iqshell 35

CHAPTER

FIVE

DEFAULT CONFIG FILE

The below default config file is included with the Qtile package and will be copied to your home config folder (~/.con-fig/qtile/config.py) if no config file exists when you start Qtile for the first time.

```
# Copyright (c) 2010 Aldo Cortesi
# Copyright (c) 2010, 2014 dequis
# Copyright (c) 2012 Randall Ma
# Copyright (c) 2012-2014 Tycho Andersen
# Copyright (c) 2012 Craig Barnes
# Copyright (c) 2013 horsik
# Copyright (c) 2013 Tao Sauvage
# Permission is hereby granted, free of charge, to any person obtaining a copy
# of this software and associated documentation files (the "Software"), to deal
# in the Software without restriction, including without limitation the rights
# to use, copy, modify, merge, publish, distribute, sublicense, and/or sell
# copies of the Software, and to permit persons to whom the Software is
# furnished to do so, subject to the following conditions:
# The above copyright notice and this permission notice shall be included in
# all copies or substantial portions of the Software.
# THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR
# IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY,
# FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE
# AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER
# LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM,
# OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE
# SOFTWARE.
import os
import libqtile.resources
from libqtile import bar, layout, qtile, widget
from libqtile.config import Click, Drag, Group, Key, Match, Screen
from libqtile.lazy import lazy
from libqtile.utils import guess_terminal
mod = "mod4"
terminal = guess_terminal()
```

```
kevs = \Gamma
    # A list of available commands that can be bound to keys can be found
    # at https://docs.qtile.org/en/latest/manual/config/lazy.html
    # Switch between windows
   Key([mod], "h", lazy.layout.left(), desc="Move focus to left"),
   Key([mod], "1", lazy.layout.right(), desc="Move focus to right"),
   Key([mod], "j", lazy.layout.down(), desc="Move focus down"),
   Key([mod], "k", lazy.layout.up(), desc="Move focus up"),
   Key([mod], "space", lazy.layout.next(), desc="Move window focus to other window"),
    # Move windows between left/right columns or move up/down in current stack.
    # Moving out of range in Columns layout will create new column.
   Key([mod, "shift"], "h", lazy.layout.shuffle_left(), desc="Move window to the left"),
   Key([mod, "shift"], "l", lazy.layout.shuffle_right(), desc="Move window to the right
   Key([mod, "shift"], "j", lazy.layout.shuffle_down(), desc="Move window down"),
   Key([mod, "shift"], "k", lazy.layout.shuffle_up(), desc="Move window up"),
    # Grow windows. If current window is on the edge of screen and direction
    # will be to screen edge - window would shrink.
   Key([mod, "control"], "h", lazy.layout.grow_left(), desc="Grow window to the left"),
   Key([mod, "control"], "l", lazy.layout.grow_right(), desc="Grow window to the right
   Key([mod, "control"], "j", lazy.layout.grow_down(), desc="Grow window down"),
   Key([mod, "control"], "k", lazy.layout.grow_up(), desc="Grow window up"),
   Key([mod], "n", lazy.layout.normalize(), desc="Reset all window sizes"),
    # Toggle between split and unsplit sides of stack.
    # Split = all windows displayed
    # Unsplit = 1 window displayed, like Max layout, but still with
    # multiple stack panes
   Key(
        [mod, "shift"],
        "Return",
       lazy.layout.toggle_split(),
        desc="Toggle between split and unsplit sides of stack",
   ),
   Key([mod], "Return", lazy.spawn(terminal), desc="Launch terminal"),
    # Toggle between different layouts as defined below
   Key([mod], "Tab", lazy.next_layout(), desc="Toggle between layouts"),
   Key([mod], "w", lazy.window.kill(), desc="Kill focused window"),
   Key(
        [mod],
        "f",
       lazy.window.toggle_fullscreen(),
       desc="Toggle fullscreen on the focused window",
   Key([mod], "t", lazy.window.toggle_floating(), desc="Toggle floating on the focused_
→window"),
   Key([mod, "control"], "r", lazy.reload_config(), desc="Reload the config"),
   Key([mod, "control"], "q", lazy.shutdown(), desc="Shutdown Qtile"),
   Key([mod], "r", lazy.spawncmd(), desc="Spawn a command using a prompt widget"),
1
# Add key bindings to switch VTs in Wayland.
```

```
# We can't check qtile.core.name in default config as it is loaded before qtile is..
# We therefore defer the check until the key binding is run by using .when(func=...)
for vt in range(1, 8):
   keys.append(
        Key(
            ["control", "mod1"],
            f"f{vt}",
            lazy.core.change_vt(vt).when(func=lambda: gtile.core.name == "wayland"),
            desc=f"Switch to VT{vt}",
        )
   )
groups = [Group(i) for i in "123456789"]
for i in groups:
   keys.extend(
        # mod + group number = switch to group
            Key(
                [mod],
                i.name,
                lazy.group[i.name].toscreen(),
                desc=f"Switch to group {i.name}",
            ),
            # mod + shift + group number = switch to & move focused window to group
            Key(
                [mod, "shift"],
                i.name,
                lazy.window.togroup(i.name, switch_group=True),
                desc=f"Switch to & move focused window to group {i.name}",
            ),
            # Or, use below if you prefer not to switch to that group.
            # # mod + shift + group number = move focused window to group
            # Key([mod, "shift"], i.name, lazy.window.togroup(i.name),
                  desc="move focused window to group {}".format(i.name)),
       ]
   )
layouts = [
   layout.Columns(border_focus_stack=["#d75f5f", "#8f3d3d"], border_width=4),
   layout.Max(),
    # Try more layouts by unleashing below layouts.
    # layout.Stack(num_stacks=2),
    # layout.Bsp(),
    # layout.Matrix(),
   # layout.MonadTall(),
   # layout.MonadWide(),
   # layout.RatioTile().
    # layout.Tile(),
    # layout.TreeTab(),
                                                                            (continues on next page)
```

```
# layout.VerticalTile(),
    # layout.Zoomy(),
]
widget_defaults = dict(
    font="sans",
    fontsize=12,
   padding=3,
extension_defaults = widget_defaults.copy()
logo = os.path.join(os.path.dirname(libqtile.resources.__file__), "logo.png")
screens = [
    Screen(
        bottom=bar.Bar(
                widget.CurrentLayout(),
                widget.GroupBox(),
                widget.Prompt(),
                widget.WindowName(),
                widget.Chord(
                    chords_colors={
                        "launch": ("#ff0000", "#ffffff"),
                    },
                    name_transform=lambda name: name.upper(),
                ),
                widget.TextBox("default config", name="default"),
                widget.TextBox("Press <M-r&gt; to spawn", foreground="#d75f5f"),
                # NB Systray is incompatible with Wayland, consider using StatusNotifier.
→instead
                # widget.StatusNotifier(),
                widget.Systray(),
                widget.Clock(format="%Y-%m-%d %a %I:%M %p"),
                widget QuickExit(),
            ],
            24,
            # border_width=[2, 0, 2, 0], # Draw top and bottom borders
            # border_color=["ff00ff", "000000", "ff00ff", "000000"] # Borders are,
→ magenta
        background="#000000",
        wallpaper=logo,
        wallpaper_mode="center",
        # You can uncomment this variable if you see that on X11 floating resize/moving_
⇒is laggy
        # By default we handle these events delayed to already improve performance,
→however your system might still be struggling
        # This variable is set to None (no cap) by default, but you can set it to 60 to...
→indicate that you limit it to 60 events per second
        # x11_drag_polling_rate = 60.
   ),
]
```

```
# Drag floating layouts.
mouse = [
   Drag([mod], "Button1", lazy.window.set_position_floating(), start=lazy.window.get_
→position()),
   Drag([mod], "Button3", lazy.window.set_size_floating(), start=lazy.window.get_
\rightarrowsize()),
    Click([mod], "Button2", lazy.window.bring_to_front()),
]
dgroups_key_binder = None
dgroups_app_rules = [] # type: list
follow_mouse_focus = True
bring_front_click = False
floats_kept_above = True
cursor_warp = False
floating_layout = layout.Floating(
    float_rules=[
        # Run the utility of `xprop` to see the wm class and name of an X client.
        *layout.Floating.default_float_rules,
        Match(wm_class="confirmreset"), # gitk
        Match(wm_class="makebranch"), # gitk
        Match(wm_class="maketag"), # gitk
        Match(wm_class="ssh-askpass"), # ssh-askpass
        Match(title="branchdialog"), # gitk
        Match(title="pinentry"), # GPG key password entry
   ]
)
auto_fullscreen = True
focus_on_window_activation = "smart"
focus_previous_on_window_remove = False
reconfigure_screens = True
# If things like steam games want to auto-minimize themselves when losing
# focus, should we respect this or not?
auto_minimize = True
# When using the Wayland backend, this can be used to configure input devices.
wl_input_rules = None
# xcursor theme (string or None) and size (integer) for Wayland backend
wl_xcursor_theme = None
wl xcursor size = 24
# XXX: Gasp! We're lying here. In fact, nobody really uses or cares about this
# string besides java UI toolkits; you can see several discussions on the
# mailing lists, GitHub issues, and other WM documentation that suggest setting
# this string if your java app doesn't work correctly. We may as well just lie
# and say that we're a working one by default.
# We choose LG3D to maximize irony: it is a 3D non-reparenting WM written in
# java that happens to be on java's whitelist.
```

wmname = "LG3D"

CHAPTER

SIX

THE CONFIG FILE

Qtile is configured in Python. A script (~/.config/qtile/config.py by default) is evaluated, and a small set of configuration variables are pulled from its global namespace.

6.1 Configuration lookup order

Qtile looks in the following places for a configuration file, in order:

- The location specified by the -c argument.
- \$XDG_CONFIG_HOME/qtile/config.py, if it is set
- ~/.config/qtile/config.py
- first qtile/config.py found in \$XDG_CONFIG_DIRS (defaults to /etc/xdg)
- It reads the module libgtile.resources.default_config, included by default with every Qtile installation.

Qtile will try to create the configuration file as a copy of the default config, if it doesn't exist yet, this one will be placed inside of \$XDG_CONFIG_HOME/qtile/config.py (if set) or ~/.config/qtile/config.py.

6.2 Default Configuration

The *default configuration* is invoked when qtile cannot find a configuration file. In addition, if qtile is restarted or the config is reloaded, qtile will load the default configuration if the config file it finds has some kind of error in it. The documentation below describes the configuration lookup process, as well as what the key bindings are in the default config.

The default config is not intended to be suitable for all users; it's mostly just there so quile does /something/ when fired up, and so that it doesn't crash and cause you to lose all your work if you reload a bad config.

6.3 Configuration variables

A Qtile configuration consists of a file with a bunch of variables in it, which qtile imports and then runs as a Python file to derive its final configuration. The documentation below describes the most common configuration variables; more advanced configuration can be found in the qtile-examples repository, which includes a number of real-world configurations that demonstrate how you can tune Qtile to your liking. (Feel free to issue a pull request to add your own configuration to the mix!)

6.3.1 Lazy objects

Lazy objects are a way of executing any of the commands available in Qtile's commands API.

The name "lazy" refers to the fact that the commands are not executed at the time of the call. Instead, the lazy object creates a reference to the relevant command and this is only executed when the relevant event is triggered (e.g. on a keypress).

Typically, for config files, the commands are used to manipulate windows, layouts and groups as well application commands like exiting, restarting, reloading the config file etc.

Example

Note: As noted above, lazy calls do not call the relevant command but only create a reference to it. While this makes it ideal for binding commands to key presses and mouse_callbacks for widgets, it also means that lazy calls cannot be included in user-defined functions.

Lazy functions

This is overview of the commonly used functions for the key bindings. These functions can be called from commands on the REPLACE object or on another object in the command tree.

Some examples are given below. For a complete list of available commands, please refer to Commands API.

General functions

function	description	
lazy. spawn("application	Run the application	
<pre>lazy.spawncmd()</pre>	Open command prompt on the bar. See prompt widget.	
<pre>lazy. reload_config()</pre>	Reload the config.	
<pre>lazy.restart()</pre>	Restart Qtile. In X11, it won't close your windows.	
<pre>lazy.shutdown()</pre>	Close the whole Qtile	

Group functions

function	description	
<pre>lazy. next_layout()</pre>	Use next layout on the actual group	
<pre>lazy. prev_layout()</pre>	Use previous layout on the actual group	
<pre>lazy.screen. next_group()</pre>	Move to the group on the right	
<pre>lazy.screen. prev_group()</pre>	Move to the group on the left	
<pre>lazy.screen. toggle_group()</pre>	Move to the last visited group	
<pre>lazy.group. next_window()</pre>	Switch window focus to next window in group	
<pre>lazy.group. prev_window()</pre>	Switch window focus to previous window in group	
<pre>lazy. group["group_name toscreen()</pre>	Move to the group called group_name. Takes an optional toggle parameter (defaults to False). If this group is already on the screen, it does nothing by default; to toggle with the last used group instead, use toggle=True.	
<pre>lazy.layout. increase_ratio()</pre>	Increase the space for master window at the expense of slave windows	
<pre>lazy.layout. decrease_ratio()</pre>	Decrease the space for master window in the advantage of slave windows	

Window functions

function	description	
lazy.window. kill()	Close the focused window	
<pre>lazy.layout. next()</pre>	Switch window focus to other pane(s) of stack	
<pre>lazy.window. togroup("group_na</pre>	Move focused window to the group called group_name	
<pre>lazy.window. toggle_floating()</pre>	Put the focused window to/from floating mode	
lazy.window. toggle_fullscreen	Put the focused window to/from fullscreen mode	
<pre>lazy.window. move_up()</pre>	Move the window above the next window in the stack.	
<pre>lazy.window. move_down()</pre>	Move the window below the previous window in the stack.	
<pre>lazy.window. move_to_top()</pre>	Move the window above all other windows with similar priority (i.e. a "normal" window will not be moved above a kept_above window).	
<pre>lazy.window. move_to_bottom()</pre>	Move the window below all other windows with similar priority (i.e. a "normal" window will not be moved below a kept_below window).	
<pre>lazy.window. keep_above()</pre>	Keep window above other windows.	
<pre>lazy.window. keep_below()</pre>	Keep window below other windows.	
<pre>lazy.window. bring_to_front()</pre>	Bring window above all other windows. Ignores kept_above priority.	

Screen functions

function	description
<pre>lazy.screen. set_wallpaper(pat mode=None)</pre>	Set the wallpaper to the specificied image. Possible modes: None no resizing, 'fill' centre and resize to fill screen, 'stretch' stretch to fill screen.

ScratchPad DropDown functions

function	description
<pre>lazy. group["group_name dropdown_toggle("</pre>	Toggles the visibility of the specified DropDown window. On first use, the configured process is spawned.
<pre>lazy. group["group_name hide_all()</pre>	Hides all DropDown windows.
<pre>lazy. group["group_name dropdown_reconfig</pre>	Update the configuration of the named DropDown.
**configuration)	

User-defined functions

function	description
<pre>lazy. function(func, *args, **kwargs)</pre>	Calls func(qtile, *args, **kwargs). NB. the qtile object is automatically passed as the first argument.

Examples

lazy.function can also be used as a decorator for functions.

Additionally, you can pass arguments to user-defined function in one of two ways:

1) In-line definition

Arguments can be added to the lazy.function call.

```
from libqtile.config import Key
from libqtile.lazy import lazy

(continues on next page)
```

2) Decorator

Arguments can also be passed to the decorated function.

6.3.2 Groups

A group is a container for a bunch of windows, analogous to workspaces in other window managers. Each client window managed by the window manager belongs to exactly one group. The groups config file variable should be initialized to a list of Group objects.

Group objects provide several options for group configuration. Groups can be configured to show and hide themselves when they're not empty, spawn applications for them when they start, automatically acquire certain groups, and various other options.

Example

```
from libqtile.config import Group, Match

groups = [
    Group("a"),
    Group("b"),
    Group("c", matches=[Match(wm_class="Firefox")]),
]
```

```
# allow mod3+1 through mod3+0 to bind to groups; if you bind your groups
# by hand in your config, you don't need to do this.
from libqtile.dgroups import simple_key_binder

dgroups_key_binder = simple_key_binder("mod3")
```

Reference

Group

```
class libqtile.config.Group(name: str, matches: list[Match] \mid None = None, exclusive: bool = False, spawn: str \mid list[str] \mid None = None, layout: str \mid None = None, layout: list[Layout] \mid None = None, persist: bool = True, layout_opts: dict[str, Any] \mid None = None, persist: lool = True, position: lool = True, position: lool = True, position: position:
```

Represents a "dynamic" group

These groups can spawn apps, only allow certain Matched windows to be on them, hide when they're not in use, etc. Groups are identified by their name.

Parameters

name:

The name of this group.

matches:

List of Match objects whose matched windows will be assigned to this group.

exclusive:

When other apps are started in this group, should we allow them here or not?

spawn:

This will be executed (via qtile.spawn()) when the group is created. You can pass either a program name or a list of programs to exec().

layout:

The name of default layout for this group (e.g. "max"). This is the name specified for a particular layout in config.py or if not defined it defaults in general to the class name in all lower case.

layouts

The group layouts list overriding global layouts. Use this to define a separate list of layouts for this particular group.

persist:

Should this group stay alive when it has no member windows?

init:

Should this group be alive when Qtile starts?

layout_opts:

Options to pass to a layout.

screen_affinity:

Make a dynamic group prefer to start on a specific screen.

position:

The position of this group.

label:

The display name of the group. Use this to define a display name other than name of the group. If set to None, the display name is set to the name.

libqtile.dgroups.simple_key_binder(mod, keynames=None)

Bind keys to mod+group position or to the keys specified as second argument

Group Matching

Match

Window properties to compare (match) with a window.

The properties will be compared to a Window to determine if its properties *match*. It can match by title, wm_class, role, wm_type, wm_instance_class, net_wm_pid, or wid. Additionally, a function may be passed, which takes in the Window to be compared against and returns a boolean.

For some properties, Match supports both regular expression objects (i.e. the result of re.compile()) or strings (match as an exact string). If a window matches all specified values, it is considered a match.

Parameters

title:

Match against the WM NAME atom (X11) or title (Wayland).

wm_class:

Match against any value in the whole WM_CLASS atom (X11) or app ID (Wayland).

role:

Match against the WM ROLE atom (X11 only).

wm_type:

Match against the WM_TYPE atom (X11 only).

wm_instance_class:

Match against the first string in WM_CLASS atom (X11) or app ID (Wayland).

net_wm_pid:

Match against the _NET_WM_PID atom (X11) or PID (Wayland).

func:

Delegate the match to the given function, which receives the tested client as an argument and must return True if it matches, False otherwise.

wid:

Match against the window ID. This is a unique ID given to each window.

Rule

```
 \textbf{class libqtile.config.Rule}(\textit{match: \_Match} \mid \textit{list}[\_\textit{Match}], \textit{group: \_Group} \mid \textit{None} = \textit{None}, \textit{float: bool} = \textit{False}, \\ \textit{intrusive: bool} = \textit{False}, \textit{break\_on\_match: bool} = \textit{True}, \textit{one\_time: bool} = \textit{False})
```

How to act on a match.

A Rule contains a list of Match objects, and a specification about what to do when any of them is matched.

Parameters

match:

Match object or a list of such associated with this rule.

float:

Should we auto float this window?

intrusive:

Should we override the group's exclusive setting?

break_on_match:

Should we stop applying rules if this rule is matched?

one time:

Should we delete rule once if it has been matched?

ScratchPad and DropDown

ScratchPad is a special - by default invisible - group which acts as a container for DropDown configurations. A DropDown can be configured to spawn a defined process and bind thats process' window to it. The associated window can then be shown and hidden by the lazy command dropdown_toggle() (see *Lazy objects*) from the ScratchPad group. Thus - for example - your favorite terminal emulator turns into a quake-like terminal by the control of Qtile.

If the DropDown window turns visible it is placed as a floating window on top of the current group. If the DropDown is hidden, it is simply switched back to the ScratchPad group.

Example

```
Key([], 'F11', lazy.group['scratchpad'].dropdown_toggle('term')),
Key([], 'F12', lazy.group['scratchpad'].dropdown_toggle('qtile shell')),
]
```

Note that if the window is set to not floating, it is detached from DropDown and ScratchPad, and a new process is spawned next time the DropDown is set visible.

Some programs run in a server-like mode where the spawned process does not directly own the window that is created, which is instead created by a background process. In this case, the window may not be correctly caught in the scratchpad group. To work around this, you can pass a Match object to the corresponding DropDown. See below.

Reference

ScratchPad

Represents a "ScratchPad" group

ScratchPad adds a (by default) invisible group to Qtile. That group is used as a place for currently not visible windows spawned by a DropDown configuration.

Parameters

name:

The name of this group.

dropdowns:

DropDown s available on the scratchpad.

position:

The position of this group.

label:

The display name of the ScratchPad group. Defaults to the empty string such that the group is hidden in GroupBox widget.

single:

If True, only one of the dropdowns will be visible at a time.

DropDown

```
class libqtile.config.DropDown(name: str, cmd: str, **config: Any)
```

Configure a specified command and its associated window for the ScratchPad. That window can be shown and hidden using a configurable keystroke or any other scripted trigger.

Configuration options

key	default	description
height	0.35	Height of window as fraction of current screen.
match	None	Use a Match to identify the spawned window and move it to the scratchpad, instead of relying on the window's PID. This works around some programs that may not be caught by the window's PID if it does not match the PID of the spawned process.
on_focus_lost_hi	True	Shall the window be hidden if focus is lost? If so, the DropDown is hidden if window focus or the group is changed.
opacity	0.9	Opacity of window as fraction. One is opaque.
warp_pointer	True	Shall pointer warp to center of window on activation? This only has effect if any of the on_focus_lost_xxx options are True
width	0.8	Width of window as fraction of current screen width
X	0.1	X position of window as fraction of current screen width. 0 is the left most position.
у	0.0	Y position of window as fraction of current screen height. 0 is the top most position. To show the window at bottom, you have to configure a value < 1 and an appropriate height.

6.3.3 Keys

The keys variable defines Qtile's key bindings.

Default Key Bindings

The mod key for the default config is mod4, which is typically bound to the "Super" keys, which are things like the windows key and the mac command key. The basic operation is:

- mod + k or mod + j: switch windows on the current stack
- mod + <space>: put focus on the other pane of the stack (when in stack layout)
- mod + <tab>: switch layouts
- mod + w: close window
- mod + <ctrl> + r: reload the config
- mod + <group name>: switch to that group
- mod + <shift> + <group name>: send a window to that group
- mod + <enter>: start terminal guessed by libqtile.utils.guess_terminal
- mod + r: start a little prompt in the bar so users can run arbitrary commands

The default config defines one screen and 8 groups, one for each letter in asdfuiop. It has a basic bottom bar that includes a group box, the current window name, a little text reminder that you're using the default config, a system tray, and a clock.

The default configuration has several more advanced key combinations, but the above should be enough for basic usage of qtile.

See Keybindings in images for visual keybindings in keyboard layout.

Defining key bindings

Individual key bindings are defined with Key as demonstrated in the following example. Note that you may specify more than one callback functions.

```
from libqtile.config import Key

keys = [
    # Pressing "Meta + Shift + a".
    Key(["mod4", "shift"], "a", callback, ...),

# Pressing "Control + p".
    Key(["control"], "p", callback, ...),

# Pressing "Meta + Tab".
    Key(["mod4", "mod1"], "Tab", callback, ...),
]
```

The above may also be written more concisely with the help of the EzKey helper class. The following example is functionally equivalent to the above:

```
from libqtile.config import EzKey as Key

keys = [
   Key("M-S-a", callback, ...),
   Key("C-p", callback, ...),
   Key("M-A-<Tab>", callback, ...),
]
```

The EzKey modifier keys (i.e. MASC) can be overwritten through the EzKey.modifier_keys dictionary. The defaults are:

```
modifier_keys = {
    'M': 'mod4',
    'A': 'mod1',
    'S': 'shift',
    'C': 'control',
}
```

Callbacks can also be configured to work only under certain conditions by using the when() method. Currently, the following conditions are supported:

```
from libqtile.config import Key

keys = [
    # Only trigger callback for a specific layout
    Key(
        [mod, 'shift'],
        "j",
        lazy.layout.grow().when(layout='verticaltile'),
        lazy.layout.grow_down().when(layout='columns')
    ),

# Limit action to when the current window is not floating
```

KeyChords

Qtile also allows sequences of keys to trigger callbacks. These sequences are known as chords and are defined with KeyChord. Chords are added to the keys section of the config file.

```
from libqtile.config import Key, KeyChord

keys = [
    KeyChord([mod], "z", [
         Key([], "x", lazy.spawn("xterm"))
    ])
]
```

The above code will launch xterm when the user presses Mod + z, followed by x.

Warning: Users should note that key chords are aborted by pressing $\langle escape \rangle$. In the above example, if the user presses Mod + z, any following key presses will still be sent to the currently focussed window. If $\langle escape \rangle$ has not been pressed, the next press of x will launch xterm.

Modes

Chords can optionally persist until a user presses <escape>. This can be done by setting mode=True. This can be useful for configuring a subset of commands for a particular situations (i.e. similar to vim modes).

```
from libqtile.config import Key, KeyChord

keys = [
    KeyChord([mod], "z", [
        Key([], "g", lazy.layout.grow()),
        Key([], "s", lazy.layout.shrink()),
        Key([], "n", lazy.layout.normalize()),
        Key([], "m", lazy.layout.maximize())],
        mode=True,
        name="Windows"
    )
]
```

In the above example, pressing Mod + z triggers the "Windows" mode. Users can then resize windows by just pressing g (to grow the window), s to shrink it etc. as many times as needed. To exit the mode, press <escape>.

Note: The Chord widget (Chord) will display the name of the active chord (as set by the name parameter). This is particularly useful where the chord is a persistent mode as this will indicate when the chord's mode is still active.

Chains

Chords can also be chained to make even longer sequences.

Modes can also be added to chains if required. The following example demonstrates the behaviour when using the mode argument in chains:

After pressing Mod+z y x c, the "inner" mode will remain active. When pressing <escape>, the "inner" mode is exited. Since the mode in between does not have mode set, it is also left. Arriving at the "outer" mode (which has this argument set) stops the "leave" action and "outer" now becomes the active mode.

Note: If you want to bind a custom key to leave the current mode (e.g. Control + G in addition to <escape>), you can specify lazy.ungrab_chord() as the key action. To leave all modes and return to the root bindings, use lazy.ungrab_all_chords().

Modifiers

On most systems mod1 is the Alt key - you can see which modifiers, which are enclosed in a list, map to which keys on your system by running the xmodmap command. This example binds Alt-k to the "down" command on the current layout. This command is standard on all the included layouts, and switches to the next window (where "next" is defined differently in different layouts). The matching "up" command switches to the previous window.

Modifiers include: "shift", "lock", "control", "mod1", "mod2", "mod3", "mod4", and "mod5". They can be used in combination by appending more than one modifier to the list:

```
Key(
    ["mod1", "control"], "k",
    lazy.layout.shuffle_down()
)
```

Special keys

These are most commonly used special keys. For complete list please see the code. You can create bindings on them just like for the regular keys. For example Key(["mod1"], "F4", lazy.window.kill()).

Return
BackSpace
Tab
space
Home, End
Left, Up, Right, Down
F1, F2, F3,
XF86AudioRaiseVolume
XF86AudioLowerVolume
XF86AudioMute
XF86AudioNext
XF86AudioPrev
XF86MonBrightnessUp
XF86MonBrightnessDown

Reference

Key

```
class libqtile.config.Key(modifiers: list[str], key: str \mid int, *commands: LazyCall, desc: str = ", swallow: bool = <math>True)
```

Defines a keybinding.

Parameters

modifiers:

```
A list of modifier specifications. Modifier specifications are one of: "shift", "lock", "control", "mod1", "mod2", "mod3", "mod4", "mod5".
```

key:

A key specification, e.g. "a", "Tab", "Return", "space". Also accepts an integer value representing a keycode.

commands:

One or more LazyCall objects to evaluate in sequence upon keypress. Multiple commands should be separated by commas.

desc:

Description to be added to the key binding. (Optional)

swallow:

Configures when we swallow the key binding. (Optional) Setting it to False will forward the key binding to the focused window after the commands have been executed.

KeyChord

```
class libqtile.config.KeyChord(modifiers: list[str], key: str | int, submappings: list[libqtile.config.Key | libqtile.config.KeyChord], mode: bool | str = False, name: str = ", desc: str = ", swallow: bool = True)
```

Define a key chord aka Vim-like mode.

Parameters

modifiers:

A list of modifier specifications. Modifier specifications are one of: "shift", "lock", "control", "mod1", "mod2", "mod3", "mod4", "mod5".

key:

A key specification, e.g. "a", "Tab", "Return", "space". Also accepts an integer value representing a keycode.

submappings:

A list of Key or KeyChord declarations to bind in this chord.

mode:

Boolean. Setting to True will result in the chord persisting until Escape is pressed. Setting to False (default) will exit the chord once the sequence has ended.

name:

A string to name the chord. The name will be displayed in the Chord widget.

desc:

A string to describe the chord. This attribute is not directly used by Qtile but users may want to access this when creating scripts to show configured keybindings.

swallow:

Configures when we swallow the key binding of the chord. (Optional) Setting it to False will forward the key binding to the focused window after the commands have been executed.

EzKey

```
class libqtile.config.EzKey(keydef: str, *commands: LazyCall, desc: str = ")
    Defines a keybinding using the Emacs-like format.

Parameters
    keydef:
        The Emacs-like key specification, e.g. "M-S-a".
    commands:
        A list LazyCall objects to evaluate in sequence upon keypress.
    desc:
        Description to be added to the key binding. (Optional)
```

6.3.4 Layouts

A layout is an algorithm for laying out windows in a group on your screen. Since Qtile is a tiling window manager, this usually means that we try to use space as efficiently as possible, and give the user ample commands that can be bound to keys to interact with layouts.

The layouts variable defines the list of layouts you will use with Qtile. The first layout in the list is the default. If you define more than one layout, you will probably also want to define key bindings to let you switch to the next and previous layouts.

See Built-in Layouts for a listing of available layouts.

Example

```
from libqtile import layout

layouts = [
    layout.Max(),
    layout.Stack(stacks=2)
]
```

6.3.5 Mouse

The mouse config file variable defines a set of global mouse actions, and is a list of Click and Drag objects, which define what to do when a window is clicked or dragged.

Default Mouse Bindings

By default, holding your mod key and left-clicking (and holding) a window will allow you to drag it around as a floating window. Holding your mod key and right-clicking (and holding) a window will resize the window (and also make it float if it is not already floating).

Example

```
from libqtile.config import Click, Drag
mouse = [
    Drag([mod], "Button1", lazy.window.set_position_floating(),
        start=lazy.window.get_position()),
    Drag([mod], "Button3", lazy.window.set_size_floating(),
        start=lazy.window.get_size()),
    Click([mod], "Button2", lazy.window.bring_to_front())
]
```

The above example can also be written more concisely with the help of the EzClick and EzDrag helpers:

```
from libqtile.config import EzClick as Click, EzDrag as Drag

mouse = [
    Drag("M-1", lazy.window.set_position_floating(),
        start=lazy.window.get_position()),
    Drag("M-3", lazy.window.set_size_floating(),
        start=lazy.window.get_size()),
    Click("M-2", lazy.window.bring_to_front())
]
```

Reference

Click

class libqtile.config.**Click**(*modifiers: list[str]*, *button: str*, **commands: LazyCall*) Bind commands to a clicking action.

Parameters

modifiers:

```
A list of modifier specifications. Modifier specifications are one of: "shift", "lock", "control", "mod1", "mod2", "mod3", "mod4", "mod5".
```

button:

The button used to click e.g. "Button1".

commands:

A list LazyCall objects to evaluate in sequence upon click.

Drag

Bind commands to a dragging action.

On each motion event the bound commands are executed with two additional parameters specifying the x and y offset from the previous position.

Parameters

modifiers:

```
A list of modifier specifications. Modifier specifications are one of: "shift", "lock", "control", "mod1", "mod2", "mod3", "mod4", "mod5".
```

button:

The button used to start dragging e.g. "Button1".

commands:

A list LazyCall objects to evaluate in sequence upon drag.

start:

A LazyCall object to be evaluated when dragging begins. (Optional)

warp_pointer:

A bool indicating if the pointer should be warped to the bottom right of the window at the start of dragging. (Default: *False*)

EzClick

```
class libqtile.config.EzClick(btndef: str, *commands: LazyCall)
```

Bind commands to a clicking action using the Emacs-like format.

Parameters

btndef:

The Emacs-like button specification, e.g. "M-1".

commands:

A list LazyCall objects to evaluate in sequence upon drag.

6.3.6 Screens

The screens configuration variable is where the physical screens, their associated bars, and the widgets contained within the bars are defined (see *Built-in Widgets* for a listing of available widgets).

Example

Tying together screens, bars and widgets, we get something like this:

```
from libqtile.config import Screen
from libqtile import bar, widget

window_name = widget.WindowName()

screens = [
    Screen(
        bottom=bar.Bar([
            widget.GroupBox(),
            window_name,
            ], 30),
    ),
    Screen(
        bottom=bar.Bar([
            widget.GroupBox(),
```

Note that a widget can be passed to multiple bars (and likewise multiple times to the same bar). Its contents is mirrored across all copies so this is useful where you want identical content (e.g. the name of the focussed window, like in this example).

Bars support both solid background colors and gradients by supplying a list of colors that make up a linear gradient. For example, bar.Bar(..., background="#000000") will give you a black back ground (the default), while bar.Bar(..., background=["#000000", "#FFFFFF"]) will give you a background that fades from black to white.

Bars (and widgets) also support transparency by adding an alpha value to the desired color. For example, bar.Bar(..., background="#00000000") will result in a fully transparent bar. Widget contents will not be impacted i.e. this is different to the opacity parameter which sets the transparency of the entire window.

Note: In X11 backends, transparency will be disabled in a bar if the background color is fully opaque.

Users can add borders to the bar by using the border_width and border_color parameters. Providing a single value sets the value for all four sides while sides can be customised individually by setting four values in a list (top, right, bottom, left) e.g. border_width=[2, 0, 2, 0] would draw a border 2 pixels thick on the top and bottom of the bar.

Multiple Screens

You will see from the example above that screens is a list of individual Screen objects. The order of the screens in this list should match the order of screens as seen by your display server.

X11

You can view the current order of your screens by running xrandr --listmonitors.

Examples of how to set the order of your screens can be found on the Arch wiki.

Wayland

The Wayland backend supports the wlr-output-management protocol for configuration of outputs by tools such as Kanshi

Fake Screens

instead of using the variable *screens* the variable *fake_screens* can be used to set split a physical monitor into multiple screens. They can be used like this:

```
from libqtile.config import Screen
from libqtile import bar, widget

# screens look like this
# 600 300
```

```
| 480| |580
| A | B |
 |----|
 400/--/---/
  1 C
          | |400
  |----| D
#
  500 |----|
#
                400
# Notice there is a hole in the middle
# also D goes down below the others
fake_screens = [
 Screen(
     bottom=bar.Bar(
             widget.Prompt(),
             widget.Sep(),
             widget.WindowName(),
             widget.Sep(),
             widget.Systray(),
             widget.Sep(),
             widget.Clock(format='%H:%M:%S %d.%m.%Y')
         ],
         24,
         background="#555555"
     ),
     x=0,
     y=0,
     width=600,
     height=480
 ),
 Screen(
     top=bar.Bar(
         Γ
             widget.GroupBox(),
             widget.WindowName(),
             widget.Clock()
         ],
         30,
     ),
     x=600,
     y=0,
     width=300.
     height=580
 ),
 Screen(
     top=bar.Bar(
         Ε
             widget.GroupBox(),
             widget.WindowName(),
```

```
widget.Clock()
          ],
           30,
      ),
      x=0,
      y = 480,
      width=500,
      height=400
  ),
  Screen(
      top=bar.Bar(
           Ε
               widget.GroupBox(),
               widget.WindowName(),
               widget.Clock()
          ],
           30.
      ),
      x=500,
      y=580,
      width=400,
      height=400
  ),
]
```

Third-party bars

There might be some reasons to use third-party bars. For instance you can come from another window manager and you have already configured dzen2, xmobar, or something else. They definitely can be used with Qtile too. In fact, any additional configurations aren't needed. Just run the bar and qtile will adapt.

Reference

Screen

```
class libqtile.config.Screen(*args, **kwargs)
```

A physical screen, and its associated paraphernalia.

Define a screen with a given set of Bars of a specific geometry. Also, x, y, width, and height aren't specified usually unless you are using 'fake screens'.

The background parameter, if given, should be a valid single colour. This will paint a solid background colour to the screen. Note, the setting is ignored if wallpaper is also set (see below).

The wallpaper parameter, if given, should be a path to an image file. How this image is painted to the screen is specified by the wallpaper_mode parameter. By default, the image will be placed at the screens origin and retain its own dimensions. If the mode is "fill", the image will be centred on the screen and resized to fill it. If the mode is "stretch", the image is stretched to fit all of it into the screen. If the mode is "center", the image is centered on the screen. The "background" painting is done before the image is drawn, so you can set the background color for an image by setting background here.

The x11_drag_polling_rate parameter specifies the rate for drag events in the X11 backend. By default this is set to None, indicating no limit. Because in the X11 backend we already handle motion notify events later, the performance should already be okay. However, to limit these events further you can use this variable and e.g. set it to your monitor refresh rate. 60 would mean that we handle a drag event 60 times per second.

Available commands

Click to view the available commands for *Screen*

Bar

class libqtile.bar.Bar(*args, **kwargs)

A bar, which can contain widgets

Parameters

widgets

A list of widget objects.

size

The "thickness" of the bar, i.e. the height of a horizontal bar, or the width of a vertical bar.

Configuration options

key	default	description
background	'#000000'	Background colour.
border_color	'#000000'	Border colour as str or list of str [N E S W]
border_width	0	Width of border as int of list of ints [N E S W]
margin	0	Space around bar as int or list of ints [N E S W].
opacity	1	Bar window opacity.
reserve	True	Reserve screen space (when set to 'False', bar will be drawn above windows).

Available commands

Click to view the available commands for Bar

Gap

class libqtile.bar.Gap(size: int)

A gap placed along one of the edges of the screen

Qtile will avoid covering gaps with windows.

Parameters

size

The "thickness" of the gap, i.e. the height of a horizontal gap, or the width of a vertical gap.

6.3.7 Hooks

Qtile provides a mechanism for subscribing to certain events in libqtile.hook. To subscribe to a hook in your configuration, simply decorate a function with the hook you wish to subscribe to.

See Built-in Hooks for a listing of available hooks.

Examples

Automatic floating dialogs

Let's say we wanted to automatically float all dialog windows (this code is not actually necessary; Qtile floats all dialogs by default). We would subscribe to the client_new hook to tell us when a new window has opened and, if the type is "dialog", as can set the window to float. In our configuration file it would look something like this:

```
from libqtile import hook

@hook.subscribe.client_new
def floating_dialogs(window):
    dialog = window.window.get_wm_type() == 'dialog'
    transient = window.window.get_wm_transient_for()
    if dialog or transient:
        window.floating = True
```

A list of available hooks can be found in the *Built-in Hooks* reference.

Autostart

If you want to run commands or spawn some applications when Qtile starts, you'll want to look at the startup and startup_once hooks. startup is emitted every time Qtile starts (including restarts), whereas startup_once is only emitted on the very first startup.

Let's create an executable file \sim /.config/qtile/autostart.sh that will start a few programs when Qtile first runs. Remember to *chmod* +*x* \sim /.config/qtile/autostart.sh so that it can be executed.

```
#!/bin/sh
pidgin &
dropbox start &
```

We can then subscribe to startup_once to run this script:

```
import os
import subprocess

from libqtile import hook

@hook.subscribe.startup_once
def autostart():
   home = os.path.expanduser('~/.config/qtile/autostart.sh')
   subprocess.call(home)
```

Accessing the qtile object

If you want to do something with the Qtile manager instance inside a hook, it can be imported into your config:

```
from libqtile import qtile
```

Async hooks

Hooks can also be defined as coroutine functions using async def, which will run them asynchronously in the event loop:

```
@hook.subscribe.focus_change
async def _():
    ...
```

6.3.8 Matching windows

Qtile's config provides a number of situations where the behaviour depends on whether the relevant window matches some specified criteria.

These situations include:

- Defining which windows should be floated by default
- Assigning windows to specific groups
- · Assigning window to a master section of a layout

In each instance, the criteria are defined via a Match object. The properties of the object will be compared to a Window to determine if its properties *match*. It can match by title, wm_class, role, wm_type, wm_instance_class, net_wm_pid, or wid. Additionally, a function may be passed, which takes in the Window to be compared against and returns a boolean.

A basic rule would therefore look something like:

```
Match(wm_class="mpv")
```

This would match against any window whose class was mpv.

Where a string is provided as an argument then the value must match exactly. More flexibility can be achieved by using regular expressions. For example:

```
import re

Match(wm_class=re.compile(r"mpv"))
```

This would still match a window whose class was mpv but it would also match any class starting with mpv e.g. mpvideo.

Note: When providing a regular expression, qtile applies the .match method. This matches from the start of the string so, if you want to match any substring, you will need to adapt the regular expression accordingly e.g.

```
import re

Match(wm_class=re.compile(r".*mpv"))
```

This would match any string containing mpv

Creating advanced rules

While the func parameter allows users to create more complex matches, this requires a knowledge of qtile's internal objects. An alternative is to combine Match objects using logical operators & (and), $| (or), \sim (not)$ and $^{\wedge}(xor)$.

For example, to create rule that matches all windows with a fixed aspect ratio except for mpv windows, you would provide the following:

```
Match(func=lambda c: c.has_fixed_ratio()) & ~Match(wm_class="mpv")
```

It is also possible to use wrappers for Match objects if you do not want to use the operators. The following wrappers are available:

- MatchAll(Match(...), ...) equivalent to "and" test. All matches must match.
- MatchAny(Match(...), ...) equivalent to "or" test. At least one match must match.
- MatchOnlyOne(Match(...), Match(...)) equivalent to "xor". Only one match must match.
- InvertMatch(Match(...)) equivalent to "not". Inverts the result of the match.

So, to recreate the above rule using the wrappers, you would write the following:

```
from libqtile.config import InvertMatch, Match, MatchAll
MatchAll(Match(func=lambda c: c.has_fixed_ratio()), InvertMatch(Match(wm_class="mpv")))
```

In addition to the above variables, there are several other boolean configuration variables that control specific aspects of Qtile's behavior:

variable	default	description
auto_ful	True	If a window requests to be fullscreen, it is automatically fullscreened. Set this to false if you only want windows to be fullscreen if you ask them to be.
bring_fr	False	When clicked, should the window be brought to the front or not. If this is set to "floating_only", only floating windows will get affected (This sets the X Stack Mode to Above.). This will ignore the layering rules and will therefore bring windows above other windows, even if they have been set as "kept_above". This may cause issues with docks and other similar apps as these may end up hidden behind other windows. Setting this to False or "floating_only" may therefore be required when using these apps.
cursor_w	False	If true, the cursor follows the focus as directed by the keyboard, warping to the center of the focused window. When switching focus between screens, If there are no windows in the screen, the cursor will warp to the center of the screen.
dgroups_	None	A function which generates group binding hotkeys. It takes a single argument, the DGroups object, and can use that to set up dynamic key bindings. A sample implementation is available in libqtile/dgroups.py called simple_key_binder(), which will bind groups to mod+shift+0-10 by default.
dgroups_	[]	A list of Rule objects which can send windows to various groups based on matching criteria.
extensio	<pre>same as widget_d</pre>	Default settings for extensions.
floating		The default floating layout to use. This allows you to set custom floating rules among other things if you wish. See the configuration file for the default <i>float_rules</i> .
floats_k		Floating windows are kept above tiled windows (Currently x11 only. Wayland support coming soon.)
focus_on	'smart'	Behavior of the _NET_ACTIVE_WINDOW message sent by applications • urgent: urgent flag is set for the window • focus: automatically focus the window • smart: automatically focus if the window is in the current group • never: never automatically focus any window that requests it • can also be a function which takes the window as an argument: — returns True: focus window — returns False: doesn't do anything
focus_pr	False	If a window is closed, the next focused window is not always the previous window, depending on current window state. Set this to true if you want to focus previous window in all circumstances.
follow_n	True	Controls whether or not focus follows the mouse around as it moves across windows in a layout. Otherwise set this to "click_or_drag_only" to change focus only when doing a Click or Drag action.
widget_d		Default settings for bar widgets.
	fontsize	
6.	padding=	
reconfig		Controls whether or not to automatically reconfigure screens when there are changes in randr output configuration.
wmname	'LG3D'	Gasp! We're lying here. In fact, nobody really uses or cares about this string besides java UI toolkits; you can see several discussions on the mailing lists, GitHub issues, and other WM documentation that suggest setting this string if your java app doesn't work correctly. We may as well just lie and say that we're a working one by default. We choose LG3D to maximize irony: it is a 3D non-reparenting WM written in java that happens to be on java's whitelist.
auto_min	True	If things like steam games want to auto-minimize themselves when losing focus, should we respect this or not?

6.4 Testing your configuration

The best way to test changes to your configuration is with the provided scripts at ./scripts/xephyr (X11) or ./scripts/wephyr (Wayland). This will run Qtile with your config.py inside a nested window and prevent your running instance of Qtile from crashing if something goes wrong.

See *Hacking Qtile* for more information on using Xephyr.

CHAPTER

SEVEN

BUILT-IN LAYOUTS

7.1 Bsp

```
class libqtile.layout.Bsp(*args, **kwargs)
```

This layout is inspired by bspwm, but it does not try to copy its features.

The first client occupies the entire screen space. When a new client is created, the selected space is partitioned in 2 and the new client occupies one of those subspaces, leaving the old client with the other.

The partition can be either horizontal or vertical according to the dimensions of the current space: if its width/height ratio is above a pre-configured value, the subspaces are created side-by-side, otherwise, they are created on top of each other. The partition direction can be freely toggled. All subspaces can be resized and clients can be shuffled around.

All clients are organized at the leaves of a full binary tree.

An example key configuration is:

```
Key([mod], "j", lazy.layout.down()),
Key([mod], "k", lazy.layout.up()),
Key([mod], "h", lazy.layout.left()),
Key([mod], "1", lazy.layout.right()),
Key([mod, "shift"], "j", lazy.layout.shuffle_down()),
Key([mod, "shift"], "k", lazy.layout.shuffle_up()),
Key([mod, "shift"], "h", lazy.layout.shuffle_left()),
Key([mod, "shift"], "l", lazy.layout.shuffle_right()),
Key([mod, "mod1"], "j", lazy.layout.flip_down()),
Key([mod, "mod1"], "k", lazy.layout.flip_up()),
Key([mod, "mod1"], "h", lazy.layout.flip_left()),
Key([mod, "mod1"], "1", lazy.layout.flip_right()),
Key([mod, "control"], "j", lazy.layout.grow_down()),
Key([mod, "control"], "k", lazy.layout.grow_up()),
Key([mod, "control"], "h", lazy.layout.grow_left()),
Key([mod, "control"], "l", lazy.layout.grow_right()),
Key([mod, "shift"], "n", lazy.layout.normalize()),
Key([mod], "Return", lazy.layout.toggle_split()),
```

key	default	description
border_focus	'#881111'	Border colour(s) for the focused window.
border_normal	'#220000'	Border colour(s) for un-focused windows.
border_on_single	False	Draw border when there is only one window.
border_width	2	Border width.
fair	True	New clients are inserted in the shortest branch.
grow_amount	10	Amount by which to grow a window/column.
lower_right	True	New client occupies lower or right subspace.
margin	0	Margin of the layout (int or list of ints [N E S W]).
margin_on_single	None	Margin when there is only one window (int or list of ints [N E S
		W], 'None' to use 'margin' value).
ratio	1.6	Width/height ratio that defines the partition direction.
wrap_clients	False	Whether client list should be wrapped when using next and previous commands.

Click to view the available commands for Bsp

7.2 Columns

```
class libqtile.layout.Columns(*args, **kwargs)
```

Extension of the Stack layout.

The screen is split into columns, which can be dynamically added or removed. Each column can present its windows in 2 modes: split or stacked. In split mode, all windows are presented simultaneously, spliting the column space. In stacked mode, only a single window is presented from the stack of windows. Columns and windows can be resized and windows can be shuffled around.

This layout can also emulate wmii's default layout via:

```
layout.Columns(num_columns=1, insert_position=1)
```

Or the "Vertical", and "Max", depending on the default parameters.

An example key configuration is:

```
Key([mod], "j", lazy.layout.down()),
Key([mod], "k", lazy.layout.left()),
Key([mod], "h", lazy.layout.right()),
Key([mod], "l", lazy.layout.right()),
Key([mod, "shift"], "j", lazy.layout.shuffle_down()),
Key([mod, "shift"], "k", lazy.layout.shuffle_left()),
Key([mod, "shift"], "h", lazy.layout.shuffle_left()),
Key([mod, "shift"], "l", lazy.layout.shuffle_right()),
Key([mod, "control"], "j", lazy.layout.grow_down()),
Key([mod, "control"], "k", lazy.layout.grow_up()),
Key([mod, "control"], "h", lazy.layout.grow_right()),
Key([mod, "shift", "control"], "h", lazy.layout.swap_column_left()),
Key([mod, "shift", "control"], "l", lazy.layout.swap_column_right()),
Key([mod], "Return", lazy.layout.toggle_split()),
Key([mod], "n", lazy.layout.normalize()),
```

Configuration options

key	default	description
align	1	Which side of screen new windows will be added to (one of
		Columnsleft or Columnsright). Ignored if 'fair=True'.
border_focus	'#881111'	Border colour(s) for the focused window.
border_focus_sta	'#881111'	Border colour(s) for the focused window in stacked columns.
border_normal	' #220000'	Border colour(s) for un-focused windows.
border_normal_st	'#220000'	Border colour(s) for un-focused windows in stacked columns.
border_on_single	False	Draw a border when there is one only window.
border_width	2	Border width.
fair	False	Add new windows to the column with least windows.
grow_amount	10	Amount by which to grow a window/column.
initial_ratio	1	Ratio of first column to second column.
<pre>insert_position</pre>	0	Position relative to the current window where new ones are in-
		serted (0 means right above the current window, 1 means right after).
margin	0	Margin of the layout (int or list of ints [N E S W]).
margin_on_single	None	Margin when only one window. (int or list of ints [N E S W])
num_columns	2	Preferred number of columns.
single_border_wi	None	Border width for single window.
split	True	New columns presentation mode.
wrap_focus_colum	True	Wrap the screen when moving focus across columns.
wrap_focus_rows	True	Wrap the screen when moving focus across rows.
wrap_focus_stack	True	Wrap the screen when moving focus across stacked.

Available commands

Click to view the available commands for Columns

7.3 Floating

class libqtile.layout.Floating(*args, **kwargs)

Floating layout, which does nothing with windows but handles focus order

Configuration options

key	default	description
border_focus	'#0000ff'	Border colour(s) for the focused window.
border_normal	'#000000'	Border colour(s) for un-focused windows.
border_width	1	Border width.
fullscreen_borde	0	Border width for fullscreen.
max_border_width	0	Border width for maximize.

Available commands

Click to view the available commands for *Floating*

7.3. Floating 73

7.4 Matrix

class libqtile.layout.Matrix(*args, **kwargs)

This layout divides the screen into a matrix of equally sized cells and places one window in each cell. The number of columns is configurable and can also be changed interactively.

Configuration options

key	default	description
border_focus	'#0000ff'	Border colour(s) for the focused window.
border_normal	'#000000'	Border colour(s) for un-focused windows.
border_width	1	Border width.
columns	2	Number of columns
margin	0	Margin of the layout (int or list of ints [N E S W])

Available commands

Click to view the available commands for Matrix

7.5 Max

class libqtile.layout.Max(*args, **kwargs)

Maximized layout

A simple layout that only displays one window at a time, filling the screen_rect. This is suitable for use on laptops and other devices with small screens. Conceptually, the windows are managed as a stack, with commands to switch to next and previous windows in the stack.

Configuration options

key	default	description
border_focus	'#0000ff'	Border colour(s) for the window when focused
border_normal	'#000000'	Border colour(s) for the window when not focused
border_width	0	Border width.
margin	0	Margin of the layout (int or list of ints [N E S W])
only_focused	True	Only draw the focused window

Available commands

Click to view the available commands for Max

7.6 MonadTall

class libqtile.layout.MonadTall(*args, **kwargs)

Emulate the behavior of XMonad's default tiling scheme.

Main-Pane:

A main pane that contains a single window takes up a vertical portion of the screen_rect based on the ratio setting. This ratio can be adjusted with the grow_main and shrink_main or, while the main pane is in focus, grow and shrink. You may also set the ratio directly with set_ratio.



Using the flip method will switch which horizontal side the main pane will occupy. The main pane is considered the "top" of the stack.

,	,			
ſ				
ı				
ı				
ı	1 1	1		
ı				
ı				
1		1		
ı				
1		1		
1				
1	1	1		
П	1 1	1		
П				
1				
1		1		
1		ı		
1				
П				
1	1			
ı				
1				
ı				
٠,				

Secondary-panes:

Occupying the rest of the screen_rect are one or more secondary panes. The secondary panes will share the vertical space of the screen_rect however they can be resized at will with the grow and shrink methods. The other secondary panes will adjust their sizes to smoothly fill all of the space.

Panes can be moved with the shuffle_up and shuffle_down methods. As mentioned the main pane is considered the top of the stack; moving up is counter-clockwise and moving down is clockwise.

ĺ		 	
		Focus	
Ĺ			(aontinuos on navt naga)


(continues on next page)

7.6. MonadTall

(continued from previous page)

Setting auto_maximize will cause the focused secondary pane to be automatically maximized on focus. The non-maximized panes will shrink to the height specified by min_secondary_size.

The opposite is true if the layout is "flipped".



Normalizing/Resetting:

To restore all secondary client windows to their default size ratios use the normalize method.

To reset all client windows to their default sizes, including the primary window, use the reset method.

Maximizing:

To toggle a client window between its minimum and maximum sizes simply use the maximize on a focused client.

Suggested Bindings:

```
Key([modkey], "h", lazy.layout.left()),
Key([modkey], "l", lazy.layout.right()),
Key([modkey], "j", lazy.layout.down()),
Key([modkey], "k", lazy.layout.up()),
Key([modkey, "shift"], "h", lazy.layout.swap_left()),
Key([modkey, "shift"], "l", lazy.layout.swap_right()),
Key([modkey, "shift"], "j", lazy.layout.shuffle_down()),
Key([modkey, "shift"], "k", lazy.layout.shuffle_up()),
Key([modkey], "i", lazy.layout.grow()),
Key([modkey], "m", lazy.layout.shrink()),
Key([modkey], "n", lazy.layout.reset()),
Key([modkey, "shift"], "n", lazy.layout.normalize()),
Key([modkey, "shift"], "s", lazy.layout.toggle_auto_maximize()),
Key([modkey, "shift"], "s", lazy.layout.flip()),
```

key	default	description
align	0	Which side master plane will be placed (one of MonadTallleft or MonadTallright)
auto_maximize	False	Maximize secondary windows on focus.
border_focus	'#ff0000'	Border colour(s) for the focused window.
border_normal	'#000000'	Border colour(s) for un-focused windows.
border_width	2	Border width.
change_ratio	0.05	Resize ratio
change_size	20	Resize change in pixels
margin	0	Margin of the layout
max_ratio	0.75	The percent of the screen-space the master pane should occupy at maximum.
min_ratio	0.25	The percent of the screen-space the master pane should occupy at minimum.
min_secondary_si	85	minimum size in pixel for a secondary pane window
new_client_posit	'after_current'	Place new windows: after_current - after the active window. before_current - before the active window, top - at the top of the stack, bottom - at the bottom of the stack,
ratio	0.5	The percent of the screen-space the master pane should occupy by default.
single_border_wi	None	Border width for single window
single_margin	None	Margin size for single window

Click to view the available commands for MonadTall

7.7 MonadThreeCol

class libqtile.layout.MonadThreeCol(*args, **kwargs)

Emulate the behavior of XMonad's ThreeColumns layout.

A layout similar to tall but with three columns. With an ultra wide display this layout can be used for a huge main window - ideally at the center of the screen - and up to six reasonable sized secondary windows.

Main-Pane:


A main pane that contains a single window takes up a vertical portion of the screen_rect based on the ratio setting. This ratio can be adjusted with the <code>grow_main</code> and <code>shrink_main</code> or, while the main pane is in focus, <code>grow</code> and <code>shrink</code>. The main pane can also be centered.



Secondary-panes:

7.7. MonadThreeCol 77

Occupying the rest of the screen_rect are one or more secondary panes. The secondary panes will be divided into two columns and share the vertical space of each column. However they can be resized at will with the grow and shrink methods. The other secondary panes will adjust their sizes to smoothly fill all of the space.



Panes can be moved with the shuffle_up and shuffle_down methods. As mentioned the main pane is considered the top of the stack; moving up is counter-clockwise and moving down is clockwise. A secondary pane can also be promoted to the main pane with the swap_main method.

Normalizing/Resetting:

To restore all secondary client windows to their default size ratios use the normalize method.

To reset all client windows to their default sizes, including the primary window, use the reset method.

Maximizing:

To maximized a client window simply use the maximize on a focused client.

Configuration options

key	default	description
align	0	Which side master plane will be placed (one of MonadTallleft or MonadTallright)
auto_maximize	False	Maximize secondary windows on focus.
border_focus	'#ff0000'	Border colour(s) for the focused window.
border_normal	'#000000'	Border colour(s) for un-focused windows.
border_width	2	Border width.
change_ratio	0.05	Resize ratio
change_size	20	Resize change in pixels
main_centered	True	Place the main pane at the center of the screen
margin	0	Margin of the layout
max_ratio	0.75	The percent of the screen-space the master pane should occupy at maximum.
min_ratio	0.25	The percent of the screen-space the master pane should occupy at minimum.
min_secondary_si	85	minimum size in pixel for a secondary pane window
new_client_posit	'top'	Place new windows: after_current - after the active window. before_current - before the active window, top - at the top of the stack, bottom - at the bottom of the stack,
ratio	0.5	The percent of the screen-space the master pane should occupy by default.
single_border_wi	None	Border width for single window
single_margin	None	Margin size for single window

Available commands

Click to view the available commands for MonadThreeCol

7.8 MonadWide

class libqtile.layout.MonadWide(*args, **kwargs)

Emulate the behavior of XMonad's horizontal tiling scheme.


This layout attempts to emulate the behavior of XMonad wide tiling scheme.

Main-Pane:

A main pane that contains a single window takes up a horizontal portion of the screen_rect based on the ratio setting. This ratio can be adjusted with the grow_main and shrink_main or, while the main pane is in focus, grow and shrink.




Using the flip method will switch which vertical side the main pane will occupy. The main pane is considered the "top" of the stack.



Secondary-panes:


Occupying the rest of the screen_rect are one or more secondary panes. The secondary panes will share the horizontal space of the screen_rect however they can be resized at will with the grow and shrink methods. The other secondary panes will adjust their sizes to smoothly fill all of the space.



Panes can be moved with the shuffle_up and shuffle_down methods. As mentioned the main pane is considered the top of the stack; moving up is counter-clockwise and moving down is clockwise.

The opposite is true if the layout is "flipped".

7.8. MonadWide 79



Normalizing/Resetting:

To restore all secondary client windows to their default size ratios use the normalize method.

To reset all client windows to their default sizes, including the primary window, use the reset method.

Maximizing:

To toggle a client window between its minimum and maximum sizes simply use the maximize on a focused client.

Suggested Bindings:

```
Key([modkey], "h", lazy.layout.left()),
Key([modkey], "l", lazy.layout.right()),
Key([modkey], "j", lazy.layout.down()),
Key([modkey], "k", lazy.layout.up()),
Key([modkey, "shift"], "h", lazy.layout.swap_left()),
Key([modkey, "shift"], "l", lazy.layout.swap_right()),
Key([modkey, "shift"], "j", lazy.layout.shuffle_down()),
Key([modkey, "shift"], "k", lazy.layout.shuffle_up()),
Key([modkey], "i", lazy.layout.grow()),
Key([modkey], "m", lazy.layout.shrink()),
Key([modkey], "n", lazy.layout.reset()),
Key([modkey], "o", lazy.layout.normalize()),
Key([modkey], "o", lazy.layout.maximize()),
Key([modkey, "shift"], "space", lazy.layout.flip()),
```

key	default	description
align	0	Which side master plane will be placed (one of MonadTallleft or MonadTallright)
auto_maximize	False	Maximize secondary windows on focus.
border_focus	'#ff0000'	Border colour(s) for the focused window.
border_normal	'#000000'	Border colour(s) for un-focused windows.
border_width	2	Border width.
change_ratio	0.05	Resize ratio
change_size	20	Resize change in pixels
margin	0	Margin of the layout
max_ratio	0.75	The percent of the screen-space the master pane should occupy at maximum.
min_ratio	0.25	The percent of the screen-space the master pane should occupy at minimum.
min_secondary_si	85	minimum size in pixel for a secondary pane window
new_client_posit	'after_current'	Place new windows: after_current - after the active window. before_current - before the active window, top - at the top of the stack, bottom - at the bottom of the stack,
ratio	0.5	The percent of the screen-space the master pane should occupy by default.
single_border_wi	None	Border width for single window
single_margin	None	Margin size for single window

Click to view the available commands for MonadWide

7.9 Plasma

class libqtile.layout.Plasma(*args, **kwargs)

A flexible tree-based layout.

Each tree node represents a container whose children are aligned either horizontally or vertically. Each window is attached to a leaf of the tree and takes either a calculated relative amount or a custom absolute amount of space in its parent container. Windows can be resized, rearranged and integrated into other containers.

Windows in a container will all open in the same direction. Calling lazy.layout.mode_vertical/horizontal() will insert a new container allowing windows to be added in the new direction.

You can use the Plasma widget to show which mode will apply when opening a new window based on the currently focused node.

Windows can be focused selectively by using lazy.layout.up/down/left/right() to focus the nearest window in that direction relative to the currently focused window.

"Integrating" windows is best explained with an illustration. Starting with three windows, a, b, c. b is currently focused. Calling lazy.layout.integrate_left() will have the following effect:

a	b	c		a	c		
			I			I	
			>		I	I	

(continues on next page)

7.9. Plasma 81

(continued from previous page)

Finally, windows can me moved around the layout with lazy.layout.move_up/down/left/right().

Example keybindings:

```
from libqtile.config import EzKey
from libqtile.lazy import lazy
keymap = {
    'M-h': lazy.layout.left(),
    'M-j': lazy.layout.down(),
    'M-k': lazy.layout.up(),
    'M-1': lazy.layout.right(),
    'M-S-h': lazy.layout.move_left(),
    'M-S-j': lazy.layout.move_down(),
    'M-S-k': lazy.layout.move_up(),
    'M-S-1': lazy.layout.move_right(),
    'M-A-h': lazy.layout.integrate_left(),
    'M-A-j': lazy.layout.integrate_down(),
    'M-A-k': lazy.layout.integrate_up(),
    'M-A-1': lazy.layout.integrate_right(),
    'M-d': lazy.layout.mode_horizontal(),
    'M-v': lazy.layout.mode_vertical(),
    'M-S-d': lazy.layout.mode_horizontal_split(),
    'M-S-v': lazy.layout.mode_vertical_split(),
    'M-a': lazy.layout.grow_width(30),
    'M-x': lazy.layout.grow_width(-30),
    'M-S-a': lazy.layout.grow_height(30),
    'M-S-x': lazy.layout.grow_height(-30),
    'M-C-5': lazy.layout.size(500),
    'M-C-8': lazy.layout.size(800),
    'M-n': lazy.layout.reset_size(),
}
keys = [EzKey(k, v) for k, v in keymap.items()]
```

Acknowledgements: This layout was developed by numirias and published at https://github.com/numirias/qtile-plasma A few minor amendments have been made to that layout as part of incorporating this into the main qtile codebase but the majority of the work is theirs.

key	default	description
border_focus	'#00e891'	Focused window border color
border_focus_fix	'#00e8dc'	Focused fixed-size window border color
border_normal	'#333333'	Unfocused window border color
border_normal_fi	'#333333'	Unfocused fixed-size window border color
border_width	1	Border width
border_width_sin	0	Border width for single window
fair	False	When False effort will be made to preserve nodes with a fixed size. Set to True to enable new windows to take more space from fixed size nodes.
margin	0	Layout margin
name	'Plasma'	Layout name

Click to view the available commands for Plasma

7.10 RatioTile

class libqtile.layout.RatioTile(*args, **kwargs)

Tries to tile all windows in the width/height ratio passed in

Configuration options

key	default	description
border_focus	'#0000ff'	Border colour(s) for the focused window.
border_normal	'#000000'	Border colour(s) for un-focused windows.
border_width	1	Border width.
fancy	False	Use a different method to calculate window sizes.
margin	0	Margin of the layout (int or list of ints [N E S W])
ratio	1.618	Ratio of the tiles
ratio_increment	0.1	Amount to increment per ratio increment

Available commands

Click to view the available commands for RatioTile

7.11 ScreenSplit

class libqtile.layout.ScreenSplit(*args, **kwargs)

A layout that allows you to split the screen into separate areas, each of which can be assigned its own layout.

This layout is intended to be used on large monitors where separate layouts may be desirable. However, unlike creating virtual screens, this layout retains the full screen configuration meaning that full screen windows will continue to fill the entire screen.

Each split is defined as a dictionary with the following keys:

• name: this is used with the ScreenSplit widget (see below)

7.10. RatioTile 83

- rect: a tuple of (x, y, width, height) with each value being between 0 and 1. These are relative values based on the screen's dimensions e.g. a value of (0.5, 0, 0.5, 1) would define an area starting at the top middle of the screen and extending to the bottom left corner.
- layout: the layout to occupy the defined split.
- matches: (optional) list of Match objects which define which windows will open in the defined split.

Different splits can be selected by using the following lazy.layout.next_split() and lazy.layout.previous_split() commands.

To identify which split is active, users can use the ScreenSplit widget will show the name of the split and the relevant layout. Scrolling up and down on the widget will change the active split.

Note: While keybindings will be passed to the active split's layout, bindings using the .when(layout=...)` syntax will not be applied as the primary layout is ScreenSplit.

Configuration options

key	default	description
splits	[{'layout': layout.max. Max object at 0x7500c2543dd0>, 'name': 'top', 'rect': (0, 0, 1, 0.5)}, {'layout': layout. columns. Columns object at 0x7500c25a04d0>, 'name': 'bottom', 'rect': (0, 0.5, 1, 0.5)}]	

Available commands

Click to view the available commands for ScreenSplit

7.12 Slice

class libqtile.layout.Slice(*args, **kwargs)

Slice layout

This layout cuts piece of screen_rect and places a single window on that piece, and delegates other window placement to other layout

Configuration options

key	default	description
fallback	<pre><libqtile. 0x7500c241a750="" at="" layout.max.="" max="" object=""></libqtile.></pre>	Layout to be used for the non-slice area.
match	None	Match-object describing which window(s) to move to the slice.
side	'left'	Position of the slice (left, right, top, bottom).
width	256	Slice width.

Available commands

Click to view the available commands for Slice

7.13 Spiral

class libqtile.layout.Spiral(*args, **kwargs)

A mathematical layout.

Renders windows in a spiral form by splitting the screen based on a selected ratio. The direction of the split is changed every time in a defined order resulting in a spiral formation.


The main window can be sized with lazy.layout.grow_main() and lazy.layout.shrink_main(). All other windows are sized by lazy.layout.increase_ratio() and lazy.layout.decrease_ratio().

NB if main_pane_ratio is not set then it will also be adjusted according to ratio. However, as soon shrink_main() or grow_main() have been called once then the master pane will only change size following further calls to those methods.

Users are able to choose the location of the main (i.e. largest) pane and the direction of the rotation.

Some examples:

main_pane="left", clockwise=True



7.12. Slice 85

main_pane="top", clockwise=False



Configuration options

key	default	description
border_focus	'#0000ff'	Border colour(s) for the focused window.
border_normal	'#000000'	Border colour(s) for un-focused windows.
border_on_single	True	Draw border when there is only one window.
border_width	1	Border width.
clockwise	True	Direction of spiral
main_pane	'left'	Location of biggest window 'top', 'bottom', 'left', 'right'
main_pane_ratio	None	Ratio for biggest window or 'None' to use same ratio for all windows.
margin	0	Margin of the layout (int or list of ints [N E S W])
new_client_posit	'top'	Place new windows: 'after_current' - after the active window, 'before_current' - before the active window, 'top' - in the main pane, 'bottom' - at the bottom of the stack. NB windows that are added too low in the stack may be hidden if there is no remaining space in the spiral.
ratio	0.6180469715698392	Ratio of the tiles
ratio_increment	0.1	Amount to increment per ratio increment

Available commands

Click to view the available commands for Spiral

7.14 Stack

class libqtile.layout.Stack(*args, **kwargs)

A layout composed of stacks of windows

The stack layout divides the screen_rect horizontally into a set of stacks. Commands allow you to switch between stacks, to next and previous windows within a stack, and to split a stack to show all windows in the stack, or unsplit it to show only the current window.

Unlike the columns layout the number of stacks is fixed.

key	default	description
autosplit	False	Auto split all new stacks.
border_focus	'#0000ff'	Border colour(s) for the focused window.
border_focus_sta	None	Border colour(s) for the focused stacked window. If 'None' will default to border_focus.
border_normal	'#000000'	Border colour(s) for un-focused windows.
border_normal_st	None	Border colour(s) for un-focused stacked windows. If 'None' will default to border_normal.
border_width	1	Border width.
fair	False	Add new windows to the stacks in a round robin way.
margin	0	Margin of the layout (int or list of ints [N E S W])
num_stacks	2	Number of stacks.

Click to view the available commands for Stack

7.15 Tile

class libqtile.layout.Tile(*args, **kwargs)

A layout with two stacks of windows dividing the screen

The Tile layout divides the screen_rect horizontally into two stacks. The maximum amount of "master" windows can be configured; surplus windows will be displayed in the slave stack on the right. Within their stacks, the windows will be tiled vertically. The windows can be rotated in their entirety by calling up() or down() or, if shift_windows is set to True, individually.

Configuration options

7.15. Tile 87

key	default	description
add_after_last	False	Add new clients after all the others. If this is True, it overrides add_on_top.
add_on_top	True	Add new clients before all the others, potentially pushing other windows into slave stack.
border_focus	'#0000ff'	Border colour(s) for the focused window.
border_normal	'#000000'	Border colour(s) for un-focused windows.
border_on_single	True	Whether to draw border if there is only one window.
border_width	1	Border width.
expand	True	Expand the master windows to the full screen width if no slaves are present.
margin	0	Margin of the layout (int or list of ints [N E S W])
margin_on_single	True	Whether to draw margin if there is only one window.
master_length	1	Amount of windows displayed in the master stack. Surplus windows will be moved to the slave stack.
master_match	None	A Match object defining which window(s) should be kept masters (single or a list of Match-objects).
max_ratio	0.85	Maximum width of master windows
min_ratio	0.15	Minimum width of master windows
ratio	0.618	Width-percentage of screen size reserved for master windows.
ratio_increment	0.05	By which amount to change ratio when decrease_ratio or increase_ratio are called.
shift_windows	False	Allow to shift windows within the layout. If False, the layout will be rotated instead.

Click to view the available commands for Tile

7.16 TreeTab

class libqtile.layout.TreeTab(*args, **kwargs)

Tree Tab Layout

This layout works just like Max but displays tree of the windows at the left border of the screen_rect, which allows you to overview all opened windows. It's designed to work with uzbl-browser but works with other windows too.

The panel at the left border contains sections, each of which contains windows. Initially the panel looks like flat lists inside its section, and looks like trees if some of the windows are "moved" left or right.

For example, it looks like below with two sections initially:



(continues on next page)

(continued from previous page)

And then it will look like below if "Window B" is moved right and "Window C" is moved right too:

Configuration options

key	default	description
active_bg	'000080'	Background color of active tab
active_fg	'ffffff'	Foreground color of active tab
bg_color	'000000'	Background color of tabs
border_width	2	Width of the border
font	'sans'	Font
fontshadow	None	font shadow color, default is None (no shadow)
fontsize	14	Font pixel size.
inactive_bg	'606060'	Background color of inactive tab
inactive_fg	'ffffff'	Foreground color of inactive tab
level_shift	8	Shift for children tabs
margin_left	6	Left margin of tab panel
margin_y	6	Vertical margin of tab panel
padding_left	6	Left padding for tabs
padding_x	6	Left padding for tab label
padding_y	2	Top padding for tab label
panel_width	150	Width of the left panel
place_right	False	Place the tab panel on the right side
previous_on_rm	False	Focus previous window on close instead of first.
section_bottom	6	Bottom margin of section
section_fg	'ffffff'	Color of section label
section_fontsize	11	Font pixel size of section label
section_left	4	Left margin of section label
section_padding	4	Bottom of margin section label
section_top	4	Top margin of section label
sections	['Default']	Titles of section instances
urgent_bg	'ff0000'	Background color of urgent tab
urgent_fg	'ffffff'	Foreground color of urgent tab
vspace	2	Space between tabs

Available commands

7.16. TreeTab 89


Click to view the available commands for TreeTab

7.17 VerticalTile

class libqtile.layout.VerticalTile(*args, **kwargs)

Tiling layout that works nice on vertically mounted monitors

The available height gets divided by the number of panes, if no pane is maximized. If one pane has been maximized, the available height gets split in master and secondary area. The maximized pane (master pane) gets the full height of the master area and the other panes (secondary panes) share the remaining space. The master area (at default 75%) can grow and shrink via keybindings.



```
| In some cases, VerticalTile can be | useful on horizontal mounted | monitors too. | For example, if you want to have a | web browser and a shell below it. | | 2 | | | |
```

Suggested keybindings:

continues on next page)

(continued from previous page)

```
Key([modkey], 'm', lazy.layout.maximize()),
Key([modkey], 'n', lazy.layout.normalize()),
```

Configuration options

key	default	description
border_focus	'#FF0000'	Border color(s) for the focused window.
border_normal	'#FFFFFF'	Border color(s) for un-focused windows.
border_width	1	Border width.
margin	0	Border margin (int or list of ints [N E S W]).
single_border_wi	None	Border width for single window.
single_margin	None	Margin for single window.

Available commands

Click to view the available commands for VerticalTile

7.18 Zoomy

class libqtile.layout.Zoomy(*args, **kwargs)

A layout with single active windows, and few other previews at the right

Configuration options

key	default	description
columnwidth	150	Width of the right column
margin	0	Margin of the layout (int or list of ints [N E S W])
property_big	'1.0'	Property value to set on normal window (X11 only)
property_name	'ZOOM'	Property to set on zoomed window (X11 only)
<pre>property_small</pre>	'0.1'	Property value to set on zoomed window (X11 only)

Available commands

Click to view the available commands for Zoomy

7.18. Zoomy 91

CHAPTER

EIGHT

BUILT-IN WIDGETS

8.1 AGroupBox

class libqtile.widget.AGroupBox(*args, **kwargs)

A widget that graphically displays the current group

Supported bar orientations: horizontal only

key	default	description
background	None	Widget background color
border	'000000'	group box border color
borderwidth	3	Current group border width
center_aligned	True	center-aligned group box
direction	'default'	Override the text direction in vertical bar, has no effect on text in horizontal bar.default: text displayed based on vertical bar position (left/right)ttb: text read from top to bottom, btt: text read from bottom to top.'default', 'ttb', 'btt'
fmt	'{}'	Format to apply to the string returned by the widget. Main purpose: applying markup. For a widget that returns foo, using fmt=' <i>{}</i> ' would give you <i>foo</i> . To control what the widget outputs in the first place, use the format paramater of the widget (if it has one).
font	'sans'	Default font
fontshadow	None	font shadow color, default is None(no shadow)
fontsize	None	Font size. Calculated if None.
foreground	'ffffff'	Foreground colour
hide_crash	False	Don't display error in bar if widget crashes on startup.
margin	3	Margin inside the box
margin_x	None	X Margin. Overrides 'margin' if set
margin_y	None	Y Margin. Overrides 'margin' if set
markup	False	Whether or not to use pango markup
max_chars	0	Maximum number of characters to display in widget.
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions and lazy calls.
padding	None	Padding. Calculated if None.
padding_x	None	X Padding. Overrides 'padding' if set
padding_y	None	Y Padding. Overrides 'padding' if set
rotate	True	Rotate text in vertical bar.
scroll	False	Whether text should be scrolled. When True, you must set the widget's width.
scroll_clear	False	Whether text should scroll completely away (True) or stop when the end of the text is shown (False)
scroll_delay	2	Number of seconds to pause before starting scrolling and restarting/clearing text at end
scroll_fixed_wid	False	When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text.
scroll_hide	False	Whether the widget should hide when scrolling has finished
scroll_interval	0.1	Time in seconds before next scrolling step
scroll_repeat	True	Whether text should restart scrolling once the text has ended
scroll_step	1	Number of pixels to scroll with each step

Click to view the available commands for AGroupBox

8.2 Backlight

```
class libqtile.widget.Backlight(*args, **kwargs)
```

A simple widget to show the current brightness of a monitor.

If the change_command parameter is set to None, the widget will attempt to use the interface at /sys/class to change brightness. This depends on having the correct udev rules, so be sure Qtile's udev rules are installed correctly.

You can also bind keyboard shortcuts to the backlight widget with:

```
from libqtile.widget import backlight
Key(
    [],
    "XF86MonBrightnessUp",
    lazy.widget['backlight'].change_backlight(backlight.ChangeDirection.UP)
)
Key(
    [],
    "XF86MonBrightnessDown",
    lazy.widget['backlight'].change_backlight(backlight.ChangeDirection.DOWN)
)
```

Supported bar orientations: horizontal and vertical

Configuration options

8.2. Backlight 95

key	default	description
background	None	Widget background color
backlight_name	'acpi_video0'	ACPI name of a backlight device
brightness_file	'brightness'	Name of file with the current brightness in /sys/class/backlight/backlight_name
change_command	<pre>'xbacklight -set {0}'</pre>	Execute command to change value
direction	'default'	Override the text direction in vertical bar, has no effect on text in horizontal bar.default: text displayed based on vertical bar position (left/right)ttb: text read from top to bottom, btt: text read from bottom to top.'default', 'ttb', 'btt'
fmt	'{}'	Format to apply to the string returned by the widget. Main purpose: applying markup. For a widget that returns foo, using fmt=' <i>{}</i> ' would give you <i>foo</i> . To control what the widget outputs in the first place, use the format paramater of the widget (if it has one).
font	'sans'	Default font
fontshadow	None	font shadow color, default is None(no shadow)
fontsize	None	Font size. Calculated if None.
foreground	'ffffff'	Foreground colour
format	'{percent:2. 0%}'	Display format
hide_crash	False	Don't display error in bar if widget crashes on startup.
markup	True	Whether or not to use pango markup
max_brightness_f	'max_brightness'	Name of file with the maximum brightness in /sys/class/backlight/backlight_name
max_chars	0	Maximum number of characters to display in widget.
min_brightness	0	Minimum brightness percentage
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions and lazy calls.
padding	None	Padding. Calculated if None.
rotate	True	Rotate text in vertical bar.
scroll	False	Whether text should be scrolled. When True, you must set the widget's width.
scroll_clear	False	Whether text should scroll completely away (True) or stop when the end of the text is shown (False)
scroll_delay	2	Number of seconds to pause before starting scrolling and restarting/clearing text at end
scroll_fixed_wid	False	When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text.
scroll_hide	False	Whether the widget should hide when scrolling has finished
scroll_interval	0.1	Time in seconds before next scrolling step
scroll_repeat	True	Whether text should restart scrolling once the text has ended
scroll_step	1	Number of pixels to scroll with each step
step	10	Percent of backlight every scroll changed
update_interval	0.2	The delay in seconds between updates

Click to view the available commands for <code>Backlight</code>

8.3 Battery

class libqtile.widget.Battery(*args, **kwargs)

A text-based battery monitoring widget supporting both Linux and FreeBSD.

The Linux version of this widget has functionality to charge "smartly" (i.e. not to 100%) under user defined conditions, and provides some implementations for doing so. For example, to only charge the battery to 90%, use:

```
Battery(..., charge_controller=lambda: (0, 90))
```

The battery widget also supplies some charging algorithms. To only charge the battery between 40-50% while connected to a thunderbolt docking station, but 90% all other times, use:

```
from libqtile.widget.battery import thunderbolt_smart_charge
Battery(..., charge_controller=thunderbolt_smart_charge)
```

To temporarily disable/re-enable this (e.g. if you know you're going mobile and need to charge) use either:

```
qtile cmd-obj -o bar top widget battery -f charge_to_full qtile cmd-obj -o bar top widget battery -f charge_dynamically
```

or bind a key to:

```
Key([mod, "shift"], "c", lazy.widget['battery'].charge_to_full())
Key([mod, "shift"], "x", lazy.widget['battery'].charge_dynamically())
```

note that this functionality requires quile to be able to write to certain files in sysfs, so make sure that quile's udev rules are installed correctly.

Supported bar orientations: horizontal and vertical

Configuration options

key	default	description
background	None	Widget background color
battery	0	Which battery should be monitored (battery number or name)
charge_char	' ' '	Character to indicate the battery is charging
charging_backgro	None	Background color on charging battery. Set to None to disable.
charging_foregro	None	Font color on charging battery. Set to None to disable.
direction	'default'	Override the text direction in vertical bar, has no effect on text in horizontal bar.default: text displayed based on vertical bar position (left/right)ttb: text read from top to bottom, btt: text read from bottom to top.'default', 'ttb', 'btt'
discharge_char	'∀'	Character to indicate the battery is discharging
empty_char	'x'	Character to indicate the battery is empty
empty_short_text	'Empty'	Short text to indicate battery is empty; see <i>show_short_text</i>
fmt	'{}'	Format to apply to the string returned by the widget. Main purpose: applying markup. For a widget that returns foo, using fmt=' <i>{}</i> ' would give you <i>foo</i> . To control what the widget outputs in the first place, use the format paramater of the widget (if it has one).
font	'sans'	Default font

continues on next page

8.3. Battery 97

Table 1 – continued from previous page

		· · ·
key	default	description
fontshadow	None	font shadow color, default is None(no shadow)
fontsize	None	Font size. Calculated if None.
foreground	'ffffff'	Foreground colour
format	'{char} {percent:2.0%} {hour:d}:{min:02 {watt:.2f} W'	Display format
full_char	'='	Character to indicate the battery is full
full_short_text	'Full'	Short text to indicate battery is full; see <i>show_short_text</i>
hide_crash	False	Don't display error in bar if widget crashes on startup.
hide_threshold	None	Hide the text when there is enough energy $0 \le x \le 1$
low_background	None	Background color on low battery
low_foreground	'FF0000'	Font color on low battery
low_percentage	0.1	Indicates when to use the low_foreground color $0 < x < 1$
markup	True	Whether or not to use pango markup
max_chars	0	Maximum number of characters to display in widget.
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions and lazy calls.
not_charging_cha	1 % 1	Character to indicate the batter is not charging
notification_tim	10	Time in seconds to display notification. 0 for no expiry.
notify_below	None	Send a notification below this battery level.
padding	None	Padding. Calculated if None.
rotate	True	Rotate text in vertical bar.
scroll	False	Whether text should be scrolled. When True, you must set the widget's width.
scroll_clear	False	Whether text should scroll completely away (True) or stop when the end of the text is shown (False)
scroll_delay	2	Number of seconds to pause before starting scrolling and restart- ing/clearing text at end
scroll_fixed_wid	False	When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text.
scroll_hide	False	Whether the widget should hide when scrolling has finished
scroll_interval	0.1	Time in seconds before next scrolling step
scroll_repeat	True	Whether text should restart scrolling once the text has ended
scroll_step	1	Number of pixels to scroll with each step
show_short_text	True	Show only characters rather than formatted text when battery is full or empty
unknown_char	'?'	Character to indicate the battery status is unknown
update_interval	60	Seconds between status updates

Click to view the available commands for *Battery*

8.4 Batterylcon

class libqtile.widget.BatteryIcon(*args, **kwargs)

Battery life indicator widget.

Supported bar orientations: horizontal only

Configuration options

key	default	description
background	None	Widget background color
battery	0	Which battery should be monitored
hide_crash	False	Don't display error in bar if widget crashes on startup.
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions and lazy calls.
padding	0	Additional padding either side of the icon
scale	1	Scale factor relative to the bar height. Defaults to 1
theme_path	'/home/docs/ checkouts/ readthedocs. org/ user_builds/ qtile/ checkouts/ stable/ libqtile/ resources/ battery-icons'	Path of the icons
update_interval	60	Seconds between status updates

Available commands

Click to view the available commands for BatteryIcon

8.5 Bluetooth

class libqtile.widget.Bluetooth(*args, **kwargs)

Bluetooth widget that provides following functionality: - View multiple adapters/devices (adapters can be filtered) - Set power and discovery status for adapters - Connect/disconnect/pair devices

The widget works by providing a menu in the bar. Different items are accessed by scrolling up and down on the widget.

Clicking on an adapter will open a submenu allowing you to set power and discovery status.

Clicking on a device will perform an action based on the status of that device: - Connected devices will be disconnected - Disconnected devices will be connected - Unpaired devices (which appear if discovery is on) will be paired and connected

Symbols are used to show the status of adapters and devices.

Battery level for bluetooth devices can also be shown if available. This functionality is not available by default on all distros. If it doesn't work, you can try adding Experimental = true to /etc/bluetooth/main.conf.

8.4. Batterylcon 99

Supported bar orientations: horizontal and vertical

key	default	description
adapter_format	'Adapter: {name} [{powered}{disco	Text to display when showing adapter device.
adapter_paths		List of DBus object path for bluetooth adapter (e.g. '/org/bluez/hci0'). Empty list will show all adapters.
background	None	Widget background color
default_show_bat	False	Include battery level of 'connected_devices' in 'default_text'. Uses 'device_battery_format'.
default_text	'BT {connected_devic	Text to show when not scrolling through menu. Available fields: 'connected_devices' list of connected devices, 'num_connected_devices' number of connected devices, 'adapters' list of bluetooth adapters, 'num_adapters' number of bluetooth adapters.
default_timeout	None	Time before reverting to default_text. If 'None', text will stay on selected item.
device	None	Device path, can be found with d-feet or similar dbus explorer. When set, the widget will default to showing this device status.
device_battery_f	' ({battery}%)'	Text to be shown if device reports battery level
device_format	'Device: {name}{battery_l [{symbol}]'	Text to display when showing bluetooth device. The {adapter field is also available if you're using multiple adapters.
direction	'default'	Override the text direction in vertical bar, has no effect on text in horizontal bar.default: text displayed based on vertical bar position (left/right)ttb: text read from top to bottom, btt: text read from bottom to top.'default', 'ttb', 'btt'
fmt	'{}'	Format to apply to the string returned by the widget. Main purpose: applying markup. For a widget that returns foo, using fmt=' <i>{}</i> ' would give you <i>foo</i> . To control what the widget outputs in the first place, use the format paramater of the widget (if it has one).
font	'sans'	Default font
fontshadow	None	font shadow color, default is None(no shadow)
fontsize	None	Font size. Calculated if None.
foreground	'ffffff'	Foreground colour
hide_crash	False	Don't display error in bar if widget crashes on startup.
hide_unnamed_dev		Devices with no name will be hidden from scan results
margin	3	Margin inside the box
margin_x	None	X Margin. Overrides 'margin' if set
margin_y	None	Y Margin. Overrides 'margin' if set
markup	True	Whether or not to use pango markup
max_chars mouse_callbacks	0 {}	Maximum number of characters to display in widget. Dict of mouse button press callback functions. Accepts functions and lazy calls.
padding	None	Padding. Calculated if None.
rotate	True	Rotate text in vertical bar.
scroll	False	Whether text should be scrolled. When True, you must set the widget's width.
		continues on next page

Table 2 – continued from previous page

key	default	description
scroll_clear	False	Whether text should scroll completely away (True) or stop when the end of the text is shown (False)
scroll_delay	2	Number of seconds to pause before starting scrolling and restarting/clearing text at end
scroll_fixed_wid	False	When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text.
scroll_hide	False	Whether the widget should hide when scrolling has finished
scroll_interval	0.1	Time in seconds before next scrolling step
scroll_repeat	True	Whether text should restart scrolling once the text has ended
scroll_step	1	Number of pixels to scroll with each step
separator	', '	Separator for lists in 'default_text'.
symbol_connected	1 % 1	Symbol to indicate device is connected
symbol_discovery	('D', '')	Symbols when adapter is discovering and not discovering
symbol_paired	1_1	Symbol to indicate device is paired but unconnected
symbol_powered	('*', '-')	Symbols when adapter is powered and unpowered.
symbol_unknown	'?'	Symbol to indicate device is unpaired

Click to view the available commands for Bluetooth

8.6 CPU

class libqtile.widget.CPU(*args, **kwargs)

A simple widget to display CPU load and frequency.

Widget requirements: psutil.

Supported bar orientations: horizontal and vertical

Configuration options

8.6. CPU 101

key	default	description
background	None	Widget background color
direction	'default'	Override the text direction in vertical bar, has no effect on text in horizontal bar.default: text displayed based on vertical bar position (left/right)ttb: text read from top to bottom, btt: text read from bottom to top.'default', 'ttb', 'btt'
fmt	'{}'	Format to apply to the string returned by the widget. Main purpose: applying markup. For a widget that returns foo, using fmt=' <i>{}</i> ' would give you <i>foo</i> . To control what the widget outputs in the first place, use the format paramater of the widget (if it has one).
font	'sans'	Default font
fontshadow	None	font shadow color, default is None(no shadow)
fontsize	None	Font size. Calculated if None.
foreground	'ffffff'	Foreground colour
format	'CPU {freq_current}GH {load_percent}%'	CPU display format
hide_crash	False	Don't display error in bar if widget crashes on startup.
markup	True	Whether or not to use pango markup
max_chars	0	Maximum number of characters to display in widget.
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions and lazy calls.
padding	None	Padding. Calculated if None.
rotate	True	Rotate text in vertical bar.
scroll	False	Whether text should be scrolled. When True, you must set the widget's width.
scroll_clear	False	Whether text should scroll completely away (True) or stop when the end of the text is shown (False)
scroll_delay	2	Number of seconds to pause before starting scrolling and restarting/clearing text at end
scroll_fixed_wid	False	When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text.
scroll_hide	False	Whether the widget should hide when scrolling has finished
scroll_interval	0.1	Time in seconds before next scrolling step
scroll_repeat	True	Whether text should restart scrolling once the text has ended
scroll_step	1	Number of pixels to scroll with each step
update_interval	1.0	Update interval for the CPU widget

Click to view the available commands for CPU

8.7 CPUGraph

class libqtile.widget.CPUGraph(*args, **kwargs)

Display CPU usage graph.

Widget requirements: psutil.

Supported bar orientations: horizontal only

Configuration options

key	default	description
background	None	Widget background color
border_color	'215578'	Widget border color
border_width	2	Widget border width
core	'all'	Which core to show (all/0/1/2/)
fill_color	'1667EB.3'	Fill color for linefill graph
frequency	1	Update frequency in seconds
graph_color	'18BAEB'	Graph color
hide_crash	False	Don't display error in bar if widget crashes on startup.
line_width	3	Line width
margin_x	3	Margin X
margin_y	3	Margin Y
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions and lazy calls.
samples	100	Count of graph samples.
start_pos	'bottom'	Drawer starting position ('bottom'/'top')
type	'linefill'	'box', 'line', 'linefill'

Available commands

Click to view the available commands for CPUGraph

8.8 Canto

class libqtile.widget.Canto(*args, **kwargs)

Display RSS feeds updates using the canto console reader

Widget requirements: canto

Supported bar orientations: horizontal and vertical

Configuration options

8.7. CPUGraph

key	default	description
all_format	'{number}'	All feeds display format
background	None	Widget background color
direction	'default'	Override the text direction in vertical bar, has no effect on text in horizontal bar.default: text displayed based on vertical bar position (left/right)ttb: text read from top to bottom, btt: text read from bottom to top.'default', 'ttb', 'btt'
feeds	[]	List of feeds to display, empty for all
fetch	False	Whether to fetch new items on update
fmt	'{}'	Format to apply to the string returned by the widget. Main purpose: applying markup. For a widget that returns foo, using fmt=' <i>{}</i> ' would give you <i>foo</i> . To control what the widget outputs in the first place, use the format paramater of the widget (if it has one).
font	'sans'	Default font
fontshadow	None	font shadow color, default is None(no shadow)
fontsize	None	Font size. Calculated if None.
foreground	'ffffff'	Foreground colour
hide_crash	False	Don't display error in bar if widget crashes on startup.
markup	True	Whether or not to use pango markup
max_chars	0	Maximum number of characters to display in widget.
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions and lazy calls.
one_format	'{name}: {number}'	One feed display format
padding	None	Padding. Calculated if None.
rotate	True	Rotate text in vertical bar.
scroll	False	Whether text should be scrolled. When True, you must set the widget's width.
scroll_clear	False	Whether text should scroll completely away (True) or stop when the end of the text is shown (False)
scroll_delay	2	Number of seconds to pause before starting scrolling and restart- ing/clearing text at end
scroll_fixed_wid	False	When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text.
scroll_hide	False	Whether the widget should hide when scrolling has finished
scroll_interval	0.1	Time in seconds before next scrolling step
scroll_repeat	True	Whether text should restart scrolling once the text has ended
scroll_step	1	Number of pixels to scroll with each step
update_interval	600	Update interval in seconds, if none, the widget updates only once.

Click to view the available commands for Canto

8.9 CapsNumLockIndicator

class libqtile.widget.CapsNumLockIndicator(*args, **kwargs)

Really simple widget to show the current Caps/Num Lock state.

Supported bar orientations: horizontal and vertical

Configuration options

key	default	description
background	None	Widget background color
direction	'default'	Override the text direction in vertical bar, has no effect on text in horizontal bar.default: text displayed based on vertical bar position (left/right)ttb: text read from top to bottom, btt: text read from bottom to top.'default', 'ttb', 'btt'
fmt	'{}'	Format to apply to the string returned by the widget. Main purpose: applying markup. For a widget that returns foo, using fmt=' <i>{i>{}</i> ' would give you <i>foo</i> . To control what the widget outputs in the first place, use the format paramater of the widget (if it has one).
font	'sans'	Default font
fontshadow	None	font shadow color, default is None(no shadow)
fontsize	None	Font size. Calculated if None.
foreground	'ffffff'	Foreground colour
hide_crash	False	Don't display error in bar if widget crashes on startup.
markup	True	Whether or not to use pango markup
max_chars	0	Maximum number of characters to display in widget.
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions and lazy calls.
padding	None	Padding. Calculated if None.
rotate	True	Rotate text in vertical bar.
scroll	False	Whether text should be scrolled. When True, you must set the widget's width.
scroll_clear	False	Whether text should scroll completely away (True) or stop when the end of the text is shown (False)
scroll_delay	2	Number of seconds to pause before starting scrolling and restart- ing/clearing text at end
scroll_fixed_wid	False	When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text.
scroll_hide	False	Whether the widget should hide when scrolling has finished
scroll_interval	0.1	Time in seconds before next scrolling step
scroll_repeat	True	Whether text should restart scrolling once the text has ended
scroll_step	1	Number of pixels to scroll with each step
update_interval	0.5	Update Time in seconds.

Available commands

Click to view the available commands for ${\it CapsNumLockIndicator}$

8.10 CheckUpdates

class libqtile.widget.CheckUpdates(*args, **kwargs)

Shows number of pending updates in different unix systems.

The following built-in options are available via the distro parameter:

- 'Arch' runs ('pacman -Qu', 0)
- 'Arch_checkupdates' runs ('checkupdates', 0)
- 'Arch_Sup' runs ('pacman -Sup', 0)
- 'Arch_paru' runs ('paru -Qu', 0)
- 'Arch_paru_Sup' runs ('paru -Sup', 0)
- 'Arch_yay' runs ('yay -Qu', 0)
- 'Debian' runs ('apt-show-versions -u -b', 0)
- 'Gentoo_eix' runs ('EIX_LIMIT=0 eix -u# --world', 0)
- 'Guix' runs ('guix upgrade --dry-run', 0)
- 'Ubuntu' runs ('aptitude search ~U', 0)
- 'Fedora' runs ('dnf list --upgrades -q', 1)
- 'FreeBSD' runs ("pkg upgrade -n | awk '/\t/ { print \$0 }'", 0)
- 'Mandriva' runs ('urpmq --auto-select', 0)
- 'Void' runs ('xbps-install -nuMS', 0)

Note: It is common for package managers to return a non-zero code when there are no updates. As a result, the widget will treat *any* error as if there are no updates. If you are using a custom command/script, you should therefore ensure that it returns zero when it completes if you wish to see the output of your command.

In addition, as no errors are recorded to the log, if the widget is showing no updates and you believe that to be incorrect, you should run the appropriate command in a terminal to view any error messages.

Supported bar orientations: horizontal and vertical

Configuration options

key	default	description
background colour_have_upda colour_no_update custom_command		Widget background color Colour when there are updates. Colour when there's no updates. Custom shell command for checking updates (counts the lines of the output)
custom_command_r	<function <lambda="" checkupdates.=""> at 0x7500c142ea20></function>	Lambda function to modify line count from custom_command

continues on next page

Table 3 – continued from previous page

key	default	description
direction	'default'	Override the text direction in vertical bar, has no effect on text in horizontal bar.default: text displayed based on vertical bar position (left/right)ttb: text read from top to bottom, btt: text read from bottom to top.'default', 'ttb', 'btt'
display_format	'Updates: {updates}'	Display format if updates available
distro	'Arch'	Name of your distribution
execute	None	Command to execute on click
fmt	'{}'	Format to apply to the string returned by the widget. Main purpose: applying markup. For a widget that returns foo, using fmt=' <i>{}</i> ' would give you <i>foo</i> . To control what the widget outputs in the first place, use the format paramater of the widget (if it has one).
font	'sans'	Default font
fontshadow	None	font shadow color, default is None(no shadow)
fontsize	None	Font size. Calculated if None.
foreground	'ffffff'	Foreground colour
hide_crash	False	Don't display error in bar if widget crashes on startup.
initial_text	1.1	Draw the widget immediately with an initial text, useful if it takes time to check system updates.
markup	True	Whether or not to use pango markup
max_chars	0	Maximum number of characters to display in widget.
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions and lazy calls.
no_update_string	11	String to display if no updates available
padding	None	Padding. Calculated if None.
restart_indicato	11	Indicator to represent reboot is required. (Ubuntu only)
rotate	True	Rotate text in vertical bar.
scroll	False	Whether text should be scrolled. When True, you must set the widget's width.
scroll_clear	False	Whether text should scroll completely away (True) or stop when the end of the text is shown (False)
scroll_delay	2	Number of seconds to pause before starting scrolling and restarting/clearing text at end
scroll_fixed_wid	False	When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text.
scroll_hide	False	Whether the widget should hide when scrolling has finished
scroll_interval	0.1	Time in seconds before next scrolling step
scroll_repeat	True	Whether text should restart scrolling once the text has ended
scroll_step	1	Number of pixels to scroll with each step
update_interval	60	Update interval in seconds.

Click to view the available commands for *CheckUpdates*

8.11 Chord

class libqtile.widget.Chord(*args, **kwargs)

Display current key chord

Supported bar orientations: horizontal and vertical

key	default	description
background	None	Widget background color
chords_colors	{}	colors per chord in form of tuple {'chord_name': ('bg', 'fg')}. Where a chord name is not in the dictionary, the default background and foreground values will be used.
direction	'default'	Override the text direction in vertical bar, has no effect on text in horizontal bar.default: text displayed based on vertical bar position (left/right)ttb: text read from top to bottom, btt: text read from bottom to top.'default', 'ttb', 'btt'
fmt	'{}'	Format to apply to the string returned by the widget. Main purpose: applying markup. For a widget that returns foo, using fmt=' <i>{}</i> ' would give you <i>foo</i> . To control what the widget outputs in the first place, use the format paramater of the widget (if it has one).
font	'sans'	Default font
fontshadow	None	font shadow color, default is None(no shadow)
fontsize	None	Font size. Calculated if None.
foreground	'ffffff'	Foreground colour
hide_crash	False	Don't display error in bar if widget crashes on startup.
markup	True	Whether or not to use pango markup
max_chars	0	Maximum number of characters to display in widget.
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions and lazy calls.
name_transform	<function <lambda="" chord.=""> at 0x7500c142e980></function>	preprocessor for chord name it is pure function string -> string
padding	None	Padding. Calculated if None.
rotate	True	Rotate text in vertical bar.
scroll	False	Whether text should be scrolled. When True, you must set the widget's width.
scroll_clear	False	Whether text should scroll completely away (True) or stop when the end of the text is shown (False)
scroll_delay	2	Number of seconds to pause before starting scrolling and restarting/clearing text at end
scroll_fixed_wid	False	When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text.
scroll_hide	False	Whether the widget should hide when scrolling has finished
scroll_interval	0.1	Time in seconds before next scrolling step
scroll_repeat	True	Whether text should restart scrolling once the text has ended
scroll_step	1	Number of pixels to scroll with each step

Click to view the available commands for Chord

8.12 Clipboard

class libqtile.widget.Clipboard(*args, **kwargs)

Display current clipboard contents

Supported bar orientations: horizontal and vertical

Configuration options

8.12. Clipboard 109

key	default	description
background	None	Widget background color
blacklist	['keepassx']	list with blacklisted wm_class, sadly not every clipboard window sets them, keepassx does. Clipboard contents from blacklisted wm_classes will be replaced by the value of blacklist_text.
blacklist_text	**********	text to display when the wm_class is blacklisted
direction	'default'	Override the text direction in vertical bar, has no effect on text in horizontal bar.default: text displayed based on vertical bar position (left/right)ttb: text read from top to bottom, btt: text read from bottom to top.'default', 'ttb', 'btt'
fmt	'{}'	Format to apply to the string returned by the widget. Main purpose: applying markup. For a widget that returns foo, using fmt=' <i>{}</i> ' would give you <i>foo</i> . To control what the widget outputs in the first place, use the format paramater of the widget (if it has one).
font	'sans'	Default font
fontshadow	None	font shadow color, default is None(no shadow)
fontsize	None	Font size. Calculated if None.
foreground	'ffffff'	Foreground colour
hide_crash	False	Don't display error in bar if widget crashes on startup.
markup	True	Whether or not to use pango markup
max_chars	0	Maximum number of characters to display in widget.
max_width	10	maximum number of characters to display (None for all, useful when width is bar.STRETCH)
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions and lazy calls.
padding	None	Padding. Calculated if None.
rotate	True	Rotate text in vertical bar.
scroll	False	Whether text should be scrolled. When True, you must set the widget's width.
scroll_clear	False	Whether text should scroll completely away (True) or stop when the end of the text is shown (False)
scroll_delay	2	Number of seconds to pause before starting scrolling and restarting/clearing text at end
scroll_fixed_wid	False	When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text.
scroll_hide	False	Whether the widget should hide when scrolling has finished
scroll_interval	0.1	Time in seconds before next scrolling step
scroll_repeat	True	Whether text should restart scrolling once the text has ended
scroll_step	1	Number of pixels to scroll with each step
selection	'CLIPBOARD'	the selection to display(CLIPBOARD or PRIMARY)
timeout	10	Default timeout (seconds) for display text, None to keep forever

Click to view the available commands for ${\it Clipboard}$

8.13 Clock

class libqtile.widget.Clock(*args, **kwargs)

A simple but flexible text-based clock

Supported bar orientations: horizontal and vertical

Configuration options

key	default	description
background	None	Widget background color
direction	'default'	Override the text direction in vertical bar, has no effect on text in horizontal bar.default: text displayed based on vertical bar position (left/right)ttb: text read from top to bottom, btt: text read from bottom to top.'default', 'ttb', 'btt'
fmt	'{}'	Format to apply to the string returned by the widget. Main purpose: applying markup. For a widget that returns foo, using fmt=' <i>{}</i> ' would give you <i>foo</i> . To control what the widget outputs in the first place, use the format paramater of the widget (if it has one).
font	'sans'	Default font
fontshadow	None	font shadow color, default is None(no shadow)
fontsize	None	Font size. Calculated if None.
foreground	'ffffff'	Foreground colour
format	'%H:%M'	A Python datetime format string
hide_crash	False	Don't display error in bar if widget crashes on startup.
markup	True	Whether or not to use pango markup
max_chars	0	Maximum number of characters to display in widget.
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions and lazy calls.
padding	None	Padding. Calculated if None.
rotate	True	Rotate text in vertical bar.
scroll	False	Whether text should be scrolled. When True, you must set the widget's width.
scroll_clear	False	Whether text should scroll completely away (True) or stop when the end of the text is shown (False)
scroll_delay	2	Number of seconds to pause before starting scrolling and restart- ing/clearing text at end
scroll_fixed_wid	False	When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text.
scroll_hide	False	Whether the widget should hide when scrolling has finished
scroll_interval	0.1	Time in seconds before next scrolling step
scroll_repeat	True	Whether text should restart scrolling once the text has ended
scroll_step	1	Number of pixels to scroll with each step
timezone	None	The timezone to use for this clock, either as string if pytz or dateutil is installed (e.g. "US/Central" or anything in /usr/share/zoneinfo), or as tzinfo (e.g. datetime.timezone.utc). None means the system local timezone and is the default.
update_interval	1.0	Update interval for the clock

Available commands

8.13. Clock 111

Click to view the available commands for Clock

8.14 Cmus

class libqtile.widget.Cmus(*args, **kwargs)

A simple Cmus widget.

Show the metadata of now listening song and allow basic mouse control from the bar:

- toggle pause (or play if stopped) on left click;
- skip forward in playlist on scroll up;
- skip backward in playlist on scroll down.

The following fields (extracted from cmus-remote -C status) are available in the *format* string:

- status: cmus playback status, one of "playing", "paused" or "stopped".
- file
- position: Current position in [h:]mm:ss.
- position_percent: Current position in percent.
- remaining: Remaining time in [h:]mm:ss.
- remaining_percent: Remaining time in percent.
- duration: Total length in [h:]mm:ss.
- artist
- album
- albumartist
- composer
- comment
- date
- discnumber
- genre
- title: Title or filename if no title is available.
- tracknumber
- stream
- status_text: Text indicating the playback status, corresponds to one of *playing_text*, *paused_text* or *stopped_text*.

Cmus (https://cmus.github.io) should be installed.

Supported bar orientations: horizontal and vertical

background direction 'default' Override the text direction in vertical bar, has no effect on text in horizontal bar, default: text displayed based on vertical bar position (left/right)(tb: text read from top to bottom, btt: text read from top to bottom, btt: text read from top to top 'default', 'tb', 'bu' fmt '{}' Format to apply to the string returned by the widget. Main purpose: applying markup. For a widget that returns foo, using fmt='cis'/s-/is' would give you 'cisoos'.)> To control what the widget outputs in the first place, use the format paramater of the widget (if it has one). font 'sans' Default from fontshadow Mone font shadow color, default is None(no shadow) fontsize None Font size. Calculated if None. foreground 'fffffff' Foreground colour format '(status_text){a Format of playback info {title}' hide_crash False Don't display error in bar if widget crashes on startup. max_chars 0 Maximum number of characters to display in widget. mouse_callbacks {} Don't display error in bar if widget crashes on startup. max_chars 0 Maximum number of characters to display in widget. play_color 'status_text}{format of playback info if no artist available. DEPRECATED Text colour when paused or stopped. Padding. Calculated if None. Pater Colour when playing. DEPRECATED Text colour when playing. DEPRECATED Text colour when playing. Text colour when playing. Text to display when playing, if chosen. Playing_color '00ff00' Text colour when playing. PLEVECATED Text to display when playing, paused, and stopped, if chosen. Playing_color '00ff00' Text colour when playing, if chosen. PLEVECATED Text to display when playing, paused, and stopped, if chosen. PLEVECATED Text to display when playing, paused, and stopped, if chosen. PLEVECATED Text to display when playing one text the widget's width. Whether text should be scrolled. When True, you must set the wid	key	default	description
direction 'default' Override the text direction in vertical bar, has no effect on text in horizontal bar.default: text displayed based on vertical bar position (left/right)tib: text read from top to bottom, bt: text read from bottom to top.'default', 'tb',' bt' fmt '{}' Format to apply to the string returned by the widget. Main purpose: applying markup. For a widget that returns foo, using fmt='<1>{} >√1>' would give you <1>foo 1 >. To control what the widget outputs in the first place, use the format paramater of the widget (if it has one). Font shadow None font shadow color, default is None(no shadow) fontsize None Font size. Calculated if None. Foreground colour Format of playback info. - {title}' hide_crash False Don't display error in bar if widget crashes on startup. max_chars 0 Maximum number of characters to display in widget. mouse_callbacks {} Dict of mouse button press callback functions. Accepts functions and lazy calls. no_artist_format '{status_text}{t} Format of playback info if no artist available. noplay_color 'ceecee' Text colour when paused or stopped. paused_color 'ceecee' Text colour when paused, if chosen. playing_color '0eff00' Text colour when palying. playing_color '90ff00' Text colour when playing. playing_color '0eff00' Text colour when playing. playing_color '1ext to display when playing, if chosen. playing_color '90ff00' Text colour when playing, if chosen. Prex to display when pla	background	None	Widget background color
pose: applying markup. For a widget that returns foo, using fmt='cis\3\cis\7\cis\ would give you ci>foo what the widget outputs in the first place, use the format paramater of the widget (if it has one). Font size None Font size. Calculated if None. Foreground 'fffffff' Foreground colour format '(status_text)\{a} Foreground colour format '(status_text)\{a} Foreground colour format '(status_text)\{a} Foreground colour Format of playback info. - {title}' hide_crash False Don't display error in bar if widget crashes on startup. max_chars 0 Maximum number of characters to display in widget. Dict of mouse button press callback functions. Accepts functions and lazy calls. no_artist_format '(status_text)\{f Format of playback info if no artist available. no_play_color ' padding None Padding. Calculated if None. Padding. Calculated if None. DEPRECATED Text colour when paused or stopped. DEPRECATED Text colour when paused or stopped. Padding. Calculated if None. DEPRECATED Text colour when playing. DEPRECATED Text to display when playing. Text to display when playing, fotosen. Playing_color 'Off00' Text colour when playing, fotosen. Totate True Rotate text in vertical bar. Scroll_clear False Whether text should be scrolled. When True, you must set the widget width. Scroll_delay 2 Number of seconds to pause before starting scrolling and restarting/clearing text at end Whether text should brown the widget will resize. Setting scroll_fixed_width False Whether text should restart scrolling once the text have a fixed width, regardless of the isz. Scroll_fixed_wid False Whether text should restart scrolling step Whether text should restart scrolling once the text	direction		Override the text direction in vertical bar, has no effect on text in horizontal bar.default: text displayed based on vertical bar position (left/right)ttb: text read from top to bottom, btt: text read from bottom to top.'default', 'ttb', 'btt'
fontshadow fontsize None Font shadow color, default is None(no shadow) fontsize None Font size. Calculated if None. foreground 'ffffff' Foreground colour format '{status_text}{a Format of playback info.	fmt	'{}'	pose: applying markup. For a widget that returns foo, using $fmt='{i>{i>}'}$ would give you ${i>}$ To control what the widget outputs in the first place, use the format para-
fontshadow fontsize None Font shadow color, default is None(no shadow) fontsize None Font size. Calculated if None. foreground 'ffffff' Foreground colour format '{status_text}{a} Format of playback info {title}' hide_crash False Don't display error in bar if widget crashes on startup. markup True Whether or not to use pango markup max_chars 0 Maximum number of characters to display in widget. Dict of mouse button press callback functions. Accepts functions and lazy calls. no_artist_format '{status_text}{t} Format of playback info if no artist available. DEPRECATED Text colour when paused or stopped. DEPRECATED Text colour when paused or stopped. Padding None Padding. Calculated if None. Paused_color 'cecece' Text color when paused, if chosen. Play_color '' DEPRECATED Text to display when playing. DEPRECATED Text to display when playing, paused, and stopped, if chosen. Playing_color '00ff00' Text colour when playing. Playing_text '' Text to display when playing, if chosen. Playing_text '' Text to display when playing, if chosen. True Rotate text in vertical bar. scroll_clear False Whether text should be scrolled. When True, you must set the widget's width. scroll_delay 2 Number of seconds to pause before starting scrolling and restarting/clearing text at end scroll_fixed_wid False Whether text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text. scroll_hide False Whether the widget should hide when scrolling has finished scroll_interval 0.1 Time in seconds before next scrolling text. scroll_step 1 Number of pixels to scroll with each step scroll_step 1 Number of pixels to scroll with each step stopped_color 'cecece' Text to display when stopped, if chosen. stream_format '{status_text}{s} Format of playback info for streams.	font	'sans'	
fontsize foreground format 'fffffff' format '(status_text){a	fontshadow	None	
foreground format '{status_text}{a} - {title}' Format of playback info {title}' hide_crash False Don't display error in bar if widget crashes on startup. Maximum number of characters to display in widget. Diet of mouse button press callback functions. Accepts functions and lazy calls. No_artist_format '{status_text}{t} Format of playback info if no artist available. DEPRECATED Text colour when paused or stopped. Padding None Padding. Calculated if None. Paused_color 'ceece' Text color when paused, if chosen. Play_color '' DEPRECATED Text to display when playing, paused, and stopped, if chosen. Play_color '' DEPRECATED Text to display when playing, paused, and stopped, if chosen. Playing_color '00ff00' Text colour when playing, if chosen. Playing_text ' Text to display when playing, if chosen. Playing_text '' Text to display when playing, if chosen. Playing_text '' Text to display when playing, if chosen. Rotate text in vertical bar. Scroll_clear False Whether text should be scrolled. When True, you must set the widget's width. Scroll_clear False Whether text should scroll completely away (True) or stop when the end of the text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text. Scroll_hide False Whether text should hide when scrolling has finished scroll_repeat True Whether text should restart scrolling step Scroll_step 1 Number of pixels to scroll with each step Stopped_color 'ceecee' Text to display when stopped, if chosen. **Text to display when stopped, if chosen.			
'status_text sa Format of playback info.			
Hide_crash	_		
markup True Whether or not to use pango markup max_chars 0 Maximum number of characters to display in widget. mouse_callbacks {} Dict of mouse button press callback functions. Accepts functions and lazy calls. no_artist_format '{status_text}{t Format of playback info if no artist available. noplay_color '' DEPRECATED Text colour when paused or stopped. padding None Padding. Calculated if None. paused_text '' Text to display when paused, if chosen. play_color '' DEPRECATED Text to display when playing. play_icon '' DEPRECATED Text to display when playing, paused, and stopped, if chosen. playing_color '00ff00' Text to display when playing, paused, and stopped, if chosen. playing_text '' Text to display when playing, for colour when playing, playing_text '' Text to display when playing, playing_text '' Text to display when playing, for colour when playing, playing_text '' Text to display when playing, for colour when playi	TOTIMA		Tornat of playouek line.
max_chars mouse_callbacks {} Dict of mouse button press callback functions. Accepts functions and lazy calls. no_artist_format noplay_color padding paused_color padding paused_text play_color play_color play_color padding paused_text play_color play_icon play_icon playing_color playing_color playing_text play_color playing_text play_icon playing_text play_icon playing_text play_icon playing_text play_icon playing_text play_icon playing_text play_icon playing_text play_icolor playing_text playing_	hide_crash	False	Don't display error in bar if widget crashes on startup.
mouse_callbacks no_artist_format '{status_text}{t Format of playback info if no artist available. noplay_color '' DEPRECATED Text colour when paused or stopped. padding None Padding. Calculated if None. paused_color 'cecece' Text color when paused, if chosen. play_color '' DEPRECATED Text to display when playing. play_color '' DEPRECATED Text to display when playing. play_icon '' DEPRECATED Text to display when playing, paused, and stopped, if chosen. playing_color '00ff00' Text colour when playing, if chosen. playing_text '' Text to display when playing, if chosen. rotate True Rotate text in vertical bar. scroll False Whether text should be scrolled. When True, you must set the widget's width. scroll_clear False Whether text should scroll completely away (True) or stop when the end of the text is shown (False) scroll_fixed_wid False When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text. scroll_hide False Whether the widget should hide when scrolling has finished scroll_interval scroll_repeat True Whether text should restart scrolling once the text has ended scroll_step 1 Number of pixels to scroll with each step stopped_clor' 'cecece' Text color when stopped, if chosen. stream_format '{status_text}{s} Format of playback info for streams.	markup	True	Whether or not to use pango markup
mouse_callbacks no_artist_format '{status_text}{t Format of playback info if no artist available. noplay_color '' DEPRECATED Text colour when paused or stopped. padding None Padding. Calculated if None. paused_color 'cecece' Text color when paused, if chosen. play_color '' DEPRECATED Text to display when playing. play_color '' DEPRECATED Text to display when playing. play_icon '' DEPRECATED Text to display when playing, paused, and stopped, if chosen. playing_color '00ff00' Text colour when playing, if chosen. playing_text '' Text to display when playing, if chosen. rotate True Rotate text in vertical bar. scroll False Whether text should be scrolled. When True, you must set the widget's width. scroll_clear False Whether text should scroll completely away (True) or stop when the end of the text is shown (False) scroll_fixed_wid False When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text. scroll_hide False Whether the widget should hide when scrolling has finished scroll_interval scroll_repeat True Whether text should restart scrolling once the text has ended scroll_step 1 Number of pixels to scroll with each step stopped_clor' 'cecece' Text color when stopped, if chosen. stream_format '{status_text}{s} Format of playback info for streams.	max_chars	0	Maximum number of characters to display in widget.
no_artist_format '{status_text}{t Format of playback info if no artist available. noplay_color ''' DEPRECATED Text colour when paused or stopped. padding None Padding. Calculated if None. paused_color 'cecece' Text color when paused, if chosen. play_color '' DEPRECATED Text to display when playing. play_icon '' DEPRECATED Text to display when playing, paused, and stopped, if chosen. playing_color '00ff00' Text to display when playing, paused, and stopped, if chosen. playing_text '' Text to display when playing, if chosen. rotate True Rotate text in vertical bar. scroll False Whether text should be scrolled. When True, you must set the widget's width. scroll_clear False Whether text should scroll completely away (True) or stop when the end of the text is shown (False) scroll_fixed_wid False When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_wid hregardless of the size of the text. scroll_hide False Whether the widget should hide when scrolling has finished scroll_repeat True Whether text should restart scrolling step scroll_step 1 Number of pixels to scroll with each step stopped_color 'cecece' Text color when stopped, if chosen. stream_format '{status_text}{s} Format of playback info for streams.	mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions
noplay_color padding None Padding. Calculated if None. paused_color 'cecece' Text color when paused. paused_text play_color ''' Text to display when paused, if chosen. play_color ''' DEPRECATED Text colour when playing. play_icon '' DEPRECATED Text to display when playing, paused, and stopped, if chosen. playing_color '00ff00' Text colour when playing. playing_text '' Text to display when playing, if chosen. rotate True Rotate text in vertical bar. scroll False Whether text should be scrolled. When True, you must set the widget's width. scroll_clear False Whether text should scroll completely away (True) or stop when the end of the text is shown (False) scroll_delay 2 Number of seconds to pause before starting scrolling and restarting/clearing text at end scroll_fixed_wid False Whether text should hide when scrolling and restarting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text. scroll_nide False Whether the widget should hide when scrolling has finished scroll_interval 0.1 Time in seconds before next scrolling once the text has ended scroll_step 1 Number of pixels to scroll with each step stopped_color 'cecece' Text color when stopped, if chosen. stream_format '{status_text}{s}	no_artist_format	'{status_text}{t	•
padding paused_color 'cecece' Text color when paused. paused_text ' ' Text to display when paused, if chosen. play_color '' DEPRECATED Text to display when playing. play_icon '' DEPRECATED Text to display when playing, paused, and stopped, if chosen. playing_color '00ff00' Text colour when playing, if chosen. playing_text ' ' Text to display when playing, if chosen. rotate True Rotate text in vertical bar. scroll False Whether text should be scrolled. When True, you must set the widget's width. scroll_clear False Whether text should scroll completely away (True) or stop when the end of the text is shown (False) scroll_delay 2 Number of seconds to pause before starting scrolling and restarting/clearing text at end scroll_fixed_wid False Whether text should hide when scrolling and restarting scroll_fixed_width_and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width_True will force the widget to have a fixed width, regardless of the size of the text. scroll_interval 0.1 Time in seconds before next scrolling step scroll_repeat True Whether text should restart scrolling once the text has ended scroll_step 1 Number of pixels to scroll with each step stopped_color 'cecece' Text color when stopped, if chosen. stream_format '{status_text}{s}			
paused_color 'cecece' Text color when paused. paused_text '' Text to display when paused, if chosen. play_color '' DEPRECATED Text colour when playing. play_icon 'DEPRECATED Text to display when playing, paused, and stopped, if chosen. playing_color '00ff00' Text colour when playing. playing_text '' Text to display when playing, if chosen. rotate True Rotate text in vertical bar. scroll False Whether text should be scrolled. When True, you must set the widget's width. scroll_clear False Whether text should scroll completely away (True) or stop when the end of the text is shown (False) scroll_delay 2 Number of seconds to pause before starting scrolling and restarting/clearing text at end scroll_fixed_wid False When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width. True will force the widget to have a fixed width, regardless of the size of the text. scroll_hide False Whether the widget should hide when scrolling has finished scroll_interval 0.1 Time in seconds before next scrolling step scroll_repeat True Whether text should restart scrolling once the text has ended scroll_step 1 Number of pixels to scroll with each step stopped_color 'cecece' Text color when stopped, stream_format '{status_text}{s} Format of playback info for streams.		None	
paused_text		'cecece'	
play_color			
playing_color '00ff00' Text colour when playing, frosen. playing_text ' Text to display when playing, if chosen. rotate True Rotate text in vertical bar. scroll False Whether text should be scrolled. When True, you must set the widget's width. scroll_clear False Whether text should scroll completely away (True) or stop when the end of the text is shown (False) scroll_delay 2 Number of seconds to pause before starting scrolling and restarting/clearing text at end scroll_fixed_wid False When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text. scroll_interval 0.1 Time in seconds before next scrolling step scroll_repeat True Whether text should restart scrolling once the text has ended scroll_step 1 Number of pixels to scroll with each step stopped_color 'cecece' Text color when stopped. stream_format '{status_text}{s} Format of playback info for streams.	-	11	
playing_color '00ff00' Text colour when playing. playing_text ' Text to display when playing, if chosen. rotate True Rotate text in vertical bar. scroll False Whether text should be scrolled. When True, you must set the widget's width. scroll_clear False Whether text should scroll completely away (True) or stop when the end of the text is shown (False) scroll_delay 2 Number of seconds to pause before starting scrolling and restarting/clearing text at end scroll_fixed_wid False When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text. scroll_hide False Whether the widget should hide when scrolling has finished scroll_interval 0.1 Time in seconds before next scrolling step scroll_repeat True Whether text should restart scrolling once the text has ended scroll_step 1 Number of pixels to scroll with each step stopped_color 'cecece' Text color when stopped. stopped_text ' ' Text to display when stopped, if chosen. stream_format '{status_text}{s} Format of playback info for streams.		1 1	DEPRECATED Text to display when playing, paused, and
playing_text ' ' Text to display when playing, if chosen. rotate True Rotate text in vertical bar. scroll False Whether text should be scrolled. When True, you must set the widget's width. scroll_clear False Whether text should scroll completely away (True) or stop when the end of the text is shown (False) scroll_delay 2 Number of seconds to pause before starting scrolling and restarting/clearing text at end scroll_fixed_wid False When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text. scroll_hide False Whether the widget should hide when scrolling has finished scroll_interval 0.1 Time in seconds before next scrolling step scroll_repeat True Whether text should restart scrolling once the text has ended scroll_step 1 Number of pixels to scroll with each step stopped_color 'cecece' Text color when stopped. stopped_text ' ' Text to display when stopped, if chosen. stream_format '{status_text}{s} Format of playback info for streams.	playing color	'00ff00'	**
rotate Scroll False Whether text should be scrolled. When True, you must set the widget's width. scroll_clear False Whether text should scroll completely away (True) or stop when the end of the text is shown (False) scroll_delay 2 Number of seconds to pause before starting scrolling and restarting/clearing text at end scroll_fixed_wid False When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text. scroll_hide False Whether the widget should hide when scrolling has finished scroll_interval 0.1 Time in seconds before next scrolling step scroll_repeat True Whether text should restart scrolling once the text has ended scroll_step 1 Number of pixels to scroll with each step stopped_color 'cecece' Text color when stopped. stopped_text ' ' Text to display when stopped, if chosen. stream_format '{status_text}{s} Format of playback info for streams.			
scroll_clear False Whether text should be scrolled. When True, you must set the widget's width. scroll_clear False Whether text should scroll completely away (True) or stop when the end of the text is shown (False) scroll_delay 2 Number of seconds to pause before starting scrolling and restarting/clearing text at end scroll_fixed_wid False When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text. scroll_hide False Whether the widget should hide when scrolling has finished scroll_interval 0.1 Time in seconds before next scrolling step scroll_repeat True Whether text should restart scrolling once the text has ended scroll_step 1 Number of pixels to scroll with each step stopped_color 'cecece' Text color when stopped. stopped_text ' ' Text to display when stopped, if chosen. stream_format '{status_text}{s} Format of playback info for streams.		True	
scroll_clear			
the end of the text is shown (False) scroll_delay 2 Number of seconds to pause before starting scrolling and restarting/clearing text at end scroll_fixed_wid False When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text. scroll_hide False Whether the widget should hide when scrolling has finished scroll_interval 0.1 Time in seconds before next scrolling step scroll_repeat True Whether text should restart scrolling once the text has ended scroll_step 1 Number of pixels to scroll with each step stopped_color 'cecece' Text color when stopped. stopped_text ' Text to display when stopped, if chosen. stream_format '{status_text}{s Format of playback info for streams.		P-1	· ·
ing/clearing text at end scroll_fixed_wid False When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text. scroll_hide False Whether the widget should hide when scrolling has finished scroll_interval 0.1 Time in seconds before next scrolling step scroll_repeat True Whether text should restart scrolling once the text has ended scroll_step 1 Number of pixels to scroll with each step stopped_color 'cecece' Text color when stopped. stopped_text ' ' Text to display when stopped, if chosen. stream_format '{status_text}{s Format of playback info for streams.			the end of the text is shown (False)
and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text. scroll_hide False Whether the widget should hide when scrolling has finished scroll_interval 0.1 Time in seconds before next scrolling step scroll_repeat True Whether text should restart scrolling once the text has ended scroll_step 1 Number of pixels to scroll with each step stopped_color 'cecece' Text color when stopped. stopped_text ' ' Text to display when stopped, if chosen. stream_format '{status_text}{s Format of playback info for streams.	scroll_delay	2	ing/clearing text at end
scroll_interval 0.1 Time in seconds before next scrolling step scroll_repeat True Whether text should restart scrolling once the text has ended scroll_step 1 Number of pixels to scroll with each step stopped_color 'cecece' Text color when stopped. stopped_text ' Text to display when stopped, if chosen. stream_format '{status_text}{s Format of playback info for streams.	scroll_fixed_wid	False	and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have
scroll_interval 0.1 Time in seconds before next scrolling step scroll_repeat True Whether text should restart scrolling once the text has ended scroll_step 1 Number of pixels to scroll with each step stopped_color 'cecece' Text color when stopped. stopped_text ' Text to display when stopped, if chosen. stream_format '{status_text}{s Format of playback info for streams.	scroll_hide	False	Whether the widget should hide when scrolling has finished
scroll_repeat True Whether text should restart scrolling once the text has ended scroll_step 1 Number of pixels to scroll with each step stopped_color 'cecece' Text color when stopped. stopped_text ' ' Text to display when stopped, if chosen. stream_format '{status_text}{s Format of playback info for streams.	scroll_interval	0.1	
scroll_step 1 Number of pixels to scroll with each step stopped_color 'cecece' Text color when stopped. stopped_text ' Text to display when stopped, if chosen. stream_format '{status_text}{s Format of playback info for streams.	scroll_repeat	True	
stopped_color 'cecece' Text color when stopped. stopped_text ' Text to display when stopped, if chosen. stream_format '{status_text}{s Format of playback info for streams.	_	1	-
stopped_text ' Text to display when stopped, if chosen. stream_format '{status_text}{s Format of playback info for streams.		'cecece'	
stream_format '{status_text}{s Format of playback info for streams.		1 1	
· · · · · · · · · · · · · · · · · · ·		'{status_text}{s	
	update_interval		Update Time in seconds.

8.14. Cmus 113

Click to view the available commands for Cmus

8.15 Countdown

class libqtile.widget.Countdown(*args, **kwargs)

A simple countdown timer text widget

Supported bar orientations: horizontal and vertical

key	default	description
background	None	Widget background color
date	datetime. datetime(2025, 7, 25, 20, 10, 56, 689855)	The datetime for the end of the countdown
direction	'default'	Override the text direction in vertical bar, has no effect on text in horizontal bar.default: text displayed based on vertical bar position (left/right)ttb: text read from top to bottom, btt: text read from bottom to top.'default', 'ttb', 'btt'
fmt	'{}'	Format to apply to the string returned by the widget. Main purpose: applying markup. For a widget that returns foo, using fmt=' <i>{}</i> ' would give you <i>foo</i> . To control what the widget outputs in the first place, use the format paramater of the widget (if it has one).
font	'sans'	Default font
fontshadow	None	font shadow color, default is None(no shadow)
fontsize	None	Font size. Calculated if None.
foreground	'ffffff'	Foreground colour
format	'{D}d {H}h {M}m {S}s'	Format of the displayed text. Available variables: $\{D\}$ == days, $\{H\}$ == hours, $\{M\}$ == minutes, $\{S\}$ seconds.
hide_crash	False	Don't display error in bar if widget crashes on startup.
markup	True	Whether or not to use pango markup
max_chars	0	Maximum number of characters to display in widget.
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions and lazy calls.
padding	None	Padding. Calculated if None.
rotate	True	Rotate text in vertical bar.
scroll	False	Whether text should be scrolled. When True, you must set the widget's width.
scroll_clear	False	Whether text should scroll completely away (True) or stop when the end of the text is shown (False)
scroll_delay	2	Number of seconds to pause before starting scrolling and restarting/clearing text at end
scroll_fixed_wid	False	When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text.
scroll_hide	False	Whether the widget should hide when scrolling has finished
scroll_interval	0.1	Time in seconds before next scrolling step
scroll_repeat	True	Whether text should restart scrolling once the text has ended
scroll_step	1	Number of pixels to scroll with each step
update_interval	1.0	Update interval in seconds for the clock

Click to view the available commands for Countdown

8.15. Countdown 115

8.16 CryptoTicker

class libqtile.widget.CryptoTicker(*args, **kwargs)

A cryptocurrency ticker widget, data provided by the coinbase.com or the binance.com API. Defaults to displaying currency in whatever the current locale is. Examples:

- # display the average price of bitcoin in local currency widget.CryptoTicker()
- # display it in Euros: widget.CryptoTicker(currency="EUR")
- # or a different cryptocurrency! widget.CryptoTicker(crypto="ETH")
- # change the currency symbol: widget.CryptoTicker(currency="EUR", symbol="€")
- # display from Binance API widget.CryptoTicker(api="binance", currency="USDT")

Supported bar orientations: horizontal and vertical

Configuration options

key	default	description
api	'coinbase'	API that provides the data.
background	None	Widget background color
crypto	'BTC'	The cryptocurrency to display.
currency	11	The baseline currency that the value of the crypto is displayed in.
data	None	Post Data
direction	'default'	Override the text direction in vertical bar, has no effect on text in horizontal bar.default: text displayed based on vertical bar position (left/right)ttb: text read from top to bottom, btt: text read from bottom to top.'default', 'ttb', 'btt'
fmt	' {}'	Format to apply to the string returned by the widget. Main purpose: applying markup. For a widget that returns foo, using fmt=' <i>{}</i> ' would give you <i>foo</i> . To control what the widget outputs in the first place, use the format paramater of the widget (if it has one).
font	'sans'	Default font
fontshadow	None	font shadow color, default is None(no shadow)
fontsize	None	Font size. Calculated if None.
foreground	'ffffff'	Foreground colour
format	'{crypto}: {symbol}{amount: 2f}'	Display string formatting.
headers	{}	Extra Headers
hide_crash	False	Don't display error in bar if widget crashes on startup.
json	True	Is Json?
markup	True	Whether or not to use pango markup
max_chars	0	Maximum number of characters to display in widget.
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions and lazy calls.
padding	None	Padding. Calculated if None.
parse	None	Parse Function
rotate	True	Rotate text in vertical bar.
scroll	False	Whether text should be scrolled. When True, you must set the widget's width.

continues on next page

Table 5 – continued from previous page

key	default	description
scroll_clear	False	Whether text should scroll completely away (True) or stop when the end of the text is shown (False)
scroll_delay	2	Number of seconds to pause before starting scrolling and restart- ing/clearing text at end
scroll_fixed_wid	False	When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text.
scroll_hide	False	Whether the widget should hide when scrolling has finished
scroll_interval	0.1	Time in seconds before next scrolling step
scroll_repeat	True	Whether text should restart scrolling once the text has ended
scroll_step	1	Number of pixels to scroll with each step
symbol	11	The symbol for the baseline currency.
update_interval	600	Update interval in seconds, if none, the widget updates only once.
url	None	Url
user_agent	'Qtile'	Set the user agent
xml	False	Is XML?

Click to view the available commands for CryptoTicker

8.17 CurrentLayout

class libqtile.widget.CurrentLayout(*args, **kwargs)

Display the icon or the name of the current layout of the current group of the screen on which the bar containing the widget is.

If you are using custom layouts, a default icon with question mark will be displayed for them. If you want to use custom icon for your own layout, for example, *FooGrid*, then create a file named "layout-foogrid.png" and place it in ~/.icons directory. You can as well use other directories, but then you need to specify those directories in custom_icon_paths argument for this plugin.

The widget will look for icons with a png or svg extension.

The order of icon search is:

- dirs in custom_icon_paths config argument
- ~/.icons
- built-in qtile icons

Supported bar orientations: horizontal and vertical

Configuration options

8.17. CurrentLayout 117

key	default	description
background	None	Widget background color
custom_icon_path	[]	List of folders where to search icons beforeusing built-in icons or icons in ~/.icons dir. This can also be used to providemissing icons for custom layouts. Defaults to empty list.
direction	'default'	Override the text direction in vertical bar, has no effect on text in horizontal bar.default: text displayed based on vertical bar position (left/right)ttb: text read from top to bottom, btt: text read from bottom to top.'default', 'ttb', 'btt'
fmt	'{}'	Format to apply to the string returned by the widget. Main purpose: applying markup. For a widget that returns foo, using fmt=' <i>{}</i> ' would give you <i>foo</i> . To control what the widget outputs in the first place, use the format paramater of the widget (if it has one).
font	'sans'	Default font
fontshadow	None	font shadow color, default is None(no shadow)
fontsize	None	Font size. Calculated if None.
foreground	'ffffff'	Foreground colour
hide_crash	False	Don't display error in bar if widget crashes on startup.
icon_first	False	Should draw icon or text when bar is initialized.
markup	True	Whether or not to use pango markup
max_chars	0	Maximum number of characters to display in widget.
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions and lazy calls.
padding	None	Padding. Calculated if None.
rotate	True	Rotate text in vertical bar.
scale	1	Scale factor relative to the bar height. Defaults to 1
scroll	False	Whether text should be scrolled. When True, you must set the widget's width.
scroll_clear	False	Whether text should scroll completely away (True) or stop when the end of the text is shown (False)
scroll_delay	2	Number of seconds to pause before starting scrolling and restarting/clearing text at end
scroll_fixed_wid	False	When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text.
scroll_hide	False	Whether the widget should hide when scrolling has finished
scroll_interval	0.1	Time in seconds before next scrolling step
scroll_repeat	True	Whether text should restart scrolling once the text has ended
scroll_step	1	Number of pixels to scroll with each step

Click to view the available commands for CurrentLayout

8.18 CurrentScreen

class libqtile.widget.CurrentScreen(*args, **kwargs)

Indicates whether the screen this widget is on is currently active or not

Supported bar orientations: horizontal and vertical

Configuration options

key	default	description
active_color	'00ff00'	Color when screen is active
active_text	'A'	Text displayed when the screen is active
background	None	Widget background color
direction	'default'	Override the text direction in vertical bar, has no effect on text in horizontal bar.default: text displayed based on vertical bar position (left/right)ttb: text read from top to bottom, btt: text read from bottom to top.'default', 'ttb', 'btt'
fmt	'{}'	Format to apply to the string returned by the widget. Main purpose: applying markup. For a widget that returns foo, using fmt=' <i>{}</i> ' would give you <i>foo</i> . To control what the widget outputs in the first place, use the format paramater of the widget (if it has one).
font	'sans'	Default font
fontshadow	None	font shadow color, default is None(no shadow)
fontsize	None	Font size. Calculated if None.
foreground	'ffffff'	Foreground colour
hide_crash	False	Don't display error in bar if widget crashes on startup.
inactive_color	'ff0000'	Color when screen is inactive
inactive_text	'I'	Text displayed when the screen is inactive
markup	True	Whether or not to use pango markup
max_chars	0	Maximum number of characters to display in widget.
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions and lazy calls.
padding	None	Padding. Calculated if None.
rotate	True	Rotate text in vertical bar.
scroll	False	Whether text should be scrolled. When True, you must set the widget's width.
scroll_clear	False	Whether text should scroll completely away (True) or stop when the end of the text is shown (False)
scroll_delay	2	Number of seconds to pause before starting scrolling and restarting/clearing text at end
scroll_fixed_wid	False	When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text.
scroll_hide	False	Whether the widget should hide when scrolling has finished
scroll_interval	0.1	Time in seconds before next scrolling step
scroll_repeat	True	Whether text should restart scrolling once the text has ended
scroll_step	1	Number of pixels to scroll with each step

Available commands

Click to view the available commands for CurrentScreen

8.18. CurrentScreen 119

8.19 DF

class libqtile.widget.DF(*args, **kwargs)

Disk Free Widget

By default the widget only displays if the space is less than warn_space.

Supported bar orientations: horizontal and vertical

key	default	description
background	None	Widget background color
direction	'default'	Override the text direction in vertical bar, has no effect on text in horizontal bar.default: text displayed based on vertical bar position (left/right)ttb: text read from top to bottom, btt: text read from bottom to top.'default', 'ttb', 'btt'
fmt	'{}'	Format to apply to the string returned by the widget. Main purpose: applying markup. For a widget that returns foo, using fmt=' <i>{}</i> ' would give you <i>foo</i> . To control what the widget outputs in the first place, use the format paramater of the widget (if it has one).
font	'sans'	Default font
fontshadow	None	font shadow color, default is None(no shadow)
fontsize	None	Font size. Calculated if None.
foreground	'ffffff'	Foreground colour
format	'{p} ({uf}{m} {r:. 0f}%)'	String format (p: partition, s: size, f: free space, uf: user free space, m: measure, r: ratio (uf/s))
hide_crash	False	Don't display error in bar if widget crashes on startup.
markup	True	Whether or not to use pango markup
max_chars	0	Maximum number of characters to display in widget.
measure	'G'	Measurement (G, M, B)
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions and lazy calls.
padding	None	Padding. Calculated if None.
partition	'/'	the partition to check space
rotate	True	Rotate text in vertical bar.
scroll	False	Whether text should be scrolled. When True, you must set the widget's width.
scroll_clear	False	Whether text should scroll completely away (True) or stop when the end of the text is shown (False)
scroll_delay	2	Number of seconds to pause before starting scrolling and restart- ing/clearing text at end
scroll_fixed_wid	False	When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text.
scroll_hide	False	Whether the widget should hide when scrolling has finished
scroll_interval	0.1	Time in seconds before next scrolling step
scroll_repeat	True	Whether text should restart scrolling once the text has ended
scroll_step	1	Number of pixels to scroll with each step
update_interval	60	The update interval.
visible_on_warn	True	Only display if warning
warn_color	'ff0000'	Warning color
warn_space	2	Warning space in scale defined by the measure option.

Click to view the available commands for DF

8.19. DF 121

8.20 DoNotDisturb

class libqtile.widget.DoNotDisturb(*args, **kwargs)

Displays Do Not Disturb status for notification server Dunst by default. Can be used with other servers by changing the poll command and mouse callbacks.

Supported bar orientations: horizontal and vertical

key	default	description
background	None	Widget background color
direction	'default'	Override the text direction in vertical bar, has no effect on text in horizontal bar.default: text displayed based on vertical bar position (left/right)ttb: text read from top to bottom, btt: text read from bottom to top.'default', 'ttb', 'btt'
disabled_icon	'0'	Icon that displays when do not disturb is disabled
enabled_icon	'X'	Icon that displays when do not disturb is enabled
fmt	'{}'	Format to apply to the string returned by the widget. Main purpose: applying markup. For a widget that returns foo, using fmt=' <i>{}</i> ' would give you <i>foo</i> . To control what the widget outputs in the first place, use the format paramater of the widget (if it has one).
font	'sans'	Default font
fontshadow	None	font shadow color, default is None(no shadow)
fontsize	None	Font size. Calculated if None.
foreground	'ffffff'	Foreground colour
hide_crash	False	Don't display error in bar if widget crashes on startup.
markup	True	Whether or not to use pango markup
max_chars	0	Maximum number of characters to display in widget.
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions and lazy calls.
padding	None	Padding. Calculated if None.
poll_function	None	Function that returns the notification server status. Define the function on your configuration file and pass it like poll_function=my_func. Must return either true or false
rotate	True	Rotate text in vertical bar.
scroll	False	Whether text should be scrolled. When True, you must set the widget's width.
scroll_clear	False	Whether text should scroll completely away (True) or stop when the end of the text is shown (False)
scroll_delay	2	Number of seconds to pause before starting scrolling and restarting/clearing text at end
scroll_fixed_wid	False	When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text.
scroll_hide	False	Whether the widget should hide when scrolling has finished
scroll_interval	0.1	Time in seconds before next scrolling step
scroll_repeat	True	Whether text should restart scrolling once the text has ended
scroll_step	1	Number of pixels to scroll with each step
update_interval	1	How often in seconds the text must update

Click to view the available commands for <code>DoNotDisturb</code>

8.21 GenPollCommand

class libqtile.widget.GenPollCommand(*args, **kwargs)

A generic text widget to display output from scripts or shell commands

Supported bar orientations: horizontal and vertical

Configuration options

8.21. GenPollCommand

key	default	description
background	None	Widget background color
cmd	None	command line as a string or list of arguments to execute
direction	'default'	Override the text direction in vertical bar, has no effect on text
		in horizontal bar.default: text displayed based on vertical bar po-
		sition (left/right)ttb: text read from top to bottom, btt: text read
		from bottom to top.'default', 'ttb', 'btt'
fmt	'{}'	Format to apply to the string returned by the widget. Main purpose: applying markup. For a widget that returns foo, using fmt=' <i>{i>{}</i> ' would give you <i>foo</i> . To control what the widget outputs in the first place, use the format para-
		mater of the widget (if it has one).
font	'sans'	Default font
fontshadow	None	font shadow color, default is None(no shadow)
fontsize	None	Font size. Calculated if None.
foreground	'ffffff'	Foreground colour
hide_crash	False	Don't display error in bar if widget crashes on startup.
markup	True	Whether or not to use pango markup
max_chars	0	Maximum number of characters to display in widget.
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions and lazy calls.
padding	None	Padding. Calculated if None.
parse	None	Function to parse output of command
rotate	True	Rotate text in vertical bar.
scroll	False	Whether text should be scrolled. When True, you must set the widget's width.
scroll_clear	False	Whether text should scroll completely away (True) or stop when the end of the text is shown (False)
scroll_delay	2	Number of seconds to pause before starting scrolling and restarting/clearing text at end
scroll_fixed_wid	False	When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text.
scroll_hide	False	Whether the widget should hide when scrolling has finished
scroll_interval	0.1	Time in seconds before next scrolling step
scroll_repeat	True	Whether text should restart scrolling once the text has ended
scroll_step	1	Number of pixels to scroll with each step
shell	False	run command through shell to enable piping and shell expansion
update_interval	60	update time in seconds

Click to view the available commands for GenPollCommand

8.22 GenPollText

class libqtile.widget.GenPollText(*args, **kwargs)

A generic text widget that polls using poll function to get the text

Supported bar orientations: horizontal and vertical

Configuration options

key	default	description
background	None	Widget background color
direction	'default'	Override the text direction in vertical bar, has no effect on text in horizontal bar.default: text displayed based on vertical bar position (left/right)ttb: text read from top to bottom, btt: text read from bottom to top.'default', 'ttb', 'btt'
fmt	'{}'	Format to apply to the string returned by the widget. Main purpose: applying markup. For a widget that returns foo, using fmt=' <i>{}</i> ' would give you <i>foo</i> . To control what the widget outputs in the first place, use the format paramater of the widget (if it has one).
font	'sans'	Default font
fontshadow	None	font shadow color, default is None(no shadow)
fontsize	None	Font size. Calculated if None.
foreground	'ffffff'	Foreground colour
func	None	Poll Function
hide_crash	False	Don't display error in bar if widget crashes on startup.
markup	True	Whether or not to use pango markup
max_chars	0	Maximum number of characters to display in widget.
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions and lazy calls.
padding	None	Padding. Calculated if None.
rotate	True	Rotate text in vertical bar.
scroll	False	Whether text should be scrolled. When True, you must set the widget's width.
scroll_clear	False	Whether text should scroll completely away (True) or stop when the end of the text is shown (False)
scroll_delay	2	Number of seconds to pause before starting scrolling and restarting/clearing text at end
scroll_fixed_wid	False	When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text.
scroll_hide	False	Whether the widget should hide when scrolling has finished
scroll_interval	0.1	Time in seconds before next scrolling step
scroll_repeat	True	Whether text should restart scrolling once the text has ended
scroll_step	1	Number of pixels to scroll with each step
update_interval	600	Update interval in seconds, if none, the widget updates only once.

Available commands

Click to view the available commands for GenPollText

8.22. GenPollText 125

8.23 GenPollUrl

class libqtile.widget.GenPollUrl(*args, **kwargs)

A generic text widget that polls an url and parses it using parse function

Supported bar orientations: horizontal and vertical

key	default	description
background	None	Widget background color
data	None	Post Data
direction	'default'	Override the text direction in vertical bar, has no effect on text in horizontal bar.default: text displayed based on vertical bar position (left/right)ttb: text read from top to bottom, btt: text read from bottom to top.'default', 'ttb', 'btt'
fmt	'{}'	Format to apply to the string returned by the widget. Main purpose: applying markup. For a widget that returns foo, using fmt=' <i>{}</i> ' would give you <i>foo</i> . To control what the widget outputs in the first place, use the format paramater of the widget (if it has one).
font	'sans'	Default font
fontshadow	None	font shadow color, default is None(no shadow)
fontsize	None	Font size. Calculated if None.
foreground	'ffffff'	Foreground colour
headers	{}	Extra Headers
hide_crash	False	Don't display error in bar if widget crashes on startup.
json	True	Is Json?
markup	True	Whether or not to use pango markup
max_chars	0	Maximum number of characters to display in widget.
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions and lazy calls.
padding	None	Padding. Calculated if None.
parse	None	Parse Function
rotate	True	Rotate text in vertical bar.
scroll	False	Whether text should be scrolled. When True, you must set the widget's width.
scroll_clear	False	Whether text should scroll completely away (True) or stop when the end of the text is shown (False)
scroll_delay	2	Number of seconds to pause before starting scrolling and restarting/clearing text at end
scroll_fixed_wid	False	When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text.
scroll_hide	False	Whether the widget should hide when scrolling has finished
scroll_interval	0.1	Time in seconds before next scrolling step
scroll_repeat	True	Whether text should restart scrolling once the text has ended
scroll_step	1	Number of pixels to scroll with each step
update_interval	600	Update interval in seconds, if none, the widget updates only once.
url	None	Url
user_agent	'Qtile'	Set the user agent
xml	False	Is XML?

Click to view the available commands for GenPollUr1

8.24 GmailChecker

class libqtile.widget.GmailChecker(*args, **kwargs)

A simple gmail checker. If 'status_only_unseen' is True - set 'fmt' for one argument, ex. 'unseen: {0}'

Supported bar orientations: horizontal and vertical

Configuration options

8.24. GmailChecker 127

key	default	description
background	None	Widget background color
direction	'default'	Override the text direction in vertical bar, has no effect on text in horizontal bar.default: text displayed based on vertical bar position (left/right)ttb: text read from top to bottom, btt: text read from bottom to top.'default', 'ttb', 'btt'
display_fmt	'inbox[{0}], unseen[{1}]'	Display format
email_path	'INBOX'	email_path
fmt	'{}'	Format to apply to the string returned by the widget. Main purpose: applying markup. For a widget that returns foo, using fmt=' <i>{}</i> ' would give you <i>foo</i> . To control what the widget outputs in the first place, use the format paramater of the widget (if it has one).
font	'sans'	Default font
fontshadow	None	font shadow color, default is None(no shadow)
fontsize	None	Font size. Calculated if None.
foreground	'ffffff'	Foreground colour
hide_crash	False	Don't display error in bar if widget crashes on startup.
markup	True	Whether or not to use pango markup
max_chars	0	Maximum number of characters to display in widget.
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions and lazy calls.
padding	None	Padding. Calculated if None.
password	None	password
rotate	True	Rotate text in vertical bar.
scroll	False	Whether text should be scrolled. When True, you must set the widget's width.
scroll_clear	False	Whether text should scroll completely away (True) or stop when the end of the text is shown (False)
scroll_delay	2	Number of seconds to pause before starting scrolling and restarting/clearing text at end
scroll_fixed_wid	False	When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text.
scroll_hide	False	Whether the widget should hide when scrolling has finished
scroll_interval	0.1	Time in seconds before next scrolling step
scroll_repeat	True	Whether text should restart scrolling once the text has ended
scroll_step	1	Number of pixels to scroll with each step
status_only_unse	False	Only show unseen messages
update_interval	30	Update time in seconds.
username	None	username

Click to view the available commands for GmailChecker

8.25 GroupBox

class libqtile.widget.GroupBox(*args, **kwargs)

A widget that graphically displays the current group. All groups are displayed by their label. If the label of a group is the empty string that group will not be displayed.

Supported bar orientations: horizontal only

Configuration options

key	default	description
active	'FFFFFF'	Active group font colour
background	None	Widget background color
block_highlight_	None	Selected group font colour
borderwidth	3	Current group border width
center_aligned	True	center-aligned group box
direction	'default'	Override the text direction in vertical bar, has no effect on text in horizontal bar.default: text displayed based on vertical bar position (left/right)ttb: text read from top to bottom, btt: text read from bottom to top.'default', 'ttb', 'btt'
disable_drag	False	Disable dragging and dropping of group names on widget
fmt	'{}'	Format to apply to the string returned by the widget. Main purpose: applying markup. For a widget that returns foo, using fmt=' <i>{}</i> ' would give you <i>foo</i> . To control what the widget outputs in the first place, use the format paramater of the widget (if it has one).
font	'sans'	Default font
fontshadow	None	font shadow color, default is None(no shadow)
fontsize	None	Font size. Calculated if None.
foreground	'ffffff'	Foreground colour
hide_crash	False	Don't display error in bar if widget crashes on startup.
hide_unused	False	Hide groups that have no windows and that are not displayed on any screen.
highlight_color	['000000', '282828']	Active group highlight color when using 'line' highlight method.
highlight_method	'border'	Method of highlighting ('border', 'block', 'text', or 'line')Uses *_border color settings
inactive	'404040'	Inactive group font colour
invert_mouse_whe	False	Whether to invert mouse wheel group movement
margin	3	Margin inside the box
margin_x	None	X Margin. Overrides 'margin' if set
margin_y	None	Y Margin. Overrides 'margin' if set
markup	False	Whether or not to use pango markup
max_chars	0	Maximum number of characters to display in widget.
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions and lazy calls.
other_current_sc	'404040'	Border or line colour for group on other screen when focused.
other_screen_bor	'404040'	Border or line colour for group on other screen when unfocused.
padding	None	Padding. Calculated if None.
padding_x	None	X Padding. Overrides 'padding' if set
padding_y	None	Y Padding. Overrides 'padding' if set
rotate	True	Rotate text in vertical bar.

continues on next page

8.25. GroupBox 129

Table 6 – continued from previous page

key	default	description
rounded	True	To round or not to round box borders
scroll	False	Whether text should be scrolled. When True, you must set the widget's width.
scroll_clear	False	Whether text should scroll completely away (True) or stop when the end of the text is shown (False)
scroll_delay	2	Number of seconds to pause before starting scrolling and restart- ing/clearing text at end
scroll_fixed_wid	False	When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text.
scroll_hide	False	Whether the widget should hide when scrolling has finished
scroll_interval	0.1	Time in seconds before next scrolling step
scroll_repeat	True	Whether text should restart scrolling once the text has ended
scroll_step	1	Number of pixels to scroll with each step
spacing	None	Spacing between groups(if set to None, will be equal to margin_x)
this_current_scr	'215578'	Border or line colour for group on this screen when focused.
this_screen_bord	'215578'	Border or line colour for group on this screen when unfocused.
toggle	True	Enable toggling of group when clicking on same group name
urgent_alert_met	'border'	Method for alerting you of WM urgent hints (one of 'border', 'text', 'block', or 'line')
urgent_border	'FF0000'	Urgent border or line color
urgent_text	'FF0000'	Urgent group font color
use_mouse_wheel	True	Whether to use mouse wheel events
visible_groups	None	Groups that will be visible. If set to None or [], all groups will be visible. Visible groups are identified by name not by their displayed label.

Click to view the available commands for *GroupBox*

8.26 HDD

class libqtile.widget.HDD(*args, **kwargs)

Displays HDD usage in percent based on the number of milliseconds the device has been performing I/O operations.

Supported bar orientations: horizontal and vertical

key	default	description
background	None	Widget background color
device	'sda'	Block device to monitor (e.g. sda)
direction	'default'	Override the text direction in vertical bar, has no effect on text
direction	uciuuic	in horizontal bar.default: text displayed based on vertical bar po-
		sition (left/right)ttb: text read from top to bottom, btt: text read
		from bottom to top.'default', 'ttb', 'btt'
fmt	'{}'	Format to apply to the string returned by the widget. Main pur-
		pose: applying markup. For a widget that returns foo, using
		<pre>fmt='<i>{}</i>' would give you <i>foo</i>. To control</pre>
		what the widget outputs in the first place, use the format para-
		mater of the widget (if it has one).
font	'sans'	Default font
fontshadow	None	font shadow color, default is None(no shadow)
fontsize	None	Font size. Calculated if None.
foreground	'ffffff'	Foreground colour
format	'HDD	HDD display format
, , ,	{HDDPercent}%'	
hide_crash	False	Don't display error in bar if widget crashes on startup.
markup max_chars	True	Whether or not to use pango markup
max_cnars mouse_callbacks	0 {}	Maximum number of characters to display in widget.
mouse_callbacks	13	Dict of mouse button press callback functions. Accepts functions and lazy calls.
padding	None	Padding. Calculated if None.
rotate	True	Rotate text in vertical bar.
scroll	False	Whether text should be scrolled. When True, you must set the
501011	14150	widget's width.
scroll_clear	False	Whether text should scroll completely away (True) or stop when
		the end of the text is shown (False)
scroll_delay	2	Number of seconds to pause before starting scrolling and restart-
		ing/clearing text at end
scroll_fixed_wid	False	When scroll=True the width parameter is a maximum width
		and, when text is shorter than this, the widget will resize. Set-
		ting scroll_fixed_width=True will force the widget to have
		a fixed width, regardless of the size of the text.
scroll_hide	False	Whether the widget should hide when scrolling has finished
scroll_interval	0.1	Time in seconds before next scrolling step
scroll_repeat	True	Whether text should restart scrolling once the text has ended
scroll_step	1	Number of pixels to scroll with each step
update_interval	600	Update interval in seconds, if none, the widget updates only once.

Click to view the available commands for HDD

8.26. HDD 131

8.27 HDDBusyGraph

class libqtile.widget.HDDBusyGraph(*args, **kwargs)

Display HDD busy time graph

Parses /sys/block/<dev>/stat file and extracts overall device IO usage, based on io_ticks's value. See https://www.kernel.org/doc/Documentation/block/stat.txt

Supported bar orientations: horizontal only

Configuration options

key	default	description
background	None	Widget background color
border_color	'215578'	Widget border color
border_width	2	Widget border width
device	'sda'	Block device to display info for
fill_color	'1667EB.3'	Fill color for linefill graph
frequency	1	Update frequency in seconds
graph_color	'18BAEB'	Graph color
hide_crash	False	Don't display error in bar if widget crashes on startup.
line_width	3	Line width
margin_x	3	Margin X
margin_y	3	Margin Y
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions and lazy calls.
samples	100	Count of graph samples.
start_pos	'bottom'	Drawer starting position ('bottom'/'top')
type	'linefill'	'box', 'line', 'linefill'

Available commands

Click to view the available commands for HDDBusyGraph

8.28 HDDGraph

class libqtile.widget.HDDGraph(*args, **kwargs)

Display HDD free or used space graph

Supported bar orientations: horizontal only

key	default	description
background	None	Widget background color
border_color	'215578'	Widget border color
border_width	2	Widget border width
fill_color	'1667EB.3'	Fill color for linefill graph
frequency	1	Update frequency in seconds
graph_color	'18BAEB'	Graph color
hide_crash	False	Don't display error in bar if widget crashes on startup.
line_width	3	Line width
margin_x	3	Margin X
margin_y	3	Margin Y
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions
		and lazy calls.
path	'/'	Partition mount point.
samples	100	Count of graph samples.
space_type	'used'	free/used
start_pos	'bottom'	Drawer starting position ('bottom'/'top')
type	'linefill'	'box', 'line', 'linefill'

Click to view the available commands for HDDGraph

8.29 IdleRPG

class libqtile.widget.IdleRPG(*args, **kwargs)

A widget for monitoring and displaying IdleRPG stats.

```
# display idlerpg stats for the player 'pants' on freenode's #idlerpg
widget.IdleRPG(url="http://xethron.lolhosting.net/xml.php?player=pants")
```

Widget requirements: xmltodict.

Supported bar orientations: horizontal and vertical

Configuration options

key	default	description
background	None	Widget background color
data	None	Post Data
direction	'default'	Override the text direction in vertical bar, has no effect on text in horizontal bar.default: text displayed based on vertical bar position (left/right)ttb: text read from top to bottom, btt: text read from bottom to top.'default', 'ttb', 'btt'
fmt	'{}'	Format to apply to the string returned by the widget. Main purpose: applying markup. For a widget that returns foo, using fmt=' <i>{}</i> ' would give you <i>foo</i> . To control what the widget outputs in the first place, use the format paramater of the widget (if it has one).
font	'sans'	Default font

continues on next page

8.29. IdleRPG 133

Table 7 – continued from previous page

key	default	description
fontshadow	None	font shadow color, default is None(no shadow)
fontsize	None	Font size. Calculated if None.
foreground	'ffffff'	Foreground colour
format	'IdleRPG: {online} TTL: {ttl}'	Display format
headers	{}	Extra Headers
hide_crash	False	Don't display error in bar if widget crashes on startup.
json	True	Is Json?
markup	True	Whether or not to use pango markup
max_chars	0	Maximum number of characters to display in widget.
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions and lazy calls.
padding	None	Padding. Calculated if None.
parse	None	Parse Function
rotate	True	Rotate text in vertical bar.
scroll	False	Whether text should be scrolled. When True, you must set the widget's width.
scroll_clear	False	Whether text should scroll completely away (True) or stop when the end of the text is shown (False)
scroll_delay	2	Number of seconds to pause before starting scrolling and restarting/clearing text at end
scroll_fixed_wid		When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text.
scroll_hide	False	Whether the widget should hide when scrolling has finished
scroll_interval	0.1	Time in seconds before next scrolling step
scroll_repeat	True	Whether text should restart scrolling once the text has ended
scroll_step	1	Number of pixels to scroll with each step
update_interval	600	Update interval in seconds, if none, the widget updates only once.
url	None	Url
user_agent	'Qtile'	Set the user agent
xml	False	Is XML?

Click to view the available commands for IdleRPG

8.30 Image

class libqtile.widget.Image(*args, **kwargs)

Display a PNG image on the bar

Supported bar orientations: horizontal and vertical

key	default	description
background	None	Widget background color
filename	None	Image filename. Can contain '~'
hide_crash	False	Don't display error in bar if widget crashes on startup.
margin	3	Margin inside the box
margin_x	None	X Margin. Overrides 'margin' if set
margin_y	None	Y Margin. Overrides 'margin' if set
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions
		and lazy calls.
rotate	0.0	rotate the image in degrees counter-clockwise
scale	True	Enable/Disable image scaling

Click to view the available commands for Image

8.31 ImapWidget

```
class libqtile.widget.ImapWidget(*args, **kwargs)
```

Email IMAP widget

This widget will scan one of your imap email boxes and report the number of unseen messages present. I've configured it to only work with imap with ssl. Your password can be obtained from the Gnome Keyring.

Writing your password to the keyring initially is as simple as (changing out <userid> and <password> for your userid and password):

1) create the file ~/.local/share/python_keyring/keyringrc.cfg with the following contents:

```
[backend]
default-keyring=keyring.backends.Gnome.Keyring
keyring-path=/home/<userid>/.local/share/keyring/
```

2) Execute the following python shell script once:

```
#!/usr/bin/env python3
import keyring
user = <userid>
password = <password>
keyring.set_password('imapwidget', user, password)
```

mbox names must include the path to the mbox (except for the default INBOX). So, for example if your mailroot is ~/Maildir, and you want to look at the mailbox at HomeMail/fred, the mbox setting would be: mbox="~/Maildir/HomeMail/fred". Note the nested sets of quotes! Labels can be whatever you choose, of course.

If you want you can give password directly then Gnome Keyring will not be used.

Widget requirements: keyring.

Supported bar orientations: horizontal and vertical

Configuration options

8.31. ImapWidget 135

key	default	description
background	None	Widget background color
direction	'default'	Override the text direction in vertical bar, has no effect on text in horizontal bar.default: text displayed based on vertical bar position (left/right)ttb: text read from top to bottom, btt: text read from bottom to top.'default', 'ttb', 'btt'
fmt	'{}'	Format to apply to the string returned by the widget. Main purpose: applying markup. For a widget that returns foo, using fmt=' <i>{}</i> ' would give you <i>foo</i> . To control what the widget outputs in the first place, use the format paramater of the widget (if it has one).
font	'sans'	Default font
fontshadow	None	font shadow color, default is None(no shadow)
fontsize	None	Font size. Calculated if None.
foreground	'ffffff'	Foreground colour
hide_crash	False	Don't display error in bar if widget crashes on startup.
hide_no_unseen	False	hide when there are no unseen messages
label	'INBOX: '	label for display
markup	True	Whether or not to use pango markup
max_chars	0	Maximum number of characters to display in widget.
mbox	'"INBOX"'	mailbox to fetch
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions and lazy calls.
padding	None	Padding. Calculated if None.
password	None	email password
rotate	True	Rotate text in vertical bar.
scroll	False	Whether text should be scrolled. When True, you must set the widget's width.
scroll_clear	False	Whether text should scroll completely away (True) or stop when the end of the text is shown (False)
scroll_delay	2	Number of seconds to pause before starting scrolling and restarting/clearing text at end
scroll_fixed_wid	False	When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text.
scroll_hide	False	Whether the widget should hide when scrolling has finished
scroll_interval	0.1	Time in seconds before next scrolling step
scroll_repeat	True	Whether text should restart scrolling once the text has ended
scroll_step	1	Number of pixels to scroll with each step
server	None	email server name
update_interval	600	Update interval in seconds, if none, the widget updates only once.
user	None	email username

Click to view the available commands for <code>ImapWidget</code>

8.32 KeyboardKbdd

class libqtile.widget.KeyboardKbdd(*args, **kwargs)

Widget for changing keyboard layouts per window, using kbdd

kbdd should be installed and running, you can get it from: https://github.com/qnikst/kbdd

The widget also requires dbus-fast.

Supported bar orientations: horizontal and vertical

key	default	description
background	None	Widget background color
colours	None	foreground colour for each layouteither 'None' or a list of colours.example: ['ffffff', 'E6F0AF'].
configured_keybo		your predefined list of keyboard layouts.example: ['us', 'ir', 'es']
direction	'default'	Override the text direction in vertical bar, has no effect on text in horizontal bar.default: text displayed based on vertical bar position (left/right)ttb: text read from top to bottom, btt: text read from bottom to top.'default', 'ttb', 'btt'
fmt	'{}'	Format to apply to the string returned by the widget. Main purpose: applying markup. For a widget that returns foo, using fmt=' <i>{}</i> ' would give you <i>foo</i> . To control what the widget outputs in the first place, use the format paramater of the widget (if it has one).
font	'sans'	Default font
fontshadow	None	font shadow color, default is None(no shadow)
fontsize	None	Font size. Calculated if None.
foreground	'ffffff'	Foreground colour
hide_crash	False	Don't display error in bar if widget crashes on startup.
markup	True	Whether or not to use pango markup
max_chars	0	Maximum number of characters to display in widget.
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions and lazy calls.
padding	None	Padding. Calculated if None.
rotate	True	Rotate text in vertical bar.
scroll	False	Whether text should be scrolled. When True, you must set the widget's width.
scroll_clear	False	Whether text should scroll completely away (True) or stop when the end of the text is shown (False)
scroll_delay	2	Number of seconds to pause before starting scrolling and restart- ing/clearing text at end
scroll_fixed_wid	False	When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text.
scroll_hide	False	Whether the widget should hide when scrolling has finished
scroll_interval	0.1	Time in seconds before next scrolling step
scroll_repeat	True	Whether text should restart scrolling once the text has ended
scroll_step	1	Number of pixels to scroll with each step
update_interval	1	Update interval in seconds.

Click to view the available commands for KeyboardKbdd

8.33 KeyboardLayout

class libqtile.widget.KeyboardLayout(*args, **kwargs)

Widget for changing and displaying the current keyboard layout

To use this widget effectively you need to specify keyboard layouts you want to use (using "configured_keyboards") and bind function "next_keyboard" to specific keys in order to change layouts.

For example:

Key([mod], "space", lazy.widget["keyboardlayout"].next_keyboard(), desc="Next keyboard layout."),

When running Qtile with the X11 backend, this widget requires setxkbmap to be available. Xmodmap will also be used if .Xmodmap file is available.

Supported bar orientations: horizontal and vertical

key	default	description
background	None	Widget background color
configured_keybo		A list of predefined keyboard layouts represented as strings. For example: ['us', 'us colemak', 'es', 'fr'].
direction	'default'	Override the text direction in vertical bar, has no effect on text in horizontal bar.default: text displayed based on vertical bar position (left/right)ttb: text read from top to bottom, btt: text read from bottom to top.'default', 'ttb', 'btt'
display_map	{}	Custom display of layout. Key should be in format 'layout variant'. For example: {'us': 'us', 'lt sgs': 'sgs', 'ru phonetic': 'ru'}
fmt	'{}'	Format to apply to the string returned by the widget. Main purpose: applying markup. For a widget that returns foo, using fmt=' <i>{}</i> ' would give you <i>foo</i> . To control what the widget outputs in the first place, use the format paramater of the widget (if it has one).
font	'sans'	Default font
fontshadow	None	font shadow color, default is None(no shadow)
fontsize	None	Font size. Calculated if None.
foreground	'ffffff'	Foreground colour
hide_crash	False	Don't display error in bar if widget crashes on startup.
markup	True	Whether or not to use pango markup
max_chars	0	Maximum number of characters to display in widget.
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions and lazy calls.
option	None	string of setxkbmap option. Ex., 'compose:menu,grp_led:scroll'
padding	None	Padding. Calculated if None.
rotate	True	Rotate text in vertical bar.
scroll	False	Whether text should be scrolled. When True, you must set the widget's width.
scroll_clear	False	Whether text should scroll completely away (True) or stop when the end of the text is shown (False)
scroll_delay	2	Number of seconds to pause before starting scrolling and restarting/clearing text at end
scroll_fixed_wid	False	When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text.
scroll_hide	False	Whether the widget should hide when scrolling has finished
scroll_interval	0.1	Time in seconds before next scrolling step
scroll_repeat	True	Whether text should restart scrolling once the text has ended
scroll_step	1	Number of pixels to scroll with each step
update_interval	1	Update time in seconds.

Click to view the available commands for KeyboardLayout

8.34 KhalCalendar

class libqtile.widget.KhalCalendar(*args, **kwargs)

Khal calendar widget

This widget will display the next appointment on your Khal calendar in the qtile status bar. Appointments within the "reminder" time will be highlighted.

Widget requirements: dateutil.

Supported bar orientations: horizontal and vertical

key	default	description
background direction	None 'default'	Widget background color
direction		Override the text direction in vertical bar, has no effect on text in horizontal bar.default: text displayed based on vertical bar position (left/right)ttb: text read from top to bottom, btt: text read from bottom to top.'default', 'ttb', 'btt'
fmt	'{}'	Format to apply to the string returned by the widget. Main purpose: applying markup. For a widget that returns foo, using fmt=' <i>{}</i> ' would give you <i>foo</i> . To control what the widget outputs in the first place, use the format paramater of the widget (if it has one).
font	'sans'	Default font
fontshadow	None	font shadow color, default is None(no shadow)
fontsize	None	Font size. Calculated if None.
foreground	'FFFF33'	default foreground color
hide_crash	False	Don't display error in bar if widget crashes on startup.
lookahead	7	days to look ahead in the calendar
markup	True	Whether or not to use pango markup
max_chars	0	Maximum number of characters to display in widget.
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions and lazy calls.
padding	None	Padding. Calculated if None.
reminder_color	'FF0000'	color of calendar entries during reminder time
remindertime	10	reminder time in minutes
rotate	True	Rotate text in vertical bar.
scroll	False	Whether text should be scrolled. When True, you must set the widget's width.
scroll_clear	False	Whether text should scroll completely away (True) or stop when the end of the text is shown (False)
scroll_delay	2	Number of seconds to pause before starting scrolling and restart- ing/clearing text at end
scroll_fixed_wid	False	When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text.
scroll_hide	False	Whether the widget should hide when scrolling has finished
scroll_interval	0.1	Time in seconds before next scrolling step
scroll_repeat	True	Whether text should restart scrolling once the text has ended
scroll_step	1	Number of pixels to scroll with each step
update_interval	600	Update interval in seconds, if none, the widget updates only once.

Click to view the available commands for KhalCalendar

8.35 LaunchBar

class libqtile.widget.LaunchBar(*args, **kwargs)

This module defines a widget that displays icons to launch softwares or commands when clicked -- a launchbar. Only png icon files are displayed, not xpm because cairo doesn't support loading of xpm file. The order of displaying (from left to right) is in the order of the list.

If no icon was found for the name provided and if default_icon is set to None then the name is printed instead. If default_icon is defined then this icon is displayed instead.

To execute a software:

• ('thunderbird', 'thunderbird -safe-mode', 'launch thunderbird in safe mode')

To execute a python command in qtile, begin with by 'qshell:'

• ('/path/to/icon.png', 'qshell:self.qtile.shutdown()', 'logout from qtile')

Optional requirements: pyxdg for finding the icon path if it is not provided in the progs tuple.

Supported bar orientations: horizontal and vertical

Configuration options

8.35. LaunchBar 141

key	default	description
background	None	Widget background color
default_icon	'/usr/share/ icons/oxygen/ 256x256/ mimetypes/ application-x-ex png'	Default icon not found
font	'sans'	Text font
fontshadow	None	Font shadow color, default is None (no shadow)
fontsize	None	Font pixel size. Calculated if None.
foreground	'#ffffff'	Text colour.
hide_crash	False	Don't display error in bar if widget crashes on startup.
icon_size	None	Size of icons. None to fit to bar.
markup	False	Whether to allow markup in text label.
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions and lazy calls.
padding	2	Padding between icons
padding_y	0	Vertical adjustment for icons (horizontal adjustment on vertical bars).
progs	[]	A list of tuples (software_name or icon_path, com-mand_to_execute, comment), for example: [('thunderbird', 'thunderbird -safe-mode', 'launch thunderbird in safe mode'), ('/path/to/icon.png', 'qshell:self.qtile.shutdown()', 'logout from qtile')]
text_only	False	Don't use any icons.
theme_path	None	Path to icon theme to be used by pyxdg for icons. None will use default icon theme.

Click to view the available commands for LaunchBar

8.36 Load

class libqtile.widget.Load(*args, **kwargs)

A small widget to show the load averages of the system. Depends on psutil.

Supported bar orientations: horizontal and vertical

Configuration options

key	default	description
background	None	Widget background color
direction	'default'	Override the text direction in vertical bar, has no effect on text in horizontal bar.default: text displayed based on vertical bar position (left/right)ttb: text read from top to bottom, btt: text read from bottom to top.'default', 'ttb', 'btt'
fmt	'{}'	Format to apply to the string returned by the widget. Main purpose: applying markup. For a widget that returns foo, using fmt=' <i>{}</i> ' would give you <i>foo</i> . To control what the widget outputs in the first place, use the format paramater of the widget (if it has one).
font	'sans'	Default font
fontshadow	None	font shadow color, default is None(no shadow)
fontsize	None	Font size. Calculated if None.
foreground	'ffffff'	Foreground colour
format	'Load({time}):{l 2f}'	The format in which to display the results.
hide_crash	False	Don't display error in bar if widget crashes on startup.
markup	True	Whether or not to use pango markup
max_chars	0	Maximum number of characters to display in widget.
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions and lazy calls.
padding	None	Padding. Calculated if None.
rotate	True	Rotate text in vertical bar.
scroll	False	Whether text should be scrolled. When True, you must set the widget's width.
scroll_clear	False	Whether text should scroll completely away (True) or stop when the end of the text is shown (False)
scroll_delay	2	Number of seconds to pause before starting scrolling and restarting/clearing text at end
scroll_fixed_wid	False	When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text.
scroll_hide	False	Whether the widget should hide when scrolling has finished
scroll_interval	0.1	Time in seconds before next scrolling step
scroll_repeat	True	Whether text should restart scrolling once the text has ended
scroll_step	1	Number of pixels to scroll with each step
update_interval	1.0	The update interval for the widget

Click to view the available commands for Load

8.36. Load 143

8.37 Maildir

class libqtile.widget.Maildir(*args, **kwargs)

A simple widget showing the number of new mails in maildir mailboxes

Supported bar orientations: horizontal and vertical

Configuration options

key	default	description
background	None	Widget background color
direction	'default'	Override the text direction in vertical bar, has no effect on text in horizontal bar.default: text displayed based on vertical bar position (left/right)ttb: text read from top to bottom, btt: text read from bottom to top.'default', 'ttb', 'btt'
empty_color	None	Display color when no new mail is available
fmt	'{}'	Format to apply to the string returned by the widget. Main purpose: applying markup. For a widget that returns foo, using fmt=' <i>{}</i> ' would give you <i>foo</i> . To control what the widget outputs in the first place, use the format paramater of the widget (if it has one).
font	'sans'	Default font
fontshadow	None	font shadow color, default is None(no shadow)
fontsize	None	Font size. Calculated if None.
foreground	'ffffff'	Foreground colour
hide_crash	False	Don't display error in bar if widget crashes on startup.
hide_when_empty	False	Whether not to display anything if the subfolder has no new mail
maildir_path	'~/Mail'	path to the Maildir folder
markup	True	Whether or not to use pango markup
max_chars	0	Maximum number of characters to display in widget.
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions and lazy calls.
nonempty_color	None	Display color when new mail is available
padding	None	Padding. Calculated if None.
rotate	True	Rotate text in vertical bar.
scroll	False	Whether text should be scrolled. When True, you must set the widget's width.
scroll_clear	False	Whether text should scroll completely away (True) or stop when the end of the text is shown (False)
scroll_delay	2	Number of seconds to pause before starting scrolling and restart- ing/clearing text at end
scroll_fixed_wid	False	When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text.
scroll_hide	False	Whether the widget should hide when scrolling has finished
scroll_interval	0.1	Time in seconds before next scrolling step
scroll_repeat	True	Whether text should restart scrolling once the text has ended
scroll_step	1	Number of pixels to scroll with each step
separator	1 1	the string to put between the subfolder strings.

Table 8 – continued from previous page

key	default	description
sub_folders	[{'label': 'Home mail', 'path': 'INBOX'}, {'label': 'Home junk', 'path': 'spam'}]	List of subfolders to scan. Each subfolder is a dict of <i>path</i> and <i>label</i> .
subfolder_fmt	'{label}: {value}'	Display format for one subfolder
total	False	Whether or not to sum subfolders into a grand total. The first label will be used.
update_interval	600	Update interval in seconds, if none, the widget updates only once.

Click to view the available commands for Maildir

8.38 Memory

class libqtile.widget.Memory(*args, **kwargs)

Display memory/swap usage.

The following fields are available in the *format* string:

- MemUsed: Memory in use.
- MemTotal: Total amount of memory.
- MemFree: Amount of memory free.
- Available: Amount of memory available.
- NotAvailable: Equal to MemTotal MemAvailable
- MemPercent: Memory in use as a percentage.
- Buffers: Buffer amount.
- Active: Active memory.
- Inactive: Inactive memory.
- Shmem: Shared memory.
- SwapTotal: Total amount of swap.
- SwapFree: Amount of swap free.
- SwapUsed: Amount of swap in use.
- SwapPercent: Swap in use as a percentage.
- mm: Measure unit for memory.
- ms: Measure unit for swap.

8.38. Memory 145

Widget requirements: psutil.

Supported bar orientations: horizontal and vertical

Configuration options

key	default	description
background	None	Widget background color
direction	'default'	Override the text direction in vertical bar, has no effect on text in horizontal bar.default: text displayed based on vertical bar position (left/right)ttb: text read from top to bottom, btt: text read from bottom to top.'default', 'ttb', 'btt'
fmt	'{}'	Format to apply to the string returned by the widget. Main purpose: applying markup. For a widget that returns foo, using fmt=' <i>{}</i> ' would give you <i>foo</i> . To control what the widget outputs in the first place, use the format paramater of the widget (if it has one).
font	'sans'	Default font
fontshadow	None	font shadow color, default is None(no shadow)
fontsize	None	Font size. Calculated if None.
foreground	'ffffff'	Foreground colour
format	'{MemUsed: .0f}{mm}/ {MemTotal: .0f}{mm}'	Formatting for field names.
hide_crash	False	Don't display error in bar if widget crashes on startup.
markup	True	Whether or not to use pango markup
max_chars	0	Maximum number of characters to display in widget.
measure_mem	'M'	Measurement for Memory (G, M, K, B)
measure_swap	'M'	Measurement for Swap (G, M, K, B)
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions and lazy calls.
padding	None	Padding. Calculated if None.
rotate	True	Rotate text in vertical bar.
scroll	False	Whether text should be scrolled. When True, you must set the widget's width.
scroll_clear	False	Whether text should scroll completely away (True) or stop when the end of the text is shown (False)
scroll_delay	2	Number of seconds to pause before starting scrolling and restarting/clearing text at end
scroll_fixed_wid	False	When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text.
scroll_hide	False	Whether the widget should hide when scrolling has finished
scroll_interval	0.1	Time in seconds before next scrolling step
scroll_repeat	True	Whether text should restart scrolling once the text has ended
scroll_step	1	Number of pixels to scroll with each step
update_interval	1.0	Update interval for the Memory

Available commands

Click to view the available commands for Memory

8.39 MemoryGraph

class libqtile.widget.MemoryGraph(*args, **kwargs)

Displays a memory usage graph.

Widget requirements: psutil.

Supported bar orientations: horizontal only

Configuration options

key	default	description
background	None	Widget background color
border_color	'215578'	Widget border color
border_width	2	Widget border width
fill_color	'1667EB.3'	Fill color for linefill graph
frequency	1	Update frequency in seconds
graph_color	'18BAEB'	Graph color
hide_crash	False	Don't display error in bar if widget crashes on startup.
line_width	3	Line width
margin_x	3	Margin X
margin_y	3	Margin Y
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions and lazy calls.
samples	100	Count of graph samples.
start_pos	'bottom'	Drawer starting position ('bottom'/'top')
type	'linefill'	'box', 'line', 'linefill'

Available commands

Click to view the available commands for MemoryGraph

8.40 Moc

class libqtile.widget.Moc(*args, **kwargs)

A simple MOC widget.

Show the artist and album of now listening song and allow basic mouse control from the bar:

- toggle pause (or play if stopped) on left click;
- skip forward in playlist on scroll up;
- skip backward in playlist on scroll down.

MOC (http://moc.daper.net) should be installed.

Supported bar orientations: horizontal and vertical

Configuration options

8.39. MemoryGraph

key	default	description
background	None	Widget background color
direction	'default'	Override the text direction in vertical bar, has no effect on text in horizontal bar.default: text displayed based on vertical bar position (left/right)ttb: text read from top to bottom, btt: text read from bottom to top.'default', 'ttb', 'btt'
fmt	'{}'	Format to apply to the string returned by the widget. Main purpose: applying markup. For a widget that returns foo, using fmt=' <i>{}</i> ' would give you <i>foo</i> . To control what the widget outputs in the first place, use the format paramater of the widget (if it has one).
font	'sans'	Default font
fontshadow	None	font shadow color, default is None(no shadow)
fontsize	None	Font size. Calculated if None.
foreground	'ffffff'	Foreground colour
hide_crash	False	Don't display error in bar if widget crashes on startup.
markup	True	Whether or not to use pango markup
max_chars	0	Maximum number of characters to display in widget.
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions and lazy calls.
noplay_color	'cecece'	Text colour when not playing.
padding	None	Padding. Calculated if None.
play_color	'00ff00'	Text colour when playing.
rotate	True	Rotate text in vertical bar.
scroll	False	Whether text should be scrolled. When True, you must set the widget's width.
scroll_clear	False	Whether text should scroll completely away (True) or stop when the end of the text is shown (False)
scroll_delay	2	Number of seconds to pause before starting scrolling and restart- ing/clearing text at end
scroll_fixed_wid	False	When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text.
scroll_hide	False	Whether the widget should hide when scrolling has finished
scroll_interval	0.1	Time in seconds before next scrolling step
scroll_repeat	True	Whether text should restart scrolling once the text has ended
scroll_step	1	Number of pixels to scroll with each step
update_interval	0.5	Update Time in seconds.

Click to view the available commands for Moc

8.41 Mpd2

Parameters

status format:

format string to display status

For a full list of values, see:

MPDClient.status() and MPDClient.currentsong()

https://musicpd.org/doc/protocol/command_reference.html#command_status https://musicpd.org/doc/protocol/tags.html

Default:

```
'{play_status} {artist}/{title} \
    [{repeat}{random}{single}{consume}{updating_db}]'

``play_status`` is a string from ``play_states`` dict

Note that the ``time`` property of the song renamed to ``fulltime``
to prevent conflicts with status information during formating.
```

idle format:

format string to display status when no song is in queue.

Default:

```
'{play_status} {idle_message} \
    [{repeat}{random}{single}{consume}{updating_db}]'

Note that the ``artist`` key fallbacks to similar keys in specificular order.
(``artist`` -> ``albumartist`` -> ``performer`` ->
    -> ``composer`` -> ``conductor`` -> ``ensemble``)
```

idle_message:

text to display instead of song information when MPD is idle. (i.e. no song in queue)

Default:: "MPD IDLE"

undefined_value:

text to display when status key is undefined

Default:: "Undefined"

prepare status:

dict of functions to replace values in status with custom characters.

```
f(status, key, space_element) => str
```

New functionality allows use of a dictionary of plain strings.

Default:

8.41. Mpd2 149

```
status_dict = {
    'repeat': 'r',
    'random': 'z',
    'single': '1',
    'consume': 'c',
    'updating_db': 'U'
}
```

format_fns:

A dict of functions to format the various elements.

'Tag': f(str) => str

Default:: { 'all': lambda s: cgi.escape(s) }

N.B. if 'all' is present, it is processed on every element of song_info

before any other formatting is done.

mouse buttons:

A dict of mouse button numbers to actions

Widget requirements: python-mpd2_.

.. _python-mpd2: https://pypi.org/project/python-mpd2/

Supported bar orientations: horizontal and vertical

Configuration options

key	default	description
background	None	Widget background color
color_progress	None	Text color to indicate track progress.
command	<pre><function 0x7500c132f240="" at="" default_cmd=""></function></pre>	command to be executed by mapped mouse button.
direction	'default'	Override the text direction in vertical bar, has no effect on text in horizontal bar.default: text displayed based on vertical bar position (left/right)ttb: text read from top to bottom, btt: text read from bottom to top.'default', 'ttb', 'btt'
fmt	'{}'	Format to apply to the string returned by the widget. Main purpose: applying markup. For a widget that returns foo, using fmt=' <i>{}</i> ' would give you <i>foo</i> . To control what the widget outputs in the first place, use the format paramater of the widget (if it has one).
font	'sans'	Default font
fontshadow	None	font shadow color, default is None(no shadow)
fontsize	None	Font size. Calculated if None.
foreground	'ffffff'	Foreground colour
format_fns	<pre>{'all': <function 0x7500c39c8fe0="" at="" escape="">}</function></pre>	Dictionary of format methods
hide_crash	False	Don't display error in bar if widget crashes on startup.
host	'localhost'	Host of mpd server
idle_format	'{play_status} {idle_message}[{	format for status when mpd has no playlist.

Table 9 – continued from previous page

leave		description
key	default	description
idle_message	'MPD IDLE'	text to display when mpd is idle.
idletimeout	5	MPDClient idle command timeout
markup	True	Whether or not to use pango markup
max_chars	0	Maximum number of characters to display in widget.
mouse_buttons	<pre>{1: 'toggle', 3: 'stop', 4: 'previous', 5: 'next'}</pre>	b_num -> action.
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions and lazy calls.
no_connection	'No connection'	Text when mpd is disconnected
padding	None	Padding. Calculated if None.
password	None	Password for auth on mpd server
play_states	{'pause': '', 'play': '', 'stop': ''}	Play state mapping
port	6600	Port of mpd server
prepare_status	<pre>{'consume': 'c', 'random': 'z', 'repeat': 'r', 'single': '1', 'updating_db': 'U'}</pre>	characters to show the status of MPD
rotate	True	Rotate text in vertical bar.
scroll	False	Whether text should be scrolled. When True, you must set the widget's width.
scroll_clear	False	Whether text should scroll completely away (True) or stop when the end of the text is shown (False)
scroll_delay	2	Number of seconds to pause before starting scrolling and restarting/clearing text at end
scroll_fixed_wid		When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text.
scroll_hide	False	Whether the widget should hide when scrolling has finished
scroll_interval	0.1	Time in seconds before next scrolling step
scroll_repeat	True	Whether text should restart scrolling once the text has ended
scroll_step	1	Number of pixels to scroll with each step
space	'-'	Space keeper
status_format	<pre>'{play_status} {artist}/ {title} [{repeat}{random</pre>	format for displayed song info.
timeout	30	MPDClient timeout
undefined_value	'Undefined'	text to display when status key is undefined.
update_interval	1	Interval of update widget

8.41. Mpd2 151

Click to view the available commands for Mpd2

8.42 Mpris2

class libqtile.widget.Mpris2(*args, **kwargs)

An MPRIS 2 widget

A widget which displays the current track/artist of your favorite MPRIS player. This widget scrolls the text if neccessary and information that is displayed is configurable.

The widget relies on players broadcasting signals when the metadata or playback status changes. If you are getting inconsistent results then you can enable background polling of the player by setting the *poll_interval* parameter. This is disabled by default.

Basic mouse controls are also available: button 1 = play/pause, scroll up = next track, scroll down = previous track.

Widget requirements: dbus-fast.

Supported bar orientations: horizontal and vertical

Configuration options

key	default	description
background	None	Widget background color
direction	'default'	Override the text direction in vertical bar, has no effect on text in horizontal bar.default: text displayed based on vertical bar position (left/right)ttb: text read from top to bottom, btt: text read from bottom to top.'default', 'ttb', 'btt'
display_metadata	<pre>['xesam:title', 'xesam:album', 'xesam:artist']</pre>	(Deprecated) Which metadata identifiers to display.
fmt	'{}'	Format to apply to the string returned by the widget. Main purpose: applying markup. For a widget that returns foo, using fmt=' <i>{}</i> ' would give you <i>foo</i> . To control what the widget outputs in the first place, use the format paramater of the widget (if it has one).
font	'sans'	Default font
fontshadow	None	font shadow color, default is None(no shadow)
fontsize	None	Font size. Calculated if None.
foreground	'ffffff'	Foreground colour
format	<pre>'{xesam:title} - {xesam:album} - {xesam:artist}'</pre>	Format string for displaying metadata. See http://www.freedesktop.org/wiki/Specifications/mpris-spec/metadata/#index5h3 for available values. The special filed '{qtile:player}' can be used to display the player name.
hide_crash	False	Don't display error in bar if widget crashes on startup.
markup	True	Whether or not to use pango markup
max_chars	0	Maximum number of characters to display in widget.
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions and lazy calls.
name	'audacious'	Name of the MPRIS widget.

Table 10 – continued from previous page

key	default	description
no_metadata_text	'No metadata for current track'	Text to show when track has no metadata
objname	None	DBUS MPRIS 2 compatible player identifier- Find it out with dbus-monitor - Also see: http://specifications.freedesktop.org/mpris-spec/latest/#Bus-Name-Policy. None will listen for notifications from all MPRIS2 compatible players.
padding	None	Padding. Calculated if None.
paused_text	'Paused: {track}'	Text to show when paused
playing_text	'{track}'	Text to show when playing
poll_interval	0	Periodic background polling interval of player (0 to disable polling).
rotate	True	Rotate text in vertical bar.
scroll	True	Whether text should scroll.
scroll_clear	False	Whether text should scroll completely away (True) or stop when the end of the text is shown (False)
scroll_delay	2	Number of seconds to pause before starting scrolling and restarting/clearing text at end
scroll_fixed_wid	False	When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text.
scroll_hide	False	Whether the widget should hide when scrolling has finished
scroll_interval	0.1	Time in seconds before next scrolling step
scroll_repeat	True	Whether text should restart scrolling once the text has ended
scroll_step	1	Number of pixels to scroll with each step
separator	1 , 1	Separator for metadata fields that are a list.
stop_pause_text	None	(Deprecated) Optional text to display when in the stopped/paused state
stopped_text	1 1	Text to show when stopped

Click to view the available commands for Mpris2

8.43 Net

class libqtile.widget.Net(*args, **kwargs)

Displays interface down and up speed

The following fields are available in the *format* string:

• interface: name of the interface

• down: download speed

• down_suffix: suffix for the download speed

• down_cumulative: cumulative download traffic

• down_cumulative_suffix: suffix for the cumulative download traffic

8.43. Net 153

Qtile Documentation, Release 0.1.dev50+g42203cb

- up: upload speed
- up_suffix: suffix for the upload speed
- up_cumulative: cumulative upload traffic
- up_cumulative_suffix: suffix for the cumulative upload traffic
- total: total speed
- total_suffix: suffix for the total speed
- total_cumulative: cumulative total traffic
- total_cumulative_suffix: suffix for the cumulative total traffic

Widget requirements: psutil.

Supported bar orientations: horizontal and vertical

Configuration options

key	default	description
background	None	Widget background color
cumulative_prefi	None	Use a specific prefix for the unit of the cumulative traffic.
direction	'default'	Override the text direction in vertical bar, has no effect on text
		in horizontal bar.default: text displayed based on vertical bar po-
		sition (left/right)ttb: text read from top to bottom, btt: text read
fmt	'{}'	from bottom to top.'default', 'ttb', 'btt' Format to apply to the string returned by the widget. Main pur-
Imt	\(\frac{1}{2}\)	pose: applying markup. For a widget that returns foo, using fmt=' <i>{}</i> ' would give you <i>foo</i> . To control what the widget outputs in the first place, use the format paramater of the widget (if it has one).
font	'sans'	Default font
fontshadow	None	font shadow color, default is None(no shadow)
fontsize	None	Font size. Calculated if None.
foreground	'ffffff'	Foreground colour
format	'{interface}: {down:6. 2f}{down_suffix: 2f}{up_suffix:<2	Display format of down/upload/total speed of given interfaces
hide_crash	False	Don't display error in bar if widget crashes on startup.
interface	None	List of interfaces or single NIC as string to monitor, None to display all active NICs combined
markup	True	Whether or not to use pango markup
max_chars	0	Maximum number of characters to display in widget.
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions and lazy calls.
padding	None	Padding. Calculated if None.
prefix	None	Use a specific prefix for the unit of the speed.
rotate	True	Rotate text in vertical bar.
scroll	False	Whether text should be scrolled. When True, you must set the widget's width.
scroll_clear	False	Whether text should scroll completely away (True) or stop when the end of the text is shown (False)
scroll_delay	2	Number of seconds to pause before starting scrolling and restarting/clearing text at end
scroll_fixed_wid	False	When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text.
scroll_hide	False	Whether the widget should hide when scrolling has finished
scroll_interval	0.1	Time in seconds before next scrolling step
scroll_repeat	True	Whether text should restart scrolling once the text has ended
scroll_step	1	Number of pixels to scroll with each step
update_interval	1	The update interval.
use_bits	False	Use bits instead of bytes per second?

Click to view the available commands for Net

8.43. Net 155

8.44 NetGraph

class libqtile.widget.NetGraph(*args, **kwargs)

Display a network usage graph.

Widget requirements: psutil.

Supported bar orientations: horizontal only

Configuration options

key	default	description
background	None	Widget background color
bandwidth_type	'down'	down(load)/up(load)
border_color	'215578'	Widget border color
border_width	2	Widget border width
fill_color	'1667EB.3'	Fill color for linefill graph
frequency	1	Update frequency in seconds
graph_color	'18BAEB'	Graph color
hide_crash	False	Don't display error in bar if widget crashes on startup.
interface	'auto'	Interface to display info for ('auto' for detection)
line_width	3	Line width
margin_x	3	Margin X
margin_y	3	Margin Y
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions and lazy calls.
samples	100	Count of graph samples.
start_pos	'bottom'	Drawer starting position ('bottom'/'top')
type	'linefill'	'box', 'line', 'linefill'

Available commands

Click to view the available commands for NetGraph

8.45 NetUP

class libqtile.widget.NetUP(*args, **kwargs)

A widget to display whether the network connection is up or down by probing a host via ping or tcp connection.

By default host parameter is set to None.

Supported bar orientations: horizontal and vertical

Configuration options

key	default	description
background	None	Widget background color
direction	'default'	Override the text direction in vertical bar, has no effect on text in horizontal bar.default: text displayed based on vertical bar position (left/right)ttb: text read from top to bottom, btt: text read from bottom to top.'default', 'ttb', 'btt'

Table 11 – continued from previous page

key	default	description
display_fmt	'NET {0}'	Display format.
down_foreground	'FF0000'	Font color when host is down.
down_string	'down'	String to display when host is down.
fmt	'{}'	Format to apply to the string returned by the widget. Main purpose: applying markup. For a widget that returns foo, using fmt=' <i>{}</i> ' would give you <i>foo</i> . To control what the widget outputs in the first place, use the format paramater of the widget (if it has one).
font	'sans'	Default font
fontshadow	None	font shadow color, default is None(no shadow)
fontsize	None	Font size. Calculated if None.
foreground	'ffffff'	Foreground colour
hide_crash	False	Don't display error in bar if widget crashes on startup.
host	None	Host to probe.
markup	True	Whether or not to use pango markup
max_chars	0	Maximum number of characters to display in widget.
method	'ping'	tcp or ping.
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions and lazy calls.
padding	None	Padding. Calculated if None.
port	443	TCP port.
rotate	True	Rotate text in vertical bar.
scroll	False	Whether text should be scrolled. When True, you must set the widget's width.
scroll_clear	False	Whether text should scroll completely away (True) or stop when the end of the text is shown (False)
scroll_delay	2	Number of seconds to pause before starting scrolling and restarting/clearing text at end
scroll_fixed_wid	False	When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text.
scroll_hide	False	Whether the widget should hide when scrolling has finished
scroll_interval	0.1	Time in seconds before next scrolling step
scroll_repeat	True	Whether text should restart scrolling once the text has ended
scroll_step	1	Number of pixels to scroll with each step
up_foreground	'FFFFFF'	Font color when host is up.
up_string	'up'	String to display when host is up.
update_interval	30	Update interval in seconds.

Click to view the available commands for NetUP

8.45. NetUP 157

8.46 Notify

class libqtile.widget.Notify(*args, **kwargs)

A notify widget

This widget can handle actions provided by notification clients. However, only the default action is supported, so if a client provides multiple actions then only the default (first) action can be invoked. Some programs will provide their own notification windows if the notification server does not support actions, so if you want your notifications to handle more than one action then specify False for the action option to disable all action handling. Unfortunately we cannot specify the capability for exactly one action.

Supported bar orientations: horizontal and vertical

Configuration options

key	default	description
action	True	Enable handling of default action upon right click
audiofile	None	Audiofile played during notifications
background	None	Widget background color
background_low	'444444'	Background low priority colour
background_urgen	'440000'	Background urgent priority colour
default_timeout	10	Default timeout (seconds) for normal notifications
<pre>default_timeout_</pre>	5	Default timeout (seconds) for low urgency notifications.
<pre>default_timeout_</pre>	None	Default timeout (seconds) for urgent notifications
direction	'default'	Override the text direction in vertical bar, has no effect on text
		in horizontal bar.default: text displayed based on vertical bar po-
		sition (left/right)ttb: text read from top to bottom, btt: text read
		from bottom to top.'default', 'ttb', 'btt'
fmt	'{}'	Format to apply to the string returned by the widget. Main pur-
		pose: applying markup. For a widget that returns foo, using
		<pre>fmt='<i>{}</i>' would give you <i>foo</i>. To control</pre>
		what the widget outputs in the first place, use the format para-
		mater of the widget (if it has one).
font	'sans'	Default font
fontshadow	None	font shadow color, default is None(no shadow)
fontsize	None	Font size. Calculated if None.
foreground	'ffffff'	Foreground colour
foreground_low	'dddddd'	Foreground low priority colour
foreground_urgen	'ff0000'	Foreground urgent priority colour
hide_crash	False	Don't display error in bar if widget crashes on startup.
markup	True	Whether or not to use pango markup
max_chars	0	Maximum number of characters to display in widget.
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions
		and lazy calls.
padding	None	Padding. Calculated if None.
parse_text	None	Function to parse and modify notifications. e.g. function
		in config that removes line returns:def my_func(text) return
		text.replace('n', ")then set option parse_text=my_func
rotate	True	Rotate text in vertical bar.
scroll	False	Whether text should be scrolled. When True, you must set the
		widget's width.
scroll_clear	False	Whether text should scroll completely away (True) or stop when
		the end of the text is shown (False)
		continues on next page

Table 12 – continued from previous page

key	default	description
scroll_delay	2	Number of seconds to pause before starting scrolling and restarting/clearing text at end
scroll_fixed_wid	False	When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text.
scroll_hide	False	Whether the widget should hide when scrolling has finished
scroll_interval	0.1	Time in seconds before next scrolling step
scroll_repeat	True	Whether text should restart scrolling once the text has ended
scroll_step	1	Number of pixels to scroll with each step

Click to view the available commands for Notify

8.47 NvidiaSensors

class libqtile.widget.NvidiaSensors(*args, **kwargs)

Displays temperature, fan speed and performance level Nvidia GPU.

Supported bar orientations: horizontal and vertical

Configuration options

8.47. NvidiaSensors

key	default	description
background	None	Widget background color
direction	'default'	Override the text direction in vertical bar, has no effect on text in horizontal bar.default: text displayed based on vertical bar position (left/right)ttb: text read from top to bottom, btt: text read from bottom to top.'default', 'ttb', 'btt'
fmt	'{}'	Format to apply to the string returned by the widget. Main purpose: applying markup. For a widget that returns foo, using fmt=' <i>{}</i> ' would give you <i>foo</i> . To control what the widget outputs in the first place, use the format paramater of the widget (if it has one).
font	'sans'	Default font
fontshadow	None	font shadow color, default is None(no shadow)
fontsize	None	Font size. Calculated if None.
foreground	'ffffff'	Foreground colour
foreground_alert		Foreground colour alert
format	'{temp}°C'	Display string format. Three options available: {temp} - temperature, {fan_speed} and {perf} - performance level
gpu_bus_id	1.1	GPU's Bus ID, ex: 01:00.0 . If leave empty will display all available GPU's
hide_crash	False	Don't display error in bar if widget crashes on startup.
markup	True	Whether or not to use pango markup
max_chars	0	Maximum number of characters to display in widget.
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions and lazy calls.
padding	None	Padding. Calculated if None.
rotate	True	Rotate text in vertical bar.
scroll	False	Whether text should be scrolled. When True, you must set the widget's width.
scroll_clear	False	Whether text should scroll completely away (True) or stop when the end of the text is shown (False)
scroll_delay	2	Number of seconds to pause before starting scrolling and restarting/clearing text at end
scroll_fixed_wid	False	When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text.
scroll_hide	False	Whether the widget should hide when scrolling has finished
scroll_interval	0.1	Time in seconds before next scrolling step
scroll_repeat	True	Whether text should restart scrolling once the text has ended
scroll_step	1	Number of pixels to scroll with each step
threshold	70	If the current temperature value is above, then change to fore-ground_alert colour
update_interval	2	Update interval in seconds.

Click to view the available commands for NvidiaSensors

8.48 OpenWeather

class libqtile.widget.OpenWeather(*args, **kwargs)

A weather widget, data provided by the OpenWeather API.

Some format options:

- location_city
- · location_cityid
- · location_country
- location_lat
- location_long
- · weather
- · weather_details
- units_temperature
- · units_wind_speed
- isotime
- humidity
- pressure
- sunrise
- sunset
- temp
- visibility
- wind_speed
- wind_deg
- · wind_direction
- main_feels_like
- main_temp_min
- main_temp_max
- clouds_all
- icon

Icon support is available but you will need a suitable font installed. A default icon mapping is provided (OpenWeather.symbols) but changes can be made by setting weather_symbols. Available icon codes can be viewed here: https://openweathermap.org/weather-conditions#Icon-list

Supported bar orientations: horizontal and vertical

Configuration options

8.48. OpenWeather 161

key	default	description
app_key	'7834197c2338888	Open Weather access key. A default is provided, butn for prolonged use obtaining your own is suggested:n https://home.openweathermap.org/users/sign_up
background	None	Widget background color
cityid	None	City ID. Can be looked up on e.g.:n https://openweathermap.org/findn Takes precedence over location and coordinates.n Note that this is not equal to a WOEID.
coordinates	None	Dictionary containing latitude and longituden Example: coordinates={"longitude": "77.22",n "latitude": "28.67"}
data	None	Post Data
dateformat	'%Y-%m-%d '	Format for dates, defaults to ISO.n For details see: https://docs.python.org/3/library/time.html#time.strftime
direction	'default'	Override the text direction in vertical bar, has no effect on text in horizontal bar.default: text displayed based on vertical bar position (left/right)ttb: text read from top to bottom, btt: text read from bottom to top.'default', 'ttb', 'btt'
fmt	'{}'	Format to apply to the string returned by the widget. Main purpose: applying markup. For a widget that returns foo, using fmt=' <i>{}</i> ' would give you <i>foo</i> . To control what the widget outputs in the first place, use the format paramater of the widget (if it has one).
font	'sans'	Default font
fontshadow	None	font shadow color, default is None(no shadow)
fontsize	None	Font size. Calculated if None.
foreground	'ffffff'	Foreground colour
format	'{location_city} {main_temp} °{units_temperat {humidity}% {weather_details	_
headers	{}	Extra Headers
hide_crash	False	Don't display error in bar if widget crashes on startup.
json	True	Is Json?
language	'en'	Language of response. List of languages supported cann be seen at: https://openweathermap.org/current undern Multilingual support
location	None	Name of the city. Country name can be appended like cambridge, NZ. Takes precedence over zip-code.
markup	True	Whether or not to use pango markup
max_chars	0	Maximum number of characters to display in widget.
metric	True	True to use metric/C, False to use imperial/F
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions and lazy calls.
padding	None	Padding. Calculated if None.
parse	None	Parse Function
rotate	True	Rotate text in vertical bar.
scroll	False	Whether text should be scrolled. When True, you must set the
		widget's width.
scroll_clear	False	Whether text should scroll completely away (True) or stop when the end of the text is shown (False)

Table 13 – continued from previous page

key	default	description
scroll_delay	2	Number of seconds to pause before starting scrolling and restart- ing/clearing text at end
scroll_fixed_wid	False	When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text.
scroll_hide	False	Whether the widget should hide when scrolling has finished
scroll_interval	0.1	Time in seconds before next scrolling step
scroll_repeat	True	Whether text should restart scrolling once the text has ended
scroll_step	1	Number of pixels to scroll with each step
timeformat	'%H:%M'	Format for times, defaults to ISO.n For details see: https://docs.python.org/3/library/time.html#time.strftime
update_interval	600	Update interval in seconds, if none, the widget updates only once.
url	None	Url
user_agent	'Qtile'	Set the user agent
weather_symbols	{}	Dictionary of weather symbols. Can be used to override default symbols.
xml	False	Is XML?
zip	None	Zip code (USA) or "zip code,country code" forn other countries. E.g. 12345,NZ. Takes precedence overn coordinates.

Click to view the available commands for <code>OpenWeather</code>

8.49 Plasma

class libqtile.widget.Plasma(*args, **kwargs)

A simple widget to indicate in which direction new windows will be added in the Plasma layout.

Supported bar orientations: horizontal and vertical

Configuration options

8.49. Plasma 163

key	default	description
background	None	Widget background color
direction	'default'	Override the text direction in vertical bar, has no effect on text in horizontal bar.default: text displayed based on vertical bar position (left/right)ttb: text read from top to bottom, btt: text read from bottom to top.'default', 'ttb', 'btt'
fmt	'{}'	Format to apply to the string returned by the widget. Main purpose: applying markup. For a widget that returns foo, using fmt=' <i>{}</i> ' would give you <i>foo</i> . To control what the widget outputs in the first place, use the format paramater of the widget (if it has one).
font	'sans'	Default font
fontshadow	None	font shadow color, default is None(no shadow)
fontsize	None	Font size. Calculated if None.
foreground	'ffffff'	Foreground colour
format	'{mode:>2}'	Format appearance of text
hide_crash	False	Don't display error in bar if widget crashes on startup.
horizontal	'H'	Text to display if horizontal mode
horizontal_split	None	Text to display for horizontal split mode
markup	True	Whether or not to use pango markup
max_chars	0	Maximum number of characters to display in widget.
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions and lazy calls.
padding	None	Padding. Calculated if None.
rotate	True	Rotate text in vertical bar.
scroll	False	Whether text should be scrolled. When True, you must set the widget's width.
scroll_clear	False	Whether text should scroll completely away (True) or stop when the end of the text is shown (False)
scroll_delay	2	Number of seconds to pause before starting scrolling and restarting/clearing text at end
scroll_fixed_wid	False	When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text.
scroll_hide	False	Whether the widget should hide when scrolling has finished
scroll_interval	0.1	Time in seconds before next scrolling step
scroll_repeat	True	Whether text should restart scrolling once the text has ended
scroll_step	1	Number of pixels to scroll with each step
split	'S'	Text to append to mode if horizontal/vertical_split not set
vertical	'V'	Text to display if horizontal mode
vertical_split	None	Text to display for horizontal split mode

Click to view the available commands for Plasma

8.50 Pomodoro

class libqtile.widget.Pomodoro(*args, **kwargs)

Pomodoro technique widget

Supported bar orientations: horizontal and vertical

Configuration options

key	default	description
background	None	Widget background color
color_active	'00ff00'	Colour then pomodoro is running
color_break	'ffff00'	Colour then it is break time
color_inactive	'ff0000'	Colour then pomodoro is inactive
direction	'default'	Override the text direction in vertical bar, has no effect on text in horizontal bar.default: text displayed based on vertical bar position (left/right)ttb: text read from top to bottom, btt: text read from bottom to top.'default', 'ttb', 'btt'
fmt	'{}'	Format to apply to the string returned by the widget. Main purpose: applying markup. For a widget that returns foo, using fmt=' <i>{}</i> ' would give you <i>foo</i> . To control what the widget outputs in the first place, use the format paramater of the widget (if it has one).
font	'sans'	Default font
fontshadow	None	font shadow color, default is None(no shadow)
fontsize	None	Font size. Calculated if None.
foreground	'ffffff'	Foreground colour
hide_crash	False	Don't display error in bar if widget crashes on startup.
<pre>length_long_brea</pre>	15	Length of a long break in minutes
length_pomodori	25	Length of one pomodori in minutes
length_short_bre	5	Length of a short break in minutes
markup	True	Whether or not to use pango markup
max_chars	0	Maximum number of characters to display in widget.
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions and lazy calls.
notification_on	True	Turn notifications on
num_pomodori	4	Number of pomodori to do in a cycle
padding	None	Padding. Calculated if None.
<pre>prefix_active</pre>	1.1	Prefix then app is active
prefix_break	'B '	Prefix during short break
<pre>prefix_inactive</pre>	'POMODORO'	Prefix when app is inactive
<pre>prefix_long_brea</pre>		Prefix during long break
<pre>prefix_paused</pre>	'PAUSE'	Prefix during pause
rotate	True	Rotate text in vertical bar.
scroll	False	Whether text should be scrolled. When True, you must set the widget's width.
scroll_clear	False	Whether text should scroll completely away (True) or stop when the end of the text is shown (False)
scroll_delay	2	Number of seconds to pause before starting scrolling and restarting/clearing text at end

continues on next page

8.50. Pomodoro 165

Table 14 – continued from previous page

key	default	description
scroll_fixed_wid	False	When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text.
scroll_hide	False	Whether the widget should hide when scrolling has finished
scroll_interval	0.1	Time in seconds before next scrolling step
scroll_repeat	True	Whether text should restart scrolling once the text has ended
scroll_step	1	Number of pixels to scroll with each step
update_interval	1	Update interval in seconds, if none, the widget updates whenever the event loop is idle.

Click to view the available commands for *Pomodoro*

8.51 Prompt

class libqtile.widget.Prompt(*args, **kwargs)

A widget that prompts for user input

Input should be started using the $.start_input()$ method on this class.

Supported bar orientations: horizontal and vertical

Configuration options

key	default	description
background bell_style	None 'audible'	Widget background color Alert at the begin/end of the command history. Possible values: 'audible' (X11 only), 'visual' and None.
cursor	True	Show a cursor
cursor_color	'bef098'	Color for the cursor and text over it.
cursorblink	0.5	Cursor blink rate. 0 to disable.
direction	'default'	Override the text direction in vertical bar, has no effect on text in horizontal bar.default: text displayed based on vertical bar position (left/right)ttb: text read from top to bottom, btt: text read from bottom to top.'default', 'ttb', 'btt'
fmt	'{}'	Format to apply to the string returned by the widget. Main purpose: applying markup. For a widget that returns foo, using fmt=' <i>{}</i> ' would give you <i>foo</i> . To control what the widget outputs in the first place, use the format paramater of the widget (if it has one).
font	'sans'	Default font
fontshadow	None	font shadow color, default is None(no shadow)
fontsize	None	Font size. Calculated if None.
foreground	'ffffff'	Foreground colour
hide_crash	False	Don't display error in bar if widget crashes on startup.
ignore_dups_hist	False	Don't store duplicates in history
markup	True	Whether or not to use pango markup

Table 15 – continued from previous page

key	default	description
max_chars	0	Maximum number of characters to display in widget.
max_history	100	Commands to keep in history. 0 for no limit.
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions and lazy calls.
padding	None	Padding. Calculated if None.
prompt	'{prompt}: '	Text displayed at the prompt
record_history	True	Keep a record of executed commands
rotate	True	Rotate text in vertical bar.
scroll	False	Whether text should be scrolled. When True, you must set the widget's width.
scroll_clear	False	Whether text should scroll completely away (True) or stop when the end of the text is shown (False)
scroll_delay	2	Number of seconds to pause before starting scrolling and restarting/clearing text at end
scroll_fixed_wid	False	When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text.
scroll_hide	False	Whether the widget should hide when scrolling has finished
scroll_interval	0.1	Time in seconds before next scrolling step
scroll_repeat	True	Whether text should restart scrolling once the text has ended
scroll_step	1	Number of pixels to scroll with each step
visual_bell_colo	'ff0000'	Color for the visual bell (changes prompt background).
visual_bell_time	0.2	Visual bell duration (in seconds).

Click to view the available commands for *Prompt*

8.52 PulseVolume

class libqtile.widget.PulseVolume(*args, **kwargs)

Volume widget for systems using PulseAudio.

The widget connects to the PulseAudio server by using the libpulse library and so should be updated virtually instantly rather than needing to poll the volume status regularly (NB this means that the update_interval parameter serves no purpose for this widget).

The widget relies on the pulsectl_asyncio library to access the libpulse bindings. If you are using python 3.11 you must use pulsectl_asyncio >= 1.0.0.

Supported bar orientations: horizontal only

Configuration options

key	default	description	
background	None	Widget background color	
cardid	None	Card Id	
channel	'Master'	Channel	

continues on next page

8.52. PulseVolume 167

Table 16 – continued from previous page

check_mute_comma None check_mute_strin '[off]' String expected from check_mute_command when volum muted. When the output of the command matches this str theaudio source is treated as muted. device 'default' Device Name direction 'default' Override the text direction in vertical bar, has no effect on in horizontal bar.default: text displayed based on vertical bar sition (left/right)ttb: text read from top to bottom, btt: text from bottom to top.'default', 'ttb', 'btt' emoji False Use emoji to display volume states, only if theme_path is set. The specified font needs to contain the correct unicode cacters. emoji_list ['', '', '', List of emojis/font-symbols to display volume states, only emoji is set. List contains 4 symbols, from lowest volume
check_mute_strin '[off]' String expected from check_mute_command when volum muted. When the output of the command matches this str theaudio source is treated as muted. device 'default' Device Name direction 'default' Override the text direction in vertical bar, has no effect on in horizontal bar.default: text displayed based on vertical bar sition (left/right)ttb: text read from top to bottom, btt: text in from bottom to top.'default', 'ttb', 'btt' emoji False Use emoji to display volume states, only if theme_path is set. The specified font needs to contain the correct unicode concerns. emoji_list ['', '', '', List of emojis/font-symbols to display volume states, only
check_mute_strin '[off]' String expected from check_mute_command when volum muted. When the output of the command matches this str theaudio source is treated as muted. device 'default' Device Name direction 'default' Override the text direction in vertical bar, has no effect on in horizontal bar.default: text displayed based on vertical bar sition (left/right)ttb: text read from top to bottom, btt: text in from bottom to top.'default', 'ttb', 'btt' emoji False Use emoji to display volume states, only if theme_path is set. The specified font needs to contain the correct unicode contains access. emoji_list ['', '', '', List of emojis/font-symbols to display volume states, only if theme_path is set. The specified font needs to contain the correct unicode contains the correct unicod
direction 'default' Override the text direction in vertical bar, has no effect on in horizontal bar.default: text displayed based on vertical bar sition (left/right)ttb: text read from top to bottom, btt: text of from bottom to top.'default', 'ttb', 'btt' emoji False Use emoji to display volume states, only if theme_path is set.The specified font needs to contain the correct unicode cacters. emoji_list ['', '', '', List of emojis/font-symbols to display volume states, only if theme_path is set.The specified font needs to contain the correct unicode cacters.
in horizontal bar.default: text displayed based on vertical bar sition (left/right)ttb: text read from top to bottom, btt: text is from bottom to top.'default', 'ttb', 'btt' emoji False Use emoji to display volume states, only if theme_path is set.The specified font needs to contain the correct unicode contains. emoji_list ['', '', '', List of emojis/font-symbols to display volume states, only if theme_path is set.The specified font needs to contain the correct unicode contains.
set.The specified font needs to contain the correct unicode c acters. emoji_list ['', '', '', List of emojis/font-symbols to display volume states, onl
highest.
fmt '{}' Format to apply to the string returned by the widget. Main pose: applying markup. For a widget that returns foo, use fmt=' <i>{}</i> ' would give you <i>foo</i>). To cor what the widget outputs in the first place, use the format p mater of the widget (if it has one).
font 'sans' Default font
fontshadow None font shadow color, default is None(no shadow)
fontsize None Font size. Calculated if None.
foreground 'ffffff' Foreground colour
get_volume_comma None Command to get the current volume. The expected output she include 1-3 numbers and a % sign.
hide_crash False Don't display error in bar if widget crashes on startup.
limit_max_volume False
markup True Whether or not to use pango markup
max_chars 0 Maximum number of characters to display in widget.
mouse_callbacks {} Dict of mouse button press callback functions. Accepts function and lazy calls.
mute_command None Mute command
mute_foreground None Foreground color for mute volume.
mute_format 'M' Format to display when volume is muted.
padding 3 Padding left and right. Calculated if None.
rotate True Rotate text in vertical bar.
scroll False Whether text should be scrolled. When True, you must set widget's width.
scroll_clear False Whether text should scroll completely away (True) or stop we the end of the text is shown (False)
scroll_delay 2 Number of seconds to pause before starting scrolling and rest ing/clearing text at end
when scroll=True the width parameter is a maximum wand, when text is shorter than this, the widget will resize. ting scroll_fixed_width=True will force the widget to ha fixed width, regardless of the size of the text.
scroll_hide False Whether the widget should hide when scrolling has finished
scroll_interval 0.1 Time in seconds before next scrolling step
scroll_repeat True Whether text should restart scrolling once the text has ended

Table 16 – continued from previous page

key	default	description
scroll_step	1	Number of pixels to scroll with each step
step	2	Volume change for up an down commands in percentage. Only used if volume_up_command and volume_down_command are not set.
theme_path	None	Path of the icons
unmute_format	'{volume}%'	Format of text to display when volume is not muted.
update_interval	0.2	Update time in seconds.
volume_app	None	App to control volume
volume_down_comm	None	Volume down command
volume_up_comman	None	Volume up command

Click to view the available commands for PulseVolume

8.53 QuickExit

class libqtile.widget.QuickExit(*args, **kwargs)

A button to shut down Qtile. When clicked, a countdown starts. Clicking the button again stops the countdown and prevents Qtile from shutting down.

Supported bar orientations: horizontal and vertical

Configuration options

8.53. QuickExit

key	default	description
background	None	Widget background color
countdown_format	'[{} seconds]'	The text displayed when counting down.
countdown_start	5	The number to count down from.
default_text	'[shutdown]'	The text displayed on the button.
direction	'default'	Override the text direction in vertical bar, has no effect on text in horizontal bar.default: text displayed based on vertical bar position (left/right)ttb: text read from top to bottom, btt: text read from bottom to top.'default', 'ttb', 'btt'
fmt	'{}'	Format to apply to the string returned by the widget. Main purpose: applying markup. For a widget that returns foo, using fmt=' <i>{}</i> ' would give you <i>foo</i> . To control what the widget outputs in the first place, use the format paramater of the widget (if it has one).
font	'sans'	Default font
fontshadow	None	font shadow color, default is None(no shadow)
fontsize	None	Font size. Calculated if None.
foreground	'ffffff'	Foreground colour
hide_crash	False	Don't display error in bar if widget crashes on startup.
markup	True	Whether or not to use pango markup
max_chars	0	Maximum number of characters to display in widget.
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions and lazy calls.
padding	None	Padding. Calculated if None.
rotate	True	Rotate text in vertical bar.
scroll	False	Whether text should be scrolled. When True, you must set the widget's width.
scroll_clear	False	Whether text should scroll completely away (True) or stop when the end of the text is shown (False)
scroll_delay	2	Number of seconds to pause before starting scrolling and restarting/clearing text at end
scroll_fixed_wid	False	When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text.
scroll_hide	False	Whether the widget should hide when scrolling has finished
scroll_interval	0.1	Time in seconds before next scrolling step
scroll_repeat	True	Whether text should restart scrolling once the text has ended
scroll_step	1	Number of pixels to scroll with each step
timer_interval	1	The countdown interval.

Click to view the available commands for QuickExit

8.54 Redshift

class libqtile.widget.Redshift(*args, **kwargs)

Redshift widget provides the following functionality:

- · Call redshift with a specific brightness, temperature and gamma config without using your location.
- Increase/Decrease the brightness/temperature

The redshift command can be called by just left-clicking the widget and disabling it the same way.

If the widget is enabled, scrolling through the widget will show the settings: - brightness (limited to 2 dp) - gamma (can't be increased/decreased) - temperature (limited to 2 dp) - finally back to the default enabled/disabled text

When at the temperature/brightness settings, the left-click/right-click mouse buttons can be used to increase/decrease respectively.

Widget requirements: redshift

Supported bar orientations: horizontal and vertical Only available on the following backends: x11

Configuration options

key	default	description
background	None	Widget background color
brightness	1.0	Redshift brightness. Brightness has a lower bound of 0.1 and an upper bound of 1.0
brightness_fmt	'Brightness: {brightness}'	Text to display when showing brightness text. Available fields: 'brightness' brightness to set when redshift is enabled.
brightness_step	0.1	The amount to increase/decrease the brightness by.
direction	'default'	Override the text direction in vertical bar, has no effect on text in horizontal bar.default: text displayed based on vertical bar position (left/right)ttb: text read from top to bottom, btt: text read from bottom to top.'default', 'ttb', 'btt'
disabled_txt	'\U000f1803'	Text to show when redshift is disabled. NOTE: by default, a nerd icon is used. Available fields: 'brightness' brightness to set when redshift is enabled, 'is_enabled' boolean to state whether the widget is enabled or not, 'gamma_blue' gamma blue value to set when redshift is enabled, 'gamma_green' gamma green value to set when redshift is enabled, 'gamma_red' gamma red value to set when redshift is enabled, 'temperature' temperature to set when redshift is enabled,
enabled_txt	'\U000f06e8'	Text to show when redshift is disabled. NOTE: by default, a nerd icon is used. Available fields: see disabled_txt's available fields for all of them
fmt	'{}'	Format to apply to the string returned by the widget. Main purpose: applying markup. For a widget that returns foo, using fmt=' <i>{}</i> ' would give you <i>foo</i> . To control what the widget outputs in the first place, use the format paramater of the widget (if it has one).
font	'sans'	Default font
fontshadow	None	font shadow color, default is None(no shadow)
fontsize	20	Font size

continues on next page

8.54. Redshift

Table 17 – continued from previous page

		continued from previous page
key	default	description
foreground	'ffffff'	Font colour for information text
gamma_blue	1.0	Redshift gamma blue. gamma_blue has a lower bound of $0.1\ \mathrm{and}$ an upper bound of $10.0\ \mathrm{.}$
gamma_fmt	'Gamma: {gamma_red}:{gam	Text to display when showing gamma text. Available fields: 'gamma_red' gamma red value to set when redshift is enabled, 'gamma_blue' gamma blue value to set when redshift is enabled, 'gamma_green' gamma green value to set when redshift is enabled.
gamma_green	1.0	Redshift gamma green. gamma_green has a lower bound of 0.1 and an upper bound of 10.0.
gamma_red	1.0	Redshift gamma red setting. gamma_red has a lower bound of 0.1 and an upper bound of 10.0.
hide_crash	False	Don't display error in bar if widget crashes on startup.
markup	True	Whether or not to use pango markup
max_chars	0	Maximum number of characters to display in widget.
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions and lazy calls.
padding	None	Padding. Calculated if None.
redshift_path	None	Path to redshift executable
rotate	True	Rotate text in vertical bar.
scroll	False	Whether text should be scrolled. When True, you must set the widget's width.
scroll_clear	False	Whether text should scroll completely away (True) or stop when the end of the text is shown (False)
scroll_delay	2	Number of seconds to pause before starting scrolling and restarting/clearing text at end
scroll_fixed_wid	False	When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text.
scroll_hide	False	Whether the widget should hide when scrolling has finished
scroll_interval	0.1	Time in seconds before next scrolling step
scroll_repeat	True	Whether text should restart scrolling once the text has ended
scroll_step	1	Number of pixels to scroll with each step
temperature	1700	Redshift temperature to set when enabled. Temperature has a lower bound of 1000 and an upper bound of 25000.
temperature_fmt	'Temperature: {temperature}'	Text to display when showing temperature text. Available fields: 'temperature' temperature to set when redshift is enabled.
temperature_step	=	The amount to increase/decrease the temperature by.

Click to view the available commands for *Redshift*

8.55 ScreenSplit

class libqtile.widget.ScreenSplit(*args, **kwargs)

A simple widget to show the name of the current split and layout for the ScreenSplit layout.

Supported bar orientations: horizontal and vertical

Configuration options

key	default	description
background	None	Widget background color
direction	'default'	Override the text direction in vertical bar, has no effect on text in horizontal bar.default: text displayed based on vertical bar position (left/right)ttb: text read from top to bottom, btt: text read from bottom to top.'default', 'ttb', 'btt'
fmt	'{}'	Format to apply to the string returned by the widget. Main purpose: applying markup. For a widget that returns foo, using fmt=' <i>{}</i> ' would give you <i>foo</i> . To control what the widget outputs in the first place, use the format paramater of the widget (if it has one).
font	'sans'	Text font
fontshadow	None	font shadow color, default is None(no shadow)
fontsize	None	Font pixel size. Calculated if None.
foreground	'#ffffff'	Foreground colour.
format	'{split_name} ({layout})'	Format string.
hide_crash	False	Don't display error in bar if widget crashes on startup.
markup	True	Whether or not to use pango markup
max_chars	0	Maximum number of characters to display in widget.
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions and lazy calls.
padding	None	Padding left and right. Calculated if None.
rotate	True	Rotate text in vertical bar.
scroll	False	Whether text should be scrolled. When True, you must set the widget's width.
scroll_clear	False	Whether text should scroll completely away (True) or stop when the end of the text is shown (False)
scroll_delay	2	Number of seconds to pause before starting scrolling and restart- ing/clearing text at end
scroll_fixed_wid	False	When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text.
scroll_hide	False	Whether the widget should hide when scrolling has finished
scroll_interval	0.1	Time in seconds before next scrolling step
scroll_repeat	True	Whether text should restart scrolling once the text has ended
scroll_step	1	Number of pixels to scroll with each step

Available commands

Click to view the available commands for ScreenSplit

8.55. ScreenSplit

8.56 Sep

class libqtile.widget.Sep(*args, **kwargs)

A visible widget separator

Supported bar orientations: horizontal and vertical

Configuration options

key	default	description
background	None	Widget background color
foreground	'888888'	Separator line colour.
hide_crash	False	Don't display error in bar if widget crashes on startup.
linewidth	1	Width of separator line.
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions and lazy calls.
padding	2	Padding on either side of separator.
size_percent	80	Size as a percentage of bar size (0-100).

Available commands

Click to view the available commands for Sep

8.57 She

class libqtile.widget.She(*args, **kwargs)

Widget to display the Super Hybrid Engine status

Can display either the mode or CPU speed on eeepc computers.

Supported bar orientations: horizontal and vertical

Configuration options

key	default	description
background	None	Widget background color
device	'/sys/devices/ platform/ eeepc/cpufv'	sys path to cpufv
direction	'default'	Override the text direction in vertical bar, has no effect on text in horizontal bar.default: text displayed based on vertical bar position (left/right)ttb: text read from top to bottom, btt: text read from bottom to top.'default', 'ttb', 'btt'
fmt	'{}'	Format to apply to the string returned by the widget. Main purpose: applying markup. For a widget that returns foo, using fmt=' <i>{}</i> ' would give you <i>foo</i> . To control what the widget outputs in the first place, use the format paramater of the widget (if it has one).
font	'sans'	Default font
fontshadow	None	font shadow color, default is None(no shadow)
fontsize	None	Font size. Calculated if None.
foreground	'ffffff'	Foreground colour
format	'speed'	Type of info to display "speed" or "name"
hide_crash	False	Don't display error in bar if widget crashes on startup.
markup	True	Whether or not to use pango markup
max_chars	0	Maximum number of characters to display in widget.
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions and lazy calls.
padding	None	Padding. Calculated if None.
rotate	True	Rotate text in vertical bar.
scroll	False	Whether text should be scrolled. When True, you must set the widget's width.
scroll_clear	False	Whether text should scroll completely away (True) or stop when the end of the text is shown (False)
scroll_delay	2	Number of seconds to pause before starting scrolling and restart- ing/clearing text at end
scroll_fixed_wid	False	When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text.
scroll_hide	False	Whether the widget should hide when scrolling has finished
scroll_interval	0.1	Time in seconds before next scrolling step
scroll_repeat	True	Whether text should restart scrolling once the text has ended
scroll_step	1	Number of pixels to scroll with each step
update_interval	0.5	Update Time in seconds.

Click to view the available commands for She

8.57. She 175

8.58 Spacer

class libqtile.widget.Spacer(*args, **kwargs)

Just an empty space on the bar

Often used with length equal to bar.STRETCH to push bar widgets to the right or bottom edge of the screen.

Parameters

length

Length of the widget. Can be either bar. STRETCH or a length in pixels.

width

DEPRECATED, same as length.

Supported bar orientations: horizontal and vertical

Configuration options

key	default	description
background	None	Widget background color
hide_crash	False	Don't display error in bar if widget crashes on startup.
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions and lazy calls.

Available commands

Click to view the available commands for Spacer

8.59 StatusNotifier

class libqtile.widget.StatusNotifier(*args, **kwargs)

A 'system tray' widget using the freedesktop StatusNotifierItem specification.

As per the specification, app icons are first retrieved from the user's current theme. If this is not available then the app may provide its own icon. In order to use this functionality, users are recommended to install the pyxdg module to support retrieving icons from the selected theme. If the icon specified by StatusNotifierItem can not be found in the user's current theme and no other icons are provided by the app, a fallback icon is used.

Left-clicking an icon will trigger an activate event.

Note: Context menus are not currently supported by the official widget. However, a modded version of the widget which provides basic menu support is available from elParaguayo's qtile-extras repo.

Supported bar orientations: horizontal and vertical

Configuration options

key	default	description
background	None	Widget background color
hide_crash	False	Don't display error in bar if widget crashes on startup.
icon_size	16	Icon width
icon_theme	None	Name of theme to use for app icons
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions and lazy calls.
padding	3	Padding between icons

Click to view the available commands for StatusNotifier

8.60 StockTicker

```
class libqtile.widget.StockTicker(*args, **kwargs)
```

A stock ticker widget, based on the alphavantage API. Users must acquire an API key from https://www.alphavantage.co/support/#api-key

The widget defaults to the TIME_SERIES_INTRADAY API function (i.e. stock symbols), but arbitrary Alpha Vantage API queries can be made by passing extra arguments to the constructor.

```
# Display AMZN
widget.StockTicker(apikey=..., symbol="AMZN")

# Display BTC
widget.StockTicker(
    apikey=..., function="DIGITAL_CURRENCY_INTRADAY", symbol="BTC", market="USD"
)
```

Supported bar orientations: horizontal and vertical

Configuration options

key	default	description
background	None	Widget background color
data	None	Post Data
direction	'default'	Override the text direction in vertical bar, has no effect on text in horizontal bar.default: text displayed based on vertical bar position (left/right)ttb: text read from top to bottom, btt: text read from bottom to top.'default', 'ttb', 'btt'
fmt	'{}'	Format to apply to the string returned by the widget. Main purpose: applying markup. For a widget that returns foo, using fmt=' <i>{}</i> ' would give you <i>foo</i> . To control what the widget outputs in the first place, use the format paramater of the widget (if it has one).
font	'sans'	Default font
fontshadow	None	font shadow color, default is None(no shadow)
fontsize	None	Font size. Calculated if None.
foreground	'ffffff'	Foreground colour

continues on next page

8.60. StockTicker 177

Table 18 – continued from previous page

key	default	description
func	'TIME_SERIES_INT	The default API function to query
function	'TIME_SERIES_INT	DEPRECATED: Use func.
headers	{}	Extra Headers
hide_crash	False	Don't display error in bar if widget crashes on startup.
interval	'1min'	The default latency to query
json	True	Is Json?
markup	True	Whether or not to use pango markup
max_chars	0	Maximum number of characters to display in widget.
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions and lazy calls.
padding	None	Padding. Calculated if None.
parse	None	Parse Function
rotate	True	Rotate text in vertical bar.
scroll	False	Whether text should be scrolled. When True, you must set the widget's width.
scroll_clear	False	Whether text should scroll completely away (True) or stop when the end of the text is shown (False)
scroll_delay	2	Number of seconds to pause before starting scrolling and restarting/clearing text at end
scroll_fixed_wid	False	When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text.
scroll_hide	False	Whether the widget should hide when scrolling has finished
scroll_interval	0.1	Time in seconds before next scrolling step
scroll_repeat	True	Whether text should restart scrolling once the text has ended
scroll_step	1	Number of pixels to scroll with each step
update_interval	600	Update interval in seconds, if none, the widget updates only once.
url	None	Url
user_agent	'Qtile'	Set the user agent
xml	False	Is XML?

Click to view the available commands for StockTicker

8.61 SwapGraph

class libqtile.widget.SwapGraph(*args, **kwargs)

Display a swap info graph.

Widget requirements: psutil.

Supported bar orientations: horizontal only

Configuration options

key	default	description
background	None	Widget background color
border_color	'215578'	Widget border color
border_width	2	Widget border width
fill_color	'1667EB.3'	Fill color for linefill graph
frequency	1	Update frequency in seconds
graph_color	'18BAEB'	Graph color
hide_crash	False	Don't display error in bar if widget crashes on startup.
line_width	3	Line width
margin_x	3	Margin X
margin_y	3	Margin Y
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions and lazy calls.
samples	100	Count of graph samples.
start_pos	'bottom'	Drawer starting position ('bottom'/'top')
type	'linefill'	'box', 'line', 'linefill'

Click to view the available commands for SwapGraph

8.62 SwayNC

class libqtile.widget.SwayNC(*args, **kwargs)

A simple widget for the Sway Notification Center.

The widget can display the number of notifications as well as the do not disturb status.

Left-clicking on the widget will toggle the panel. Right-clicking will toggle the do not disturb status.

Supported bar orientations: horizontal and vertical Only available on the following backends: wayland

Configuration options

8.62. SwayNC 179

key	default	description
background	None	Widget background color
direction	'default'	Override the text direction in vertical bar, has no effect on text in horizontal bar.default: text displayed based on vertical bar position (left/right)ttb: text read from top to bottom, btt: text read from bottom to top.'default', 'ttb', 'btt'
dnd_status_text	('DND ', '')	Text to show do-not-disturb status. Tuple of text ('on', 'off').
fmt	'{}'	Format to apply to the string returned by the widget. Main purpose: applying markup. For a widget that returns foo, using fmt=' <i>{i>{i>' would give you <i>foo</i> what the widget outputs in the first place, use the format paramater of the widget (if it has one).</i>
font	'sans'	Default font
fontshadow	None	font shadow color, default is None(no shadow)
fontsize	None	Font size. Calculated if None.
foreground	'ffffff'	Foreground colour
format	'{dnd}{num}'	Text to display.
hide_crash	False	Don't display error in bar if widget crashes on startup.
markup	True	Whether or not to use pango markup
max_chars	0	Maximum number of characters to display in widget.
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions and lazy calls.
padding	None	Padding. Calculated if None.
rotate	True	Rotate text in vertical bar.
scroll	False	Whether text should be scrolled. When True, you must set the widget's width.
scroll_clear	False	Whether text should scroll completely away (True) or stop when the end of the text is shown (False)
scroll_delay	2	Number of seconds to pause before starting scrolling and restarting/clearing text at end
scroll_fixed_wid	False	When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text.
scroll_hide	False	Whether the widget should hide when scrolling has finished
scroll_interval	0.1	Time in seconds before next scrolling step
scroll_repeat	True	Whether text should restart scrolling once the text has ended
scroll_step	1	Number of pixels to scroll with each step
swaync_client	None	Command to execute.

Click to view the available commands for SwayNC

8.63 Systray

class libqtile.widget.Systray(*args, **kwargs)

A widget that manages system tray.

Only one Systray widget is allowed. Adding additional Systray widgets will result in a ConfigError.

Note: Icons will not render correctly where the bar/widget is drawn with a semi-transparent background. Instead, icons will be drawn with a transparent background.

If using this widget it is therefore recommended to use a fully opaque background colour or a fully transparent one.

Supported bar orientations: horizontal and vertical Only available on the following backends: x11

Configuration options

key	default	description
background	None	Widget background color
hide_crash	False	Don't display error in bar if widget crashes on startup.
icon_size	20	Icon width
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions and lazy calls.
padding	5	Padding between icons

Available commands

Click to view the available commands for Systray

8.64 TaskList

class libqtile.widget.TaskList(*args, **kwargs)

Displays the icon and name of each window in the current group

Contrary to WindowTabs this is an interactive widget. The window that currently has focus is highlighted.

Optional requirements: pyxdg is needed to use theme icons and to display icons on Wayland.

Supported bar orientations: horizontal and vertical

Configuration options

key	default	description
background	None	Widget background color
border	'215578'	Border colour
borderwidth	2	Current group border width
font	'sans'	Default font
fontshadow	None	font shadow color, default is None(no shadow)
fontsize	None	Font size. Calculated if None.

continues on next page

8.63. Systray 181

Table 19 – continued from previous page

	Table 19 –	continued from previous page
key	default	description
foreground	'ffffff'	Foreground colour
hide_crash	False	Don't display error in bar if widget crashes on startup.
highlight_method	'border'	Method of highlighting (one of 'border' or 'block') Uses *_border color settings
icon_size	None	Icon size. (Calculated if set to None. Icons are hidden if set to 0.)
margin	3	Margin inside the box
margin_x	None	X Margin. Overrides 'margin' if set
margin_y	None	Y Margin. Overrides 'margin' if set
markup_floating	None	Text markup of the floating window state. Supports pangomarkup with markup=True.e.g., "{}" or " {} "
markup_focused	None	Text markup of the focused window state. Supports pangomarkup with markup=True.e.g., "{}" or " {} "
markup_focused_f	None	Text markup of the focused and floating window state. Supports pangomarkup with markup=True.e.g., "{}" or " {} "
markup_maximized	None	Text markup of the maximized window state. Supports pangomarkup with markup=True.e.g., "{}" or " {} "
markup_minimized	None	Text markup of the minimized window state. Supports pangomarkup with markup=True.e.g., "{}" or " {} "
markup_normal	None	Text markup of the normal window state. Supports pangomarkup with markup=True.e.g., "{}" or " {} "
<pre>max_title_width</pre>	None	Max size in pixels of task title.(if set to None, as much as available.)
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions and lazy calls.
padding	3	Padding inside the box
padding_x	None	X Padding. Overrides 'padding' if set
padding_y	None	Y Padding. Overrides 'padding' if set
parse_text	None	Function to parse and modify window names. e.g. function in config that removes excess strings from window name: def my_func(text) for string in [" - Chromium", " - Firefox"]: text = text.replace(string, "") return textthen set option parse_text=my_func
rounded	True	To round or not to round borders
spacing	None	Spacing between tasks.(if set to None, will be equal to margin_x)
stretch	True	Widget fills available space in bar. Set to <i>False</i> to limit widget width to size of its contents.
theme_mode	None	When to use theme icons. <i>None</i> = never, <i>preferred</i> = use if available, <i>fallback</i> = use if app does not provide icon directly. <i>preferred</i> and <i>fallback</i> have identical behaviour on Wayland.
theme_path	None	Path to icon theme to be used by pyxdg for icons. None will use default icon theme.
title_width_meth	None	Method to compute the width of task title. (None, 'uniform'.)Defaults to None, the normal behaviour.

continues on next page

Table 19 – continued from previous page

key	default	description
txt_floating	'Υ'	Text representation of the floating window state. e.g., "V " or " "
txt_maximized	'[] '	Text representation of the maximized window state. e.g., "[] " or " " $\!\!\!$
txt_minimized	'- '	Text representation of the minimized window state. e.g., " $_$ " or " "
unfocused_border	None	Border color for unfocused windows. Affects only hight-light_method 'border' and 'block'. Defaults to None, which means no special color.
urgent_alert_met	'border'	Method for alerting you of WM urgent hints (one of 'border' or 'text')
urgent_border	'FF0000'	Urgent border color
window_name_loca	False	Whether to show the location of the window in the title.
window_name_loca	0	The offset given to the window location

Click to view the available commands for TaskList

8.65 TextBox

class libqtile.widget.TextBox(*args, **kwargs)

A flexible textbox that can be updated from bound keys, scripts, and qshell.

Supported bar orientations: horizontal and vertical

Configuration options

8.65. TextBox 183

key	default	description
background	None	Widget background color
direction	'default'	Override the text direction in vertical bar, has no effect on text in horizontal bar.default: text displayed based on vertical bar position (left/right)ttb: text read from top to bottom, btt: text read from bottom to top.'default', 'ttb', 'btt'
fmt	'{}'	Format to apply to the string returned by the widget. Main purpose: applying markup. For a widget that returns foo, using fmt=' <i>{}</i> ' would give you <i>foo</i> . To control what the widget outputs in the first place, use the format paramater of the widget (if it has one).
font	'sans'	Text font
fontshadow	None	font shadow color, default is None(no shadow)
fontsize	None	Font pixel size. Calculated if None.
foreground	'#ffffff'	Foreground colour.
hide_crash	False	Don't display error in bar if widget crashes on startup.
markup	True	Whether or not to use pango markup
max_chars	0	Maximum number of characters to display in widget.
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions and lazy calls.
padding	None	Padding left and right. Calculated if None.
rotate	True	Rotate text in vertical bar.
scroll	False	Whether text should be scrolled. When True, you must set the widget's width.
scroll_clear	False	Whether text should scroll completely away (True) or stop when the end of the text is shown (False)
scroll_delay	2	Number of seconds to pause before starting scrolling and restarting/clearing text at end
scroll_fixed_wid		When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text.
scroll_hide	False	Whether the widget should hide when scrolling has finished
scroll_interval	0.1	Time in seconds before next scrolling step
scroll_repeat	True	Whether text should restart scrolling once the text has ended
scroll_step	1	Number of pixels to scroll with each step

Click to view the available commands for TextBox

8.66 ThermalSensor

class libqtile.widget.ThermalSensor(*args, **kwargs)

Widget to display temperature sensor information

For using the thermal sensor widget you need to have lm-sensors installed. You can get a list of the tag_sensors executing "sensors" in your terminal. Then you can choose which you want, otherwise it will display the first available.

Widget requirements: psutil.

Supported bar orientations: horizontal and vertical

Configuration options

key	default	description
background	None	Widget background color
direction	'default'	Override the text direction in vertical bar, has no effect on text in horizontal bar.default: text displayed based on vertical bar position (left/right)ttb: text read from top to bottom, btt: text read from bottom to top.'default', 'ttb', 'btt'
fmt	'{}'	Format to apply to the string returned by the widget. Main purpose: applying markup. For a widget that returns foo, using fmt=' <i>{}</i> ' would give you <i>foo</i> . To control what the widget outputs in the first place, use the format paramater of the widget (if it has one).
font	'sans'	Default font
fontshadow	None	font shadow color, default is None(no shadow)
fontsize	None	Font size. Calculated if None.
foreground	'ffffff'	Foreground colour
foreground_alert	'ff0000'	Foreground colour alert
format	'{temp:. 1f}{unit}'	Display string format. Three options available: $\{temp\}$ - temperature, $\{tag\}$ - tag of the temperature sensor, and $\{unit\}$ - $^{\circ}C$ or $^{\circ}F$
hide_crash	False	Don't display error in bar if widget crashes on startup.
markup	True	Whether or not to use pango markup
max_chars	0	Maximum number of characters to display in widget.
metric	True	True to use metric/C, False to use imperial/F
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions and lazy calls.
padding	None	Padding. Calculated if None.
rotate	True	Rotate text in vertical bar.
scroll	False	Whether text should be scrolled. When True, you must set the widget's width.
scroll_clear	False	Whether text should scroll completely away (True) or stop when the end of the text is shown (False)
scroll_delay	2	Number of seconds to pause before starting scrolling and restart- ing/clearing text at end
scroll_fixed_wid	False	When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text.
scroll_hide	False	Whether the widget should hide when scrolling has finished
scroll_interval	0.1	Time in seconds before next scrolling step
scroll_repeat	True	Whether text should restart scrolling once the text has ended
scroll_step	1	Number of pixels to scroll with each step
tag_sensor	None	Tag of the temperature sensor. For example: "temp1" or "Core 0 "
threshold	70	If the current temperature value is above, then change to fore-ground_alert colour
update_interval	2	Update interval in seconds

Available commands

Click to view the available commands for ThermalSensor

8.66. ThermalSensor

8.67 ThermalZone

class libqtile.widget.ThermalZone(*args, **kwargs)

Thermal zone widget.

This widget was made to read thermal zone files and transform values to human readable format. You can set zone parameter to any standard thermal zone file from /sys/class/thermal directory.

Supported bar orientations: horizontal only

Configuration options

key	default	description
background	None	Widget background color
crit	70	Critical temperature level
direction	'default'	Override the text direction in vertical bar, has no effect on text in horizontal bar.default: text displayed based on vertical bar position (left/right)ttb: text read from top to bottom, btt: text read from bottom to top.'default', 'ttb', 'btt'
fgcolor_crit	'ff0000'	Font color on critical values
fgcolor_high	'ffaa00'	Font color on high values
fgcolor_normal	'ffffff'	Font color on normal values
fmt	'{}'	Format to apply to the string returned by the widget. Main purpose: applying markup. For a widget that returns foo, using fmt=' <i>{}</i> ' would give you <i>foo</i> . To control what the widget outputs in the first place, use the format paramater of the widget (if it has one).
font	'sans'	Default font
fontshadow	None	font shadow color, default is None(no shadow)
fontsize	None	Font size. Calculated if None.
foreground	'ffffff'	Foreground colour
format	'{temp}°C'	Display format
format_crit	'{temp}°C CRIT!'	Critical display format
hidden	False	Set True to only show if critical value reached
hide_crash	False	Don't display error in bar if widget crashes on startup.
high	50	High themperature level
markup	True	Whether or not to use pango markup
max_chars	0	Maximum number of characters to display in widget.
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions and lazy calls.
padding	None	Padding. Calculated if None.
rotate	True	Rotate text in vertical bar.
scroll	False	Whether text should be scrolled. When True, you must set the widget's width.
scroll_clear	False	Whether text should scroll completely away (True) or stop when the end of the text is shown (False)
scroll_delay	2	Number of seconds to pause before starting scrolling and restart- ing/clearing text at end
scroll_fixed_wid	False	When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text.

continues on next page

Table 20 - continued from previous page

key	default	description
scroll_hide	False	Whether the widget should hide when scrolling has finished
scroll_interval	0.1	Time in seconds before next scrolling step
scroll_repeat	True	Whether text should restart scrolling once the text has ended
scroll_step	1	Number of pixels to scroll with each step
update_interval	2.0	Update interval
zone	'/sys/class/ thermal/ thermal_zone0/ temp'	Thermal zone

Click to view the available commands for ThermalZone

8.68 TunedManager

class libqtile.widget.TunedManager(*args, **kwargs)

A widget to interact with the Tuned power management daemon. It always displays the name of the currently active profile.

The user can define a list of profiles to be used, 3 default profiles exist. These 3 are the default profiles on RHEL and Fedora Linux.

A left click on the widget will go to the next layout in the list, a right click will go to the previous one. If the end of the list is reached, it cycles back to the beginning. Scrolling can also be used to cycle through the list, though keep in mind that switching the profile takes a while and so scrolling through the list quickly is not feasible.

Supported bar orientations: horizontal only

Configuration options

key	default	description
background	None	Widget background color
direction	'default'	Override the text direction in vertical bar, has no effect on text in horizontal bar.default: text displayed based on vertical bar position (left/right)ttb: text read from top to bottom, btt: text read from bottom to top.'default', 'ttb', 'btt'
fmt	'{}'	Format to apply to the string returned by the widget. Main purpose: applying markup. For a widget that returns foo, using fmt=' <i>{}</i> ' would give you <i>foo</i> . To control what the widget outputs in the first place, use the format paramater of the widget (if it has one).
font	'sans'	Default font
fontshadow	None	font shadow color, default is None(no shadow)
fontsize	None	Font size. Calculated if None.
foreground	'ffffff'	Foreground colour
hide_crash	False	Don't display error in bar if widget crashes on startup.
markup	True	Whether or not to use pango markup
max_chars	0	Maximum number of characters to display in widget.
modes	['powersave', 'balanced-batter	The modes to cycle through
mouse_callbacks	<pre>'throughput-perf {}</pre>	Dict of mouse button press callback functions. Accepts functions and lazy calls.
padding	None	Padding. Calculated if None.
rotate	True	Rotate text in vertical bar.
scroll	False	Whether text should be scrolled. When True, you must set the widget's width.
scroll_clear	False	Whether text should scroll completely away (True) or stop when the end of the text is shown (False)
scroll_delay	2	Number of seconds to pause before starting scrolling and restarting/clearing text at end
scroll_fixed_wid	False	When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text.
scroll_hide	False	Whether the widget should hide when scrolling has finished
scroll_interval	0.1	Time in seconds before next scrolling step
scroll_repeat	True	Whether text should restart scrolling once the text has ended
scroll_step	1	Number of pixels to scroll with each step
update_interval	600	Update interval in seconds, if none, the widget updates only once.

Click to view the available commands for TunedManager

8.69 VerticalClock

class libqtile.widget.VerticalClock(*args, **kwargs)

A simple but flexible text-based clock for vertical bars.

 $Unlike the \ Clock \ widget, \ Vertical Clock \ will \ display \ text \ horizontally \ in \ the \ bar.$

Supported bar orientations: vertical only

Configuration options

8.69. VerticalClock

key	default	description
background	None	Widget background color
direction	'default'	Override the text direction in vertical bar, has no effect on text in horizontal bar.default: text displayed based on vertical bar position (left/right)ttb: text read from top to bottom, btt: text read from bottom to top.'default', 'ttb', 'btt'
fmt	'{}'	Format to apply to the string returned by the widget. Main purpose: applying markup. For a widget that returns foo, using fmt=' <i>{}</i> ' would give you <i>foo</i> . To control what the widget outputs in the first place, use the format paramater of the widget (if it has one).
font	'sans'	Default font
fontshadow	None	font shadow color, default is None(no shadow)
fontsize	None	Font size. A single value will be applied to all fields. Alternatively, users can provide a list of sizes with each size being applied to the corresponding text format.
foreground	'fff'	Text colour. A single string will be applied to all fields. Alternatively, users can provide a list of strings with each colour being applied to the corresponding text format.
format	['%H', '%M']	A list of Python datetime format string. Each string is printed as a separate line.
hide_crash	False	Don't display error in bar if widget crashes on startup.
markup	True	Whether or not to use pango markup
max_chars	0	Maximum number of characters to display in widget.
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions and lazy calls.
padding	None	Padding. Calculated if None.
rotate	True	Rotate text in vertical bar.
scroll	False	Whether text should be scrolled. When True, you must set the widget's width.
scroll_clear	False	Whether text should scroll completely away (True) or stop when the end of the text is shown (False)
scroll_delay	2	Number of seconds to pause before starting scrolling and restarting/clearing text at end
scroll_fixed_wid	False	When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text.
scroll_hide	False	Whether the widget should hide when scrolling has finished
scroll_interval	0.1	Time in seconds before next scrolling step
scroll_repeat	True	Whether text should restart scrolling once the text has ended
scroll_step	1	Number of pixels to scroll with each step
timezone	None	The timezone to use for this clock, either as string if pytz or dateutil is installed (e.g. "US/Central" or anything in /usr/share/zoneinfo), or as tzinfo (e.g. datetime.timezone.utc). None means the system local timezone and is the default.
update_interval	1.0	Update interval for the clock

Click to view the available commands for <code>VerticalClock</code>

8.70 Volume

class libqtile.widget.Volume(*args, **kwargs)

Widget that display and change volume

By default, this widget uses amixer to get and set the volume so users will need to make sure this is installed. Alternatively, users may set the relevant parameters for the widget to use a different application.

If theme_path is set it draw widget as icons.

Supported bar orientations: horizontal only

Configuration options

key	default	description
background	None	Widget background color
cardid	None	Card Id
channel	'Master'	Channel
check_mute_comma	None	Command to check mute status
check_mute_strin	'[off]'	String expected from check_mute_command when volume is muted. When the output of the command matches this string, theaudio source is treated as muted.
device	'default'	Device Name
direction	'default'	Override the text direction in vertical bar, has no effect on text in horizontal bar.default: text displayed based on vertical bar position (left/right)ttb: text read from top to bottom, btt: text read from bottom to top.'default', 'ttb', 'btt'
emoji	False	Use emoji to display volume states, only if theme_path is not set. The specified font needs to contain the correct unicode characters.
emoji_list	['', '', '',	List of emojis/font-symbols to display volume states, only if emoji is set. List contains 4 symbols, from lowest volume to highest.
fmt	'{}'	Format to apply to the string returned by the widget. Main purpose: applying markup. For a widget that returns foo, using fmt=' <i>{}</i> ' would give you <i>foo</i> . To control what the widget outputs in the first place, use the format paramater of the widget (if it has one).
font	'sans'	Default font
fontshadow	None	font shadow color, default is None(no shadow)
fontsize	None	Font size. Calculated if None.
foreground	'ffffff'	Foreground colour
get_volume_comma	None	Command to get the current volume. The expected output should include 1-3 numbers and a % sign.
hide_crash	False	Don't display error in bar if widget crashes on startup.
markup	True	Whether or not to use pango markup
max_chars	0	Maximum number of characters to display in widget.
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions and lazy calls.
mute_command	None	Mute command
mute_foreground	None	Foreground color for mute volume.
mute_format	'M'	Format to display when volume is muted.
padding	3	Padding left and right. Calculated if None.

continues on next page

8.70. Volume 191

Table 21 – continued from previous page

key	default	description
rotate	True	Rotate text in vertical bar.
scroll	False	Whether text should be scrolled. When True, you must set the widget's width.
scroll_clear	False	Whether text should scroll completely away (True) or stop when the end of the text is shown (False)
scroll_delay	2	Number of seconds to pause before starting scrolling and restarting/clearing text at end
scroll_fixed_wid	False	When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text.
scroll_hide	False	Whether the widget should hide when scrolling has finished
scroll_interval	0.1	Time in seconds before next scrolling step
scroll_repeat	True	Whether text should restart scrolling once the text has ended
scroll_step	1	Number of pixels to scroll with each step
step	2	Volume change for up an down commands in percentage. Only used if volume_up_command and volume_down_command are not set.
theme_path	None	Path of the icons
unmute_format	'{volume}%'	Format of text to display when volume is not muted.
update_interval	0.2	Update time in seconds.
volume_app	None	App to control volume
volume_down_comm	None	Volume down command
volume_up_comman	None	Volume up command

Click to view the available commands for Volume

8.71 Wallpaper

class libqtile.widget.Wallpaper(*args, **kwargs)

Supported bar orientations: horizontal and vertical

Configuration options

key	default	description
background	None	Widget background color
direction	'default'	Override the text direction in vertical bar, has no effect on text in horizontal bar.default: text displayed based on vertical bar position (left/right)ttb: text read from top to bottom, btt: text read from bottom to top.'default', 'ttb', 'btt'
directory	<pre>'~/Pictures/ wallpapers/'</pre>	Wallpaper Directory
fmt	'{}'	Format to apply to the string returned by the widget. Main purpose: applying markup. For a widget that returns foo, using fmt=' <i>{}</i> ' would give you <i>foo</i> . To control what the widget outputs in the first place, use the format paramater of the widget (if it has one).
font	'sans'	Default font
fontshadow	None	font shadow color, default is None(no shadow)
fontsize	None	Font size. Calculated if None.
foreground	'ffffff'	Foreground colour
hide_crash	False	Don't display error in bar if widget crashes on startup.
label	None	Use a fixed label instead of image name.
markup	True	Whether or not to use pango markup
max_chars	0	Maximum number of characters to display in widget.
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions and lazy calls.
option	'fill'	How to fit the wallpaper when wallpaper_command isNone. None, 'fill' or 'stretch'.
padding	None	Padding. Calculated if None.
random_selection	False	If set, use random initial wallpaper and randomly cycle through the wallpapers.
rotate	True	Rotate text in vertical bar.
scroll	False	Whether text should be scrolled. When True, you must set the widget's width.
scroll_clear	False	Whether text should scroll completely away (True) or stop when the end of the text is shown (False)
scroll_delay	2	Number of seconds to pause before starting scrolling and restart- ing/clearing text at end
scroll_fixed_wid	False	When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text.
scroll_hide	False	Whether the widget should hide when scrolling has finished
scroll_interval	0.1	Time in seconds before next scrolling step
scroll_repeat	True	Whether text should restart scrolling once the text has ended
scroll_step	1	Number of pixels to scroll with each step
wallpaper	None	Wallpaper
wallpaper_comman	['feh', 'bg-fill']	Wallpaper command. If None, thewallpaper will be painted without the use of a helper.

Click to view the available commands for Wallpaper

8.71. Wallpaper 193

8.72 WidgetBox

class libqtile.widget.WidgetBox(*args, **kwargs)

A widget to declutter your bar.

WidgetBox is a widget that hides widgets by default but shows them when the box is opened.

Widgets that are hidden will still update etc. as if they were on the main bar.

Button clicks are passed to widgets when they are visible so callbacks will work.

Widgets in the box also remain accessible via command interfaces.

Widgets can only be added to the box via the configuration file. The widget is configured by adding widgets to the "widgets" parameter as follows:

```
widget.WidgetBox(widgets=[
    widget.TextBox(text="This widget is in the box"),
    widget.Memory()
    ]
),
```

Supported bar orientations: horizontal only

Configuration options

key	default	description
background	None	Widget background color
close_button_loc	'left'	Location of close button when box open ('left' or 'right')
direction	'default'	Override the text direction in vertical bar, has no effect on text in horizontal bar.default: text displayed based on vertical bar position (left/right)ttb: text read from top to bottom, btt: text read from bottom to top.'default', 'ttb', 'btt'
fmt	'{}'	Format to apply to the string returned by the widget. Main purpose: applying markup. For a widget that returns foo, using fmt=' <i>{}</i> ' would give you <i>foo</i> . To control what the widget outputs in the first place, use the format paramater of the widget (if it has one).
font	'sans'	Default font
fontshadow	None	font shadow color, default is None(no shadow)
fontsize	None	Font size. Calculated if None.
foreground	'ffffff'	Foreground colour
hide_crash	False	Don't display error in bar if widget crashes on startup.
markup	True	Whether or not to use pango markup
max_chars	0	Maximum number of characters to display in widget.
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions and lazy calls.
padding	None	Padding. Calculated if None.
rotate	True	Rotate text in vertical bar.
scroll	False	Whether text should be scrolled. When True, you must set the widget's width.
scroll_clear	False	Whether text should scroll completely away (True) or stop when the end of the text is shown (False)
scroll_delay	2	Number of seconds to pause before starting scrolling and restarting/clearing text at end
scroll_fixed_wid	False	When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text.
scroll_hide	False	Whether the widget should hide when scrolling has finished
scroll_interval	0.1	Time in seconds before next scrolling step
scroll_repeat	True	Whether text should restart scrolling once the text has ended
scroll_step	1	Number of pixels to scroll with each step
start_opened	False	Spawn the box opened
text_closed	'[<]'	Text when box is closed
text_open	'[>]'	Text when box is open
widgets	[]	A list of widgets to include in the box

Click to view the available commands for WidgetBox

8.72. WidgetBox 195

8.73 WindowCount

class libqtile.widget.WindowCount(*args, **kwargs)

A simple widget to display the number of windows in the current group of the screen on which the widget is.

Supported bar orientations: horizontal and vertical

Configuration options

key	default	description
background	None	Widget background color
direction	'default'	Override the text direction in vertical bar, has no effect on text in horizontal bar.default: text displayed based on vertical bar position (left/right)ttb: text read from top to bottom, btt: text read from bottom to top.'default', 'ttb', 'btt'
fmt	'{}'	Format to apply to the string returned by the widget. Main purpose: applying markup. For a widget that returns foo, using fmt=' <i>{}</i> ' would give you <i>foo</i> . To control what the widget outputs in the first place, use the format paramater of the widget (if it has one).
font	'sans'	Text font
fontshadow	None	font shadow color, default is None(no shadow)
fontsize	None	Font pixel size. Calculated if None.
foreground	'#ffffff'	Foreground colour.
hide_crash	False	Don't display error in bar if widget crashes on startup.
markup	True	Whether or not to use pango markup
max_chars	0	Maximum number of characters to display in widget.
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions and lazy calls.
padding	None	Padding left and right. Calculated if None.
rotate	True	Rotate text in vertical bar.
scroll	False	Whether text should be scrolled. When True, you must set the widget's width.
scroll_clear	False	Whether text should scroll completely away (True) or stop when the end of the text is shown (False)
scroll_delay	2	Number of seconds to pause before starting scrolling and restart- ing/clearing text at end
scroll_fixed_wid	False	When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text.
scroll_hide	False	Whether the widget should hide when scrolling has finished
scroll_interval	0.1	Time in seconds before next scrolling step
scroll_repeat	True	Whether text should restart scrolling once the text has ended
scroll_step	1	Number of pixels to scroll with each step
show_zero	False	Show window count when no windows
text_format	'{num}'	Format for message

Available commands

Click to view the available commands for WindowCount

8.74 WindowName

class libqtile.widget.WindowName(*args, **kwargs)

Displays the name of the window that currently has focus

Supported bar orientations: horizontal and vertical

Configuration options

key	default	description
background	None	Widget background color
direction	'default'	Override the text direction in vertical bar, has no effect on text in horizontal bar.default: text displayed based on vertical bar position (left/right)ttb: text read from top to bottom, btt: text read from bottom to top.'default', 'ttb', 'btt'
empty_group_stri	1 1	string to display when no windows are focused on current group
fmt	'{}'	Format to apply to the string returned by the widget. Main purpose: applying markup. For a widget that returns foo, using fmt=' <i>{}</i> ' would give you <i>foo</i> . To control what the widget outputs in the first place, use the format paramater of the widget (if it has one).
font	'sans'	Default font
fontshadow	None	font shadow color, default is None(no shadow)
fontsize	None	Font size. Calculated if None.
<pre>for_current_scre</pre>	False	instead of this bars screen use currently active screen
foreground	'ffffff'	Foreground colour
format	'{state}{name}'	format of the text
hide_crash	False	Don't display error in bar if widget crashes on startup.
markup	True	Whether or not to use pango markup
max_chars	0	Maximum number of characters to display in widget.
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions and lazy calls.
padding	None	Padding. Calculated if None.
parse_text	None	Function to parse and modify window names. e.g. function in config that removes excess strings from window name: def my_func(text) for string in [" - Chromium", " - Firefox"]: text = text.replace(string, "") return textthen set option parse_text=my_func
rotate	True	Rotate text in vertical bar.
scroll	False	Whether text should be scrolled. When True, you must set the widget's width.
scroll_clear	False	Whether text should scroll completely away (True) or stop when the end of the text is shown (False)
scroll_delay	2	Number of seconds to pause before starting scrolling and restart- ing/clearing text at end
scroll_fixed_wid	False	When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text.
scroll_hide	False	Whether the widget should hide when scrolling has finished
scroll_interval	0.1	Time in seconds before next scrolling step
scroll_repeat	True	Whether text should restart scrolling once the text has ended
scroll_step	1	Number of pixels to scroll with each step

8.74. WindowName

Click to view the available commands for WindowName

8.75 WindowTabs

class libqtile.widget.WindowTabs(*args, **kwargs)

Displays the name of each window in the current group. Contrary to TaskList this is not an interactive widget. The window that currently has focus is highlighted.

Supported bar orientations: horizontal and vertical

Configuration options

key	default	description
background	None	Widget background color
direction	'default'	Override the text direction in vertical bar, has no effect on text in horizontal bar.default: text displayed based on vertical bar position (left/right)ttb: text read from top to bottom, btt: text read from bottom to top.'default', 'ttb', 'btt'
fmt	'{}'	Format to apply to the string returned by the widget. Main purpose: applying markup. For a widget that returns foo, using fmt=' <i>{}</i> ' would give you <i>foo</i> . To control what the widget outputs in the first place, use the format paramater of the widget (if it has one).
font	'sans'	Default font
fontshadow	None	font shadow color, default is None(no shadow)
fontsize	None	Font size. Calculated if None.
foreground	'ffffff'	Foreground colour
hide_crash	False	Don't display error in bar if widget crashes on startup.
markup	True	Whether or not to use pango markup
max_chars	0	Maximum number of characters to display in widget.
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions and lazy calls.
padding	None	Padding. Calculated if None.
parse_text	<pre><function <lambda="" windowtabs.=""> at 0x7500c1279ee0></function></pre>	Function to modify window names. It must accept a string argument (original window name) and return a string with the modified name.
rotate	True	Rotate text in vertical bar.
scroll	False	Whether text should be scrolled. When True, you must set the widget's width.
scroll_clear	False	Whether text should scroll completely away (True) or stop when the end of the text is shown (False)
scroll_delay	2	Number of seconds to pause before starting scrolling and restarting/clearing text at end
scroll_fixed_wid	False	When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text.
scroll_hide	False	Whether the widget should hide when scrolling has finished
scroll_interval	0.1	Time in seconds before next scrolling step
scroll_repeat	True	Whether text should restart scrolling once the text has ended
scroll_step	1	Number of pixels to scroll with each step
selected	(' ', '<!--<br-->b>')	Selected task indicator
separator	' '	Task separator text.

Click to view the available commands for *WindowTabs*

8.75. WindowTabs

8.76 Wlan

class libqtile.widget.Wlan(*args, **kwargs)

Displays Wifi SSID and quality.

Widget requirements: iwlib.

Supported bar orientations: horizontal only

Configuration options

key	default	description
background	None	Widget background color
direction	'default'	Override the text direction in vertical bar, has no effect on text in horizontal bar.default: text displayed based on vertical bar position (left/right)ttb: text read from top to bottom, btt: text read from bottom to top.'default', 'ttb', 'btt'
disconnected_mes		String to show when the wlan is diconnected.
ethernet_interfa	'eth0'	The ethernet interface to monitor, NOTE: If you do not have a wlan device in your system, ethernet functionality will not work, use the Net widget instead
ethernet_message		String to show when ethernet is being used. For IP of ethernet interface use {ipaddr}.
fmt	'{}'	Format to apply to the string returned by the widget. Main purpose: applying markup. For a widget that returns foo, using fmt=' <i>{}</i> ' would give you <i>foo</i> . To control what the widget outputs in the first place, use the format paramater of the widget (if it has one).
font	'sans'	Default font
fontshadow	None	font shadow color, default is None(no shadow)
fontsize	None	Font size. Calculated if None.
foreground	'ffffff'	Foreground colour
format	'{essid} {quality}/ 70'	Display format. For percents you can use "{essid} {percent:2.0%}". For IP of wlan interface use {ipaddr}.
hide_crash	False	Don't display error in bar if widget crashes on startup.
interface	'wlan0'	The interface to monitor
markup	True	Whether or not to use pango markup
max_chars	0	Maximum number of characters to display in widget.
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions and lazy calls.
padding	None	Padding. Calculated if None.
rotate	True	Rotate text in vertical bar.
scroll	False	Whether text should be scrolled. When True, you must set the widget's width.
scroll_clear	False	Whether text should scroll completely away (True) or stop when the end of the text is shown (False)
scroll_delay	2	Number of seconds to pause before starting scrolling and restarting/clearing text at end
scroll_fixed_wid		When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text.
scroll_hide	False	Whether the widget should hide when scrolling has finished
scroll_interval	0.1	Time in seconds before next scrolling step
scroll_repeat	True	Whether text should restart scrolling once the text has ended
scroll_step	1	Number of pixels to scroll with each step
update_interval	1	The update interval.
use_ethernet	False	Activate or deactivate checking for ethernet when no wlan connection is detected

Click to view the available commands for Wlan

8.76. Wlan 201

8.77 Wttr

class libqtile.widget.Wttr(*args, **kwargs)

Display weather widget provided by wttr.in.

To specify your own custom output format, use the special %-notation (example: 'My_city: %t(%f), wind: %w'):

- %c Weather condition,
- %C Weather condition textual name,
- %h Humidity,
- %t Temperature (Actual),
- %f Temperature (Feels Like),
- %w Wind,
- %l Location,
- %m Moonphase,
- %M Moonday,
- %p precipitation (mm),
- %P pressure (hPa),
- %D Dawn!,
- %S Sunrise!,
- %z Zenith!,
- %s Sunset!,
- %d Dusk!. (!times are shown in the local timezone)

Add the character ~ at the beginning to get weather for some special location: ~Vostok Station or ~Eiffel Tower.

Also can use IP-addresses (direct) or domain names (prefixed with @) to specify a location: @github.com, 123.456.678.123

Specify multiple locations as dictionary

```
location={
    'Minsk': 'Minsk',
    '64.127146,-21.873472': 'Reykjavik',
}
```

Cities will change randomly every update.

Supported bar orientations: horizontal and vertical

Configuration options

key	default	description
background	None	Widget background color
data	None	Post Data

continues on next page

Table 22 – continued from previous page

		continued from previous page
key	default	description
direction	'default'	Override the text direction in vertical bar, has no effect on text in horizontal bar.default: text displayed based on vertical bar position (left/right)ttb: text read from top to bottom, btt: text read from bottom to top.'default', 'ttb', 'btt'
fmt	'{}'	Format to apply to the string returned by the widget. Main purpose: applying markup. For a widget that returns foo, using fmt=' <i>{}</i> ' would give you <i>foo</i> . To control what the widget outputs in the first place, use the format paramater of the widget (if it has one).
font	'sans'	Default font
fontshadow	None	font shadow color, default is None(no shadow)
fontsize	None	Font size. Calculated if None.
foreground	'ffffff'	Foreground colour
format	'3'	Display text format. Choose presets in range 1-4 (Ex. "1") or build your own custom output format, use the special %-notation. See https://github.com/chubin/wttr.in#one-line-output
headers	{}	Extra Headers
hide_crash	False	Don't display error in bar if widget crashes on startup.
json	False	Is Json?
lang	'en'	Display text language. List of supported languages https://wttr. in/:translation
location	{}	Dictionary. Key is a city or place name, or GPS coordinates. Value is a display name. If the dictionary is empty, the location will be determined based on your IP address.
markup	True	Whether or not to use pango markup
max_chars	0	Maximum number of characters to display in widget.
mouse_callbacks	{}	Dict of mouse button press callback functions. Accepts functions and lazy calls.
padding	None	Padding. Calculated if None.
parse	None	Parse Function
rotate	True	Rotate text in vertical bar.
scroll	False	Whether text should be scrolled. When True, you must set the widget's width.
scroll_clear	False	Whether text should scroll completely away (True) or stop when the end of the text is shown (False)
scroll_delay	2	Number of seconds to pause before starting scrolling and restart- ing/clearing text at end
scroll_fixed_wid	False	When scroll=True the width parameter is a maximum width and, when text is shorter than this, the widget will resize. Setting scroll_fixed_width=True will force the widget to have a fixed width, regardless of the size of the text.
scroll_hide	False	Whether the widget should hide when scrolling has finished
scroll_interval	0.1	Time in seconds before next scrolling step
scroll_repeat	True	Whether text should restart scrolling once the text has ended
scroll_step	1	Number of pixels to scroll with each step
units	'm'	'm' - metric, 'M' - show wind speed in m/s, 'u' - United States units
update_interval	600	Update interval in seconds. Recommendation: if you want to display multiple locations alternately, maybe set a smaller interval, ex. 30.

continues on next page

8.77. Wttr 203

Table 22 – continued from previous page

key	default	description
url	None	Url
user_agent	'Qtile'	Set the user agent
xml	False	Is XML?

Click to view the available commands for Wttr

CHAPTER

NINE

BUILT-IN HOOKS

```
subscribe.addgroup()
```

Called when a new group is added

Arguments

· name of new group

Example:

```
from libqtile import hook
from libqtile.utils import send_notification

@hook.subscribe.addgroup
def group_added(group_name):
    send_notification("qtile", f"New group added: {group_name}")
```

subscribe.changegroup()

Called whenever a group change occurs.

The following changes will result in this hook being fired: 1) New group added (unlike addgroup, no group name is passed with this hook) 2) Group deleted (unlike delgroup, no group name is passed with this hook) 3) Groups order is changed 4) Group is renamed

Arguments

None

Example:

```
from libqtile import hook
from libqtile.utils import send_notification

@hook.subscribe.changegroup
def change_group():
    send_notification("qtile", "Change group event")
```

subscribe.client_focus()

Called whenever focus moves to a client window

Arguments

• Window object of the new focus.

```
from libqtile import hook
from libqtile.utils import send_notification

@hook.subscribe.client_focus
def client_focus(client):
    send_notification("qtile", f"{client.name} has been focused")
```

subscribe.client_killed()

Called after a client has been unmanaged. This hook is not called for internal windows.

Arguments

• Window object of the killed window.

Example:

```
from libqtile import hook
from libqtile.utils import send_notification

@hook.subscribe.client_killed
def client_killed(client):
    send_notification("qtile", f"{client.name} has been killed")
```

subscribe.client_managed()

Called after Qtile starts managing a new client

Called after a window is assigned to a group, or when a window is made static. This hook is not called for internal windows.

Arguments

· Window object of the managed window

Example:

```
from libqtile import hook
from libqtile.utils import send_notification

@hook.subscribe.client_managed
def client_managed(client):
    send_notification("qtile", f"{client.name} has been managed by qtile")
```

subscribe.client_mouse_enter()

Called when the mouse enters a client

Arguments

• Window of window entered

```
from libqtile import hook
from libqtile.utils import send_notification

@hook.subscribe.client_mouse_enter
def client_mouse_enter(client):
    send_notification("qtile", f"Mouse has entered {client.name}")
```

subscribe.client_name_updated()

Called when the client name changes

Arguments

• Window of client with updated name

Example:

```
from libqtile import hook
from libqtile.utils import send_notification

@hook.subscribe.client_name_updated
def client_name_updated(client):
    send_notification(
        "qtile",
        f"Client's has been updated to {client.name}"
    )
```

subscribe.client_new()

Called before Qtile starts managing a new client

Use this hook to declare windows static, or add them to a group on startup. This hook is not called for internal windows. Use group_window_add for focus decisions.

Arguments

• Window object

Example:

```
from libqtile import hook

@hook.subscribe.client_new
def new_client(client):
    if client.name == "xterm":
        client.togroup("a")
    elif client.name == "dzen":
        client.static(0)
```

subscribe.client_urgent_hint_changed()

Called when the client urgent hint changes

Arguments

• Window of client with hint change

```
from libqtile import hook
from libqtile.utils import send_notification

@hook.subscribe.client_urgent_hint_changed
def client_urgency_change(client):
    send_notification(
        "qtile",
        f"{client.name} has changed its urgency state"
    )
```

subscribe.current_screen_change()

Called when the current screen (i.e. the screen with focus) changes

Arguments

None

Example:

```
from libqtile import hook
from libqtile.utils import send_notification

@hook.subscribe.current_screen_change
def screen_change():
    send_notification("qtile", "Current screen change detected.")
```

subscribe.delgroup()

Called when group is deleted

Arguments

· name of deleted group

Example:

```
from libqtile import hook
from libqtile.utils import send_notification

@hook.subscribe.delgroup
def group_deleted(group_name):
    send_notification("qtile", f"Group deleted: {group_name}")
```

subscribe.enter_chord()

Called when key chord begins

Note: if you only want to use this chord to display the chord name then you should use the Chord widget.

Arguments

• name of chord(mode)

Example:

```
from libqtile import hook
from libqtile.utils import send_notification

@hook.subscribe.enter_chord
def enter_chord(chord_name):
    send_notification("qtile", "Started {chord_name} key chord.")
```

subscribe.float_change()

Called when a change in float state is made (e.g. toggle floating, minimised and fullscreen states)

Arguments

None

```
from libqtile import hook
from libqtile.utils import send_notification

@hook.subscribe.float_change
def float_change():
    send_notification("qtile", "Window float state changed.")
```

subscribe.focus_change()

Called when focus is changed, including moving focus between groups or when focus is lost completely (i.e. when a window is closed.)

Arguments

None

Example:

```
from libqtile import hook
from libqtile.utils import send_notification

@hook.subscribe.focus_change
def focus_changed():
    send_notification("qtile", "Focus changed.")
```

subscribe.group_window_add()

Called when a new window is added to a group

This hook can for example be used for focus decisions.

Arguments

- Group receiving the new window
- Window added to the group

Example:

```
from libqtile import hook
from libqtile import qtile

@hook.subscribe.group_window_add
def group_window_add(group, window):
    #disallow focus steals except if there's no focus
    if not qtile.current_window:
        return
    window.can_steal_focus = False
```

subscribe.group_window_remove()

Called when a window is removed from a group

Arguments

- Group removing the window
- Window removed from the group

```
from libqtile import hook
from libqtile.utils import send_notification

@hook.subscribe.group_window_remove
def group_window_remove(group, window):
    send_notification("qtile", f"Window {window.name} removed from {group.name}")
```

subscribe.layout_change()

Called on layout change event (including when a new group is displayed on the screen)

Arguments

- · layout object for new layout
- group object on which layout is changed

Example:

```
from libqtile import hook
from libqtile.utils import send_notification

@hook.subscribe.layout_change
def layout_change(layout, group):
    send_notification(
        "qtile",
            f"{layout.name} is now on group {group.name}"
    )
```

subscribe.leave_chord()

Called when key chord ends

Arguments

None

Example:

```
from libqtile import hook
from libqtile.utils import send_notification

@hook.subscribe.leave_chord
ded leave_chord():
    send_notification("qtile", "Key chord exited")
```

subscribe.net_wm_icon_change()

Called on _NET_WM_ICON change

X11 only. Called when a window notifies that it has changed its icon.

Arguments

• Window of client with changed icon

Example:

```
from libqtile import hook
from libqtile.utils import send_notification
```

(continues on next page)

(continued from previous page)

```
@hook.subscribe.net_wm_icon_change
def icon_change(client):
    send_notification("qtile", f"{client.name} has changed its icon")
```

subscribe.plasma_add_mode()

Used to flag when the add mode of the Plasma layout has changed.

The hooked function should take one argument being the layout object.

subscribe.restart()

Called before qtile is restarted.

This hook fires before qtile restarts but after qtile has checked that it is able to restart (i.e. the config file is valid).

Arguments

None

Example:

```
from libqtile import hook
from libqtile.utils import send_notification

@hook.subscribe.restart
def run_every_startup():
    send_notification("qtile", "Restarting...")
```

subscribe.resume()

Called when system wakes up from sleep, suspend or hibernate.

Relies on systemd's inhibitor dbus interface, via the dbus-fast package.

Note: the hook is not fired when resuming from shutdown/reboot events. Use the "startup" hooks for those scenarios.

Arguments

None

subscribe.screen_change()

Called when the output configuration is changed (e.g. via randr in X11).

Note: If you have reconfigure_screens = True in your config then qtile will automatically reconfigure your screens when it detects a change to the screen configuration. This hook is fired *before* that reconfiguration takes place. The screens_reconfigured hook should be used where you want to trigger an event after the reconfiguration.

Arguments

• xproto.randr.ScreenChangeNotify event (X11) or None (Wayland).

Example:

```
from libqtile import hook
from libqtile.utils import send_notification

@hook.subscribe.screen_change
```

(continues on next page)

(continued from previous page)

```
def screen_change(event):
    send_notification("qtile", "Screen change detected.")
```

subscribe.screens_reconfigured()

Called once qtile.reconfigure_screens has completed (e.g. if reconfigure_screens is set to True in your config).

Arguments

None

Example:

```
from libqtile import hook
from libqtile.utils import send_notification

@hook.subscribe.screens_reconfigured
def screen_reconf():
    send_notification("qtile", "Screens have been reconfigured.")
```

subscribe.selection_change()

Called on selection change

X11 only. Fired when a selection property is changed (e.g. new selection created or existing selection is emptied)

Arguments

- · name of the selection
- dictionary describing selection, containing owner and selection as keys

The selection owner will typically be "PRIMARY" when contents is highlighted and "CLIPBOARD" when contents is actively copied to the clipboard, e.g. with Ctrl + C.

Example:

```
from libqtile import hook
from libqtile.utils import send_notification

@hook.subscribe.selection_change
def selection_change(name, selection):
    send_notification(
        "qtile",
        f"Window {selection['owner']} has changed the {name} selection."
    )
```

subscribe.selection_notify()

Called on selection notify

X11 only. Fired when a selection is made in a window.

Arguments

- name of the selection
- dictionary describing selection, containing owner and selection as keys

The selection owner will typically be "PRIMARY" when contents is highlighted and "CLIPBOARD" when contents is actively copied to the clipboard, e.g. with Ctrl + C.

Example:

```
from libqtile import hook
from libqtile.utils import send_notification

@hook.subscribe.selection_notify
def selection_notify(name, selection):
    send_notification(
        "qtile",
        f"Window {selection['owner']} has made a selection in the {name} selection."
    )
```

subscribe.setgroup()

Called when group is put on screen.

This hook is fired in 3 situations: 1) When the screen changes to a new group 2) When two groups are switched 3) When a screen is focused

Arguments

None

Example:

```
from libqtile import hook
from libqtile.utils import send_notification

@hook.subscribe.setgroup
def setgroup():
    send_notification("qtile", "Group set")
```

subscribe.shutdown()

Called before qtile is shutdown.

Using a long-running command in this function will cause the shutdown to be delayed.

This hook is only fired when qtile is shutting down, if you want a command to be run when the system sleeps then you should use the suspend hook instead.

Arguments

None

Example:

```
import os
import subprocess

from libqtile import hook

@hook.subscribe.shutdown
def autostart:
    script = os.path.expanduser("~/.config/qtile/shutdown.sh")
    subprocess.run([script])
```

subscribe.startup()

Called when qtile is started. Unlike startup_once, this hook is fired on every start, including restarts.

When restarting, this hook is fired after quile has restarted but before quile tries to restore the session to the same state that it was in before the restart.

Arguments

None

Example:

```
import subprocess

from libqtile import hook
from libqtile.utils import send_notification

@hook.subscribe.startup
def run_every_startup():
    send_notification("qtile", "Startup")
```

subscribe.startup_complete()

Called when gtile is started after all resources initialized.

This is the same as startup with the only difference being that this hook is fired after the saved state has been restored.

Arguments

None

Example:

```
import subprocess

from libqtile import hook
from libqtile.utils import send_notification

@hook.subscribe.startup_complete
def run_every_startup():
    send_notification("qtile", "Startup complete")
```

subscribe.startup_once()

Called when Qtile has started on first start

This hook is called exactly once per session (i.e. not on each lazy.restart()).

Arguments

None

Example:

```
import os
import subprocess

from libqtile import hook

@hook.subscribe.startup_once
def autostart():
    script = os.path.expanduser("~/.config/qtile/autostart.sh")
    subprocess.run([script])
```

subscribe.suspend()

Called when system is about to sleep, suspend or hibernate.

Relies on systemd's inhibitor dbus interface, via the dbus-fast package.

When this hook is used, qtile will set an inhibitor that prevent the system from sleeping. The inhibitor is removed as soon as your function exits. You should therefore not use long-running code in this function.

Please note, this inhibitor will also only delay, not block, the computer's ability to sleep. The default delay is 5 seconds. If your function has not completed within that time, the machine will still sleep (see important note below).

You can increase this delay by setting InhibitDelayMaxSec in logind.conf. see: https://www.freedesktop.org/software/systemd/man/logind.conf.html

In addition, closing a laptop lid will ignore inhibitors by default. You can override this by setting LidSwitchIgnoreInhibited=no in /etc/systemd/logind.conf.

Important: The logind service creates an inhibitor by passing a reference to a lock file which must be closed to release the lock. Additional references to the lock may be created if you spawn processes with the subprocess module and these processes are running when the machine tries to suspend. As a result, it is strongly recommended that you launch any processes with qtile.spawn(...) as this will not create additional copies of the lock.

Arguments

None

Example:

```
from libqtile import hook, qtile

@hook.subscribe.suspend
def lock_on_sleep():
    # Run screen locker
    qtile.spawn("/path/to/screen_locker")
```

subscribe.user()

Use to create user-defined hooks.

The purpose of these hooks is to allow a hook to be fired by an external application.

Hooked functions can receive arguments but it is up to the application firing the hook to ensure the correct arguments are passed. No checking will be performed by qtile.

Example:

```
from libqtile import hook
from libqtile.log_utils import logger

@hook.subscribe.user("my_custom_hook")
def hooked_function():
   logger.warning("Custom hook received.")
```

The external script can then call the hook with the following command:

```
qtile cmd-obj -o cmd -f fire_user_hook -a my_custom_hook
```

Note: If the script will be run by a different user then you will need to pass the path to the socket file used by the current process. One way to achieve this is to specify a path for the socket when starting qtile e.g. qtile start -s /tmp/qtile.socket. When firing the hook, you should then call qtile cmd-obj -o cmd -f fire_user_hook -a my_custom_hook -s /tmp/qtile.socket However, the same socket will need to be passed wherever you run qtile cmd-obj or qtile shell.

BUILT-IN EXTENSIONS

10.1 CommandSet

class libqtile.extension.CommandSet(**config)

Give list of commands to be executed in dmenu style.

ex. manage mocp deamon:

```
Key([mod], 'm', lazy.run_extension(extension.CommandSet(
    commands={
        'play/pause': '[ $(mocp -i | wc -l) -lt 2 ] && mocp -p || mocp -G',
        'next': 'mocp -f',
        'previous': 'mocp -r',
        'quit': 'mocp -x',
        'open': 'urxvt -e mocp',
        'shuffle': 'mocp -t shuffle',
        'repeat': 'mocp -t repeat',
      },
    pre_commands=['[ $(mocp -i | wc -l) -lt 1 ] && mocp -S'],
    **Theme.dmenu))),
```

ex. CommandSet inside another CommandSet

Configuration options

key	default	description	
background	None	defines the normal background color (#RGB or #RRGGBB)	
command	None	the command to be launched (string or list with arguments)	
commands	None	dictionary of commands where key is runable command	
dmenu_bottom	False	dmenu appears at the bottom of the screen	
dmenu_command	'dmenu'	the dmenu command to be launched	
dmenu_font	None	override the default 'font' and 'fontsize' options for dmenu	
dmenu_height	None	defines the height (only supported by some dmenu forks)	
dmenu_ignorecase	False	dmenu matches menu items case insensitively	
dmenu_lines	None	dmenu lists items vertically, with the given number of lines	
dmenu_prompt	None	defines the prompt to be displayed to the left of the input field	
font	'sans'	defines the font name to be used	
fontsize	None	defines the font size to be used	
foreground	None	defines the normal foreground color (#RGB or #RRGGBB)	
pre_commands	None	list of commands to be executed before getting dmenu answer	
selected_backgro	None	defines the selected background color (#RGB or #RRGGBB)	
selected_foregro	None	defines the selected foreground color (#RGB or #RRGGBB)	

10.2 Dmenu

class libqtile.extension.Dmenu(**config)

Python wrapper for dmenu http://tools.suckless.org/dmenu/

Configuration options

key	default	description	
background	None	defines the normal background color (#RGB or #RRGGBB)	
command	None	the command to be launched (string or list with arguments)	
dmenu_bottom	False	dmenu appears at the bottom of the screen	
dmenu_command	'dmenu'	the dmenu command to be launched	
dmenu_font	None	override the default 'font' and 'fontsize' options for dmenu	
dmenu_height	None	defines the height (only supported by some dmenu forks)	
dmenu_ignorecase	False	dmenu matches menu items case insensitively	
dmenu_lines	None	dmenu lists items vertically, with the given number of lines	
dmenu_prompt	None	defines the prompt to be displayed to the left of the input field	
font	'sans'	defines the font name to be used	
fontsize	None	defines the font size to be used	
foreground	None	defines the normal foreground color (#RGB or #RRGGBB)	
selected_backgro	None	defines the selected background color (#RGB or #RRGGBB)	
selected_foregro	None	defines the selected foreground color (#RGB or #RRGGBB)	

10.3 DmenuRun

class libqtile.extension.DmenuRun(**config)

Special case to run applications.

config.py should have something like:

Configuration options

key	default	description
background	None	defines the normal background color (#RGB or #RRGGBB)
command	None	the command to be launched (string or list with arguments)
dmenu_bottom	False	dmenu appears at the bottom of the screen
dmenu_command	'dmenu_run'	the dmenu command to be launched
dmenu_font	None	override the default 'font' and 'fontsize' options for dmenu
dmenu_height	None	defines the height (only supported by some dmenu forks)
dmenu_ignorecase	False	dmenu matches menu items case insensitively
dmenu_lines	None	dmenu lists items vertically, with the given number of lines
dmenu_prompt	None	defines the prompt to be displayed to the left of the input field
font	'sans'	defines the font name to be used
fontsize	None	defines the font size to be used
foreground	None	defines the normal foreground color (#RGB or #RRGGBB)
selected_backgro	None	defines the selected background color (#RGB or #RRGGBB)
selected_foregro	None	defines the selected foreground color (#RGB or #RRGGBB)

10.4 J4DmenuDesktop

class libqtile.extension.J4DmenuDesktop(**config)

Python wrapper for j4-dmenu-desktop https://github.com/enkore/j4-dmenu-desktop

Configuration options

10.3. DmenuRun 219

key	default	description	
background	None	defines the normal background color (#RGB or #RRGGBB)	
command	None	the command to be launched (string or list with arguments)	
dmenu_bottom	False	dmenu appears at the bottom of the screen	
dmenu_command	'dmenu'	the dmenu command to be launched	
dmenu_font	None	override the default 'font' and 'fontsize' options for dmenu	
dmenu_height	None	defines the height (only supported by some dmenu forks)	
dmenu_ignorecase	False	dmenu matches menu items case insensitively	
dmenu_lines	None	dmenu lists items vertically, with the given number of lines	
dmenu_prompt	None	defines the prompt to be displayed to the left of the input field	
font	'sans'	defines the font name to be used	
fontsize	None	defines the font size to be used	
foreground	None	defines the normal foreground color (#RGB or #RRGGBB)	
j4dmenu_command	'j4-dmenu-deskto	the dmenu command to be launched	
j4dmenu_display_	False	display binary name after each entry	
j4dmenu_generic	True	include the generic name of desktop entries	
j4dmenu_terminal	None	terminal emulator used to start terminal apps	
j4dmenu_usage_lc	None	file used to sort items by usage frequency	
j4dmenu_use_xdg_	False	read \$XDG_CURRENT_DESKTOP to determine the desktop	
		environment	
selected_backgro	None	defines the selected background color (#RGB or #RRGGBB)	
selected_foregro	None	defines the selected foreground color (#RGB or #RRGGBB)	

10.5 RunCommand

class libqtile.extension.RunCommand(**config)

Run an arbitrary command.

Mostly useful as a superclass for more specific extensions that need to interact with the qtile object.

Also consider simply using lazy.spawn() or writing a client.

Configuration options

key	default	description
background	None	defines the normal background color (#RGB or #RRGGBB)
command	None	the command to be launched (string or list with arguments)
font	'sans'	defines the font name to be used
fontsize	None	defines the font size to be used
foreground	None	defines the normal foreground color (#RGB or #RRGGBB)
selected_backgro	None	defines the selected background color (#RGB or #RRGGBB)
selected_foregro	None	defines the selected foreground color (#RGB or #RRGGBB)

10.6 WindowList

class libqtile.extension.WindowList(**config)

Give vertical list of all open windows in dmenu. Switch to selected.

Configuration options

key	default	description
all_groups	True	If True, list windows from all groups; otherwise only from the current group
background	None	defines the normal background color (#RGB or #RRGGBB)
command	None	the command to be launched (string or list with arguments)
dmenu_bottom	False	dmenu appears at the bottom of the screen
dmenu_command	'dmenu'	the dmenu command to be launched
dmenu_font	None	override the default 'font' and 'fontsize' options for dmenu
dmenu_height	None	defines the height (only supported by some dmenu forks)
dmenu_ignorecase	False	dmenu matches menu items case insensitively
dmenu_lines	'80'	Give lines vertically. Set to None get inline
dmenu_prompt	None	defines the prompt to be displayed to the left of the input field
font	'sans'	defines the font name to be used
fontsize	None	defines the font size to be used
foreground	None	defines the normal foreground color (#RGB or #RRGGBB)
item_format	'{group}.{id}: {window}'	the format for the menu items
selected_backgro	None	defines the selected background color (#RGB or #RRGGBB)
selected_foregro	None	defines the selected foreground color (#RGB or #RRGGBB)


10.6. WindowList


CHAPTER


ELEVEN

KEYBINDINGS IN IMAGES

11.1 Default configuration







11.2 Generate your own images

Qtile provides a tiny helper script to generate keybindings images from a config file. In the repository, the script is located under scripts/gen-keybinding-img.

This script accepts a configuration file and an output directory. If no argument is given, the default configuration will be used and files will be placed in same directory where the command has been run.

CHAPTER

TWELVE

WINDOW STACKING

A number of window commands (move_up/down(), bring_to_front() etc.) relate to the stacking order of windows. The aim of this page is to provide more details as to how stacking is implemented in Qtile.

Important: Currently, stacking is only implemented in the X11 background. Support will be added to the Wayland backend in future and this page will be updated accordingly.

12.1 Layer priority groups

We have tried to adhere to the EWMH specification. Windows are therefore stacked, from the bottom, according to the following priority rules:

- windows of type NET WM TYPE DESKTOP
- windows having state _NET_WM_STATE_BELOW
- · windows not belonging in any other layer
- windows of type _NET_WM_TYPE_DOCK (unless they have state _NET_WM_TYPE_BELOW) and windows having state _NET_WM_STATE_ABOVE
- focused windows having state _NET_WM_STATE_FULLSCREEN

Qtile had then added an additional layer so that Scratchpad windows are placed above everything else.

Tiled windows will open in the default, "windows not belonging in any other layer", layer. If floats_kept_above is set to True in the config then new floating windows will have the _NET_WM_STATE_ABOVE property set which will ensure they remain above tiled windows.

12.2 Moving windows

Imagine you have four tiled windows stacked (from the top) as follows:

```
"One"
"Two"
"Three"
"Four"
```

If you call move_up() on window "Four", the result will be:

```
"One"
"Two"
"Four"
"Three"
```

If you now call move_to_top() on window "Three", the result will be:

```
"Three"
"One"
"Two"
"Four"
```

Note: bring_to_front() has a special behaviour in Qtile. This will bring any window to the very top of the stack, disregarding the priority rules set out above. When that window loses focus, it will be restacked in the appropriate location.

This can cause undesirable results if the config contains <code>bring_front_click=True</code> and the user has an app like a dock which is activated by mousing over the window. In this situation, tiled windows will be displayed above the dock making it difficult to activate. To fix this, set <code>bring_front_click</code> to <code>False</code> to disable the behaviour completely, or "floating_only" to only have this behaviour apply to floating windows.

CHAPTER

THIRTEEN

ARCHITECTURE

This page explains how Qtile's API works and how it can be accessed. Users who just want to find a list of commands can jump to *the API commands page*.

Qtile's command API is based on a graph of objects, where each object has a set of associated commands, combined with a number of interfaces that are used to navigate the graph and execute associated commands.

This page gives an overview of the command graph and the various interfaces accessible by users. The documentation also contains details of all the commands that are exposed by objects on the graph.

Note: While users are able to access the internal python objects (e.g. via a qtile instance), this is not part of the "official" API. These objects and method are not currently included in the documentation but can be viewed by looking at the source code on github. Changes to commonly-used internal objects will be kept to a minimum.

The graph and object commands are used in a number of different places:

- Commands can be *bound to keys* in the Qtile configuration file using the lazy interface.
- Commands can be called from a script using one of the various *available interfaces* to interact with Qtile from Python or shell scripts.


A couple of additional options are available if you are looking for more interactive access:

- Commands can be called through qtile shell, the Qtile shell.
- The shell can also be hooked into a Jupyter kernel *called iqshell* (NB this interface is currently broken).

If the explanations in the pages below seems a bit complex, please take a moment to explore the API using the qtile shell command shell. The shell provides a way to navigate the graph, allowing you to see how nodes are connected. Available nodes can be displayed with the ls command while command lists and detailed documentation can be accessed from the built-in help command. Commands can also be executed from this shell.

13.1 The Command Graph

The objects in Qtile's command graph come in eight flavours, matching the eight basic components of the window manager: layouts, windows, groups, bars, widgets, screens, core, and a special root node. Objects are addressed by a path specification that starts at the root and follows the available paths in the graph. This is what the graph looks like:



Each arrow can be read as "holds a reference to". So, we can see that a widget object *holds a reference to* objects of type bar and screen. Let's start with some simple examples of how the addressing works. Which particular objects we hold reference to depends on the context - for instance, widgets hold a reference to the screen that they appear on, and the bar they are attached to.

Let's look at an example, starting at the root node. The following script runs the status command on the root node, which, in this case, is represented by the InteractiveCommandClient object:

```
from libqtile.command.client import InteractiveCommandClient
c = InteractiveCommandClient()
print(c.status())
```

The InteractiveCommandClient is a class that allows us to traverse the command graph using attributes to select child nodes or commands. In this example, we have resolved the status() command on the root object. The interactive command client will automatically find and connect to a running Qtile instance, and which it will use to dispatch the call and print out the return.

An alternative is to use the CommandClient, which allows for a more precise resolution of command graph objects, but is not as easy to interact with from a REPL:

```
from libqtile.command.client import CommandClient

(continues on next page)
```

(continued from previous page)

```
c = CommandClient()
print(c.call("status"))
```

Like the interactive client, the command client will automatically connect to a running Qtile instance. Here, we first resolve the status() command with the .call("status"), which simply located the function, then we can invoke the call with no arguments.

For the rest of this example, we will use the interactive command client. From the graph, we can see that the root node holds a reference to group nodes. We can access the "info" command on the current group like so:

```
c.group.info()
```

To access a specific group, regardless of whether or not it is current, we use the Python mapping lookup syntax. This command sends group "b" to screen 1 (by the libqtile.config.Group.toscreen() method):

```
c.group["b"].toscreen(1)
```

In different contexts, it is possible to access a default object, where in other contexts a key is required. From the root of the graph, the current group, layout, screen and window can be accessed by simply leaving the key specifier out. The key specifier is mandatory for widget and bar nodes.

With this context, we can now drill down deeper in the graph, following the edges in the graphic above. To access the screen currently displaying group "b", we can do this:

```
c.group["b"].screen.info()
```

Be aware, however, that group "b" might not currently be displayed. In that case, it has no associated screen, the path resolves to a non-existent node, and we get an exception:

```
libqtile.command.CommandError: No object screen in path 'group['b'].screen'
```

The graph is not a tree, since it can contain cycles. This path (redundantly) specifies the group belonging to the screen that belongs to group "b":

```
c.group["b"].screen.group
```

This amount of connectivity makes it easy to reach out from a given object when callbacks and events fire on that object to related objects.

13.2 Navigating the command graph

As noted previously, some objects require a selector to ensure that the correct object is selected, while other nodes provide a default object without a selector.

The table below shows what selectors are required for the different nodes and whether the selector is optional (i.e. if it can be omitted to select the default object).

Object	Key	Optional?	Example
bar		No	
	"top", "bottom" (Note: if accessing this node from the root, users on multi-monitor setups may wish to navigate via a screen node to ensure that they select the correct object.)		c.screen.bar["bottom"]
group	Name string	Yes	c.group["one"] c.group
layout	Integer index	Yes	c.layout[2] c.layout
screen	Integer index	Yes	c.screen[1] c.screen
widget	Widget name (This is usually the name of the widget class in lower case but can be set by passing the name parameter to the widget.)	No	c.widget["textbox"]
window	Integer window ID	Yes	c.window[123456] c.window
core	No	n/a	c.core

13.3 Command graph development

This page provides further detail on how Qtile's command graph works. If you just want to script your Qtile window manager the *earlier information*, in addition to the documentation on the *available commands* should be enough to get started.

To develop the Qtile manager itself, we can dig into how Qtile represents these objects, which will lead to the way the commands are dispatched.

13.3.1 Client-Server Scripting Model

Qtile has a client-server control model - the main Qtile instance listens on a named pipe, over which marshalled command calls and response data is passed. This allows Qtile to be controlled fully from external scripts. Remote interaction occurs through an instance of the libqtile.command.interface.IPCCommandInterface class. This class establishes a connection to the currently running instance of Qtile. A libqtile.command.client. InteractiveCommandClient can use this connection to dispatch commands to the running instance. Commands then appear as methods with the appropriate signature on the InteractiveCommandClient object. The object hierarchy is described in the *Architecture* section of this manual. Full command documentation is available through the *Otile Shell*.

13.3.2 Digging Deeper: Command Objects

All of the configured objects setup by Qtile are CommandObject subclasses. These objects are so named because we can issue commands against them using the command scripting API. Looking through the code, the commands that are exposed are commands that are decorated with the <code>@expose_command()</code> decorator. When writing custom layouts, widgets, or any other object, you can add your own custom functions and, once you add the decorator, they will be callable using the standard command infrastructure. An available command can be extracted by calling <code>.command()</code> with the name of the command.

In addition to having a set of associated commands, each command object also has a collection of items associated with it. This is what forms the graph that is shown above. For a given object type, the items() method returns all of the names of the associated objects of that type and whether or not there is a defaultable value. For example, from the root, .items("group") returns the name of all of the groups and that there is a default value, the currently focused group.

To navigate from one command object to the next, the .select() method is used. This method resolves a requested object from the command graph by iteratively selecting objects. A selector like [("group", "b"), ("screen", None)] would be to first resolve group "b", then the screen associated to the group.

13.3.3 The Command Graph

In order to help in specifying command objects, there is the abstract command graph structure. The command graph structure allows us to address any valid command object and issue any command against it without needing to have any Qtile instance running or have anything to resolve the objects to. This is particularly useful when constructing lazy calls, where the Qtile instance does not exist to specify the path that will be resolved when the command is executed. The only limitation of traversing the command graph is that it must follow the allowed edges specified in the first section above.

Every object in the command graph is represented by a CommandGraphNode. Any call can be resolved from a given node. In addition, each node knows about all of the children objects that can be reached from it and have the ability to .navigate() to the other nodes in the command graph. Each of the object types are represented as CommandGraphObject types and the root node of the graph, the CommandGraphRoot represents the Qtile instance.

When a call is performed on an object, it returns a CommandGraphCall. Each call will know its own name as well as be able to resolve the path through the command graph to be able to find itself.

Note that the command graph itself can standalone, there is no other functionality within Qtile that it relies on. While we could have started here and built up, it is helpful to understand the objects that the graph is meant to represent, as the graph is just a representation of a traversal of the real objects in a running Qtile window manager. In order to tie the running Qtile instance to the abstract command graph, we move on to the command interface.

13.3.4 Executing graph commands: Command Interface

The CommandInterface is what lets us take an abstract call on the command graph and resolve it against a running command object. Put another way, this is what takes the graph traversal .group["b"].screen.info() and executes the info() command against the addressed screen object. Additional functionality can be used to check that a given traversal resolves to actual objects and that the requested command actually exists. Note that by construction of the command graph, the traversals here must be feasible, even if they cannot be resolved for a given configuration state. For example, it is possible to check the screen associated to a group, even though the group may not be on a screen, but it is not possible to check the widget associated to a group.

The simplest form of the command interface is the QtileCommandInterface, which can take an in-process Qtile instance as the root CommandObject and execute requested commands. This is typically how we run the unit tests for Qtile.

The other primary example of this is the IPCCommandInterface which is able to then route all calls through an IPC client connected to a running Qtile instance. In this case, the command graph call can be constructed on the client side without having to dispatch to Qtile and once the call is constructed and deemed valid, the call can be executed.

In both of these cases, executing a command on a command interface will return the result of executing the command on a running Qtile instance. To support lazy execution, the LazyCommandInterface instead returns a LazyCall which is able to be resolved later by the running Qtile instance when it is configured to fire.

13.3.5 Tying it together: Command Client

So far, we have our running Command Objects and the Command Interface to dispatch commands against these objects as well as the Command Graph structure itself which encodes how to traverse the connections between the objects. The final component which ties everything together is the Command Client, which allows us to navigate through the graph to resolve objects, find their associated commands, and execute the commands against the held command interface.

The idea of the command client is that it is created with a reference into the command graph and a command interface. All navigation can be done against the command graph, and traversal is done by creating a new command client starting from the new node. When a command is executed against a node, that command is dispatched to the held command interface. The key decision here is how to perform the traversal. The command client exists in two different flavors: the standard CommandClient which is useful for handling more programatic traversal of the graph, calling methods to traverse the graph, and the InteractiveCommandClient which behaves more like a standard Python object, traversing by accessing properties and performing key lookups.

Returning to our examples above, we now have the full context to see what is going on when we call:

```
from libqtile.command.client import CommandClient
c = CommandClient()
print(c.call("status")())
from libqtile.command.client import InteractiveCommandClient
c = InteractiveCommandClient()
print(c.status())
```

In both cases, the command clients are constructed with the default command interface, which sets up an IPC connection to the running Qtile instance, and starts the client at the graph root. When we call c.call("status") or c.status, we navigate the command client to the status command on the root graph object. When these are invoked, the commands graph calls are dispatched via the IPC command interface and the results then sent back and printed on the local command line.

The power that can be realized by separating out the traversal and resolution of objects in the command graph from actually invoking or looking up any objects within the graph can be seen in the lazy module. By creating a lazy evaluated command client, we can expose the graph traversal and object resolution functionality via the same InteractiveCommandClient that is used to perform live command execution in the Qtile prompt.

CHAPTER

FOURTEEN

INTERFACES

14.1 Introduction

This page provides an overview of the various interfaces available to interact with Qtile's command graph.

- · lazy calls
- when running qtile shell
- when running qtile cmd-obj
- when using CommandClient or InteractiveCommandClient in python

The way that these commands are called varies depending on which option you select. However, all interfaces follow the same, basic approach: navigate to the desired object and then execute a command on that object. The following examples illustrate this principle by showing how the same command can be accessed by the various interfaces:

```
Lazy call:
lazy.widget["volume"].increase_volume()

qtile shell:
> cd widget/volume
widget[volume] > increase_volume()

qtile cmd-obj:
qtile cmd-obj -o widget volume -f increase_volume

CommandClient:
>>> from libqtile.command.client import CommandClient
>>> c = CommandClient()
>>> c.navigate("widget", "volume").call("increase_volume")

InteractiveCommandClient:
>>> from libqtile.command.client import InteractiveCommandClient
>>> c = InteractiveCommandClient()
>>> c.widget["volume"].increase_volume()
```

14.2 The Interfaces

From the examples above, you can see that there are five main interfaces which can be used to interact with Qtile's command graph. Which one you choose will depend on how you intend to use it as each interface is suited to different scenarios.

- The lazy interface is used in config scripts to bind commands to keys and mouse callbacks.
- The qtile shell is a tool for exploring the graph by presenting it as a file structure. It is not designed to be used for scripting.
- For users creating shell scripts, the qtile cmd-obj interface would be the recommended choice.
- For users wanting to control Qtile from a python script, there are two available interfaces libqtile.command.client.CommandClient and libqtile.command.client.InteractiveCommandClient. Users are advised to use the InteractiveCommandClient as this simplifies the syntax for navigating the graph and calling commands.

14.2.1 The Lazy interface

The lazy.lazy object is a special helper object to specify a command for later execution. Lazy objects are typically users' first exposure to Qtile's command graph but they may not realise it. However, understanding this will help users when they try using some of the other interfaces listed on this page.

The basic syntax for a lazy command is:

lazy.node[selector].command(arguments)

No node is required when accessing commands on the root node. In addition, multiple nodes can be sequenced if required to navigate to a specific object. For example, bind a key that would focus the next window on the active group on screen 2, you would create a lazy object as follows:

lazy.screen[1].group.next_window()

Note: As noted above, lazy calls do not call the relevant command but only create a reference to it. While this makes it ideal for binding commands to key presses and mouse_callbacks for widgets, it also means that lazy calls cannot be included in user-defined functions.

14.2.2 qtile shell

The qtile shell maps the command graph to a virtual filesystem that can be navigated in a similar way. While it is unlikely to be used for scripting, the qtile shell interface provides an excellent means for users to navigate and familiarise themselves with the command graph.

For more information, please refer to qtile shell

14.2.3 qtile cmd-obj

qtile cmd-obj is a command line interface for executing commands on the command graph. It can be used as a standalone command (e.g. executed directly from the terminal) or incorporated into shell scripts.

For more information, please refer to qtile cmd-obj

14.2.4 CommandClient

The CommandClient interface is a low-level python interface for accessing and navigating the command graph. The low-level nature means that navigation steps must be called explicitly, rather than being inferred from the body of the calling command.

For example:

```
from libqtile.command.client import CommandClient

c = CommandClient()

# Call info command on clock widget
info = c.navigate("widget", "clock").call("info")

# Call info command on the screen displaying the clock widget
info = c.navigate("widget", "clock").navigate("screen", None).call("info")
```

Note from the last example that each navigation step must be called separately. The arguments passed to navigate() are node and selector. selector is None when you wish to access the default object on that node (e.g. the current screen).

More technical explanation about the python command clients can be found at *Executing graph commands: Command Interface*.

14.2.5 InteractiveCommandClient

The InteractiveCommandClient is likely to be the more popular interface for users wishing to access the command graph via external python scripts. One of the key differences between the InteractiveCommandClient and the above CommandClient is that the InteractiveCommandClient removes the need to call navigate and call explicitly. Instead, the syntax mimics that of the lazy interface.

For example, to call the same commands in the above example:

```
from libqtile.command.client import InteractiveCommandClient

c = InteractiveCommandClient()

# Call info command on clock widget
info = c.widget["clock"].info()

# Call info command on the screen displaying the clock widget
info = c.widget["clock"].screen.info()
```

14.2. The Interfaces 239

CHAPTER

FIFTEEN


COMMANDS API

The following pages list all the commands that are exposed by Qtile's command graph. As a result, all of these commands are accessible by any of the various interfaces provided by Qtile (e.g. the lazy interface for keybindings and mouse callbacks).

15.1 Qtile root object

The root node represents the main Qtile manager instance. Many of the commands on this node are therefore related to the running of the application itself.

The root can access every other node in the command graph. Certain objects can be accessed without a selector resulting in the current object being selected (e.g. current group, screen, layout, window).



class libqtile.core.manager.Qtile

API commands

To access commands on this object via the command graph, use one of the following options:

lazy. <command/> ()
qtile cmd-obj -o cmd -f <command/>

The following commands are available for this object:

<pre>add_rule(match_args, rule_args[, min_priorty])</pre>	Add a dgroup rule, returns rule_id needed to remove it
addgroup(group[, label, layout, layouts,])	Add a group with the given name

continues on next page

Table 1 – continued from previous page

	lued from previous page
change_window_order(new_location)	Change the order of the current window within the current group.
commands()	Returns a list of possible commands for this object
critical()	Set log level to CRITICAL
debug()	Set log level to DEBUG
delgroup(group)	Delete a group with the given name
display_kb()	Display table of key bindings
doc(name)	Returns the documentation for a specified command
doc(name)	name
error()	Set log level to ERROR
eval(code)	Evaluates code in the same context as this function
findwindow([prompt, widget])	Launch prompt widget to find a window of the giver
(thromby, wiegerl)	name
<pre>fire_user_hook(hook_name, *args)</pre>	Fire a custom hook.
function(function, *args, **kwargs)	Call a function with current object as argument
<pre>get_groups()</pre>	Return a dictionary containing information for all
5 <u>5</u> F - ()	groups
<pre>get_screens()</pre>	Return a list of dictionaries providing information or
	all screens
<pre>get_state()</pre>	Get pickled state for restarting qtile
<pre>get_test_data()</pre>	Returns any content arbitrarily set in the self.test_data
	attribute.
<pre>hide_show_bar([position, screen])</pre>	Toggle visibility of a given bar
info()	Set log level to INFO
<pre>internal_windows()</pre>	Return info for each internal window (bars, for exam-
	ple)
<pre>items(name)</pre>	Build a list of contained items for the given item class
<pre>labelgroup([prompt, widget])</pre>	Launch prompt widget to label the current group
list_widgets()	List of all addressible widget names
loglevel()	
loglevel() loglevelname()	
	Switch to the next layout.
<pre>loglevelname() next_layout([name])</pre>	
<pre>loglevelname() next_layout([name]) next_screen()</pre>	Switch to the next layout. Move to next screen
<pre>loglevelname() next_layout([name])</pre>	Switch to the next layout.
<pre>loglevelname() next_layout([name]) next_screen() next_urgent() pause()</pre>	Switch to the next layout. Move to next screen Focus next window with urgent hint Drops into pdb
<pre>loglevelname() next_layout([name]) next_screen() next_urgent() pause() prev_layout([name])</pre>	Switch to the next layout. Move to next screen Focus next window with urgent hint
<pre>loglevelname() next_layout([name]) next_screen() next_urgent() pause() prev_layout([name]) prev_screen()</pre>	Switch to the next layout. Move to next screen Focus next window with urgent hint Drops into pdb Switch to the previous layout. Move to the previous screen
<pre>loglevelname() next_layout([name]) next_screen() next_urgent() pause() prev_layout([name]) prev_screen() qtile_info()</pre>	Switch to the next layout. Move to next screen Focus next window with urgent hint Drops into pdb Switch to the previous layout. Move to the previous screen Returns a dictionary of info on the Qtile instance
<pre>loglevelname() next_layout([name]) next_screen() next_urgent() pause() prev_layout([name]) prev_screen() qtile_info() qtilecmd([prompt, widget, messenger])</pre>	Switch to the next layout. Move to next screen Focus next window with urgent hint Drops into pdb Switch to the previous layout. Move to the previous screen Returns a dictionary of info on the Qtile instance Execute a Qtile command using the client syntax
<pre>loglevelname() next_layout([name]) next_screen() next_urgent() pause() prev_layout([name]) prev_screen() qtile_info()</pre>	Switch to the next layout. Move to next screen Focus next window with urgent hint Drops into pdb Switch to the previous layout. Move to the previous screen Returns a dictionary of info on the Qtile instance Execute a Qtile command using the client syntax
<pre>loglevelname() next_layout([name]) next_screen() next_urgent() pause() prev_layout([name]) prev_screen() qtile_info() qtilecmd([prompt, widget, messenger]) reconfigure_screens(*_, **)</pre>	Switch to the next layout. Move to next screen Focus next window with urgent hint Drops into pdb Switch to the previous layout. Move to the previous screen Returns a dictionary of info on the Qtile instance Execute a Qtile command using the client syntax This can be used to set up screens again during rur time.
<pre>loglevelname() next_layout([name]) next_screen() next_urgent() pause() prev_layout([name]) prev_screen() qtile_info() qtilecmd([prompt, widget, messenger]) reconfigure_screens(*_, **) reload_config()</pre>	Switch to the next layout. Move to next screen Focus next window with urgent hint Drops into pdb Switch to the previous layout. Move to the previous screen Returns a dictionary of info on the Qtile instance Execute a Qtile command using the client syntax This can be used to set up screens again during run
<pre>loglevelname() next_layout([name]) next_screen() next_urgent() pause() prev_layout([name]) prev_screen() qtile_info() qtilecmd([prompt, widget, messenger]) reconfigure_screens(*_, **)</pre>	Switch to the next layout. Move to next screen Focus next window with urgent hint Drops into pdb Switch to the previous layout. Move to the previous screen Returns a dictionary of info on the Qtile instance Execute a Qtile command using the client syntax This can be used to set up screens again during runtime. Reload the configuration file.
<pre>loglevelname() next_layout([name]) next_screen() next_urgent() pause() prev_layout([name]) prev_screen() qtile_info() qtilecmd([prompt, widget, messenger]) reconfigure_screens(*_, **) reload_config() remove_rule(rule_id) restart()</pre>	Switch to the next layout. Move to next screen Focus next window with urgent hint Drops into pdb Switch to the previous layout. Move to the previous screen Returns a dictionary of info on the Qtile instance Execute a Qtile command using the client syntax This can be used to set up screens again during runtime. Reload the configuration file. Remove a dgroup rule by rule_id
<pre>loglevelname() next_layout([name]) next_screen() next_urgent() pause() prev_layout([name]) prev_screen() qtile_info() qtilecmd([prompt, widget, messenger]) reconfigure_screens(*_, **) reload_config() remove_rule(rule_id) restart() run_extension(extension)</pre>	Switch to the next layout. Move to next screen Focus next window with urgent hint Drops into pdb Switch to the previous layout. Move to the previous screen Returns a dictionary of info on the Qtile instance Execute a Qtile command using the client syntax This can be used to set up screens again during rur time. Reload the configuration file. Remove a dgroup rule by rule_id Restart Qtile. Run extensions
<pre>loglevelname() next_layout([name]) next_screen() next_urgent() pause() prev_layout([name]) prev_screen() qtile_info() qtile_info() qtilecmd([prompt, widget, messenger]) reconfigure_screens(*_, **) reload_config() remove_rule(rule_id) restart() run_extension(extension) shutdown([exitcode])</pre>	Switch to the next layout. Move to next screen Focus next window with urgent hint Drops into pdb Switch to the previous layout. Move to the previous screen Returns a dictionary of info on the Qtile instance Execute a Qtile command using the client syntax This can be used to set up screens again during runtime. Reload the configuration file. Remove a dgroup rule by rule_id Restart Qtile. Run extensions Quit Qtile
<pre>loglevelname() next_layout([name]) next_screen() next_urgent() pause() prev_layout([name]) prev_screen() qtile_info() qtile_info() qtilecmd([prompt, widget, messenger]) reconfigure_screens(*_, **) reload_config() remove_rule(rule_id) restart() run_extension(extension) shutdown([exitcode]) simulate_keypress(modifiers, key)</pre>	Switch to the next layout. Move to next screen Focus next window with urgent hint Drops into pdb Switch to the previous layout. Move to the previous screen Returns a dictionary of info on the Qtile instance Execute a Qtile command using the client syntax This can be used to set up screens again during runtime. Reload the configuration file. Remove a dgroup rule by rule_id Restart Qtile. Run extensions Quit Qtile Simulates a keypress on the focused window.
<pre>loglevelname() next_layout([name]) next_screen() next_urgent() pause() prev_layout([name]) prev_screen() qtile_info() qtilecmd([prompt, widget, messenger]) reconfigure_screens(*_, **) reload_config() remove_rule(rule_id) restart() run_extension(extension) shutdown([exitcode])</pre>	Switch to the next layout. Move to next screen Focus next window with urgent hint Drops into pdb Switch to the previous layout. Move to the previous screen Returns a dictionary of info on the Qtile instance Execute a Qtile command using the client syntax This can be used to set up screens again during runtime. Reload the configuration file. Remove a dgroup rule by rule_id Restart Qtile. Run extensions Quit Qtile

continues on next page

Table 1 – continued from previous page

<pre>start_repl_server([locals_dict])</pre>	Start the REPL server.
status()	Return "OK" if Qtile is running
<pre>stop_repl_server()</pre>	Stop the REPL server.
<pre>switch_groups(namea, nameb)</pre>	Switch position of two groups by name
<pre>switch_window(location)</pre>	Change to the window at the specified index in the current group.
<pre>switchgroup([prompt, widget])</pre>	Launch prompt widget to switch to a given group to the current screen
sync()	Sync the backend's event queue.
to_layout_index(index[, name])	Switch to the layout with the given index in self.layouts.
to_screen(n)	Warp focus to screen n, where n is a 0-based screen number
togroup([prompt, widget])	Launch prompt widget to move current window to a given group
tracemalloc_dump()	Dump tracemalloc snapshot
tracemalloc_toggle()	Toggle tracemalloc status
<pre>ungrab_all_chords()</pre>	Leave all chord modes and grab the root bindings
ungrab_chord()	Leave a chord mode
<pre>validate_config()</pre>	
warning()	Set log level to WARNING
windows()	Return info for each client window

Command documentation

add_rule($match_args: dict[str, Any], rule_args: dict[str, Any], min_priorty: bool = False$) \rightarrow int | None Add a dgroup rule, returns rule_id needed to remove it

Parameters

```
match_args
```

config.Match arguments

rule_args

config.Rule arguments

min priorty

If the rule is added with minimum priority (last) (default: False)

addgroup(group: str, label: $str \mid None = None$, layout: $str \mid None = None$, layouts: $list[Layout] \mid None = None$, index: $int \mid None = None$, persist: $bool \mid None = False) \rightarrow bool$

Add a group with the given name

 $change_window_order(new_location: int) \rightarrow None$

Change the order of the current window within the current group.

 $commands() \rightarrow list[str]$

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

 $critical() \rightarrow None$

Set log level to CRITICAL

```
debug() \rightarrow None
     Set log level to DEBUG
delgroup(group: str) \rightarrow None
     Delete a group with the given name
display_kb() \rightarrow str
     Display table of key bindings
doc(name) \rightarrow str
     Returns the documentation for a specified command name
     Used by __qsh__ to provide online help.
error() \rightarrow None
     Set log level to ERROR
eval(code: str) \rightarrow tuple[bool, str | None]
     Evaluates code in the same context as this function
     Return value is tuple (success, result), success being a boolean and result being a string representing the
     return value of eval, or None if exec was used instead.
findwindow(prompt: str = 'window', widget: str = 'prompt') \rightarrow None
     Launch prompt widget to find a window of the given name
          Parameters
               prompt
                 Text with which to prompt user (default: "window")
               widget
                 Name of the prompt widget (default: "prompt")
fire_user_hook(hook\_name: str, *args: Any) \rightarrow None
     Fire a custom hook.
function(function, *args, **kwargs) \rightarrow Task | None
     Call a function with current object as argument
get\_groups() \rightarrow dict[str, dict[str, Any]]
     Return a dictionary containing information for all groups
     Examples
     get_groups()
get\_screens() \rightarrow list[dict[str, Any]]
     Return a list of dictionaries providing information on all screens
get_state() \rightarrow str
     Get pickled state for restarting qtile
get\_test\_data() \rightarrow Any
```

Returns any content arbitrarily set in the self.test_data attribute. Useful in tests.

```
hide_show_bar(position: Literal['top', 'bottom', 'left', 'right', 'all'] = 'all', screen: Literal['current', 'all'] =
                   'current') \rightarrow None
     Toggle visibility of a given bar
          Parameters
               position
                 one of: "top", "bottom", "left", "right", or "all" (default: "all")
               screen
                 one of: "current", "all" (default: "current")
info() \rightarrow None
     Set log level to INFO
internal_windows() → list[dict[str, Any]]
     Return info for each internal window (bars, for example)
items(name: str) \rightarrow tuple[bool, list[str | int] | None]
     Build a list of contained items for the given item class.
     Exposing this allows __qsh__ to navigate the command graph.
     Returns a tuple (root, items) for the specified item class, where:
          root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout"
          defaults to current layout), and False if it does not (e.g. no default "widget").
          items: a list of contained items
labelgroup(prompt: str = 'label', widget: str = 'prompt') \rightarrow None
     Launch prompt widget to label the current group
          Parameters
               prompt
                 Text with which to prompt user (default: "label")
               widget
                 Name of the prompt widget (default: "prompt")
list\_widgets() \rightarrow list[str]
     List of all addressible widget names
loglevel() \rightarrow int
loglevelname() \rightarrow str
next_layout(name: str \mid None = None) \rightarrow None
     Switch to the next layout.
          Parameters
               name
                  Group name. If not specified, the current group is assumed
next\_screen() \rightarrow None
     Move to next screen
next\_urgent() \rightarrow None
     Focus next window with urgent hint
```

```
pause() \rightarrow None
     Drops into pdb
prev_layout(name: str | None = None) \rightarrow None
     Switch to the previous layout.
          Parameters
              name
                Group name. If not specified, the current group is assumed
prev\_screen() \rightarrow None
     Move to the previous screen
qtile_info() \rightarrow dict
     Returns a dictionary of info on the Qtile instance
qtilecmd(prompt: str = 'command', widget: str = 'prompt', messenger: str = 'xmessage') \rightarrow None
     Execute a Qtile command using the client syntax
     Tab completion aids navigation of the command tree
          Parameters
              prompt
                Text to display at the prompt (default: "command: ")
                Name of the prompt widget (default: "prompt")
              messenger
                Command to display output, set this to None to disable (default: "xmessage")
reconfigure_screens(*_: list[Any], **__: dict[Any, Any]) \rightarrow None
     This can be used to set up screens again during run time. Intended usage is to be called when the
     screen_change hook is fired, responding to changes in physical monitor setup by configuring qtile.screens
     accordingly. The args are ignored; it is here in case this function is hooked directly to screen_change.
reload_config() → None
     Reload the configuration file.
     Can also be triggered by sending Qtile a SIGUSR1 signal.
remove_rule(rule\_id: int) \rightarrow None
     Remove a dgroup rule by rule_id
restart() \rightarrow None
     Restart Qtile.
     Can also be triggered by sending Qtile a SIGUSR2 signal.
run_{extension}(extension: \_Extension) \rightarrow None
     Run extensions
shutdown(exitcode: int = 0) \rightarrow None
     Quit Qtile
          Parameters
              exitcode
                Set exit status of Qtile. Can be e.g. used to make login managers poweroff or restart the
                system. (default: 0)
```

```
simulate_keypress(modifiers: list[str], key: str) \rightarrow None
```

Simulates a keypress on the focused window.

This triggers internal bindings only; for full simulation see external tools such as xdotool or ydotool.

Parameters

modifiers

A list of modifier specification strings. Modifiers can be one of "shift", "lock", "control" and "mod1" - "mod5".

kev

Key specification.

Examples

```
simulate_keypress(["control", "mod2"], "k")
```

spawn($cmd: list[str] \mid str, shell: bool = False, env: <math>dict[str, str] = \{\}, group: str \mid None = None\} \rightarrow int$ Spawn a new process.

Parameters

cmd:

The command to execute either as a single string or list of strings.

shell:

Whether to execute the command in a new shell by prepending it with "/bin/sh -c". This enables the use of shell syntax within the command (e.g. pipes).

env:

Dictionary of environmental variables to pass with command.

group:

Name of group in which to spawn process.

Examples

Spawn a command using a prompt widget, with tab-completion.

Parameters

prompt

Text with which to prompt user (default: "spawn: ").

widget

Name of the prompt widget (default: "prompt").

command

command template (default: "%s").

complete

Tab completion function (default: "cmd")

shell

Execute the command with /bin/sh (default: True)

aliases

Dictionary mapping aliases to commands. If the entered command is a key in this dict, the command it maps to will be executed instead.

 $start_repl_server(locals\ dict:\ dict[str,\ Any] = \{\}) \rightarrow None$

Start the REPL server.

 $status() \rightarrow Literal['OK']$

Return "OK" if Qtile is running

 $stop_repl_server() \rightarrow None$

Stop the REPL server.

switch_groups(namea: str, nameb: str) \rightarrow None

Switch position of two groups by name

 $switch_window(location: int) \rightarrow None$

Change to the window at the specified index in the current group.

switchgroup($prompt: str = 'group', widget: str = 'prompt') \rightarrow None$

Launch prompt widget to switch to a given group to the current screen

Parameters

prompt

Text with which to prompt user (default: "group")

widget

Name of the prompt widget (default: "prompt")

 $sync() \rightarrow None$

Sync the backend's event queue. Should only be used for development.

 $to_layout_index(index: int, name: str | None = None) \rightarrow None$

Switch to the layout with the given index in self.layouts.

Parameters

index

Index of the layout in the list of layouts.

name

Group name. If not specified, the current group is assumed.

to_screen(n: int) \rightarrow None

Warp focus to screen n, where n is a 0-based screen number


Examples

```
to_screen(0)
togroup(prompt: str = 'group', widget: str = 'prompt') \rightarrow None
     Launch prompt widget to move current window to a given group
          Parameters
              prompt
                 Text with which to prompt user (default: "group")
                 Name of the prompt widget (default: "prompt")
tracemalloc_dump() \rightarrow tuple[bool, str]
     Dump tracemalloc snapshot
tracemalloc\_toggle() \rightarrow None
     Toggle tracemalloc status
     Running tracemalloc is required for qtile top
ungrab\_all\_chords() \rightarrow None
     Leave all chord modes and grab the root bindings
ungrab\_chord() \rightarrow None
     Leave a chord mode
validate\_config() \rightarrow None
warning() \rightarrow None
     Set log level to WARNING
windows() \rightarrow list[dict[str, Any]]
     Return info for each client window
```

15.2 Layout objects

Layouts position windows according to their specific rules. Layout commands typically include moving windows around the layout and changing the size of windows.

Layouts can access the windows being displayed, the group holding the layout and the screen displaying the layout.



15.2.1 Bsp

class libqtile.layout.bsp.Bsp

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.layout.<command>()
qtile cmd-obj -o layout -f <command>

The following commands are available for this object:

15.2. Layout objects

commands() doc(name)	Returns a list of possible commands for this object Returns the documentation for a specified command name
down()	
<pre>eval(code) flip_down()</pre>	Evaluates code in the same context as this function
flip_left()	
flip_right()	
flip_up()	
<pre>function(function, *args, **kwargs) grow_down()</pre>	Call a function with current object as argument
<pre>grow_left()</pre>	
<pre>grow_right()</pre>	
<pre>grow_up()</pre>	
<pre>info() items(name) left()</pre>	Returns a dictionary of layout information Build a list of contained items for the given item class.
next()	
normalize()	
previous()	
right()	
shuffle_down()	
<pre>shuffle_left()</pre>	
<pre>shuffle_right()</pre>	
shuffle_up()	
toggle_split()	
up()	

$commands() \rightarrow list[str]$

Returns a list of possible commands for this object

```
Used by __qsh__ for command completion and online help
doc(name) \rightarrow str
     Returns the documentation for a specified command name
     Used by __qsh__ to provide online help.
down()
eval(code: str) \rightarrow tuple[bool, str | None]
     Evaluates code in the same context as this function
     Return value is tuple (success, result), success being a boolean and result being a string representing the
     return value of eval, or None if exec was used instead.
flip_down()
flip_left()
flip_right()
flip_up()
function(function, *args, **kwargs) \rightarrow Task | None
     Call a function with current object as argument
grow_down()
grow_left()
grow_right()
grow_up()
info() \rightarrow dict[str, Any]
     Returns a dictionary of layout information
items(name: str) \rightarrow tuple[bool, list[str | int] | None]
     Build a list of contained items for the given item class.
     Exposing this allows __qsh__ to navigate the command graph.
     Returns a tuple (root, items) for the specified item class, where:
          root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout"
          defaults to current layout), and False if it does not (e.g. no default "widget").
          items: a list of contained items
left()
next() \rightarrow None
normalize()
previous() \rightarrow None
right()
shuffle_down()
shuffle_left()
```

```
shuffle_right()
shuffle_up()
toggle_split()
up()
```

15.2.2 Columns

class libqtile.layout.columns.Columns

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.layout.<command>()
qtile cmd-obj -o layout -f <command>

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command name
down()	
eval(code)	Evaluates code in the same context as this function
function(function, *args, **kwargs)	Call a function with current object as argument
<pre>grow_down()</pre>	
<pre>grow_left()</pre>	
<pre>grow_right()</pre>	
<pre>grow_up()</pre>	
info()	Returns a dictionary of layout information
<pre>items(name)</pre>	Build a list of contained items for the given item class.
left()	
next()	
normalize()	Give columns equal widths.
previous()	
reset()	Resets column widths, respecting 'initial_ratio' value.
right()	
shuffle_down()	
shuffle_left()	
<pre>shuffle_right()</pre>	
shuffle_up()	
<pre>swap_column_left()</pre>	
<pre>swap_column_right()</pre>	
toggle_split()	
up()	

```
commands() \rightarrow list[str]
```

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

 $\textbf{doc}(\textit{name}) \rightarrow \textit{str}$

Returns the documentation for a specified command name

```
Used by __qsh__ to provide online help.
down()
eval(code: str) \rightarrow tuple[bool, str | None]
     Evaluates code in the same context as this function
     Return value is tuple (success, result), success being a boolean and result being a string representing the
     return value of eval, or None if exec was used instead.
function(function, *args, **kwargs) \rightarrow Task | None
     Call a function with current object as argument
grow_down()
grow_left()
grow_right()
grow_up()
info() \rightarrow dict[str, Any]
     Returns a dictionary of layout information
items (name: str) \rightarrow tuple[bool, list[str | int] | None]
     Build a list of contained items for the given item class.
     Exposing this allows __qsh__ to navigate the command graph.
     Returns a tuple (root, items) for the specified item class, where:
          root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout"
          defaults to current layout), and False if it does not (e.g. no default "widget").
          items: a list of contained items
left()
next() \rightarrow None
normalize()
     Give columns equal widths.
previous() \rightarrow None
reset()
     Resets column widths, respecting 'initial ratio' value.
right()
shuffle_down()
shuffle_left()
shuffle_right()
shuffle_up()
swap_column_left()
swap_column_right()
```

```
toggle_split()
up()
```

15.2.3 Floating

class libqtile.layout.floating.Floating

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.layout.<command>()
qtile cmd-obj -o layout -f <command>

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Returns a dictionary of layout information
items(name)	Build a list of contained items for the given item class.
next()	
previous()	

Command documentation

```
commands() \rightarrow list[str]
```

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

 $doc(name) \rightarrow str$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (success, result), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info() \rightarrow dict[str, Any]

Returns a dictionary of layout information

```
items(name: str) \rightarrow tuple[bool, list[str | int] | None]
```

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

 $next() \rightarrow None$

 $previous() \rightarrow None$

15.2.4 Matrix

class libqtile.layout.matrix.Matrix

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.layout.<command>() qtile cmd-obj -o layout -f <command>

The following commands are available for this object:

110	T 1 0 1
add()	Increase number of columns
commands()	Returns a list of possible commands for this object
delete()	Decrease number of columns
doc(name)	Returns the documentation for a specified command
	name
down()	Switch to the next window in current column
eval(code)	Evaluates code in the same context as this function
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Returns a dictionary of layout information
<pre>items(name)</pre>	Build a list of contained items for the given item class.
left()	Switch to the next window on current row
next()	
previous()	
right()	Switch to the next window on current row
up()	Switch to the previous window in current column

Command documentation

add()

Increase number of columns

commands() \rightarrow list[str]

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

delete()

Decrease number of columns

$doc(name) \rightarrow str$

Returns the documentation for a specified command name

Used by qsh to provide online help.

down()

Switch to the next window in current column

```
eval(code: str) \rightarrow tuple[bool, str | None]
```

Evaluates code in the same context as this function

Return value is tuple (success, result), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

```
function(function, *args, **kwargs) \rightarrow Task | None
```

Call a function with current object as argument

```
info() \rightarrow dict[str, Any]
```

Returns a dictionary of layout information

```
items (name: str) \rightarrow tuple[bool, list[str | int] | None]
```

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

left()

Switch to the next window on current row

```
next() \rightarrow None
```

 $previous() \rightarrow None$

right()

Switch to the next window on current row

up()

Switch to the previous window in current column

15.2.5 Max

class libqtile.layout.max.Max

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.layout.<command>() qtile cmd-obj -o layout -f <command> The following commands are available for this object:

commands() doc(name)	Returns a list of possible commands for this object Returns the documentation for a specified command
uoe(name)	name
down()	
eval(code)	Evaluates code in the same context as this function
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Returns a dictionary of layout information
<pre>items(name)</pre>	Build a list of contained items for the given item class.
next()	
previous()	
up()	

Command documentation

 $commands() \rightarrow list[str]$

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

 $doc(name) \rightarrow str$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

down()

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (success, result), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info() \rightarrow dict[str, Any]

Returns a dictionary of layout information

items (name: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

next()

previous()
up()

15.2.6 MonadTall

class libqtile.layout.xmonad.MonadTall

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.layout.<command>() qtile cmd-obj -o layout -f <command>

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
down()	Focus on the closest window below the current win-
	dow
eval(code)	Evaluates code in the same context as this function
flip()	Flip the layout horizontally
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
grow()	Grow current window
<pre>grow_main()</pre>	Grow main pane
info()	Returns a dictionary of layout information
<pre>items(name)</pre>	Build a list of contained items for the given item class.
left()	Focus on the closest window to the left of the current window
<pre>maximize()</pre>	Grow the currently focused client to the max size
next()	
	French distribute commence commence constitution
normalize([redraw])	Evenly distribute screen-space among secondary clients
previous()	
reset([ratio, redraw])	Reset Layout.
right()	Focus on the closest window to the right of the current
	window
set_ratio(ratio)	Directly set the main pane ratio
shrink()	Shrink current window
shrink_main()	Shrink main pane
<pre>shuffle_down()</pre>	Shuffle the client down the stack
shuffle_up()	Shuffle the client up the stack
swap(window1, window2)	Swap two windows
<pre>swap_left()</pre>	Swap current window with closest window to the left
<pre>swap_main()</pre>	Swap current window to main pane
<pre>swap_right()</pre>	Swap current window with closest window to the right
toggle_auto_maximize()	Toggle auto maximize secondary window on focus.
up()	Focus on the closest window above the current window

 $commands() \rightarrow list[str]$

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

 $\mathbf{doc}(\mathit{name}) \to \mathsf{str}$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

down()

Focus on the closest window below the current window

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (success, result), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

flip()

Flip the layout horizontally

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

grow()

Grow current window

Will grow the currently focused client reducing the size of those around it. Growing will stop when no other secondary clients can reduce their size any further.

grow_main()

Grow main pane

Will grow the main pane, reducing the size of clients in the secondary pane.

```
info() \rightarrow dict[str, Any]
```

Returns a dictionary of layout information

items (*name*: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

left()

Focus on the closest window to the left of the current window

maximize()

Grow the currently focused client to the max size

```
next() \rightarrow None
```

normalize(redraw=True)

Evenly distribute screen-space among secondary clients

```
previous() \rightarrow None
```

reset(ratio=None, redraw=True)

Reset Layout.

right()

Focus on the closest window to the right of the current window

set_ratio(ratio)

Directly set the main pane ratio

shrink()

Shrink current window

Will shrink the currently focused client reducing the size of those around it. Shrinking will stop when the client has reached the minimum size.

shrink_main()

Shrink main pane

Will shrink the main pane, increasing the size of clients in the secondary pane.

shuffle_down()

Shuffle the client down the stack

shuffle_up()

Shuffle the client up the stack

swap(window1: Window, window2: Window) \rightarrow None

Swap two windows

swap_left()

Swap current window with closest window to the left

swap_main()

Swap current window to main pane

swap_right()

Swap current window with closest window to the right

toggle_auto_maximize()

Toggle auto maximize secondary window on focus.

up()

Focus on the closest window above the current window

15.2.7 MonadThreeCol

class libqtile.layout.xmonad.MonadThreeCol

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.layout.<command>()
qtile cmd-obj -o layout -f <command>

commands() Returns a list of possible commands in the documentation for a specimane. down() Focus on the closest window below the downown down the closest window below the downown dow	cified command the current win- s this function s argument given item class.
name down() Focus on the closest window below to dow eval(code) Evaluates code in the same context as flip() function(function, *args, **kwargs) grow() Grow current window grow_main() items(name) left() Focus on the closest window to the left window	s this function argument given item class.
dow eval(code) Evaluates code in the same context as flip() Flip the layout horizontally function(function, *args, **kwargs) Call a function with current object as grow() Grow current window grow_main() Grow main pane items(name) Build a list of contained items for the g left() Focus on the closest window to the le window	s this function s argument given item class.
eval(code)Evaluates code in the same context asflip()Flip the layout horizontallyfunction(function, *args, **kwargs)Call a function with current object asgrow()Grow current windowgrow_main()Grow main paneitems(name)Build a list of contained items for the grown on the closest window to the lewindow	argument
flip()Flip the layout horizontallyfunction(function, *args, **kwargs)Call a function with current object asgrow()Grow current windowgrow_main()Grow main paneitems(name)Build a list of contained items for the grown on the closest window to the lewindow	argument
function(function, *args, **kwargs)Call a function with current object asgrow()Grow current windowgrow_main()Grow main paneitems(name)Build a list of contained items for the grown on the closest window to the lewindow	given item class.
grow()Grow current windowgrow_main()Grow main paneitems(name)Build a list of contained items for the graphleft()Focus on the closest window to the lewindow	given item class.
grow_main() items(name) Build a list of contained items for the graph of the grap	
items(name)Build a list of contained items for the graphleft()Focus on the closest window to the lewindow	
left() Focus on the closest window to the lewindow	
window	ft of the current
· ·	
Crow the currently feared alient to	
maximize() Grow the currently focused client to t	the max size
next()	
normalize([redraw]) Evenly distribute screen-space am	ong secondary
clients	
previous()	
reset([ratio, redraw]) Reset Layout.	
right() Focus on the closest window to the rig	tht of the current
window	
set_ratio(ratio) Directly set the main pane ratio	
shrink() Shrink current window	
shrink_main() Shrink main pane	
shuffle_down() Shuffle the client down the stack	
shuffle_up() Shuffle the client up the stack	
swap(window1, window2) Swap two windows	
swap_left() Swap current window with closest wi	ndow to the left
swap_main() Swap current window to main pane	
swap_right() Swap current window with closest	window to the
right	
toggle_auto_maximize() Toggle auto maximize secondary win	
<i>up</i> () Focus on the closest window above t	he current win-
dow	

commands() \rightarrow list[str]

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

$\mathbf{doc}(\mathit{name}) \to \mathit{str}$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

down()

Focus on the closest window below the current window

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (success, result), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

flip()

Flip the layout horizontally

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

grow()

Grow current window

Will grow the currently focused client reducing the size of those around it. Growing will stop when no other secondary clients can reduce their size any further.

grow_main()

Grow main pane

Will grow the main pane, reducing the size of clients in the secondary pane.

items(name: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

left()

Focus on the closest window to the left of the current window

maximize()

Grow the currently focused client to the max size

```
next() \rightarrow None
```

normalize(redraw=True)

Evenly distribute screen-space among secondary clients

```
previous() \rightarrow None
```

```
reset(ratio=None, redraw=True)
```

Reset Layout.

right()

Focus on the closest window to the right of the current window

set_ratio(ratio)

Directly set the main pane ratio

shrink()

Shrink current window

Will shrink the currently focused client reducing the size of those around it. Shrinking will stop when the client has reached the minimum size.

shrink_main()

Shrink main pane

Will shrink the main pane, increasing the size of clients in the secondary pane.

shuffle_down()

Shuffle the client down the stack

shuffle_up()

Shuffle the client up the stack

swap(*window1*: Window, *window2*: Window) \rightarrow None

Swap two windows

swap_left()

Swap current window with closest window to the left

swap_main()

Swap current window to main pane

swap_right()

Swap current window with closest window to the right

toggle_auto_maximize()

Toggle auto maximize secondary window on focus.

up()

Focus on the closest window above the current window

15.2.8 MonadWide

class libqtile.layout.xmonad.MonadWide

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.layout.<command>()
qtile cmd-obj -o layout -f <command>

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
down()	Focus on the closest window below the current win-
	dow
eval(code)	Evaluates code in the same context as this function
flip()	Flip the layout horizontally
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
grow()	Grow current window
<pre>grow_main()</pre>	Grow main pane
info()	Returns a dictionary of layout information
<pre>items(name)</pre>	Build a list of contained items for the given item class.
left()	Focus on the closest window to the left of the current window
<pre>maximize()</pre>	Grow the currently focused client to the max size
next()	
normalize([redraw])	Evenly distribute screen-space among secondary clients
previous()	
reset([ratio, redraw])	Reset Layout.
right()	Focus on the closest window to the right of the current
	window
set_ratio(ratio)	Directly set the main pane ratio
shrink()	Shrink current window
<pre>shrink_main()</pre>	Shrink main pane
<pre>shuffle_down()</pre>	Shuffle the client down the stack
shuffle_up()	Shuffle the client up the stack
swap(window1, window2)	Swap two windows
<pre>swap_left()</pre>	Swap current window with closest window to the
	down
<pre>swap_main()</pre>	Swap current window to main pane
<pre>swap_right()</pre>	Swap current window with closest window to the up
<pre>toggle_auto_maximize()</pre>	Toggle auto maximize secondary window on focus.
up()	Focus on the closest window above the current window

 $commands() \rightarrow list[str]$

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

 $\mathbf{doc}(\mathit{name}) \to \mathsf{str}$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

down()

Focus on the closest window below the current window

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (success, result), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

flip()

Flip the layout horizontally

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

grow()

Grow current window

Will grow the currently focused client reducing the size of those around it. Growing will stop when no other secondary clients can reduce their size any further.

grow_main()

Grow main pane

Will grow the main pane, reducing the size of clients in the secondary pane.

```
info() \rightarrow dict[str, Any]
```

Returns a dictionary of layout information

items (*name*: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

left()

Focus on the closest window to the left of the current window

maximize()

Grow the currently focused client to the max size

```
next() \rightarrow None
```

normalize(redraw=True)

Evenly distribute screen-space among secondary clients

```
previous() \rightarrow None
```

reset(ratio=None, redraw=True)

Reset Layout.

right()

Focus on the closest window to the right of the current window

set_ratio(ratio)

Directly set the main pane ratio

shrink()

Shrink current window

Will shrink the currently focused client reducing the size of those around it. Shrinking will stop when the client has reached the minimum size.

shrink_main()

Shrink main pane

Will shrink the main pane, increasing the size of clients in the secondary pane.

shuffle_down()

Shuffle the client down the stack

shuffle_up()

Shuffle the client up the stack

swap(window1: Window, window2: Window) \rightarrow None

Swap two windows

swap_left()

Swap current window with closest window to the down

swap_main()

Swap current window to main pane

swap_right()

Swap current window with closest window to the up

toggle_auto_maximize()

Toggle auto maximize secondary window on focus.

up()

Focus on the closest window above the current window

15.2.9 Plasma

class libqtile.layout.plasma.Plasma

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.layout.<command>()
qtile cmd-obj -o layout -f <command>

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
down()	Focus window below.
eval(code)	Evaluates code in the same context as this function
function(function, *args, **kwargs)	Call a function with current object as argument
grow(x)	Grow size of current window.
<pre>grow_height(x)</pre>	Grow height of current window.
<pre>grow_width(x)</pre>	Grow width of current window.
info()	Returns a dictionary of layout information
<pre>integrate_down()</pre>	Integrate current window down.
<pre>integrate_left()</pre>	Integrate current window left.

continues on next page

Table 2 – continued from previous page

integrate_right()Integrate current window right.integrate_up()Integrate current window up.items(name)Build a list of contained items for the given item classleft()Focus window to the left.
items(name) Build a list of contained items for the given item class
-
left() Focus window to the left.
mode_horizontal() Next window will be added horizontally.
mode_horizontal_split() Next window will be added horizontally, splitting
space of current window.
mode_vertical() Next window will be added vertically.
mode_vertical_split() Next window will be added vertically, splitting space
of current window.
move_down() Move current window down.
move_left() Move current window left.
move_right() Move current window right.
move_up() Move current window up.
next() Focus next window.
previous() Focus previous window.
recent() Focus most recently focused window.
reset_size() Reset size of current window to automatic (relative
sizing.
right() Focus window to the right.
set_height(x) Set height of current window.
set_size(x) Change size of current window.
set_width(x) Set width of current window.
<i>up</i> () Focus window above.

commands() \rightarrow list[str]

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

$\mathbf{doc}(\mathit{name}) \to \mathit{str}$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

down()

Focus window below.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (success, result), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

grow(x: int)

Grow size of current window.

(It's recommended to use grow_width()/grow_height() instead.)

grow_height(x: int)

Grow height of current window.

```
grow_width(x: int)
     Grow width of current window.
info()
     Returns a dictionary of layout information
integrate_down()
     Integrate current window down.
integrate_left()
     Integrate current window left.
integrate_right()
     Integrate current window right.
integrate_up()
     Integrate current window up.
items(name: str) \rightarrow tuple[bool, list[str | int] | None]
     Build a list of contained items for the given item class.
     Exposing this allows __qsh__ to navigate the command graph.
     Returns a tuple (root, items) for the specified item class, where:
         root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout"
         defaults to current layout), and False if it does not (e.g. no default "widget").
         items: a list of contained items
left()
     Focus window to the left.
mode_horizontal()
     Next window will be added horizontally.
mode_horizontal_split()
     Next window will be added horizontally, splitting space of current window.
mode_vertical()
     Next window will be added vertically.
mode_vertical_split()
     Next window will be added vertically, splitting space of current window.
move_down()
     Move current window down.
move_left()
     Move current window left.
move_right()
     Move current window right.
move_up()
     Move current window up.
next()
```

Focus next window.

```
previous()
     Focus previous window.
recent()
     Focus most recently focused window.
     (Toggles between the two latest active windows.)
reset_size()
     Reset size of current window to automatic (relative) sizing.
right()
     Focus window to the right.
set_height(x: int)
     Set height of current window.
set_size(x: int)
     Change size of current window.
     (It's recommended to use width()/height() instead.)
set_width(x: int)
     Set width of current window.
up()
     Focus window above.
```

15.2.10 RatioTile

class libqtile.layout.ratiotile.RatioTile

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.layout.<command>() qtile cmd-obj -o layout -f <command>

commands()	Returns a list of possible commands for this object
<pre>decrease_ratio()</pre>	
doc(name)	Returns the documentation for a specified command name
eval(code)	Evaluates code in the same context as this function
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
<pre>increase_ratio()</pre>	
info()	Returns a dictionary of layout information
<pre>items(name)</pre>	Build a list of contained items for the given item class.
next()	
<pre>previous()</pre>	
shuffle_down()	
shuffle_up()	

commands() \rightarrow list[str]

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

decrease_ratio()

 $doc(name) \rightarrow str$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (success, result), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

increase_ratio()

info() \rightarrow dict[str, Any]

Returns a dictionary of layout information

items(name: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

```
next() \rightarrow None
previous() \rightarrow None
shuffle_down()
shuffle_up()
```

15.2.11 ScreenSplit

class libqtile.layout.screensplit.ScreenSplit

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.layout.<command>()
qtile cmd-obj -o layout -f <command>

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Returns a dictionary of layout information
<pre>items(name)</pre>	Build a list of contained items for the given item class.
<pre>move_window_to_next_split()</pre>	Move current window to next split.
<pre>move_window_to_previous_split()</pre>	Move current window to previous split.
next()	Move to next client.
<pre>next_split()</pre>	Move to next split.
previous()	Move to previous client.
<pre>previous_split()</pre>	Move to previous client.

Command documentation

commands()

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

 $\mathbf{doc}(\mathit{name}) \to \mathrm{str}$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (success, result), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

```
info() \rightarrow dict[str, Any]
```

Returns a dictionary of layout information

items(name: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

$move_window_to_next_split() \rightarrow None$

Move current window to next split.

${\tt move_window_to_previous_split()} \rightarrow None$

Move current window to previous split.

 $next() \rightarrow None$

Move to next client.

 $next_split() \rightarrow None$

Move to next split.

 $previous() \rightarrow None$

Move to previous client.

 $previous_split() \rightarrow None$

Move to previous client.

15.2.12 Slice

class libqtile.layout.slice.Slice

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.layout.<command>()
qtile cmd-obj -o layout -f <command>

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Returns a dictionary of layout information
<pre>items(name)</pre>	Build a list of contained items for the given item class.
<pre>move_to_slice()</pre>	Moves the current window to the slice.
next()	
previous()	

commands()

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

 $doc(name) \rightarrow str$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (*success*, *result*), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info() \rightarrow dict[str, Any]

Returns a dictionary of layout information

items(name: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

move_to_slice()

Moves the current window to the slice.

 $next() \rightarrow None$

 $previous() \rightarrow None$

15.2.13 Spiral

class libqtile.layout.spiral.Spiral

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.layout.<command>() qtile cmd-obj -o layout -f <command>

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
<pre>decrease_ratio()</pre>	Decrease spiral ratio.
doc(name)	Returns the documentation for a specified command name
eval(code)	Evaluates code in the same context as this function
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
<pre>grow_main()</pre>	Grow the main window.
<pre>increase_ratio()</pre>	Increase spiral ratio.
<pre>items(name)</pre>	Build a list of contained items for the given item class.
next()	
previous()	
reset()	Reset ratios to values set in config.
<pre>set_master_ratio(ratio)</pre>	Set the ratio for the main window.
set_ratio(ratio)	Set the ratio for all windows.
<pre>shrink_main()</pre>	Shrink the main window.
shuffle_down()	
shuffle_up()	

Command documentation

 $\textbf{commands()} \rightarrow list[str]$

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

decrease_ratio()

Decrease spiral ratio.

 $doc(name) \rightarrow str$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (success, result), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

```
function(function, *args, **kwargs) \rightarrow Task | None
     Call a function with current object as argument
grow_main()
     Grow the main window.
increase_ratio()
     Increase spiral ratio.
items(name: str) \rightarrow tuple[bool, list[str | int] | None]
     Build a list of contained items for the given item class.
     Exposing this allows __qsh__ to navigate the command graph.
     Returns a tuple (root, items) for the specified item class, where:
          root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout"
          defaults to current layout), and False if it does not (e.g. no default "widget").
          items: a list of contained items
next() \rightarrow None
previous() \rightarrow None
reset()
     Reset ratios to values set in config.
set_master_ratio(ratio: float)
     Set the ratio for the main window.
set_ratio(ratio: float)
     Set the ratio for all windows.
shrink_main()
     Shrink the main window.
shuffle_down()
shuffle_up()
```

15.2.14 Stack

class libgtile.layout.stack.Stack

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.layout.<command>()
qtile cmd-obj -o layout -f <command>

add()	Add another stack to the layout
<pre>client_to_next()</pre>	Send the current client to the next stack
<pre>client_to_previous()</pre>	Send the current client to the previous stack
<pre>client_to_stack(n)</pre>	Send the current client to stack n, where n is an integer offset.
commands()	Returns a list of possible commands for this object
delete()	Delete the current stack from the layout
doc(name)	Returns the documentation for a specified command name
down()	Switch to the next window in this stack
eval(code)	Evaluates code in the same context as this function
function(function, *args, **kwargs)	Call a function with current object as argument
info()	Returns a dictionary of layout information
<pre>items(name)</pre>	Build a list of contained items for the given item class.
next()	Focus next stack
<pre>previous()</pre>	Focus previous stack
rotate()	Rotate order of the stacks
<pre>shuffle_down()</pre>	Shuffle the order of this stack down
shuffle_up()	Shuffle the order of this stack up
toggle_split()	Toggle vertical split on the current stack
up()	Switch to the previous window in this stack

add()

Add another stack to the layout

client_to_next()

Send the current client to the next stack

client_to_previous()

Send the current client to the previous stack

client_to_stack(n)

Send the current client to stack n, where n is an integer offset. If is too large or less than 0, it is wrapped modulo the number of stacks.

$\textbf{commands()} \rightarrow list[str]$

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

delete()

Delete the current stack from the layout

$\mathbf{doc}(name) \rightarrow \mathbf{str}$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

down()

Switch to the next window in this stack

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (success, result), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

```
function(function, *args, **kwargs) \rightarrow Task | None
```

Call a function with current object as argument

```
info() \rightarrow dict[str, Any]
```

Returns a dictionary of layout information

items(name: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

 $next() \rightarrow None$

Focus next stack

 $previous() \rightarrow None$

Focus previous stack

rotate()

Rotate order of the stacks

shuffle_down()

Shuffle the order of this stack down

shuffle_up()

Shuffle the order of this stack up

toggle_split()

Toggle vertical split on the current stack

up()

Switch to the previous window in this stack

15.2.15 Tile

class libgtile.layout.tile.Tile

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.layout.<command>()
qtile cmd-obj -o layout -f <command>

commands()	Returns a list of possible commands for this object
<pre>decrease_nmaster()</pre>	
decrease_ratio()	
doc(name)	Returns the documentation for a specified command name
eval(code)	Evaluates code in the same context as this function
function(function, *args, **kwargs)	Call a function with current object as argument
<pre>increase_nmaster()</pre>	
<pre>increase_ratio()</pre>	
info()	Returns a dictionary of layout information
<pre>items(name)</pre>	Build a list of contained items for the given item class.
next()	
previous()	
reset()	
shuffle_down()	
shuffle_up()	

```
commands() \rightarrow list[str]
```

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

decrease_nmaster()

decrease_ratio()

 $doc(name) \rightarrow str$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (success, result), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

increase_nmaster()

increase_ratio()

```
info() → dict[str, Any]
    Returns a dictionary of layout information

items(name: str) → tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

    root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

    items: a list of contained items

next() → None

previous() → None

reset()

shuffle_down()

shuffle_up()
```

15.2.16 TreeTab

class libqtile.layout.tree.TreeTab

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.layout.<command>()
qtile cmd-obj -o layout -f <command>

<pre>add_section(name)</pre>	Add named section to tree
collapse_branch()	
commands()	Returns a list of possible commands for this object
<pre>decrease_ratio()</pre>	
<pre>del_section(name)</pre>	Remove named section from tree
doc(name)	Returns the documentation for a specified command
doc(name)	name
eval(code)	Evaluates code in the same context as this function
expand_branch()	
function(function, *args, **kwargs)	Call a function with aument abject as argument
increase_ratio()	Call a function with current object as argument
Increase_ratio()	
info()	Returns a dictionary of layout information
items(name)	Build a list of contained items for the given item class.
move_down()	
<pre>move_left()</pre>	
<pre>move_right()</pre>	
move_11gnt()	
move_up()	
- 1 0	
next()	Switch down in the window list
<pre>previous()</pre>	Switch up in the window list
section_down()	
section_up()	
<pre>sort_windows(sorter[, create_sections])</pre>	Sorts window to sections using sorter function

add_section(name)

Add named section to tree

collapse_branch()

$commands() \rightarrow list[str]$

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

decrease_ratio()

del_section(name)

Remove named section from tree

$doc(name) \rightarrow str$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

```
eval(code: str) \rightarrow tuple[bool, str | None]
     Evaluates code in the same context as this function
     Return value is tuple (success, result), success being a boolean and result being a string representing the
     return value of eval, or None if exec was used instead.
expand_branch()
function(function, *args, **kwargs) \rightarrow Task | None
     Call a function with current object as argument
increase_ratio()
info() \rightarrow dict[str, Any]
     Returns a dictionary of layout information
items(name: str) \rightarrow tuple[bool, list[str | int] | None]
     Build a list of contained items for the given item class.
     Exposing this allows __qsh__ to navigate the command graph.
     Returns a tuple (root, items) for the specified item class, where:
          root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout"
          defaults to current layout), and False if it does not (e.g. no default "widget").
          items: a list of contained items
move_down()
move_left()
move_right()
move_up()
next() \rightarrow None
     Switch down in the window list
previous() \rightarrow None
     Switch up in the window list
section_down()
section_up()
sort_windows(sorter, create sections=True)
     Sorts window to sections using sorter function
          Parameters
              sorter: function with single arg returning string
                 returns name of the section where window should be
              create_sections:
                 if this parameter is True (default), if sorter returns unknown section name it will be created
                 dynamically
```

15.2.17 VerticalTile

class libqtile.layout.verticaltile.VerticalTile

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.layout.<command>() qtile cmd-obj -o layout -f <command>

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command name
eval(code)	Evaluates code in the same context as this function
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
grow()	
info()	Returns a dictionary of layout information
<pre>items(name)</pre>	Build a list of contained items for the given item class.
maximize()	
next()	
normalize()	
previous()	
shrink()	
shuffle_down()	
shuffle_up()	

Command documentation

commands() \rightarrow list[str]

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

 $doc(name) \rightarrow str$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (success, result), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

```
function(function, *args, **kwargs) \rightarrow Task | None
      Call a function with current object as argument
grow()
info() \rightarrow dict[str, Any]
      Returns a dictionary of layout information
items(name: str) \rightarrow tuple[bool, list[str | int] | None]
      Build a list of contained items for the given item class.
      Exposing this allows __qsh__ to navigate the command graph.
      Returns a tuple (root, items) for the specified item class, where:
          root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout"
          defaults to current layout), and False if it does not (e.g. no default "widget").
          items: a list of contained items
maximize()
next() \rightarrow None
normalize()
previous() \rightarrow None
shrink()
shuffle_down()
shuffle_up()
```

15.2.18 Zoomy

class libqtile.layout.zoomy.Zoomy

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.layout.<command>()
qtile cmd-obj -o layout -f <command>

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Returns a dictionary of layout information
<pre>items(name)</pre>	Build a list of contained items for the given item class.
next()	
previous()	

```
commands() → list[str]
    Returns a list of possible commands for this object
    Used by __qsh__ for command completion and online help
doc(name) → str
    Returns the documentation for a specified command name
    Used by __qsh__ to provide online help.
eval(code: str) → tuple[bool, str | None]
```

Evaluates code in the same context as this function

Return value is tuple (*success*, *result*), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

```
function(function, *args, **kwargs) → Task | None
    Call a function with current object as argument
info() → dict[str, Any]
```

Returns a dictionary of layout information

```
\textbf{items}(\textit{name: str}) \rightarrow \text{tuple[bool, list[str | int] | None]}
```

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").


items: a list of contained items

```
next() \rightarrow None
previous() \rightarrow None
```

15.3 Window objects

The size and position of windows is determined by the current layout. Nevertheless, windows can still change their appearance in multiple ways (toggling floating state, fullscreen, opacity).

Windows can access objects relevant to the display of the window (i.e. the screen, group and layout).



class libqtile.backend.base.window.Window

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.window.<command>()
qtile cmd-obj -o window -f <command>

The following commands are available for this object:

center() Centers a floating window on the screen. commands() Returns a list of possible commands for this	
11 - 1.1 - C1 - 1.1 - C	object
disable_floating() Tile the window.	

continues on next page

Table 3 – continued from previous page

disable_fullscreen()	Un-fullscreen the window
doc(name)	Returns the documentation for a specified command
n	name
	Decrease the window's opacity by 10%.
<pre>enable_floating()</pre>	Float the window.
enable_fullscreen()	Fullscreen the window
eval(code)	Evaluates code in the same context as this function
focus([warp])	Focus this window and optional warp the pointer to
it	it.
function(function, *args, **kwargs)	Call a function with current object as argument
<pre>get_position()</pre>	Get the (x, y) of the window
<pre>get_size()</pre>	Get the (width, height) of the window
info()	Return information on this window.
is_visible()	Is this window visible (i.e.
	Build a list of contained items for the given item class.
	Keep this window above all others
keep_below([enable]) k	Keep this window below all others
kill()	Kill the window
move_down([force])	Move this window below the previous window along
ti	the z axis.
<pre>move_floating(dx, dy)</pre>	Move window by dx and dy
<pre>move_to_bottom()</pre>	Move this window below all windows in the current
la	layer e.g.
<pre>move_to_top()</pre>	Move this window above all windows in the current
la	ayer e.g.
move_up([force])	Move this window above the next window along the
Z	z axis.
<pre>place(x, y, width, height, borderwidth,)</pre>	Place the window in the given position.
resize_floating(dw, dh)	Add dw and dh to size of window
set_opacity(opacity)	Set the window's opacity
<pre>set_position(x, y)</pre>	Move floating window to x and y; swap tiling window
v	with the window under the pointer.
<pre>set_position_floating(x, y)</pre>	Move window to x and y
set_size_floating(w, h)	Set window dimensions to w and h
static([screen, x, y, width, height])	Makes this window a static window, attached to a
	Screen.
<pre>toggle_floating()</pre>	Toggle the floating state of the window.
toggle_fullscreen()	Toggle the fullscreen state of the window.
toggle_maximize()	Toggle the fullscreen state of the window.
toggle_minimize()	Toggle the minimized state of the window.
togroup([group_name, switch_group, toggle])	Move window to a specified group
toscreen([index])	Move window to a specified screen.
<pre>up_opacity()</pre>	Increase the window's opacity by 10%.

$\textbf{abstract bring_to_front()} \rightarrow None$

Bring the window to the front.

In X11, *bring_to_front* ignores all other layering rules and brings the window to the very front. When that window loses focus, it will be stacked again according the appropriate rules.

$\textbf{center()} \rightarrow None$

Centers a floating window on the screen.

commands() \rightarrow list[str]

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

abstract disable_floating() \rightarrow None

Tile the window.

abstract disable_fullscreen() \rightarrow None

Un-fullscreen the window

$doc(name) \rightarrow str$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

$down_opacity() \rightarrow None$

Decrease the window's opacity by 10%.

$\textbf{abstract enable_floating()} \rightarrow None$

Float the window.

abstract enable_fullscreen() \rightarrow None

Fullscreen the window

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (success, result), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

abstract focus(warp: bool = True) \rightarrow None

Focus this window and optional warp the pointer to it.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

abstract get_position() \rightarrow tuple[int, int]

Get the (x, y) of the window

abstract get_size() → tuple[int, int]

Get the (width, height) of the window

abstract info() → dict[str, Any]

Return information on this window.

Mimimum required keys are: - name - x - y - width - height - group - id - wm_class

$is_visible() \rightarrow bool$

Is this window visible (i.e. not hidden)?

items(name: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

keep_above(*enable*: *bool* | *None* = *None*)

Keep this window above all others

keep_below(enable: bool | None = None)

Keep this window below all others

abstract kill() \rightarrow None

Kill the window

move_down(force: bool = False) \rightarrow None

Move this window below the previous window along the z axis.

Will not lower a "normal" window (i.e. one that is not "kept_above/below") below a window that is marked as "kept_below".

Will not lower a window where "keep_above" is True unless force is set to True.

abstract move_floating(dx: int, dy: int) \rightarrow None

Move window by dx and dy

 $move_to_bottom() \rightarrow None$

Move this window below all windows in the current layer e.g. if you have 3 windows all with "keep_above" set, calling this method will move the window to the bottom of those three windows.

Calling this on a "normal" window will not raise it below a "kept_below" window.

 $move_to_top() \rightarrow None$

Move this window above all windows in the current layer e.g. if you have 3 windows all with "keep_above" set, calling this method will move the window to the top of those three windows.

Calling this on a "normal" window will not raise it above a "kept_above" window.

move_up(force: bool = False) \rightarrow None

Move this window above the next window along the z axis.

Will not raise a "normal" window (i.e. one that is not "kept_above/below") above a window that is marked as "kept_above".

Will not raise a window where "keep_below" is True unless force is set to True.

abstract place $(x, y, width, height, borderwidth, bordercolor, above=False, margin=None, respect_hints=False)$

Place the window in the given position.

abstract resize_floating(dw: int, dh: int) \rightarrow None

Add dw and dh to size of window

 $set_opacity(opacity: float) \rightarrow None$

Set the window's opacity

abstract set_position(x: int, y: int) \rightarrow None

Move floating window to x and y; swap tiling window with the window under the pointer.

abstract set_position_floating(x: int, y: int) \rightarrow None

Move window to x and y

abstract set_size_floating(w: int, h: int) \rightarrow None

Set window dimensions to w and h

abstract static($screen: int \mid None = None, x: int \mid None = None, y: int \mid None = None, width: int \mid None = None, height: int \mid None = None) <math>\rightarrow$ None

Makes this window a static window, attached to a Screen.

Values left unspecified are taken from the existing window state.

abstract toggle_floating() \rightarrow None

Toggle the floating state of the window.

$abstract\ toggle_fullscreen() \rightarrow None$

Toggle the fullscreen state of the window.

$abstract\ toggle_maximize() \rightarrow None$

Toggle the fullscreen state of the window.

$abstract\ toggle_minimize() \rightarrow None$

Toggle the minimized state of the window.

 $\textbf{abstract togroup} (\textit{group_name: str} \mid \textit{None} = \textit{None}, \textit{switch_group: bool} = \textit{False}, \textit{toggle: bool} = \textit{False}) \rightarrow \\ \textbf{None}$

Move window to a specified group

Also switch to that group if *switch_group* is True.

If *toggle* is True and and the specified group is already on the screen, use the last used group as target instead.

Examples

Move window to current group:

togroup()

Move window to group "a":

togroup("a")

Move window to group "a", and switch to group "a":

```
togroup("a", switch_group=True)
```

toscreen($index: int \mid None = None$) \rightarrow None

Move window to a specified screen.

If index is not specified, we assume the current screen

Examples

Move window to current screen:

toscreen()

Move window to screen 0:

toscreen(∅)


 $up_opacity() \rightarrow None$

Increase the window's opacity by 10%.

15.4 Group objects

Groups are Qtile's workspaces. Groups are not responsible for the positioning of windows (that is handled by the *layouts*) so the available commands are somewhat more limited in scope.

Groups have access to the layouts in that group, the windows in the group and the screen displaying the group.



class libqtile.group._Group

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.group.<command>() qtile cmd-obj -o group -f <command>

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command name
eval(code)	Evaluates code in the same context as this function
focus_back()	Focus the window that had focus before the current one got it.
focus_by_index(index)	Change to the window at the specified index in the current group.
<pre>focus_by_name(name)</pre>	Focus the first window with the given name.
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Returns a dictionary of info for this group
<pre>info_by_name(name)</pre>	Get the info for the first window with the given name without giving it focus.
<pre>items(name)</pre>	Build a list of contained items for the given item class.
<pre>next_window()</pre>	Focus the next window in group.
<pre>prev_window()</pre>	Focus the previous window in group.
set_label(label)	Set the display name of current group to be used in GroupBox widget.
setlayout(layout)	
swap_window_order(new_location)	Change the order of the current window within the current group.
<pre>switch_groups(name)</pre>	Switch position of current group with name
toscreen([screen, toggle])	Pull a group to a specified screen.
unminimize_all()	Unminimise all windows in this group

Command documentation

$commands() \rightarrow list[str]$

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

$doc(name) \rightarrow str$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (success, result), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

focus_back()

Focus the window that had focus before the current one got it.

Repeated calls to this function would basically continuously switch between the last two focused windows. Do nothing if less than 2 windows ever received focus.

focus_by_index(index: int) \rightarrow None

Change to the window at the specified index in the current group.

focus_by_name(name)

Focus the first window with the given name. Do nothing if the name is not found.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info()

Returns a dictionary of info for this group

info_by_name(name)

Get the info for the first window with the given name without giving it focus. Do nothing if the name is not found.

items (name: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

next_window()

Focus the next window in group.

Method cycles _all_ windows in group regardless if tiled in current layout or floating. Cycling of tiled and floating windows is not mixed. The cycling order depends on the current Layout.

prev_window()

Focus the previous window in group.

Method cycles _all_ windows in group regardless if tiled in current layout or floating. Cycling of tiled and floating windows is not mixed. The cycling order depends on the current Layout.

set_label(label)

Set the display name of current group to be used in GroupBox widget. If label is None, the name of the group is used as display name. If label is the empty string, the group is invisible in GroupBox.

setlayout(layout)

$swap_window_order(new\ location:\ int) \rightarrow None$

Change the order of the current window within the current group.

switch_groups(name)

Switch position of current group with name

toscreen(screen=None, toggle=False)

Pull a group to a specified screen.

Parameters

screen

Screen offset. If not specified, we assume the current screen.

toggle

If this group is already on the screen, then the group is toggled with last used

Examples

Pull group to the current screen:

toscreen()

Pull group to screen 0:

toscreen(∅)

unminimize_all()

Unminimise all windows in this group


15.5 Bar objects

The bar is primarily used to display widgets on the screen. As a result, the bar does not need many of its own commands.

To select a bar on the command graph, you must use a selector (as there is no default bar). The selector is the position of the bar on the screen i.e. "top", "bottom", "left" or "right".

The bar can access the screen it's on and the widgets it contains via the command graph.

15.5. Bar objects 297



class libqtile.bar.Bar

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.bar["position"].<command>()
qtile cmd-obj -o bar position -f <command>

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>fake_button_press(x, y[, button])</pre>	Fake a mouse-button-press on the bar.
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Info for this object.
<pre>items(name)</pre>	Build a list of contained items for the given item class.

```
commands() \rightarrow list[str]
```

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

```
doc(name) \rightarrow str
```

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

```
eval(code: str) \rightarrow tuple[bool, str | None]
```

Evaluates code in the same context as this function

Return value is tuple (*success*, *result*), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

```
fake_button_press(x: int, y: int, button: int = 1) \rightarrow None
```

Fake a mouse-button-press on the bar. Coordinates are relative to the top-left corner of the bar.

Parameters

 \mathbf{X}

X coordinate of the mouse button press.

y

Y coordinate of the mouse button press.

button:

Mouse button, for more details, see Mouse events.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

```
info() \rightarrow dict[str, Any]
```

Info for this object.

items(name: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:


root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

15.6 Widget objects

Widgets are small scripts that are used to provide content or add functionality to the bar. Some widgets will expose commands in order for functionality to be triggered indirectly (e.g. via a keypress).

Widgets can access the parent bar and screen via the command graph.



15.6.1 AGroupBox

class libqtile.widget.groupbox.AGroupBox

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["agroupbox"].<command>()
qtile cmd-obj -o widget agroupbox -f <command>

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Info for this object.
<pre>items(name)</pre>	Build a list of contained items for the given item class.
<pre>set_font([font, fontsize, fontshadow])</pre>	Change the font used by this widget.

$commands() \rightarrow list[str]$

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

 $doc(name) \rightarrow str$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (success, result), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info()

Info for this object.

items(name: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

set_font(font: str | None = None, fontsize: int = 0, fontshadow: str | tuple[int, int, int] | tuple[int, int, int, int, float] = ")

Change the font used by this widget. If font is None, the current font is used.

15.6.2 Backlight

class libqtile.widget.backlight.Backlight

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["backlight"].<command>()
qtile cmd-obj -o widget backlight -f <command>

The following commands are available for this object:

change_backlight(direction[, step])	
commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Info for this object.
items(name)	Build a list of contained items for the given item class.
<pre>set_font([font, fontsize, fontshadow])</pre>	Change the font used by this widget.

Command documentation

change_backlight(direction, step=None)

 $commands() \rightarrow list[str]$

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

 $doc(name) \rightarrow str$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (*success*, *result*), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info()

Info for this object.

items (*name*: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

 $set_font(font: str \mid None = None, fontsize: int = 0, fontshadow: str \mid tuple[int, int, int] \mid tuple[int, int, int, float] = ")$

Change the font used by this widget. If font is None, the current font is used.

15.6.3 Battery

class libqtile.widget.battery.Battery

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["battery"].<command>()
qtile cmd-obj -o widget battery -f <command>

The following commands are available for this object:

charge_dynamically()	
<pre>charge_to_full()</pre>	
commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>force_update()</pre>	Immediately poll the widget.
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Info for this object.
items(name)	Build a list of contained items for the given item class.
<pre>set_font([font, fontsize, fontshadow])</pre>	Change the font used by this widget.

Command documentation

charge_dynamically()

charge_to_full()

commands() \rightarrow list[str]

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

 $\mathbf{doc}(\mathit{name}) \to \mathrm{str}$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

```
eval(code: str) \rightarrow tuple[bool, str | None]
```

Evaluates code in the same context as this function

Return value is tuple (*success*, *result*), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

force_update()

Immediately poll the widget. Existing timers are unaffected.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info()

Info for this object.

items (*name*: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

 $set_font(font: str \mid None = None, fontsize: int = 0, fontshadow: str \mid tuple[int, int, int] \mid tuple[int, int, int, float] = ")$

Change the font used by this widget. If font is None, the current font is used.

15.6.4 Batterylcon

class libqtile.widget.battery.BatteryIcon

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["batteryicon"].<command>()
qtile cmd-obj -o widget batteryicon -f <command>

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Info for this object.
<pre>items(name)</pre>	Build a list of contained items for the given item class.

Command documentation

commands() \rightarrow list[str]

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

$doc(name) \rightarrow str$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (success, result), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info()

Info for this object.

items (name: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

15.6.5 Bluetooth

class libqtile.widget.bluetooth.Bluetooth

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["bluetooth"].<command>()
qtile cmd-obj -o widget bluetooth -f <command>

The following commands are available for this object:

click()	Perform default action on visible item.
commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command name
eval(code)	Evaluates code in the same context as this function
function(function, *args, **kwargs)	Call a function with current object as argument
info()	Info for this object.
items(name)	Build a list of contained items for the given item class.
scroll_down()	Scroll down to next item.
scroll_up()	Scroll up to next item.
<pre>set_font([font, fontsize, fontshadow])</pre>	Change the font used by this widget.

click()

Perform default action on visible item.

commands() \rightarrow list[str]

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

$doc(name) \rightarrow str$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (*success*, *result*), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info()

Info for this object.

items(name: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

scroll_down()

Scroll down to next item.

scroll_up()

Scroll up to next item.

```
set_font(font: str \mid None = None, fontsize: int = 0, fontshadow: str \mid tuple[int, int, int] \mid tuple[int, int, int, float] = ")
```

Change the font used by this widget. If font is None, the current font is used.

15.6.6 CPU

class libqtile.widget.cpu.CPU

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["cpu"].<command>()
qtile cmd-obj -o widget cpu -f <command>

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>force_update()</pre>	Immediately poll the widget.
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Info for this object.
<pre>items(name)</pre>	Build a list of contained items for the given item class.
<pre>set_font([font, fontsize, fontshadow])</pre>	Change the font used by this widget.

Command documentation

$commands() \rightarrow list[str]$

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

 $doc(name) \rightarrow str$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (success, result), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

force_update()

Immediately poll the widget. Existing timers are unaffected.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info()

Info for this object.

items (*name*: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

 $set_font(font: str \mid None = None, fontsize: int = 0, fontshadow: str \mid tuple[int, int, int] \mid tuple[int, int, int, float] = ")$

Change the font used by this widget. If font is None, the current font is used.

15.6.7 CPUGraph

class libqtile.widget.graph.CPUGraph

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["cpugraph"].<command>()
qtile cmd-obj -o widget cpugraph -f <command>

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Info for this object.
<pre>items(name)</pre>	Build a list of contained items for the given item class.

Command documentation

commands() \rightarrow list[str]

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

 $doc(name) \rightarrow str$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (success, result), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info()

Info for this object.

items(name: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

15.6.8 Canto

class libqtile.widget.canto.Canto

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["canto"].<command>()
qtile cmd-obj -o widget canto -f <command>

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>force_update()</pre>	Immediately poll the widget.
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Info for this object.
<pre>items(name)</pre>	Build a list of contained items for the given item class.
<pre>set_font([font, fontsize, fontshadow])</pre>	Change the font used by this widget.

Command documentation

commands() \rightarrow list[str]

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

$doc(name) \rightarrow str$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (success, result), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

force_update()

Immediately poll the widget. Existing timers are unaffected.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info()

Info for this object.

items (*name*: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

set_font(font: str | None = None, fontsize: int = 0, fontshadow: str | tuple[int, int, int] | tuple[int, int, int, int, float] = ")

Change the font used by this widget. If font is None, the current font is used.

15.6.9 CapsNumLockIndicator

class libqtile.widget.caps_num_lock_indicator.CapsNumLockIndicator

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["capsnumlockindicator"].<command>()
qtile cmd-obj -o widget capsnumlockindicator -f <command>

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>force_update()</pre>	Immediately poll the widget.
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Info for this object.
<pre>items(name)</pre>	Build a list of contained items for the given item class.
<pre>set_font([font, fontsize, fontshadow])</pre>	Change the font used by this widget.

Command documentation

commands() \rightarrow list[str]

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

 $\mathbf{doc}(\mathit{name}) \to \mathit{str}$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (success, result), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

force_update()

Immediately poll the widget. Existing timers are unaffected.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info()

Info for this object.

items(name: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

 $set_font(font: str \mid None = None, fontsize: int = 0, fontshadow: str \mid tuple[int, int, int] \mid tuple[int, int, int, float] = ")$

Change the font used by this widget. If font is None, the current font is used.

15.6.10 CheckUpdates

class libqtile.widget.check_updates.CheckUpdates

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["checkupdates"].<command>()
qtile cmd-obj -o widget checkupdates -f <command>

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>force_update()</pre>	Immediately poll the widget.
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Info for this object.
<pre>items(name)</pre>	Build a list of contained items for the given item class.
<pre>set_font([font, fontsize, fontshadow])</pre>	Change the font used by this widget.

Command documentation

 $commands() \rightarrow list[str]$

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

 $doc(name) \rightarrow str$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

```
eval(code: str) \rightarrow tuple[bool, str | None]
```

Evaluates code in the same context as this function

Return value is tuple (*success*, *result*), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

force_update()

Immediately poll the widget. Existing timers are unaffected.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info()

Info for this object.

items (name: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

 $set_font(font: str \mid None = None, fontsize: int = 0, fontshadow: str \mid tuple[int, int, int] \mid tuple[int, int, int, float] = ")$

Change the font used by this widget. If font is None, the current font is used.

15.6.11 Chord

class libqtile.widget.chord.Chord

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["chord"].<command>()
qtile cmd-obj -o widget chord -f <command>

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Info for this object.
<pre>items(name)</pre>	Build a list of contained items for the given item class.
<pre>set_font([font, fontsize, fontshadow])</pre>	Change the font used by this widget.

Command documentation

commands() \rightarrow list[str]

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

$doc(name) \rightarrow str$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (*success*, *result*), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info()

Info for this object.

items (name: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

set_font(font: str | None = None, fontsize: int = 0, fontshadow: str | tuple[int, int, int] | tuple[int, int, int, float] = ")

Change the font used by this widget. If font is None, the current font is used.

15.6.12 Clipboard

class libqtile.widget.clipboard.Clipboard

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["clipboard"].<command>()
qtile cmd-obj -o widget clipboard -f <command>

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Info for this object.
<pre>items(name)</pre>	Build a list of contained items for the given item class.
<pre>set_font([font, fontsize, fontshadow])</pre>	Change the font used by this widget.

$commands() \rightarrow list[str]$

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

 $doc(name) \rightarrow str$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (success, result), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info()

Info for this object.

items(name: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

set_font(font: str | None = None, fontsize: int = 0, fontshadow: str | tuple[int, int, int] | tuple[int, int, int, int, float] = ")

Change the font used by this widget. If font is None, the current font is used.

15.6.13 Clock

class libqtile.widget.clock.Clock

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["clock"].<command>()
qtile cmd-obj -o widget clock -f <command>

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Info for this object.
<pre>items(name)</pre>	Build a list of contained items for the given item class.
<pre>set_font([font, fontsize, fontshadow])</pre>	Change the font used by this widget.
<pre>update_timezone([timezone])</pre>	Force the clock to update timezone information.
<pre>use_system_timezone()</pre>	Force clock to use system timezone.

Command documentation

$commands() \rightarrow list[str]$

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

$doc(name) \rightarrow str$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (success, result), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info()

Info for this object.

items(name: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

set_font(font: str | None = None, fontsize: int = 0, fontshadow: str | tuple[int, int, int] | tuple[int, int, int, int, float] = ")

Change the font used by this widget. If font is None, the current font is used.

```
update_timezone(timezone: str | tzinfo | None = None)
```

Force the clock to update timezone information.

If the method is called with no arguments then the widget will reload the timzeone set on the computer (e.g. via timedatectl set-timezone ..). This will have no effect if you have previously set a timezone value.

Alternatively, you can pass a timezone string (e.g. "Europe/Lisbon") to change the specified timezone. Setting this to an empty string will cause the clock to rely on the system timezone.

use_system_timezone()

Force clock to use system timezone.

15.6.14 Cmus

class libqtile.widget.cmus.Cmus

API commands

To access commands on this object via the command graph, use one of the following options:

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>force_update()</pre>	Immediately poll the widget.
function(function, *args, **kwargs)	Call a function with current object as argument
info()	Info for this object.
<pre>items(name)</pre>	Build a list of contained items for the given item class.
<pre>set_font([font, fontsize, fontshadow])</pre>	Change the font used by this widget.

Command documentation

commands() \rightarrow list[str]

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

 $\mathbf{doc}(\mathit{name}) \to \mathrm{str}$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (success, result), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

force_update()

Immediately poll the widget. Existing timers are unaffected.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info()

Info for this object.

items (*name*: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

 $set_font(font: str \mid None = None, fontsize: int = 0, fontshadow: str \mid tuple[int, int, int] \mid tuple[int, int, int, float] = ")$

Change the font used by this widget. If font is None, the current font is used.

15.6.15 Countdown

class libqtile.widget.countdown.Countdown

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["countdown"].<command>()
qtile cmd-obj -o widget countdown -f <command>

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Info for this object.
<pre>items(name)</pre>	Build a list of contained items for the given item class.
<pre>set_font([font, fontsize, fontshadow])</pre>	Change the font used by this widget.

Command documentation

```
commands() \rightarrow list[str]
```

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

```
doc(name) \rightarrow str
```

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

```
eval(code: str) \rightarrow tuple[bool, str | None]
```

Evaluates code in the same context as this function

Return value is tuple (success, result), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

```
function(function, *args, **kwargs) \rightarrow Task | None
```

Call a function with current object as argument

info()

Info for this object.

```
items(name: str) \rightarrow tuple[bool, list[str | int] | None]
```

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

set_font(font: str | None = None, fontsize: int = 0, fontshadow: str | tuple[int, int, int] | tuple[int, int, int, float] = ")

Change the font used by this widget. If font is None, the current font is used.

15.6.16 CryptoTicker

class libqtile.widget.crypto_ticker.CryptoTicker

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["cryptoticker"].<command>()
qtile cmd-obj -o widget cryptoticker -f <command>

The following commands are available for this object:

commands()Returns a list of possible commands for this objectdoc(name)Returns the documentation for a specified command nameeval(code)Evaluates code in the same context as this functionforce_update()Immediately poll the widget.function(function, *args, **kwargs)Call a function with current object as argumentinfo()Info for this object.items(name)Build a list of contained items for the given item class.set_font([font, fontsize, fontshadow])Change the font used by this widget.		
name eval(code) Evaluates code in the same context as this function force_update() Immediately poll the widget. function(function, *args, **kwargs) Call a function with current object as argument info() Info for this object. items(name) Build a list of contained items for the given item class.	commands()	Returns a list of possible commands for this object
eval(code)Evaluates code in the same context as this functionforce_update()Immediately poll the widget.function(function, *args, **kwargs)Call a function with current object as argumentinfo()Info for this object.items(name)Build a list of contained items for the given item class.	doc(name)	Returns the documentation for a specified command
force_update()Immediately poll the widget.function(function, *args, **kwargs)Call a function with current object as argumentinfo()Info for this object.items(name)Build a list of contained items for the given item class.		name
function(function, *args, **kwargs)Call a function with current object as argumentinfo()Info for this object.items(name)Build a list of contained items for the given item class.	eval(code)	Evaluates code in the same context as this function
info()Info for this object.items(name)Build a list of contained items for the given item class.	<pre>force_update()</pre>	Immediately poll the widget.
items(name) Build a list of contained items for the given item class.	function(function, *args, **kwargs)	Call a function with current object as argument
· · · · ·	info()	Info for this object.
<pre>set_font([font, fontsize, fontshadow])</pre> Change the font used by this widget.	<pre>items(name)</pre>	Build a list of contained items for the given item class.
	<pre>set_font([font, fontsize, fontshadow])</pre>	Change the font used by this widget.

$commands() \rightarrow list[str]$

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

$doc(name) \rightarrow str$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (success, result), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

force_update()

Immediately poll the widget. Existing timers are unaffected.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info()

Info for this object.

items (*name*: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

set_font(font: str | None = None, fontsize: int = 0, fontshadow: str | tuple[int, int, int] | tuple[int, int, int, float] = ")

Change the font used by this widget. If font is None, the current font is used.

15.6.17 CurrentLayout

class libqtile.widget.currentlayout.CurrentLayout

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["currentlayout"].<command>()
qtile cmd-obj -o widget currentlayout -f <command>

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Info for this object.
<pre>items(name)</pre>	Build a list of contained items for the given item class.
<pre>set_font([font, fontsize, fontshadow])</pre>	Change the font used by this widget.

Command documentation

commands() \rightarrow list[str]

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

$\mathbf{doc}(\mathit{name}) \to \mathrm{str}$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (success, result), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info()

Info for this object.

items (name: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

 $set_font(font: str \mid None = None, fontsize: int = 0, fontshadow: str \mid tuple[int, int, int] \mid tuple[int, int, int, float] = ")$

Change the font used by this widget. If font is None, the current font is used.

15.6.18 CurrentScreen

class libgtile.widget.currentscreen.CurrentScreen

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["currentscreen"].<command>()
qtile cmd-obj -o widget currentscreen -f <command>

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Info for this object.
<pre>items(name)</pre>	Build a list of contained items for the given item class.
<pre>set_font([font, fontsize, fontshadow])</pre>	Change the font used by this widget.

Command documentation

$commands() \rightarrow list[str]$

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

 $doc(name) \rightarrow str$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (*success, result*), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info()

Info for this object.

items(name: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

set_font(font: str | None = None, fontsize: int = 0, fontshadow: str | tuple[int, int, int] | tuple[int, int, int, int, float] = ")

Change the font used by this widget. If font is None, the current font is used.

15.6.19 DF

class libqtile.widget.df.DF

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["df"].<command>()
qtile cmd-obj -o widget df -f <command>

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>force_update()</pre>	Immediately poll the widget.
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Info for this object.
<pre>items(name)</pre>	Build a list of contained items for the given item class.
<pre>set_font([font, fontsize, fontshadow])</pre>	Change the font used by this widget.

Command documentation

commands() \rightarrow list[str]

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

 $doc(name) \rightarrow str$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (success, result), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

force_update()

Immediately poll the widget. Existing timers are unaffected.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info()

Info for this object.

items(name: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

 $set_font(font: str \mid None = None, fontsize: int = 0, fontshadow: str \mid tuple[int, int, int] \mid tuple[int, int, int, float] = ")$

Change the font used by this widget. If font is None, the current font is used.

15.6.20 DoNotDisturb

class libqtile.widget.do_not_disturb.DoNotDisturb

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["donotdisturb"].<command>()
qtile cmd-obj -o widget donotdisturb -f <command>

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Info for this object.
<pre>items(name)</pre>	Build a list of contained items for the given item class.
<pre>set_font([font, fontsize, fontshadow])</pre>	Change the font used by this widget.

Command documentation

commands() \rightarrow list[str]

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

 $\mathbf{doc}(name) \rightarrow \mathbf{str}$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (success, result), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info()

Info for this object.

items(name: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

 $set_font(font: str \mid None = None, fontsize: int = 0, fontshadow: str \mid tuple[int, int, int] \mid tuple[int, int, int, float] = ")$

Change the font used by this widget. If font is None, the current font is used.

15.6.21 GenPollCommand

class libqtile.widget.generic_poll_text.GenPollCommand

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["genpollcommand"].<command>()
qtile cmd-obj -o widget genpollcommand -f <command>

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>force_update()</pre>	Immediately poll the widget.
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Info for this object.
<pre>items(name)</pre>	Build a list of contained items for the given item class.
<pre>set_font([font, fontsize, fontshadow])</pre>	Change the font used by this widget.

Command documentation

commands() \rightarrow list[str]

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

$doc(name) \rightarrow str$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (*success*, *result*), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

force_update()

Immediately poll the widget. Existing timers are unaffected.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info()

Info for this object.

items(name: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

set_font(font: str | None = None, fontsize: int = 0, fontshadow: str | tuple[int, int, int] | tuple[int, int, int, int, float] = ")

Change the font used by this widget. If font is None, the current font is used.

15.6.22 GenPollText

class libqtile.widget.generic_poll_text.GenPollText

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["genpolltext"].<command>()
qtile cmd-obj -o widget genpolltext -f <command>

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>force_update()</pre>	Immediately poll the widget.
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Info for this object.
<pre>items(name)</pre>	Build a list of contained items for the given item class.
<pre>set_font([font, fontsize, fontshadow])</pre>	Change the font used by this widget.

commands() \rightarrow list[str]

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

$doc(name) \rightarrow str$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (success, result), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

force_update()

Immediately poll the widget. Existing timers are unaffected.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info()

Info for this object.

items (*name*: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

set_font(font: str | None = None, fontsize: int = 0, fontshadow: str | tuple[int, int, int] | tuple[int, int, int, int, float] = ")

Change the font used by this widget. If font is None, the current font is used.

15.6.23 GenPollUrl

class libqtile.widget.generic_poll_text.GenPollUrl

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["genpollurl"].<command>()
qtile cmd-obj -o widget genpollurl -f <command>

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>force_update()</pre>	Immediately poll the widget.
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Info for this object.
<pre>items(name)</pre>	Build a list of contained items for the given item class.
<pre>set_font([font, fontsize, fontshadow])</pre>	Change the font used by this widget.

Command documentation

commands() \rightarrow list[str]

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

$doc(name) \rightarrow str$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (success, result), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

force_update()

Immediately poll the widget. Existing timers are unaffected.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info()

Info for this object.

items (*name*: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

set_font(font: str | None = None, fontsize: int = 0, fontshadow: str | tuple[int, int, int] | tuple[int, int, int, int, float] = ")

Change the font used by this widget. If font is None, the current font is used.

15.6.24 GmailChecker

class libqtile.widget.gmail_checker.GmailChecker

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["gmailchecker"].<command>()
qtile cmd-obj -o widget gmailchecker -f <command>

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>force_update()</pre>	Immediately poll the widget.
function(function, *args, **kwargs)	Call a function with current object as argument
info()	Info for this object.
<pre>items(name)</pre>	Build a list of contained items for the given item class.
<pre>set_font([font, fontsize, fontshadow])</pre>	Change the font used by this widget.

Command documentation

commands() \rightarrow list[str]

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

 $\mathbf{doc}(\mathit{name}) \to \mathit{str}$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (*success*, *result*), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

force_update()

Immediately poll the widget. Existing timers are unaffected.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info()

Info for this object.

items (*name*: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

 $set_font(font: str \mid None = None, fontsize: int = 0, fontshadow: str \mid tuple[int, int, int] \mid tuple[int, int, int, float] = ")$

Change the font used by this widget. If font is None, the current font is used.

15.6.25 GroupBox

class libqtile.widget.groupbox.GroupBox

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["groupbox"].<command>()
qtile cmd-obj -o widget groupbox -f <command>

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Info for this object.
<pre>items(name)</pre>	Build a list of contained items for the given item class.
<pre>set_font([font, fontsize, fontshadow])</pre>	Change the font used by this widget.

Command documentation

commands() \rightarrow list[str]

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

 $\mathbf{doc}(\mathit{name}) \to \mathrm{str}$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (success, result), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info()

Info for this object.

items(name: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

 $set_font(font: str \mid None = None, fontsize: int = 0, fontshadow: str \mid tuple[int, int, int] \mid tuple[int, int, int, float] = ")$

Change the font used by this widget. If font is None, the current font is used.

15.6.26 HDD

class libqtile.widget.hdd.HDD

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["hdd"].<command>()
qtile cmd-obj -o widget hdd -f <command>

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>force_update()</pre>	Immediately poll the widget.
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Info for this object.
<pre>items(name)</pre>	Build a list of contained items for the given item class.
<pre>set_font([font, fontsize, fontshadow])</pre>	Change the font used by this widget.

Command documentation

commands() \rightarrow list[str]

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

$doc(name) \rightarrow str$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (*success*, *result*), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

force_update()

Immediately poll the widget. Existing timers are unaffected.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info()

Info for this object.

items(name: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

 $set_font(font: str \mid None = None, fontsize: int = 0, fontshadow: str \mid tuple[int, int, int] \mid tuple[int, int, int, float] = ")$

Change the font used by this widget. If font is None, the current font is used.

15.6.27 HDDBusyGraph

class libqtile.widget.graph.HDDBusyGraph

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["hddbusygraph"].<command>()
qtile cmd-obj -o widget hddbusygraph -f <command>

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
function(function, *args, **kwargs)	Call a function with current object as argument
info()	Info for this object.
<pre>items(name)</pre>	Build a list of contained items for the given item class.

commands() \rightarrow list[str]

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

$doc(name) \rightarrow str$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (*success*, *result*), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info()

Info for this object.

items(name: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

15.6.28 HDDGraph

class libqtile.widget.graph.HDDGraph

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["hddgraph"].<command>()
qtile cmd-obj -o widget hddgraph -f <command>

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
function(function, *args, **kwargs)	Call a function with current object as argument
info()	Info for this object.
<pre>items(name)</pre>	Build a list of contained items for the given item class.

commands() \rightarrow list[str]

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

$doc(name) \rightarrow str$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (*success*, *result*), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info()

Info for this object.

items(name: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

15.6.29 IdleRPG

class libqtile.widget.idlerpg.IdleRPG

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["idlerpg"].<command>()
qtile cmd-obj -o widget idlerpg -f <command>

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>force_update()</pre>	Immediately poll the widget.
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Info for this object.
<pre>items(name)</pre>	Build a list of contained items for the given item class.
<pre>set_font([font, fontsize, fontshadow])</pre>	Change the font used by this widget.

commands() \rightarrow list[str]

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

$doc(name) \rightarrow str$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (success, result), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

force_update()

Immediately poll the widget. Existing timers are unaffected.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info()

Info for this object.

items (*name*: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

set_font(font: str | None = None, fontsize: int = 0, fontshadow: str | tuple[int, int, int] | tuple[int, int, int, int, float] = ")

Change the font used by this widget. If font is None, the current font is used.

15.6.30 Image

class libqtile.widget.image.Image

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["image"].<command>()
qtile cmd-obj -o widget image -f <command>

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
function(function, *args, **kwargs)	Call a function with current object as argument
info()	Info for this object.
<pre>items(name)</pre>	Build a list of contained items for the given item class.
<pre>update(filename)</pre>	

Command documentation

 $commands() \rightarrow list[str]$

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

 $doc(name) \rightarrow str$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (success, result), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info()

Info for this object.

items(name: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

update(filename)

15.6.31 ImapWidget

class libqtile.widget.imapwidget.ImapWidget

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["imapwidget"].<command>()
qtile cmd-obj -o widget imapwidget -f <command>

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>force_update()</pre>	Immediately poll the widget.
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Info for this object.
<pre>items(name)</pre>	Build a list of contained items for the given item class.
<pre>set_font([font, fontsize, fontshadow])</pre>	Change the font used by this widget.

Command documentation

$commands() \rightarrow list[str]$

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

$doc(name) \rightarrow str$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (success, result), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

force_update()

Immediately poll the widget. Existing timers are unaffected.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info()

Info for this object.

items(name: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

set_font(font: str | None = None, fontsize: int = 0, fontshadow: str | tuple[int, int, int] | tuple[int, int, int, int, float] = ")

Change the font used by this widget. If font is None, the current font is used.

15.6.32 KeyboardKbdd

class libqtile.widget.keyboardkbdd.KeyboardKbdd

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["keyboardkbdd"].<command>()
qtile cmd-obj -o widget keyboardkbdd -f <command>

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>force_update()</pre>	Immediately poll the widget.
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Info for this object.
<pre>items(name)</pre>	Build a list of contained items for the given item class.
<pre>set_font([font, fontsize, fontshadow])</pre>	Change the font used by this widget.

Command documentation

 $\textbf{commands()} \rightarrow list[str]$

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

 $doc(name) \rightarrow str$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (success, result), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

force_update()

Immediately poll the widget. Existing timers are unaffected.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info()

Info for this object.

items(name: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

set_font(font: str | None = None, fontsize: int = 0, fontshadow: str | tuple[int, int, int] | tuple[int, int, int, int, float] = ")

Change the font used by this widget. If font is None, the current font is used.

15.6.33 KeyboardLayout

class libqtile.widget.keyboardlayout.KeyboardLayout

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["keyboardlayout"].<command>()
qtile cmd-obj -o widget keyboardlayout -f <command>

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Info for this object.
<pre>items(name)</pre>	Build a list of contained items for the given item class.
next_keyboard()	set the next layout in the list of configured keyboard
	layouts as new current layout in use
<pre>set_font([font, fontsize, fontshadow])</pre>	Change the font used by this widget.

Command documentation

commands() \rightarrow list[str]

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

$doc(name) \rightarrow str$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (success, result), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info()

Info for this object.

items(name: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

next_keyboard()

set the next layout in the list of configured keyboard layouts as new current layout in use

If the current keyboard layout is not in the list, it will set as new layout the first one in the list.

set_font(font: str | None = None, fontsize: int = 0, fontshadow: str | tuple[int, int, int] | tuple[int, int, int, float] = ")

Change the font used by this widget. If font is None, the current font is used.

15.6.34 KhalCalendar

class libqtile.widget.khal_calendar.KhalCalendar

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["khalcalendar"].<command>()
qtile cmd-obj -o widget khalcalendar -f <command>

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>force_update()</pre>	Immediately poll the widget.
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Info for this object.
<pre>items(name)</pre>	Build a list of contained items for the given item class.
<pre>set_font([font, fontsize, fontshadow])</pre>	Change the font used by this widget.

commands() \rightarrow list[str]

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

$doc(name) \rightarrow str$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (success, result), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

force_update()

Immediately poll the widget. Existing timers are unaffected.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info()

Info for this object.

items (*name*: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

set_font(font: str | None = None, fontsize: int = 0, fontshadow: str | tuple[int, int, int] | tuple[int, int, int, int, float] = ")

Change the font used by this widget. If font is None, the current font is used.

15.6.35 LaunchBar

class libqtile.widget.launchbar.LaunchBar

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["launchbar"].<command>()
qtile cmd-obj -o widget launchbar -f <command>

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Info for this object.
<pre>items(name)</pre>	Build a list of contained items for the given item class.

Command documentation

commands() \rightarrow list[str]

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

 $doc(name) \rightarrow str$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (success, result), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info()

Info for this object.

items(name: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

15.6.36 Load

class libqtile.widget.load.Load

API commands

To access commands on this object via the command graph, use one of the following options:

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>force_update()</pre>	Immediately poll the widget.
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Info for this object.
<pre>items(name)</pre>	Build a list of contained items for the given item class.
next_load()	
<pre>set_font([font, fontsize, fontshadow])</pre>	Change the font used by this widget.

Command documentation

$commands() \rightarrow list[str]$

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

$doc(name) \rightarrow str$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (success, result), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

force_update()

Immediately poll the widget. Existing timers are unaffected.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info()

Info for this object.

items(name: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

next_load()

 $set_font(font: str \mid None = None, fontsize: int = 0, fontshadow: str \mid tuple[int, int, int] \mid tuple[int, int, int, float] = ")$

Change the font used by this widget. If font is None, the current font is used.

15.6.37 Maildir

class libqtile.widget.maildir.Maildir

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["maildir"].<command>()
qtile cmd-obj -o widget maildir -f <command>

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>force_update()</pre>	Immediately poll the widget.
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Info for this object.
<pre>items(name)</pre>	Build a list of contained items for the given item class.
<pre>set_font([font, fontsize, fontshadow])</pre>	Change the font used by this widget.

Command documentation

commands() \rightarrow list[str]

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

 $doc(name) \rightarrow str$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (success, result), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

force_update()

Immediately poll the widget. Existing timers are unaffected.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info()

Info for this object.

items (name: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

 $set_font(font: str \mid None = None, fontsize: int = 0, fontshadow: str \mid tuple[int, int, int] \mid tuple[int, int, int, float] = ")$

Change the font used by this widget. If font is None, the current font is used.

15.6.38 **Memory**

class libqtile.widget.memory.Memory

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["memory"].<command>()
qtile cmd-obj -o widget memory -f <command>

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>force_update()</pre>	Immediately poll the widget.
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Info for this object.
<pre>items(name)</pre>	Build a list of contained items for the given item class.
<pre>set_font([font, fontsize, fontshadow])</pre>	Change the font used by this widget.

Command documentation

commands() \rightarrow list[str]

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

 $\mathbf{doc}(\mathit{name}) \to \mathit{str}$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (success, result), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

force_update()

Immediately poll the widget. Existing timers are unaffected.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info()

Info for this object.

items (*name*: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

 $set_font(font: str \mid None = None, fontsize: int = 0, fontshadow: str \mid tuple[int, int, int] \mid tuple[int, int, int, float] = ")$

Change the font used by this widget. If font is None, the current font is used.

15.6.39 MemoryGraph

class libqtile.widget.graph.MemoryGraph

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["memorygraph"].<command>()
qtile cmd-obj -o widget memorygraph -f <command>

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Info for this object.
<pre>items(name)</pre>	Build a list of contained items for the given item class.

Command documentation

commands() \rightarrow list[str]

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

$doc(name) \rightarrow str$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (success, result), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info()

Info for this object.

items(name: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

15.6.40 Mirror

class libqtile.widget.base.Mirror

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["mirror"].<command>()
qtile cmd-obj -o widget mirror -f <command>

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Info for this object.
<pre>items(name)</pre>	Build a list of contained items for the given item class.

Command documentation

commands() \rightarrow list[str]

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

$doc(name) \rightarrow str$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (success, result), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info()

Info for this object.

items(name: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

15.6.41 Moc

class libqtile.widget.moc.Moc

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["moc"].<command>()
qtile cmd-obj -o widget moc -f <command>

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>force_update()</pre>	Immediately poll the widget.
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Info for this object.
<pre>items(name)</pre>	Build a list of contained items for the given item class.
<pre>set_font([font, fontsize, fontshadow])</pre>	Change the font used by this widget.

```
commands() \rightarrow list[str]
```

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

```
doc(name) \rightarrow str
```

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

```
eval(code: str) \rightarrow tuple[bool, str | None]
```

Evaluates code in the same context as this function

Return value is tuple (*success*, *result*), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

force_update()

Immediately poll the widget. Existing timers are unaffected.

```
function(function, *args, **kwargs) \rightarrow Task | None
```

Call a function with current object as argument

info()

Info for this object.

```
items(name: str) \rightarrow tuple[bool, list[str | int] | None]
```

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

 $set_font(font: str \mid None = None, fontsize: int = 0, fontshadow: str \mid tuple[int, int, int] \mid tuple[int, int, int, float] = ")$

Change the font used by this widget. If font is None, the current font is used.

15.6.42 Mpd2

class libqtile.widget.mpd2widget.Mpd2

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["mpd2"].<command>()
qtile cmd-obj -o widget mpd2 -f <command>

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>force_update()</pre>	Immediately poll the widget.
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Info for this object.
<pre>items(name)</pre>	Build a list of contained items for the given item class.
<pre>set_font([font, fontsize, fontshadow])</pre>	Change the font used by this widget.

commands() \rightarrow list[str]

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

$doc(name) \rightarrow str$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (success, result), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

force_update()

Immediately poll the widget. Existing timers are unaffected.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info()

Info for this object.

items (*name*: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

set_font(font: str | None = None, fontsize: int = 0, fontshadow: str | tuple[int, int, int] | tuple[int, int, int, float] = ")

Change the font used by this widget. If font is None, the current font is used.

15.6.43 Mpris2

class libqtile.widget.mpris2widget.Mpris2

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["mpris2"].<command>()
qtile cmd-obj -o widget mpris2 -f <command>

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	What's the current state of the widget?
items(name)	Build a list of contained items for the given item class.
next()	Play the next track.
play_pause()	Toggle the playback status.
previous()	Play the previous track.
<pre>set_font([font, fontsize, fontshadow])</pre>	Change the font used by this widget.
stop()	Stop playback.

Command documentation

$commands() \rightarrow list[str]$

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

 $doc(name) \rightarrow str$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (*success*, *result*), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info()

What's the current state of the widget?

items(name: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

 $next() \rightarrow None$

Play the next track.

 $play_pause() \rightarrow None$

Toggle the playback status.

 $previous() \rightarrow None$

Play the previous track.

set_font(font: str | None = None, fontsize: int = 0, fontshadow: str | tuple[int, int, int] | tuple[int, int, int, float] = ")

Change the font used by this widget. If font is None, the current font is used.

 $stop() \rightarrow None$

Stop playback.

15.6.44 Net

class libqtile.widget.net.Net

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["net"].<command>()
qtile cmd-obj -o widget net -f <command>

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>force_update()</pre>	Immediately poll the widget.
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Info for this object.
<pre>items(name)</pre>	Build a list of contained items for the given item class.
<pre>set_font([font, fontsize, fontshadow])</pre>	Change the font used by this widget.

Command documentation

 $commands() \rightarrow list[str]$

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

 $doc(name) \rightarrow str$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

```
eval(code: str) \rightarrow tuple[bool, str | None]
```

Evaluates code in the same context as this function

Return value is tuple (*success*, *result*), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

force_update()

Immediately poll the widget. Existing timers are unaffected.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info()

Info for this object.

items (*name*: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

 $set_font(font: str \mid None = None, fontsize: int = 0, fontshadow: str \mid tuple[int, int, int] \mid tuple[int, int, int, float] = ")$

Change the font used by this widget. If font is None, the current font is used.

15.6.45 NetGraph

class libqtile.widget.graph.NetGraph

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["netgraph"].<command>()
qtile cmd-obj -o widget netgraph -f <command>

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Info for this object.
items(name)	Build a list of contained items for the given item class.

Command documentation

commands() \rightarrow list[str]

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

$doc(name) \rightarrow str$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (success, result), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info()

Info for this object.

items(name: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

15.6.46 NetUP

class libqtile.widget.netup.NetUP

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["netup"].<command>()
qtile cmd-obj -o widget netup -f <command>

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>force_update()</pre>	Immediately poll the widget.
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Info for this object.
<pre>items(name)</pre>	Build a list of contained items for the given item class.
<pre>set_font([font, fontsize, fontshadow])</pre>	Change the font used by this widget.

```
commands() \rightarrow list[str]
```

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

```
doc(name) \rightarrow str
```

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

```
eval(code: str) \rightarrow tuple[bool, str | None]
```

Evaluates code in the same context as this function

Return value is tuple (*success*, *result*), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

force_update()

Immediately poll the widget. Existing timers are unaffected.

```
function(function, *args, **kwargs) \rightarrow Task | None
```

Call a function with current object as argument

info()

Info for this object.

```
items(name: str) \rightarrow tuple[bool, list[str | int] | None]
```

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

 $set_font(font: str \mid None = None, fontsize: int = 0, fontshadow: str \mid tuple[int, int, int] \mid tuple[int, int, int, float] = ")$

Change the font used by this widget. If font is None, the current font is used.

15.6.47 Notify

class libqtile.widget.notify.Notify

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["notify"].<command>()
qtile cmd-obj -o widget notify -f <command>

clear([reason])	Clear the notification
commands()	Returns a list of possible commands for this object
display()	
doc(name)	Returns the documentation for a specified command name
eval(code)	Evaluates code in the same context as this function
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Info for this object.
invoke()	Invoke the notification's default action
<pre>items(name)</pre>	Build a list of contained items for the given item class.
next()	
prev()	Show previous notification.
<pre>set_font([font, fontsize, fontshadow])</pre>	Change the font used by this widget.
toggle()	Toggle showing/clearing the notification

clear(reason=2)

Clear the notification

$commands() \rightarrow list[str]$

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

display()

$doc(name) \rightarrow str$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (success, result), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info()

Info for this object.

invoke()

Invoke the notification's default action

items(name: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

next()

prev()

Show previous notification.

set_font(font: str | None = None, fontsize: int = 0, fontshadow: str | tuple[int, int, int] | tuple[int, int, int, float] = ")

Change the font used by this widget. If font is None, the current font is used.

toggle()

Toggle showing/clearing the notification

15.6.48 NvidiaSensors

class libqtile.widget.nvidia_sensors.NvidiaSensors

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["nvidiasensors"].<command>()
qtile cmd-obj -o widget nvidiasensors -f <command>

The following commands are available for this object:

commanda()	Daturns a list of possible commands for this object
commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>force_update()</pre>	Immediately poll the widget.
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Info for this object.
<pre>items(name)</pre>	Build a list of contained items for the given item class.
<pre>set_font([font, fontsize, fontshadow])</pre>	Change the font used by this widget.

Command documentation

commands() \rightarrow list[str]

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

 $doc(name) \rightarrow str$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (success, result), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

force_update()

Immediately poll the widget. Existing timers are unaffected.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info()

Info for this object.

items (*name*: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

 $set_font(font: str \mid None = None, fontsize: int = 0, fontshadow: str \mid tuple[int, int, int] \mid tuple[int, int, int, float] = ")$

Change the font used by this widget. If font is None, the current font is used.

15.6.49 OpenWeather

class libqtile.widget.open_weather.OpenWeather

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["openweather"].<command>()
qtile cmd-obj -o widget openweather -f <command>

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>force_update()</pre>	Immediately poll the widget.
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Info for this object.
<pre>items(name)</pre>	Build a list of contained items for the given item class.
<pre>set_font([font, fontsize, fontshadow])</pre>	Change the font used by this widget.

Command documentation

```
commands() \rightarrow list[str]
```

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

```
doc(name) \rightarrow str
```

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

```
eval(code: str) \rightarrow tuple[bool, str | None]
```

Evaluates code in the same context as this function

Return value is tuple (*success*, *result*), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

force_update()

Immediately poll the widget. Existing timers are unaffected.

```
function(function, *args, **kwargs) \rightarrow Task | None
```

Call a function with current object as argument

info()

Info for this object.

```
items (name: str) \rightarrow tuple[bool, list[str | int] | None]
```

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

set_font(font: str | None = None, fontsize: int = 0, fontshadow: str | tuple[int, int, int] | tuple[int, int, int, int, float] = ")

Change the font used by this widget. If font is None, the current font is used.

15.6.50 Plasma

class libqtile.widget.plasma.Plasma

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["plasma"].<command>()
qtile cmd-obj -o widget plasma -f <command>

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Info for this object.
<pre>items(name)</pre>	Build a list of contained items for the given item class.
next_mode()	Change the add mode for the Plasma layout.
<pre>set_font([font, fontsize, fontshadow])</pre>	Change the font used by this widget.

Command documentation

commands() \rightarrow list[str]

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

$doc(name) \rightarrow str$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (success, result), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info()

Info for this object.

items(name: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

next_mode()

Change the add mode for the Plasma layout.

 $set_font(font: str \mid None = None, fontsize: int = 0, fontshadow: str \mid tuple[int, int, int] \mid tuple[int, int, int, float] = ")$

Change the font used by this widget. If font is None, the current font is used.

15.6.51 **Pomodoro**

class libqtile.widget.pomodoro.Pomodoro

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["pomodoro"].<command>()
qtile cmd-obj -o widget pomodoro -f <command>

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>force_update()</pre>	Immediately poll the widget.
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Info for this object.
<pre>items(name)</pre>	Build a list of contained items for the given item class.
<pre>set_font([font, fontsize, fontshadow])</pre>	Change the font used by this widget.
toggle_active()	
toggle_break()	

Command documentation

$commands() \rightarrow list[str]$

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

$\mathbf{doc}(\mathit{name}) \to \mathrm{str}$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (success, result), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

force_update()

Immediately poll the widget. Existing timers are unaffected.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info()

Info for this object.

items(name: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

 $set_font(font: str \mid None = None, fontsize: int = 0, fontshadow: str \mid tuple[int, int, int] \mid tuple[int, int, int, float] = ")$

Change the font used by this widget. If font is None, the current font is used.

toggle_active()

toggle_break()

15.6.52 Prompt

class libqtile.widget.prompt.Prompt

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["prompt"].<command>()
qtile cmd-obj -o widget prompt -f <command>

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>exec_general(prompt, object_name, cmd_name)</pre>	Execute a cmd of any object.
<pre>fake_keypress(key)</pre>	
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Returns a dictionary of info for this object
<pre>items(name)</pre>	Build a list of contained items for the given item class.
<pre>set_font([font, fontsize, fontshadow])</pre>	Change the font used by this widget.

Command documentation

commands() \rightarrow list[str]

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

 $\mathbf{doc}(\mathit{name}) \to \mathit{str}$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

```
eval(code: str) \rightarrow tuple[bool, str | None]
```

Evaluates code in the same context as this function

Return value is tuple (*success*, *result*), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

```
exec_general(prompt, object_name, cmd_name, selector=None, completer=None)
```

Execute a cmd of any object. For example layout, group, window, widget, etc with a string that is obtained from start_input.

Parameters

prompt

Text displayed at the prompt.

object name

Name of a object in Qtile. This string has to be 'layout', 'widget', 'bar', 'window' or 'screen'.

cmd name

Execution command of selected object using object_name and selector.

selector

This value select a specific object within a object list that is obtained by object_name. If this value is None, current object is selected. e.g. current layout, current window and current screen.

completer:

Completer to use.

config example:

```
Key([alt, 'shift'], 'a',
```

lazy.widget['prompt'].exec_general(

'section(add)', 'layout', 'add_section'))

```
fake_keypress(key: str) \rightarrow None
```

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info()

Returns a dictionary of info for this object

```
items(name: str) \rightarrow tuple[bool, list[str | int] | None]
```

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

```
set\_font(font: str \mid None = None, fontsize: int = 0, fontshadow: str \mid tuple[int, int, int] \mid tuple[int, int, int, float] = ")
```

Change the font used by this widget. If font is None, the current font is used.

15.6.53 PulseVolume

class libqtile.widget.pulse_volume.PulseVolume

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["pulsevolume"].<command>()
qtile cmd-obj -o widget pulsevolume -f <command>

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
<pre>decrease_vol([value])</pre>	Decrease volume.
doc(name)	Returns the documentation for a specified command name
eval(code)	Evaluates code in the same context as this function
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
<pre>increase_vol([value])</pre>	Increase volume.
info()	Info for this object.
<pre>items(name)</pre>	Build a list of contained items for the given item class.
<pre>mute()</pre>	Mute the sound device.
run_app()	
<pre>set_font([font, fontsize, fontshadow])</pre>	Change the font used by this widget.

Command documentation

commands() \rightarrow list[str]

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

decrease_vol(value=None)

Decrease volume.

$doc(name) \rightarrow str$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (*success*, *result*), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

increase_vol(value=None)

Increase volume.

info()

Info for this object.

```
items(name: str) \rightarrow tuple[bool, list[str | int] | None]
```

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

mute()

Mute the sound device.

run_app()

```
set\_font(font: str \mid None = None, fontsize: int = 0, fontshadow: str \mid tuple[int, int, int] \mid tuple[int, int, int, float] = ")
```

Change the font used by this widget. If font is None, the current font is used.

15.6.54 QuickExit

class libqtile.widget.quick_exit.QuickExit

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["quickexit"]. <command/> ()	
qtile cmd-obj -o widget quickexit -f <command/>	

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Info for this object.
<pre>items(name)</pre>	Build a list of contained items for the given item class.
<pre>set_font([font, fontsize, fontshadow])</pre>	Change the font used by this widget.
trigger()	

Command documentation

commands() \rightarrow list[str]

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

 $doc(name) \rightarrow str$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

```
eval(code: str) \rightarrow tuple[bool, str | None]
```

Evaluates code in the same context as this function

Return value is tuple (*success*, *result*), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info()

Info for this object.

items(name: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

set_font(font: str | None = None, fontsize: int = 0, fontshadow: str | tuple[int, int, int] | tuple[int, int, int, int, float] = ")

Change the font used by this widget. If font is None, the current font is used.

trigger()

15.6.55 Redshift

class libgtile.widget.redshift.Redshift

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["redshift"].<command>()
qtile cmd-obj -o widget redshift -f <command>

The following commands are available for this object:

click()	Has no action for the gamma line.
commands()	Returns a list of possible commands for this object
<pre>decrease_brightness()</pre>	Decrease brightness by a single step.
<pre>decrease_temperature()</pre>	Decrease redshift temperature by a single step.
doc(name)	Returns the documentation for a specified command name
eval(code)	Evaluates code in the same context as this function
function(function, *args, **kwargs)	Call a function with current object as argument
<pre>increase_brightness()</pre>	Increase brightness by a single step.
<pre>increase_temperature()</pre>	Increase redshift temperature by a single step.
info()	Info for this object.
<pre>items(name)</pre>	Build a list of contained items for the given item class.
reset_redshift()	Call reset on redshift to reset to default settings.
right_click()	Has no action for the first line of the widget nor the gamma line.
<pre>run_redshift()</pre>	Run redshift command with defined parameters.
scroll_down()	Scroll down to next item.
scroll_up()	Scroll up to next item.
<pre>set_font([font, fontsize, fontshadow])</pre>	Change the font used by this widget.

Command documentation

click()

Has no action for the gamma line. Either enable or disable the widget if we are currently on the first line. Else decrease brightness/temperature accordingly

$commands() \rightarrow list[str]$

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

decrease_brightness()

Decrease brightness by a single step.

decrease_temperature()

Decrease redshift temperature by a single step.

$\mathbf{doc}(\mathit{name}) \to \mathsf{str}$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (success, result), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

increase_brightness()

Increase brightness by a single step.

increase_temperature()

Increase redshift temperature by a single step.

info()

Info for this object.

items(name: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

reset_redshift()

Call reset on redshift to reset to default settings.

right_click()

Has no action for the first line of the widget nor the gamma line. Increase brightness/temperature accordingly.

run_redshift()

Run redshift command with defined parameters.

scroll_down()

Scroll down to next item.

scroll_up()

Scroll up to next item.

```
set\_font(font: str \mid None = None, fontsize: int = 0, fontshadow: str \mid tuple[int, int, int] \mid tuple[int, int, int, int, float] = ")
```

Change the font used by this widget. If font is None, the current font is used.

15.6.56 ScreenSplit

class libqtile.widget.screensplit.ScreenSplit

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["screensplit"].<command>()
qtile cmd-obj -o widget screensplit -f <command>

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
get()	Retrieve the text in a TextBox widget
info()	Info for this object.
<pre>items(name)</pre>	Build a list of contained items for the given item class.
<pre>set_font([font, fontsize, fontshadow])</pre>	Change the font used by this widget.
update(text)	Update the widget text.

Command documentation

$commands() \rightarrow list[str]$

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

$doc(name) \rightarrow str$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (*success*, *result*), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

get()

Retrieve the text in a TextBox widget

info()

Info for this object.

items (name: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

 $set_font(font: str \mid None = None, fontsize: int = 0, fontshadow: str \mid tuple[int, int, int] \mid tuple[int, int, int, float] = ")$

Change the font used by this widget. If font is None, the current font is used.

update(text)

Update the widget text.

15.6.57 Sep

class libqtile.widget.sep.Sep

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["sep"].<command>()
qtile cmd-obj -o widget sep -f <command>

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Info for this object.
<pre>items(name)</pre>	Build a list of contained items for the given item class.

Command documentation

commands() \rightarrow list[str]

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

 $\mathbf{doc}(\mathit{name}) \to \mathit{str}$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (success, result), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info()

Info for this object.

items(name: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

15.6.58 She

class libqtile.widget.she.She

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["she"].<command>()
qtile cmd-obj -o widget she -f <command>

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Info for this object.
<pre>items(name)</pre>	Build a list of contained items for the given item class.
<pre>set_font([font, fontsize, fontshadow])</pre>	Change the font used by this widget.

Command documentation

commands() \rightarrow list[str]

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

 $doc(name) \rightarrow str$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (success, result), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info()

Info for this object.

items (name: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

set_font(font: str | None = None, fontsize: int = 0, fontshadow: str | tuple[int, int, int] | tuple[int, int, int, int, float] = ")

Change the font used by this widget. If font is None, the current font is used.

15.6.59 Spacer

class libgtile.widget.spacer.Spacer

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["spacer"]. <command/> ()	
qtile cmd-obj -o widget spacer -f <command/>	

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
function(function, *args, **kwargs)	Call a function with current object as argument
info()	Info for this object.
<pre>items(name)</pre>	Build a list of contained items for the given item class.

Command documentation

commands() \rightarrow list[str]

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

$$doc(name) \rightarrow str$$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (success, result), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info()

Info for this object.

items(name: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

15.6.60 StatusNotifier

class libgtile.widget.statusnotifier.StatusNotifier

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["statusnotifier"].<command>()
qtile cmd-obj -o widget statusnotifier -f <command>

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Info for this object.
<pre>items(name)</pre>	Build a list of contained items for the given item class.

Command documentation

$commands() \rightarrow list[str]$

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

 $doc(name) \rightarrow str$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (success, result), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info()

Info for this object.

items(name: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

15.6.61 StockTicker

class libqtile.widget.stock_ticker.StockTicker

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["stockticker"].<command>()
qtile cmd-obj -o widget stockticker -f <command>

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>force_update()</pre>	Immediately poll the widget.
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Info for this object.
items(name)	Build a list of contained items for the given item class.
<pre>set_font([font, fontsize, fontshadow])</pre>	Change the font used by this widget.

Command documentation

$commands() \rightarrow list[str]$

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

 $\mathbf{doc}(\mathit{name}) \to \mathit{str}$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (success, result), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

force_update()

Immediately poll the widget. Existing timers are unaffected.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info()

Info for this object.

items(name: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

 $set_font(font: str \mid None = None, fontsize: int = 0, fontshadow: str \mid tuple[int, int, int] \mid tuple[int, int, int, float] = ")$

Change the font used by this widget. If font is None, the current font is used.

15.6.62 SwapGraph

class libqtile.widget.graph.SwapGraph

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["swapgraph"].<command>()
qtile cmd-obj -o widget swapgraph -f <command>

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Info for this object.
<pre>items(name)</pre>	Build a list of contained items for the given item class.

Command documentation

commands() \rightarrow list[str]

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

 $doc(name) \rightarrow str$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (*success*, *result*), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info()

Info for this object.

items (*name*: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

15.6.63 SwayNC

class libqtile.widget.swaync.SwayNC

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["swaync"].<command>()
qtile cmd-obj -o widget swaync -f <command>

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Info for this object.
items(name)	Build a list of contained items for the given item class.
<pre>set_font([font, fontsize, fontshadow])</pre>	Change the font used by this widget.
<pre>toggle_dnd()</pre>	Toggle do not disturb status.
toggle_panel()	Show swaync client panel.

Command documentation

 $commands() \rightarrow list[str]$

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

 $doc(name) \rightarrow str$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

```
eval(code: str) \rightarrow tuple[bool, str | None]
```

Evaluates code in the same context as this function

Return value is tuple (*success*, *result*), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

```
function(function, *args, **kwargs) \rightarrow Task | None
```

Call a function with current object as argument

info()

Info for this object.

items(name: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

set_font(font: str | None = None, fontsize: int = 0, fontshadow: str | tuple[int, int, int] | tuple[int, int, int, int, float] = ")

Change the font used by this widget. If font is None, the current font is used.

toggle_dnd()

Toggle do not disturb status.

toggle_panel()

Show swaync client panel.

15.6.64 Systray

class libqtile.widget.systray.Systray

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["systray"].<command>()
qtile cmd-obj -o widget systray -f <command>

The following commands are available for this object:

_window_mask	
<pre>bring_to_front()</pre>	
commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command name
eval(code)	Evaluates code in the same context as this function
focus([warp])	Focuses the window.
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
<pre>get_hints()</pre>	Returns the X11 hints (WM_HINTS and WM_SIZE_HINTS) for this window.
inspect()	Tells you more than you ever wanted to know about a window
items(name)	Build a list of contained items for the given item class.
keep_above([enable])	
<pre>keep_below([enable])</pre>	
kill()	
<pre>move_down([force])</pre>	
<pre>move_to_bottom([force])</pre>	
<pre>move_to_top([force])</pre>	
<pre>move_up([force])</pre>	
place(x, y, width, height, borderwidth,)	Places the window at the specified location with the given size.

Command documentation

```
_window_mask(**kwargs)
```

 $int([x]) \rightarrow integer int(x, base=10) \rightarrow integer$

Convert a number or string to an integer, or return 0 if no arguments are given. If x is a number, return x.__int__(). For floating-point numbers, this truncates towards zero.

If x is not a number or if base is given, then x must be a string, bytes, or bytearray instance representing an integer literal in the given base. The literal can be preceded by '+' or '-' and be surrounded by whitespace. The base defaults to 10. Valid bases are 0 and 2-36. Base 0 means to interpret the base from the string as an integer literal. >>> int('0b100', base=0) 4

bring_to_front()

$commands() \rightarrow list[str]$

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

$doc(name) \rightarrow str$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

```
eval(code: str) \rightarrow tuple[bool, str | None]
      Evaluates code in the same context as this function
      Return value is tuple (success, result), success being a boolean and result being a string representing the
      return value of eval, or None if exec was used instead.
focus(warp: bool = True) \rightarrow None
      Focuses the window.
function(function, *args, **kwargs) \rightarrow Task | None
      Call a function with current object as argument
get_hints()
      Returns the X11 hints (WM_HINTS and WM_SIZE_HINTS) for this window.
inspect()
      Tells you more than you ever wanted to know about a window
items(name: str) \rightarrow tuple[bool, list[str | int] | None]
      Build a list of contained items for the given item class.
      Exposing this allows __qsh__ to navigate the command graph.
      Returns a tuple (root, items) for the specified item class, where:
           root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout"
           defaults to current layout), and False if it does not (e.g. no default "widget").
           items: a list of contained items
keep_above(enable: bool | None = None)
keep_below(enable: bool | None = None)
kill()
move_down(force=False)
move_to_bottom(force=False)
move_to_top(force=False)
move_up(force=False)
place(x, y, width, height, borderwidth, bordercolor, above=False, margin=None, respect hints=False)
      Places the window at the specified location with the given size.
           Parameters
                x: int
                y: int
                width: int
                height: int
                borderwidth: int
                bordercolor: string
                above: bool, optional
                margin: int or list, optional
                    space around window as int or list of ints [N E S W]
                above: bool, optional
                    If True, the geometry will be adjusted to respect hints provided by the client.
```

15.6.65 TaskList

class libqtile.widget.tasklist.TaskList

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["tasklist"].<command>()
qtile cmd-obj -o widget tasklist -f <command>

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Info for this object.
<pre>items(name)</pre>	Build a list of contained items for the given item class.

Command documentation

commands() \rightarrow list[str]

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

 $\mathbf{doc}(\mathit{name}) \to \mathit{str}$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (success, result), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info()

Info for this object.

items(name: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

15.6.66 TextBox

class libqtile.widget.textbox.TextBox

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["textbox"].<command>()
qtile cmd-obj -o widget textbox -f <command>

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
get()	Retrieve the text in a TextBox widget
info()	Info for this object.
<pre>items(name)</pre>	Build a list of contained items for the given item class.
<pre>set_font([font, fontsize, fontshadow])</pre>	Change the font used by this widget.
update(text)	Update the widget text.

Command documentation

commands() \rightarrow list[str]

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

$doc(name) \rightarrow str$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (*success*, *result*), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

get()

Retrieve the text in a TextBox widget

info()

Info for this object.

items(name: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

set_font(font: str | None = None, fontsize: int = 0, fontshadow: str | tuple[int, int, int] | tuple[int, int, int, int, float] = ")

Change the font used by this widget. If font is None, the current font is used.

update(text)

Update the widget text.

15.6.67 ThermalSensor

class libqtile.widget.sensors.ThermalSensor

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["thermalsensor"].<command>()
qtile cmd-obj -o widget thermalsensor -f <command>

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>force_update()</pre>	Immediately poll the widget.
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Info for this object.
<pre>items(name)</pre>	Build a list of contained items for the given item class.
<pre>set_font([font, fontsize, fontshadow])</pre>	Change the font used by this widget.

Command documentation

commands() \rightarrow list[str]

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

 $doc(name) \rightarrow str$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (*success*, *result*), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

force_update()

Immediately poll the widget. Existing timers are unaffected.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info()

Info for this object.

items (name: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

set_font(font: str | None = None, fontsize: int = 0, fontshadow: str | tuple[int, int, int] | tuple[int, int, int, float] = ")

Change the font used by this widget. If font is None, the current font is used.

15.6.68 ThermalZone

class libqtile.widget.thermal_zone.ThermalZone

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["thermalzone"].<command>()
qtile cmd-obj -o widget thermalzone -f <command>

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>force_update()</pre>	Immediately poll the widget.
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Info for this object.
<pre>items(name)</pre>	Build a list of contained items for the given item class.
<pre>set_font([font, fontsize, fontshadow])</pre>	Change the font used by this widget.

Command documentation

commands() \rightarrow list[str]

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

 $\mathbf{doc}(\mathit{name}) \to \mathit{str}$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (*success*, *result*), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

force_update()

Immediately poll the widget. Existing timers are unaffected.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info()

Info for this object.

items (*name*: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

 $set_font(font: str \mid None = None, fontsize: int = 0, fontshadow: str \mid tuple[int, int, int] \mid tuple[int, int, int, float] = ")$

Change the font used by this widget. If font is None, the current font is used.

15.6.69 TunedManager

class libqtile.widget.tuned_manager.TunedManager

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["tunedmanager"].<command>()
qtile cmd-obj -o widget tunedmanager -f <command>

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>force_update()</pre>	Immediately poll the widget.
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Info for this object.
<pre>items(name)</pre>	Build a list of contained items for the given item class.
<pre>set_font([font, fontsize, fontshadow])</pre>	Change the font used by this widget.

Command documentation

```
commands() \rightarrow list[str]
```

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

```
doc(name) \rightarrow str
```

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

```
eval(code: str) \rightarrow tuple[bool, str | None]
```

Evaluates code in the same context as this function

Return value is tuple (*success*, *result*), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

force_update()

Immediately poll the widget. Existing timers are unaffected.

```
function(function, *args, **kwargs) \rightarrow Task | None
```

Call a function with current object as argument

info()

Info for this object.

```
items (name: str) \rightarrow tuple[bool, list[str | int] | None]
```

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

 $set_font(font: str \mid None = None, fontsize: int = 0, fontshadow: str \mid tuple[int, int, int] \mid tuple[int, int, int, float] = ")$

Change the font used by this widget. If font is None, the current font is used.

15.6.70 VerticalClock

class libgtile.widget.vertical_clock.VerticalClock

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["verticalclock"].<command>()
qtile cmd-obj -o widget verticalclock -f <command>

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Info for this object.
<pre>items(name)</pre>	Build a list of contained items for the given item class.
<pre>set_font([font, fontsize, fontshadow])</pre>	Change the font used by this widget.
<pre>update_timezone([timezone])</pre>	Force the clock to update timezone information.
<pre>use_system_timezone()</pre>	Force clock to use system timezone.

Command documentation

$commands() \rightarrow list[str]$

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

$doc(name) \rightarrow str$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (*success*, *result*), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info()

Info for this object.

items (name: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

set_font(font: str | None = None, fontsize: int = 0, fontshadow: str | tuple[int, int, int] | tuple[int, int, int, int, float] = ")

Change the font used by this widget. If font is None, the current font is used.

update_timezone(timezone: str | tzinfo | None = None)

Force the clock to update timezone information.

If the method is called with no arguments then the widget will reload the timzeone set on the computer (e.g. via timedatectl set-timezone ..). This will have no effect if you have previously set a timezone value.

Alternatively, you can pass a timezone string (e.g. "Europe/Lisbon") to change the specified timezone. Setting this to an empty string will cause the clock to rely on the system timezone.

use_system_timezone()

Force clock to use system timezone.

15.6.71 Volume

class libqtile.widget.volume.Volume

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["volume"].<command>()
qtile cmd-obj -o widget volume -f <command>

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
decrease_vol()	·
doc(name)	Returns the documentation for a specified command name
eval(code)	Evaluates code in the same context as this function
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
<pre>increase_vol()</pre>	
info()	Info for this object.
<pre>items(name)</pre>	Build a list of contained items for the given item class.
<pre>mute()</pre>	
run_app()	
<pre>set_font([font, fontsize, fontshadow])</pre>	Change the font used by this widget.

Command documentation

$commands() \rightarrow list[str]$

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

decrease_vol()

$\mathbf{doc}(name) \rightarrow \mathbf{str}$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (*success*, *result*), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

```
function(function, *args, **kwargs) \rightarrow Task | None
      Call a function with current object as argument
increase_vol()
info()
      Info for this object.
items (name: str) \rightarrow tuple[bool, list[str | int] | None]
      Build a list of contained items for the given item class.
      Exposing this allows __qsh__ to navigate the command graph.
      Returns a tuple (root, items) for the specified item class, where:
            root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout"
            defaults to current layout), and False if it does not (e.g. no default "widget").
            items: a list of contained items
mute()
run_app()
set\_font(font: str \mid None = None, fontsize: int = 0, fontshadow: str \mid tuple[int, int, int] \mid tuple[int, int, int, int]
            float l = "
```

15.6.72 Wallpaper

class libqtile.widget.wallpaper.Wallpaper

API commands

To access commands on this object via the command graph, use one of the following options:

Change the font used by this widget. If font is None, the current font is used.

lazy.widget["wallpaper"].<command>()
qtile cmd-obj -o widget wallpaper -f <command>

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Info for this object.
items(name)	Build a list of contained items for the given item class.
<pre>set_font([font, fontsize, fontshadow])</pre>	Change the font used by this widget.

Command documentation

```
commands() \rightarrow list[str]
```

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

 $doc(name) \rightarrow str$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (success, result), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info()

Info for this object.

items(name: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

set_font(font: str | None = None, fontsize: int = 0, fontshadow: str | tuple[int, int, int] | tuple[int, int, int, int, float] = ")

Change the font used by this widget. If font is None, the current font is used.

15.6.73 WidgetBox

class libqtile.widget.widgetbox.WidgetBox

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["widgetbox"].<command>()
qtile cmd-obj -o widget widgetbox -f <command>

The following commands are available for this object:

close()	Close the widgetbox.
commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command name
eval(code)	Evaluates code in the same context as this function
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Info for this object.
<pre>items(name)</pre>	Build a list of contained items for the given item class.
open()	Open the widgetbox.
<pre>set_font([font, fontsize, fontshadow])</pre>	Change the font used by this widget.
toggle()	Toggle box state

Command documentation

close()

Close the widgetbox.

$commands() \rightarrow list[str]$

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

$doc(name) \rightarrow str$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (*success*, *result*), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info()

Info for this object.

items(name: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

open()

Open the widgetbox.

```
set\_font(font: str \mid None = None, fontsize: int = 0, fontshadow: str \mid tuple[int, int, int] \mid tuple[int, int, int, float] = ")
```

Change the font used by this widget. If font is None, the current font is used.

toggle()

Toggle box state

15.6.74 WindowCount

class libqtile.widget.window_count.WindowCount

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["windowcount"].<command>()
qtile cmd-obj -o widget windowcount -f <command>

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
get()	Retrieve the current text.
info()	Info for this object.
<pre>items(name)</pre>	Build a list of contained items for the given item class.
<pre>set_font([font, fontsize, fontshadow])</pre>	Change the font used by this widget.

Command documentation

$commands() \rightarrow list[str]$

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

 $doc(name) \rightarrow str$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (*success*, *result*), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

get()

Retrieve the current text.

info()

Info for this object.

items (*name*: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

 $set_font(font: str \mid None = None, fontsize: int = 0, fontshadow: str \mid tuple[int, int, int] \mid tuple[int, int, int, float] = ")$

Change the font used by this widget. If font is None, the current font is used.

15.6.75 WindowName

class libqtile.widget.windowname.WindowName

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["windowname"].<command>()
qtile cmd-obj -o widget windowname -f <command>

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Info for this object.
<pre>items(name)</pre>	Build a list of contained items for the given item class.
<pre>set_font([font, fontsize, fontshadow])</pre>	Change the font used by this widget.

Command documentation

 $commands() \rightarrow list[str]$

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

 $\mathbf{doc}(\mathit{name}) \to \mathrm{str}$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (success, result), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info()

Info for this object.

items (name: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

set_font(font: str | None = None, fontsize: int = 0, fontshadow: str | tuple[int, int, int] | tuple[int, int, int, float] = ")

Change the font used by this widget. If font is None, the current font is used.

15.6.76 WindowTabs

class libgtile.widget.windowtabs.WindowTabs

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["windowtabs"].<command>()
qtile cmd-obj -o widget windowtabs -f <command>

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Info for this object.
<pre>items(name)</pre>	Build a list of contained items for the given item class.
<pre>set_font([font, fontsize, fontshadow])</pre>	Change the font used by this widget.

Command documentation

commands() \rightarrow list[str]

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

 $doc(name) \rightarrow str$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (*success*, *result*), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info()

Info for this object.

items(name: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

set_font(font: str | None = None, fontsize: int = 0, fontshadow: str | tuple[int, int, int] | tuple[int, int, int, int, float] = ")

Change the font used by this widget. If font is None, the current font is used.

15.6.77 Wlan

class libqtile.widget.wlan.Wlan

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["wlan"].<command>()
qtile cmd-obj -o widget wlan -f <command>

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Info for this object.
<pre>items(name)</pre>	Build a list of contained items for the given item class.
<pre>set_font([font, fontsize, fontshadow])</pre>	Change the font used by this widget.

Command documentation

commands() \rightarrow list[str]

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

 $doc(name) \rightarrow str$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

 $\textbf{eval}(\textit{code: str}) \rightarrow \text{tuple[bool, str \mid None]}$

Evaluates code in the same context as this function

Return value is tuple (success, result), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info()

Info for this object.

items(name: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

set_font(font: str | None = None, fontsize: int = 0, fontshadow: str | tuple[int, int, int] | tuple[int, int, int, int, float] = ")

Change the font used by this widget. If font is None, the current font is used.

15.6.78 Wttr

class libqtile.widget.wttr.Wttr

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.widget["wttr"].<command>()
qtile cmd-obj -o widget wttr -f <command>

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>force_update()</pre>	Immediately poll the widget.
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Info for this object.
<pre>items(name)</pre>	Build a list of contained items for the given item class.
<pre>set_font([font, fontsize, fontshadow])</pre>	Change the font used by this widget.

Command documentation

 $\textbf{commands()} \rightarrow list[str]$

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

 $doc(name) \rightarrow str$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (*success*, *result*), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

force_update()

Immediately poll the widget. Existing timers are unaffected.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info()

Info for this object.

items(name: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items


set_font(font: str | None = None, fontsize: int = 0, fontshadow: str | tuple[int, int, int] | tuple[int, int, int, int, float] = ")

Change the font used by this widget. If font is None, the current font is used.

15.7 Screen objects

Screens are the display area that holds bars and an active group. Screen commands include changing the current group and changing the wallpaper.

Screens can access objects displayed on that screen e.g. bar, widgets, groups, layouts and windows.



class libqtile.config.Screen

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.screen.<command>() qtile cmd-obj -o screen -f <command>

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Returns a dictionary of info for this screen.
<pre>items(name)</pre>	Build a list of contained items for the given item class.
<pre>next_group([skip_empty, skip_managed, warp])</pre>	Switch to the next group
<pre>prev_group([skip_empty, skip_managed, warp])</pre>	Switch to the previous group
resize([x, y, w, h])	
<pre>set_wallpaper(path[, mode])</pre>	Set the wallpaper to the given file.
toggle_group([group_name, warp])	Switch to the selected group or to the previously ac-
	tive one

Command documentation

commands() \rightarrow list[str]

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

 $doc(name) \rightarrow str$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (success, result), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info() \rightarrow dict[str, int]

Returns a dictionary of info for this screen.

items(name: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

next_group($skip_empty: bool = False, skip_managed: bool = False, warp: bool = True) <math>\rightarrow$ None Switch to the next group

prev_group($skip_empty: bool = False, skip_managed: bool = False, warp: bool = True) <math>\rightarrow$ None Switch to the previous group

 $resize(x: int \mid None = None, y: int \mid None = None, w: int \mid None = None, h: int \mid None = None) \rightarrow None$

set_wallpaper($path: str, mode: str \mid None = None) \rightarrow None$ Set the wallpaper to the given file. **toggle_group**($group_name: str \mid None = None, warp: bool = True) \rightarrow None$


Switch to the selected group or to the previously active one

15.8 Backend core objects

The backend core is the link between the Qtile objects (windows, layouts, groups etc.) and the specific backend (X11 or Wayland). This core should be largely invisible to users and, as a result, these objects do not expose many commands.

Nevertheless, both backends do contain important commands, notably set_keymap on X11 and change_vt used to change to a different TTY on Wayland.

The backend core has no access to other nodes on the command graph.



15.8.1 X11 backend

class libqtile.backend.x11.core.Core

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.core.<command>()
qtile cmd-obj -o core -f <command>

The following commands are available for this object:

commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
info()	Get basic information about the running backend.
<pre>items(name)</pre>	Build a list of contained items for the given item class.

Command documentation

commands() \rightarrow list[str]

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

 $\mathbf{doc}(\mathit{name}) \to \mathit{str}$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (success, result), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

info() \rightarrow dict[str, Any]

Get basic information about the running backend.

items(name: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

15.8.2 Wayland backend

class libqtile.backend.wayland.core.Core

API commands

To access commands on this object via the command graph, use one of the following options:

lazy.core.<command>()
qtile cmd-obj -o core -f <command>

The following commands are available for this object:

change_vt(vt)	Change virtual terminal to that specified
commands()	Returns a list of possible commands for this object
doc(name)	Returns the documentation for a specified command
	name
eval(code)	Evaluates code in the same context as this function
<pre>function(function, *args, **kwargs)</pre>	Call a function with current object as argument
<pre>get_inputs()</pre>	Get information on all input devices.
hide_cursor()	Hide the cursor.
info()	Get basic information about the running backend.
<pre>items(name)</pre>	Build a list of contained items for the given item class.
<pre>query_tree()</pre>	Get IDs of all mapped windows in ascending Z order.
<pre>set_keymap([layout, options, variant])</pre>	Set the keymap for the current keyboard.
unhide_cursor()	Unhide the cursor.

Command documentation

change_vt(vt: int) \rightarrow bool

Change virtual terminal to that specified

 $commands() \rightarrow list[str]$

Returns a list of possible commands for this object

Used by __qsh__ for command completion and online help

 $doc(name) \rightarrow str$

Returns the documentation for a specified command name

Used by __qsh__ to provide online help.

eval(code: str) \rightarrow tuple[bool, str | None]

Evaluates code in the same context as this function

Return value is tuple (success, result), success being a boolean and result being a string representing the return value of eval, or None if exec was used instead.

function(function, *args, **kwargs) \rightarrow Task | None

Call a function with current object as argument

 $get_inputs() \rightarrow dict[str, list[dict[str, str]]]$

Get information on all input devices.

 $hide_cursor() \rightarrow None$

Hide the cursor.

$info() \rightarrow dict[str, Any]$

Get basic information about the running backend.

items (*name*: str) \rightarrow tuple[bool, list[str | int] | None]

Build a list of contained items for the given item class.

Exposing this allows __qsh__ to navigate the command graph.

Returns a tuple (root, items) for the specified item class, where:

root: True if this class accepts a "naked" specification without an item seletion (e.g. "layout" defaults to current layout), and False if it does not (e.g. no default "widget").

items: a list of contained items

$query_tree() \rightarrow list[int]$

Get IDs of all mapped windows in ascending Z order.

set_keymap (layout: $str \mid None = None$, options: $str \mid None = None$, variant: $str \mid None = None$) \rightarrow None Set the keymap for the current keyboard.

The options correspond to xkbcommon configuration environmental variables and if not specified are taken from the environment. Acceptable values are strings identical to those accepted by the env variables.

$unhide_cursor() \rightarrow None$

Unhide the cursor.

CHAPTER

SIXTEEN

HACKING ON QTILE

16.1 Requirements

Here are Qtile's additional dependencies that may be required for tests:

Dependency	Ubuntu Package	Needed for
pytest	python3-pytest	Running tests
pre-commit	pre-commit	Running linters
PyGObject	python3-gi	Running tests (test windows)
Xephyr	xserver-xephyr	Testing with X11 backend (optional, see below)
mypy	python3-mypy	Testing qtile check (optional)
imagemagick>=6.8	imagemagick	test/test_images* (optional)
gtk-layer-shell	libgtk-layer-shell0	Testing notification windows in Wayland (optional)
dbus-launch	dbus-x11	Testing dbus-using widgets (optional)
notifiy-send	libnotify-bin	Testing Notify widget (optional)
xvfb	xvfb	Testing with X11 headless (optional)

16.1.1 Backends

The test suite can be run using the X11 or Wayland backend, or both. By default, only the X11 backend is used for tests. To test a single backend or both backends, specify as arguments to pytest:

```
pytest --backend wayland # Test just Wayland backend
pytest --backend x11 --backend wayland # Test both
```

Testing with the X11 backend requires Xephyr (and xvfb for headless mode) in addition to the core dependencies.

16.2 Building cffi module

Qtile ships with a small in-tree pangocairo binding built using cffi, pangocffi.py, and also binds to xcursor with cffi. The bindings are not built at run time and will have to be generated manually when the code is downloaded or when any changes are made to the cffi library. This can be done by calling:

```
./scripts/ffibuild
```

16.3 Setting up the environment

In the root of the project, run ./dev.sh. It will create a virtualenv called venv.

Activate this virtualenv with . venv/bin/activate. Deactivate it with the deactivate command.

16.4 Building the documentation

To build the documentation, you will also need to install graphviz.

Go into the docs/ directory and run pip install -r requirements.txt.

Build the documentation with make html.

Check the result by opening _build/html/index.html in your browser.

Note: To speed up local testing, screenshots are not generated each time the documentation is built.

You can enable screenshots by setting the QTILE_BUILD_SCREENSHOTS environmental variable at build time e.g. QTILE_BUILD_SCREENSHOTS=1 make html. You can also export the variable so it will apply to all local builds export QTILE_BUILD_SCREENSHOTS=1 (but remember to unset it if you want to skip building screenshots).

16.5 Development and testing

In practice, the development cycle looks something like this:

- 1. make minor code change
- 2. run appropriate test: pytest tests/test_module.py or pytest -k PATTERN
- 3. GOTO 1, until hackage is complete
- 4. run entire test suite to make sure you didn't break anything else: pytest
- 5. try to commit, get changes and feedback from the pre-commit hooks
- 6. GOTO 5, until your changes actually get committed

Tests and pre-commit hooks will be run by our CI on every pull request as well so you can see whether or not your contribution passes.

16.6 Coding style

While not all of our code follows PEP8, we do try to adhere to it where possible. All new code should be PEP8 compliant.

The make lint command (or pre-commit run -a) will run our linters and formatters with our configuration over the whole libquile to ensure your patch complies with reasonable formatting constraints. We also request that git commit messages follow the standard format.

16.7 Logging

Logs are important to us because they are our best way to see what Qtile is doing when something abnormal happens. However, our goal is not to have as many logs as possible, as this hinders readability. What we want are relevant logs.

To decide which log level to use, refer to the following scenarios:

- ERROR: a problem affects the behavior of Qtile in a way that is noticeable to the end user, and we can't work
 around it.
- WARNING: a problem causes Qtile to operate in a suboptimal manner.
- INFO: the state of Qtile has changed.
- DEBUG: information is worth giving to help the developer better understand which branch the process is in.

Be careful not to overuse DEBUG and clutter the logs. No information should be duplicated between two messages.

Also, keep in mind that any other level than DEBUG is aimed at users who don't necessarily have advanced programming knowledge; adapt your message accordingly. If it can't make sense to your grandma, it's probably meant to be a DEBUG message.

16.8 Using Xephyr

Qtile has a very extensive test suite, using the Xephyr nested X server. When tests are run, a nested X server with a nested instance of Qtile is fired up, and then tests interact with the Qtile instance through the client API. The fact that we can do this is a great demonstration of just how completely scriptable Qtile is. In fact, Qtile is designed expressly to be scriptable enough to allow unit testing in a nested environment.

The Qtile repo includes a tiny helper script to let you quickly pull up a nested instance of Qtile in Xephyr, using your current configuration. Run it from the top-level of the repository, like this:

```
./scripts/xephyr
```

Change the screen size by setting the SCREEN_SIZE environment variable. Default: 800x600. Example:

```
SCREEN_SIZE=1920x1080 ./scripts/xephyr
```

Change the log level by setting the LOG_LEVEL environment variable. Default: INFO. Example:

```
LOG_LEVEL=DEBUG ./scripts/xephyr
```

The script will also pass any additional options to Qtile. For example, you can use a specific configuration file like this:

```
./scripts/xephyr -c ~/.config/qtile/other_config.py
```

Once the Xephyr window is running and focused, you can enable capturing the keyboard shortcuts by hitting Control+Shift. Hitting them again will disable the capture and let you use your personal keyboard shortcuts again.

You can close the Xephyr window by enabling the capture of keyboard shortcuts and hit Mod4+Control+Q. Mod4 (or Mod) is usually the Super key (or Windows key). You can also close the Xephyr window by running qtile cmd-obj -o cmd -f shutdown in a terminal (from inside the Xephyr window of course).

You don't need to run the Xephyr script in order to run the tests as the test runner will launch its own Xephyr instances.

16.7. Logging 405

16.9 Second X Session

Some users prefer to test Qtile in a second, completely separate X session: Just switch to a new tty and run startx normally to use the $\sim/.xinitrc\ X$ startup script.

It's likely though that you want to use a different, customized startup script for testing purposes, for example \sim /. config/qtile/xinitrc. You can do so by launching X with:

```
startx ~/.config/qtile/xinitrc
```

startx deals with multiple X sessions automatically. If you want to use xinit instead, you need to first copy /etc/X11/xinit/xserverrc to ~/.xserverrc; when launching it, you have to specify a new session number:

```
xinit ~/.config/qtile/xinitrc -- :1
```

Examples of custom X startup scripts are available in qtile-examples.

16.10 Debugging in PyCharm

Make sure to have all the requirements installed and your development environment setup.

PyCharm should automatically detect the venv virtualenv when opening the project. If you are using another viirtualenv, just instruct PyCharm to use it in Settings -> Project: qtile -> Project interpreter.

In the project tree, on the left, right-click on the libqtile folder, and click on Mark Directory as -> Sources Root.

Next, add a Configuration using a Python template with these fields:

- Script path: bin/qtile, or the absolute path to it
- Parameters: -c libqtile/resources/default_config.py, or nothing if you want to use your own config file in ~/.config/qtile/config.py
- Environment variables: PYTHONUNBUFFERED=1;DISPLAY=:1
- Working directory: the root of the project
- Add contents root to PYTHONPATH: yes
- Add source root to PYTHONPATH: yes

Then, in a terminal, run:

Xephyr +extension RANDR -screen 1920x1040:1 -ac &

Note that we used the same display, :1, in both the terminal command and the PyCharm configuration environment variables. Feel free to change the screen size to fit your own screen.

Finally, place your breakpoints in the code and click on Debug!

Once you finished debugging, you can close the Xephyr window with kill PID (use the jobs builtin to get its PID).

16.11 Debugging in VSCode

Make sure to have all the requirements installed and your development environment setup.

Open the root of the repo in VSCode. If you have created it, VSCode should detect the venv virtualenv, if not, select it.

Create a launch.json file with the following lines.

Then, in a terminal, run:

Xephyr +extension RANDR -screen 1920x1040:1 -ac &

Note that we used the same display, :1, in both the terminal command and the VSCode configuration environment variables. Then debug usually in VSCode. Feel free to change the screen size to fit your own screen.

16.12 Resources

Here are a number of resources that may come in handy:

- Inter-Client Conventions Manual
- Extended Window Manager Hints
- A reasonable basic Xlib Manual

CHAPTER

SEVENTEEN

CONTRIBUTING

17.1 Reporting bugs

Perhaps the easiest way to contribute to Qtile is to report any bugs you run into on the GitHub issue tracker.

Useful bug reports are ones that get bugs fixed. A useful bug report normally has two qualities:

- 1. **Reproducible.** If your bug is not reproducible it will never get fixed. You should clearly mention the steps to reproduce the bug. Do not assume or skip any reproducing step. Describe the issue, step-by-step, so that it is easy to reproduce and fix.
- 2. **Specific.** Do not write an essay about the problem. Be specific and to the point. Try to summarize the problem in a succinct manner. Do not combine multiple problems even if they seem to be similar. Write different reports for each problem.

Ensure to include any appropriate log entries from ~/.local/share/qtile/qtile.log and/or ~/. xsession-errors! Sometimes, an xtrace is requested. If that is the case, refer to *capturing an xtrace*.

17.2 Writing code

To get started writing code for Qtile, check out our guide to *Hacking on Qtile*. A more detailed page on creating widgets is available *here*.

Important: Use a separate **git branch** to make rebasing easy. Ideally, you would **git checkout** -b <my_feature_branch_name> before starting your work.

See also: using git.

17.2.1 Submit a pull request

You've done your hacking and are ready to submit your patch to Qtile. Great! Now it's time to submit a pull request to our issue tracker on GitHub.

Important: Pull requests are not considered complete until they include all of the following:

- Code that conforms to our linters and formatters. Run pre-commit install to install pre-commit hooks that will make sure your code is compliant before any commit.
- Unit tests that pass locally and in our CI environment (More below). *Please add unit tests* to ensure that your code works and stays working!

- **Documentation** updates on an as needed basis.
- A qtile migrate migration is required for config-breaking changes. See *here* for current migrations and see below for further information.
- Code that does not include *unrelated changes*. Examples for this are formatting changes, replacing quotes or whitespace in other parts of the code or "fixing" linter warnings popping up in your editor on existing code. *Do not include anything like the above!*
- Widgets don't need to catch their own exceptions, or introduce their own polling infrastructure. The code in libqtile.widget.base.* does all of this. Your widget should generally only include whatever parsing/rendering code is necessary, any other changes should go at the framework level. Make sure to double-check that you are not re-implementing parts of libqtile.widget.base.
- Commit messages are more important that Github PR notes, since this is what people see when they are spelunking via git blame. Please include all relevant detail in the actual git commit message (things like exact stack traces, copy/pastes of discussion in IRC/mailing lists, links to specifications or other API docs are all good). If your PR fixes a Github issue, it might also be wise to link to it with #1234 in the commit message.
- PRs with **multiple commits** should not introduce code in one patch to then change it in a later patch. Please do a patch-by-patch review of your PR, and make sure each commit passes CI and makes logical sense on its own. In other words: *do* introduce your feature in one commit and maybe add the tests and documentation in a seperate commit. *Don't* push commits that partially implement a feature and are basically broken.

Note: Others might ban *force-pushes*, we allow them and prefer them over incomplete commits or commits that have a bad and meaningless commit description.

Feel free to add your contribution (no matter how small) to the appropriate place in the CHANGELOG as well!

17.2.2 Unit testing

We must test each *unit* of code to ensure that new changes to the code do not break existing functionality. The framework we use to test Qtile is pytest. How pytest works is outside of the scope of this documentation, but there are tutorials online that explain how it is used.

Our tests are written inside the test folder at the top level of the repository. Reading through these, you can get a feel for the approach we take to test a given unit. Most of the tests involve an object called manager. This is the test manager (defined in test/helpers.py), which exposes a command client at manager. c that we use to test a Qtile instance running in a separate thread as if we were using a command client from within a running Qtile session.

For any Qtile-specific question on testing, feel free to ask on our issue tracker or on IRC (#qtile on irc.oftc.net).

17.2.3 Running tests locally

This section gives an overview about tox so that you don't have to search its documentation just to get started.

Checks are grouped in so-called environments. Some of them are configured to check that the code works (the usual unit test, e.g. py39, pypy3), others make sure that your code conforms to the style guide (pep8, codestyle, mypy). A third kind of test verifies that the documentation and packaging processes work (docs, docstyle, packaging).

We have configured tox to run the full suite of tests whenever a pull request is submitted/updated. To reduce the amount of time taken by these tests, we have created separate environments for both python versions and backends (e.g. tests for x11 and wayland run in parallel for each python version that we currently support).

These environments were designed with automation in mind so there are separate test environments which should be used for running qtile's tests locally. By default, tests will only run on x11 backend (but see below for information on how to set the backend).

The following examples show how to run tests locally:

• To run the functional tests, use tox -e test. You can specify to only run a specific test file or even a specific test within that file with the following commands:

```
tox -e test # Run all tests in default python version
tox -e test -- -x test/widgets/test_widgetbox.py # run a single file
tox -e test -- -x test/widgets/test_widgetbox.py::test_widgetbox_widget
tox -e test -- --backend=wayland --backend=x11 # run tests on both backends
tox -e test-both # same as above
tox -e test-wayland # Just run tests on wayland backend
```

• To run style and building checks, use tox -e docs,packaging,pep8,.... You can use -p auto to run the environments in parallel.

Important: The CI is configured to run all the environments. Hence it can be time- consuming to make all the tests pass. As stated above, pull requests that don't pass the tests are considered incomplete. Don't forget that this does not only include the functionality, but the style, typing annotations (if necessary) and documentation as well!

17.2.4 Writing migrations

Migrations are needed when a commit introduces a change which makes a breaking change to a user's config. Examples include renaming classes, methods, arguments and moving modules or class definitions.

Where these changes are made, it is strongly encouraged to support the old syntax where possible and warn the user about the deprecations.

Whether or not a deprecation warning is provided, a migration script should be provided that will modify the user's config when they run qtile migrate.

Click here for detailed instructions on *How to write a migration script*.

How to write a migration script

Qtile's migration scripts should provide two functions:

- Update config files to fix any breaking changes introduced by a commit
- Provide linting summary of errors in existing configs

To do this, we use LibCST to parse the config file and make changes as appropriate. Basic tips for using LibCST are included below but it is recommended that you read their documentation to familiarise yourself with the available functionalities.

17.2. Writing code 411

Stucture of a migration file

Migrations should be saved as a new file in libqtile/scripts/migrations.

A basic migration will look like this:

```
from libqtile.scripts.migrations._base import MigrationTransformer, _QtileMigrator, add_
__migration

class MyMigration(MigrationTransformer):
    """The class that actually modifies the code."""
    ...

class Migrator(_QtileMigrator):
    ID = "MyMigrationName"

    SUMMARY = "Summary of migration."

    HELP = """
    Longer text explaining purpose of the migration and, ideally, giving code examples.
    """

    AFTER_VERSION = "0.22.1"

    TESTS = []
    visitor = MyMigration

add_migration(Migrator)
```

Providing details about the migration

The purpose of Migrator class in the code above is to provide the information about the migration.

It is important that the information is as helpful as possible as it is used in multiple places.

- The ID attribute is a short, unique name to identify the migration. This allows users to select specific migrations to run via qtile migrate --run-migrations ID.
- The SUMMARY attribute is used to provide a brief summary of the migration and is used when a user runs qtile migrate --list-migrations. It is also used in the documentation.
- Similarly, the HELP attribute is used for the script (qtie migrate --info ID) and the documentation. This text should be longer and can include example code. As it is used in the documentation, it should use RST syntax (e.g. .. code:: python for codeblocks etc.).
- AFTER_VERSION should be set the name of the current release. This allows users to filter migrations to those that were added after the last release.
- The visitor attribute is a link to the class definition (not and instance of the class) for the transformer that you wish to use.

- The add_migration call at the end is required to ensure the migration is loaded into the list of available migrations.
- See below for details on TESTS.

How migrations are run

You are pretty much free to transform the code as you see fit. By default, the script will run the visit method on the parsed code and will pass the visitor attribute of the _QtileMigrator class object. Therefore, if all your transformations can be performed in a single visitor, it is not necessary to do anything further in the Migrator class.

However, if you want to run mutiple visitors, transformers, codemods, this is possible by overriding the run method of the _QtileMigrator class. For example, the RemoveCmdPrefix migrator has the following code:

In this migration, it may be required to add an import statement. LibCST has a built-in transformation for doing this so we can run that after our own transformation has been performed.

Important: The run method must return a tuple of the original code and the updated code.

Transforming the code

It is recommended that you use a transformed to update the code. For convenience, a MigrationTransformer class is defined in libqtile.scripts.migrations._base. This class definition includes some metadata information and a lint method for outputting details of errors.

Let's look at an example transformer to understand how the migration works. The code below shows how to change a positional argument to a keyword argument in the WidgetBox widget.

17.2. Writing code 413

(continued from previous page)

Our class (which inherits from MigrationTransformer) defines a single method to perform the transformation. We take advantage of LibCST and its Matchers to narrow the scope of when the transformation is run.

We are looking to modify an argument so we use the @m.leave(m.Arg()) decorator to call the function at end of parsing an argument. We can restrict when this is called by specify m.Arg(keyword=None) so that it is only called for positional arguments. Furthermore, as we only want this called for WidgetBox instantiation lines, we add an additional decorator @m.call_if_inside(m.Call()). This ensures the method is only called when we're in a call. On its own, that's not helpful as args would almost always be part of a call. However, we can say we only want to match calls to WidgetBox. The reason for the long syntax above is that LibCST parses WidgetBox() and widget.WidgetBox() differently. In the first one, WidgetBox is in the func property of the call. However, in the second, the func is an Attribute as it is a dotted name and so we need to check the attr property.

The decorated method takes two arguments, original_mode and updated_node (note: The original_node should not be modified). The method should also confirm the return type.

The above method provides a linting message by calling self.lint and passing the original node and a helpful message.

Finally, the method updates the code by calling updated_node.with_changes(). In this instance, we add a keyword ("widgets") to the argument. We also remove spaces around the equals sign as these are added by default by LibCST. The updated node is returned.

Helper classes

Helper classes are provided for common transformations.

• RenamerTransformer will update all instances of a name, replacing it with another. The class will also handle the necessary linting.

```
class RenameHookTransformer(RenamerTransformer):
   from_to = ("window_name_change", "client_name_updated")
```

Testing the migration

All migrations must be tested, ideally with a number of scenarios to confirm that the migration works as expected.

Unlike other tests, the tests for the migrations are defined within the TESTS attribute.

This is a list that should take a Check, Change or NoChange object (all are imported from libqtile.scripts.migrations._base).

A Change object needs two parameters, the input code and the expected output. A NoChange object just defines the input (as the output should be the same).

A Check object is identical to Change however, when running the test suite, the migrated code will be verified with qtile check. The code will therefore need to include all relevant imports etc.

Based on the above, the following is recommended as best practice:

- Define one Check test which addresses every situation anticipated by the migration
- Use as many Change tests as required to test individual scenarios in a minimal way
- Use NoChange tests where there are specific cases that should not be modified
- Depending on the simplicity of the migration, a single Check may be all that is required

For example, the RemoveCmdPrefix migration has the following TESTS:

```
TESTS = [
    Change("""qtile.cmd_spawn("alacritty")""", """qtile.spawn("alacritty")"""),
    Change("""qtile.cmd_groups()""", """qtile.get_groups()"""),
Change("""qtile.cmd_screens()""", """qtile.get_screens()"""),
    Change("""qtile.current_window.cmd_hints()""", """qtile.current_window.get_hints()""
→"),
    Change (
         """qtile.current_window.cmd_opacity(0.5)""",
         """qtile.current_window.set_opacity(0.5)""".
    ),
    Change (
         class MyWidget(widget.Clock):
             def cmd_my_command(self):
                  pass
         0.00
         from libgtile.command.base import expose_command
         class MyWidget(widget.Clock):
             @expose_command
             def my_command(self):
                  pass
         .....
    ),
    NoChange (
         def cmd_some_other_func():
             pass
         .....
    ),
```

(continues on next page)

17.2. Writing code 415

(continued from previous page)

```
Check(
        from libqtile import qtile, widget
        class MyClock(widget.Clock):
            def cmd_my_exposed_command(self):
                pass
        def my_func(qtile):
            qtile.cmd_spawn("rickroll")
            hints = qtile.current_window.cmd_hints()
            groups = qtile.cmd_groups()
            screens = qtile.cmd_screens()
            qtile.current_window.cmd_opacity(0.5)
        def cmd_some_other_func():
            pass
        from libqtile import qtile, widget
        from libgtile.command.base import expose_command
        class MyClock(widget.Clock):
            @expose_command
            def my_exposed_command(self):
                pass
        def my_func(qtile):
            qtile.spawn("rickroll")
            hints = qtile.current_window.get_hints()
            groups = qtile.get_groups()
            screens = qtile.get_screens()
            gtile.current_window.set_opacity(0.5)
        def cmd_some_other_func():
            pass
        .....
   )
]
```

The tests check:

- cmd_ prefix is removed on method calls, updating specific changes as required
- Exposed methods in a class should use the expose_command decorator (adding the import if it's not already included)
- No change is made to a function definition (as it's not part of a class definition)

Note: Tests will fail in the following scenarios:

- If no tests are defined
- If a Change test does not result in linting output

· If no Check test is defined

You can check your tests by running pytest -k <YourMigrationID>. Note, mpypy must be installed for the Check tests to be run.

17.2.5 Deprecation Policy

Interfaces that have been deprecated for at least two years after the first release containing the deprecation notice can be deleted. Since all new breaking changes should have a migration, users can use qtile migrate to bootstrap across versions when migrations are deleted if necessary.

Deprecated interfaces that do not have a migration (i.e. whose deprecation was noted before the migration feature was introduced) are all fair game to be deleted, since the migration feature is more than two years old.

17.3 Recommended Resources for Getting Started with Wayland Development

17.3.1 Source Code Repositories

• wlroots (https://gitlab.freedesktop.org/wlroots/wlroots)

Pluggable, composable, unopinionated modules for building a Wayland compositor — or about 60,000 lines of code you were going to write anyway.

• TinyWL (https://gitlab.freedesktop.org/wlroots/wlroots/-/tree/master/tinywl)

A minimal Wayland compositor built with wlroots. Best starting point for learning wlroots by example.

• **DWL** (https://codeberg.org/dwl/dwl)

A compact, hackable Wayland compositor inspired by dwm. Focused on minimalism and suckless philosophy, built on wlroots.

• Sway (https://github.com/swaywm/sway)

A tiling Wayland compositor and drop-in replacement for i3. Great example of a full-featured, mature compositor built on whroots.

• LabWC (https://github.com/labwc/labwc)

A wlroots-based window-stacking compositor for Wayland, inspired by Openbox.

It is light-weight and independent with a focus on simply stacking windows well and rendering some window decorations. It takes a no-bling/frills approach and says no to features such as animations. It relies on clients for panels, screenshots, wallpapers and so on to create a full desktop environment.

• weston (https://gitlab.freedesktop.org/wayland/weston/-/tree/main/)

The reference Wayland compositor. Overengineered for some, but shows "the correct way" to do things.

• River (https://github.com/riverwm/river)

A dynamic tiling Wayland compositor that's minimal, written in C and based on wlroots. Less bloated than sway, more experimental than dwl.

17.3.2 Articles & Documentation

- Wayland Architecture Overview (https://wayland.freedesktop.org/architecture.html) Official architectural documentation
- Protocol Extensions (https://wayland.app/) Interactive protocol browser and documentation
- wlroots Documentation (https://gitlab.freedesktop.org/wlroots/wlroots/-/wikis/home) Official wlroots wiki and docs
- The Wayland Book (https://wayland-book.com/) A comprehensive introduction to Wayland and how it works.
- Introduction to Wayland (https://drewdevault.com/2017/06/10/Introduction-to-Wayland.html) by Drew De-Vault
- Wayland Compositor Series by Drew DeVault:
 - Part 1: Hello wlroots
 - Part 2: Rigging up the server
 - Part 3: Rendering a window
- Input handling in wlroots (https://drewdevault.com/2018/07/17/Input-handling-in-wlroots.html)
- Wayland Shells (https://drewdevault.com/2018/07/29/Wayland-shells.html)
- Intro to Damage Tracking (https://emersion.fr/blog/2019/intro-to-damage-tracking/) by emersion

17.3.3 Development Tools

- wayland-debug (https://gitlab.freedesktop.org/wayland/wayland/-/tree/main/debug)
 - Debugging tool for inspecting Wayland protocol traffic. Invaluable for compositor/client debugging.
- wayland-protocols (https://gitlab.freedesktop.org/wayland/wayland-protocols)
 - Collection of extended Wayland protocols (xdg-shell, layer-shell, etc). Essential when implementing desktop-like behaviors.
- wlr-protocols (https://gitlab.freedesktop.org/wlroots/wlr-protocols)
 - Custom/proposed protocols used by wlroots-based compositors (e.g., for gamma control, foreign-toplevel, screencopy).
- wf-recorder (https://github.com/ammen99/wf-recorder)
 - Wayland screen recorder compatible with wlroots compositors. Great for demos and debugging output.

17.3.4 Libraries and Helpers

- xwayland (https://gitlab.freedesktop.org/xorg/xserver/-/tree/master/hw/xwayland/)
 - Lets X11 clients run inside a Wayland session. Needed for legacy app support in your compositor.
- Pixman (https://www.pixman.org/)
 - Low-level pixel manipulation library used by wlroots. Useful if you're doing custom rendering or damage handling.
- Cairo (https://www.cairographics.org/)
 - 2D graphics library sometimes used for rendering surfaces in compositors or client UIs.

17.3.5 Video & Talks

• Wayland Explained by Daniel Stone (FOSDEM) (https://www.youtube.com/watch?v=RIctzAQOe44)

Excellent conceptual breakdown of Wayland internals from a veteran contributor.

• **Drew DeVault** - **Building Wayland desktop components with layer shell** (https://www.youtube.com/watch? v=VuRXHJu5Kmg)

Demonstration of the whoots layer shell, examples of where it's useful from lead developer of **SwayWM** (https://github.com/swaywm/sway).

17.3.6 Reverse Engineering Examples

• wayland-utils (https://gitlab.freedesktop.org/wayland/wayland-utils)

Includes tools like wayland-info that help inspect running compositors and protocols.

17.3.7 Related Projects & Alternatives

• WLC (https://github.com/Cloudef/wlc) (archived but insightful)

Predecessor of wlroots — still interesting to read for historical and design insights.

• **Mir** (https://github.com/MirServer/mir)

Canonical's alternative Wayland compositor library — not wlroots-based but valuable for contrast.

• **Smithay** (https://github.com/smithay/smithay)

A compositor library in Rust, parallel to wlroots. Good if you want to understand differences in approach (e.g. memory safety).

17.3.8 Qtile-Specific Additions

• qtile-wayland issues (https://github.com/qtile/qtile/issues?q=is%3Aissue+wayland) - Current Wayland-related issues and discussions

17.3.9 Our Goal — C-based Qtile Wayland Backend

• Qtile WayC (https://github.com/qtile/qtile/tree/wayc)

Ongoing effort to rewrite Qtile's Wayland backend in C using wlroots directly.

Why?

- Wlroots changes → requires tracking upstream C changes
- Updating pywlroots for new APIs
- Translating C API semantics into Python
- Then updating Qtile to match those changes

Doing it in C cuts through all that indirection and brings more control.

• Join Wayland development discussion (https://discord.com/channels/955163559086665728/1383006376695173230)

CHAPTER

EIGHTEEN

FREQUENTLY ASKED QUESTIONS

18.1 Why the name Qtile?

Users often wonder, why the Q? Does it have something to do with Qt? No. Below is an IRC excerpt where cortesi explains the great trial that ultimately brought Qtile into existence, thanks to the benevolence of the Open Source Gods. Praise be to the OSG!

```
ramnes: what does Qtile mean?
ramnes: what's the Q?
@tych0: ramnes: it doesn't :)
@tych0: cortesi was just looking for the first letter that wasn't registered
        in a domain name with "tile" as a suffix
@tych0: qtile it was :)
cortesi: tych0, dx: we really should have something more compelling to
         explain the name. one day i was swimming at manly beach in sydney,
         where i lived at the time. suddenly, i saw an enormous great white
         right beside me. it went for my leg with massive, gaping jaws, but
         quick as a flash, i thumb-punched it in both eyes. when it reared
         back in agony, i saw that it had a jagged, gnarly scar on its
         stomach... a scar shaped like the letter "Q".
cortesi: while it was distracted, i surfed a wave to shore. i knew that i
         had to dedicate my next open source project to the ocean gods, in
         thanks for my lucky escape. and thus, qtile got its name...
```

18.2 When I first start xterm/urxvt/rxvt containing an instance of Vim, I see text and layout corruption. What gives?

Vim is not handling terminal resizes correctly. You can fix the problem by starting your xterm with the "-wf" option, like so:

```
xterm -wf -e vim
```

Alternatively, you can just cycle through your layouts a few times, which usually seems to fix it.

18.3 How do I know which modifier specification maps to which key?

To see a list of modifier names and their matching keys, use the xmodmap command. On my system, the output looks like this:

```
$ xmodmap
xmodmap: up to 3 keys per modifier, (keycodes in parentheses):
shift
            Shift_L (0x32),
                             Shift_R (0x3e)
lock
            Caps_Lock (0x9)
control
            Control_L (0x25), Control_R (0x69)
mod1
            Alt_L (0x40), Alt_R (0x6c), Meta_L (0xcd)
mod2
            Num_Lock (0x4d)
mod3
mod4
            Super_L (0xce), Hyper_L (0xcf)
mod5
            ISO_Level3_Shift (0x5c), Mode_switch (0xcb)
```

18.4 My "pointer mouse cursor" isn't the one I expect it to be!

Qtile should set the default cursor to left_ptr, you must install xcb-util-cursor if you want support for themed cursors.

18.5 LibreOffice menus don't appear or don't stay visible

A workaround for problem with the mouse in libreoffice is setting the environment variable »SAL_USE_VCLPLUGIN=gen«. It is dependent on your system configuration as to where to do this. e.g. ArchLinux with libreoffice-fresh in /etc/profile.d/libreoffice-fresh.sh.

18.6 How can I get my groups to stick to screens?

This behaviour can be replicated by configuring your keybindings to not move groups between screens. For example if you want groups "1", "2" and "3" on one screen and "q", "w", and "e" on the other, instead of binding keys to lazy.group[name].toscreen(), use this:

```
groups = [
    # Screen affinity here is used to make
    # sure the groups startup on the right screens
    Group(name="1", screen_affinity=0),
    Group(name="2", screen_affinity=0),
    Group(name="3", screen_affinity=1),
    Group(name="w", screen_affinity=1),
    Group(name="w", screen_affinity=1),
    Group(name="e", screen_affinity=1),
]

def go_to_group(name: str):
    def _inner(qtile):
        if len(qtile.screens) == 1:
```

(continues on next page)

(continued from previous page)

```
qtile.groups_map[name].toscreen()
    return

if name in '123':
    qtile.focus_screen(0)
    qtile.groups_map[name].toscreen()

else:
    qtile.focus_screen(1)
    qtile.groups_map[name].toscreen()

return _inner

for i in groups:
    keys.append(Key([mod], i.name, lazy.function(go_to_group(i.name))))
```

To be able to move windows across these groups while switching groups, a similar function can be used:

```
def go_to_group_and_move_window(name: str):
   def _inner(qtile):
        if len(qtile.screens) == 1:
            qtile.current_window.togroup(name, switch_group=True)
            return
        if name in "123":
            qtile.current_window.togroup(name, switch_group=False)
            qtile.focus_screen(0)
            qtile.groups_map[name].toscreen()
        else:
            qtile.current_window.togroup(name, switch_group=False)
            qtile.focus_screen(1)
            qtile.groups_map[name].toscreen()
   return _inner
for i in groups:
   keys.append(Key([mod, "shift"], i.name, lazy.function(go_to_group_and_move_window(i.
→name))))
```

If you use the GroupBox widget you can make it reflect this behaviour:

```
groupbox1 = widget.GroupBox(visible_groups=['1', '2', '3'])
groupbox2 = widget.GroupBox(visible_groups=['q', 'w', 'e'])
```

And if you jump between having single and double screens then modifying the visible groups on the fly may be useful:

```
@hook.subscribe.screens_reconfigured
async def _():
    if len(qtile.screens) > 1:
        groupbox1.visible_groups = ['1', '2', '3']
    else:
        groupbox1.visible_groups = ['1', '2', '3', 'q', 'w', 'e']
    if hasattr(groupbox1, 'bar'):
        groupbox1.bar.draw()
```

18.7 Where can I find example configurations and other scripts?

Please visit our qtile-examples repo which contains examples of users' configurations, scripts and other useful links.

18.8 Where are the log files for Qtile?

The log files for qtile are at ~/.local/share/qtile/qtile.log.

18.9 How can I match the bar with picom?

You can use "QTILE_INTERNAL: 32c = 1" in your picom.conf to match the bar. This will match all internal Qtile windows, so if you want to avoid that or to target bars individually, you can set a custom property and match that:

```
mybar = Bar(...)
@hook.subscribe.startup
def _():
    mybar.window.window.set_property("QTILE_BAR", 1, "CARDINAL", 32)
```

This would enable matching on mybar's window using "QTILE_BAR: 32c = 1". See 2526 and 1515 for more discussion.

18.10 Why do get a warning that fonts cannot be loaded?

When installing Qtile on a new system, when running the test suite or the Xephyr script (./scripts/xephyr), you might see errors in the output like the following or similar:

• Xephyr script:

• pytest:

```
------ Captured stderr call ------
Warning: Cannot convert string "8x13" to type FontStruct
Warning: Unable to load any usable ISO8859 font
Warning: Unable to load any usable ISO8859 font
Error: Aborting: no font found
------ Captured stderr teardown ------
Qtile exited with exitcode: -9
```

If it happens, it might be because you're missing fonts on your system.

On ArchLinux, you can fix this by installing xorg-fonts-misc:

```
sudo pacman -S xorg-fonts-misc
```

Try to search for "xorg fonts misc" with your distribution name on the internet to find how to install them.

18.11 I've upgraded and Qtile's broken. What do I do?

If you've recently upgraded, the first thing to do is check the *changelog* and see if any breaking changes were made.

Next, check your log file (see above) to see if any error messages explain what the problem is.

If you're still stuck, come and ask for help on Discord, IRC or GitHub.

CHAPTER

NINETEEN

HOW TO CREATE A WIDGET

The aim of this page is to explain the main components of qtile widgets, how they work, and how you can use them to create your own widgets.

Note: This page is not meant to be an exhaustive summary of everything needed to make a widget.

It is highly recommended that users wishing to create their own widget refer to the source documentation of existing widgets to familiarise themselves with the code.

However, the detail below may prove helpful when read in conjunction with the source code.

19.1 What is a widget?

In Qtile, a widget is a small drawing that is displayed on the user's bar. The widget can display text, images and drawings. In addition, the widget can be configured to update based on timers, hooks, dbus_events etc. and can also respond to mouse events (clicks, scrolls and hover).

19.2 Widget base classes

Qtile provides a number of base classes for widgets than can be used to implement commonly required features (e.g. display text).

Your widget should inherit one of these classes. Whichever base class you inherit for your widget, if you override either the __init__ and/or _configure methods, you should make sure that your widget calls the equivalent method from the superclass.

```
class MyCustomWidget(base._TextBox):

    def __init__(self, **config):
        super().__init__("", **config)
        # My widget's initialisation code here
```

The functions of the various base classes are explained further below.

19.2.1 Widget

This is the base widget class that defines the core components required for a widget. All other base classes are based off this class.

This is like a blank canvas so you're free to do what you want but you don't have any of the extra functionality provided by the other base classes.

The base._Widget class is therefore typically used for widgets that want to draw graphics on the widget as opposed to displaying text.

19.2.2 **_TextBox**

The base._TextBox class builds on the bare widget and adds a drawer.TextLayout which is accessible via the self.layout property. The widget will adjust its size to fit the amount of text to be displayed.

Text can be updated via the self.text property but note that this does not trigger a redrawing of the widget.

Parameters including font, fontsize, fontshadow, padding and foreground (font colour) can be configured. It is recommended not to hard-code these parameters as users may wish to have consistency across units.

19.2.3 InLoopPollText

The base.InLoopPollText class builds on the base._TextBox by adding a timer to periodically refresh the displayed text.

Widgets using this class should override the poll method to include a function that returns the required text.

Note: This loop runs in the event loop so it is important that the poll method does not call some blocking function. If this is required, widgets should inherit the base. ThreadPoolText class (see below).

19.2.4 ThreadPoolText

The base.ThreadPoolText class is very similar to the base.InLoopPollText class. The key difference is that the poll method is run asynchronously and triggers a callback once the function completes. This allows widgets to get text from long-running functions without blocking Qtile.

19.3 Mixins

As well as inheriting from one of the base classes above, widgets can also inherit one or more mixins to provide some additional functionality to the widget.

19.3.1 PaddingMixin

This provides the padding (x|y) attributes which can be used to change the appearance of the widget.

If you use this mixin in your widget, you need to add the following line to your __init__ method:

```
self.add_defaults(base.PaddingMixin.defaults)
```

19.3.2 MarginMixin

The MarginMixin is essentially effectively exactly the same as the PaddingMixin but, instead, it provides the margin(x|y|) attributes.

As above, if you use this mixin in your widget, you need to add the following line to your __init__ method:

```
self.add_defaults(base.MarginMixin.defaults)
```

19.4 Configuration

Now you know which class to base your widget on, you need to know how the widget gets configured.

19.4.1 Defining Parameters

Each widget will likely have a number of parameters that users can change to customise the look and feel and/or behaviour of the widget for their own needs.

The widget should therefore provide the default values of these parameters as a class attribute called defaults. The format of this attribute is a list of tuples.

```
defaults = [
    ("parameter_name",
    default_parameter_value,
    "Short text explaining what parameter does")
]
```

Users can override the default value when creating their config.py file.

```
MyCustomWidget(parameter_name=updated_value)
```

Once the widget is initialised, these parameters are available at self.parameter_name.

19.4.2 The __init__ method

Parameters that should not be changed by users can be defined in the __init__ method.

This method is run when the widgets are initially created. This happens before the qtile object is available.

19.4. Configuration 429

19.4.3 The configure method

The _configure method is called by the bar object and sets the self.bar and self.qtile attributes of the widget. It also creates the self.drawer attribute which is necessary for displaying any content.

Once this method has been run, your widget should be ready to display content as the bar will draw once it has finished its configuration.

Calls to methods required to prepare the content for your widget should therefore be made from this method rather than __init__.

19.5 Displaying output

A Qtile widget is just a drawing that is displayed at a certain location the user's bar. The widget's job is therefore to create a small drawing surface that can be placed in the appropriate location on the bar.

19.5.1 The "draw" method

The draw method is called when the widget needs to update its appearance. This can be triggered by the widget itself (e.g. if the content has changed) or by the bar (e.g. if the bar needs to redraw its entire contents).

This method therefore needs to contain all the relevant code to draw the various components that make up the widget. Examples of displaying text, icons and drawings are set out below.

It is important to note that the bar controls the placing of the widget by assigning the offsetx value (for horizontal positioning) and offsety value (for vertical positioning). While the widget controls its width and height. These four values should be use at the end of the draw method. It is recommended to call this helper function to do it automatically:

```
self.draw_at_default_position()
```

Note: If you need to trigger a redrawing of your widget, you should call self.draw() if the width of your widget is unchanged. Otherwise you need to call self.bar.draw() as this method means the bar recalculates the position of all widgets.

19.5.2 Displaying text

Text is displayed by using a drawer. TextLayout object. If all you are doing is displaying text then it's highly recommended that you use the base._TextBox superclass as this simplifies adding and updating text.

If you wish to implement this manually then you can create a your own drawer.TextLayout by using the self. drawer.textlayout method of the widget (only available after the _configure method has been run). object to include in your widget.

Some additional formatting of Text can be displayed using pango markup and ensuring the markup parameter is set to True.

```
self.textlayout = self.drawer.textlayout(
    "Text",
    "ffffff",  # Font colour
    "sans",  # Font family
    12,  # Font size
    (continues on next page)
```

```
None, # Font shadow
markup=False, # Pango markup (False by default)
wrap=True # Wrap long lines (True by default)
)
```

19.5.3 Displaying icons and images

Qtile provides a helper library to convert images to a surface that can be drawn by the widget. If the images are static then you should only load them once when the widget is configured. Given the small size of the bar, this is most commonly used to draw icons but the same method applies to other images.

```
from libqtile import images
def setup_images(self):
    self.surfaces = {}
   # File names to load (will become keys to the `surfaces` dictionary)
   names = (
        "audio-volume-muted",
        "audio-volume-low",
        "audio-volume-medium",
        "audio-volume-high"
   )
    d_images = images.Loader(self.imagefolder)(*names) # images.Loader can take more_
→than one folder as an argument
    for name, img in d_images.items():
       new_height = self.bar.height - 1
        img.resize(height=new_height) # Resize images to fit widget
        self.surfaces[name] = img.pattern # Images added to the `surfaces` dictionary
```

Drawing the image is then just a matter of painting it to the relevant surface:

```
def draw(self):
    self.drawer.ctx.set_source(self.surfaces[img_name]) # Use correct key here for your_
    image
    self.drawer.ctx.paint()
    self.draw_at_default_position()
```

19.5.4 Drawing shapes

It is possible to draw shapes directly to the widget. The Drawer class (available in your widget after configuration as self.drawer) provides some basic functions rounded_rectangle, rounded_fillrect, rectangle and fillrect.

In addition, you can access the Cairo context drawing functions via self.drawer.ctx.

For example, the following code can draw a wifi icon showing signal strength:

```
import math
def to_rads(self, degrees):
   return degrees * math.pi / 180.0
def draw_wifi(self, percentage):
   WIFI\_HEIGHT = 12
   WIFI_ARC_DEGREES = 90
   y_margin = (self.bar.height - WIFI_HEIGHT) / 2
   half_arc = WIFI_ARC_DEGREES / 2
   # Draw grey background
    self.drawer.ctx.new_sub_path()
    self.drawer.ctx.move_to(WIFI_HEIGHT, y_margin + WIFI_HEIGHT)
    self.drawer.ctx.arc(WIFI_HEIGHT,
                        y_margin + WIFI_HEIGHT,
                        WIFI_HEIGHT,
                        self.to_rads(270 - half_arc),
                        self.to_rads(270 + half_arc))
    self.drawer.set_source_rgb("666666")
    self.drawer.ctx.fill()
   # Draw white section to represent signal strength
    self.drawer.ctx.new_sub_path()
    self.drawer.ctx.move_to(WIFI_HEIGHT, y_margin + WIFI_HEIGHT)
    self.drawer.ctx.arc(WIFI_HEIGHT
                        y_margin + WIFI_HEIGHT,
                        WIFI_HEIGHT * percentage,
                        self.to_rads(270 - half_arc),
                        self.to_rads(270 + half_arc))
    self.drawer.set_source_rgb("ffffff")
    self.drawer.ctx.fill()
```

This creates something looking like this:



19.5.5 Background

At the start of the draw method, the widget should clear the drawer by drawing the background. Usually this is done by including the following line at the start of the method:

```
self.drawer.clear(self.background or self.bar.background)
```

The background can be a single colour or a list of colours which will result in a linear gradient from top to bottom.

19.6 Updating the widget

Widgets will usually need to update their content periodically. There are numerous ways that this can be done. Some of the most common ones are summarised below.

19.6.1 Timers

A non-blocking timer can be called by using the self.timeout_add method.

```
self.timeout_add(delay_in_seconds, method_to_call, (method_args))
```

Note: Consider using the ThreadPoolText superclass where you are calling a function repeatedly and displaying its output as text.

19.6.2 Hooks

Qtile has a number of hooks built in which are triggered on certain events.

The WindowCount widget is a good example of using hooks to trigger updates. It includes the following method which is run when the widget is configured:

```
from libqtile import hook

def _setup_hooks(self):
   hook.subscribe.client_killed(self._win_killed)
   hook.subscribe.client_managed(self._wincount)
   hook.subscribe.current_screen_change(self._wincount)
   hook.subscribe.setgroup(self._wincount)
```

Read the *Built-in Hooks* page for details of which hooks are available and which arguments are passed to the callback function.

19.6.3 Using dbus

Otile uses dbus-fast for interacting with dbus.

If you just want to listen for signals then Qtile provides a helper method called add_signal_receiver which can subscribe to a signal and trigger a callback whenever that signal is broadcast.

Note: Qtile uses the asyncio based functions of dbus-fast so your widget must make sure, where necessary, calls to dbus are made via coroutines.

There is a _config_async coroutine in the base widget class which can be overridden to provide an entry point for asyncio calls in your widget.

For example, the Mpris2 widget uses the following code:

dbus-fast can also be used to query properties, call methods etc. on dbus interfaces. Refer to the dbus-fast documentation for more information on how to use the module.

19.7 Mouse events

By default, widgets handle button presses and will call any function that is bound to the button in the mouse_callbacks dictionary. The dictionary keys are as follows:

- Button1: Left click
- Button2: Middle click
- Button3: Right click
- Button4: Scroll up
- Button5: Scroll down
- Button6: Scroll left
- Button7: Scroll right

You can then define your button bindings in your widget (e.g. in __init__):

```
class MyWidget(widget.TextBox)

def __init__(self, *args, **config):
    widget.TextBox.__init__(self, *args, **kwargs)
```

Note: As well as functions, you can also bind LazyCall objects to button presses. For example:

In addition to button presses, you can also respond to mouse enter and leave events. For example, to make a clock show a longer date when you put your mouse over it, you can do the following:

```
class MouseOverClock(widget.Clock):
   defaults = \Gamma
            "long_format",
            "%A %d %B %Y | %H:%M",
            "Format to show when mouse is over widget."
        )
   ]
   def __init__(self, **config):
        widget.Clock.__init__(self, **config)
        self.add_defaults(MouseOverClock.defaults)
        self.short_format = self.format
   def mouse_enter(self, *args, **kwargs):
        self.format = self.long_format
        self.bar.draw()
   def mouse_leave(self, *args, **kwargs):
        self.format = self.short_format
        self.bar.draw()
```

19.8 Exposing commands to the IPC interface

If you want to control your widget via lazy or scripting commands (such as qtile cmd-obj), you will need to expose the relevant methods in your widget. Exposing commands is done by adding the @expose_command() decorator to your method. For example:

```
from libqtile.command.base import expose_command
from libqtile.widget import TextBox

(continues on next page)
```

```
class ExposedWidget(TextBox):
    @expose_command()
    def uppercase(self):
        self.update(self.text.upper())
```

Text in the ExposedWidget can now be made into upper case by calling lazy.widget["exposedwidget"]. uppercase() or qtile cmd-onj -o widget exposedwidget -f uppercase.

If you want to expose a method under multiple names, you can pass these additional names to the decorator. For example, decorating a method with:

```
@expose_command(["extra", "additional"])
def mymethod(self):
    ...
```

will make make the method visible under mymethod, extra and additional.

19.9 Debugging

You can use the logger object to record messages in the Qtile log file to help debug your development.

```
from libqtile.log_utils import logger
...
logger.debug("Callback function triggered")
```

Note: The default log level for the Qtile log is INFO so you may either want to change this when debugging or use logger.info instead.

Debugging messages should be removed from your code before submitting pull requests.

19.10 Submitting the widget to the official repo

The following sections are only relevant for users who wish for their widgets to be submitted as a PR for inclusion in the main Qtile repo.

19.10.1 Including the widget in libqtile.widget

You should include your widget in the widgets dict in libqtile.widget.__init__.py. The relevant format is {"ClassName": "modulename"}.

This has a number of benefits:

- · Lazy imports
- Graceful handling of import errors (useful where widget relies on third party modules)
- Inclusion in basic unit testing (see below)

19.10.2 **Testing**

Any new widgets should include an accompanying unit test.

Basic initialisation and configurations (using defaults) will automatically be tested by test/widgets/test_widget_init_configure.py if the widget has been included in libqtile.widget.__init__.py (see above).

However, where possible, it is strongly encouraged that widgets include additional unit tests that test specific functionality of the widget (e.g. reaction to hooks).

See Unit testing for more.

19.10.3 Documentation

It is really important that we maintain good documentation for Qtile. Any new widgets must therefore include sufficient documentation in order for users to understand how to use/configure the widget.

The majority of the documentation is generated automatically from your module. The widget's docstring will be used as the description of the widget. Any parameters defined in the widget's defaults attribute will also be displayed. It is essential that there is a clear explanation of each new parameter defined by the widget.

Screenshots

While not essential, it is strongly recommended that the documentation includes one or more screenshots.

Screenshots can be generated automatically with a minimal amount of coding by using the fixtures created by Qtile's test suite.

A screenshot file must satisfy the following criteria:

- Be named ss_[widgetname].py
- Any function that takes a screenshot must be prefixed with ss_
- Define a pytest fixture named widget

An example screenshot file is below:

```
import pytest
from libqtile.widget import wttr
from test.widgets.docs_screenshots.conftest import vertical_bar, widget_config

RESPONSE = "London: +17°C"
```

```
@pytest.fixture
def widget(monkeypatch):
    def result(self):
        return RESPONSE

monkeypatch.setattr("libqtile.widget.wttr.Wttr.fetch", result)
    yield wttr.Wttr

@widget_config([{"location": {"London": "Home"}}])
def ss_wttr(screenshot_manager):
    screenshot_manager.take_screenshot()

@vertical_bar
def ss_wttr_vertical(screenshot_manager):
    screenshot_manager.take_screenshot()
```

The widget fixture returns the widget class (not an instance of the widget). Any monkeypatching of the widget should be included in this fixture.

The screenshot function (here, called ss_wttr) must take an argument called screenshot_manager. The function can also be parameterized, in which case, each dict object will be used to configure the widget for the screenshot (and the configuration will be displayed in the docs). If you want to include parameterizations but also want to show the default configuration, you should include an empty dict ({}) as the first object in the list.

Taking a screenshot is then as simple as calling screenshot_manager.take_screenshot(). The method can be called multiple times in the same function.

Screenshots can also be taken in a vertical bar orientation by using the @vertical_bar decorator as shown in the above example.

screenshot_manager.take_screenshot() only takes a picture of the widget. If you need to take a screenshot of the bar then you need a few extra steps:

```
def ss_bar_screenshot(screenshot_manager):
    # Generate a filename for the screenshot
    target = screenshot_manager.target()

# Get the bar object
bar = screenshot_manager.c.bar["top"]

# Take a screenshot. Will take screenshot of whole bar unless
# a `width` parameter is set.
bar.take_screenshot(target, width=width)
```

19.11 Getting help

If you still need help with developing your widget then please submit a question in the qtile-dev group or submit an issue on the github page if you believe there's an error in the codebase.

19.11. Getting help 439

Otile Documentation, Release 0.1.dev50+g42203cb	

CHAPTER

TWENTY

HOW TO CREATE A LAYOUT

The aim of this page is to explain the main components of qtile layouts, how they work, and how you can use them to create your own layouts or hack existing layouts to make them work the way you want them.

Note: It is highly recommended that users wishing to create their own layout refer to the source documentation of existing layouts to familiarise themselves with the code.

20.1 What is a layout?

In Qtile, a layout is essentially a set of rules that determine how windows should be displayed on the screen. The layout is responsible for positioning all windows other than floating windows, "static" windows, internal windows (e.g. the bar) and windows that have requested not to be managed by the window manager.

20.2 Base classes

To simplify the creation of layouts, a couple of base classes are available to users.

20.2.1 The Layout class

As a bare minimum, all layouts should inherit the base Layout class object as this class defines a number of methods required for basic usage and will also raise errors if the required methods are not implemented. Further information on these required methods is set out below.

20.2.2 The _SimpleLayoutBase class

This class implements everything needed for a basic layout with the exception of the configure method. Therefore, unless your layout requires special logic for updating and navigating the list of clients, it is strongly recommended that your layout inherits this base class

20.2.3 The _ClientList class

This class defines a list of clients and the current client.

The collection is meant as a base or utility class for special layouts, which need to maintain one or several collections of windows, for example Columns or Stack, which use this class as base for their internal helper.

The property current_index get and set the index to the current client, whereas current_client property can be used with clients directly.

20.3 Required methods

To create a minimal, functioning layout your layout must include the methods listed below:

- __init__
- configure
- add_client
- remove
- focus_first
- focus_last
- · focus_next
- focus_previous
- next
- previous

As noted above, if you create a layout based on the _SimpleLayoutBase class, you will only need to define configure (and _init__, if you have custom parameters). However, for the purposes of this document, we will show examples of all required methods.

20.3.1 __init__

Initialise your layout's variables here. The main use of this method will be to load any default parameters defined by layout. These are defined in a class attribute called defaults. The format of this attribute is a list of tuples.

```
def __init__(self, **config):
    base.Layout.__init__(self, **config)
    self.add_defaults(TwoByTwo.defaults)
    self.clients = []
    self.current_client = None
```

Once the layouts is initialised, these parameters are available at self.border_width etc.

20.3.2 configure

This is where the magic happens! This method is responsible for determining how to position a window on the screen.

This method should therefore configure the dimensions and borders of a window using the window's .place() method. The layout can also call either hide() or .unhide() on the window.

```
def configure(self, client: Window, screen_rect: ScreenRect) -> None:
    """Simple example breaking screen into four quarters."""
   try:
        index = self.clients.index(client)
   except ValueError:
        # Layout not expecting this window so ignore it
   # We're only showing first 4 windows
   if index > 3:
        client.hide()
        return
   # Unhide the window in case it was hiddent before
   client.unhide()
   # List to help us calculate x and y values of
   quarters = [
        (0, 0),
        (0.5, 0),
        (0, 0.5),
        (0.5, 0.5)
   # Calculate size and position for each window
   xpos, ypos = quarters[index]
   x = int(screen_rect.width * xpos) + screen_rect.x
   y = int(screen_rect.height * ypos) + screen_rect.y
   w = screen_rect.width // 2
   h = screen_rect.height // 2
   if client is self.current client:
        margin = self.margin_focused
   else:
```

```
margin = self.margin_unfocused

client.place(
    x,
    y,
    w - self.border_width * 2,
    h - self.border_width * 2,
    self.border_width,
    self.border_colour,
    margin=[margin] * 4,
)
```

20.3.3 add_client

This method is called whenever a window is added to the group, regardless of whether the layout is current or not. The layout should just add the window to its internal datastructures, without mapping or configuring/displaying.

```
def add_client(self, client: Window) -> None:
    # Assumes self.clients is simple list
    self.clients.insert(0, client)
    self.current_client = client
```

20.3.4 remove

This method is called whenever a window is removed from the group, regardless of whether the layout is current or not. The layout should just de-register the window from its data structures, without unmapping the window.

The method must also return the "next" window that should gain focus or None if there are no other windows.

```
def remove(self, client: Window) -> Window | None:
   # Assumes self.clients is a simple list
   # Client already removed so ignore this
   if client not in self.clients:
       return None
   # Client is only window in the list
   elif len(self.clients) == 1:
        self.clients.remove(client)
        self.current_client = None
        # There are no other windows so return None
       return None
   else:
        # Find position of client in our list
        index = self.clients.index(client)
        # Remove client
        self.clients.remove(client)
        # Ensure the index value is not greater than list size
        # i.e. if we closed the last window in the list, we need to return
        # the first one (index 0).
        index %= len(self.clients)
       next_client = self.clients[index]
```

```
self.current_client = next_client
return next_client
```

20.3.5 focus_first

This method is called when the first client in the layout should be focused.

This method should just return the first client in the layout, if any. NB the method should not focus the client itself, this is done by caller.

```
def focus_first(self) -> Window | None:
    if not self.clients:
        return None
    return self.client[0]
```

20.3.6 focus_last

This method is called when the last client in the layout should be focused.

This method should just return the last client in the layout, if any. NB the method should not focus the client itself, this is done by caller.

```
def focus_last(self) -> Window | None:
    if not self.clients:
        return None
    return self.client[-1]
```

20.3.7 focus_next

This method is called the next client in the layout should be focused.

This method should return the next client in the layout, if any. NB the layout should not cycle clients when reaching the end of the list as there are other method in the group for cycling windows which focus floating windows once the the end of the tiled client list is reached.

In addition, the method should not focus the client.

```
def focus_next(self, win: Window) -> Window | None:
    try:
        return self.clients[self.clients.index(win) + 1]
    except IndexError:
        return None
```

20.3.8 focus_previous

This method is called the previous client in the layout should be focused.

This method should return the previous client in the layout, if any. NB the layout should not cycle clients when reaching the end of the list as there are other method in the group for cycling windows which focus floating windows once the the end of the tiled client list is reached.

In addition, the method should not focus the client.

```
def focus_previous(self, win: Window) -> Window | None:
   if not self.clients or self.clients.index(win) == 0
      return None

   try:
      return self.clients[self.clients.index(win) - 1]
   except IndexError:
      return None
```

20.3.9 next

This method focuses the next tiled window and can cycle back to the beginning of the list.

```
def next(self) -> None:
    if self.current_client is None:
        return
    # Get the next client or, if at the end of the list, get the first
    client = self.focus_next(self.current_client) or self.focus_first()
    self.group.focus(client, True)
```

20.3.10 previous

This method focuses the previous tiled window and can cycle back to the end of the list.

```
def previous(self) -> None:
    if self.current_client is None:
        return
# Get the previous client or, if at the end of the list, get the last
    client = self.focus_previous(self.current_client) or self.focus_last()
    self.group.focus(client, True)
```

20.4 Additional methods

While not essential to implement, the following methods can also be defined:

- clone
- show
- hide
- swap

- focus
- blur

20.4.1 clone

Each group gets a copy of the layout. The clone method is used to create this copy. The default implementation in Layout is as follows:

```
def clone(self, group: _Group) -> Self:
    c = copy.copy(self)
    c._group = group
    return c
```

20.4.2 show

This method can be used to run code when the layout is being displayed. The method receives one argument, the ScreenRect for the screen showing the layout.

The default implementation is a no-op:

```
def show(self, screen_rect: ScreenRect) -> None:
    pass
```

20.4.3 hide

This method can be used to run code when the layout is being hidden.

The default implementation is a no-op:

```
def hide(self) -> None:
    pass
```

20.4.4 swap

This method is used to change the position of two windows in the layout.

```
def swap(self, c1: Window, c2: Window) -> None:
    if c1 not in self.clients and c2 not in self.clients:
        return

    index1 = self.clients.index(c1)
    index2 = self.clients.index(c2)

    self.clients[index1], self.clients[index2] = self.clients[index2], self.
        clients[index1]
```

20.4.5 focus

This method is called when a given window is being focused.

```
def focus(self, client: Window) -> None:
    if client not in self.clients:
        self.current_client = None
        return

    index = self.clients.index(client)

# Check if window is not visible
    if index > 3:
        c = self.clients.pop(index)
        self.clients.insert(0, c)
self.current_client = client
```

20.4.6 blur

This method is called when the layout loses focus.

```
def blur(self) -> None:
    self.current_client = None
```

20.5 Adding commands

Adding commands allows users to modify the behaviour of the layout. To make commands available via the command interface (e.g. via lazy.layout calls), the layout must include the following import:

```
from libqtile.command.base import expose_command
```

Commands are then decorated with @expose_command. For example:

```
@expose_command
def rotate(self, clockwise: bool = True) -> None:
    if not self.clients:
        return

if clockwise:
        client = self.clients.pop(-1)
        self.clients.insert(0, client)

else:
        client = self.clients.pop(0)
        self.clients.append(client)

# Check if current client has been rotated off the screen
    if self.current_client and self.clients.index(self.current_client) > 3:
        if clockwise:
            self.current_client = self.clients[3]
```

```
else:
    self.current_client = self.clients[0]

# Redraw the layout
self.group.layout_all()
```

20.5.1 The info command

Layouts should also implement an info method to provide information about the layout.

As a minimum, the test suite (see below) will expect a layout to return the following information:

- Its name
- Its group
- The clients managed by the layout

NB the last item is not included in Layout's implementation of the method so it should be added when defining a class that inherits that base.

```
@expose_command
def info(self) -> dict[str, Any]:
   inf = base.Layout.info(self)
   inf["clients"] = self.clients
   return inf
```

20.6 Adding layout to main repo

If you think your layout is amazing and you want to share with other users by including it in the main repo then there are a couple of extra steps that you need to take.

20.6.1 Add to list of layouts

You must save the layout in libqtile/layout and then add a line importing the layout definition to libqtile/layout/__init__.py e.g.

```
from libqtile.layout.twobytwo import TwoByTwo
```

20.6.2 Add tests

Basic functionality for all layouts is handled automatically by the core test suite. However, you should create tests for any custom functionality of your layout (e.g. testing the rotate command defined above).

20.7 Full example

The full code for the example layout is as follows:

```
from __future__ import annotations
from typing import TYPE_CHECKING
from libqtile.command.base import expose_command
from libqtile.layout import base
if TYPE_CHECKING:
    from libqtile.backend.base import Window
    from libqtile.config import ScreenRect
    from libqtile.group import _Group
class TwoByTwo(base.Layout):
   A simple layout with a fixed two by two grid.
   By default, unfocused windows are smaller than the focused window.
   defaults = [
        ("border_width", 5, "Window border width"),
        ("border_colour", "00ff00", "Window border colour"),
        ("margin_focused", 5, "Margin width for focused windows"),
        ("margin_unfocused", 50, "Margin width for unfocused windows")
   1
   def __init__(self, **config):
        base.Layout.__init__(self, **config)
        self.add_defaults(TwoByTwo.defaults)
        self.clients = []
        self.current client = None
   def configure(self, client: Window, screen_rect: ScreenRect) -> None:
        """Simple example breaking screen into four quarters."""
            index = self.clients.index(client)
        except ValueError:
            # Layout not expecting this window so ignore it
           return
        # We're only showing first 4 windows
        if index > 3:
            client.hide()
        # Unhide the window in case it was hiddent before
        client.unhide()
        # List to help us calculate x and y values of
```

(continues on next page)

451


```
quarters = [
        (0, 0),
        (0.5, 0),
        (0, 0.5),
        (0.5, 0.5)
    ]
    # Calculate size and position for each window
   xpos, ypos = quarters[index]
    x = int(screen_rect.width * xpos) + screen_rect.x
    y = int(screen_rect.height * ypos) + screen_rect.y
   w = screen_rect.width // 2
   h = screen_rect.height // 2
    if client is self.current_client:
        margin = self.margin_focused
    else:
        margin = self.margin_unfocused
    client.place(
        х.
        у,
        w - self.border_width * 2,
        h - self.border_width * 2,
        self.border_width,
        self.border_colour,
        margin=[margin] * 4,
    )
def add_client(self, client: Window) -> None:
    # Assumes self.clients is simple list
    self.clients.insert(0, client)
    self.current_client = client
def remove(self, client: Window) -> Window | None:
    # Assumes self.clients is a simple list
    # Client already removed so ignore this
    if client not in self.clients:
        return None
    # Client is only window in the list
    elif len(self.clients) == 1:
        self.clients.remove(client)
        self.current_client = None
        # There are no other windows so return None
        return None
    else:
        # Find position of client in our list
        index = self.clients.index(client)
        # Remove client
        self.clients.remove(client)
        # Ensure the index value is not greater than list size
```

20.7. Full example

```
# i.e. if we closed the last window in the list, we need to return
        # the first one (index 0).
        index %= len(self.clients)
        next_client = self.clients[index]
        self.current_client = next_client
        return next_client
def focus_first(self) -> Window | None:
    if not self.clients:
        return None
    return self.client[0]
def focus_last(self) -> Window | None:
    if not self.clients:
        return None
    return self.client[-1]
def focus_next(self, win: Window) -> Window | None:
    try:
        return self.clients[self.clients.index(win) + 1]
    except IndexError:
        return None
def focus_previous(self, win: Window) -> Window | None:
    if not self.clients or self.clients.index(win) == 0:
        return None
    try:
        return self.clients[self.clients.index(win) - 1]
    except IndexError:
        return None
def next(self) -> None:
    if self.current_client is None:
    # Get the next client or, if at the end of the list, get the first
    client = self.focus_next(self.current_client) or self.focus_first()
    self.group.focus(client, True)
def previous(self) -> None:
    if self.current_client is None:
    # Get the previous client or, if at the end of the list, get the last
    client = self.focus_previous(self.current_client) or self.focus_last()
    self.group.focus(client, True)
def swap(self, c1: Window, c2: Window) -> None:
    if c1 not in self.clients and c2 not in self.clients:
        return
```

```
index1 = self.clients.index(c1)
       index2 = self.clients.index(c2)
       self.clients[index1], self.clients[index2] = self.clients[index2], self.
def focus(self, client: Window) -> None:
       if client not in self.clients:
           self.current_client = None
           return
       index = self.clients.index(client)
       # Check if window is not visible
       if index > 3:
           c = self.clients.pop(index)
           self.clients.insert(0, c)
       self.current_client = client
   def blur(self) -> None:
       self.current client = None
   @expose_command
   def rotate(self, clockwise: bool = True) -> None:
       if not self.clients:
           return
       if clockwise:
           client = self.clients.pop(-1)
           self.clients.insert(0, client)
       else:
           client = self.clients.pop(0)
           self.clients.append(client)
       # Check if current client has been rotated off the screen
       if self.current_client and self.clients.index(self.current_client) > 3:
           if clockwise:
               self.current_client = self.clients[3]
           else:
               self.current_client = self.clients[0]
       # Redraw the layout
       self.group.layout_all()
   @expose_command
   def info(self) -> dict[str, Any]:
       inf = base.Layout.info(self)
       inf["clients"] = self.clients
       return inf
```

20.7. Full example 453



This should result in a layout looking like this:

20.8 Getting help

If you still need help with developing your widget then please submit a question in the qtile-dev group or submit an issue on the github page if you believe there's an error in the codebase.

CHAPTER

TWENTYONE

USING GIT

git is the version control system that is used to manage all of the source code. It is very powerful, but might be frightening at first. This page should give you a quick overview, but for a complete guide you will have to search the web on your own. Another great resource to get started practically without having to try out the newly-learned commands on a pre-existing repository is learn git branching. You should probably learn the basic git vocabulary and then come back to find out how you can use all that practically. This guide will be oriented on how to create a pull request and things might be in a different order compared to the introductory guides.

Warning: This guide is not complete and never will be. If something isn't clear, consult other sources until you are confident you know what you are doing.

21.1 I want to try out a feature somebody is working on

If you see a pull request on GitHub that you want to try out, have a look at the line where it says:

```
user wants to merge n commits into qtile:master from user:branch
```

Right now you probably have one *remote* from which you can fetch changes, the origin. If you cloned qtile/qtile, git remote show origin will spit out the *upstream* url. If you cloned your fork, origin points to it and you probably want to git remote add upstream https://www.github.com/qtile/qtile. To try out somebody's work, you can add their fork as a new remote:

```
git remote add <user> https://www.github.com/user/qtile
```

where you fill in the username from the line we asked you to search for before. Then you can load data from that remote with git fetch and then ultimately check out the branch with git checkout <user>/
branch>.

Alternatively, it is also possible to fetch and checkout pull requests without needing to add other remotes. The upstream remote is sufficient:

```
git fetch upstream pull/<id>/head:pr<id>
git checkout pr<id>
```

The numeric pull request id can be found in the url or next to the title (preceded by a # symbol).

Note: Having the feature branch checked out doesn't mean that it is installed and will be loaded when you restart qtile. You might still need to install it with uv.

21.2 I committed changes and the tests failed

You can easily change your last commit: After you have done your work, git add everything you need and use git commit --amend to change your last commit. This causes the git history of your local clone to be diverged from your fork on GitHub, so you need to force-push your changes with:

```
git push -f <origin> <feature-branch>
```

where origin might be your user name or origin if you cloned your fork and feature-branch is to be replaced by the name of the branch you are working on.

Assuming the feature branch is currently checked out, you can usually omit it and just specify the origin.

21.3 I was told to rebase my work

If *upstream/master* is changed and you happened to change the same files as the commits that were added upstream, you should rebase your work onto the most recent *upstream/master*. Checkout your master, pull from *upstream*, checkout your branch again and then rebase it:

```
git checkout master
git pull upstream/master
git checkout <feature-branch>
git rebase upstream/master
```

You will be asked to solve conflicts where your diff cannot be applied with confidence to the work that was pushed upstream. If that is the case, open the files in your text editor and resolve the conflicts manually. You possibly need to git rebase --continue after you have resolved conflicts for one commit if you are rebasing multiple commits.

Note that the above doesn't work if you didn't create a branch. In that case you will find guides elsewhere to fix this problem, ideally by creating a branch and resetting your master branch to where it should be.

21.4 I was told to squash some commits

If you introduce changes in one commit and replace them in another, you are told to squash these changes into one single commit without the intermediate step:

```
git rebase -i master
```

opens a text editor with your commits and a comment block reminding you what you can do with your commits. You can reword them to change the commit message, reorder them or choose fixup to squash the changes of a commit into the commit on the line above.

This also changes your git history and you will need to force-push your changes afterwards.

Note that interactive rebasing also allows you to split, reorder and edit commits.

21.5 I was told to edit a commit message

If you need to edit the commit message of the last commit you did, use:

```
git commit --amend
```

to open an editor giving you the possibility to reword the message. If you want to reword the message of an older commit or multiple commits, use git rebase -i as above with the reword command in the editor.

21.5.1 Releasing Qtile

Here is a short document about how to tag Qtile releases.

1. create a "Release vX.XX.XX" commit. I like to thank all the contributors; I find that list with something like:

note that this can sometimes generate duplicates if people commit with slightly different names; I typically clean it up manually.

Be sure that you GPG-sign (i.e. the -S argument to git commit) this commit.

- 2. Create a GPG-signed annotated tag (git tag -a -s vX.XX.XX); I usually just use exactly the same commit message as the actual release commit above.
- 3. Push your tag to qtile/qtile directly:

```
git push origin vX.XX.XX
```

- 4. Check the Release action; the "Test PyPI upload" action should build and upload the wheels to the test environment. If this step breaks, you can delete your tag (git push ...:vX.XX.XX), fix the bug, re-tag, and hopefully that will work.
- 5. Create a new Github release; this is what will trigger the actions in .github/workflows/release.yml to actually do the real pypi upload.
- 6. Make sure all of these actions complete as green. The release should show up in a few minutes after completion here: https://pypi.org/project/qtile/
- 7. Push your tag commit to master.
- 8. Update the release string on qtile.org.
- 8. Relax and enjoy a \$beverage. Thanks for releasing!

CHAPTER

TWENTYTWO

LICENSE

This project is distributed under the MIT license.

Copyright (c) 2008, Aldo Cortesi All rights reserved.

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

460 Chapter 22. License

CHAPTER

TWENTYTHREE

CHANGELOG

```
Qtile x.xx.x, released xxxx-xx-xx:
    !!! breaking changes !!!
      - Remove CurrentLayoutIcon, functionality merged with CurrentLayout

    Add support for orientation vertical to the new CurrentLayout widget

    * bugfixes
Qtile 0.32.0, released 2025-06-09:
    !!! breaking changes !!!
      - Output of `qtile cmd-obj` is now in JSON.
    * features
        - Add support for `single-pixel-buffer` protocol for wayland
        - Add charging foreground/background colors to Battery widget
    * bugfixes
        - `window.can_steal_focus = False` should be set in a `group_window_add` instead.
→of the previously recommended `client_new` hook.
        - Fix Xwayland popup windows that fail to reappear #5155
        - Wayland: retain keybindings when switching keyboard layouts
Qtile 0.31.0, released 2025-03-07:
    !!! breaking changes !!!
        - Spiral layout: `shuffle_up` and `shuffle_down` commands now shuffle the_
→focused window instead of rotating all windows.
    * features
        - Add TunedManager Widget to show the currently active power profile and cycle.

→through a list of configurable power profiles

    * bugfixes
        - Fix StatusNotifier displaying wrong icon when icon changes too quickly (e.g.,
→nm-applet)
        - PulseVolume widget: fix breakage with xrandr/wlr-randr + reload config #5111
Qtile 0.30.0, released 2025-01-06:
    !!! breaking changes !!!
      - dbus-fast is now required for dbus support.
        dbus-next was removed as the package is unmaintained.
    * features
        - Add `SwayNC` widget to interact with Sway Notification Centre (wayland only)
        - Add `swap` method to Plasma layout
        - New `click_or_drag_only` option for follow_mouse_focus to change the focus to.
→the window under the mouse when click or drag
```

```
- Customize battery widget "Full" and "Empty" short text with `full_short_text`_
→and `empty_short_text`
    * bugfixes

    Make MonadWide layout up/down focus navigation behave like MonadTall's left/

→right
Qtile 0.29.0, released 2024-10-19:
    * features
        - A Nix flake has been added which can be used by Nix(OS) users to update to the
→latest version easily
        - Add `group_window_remove` hook when window is removed from group
        - Switched to ruff for formatting
    * bugfixes
        - Add returns to lazy.function and qtile.core.function
        - Fix a bug with newer versions of cairo breaking the bar
        - Fix a few TreeTab rendering bugs
        - Fix a TaskList crash
        - Fix a scratchpad window size bug
Qtile 0.28.1, released 2024-08-12:
    * bugfixes
        - fix a crash in the StatusNotifier widget #4959 #4960
Qtile 0.28.0, released 2024-08-11:
    * bugfixes
        - various bug fixes to widgets from previous releases
        - fix xrandr commands racing with qtile startup
Otile 0.27.0, released 2024-07-12:
    * features
        - Make default `Plasma` add mode dynamic
        - Add `background` parameter to `Screen` to paint a solid colour background
        - Add ability to use key codes to bind keys. Will benefit users who change
→keyboard layouts but
          wish to retain same bindings, irrespective of layout.
        - Wayland: Add support for idle-notify-v1 protocol needed by swayidle.
        - Wayland: Make keybinds repeat according to the keyboard's repeat rate and.
→delay. Previously the keybinds did not repeat.
    * bugfixes
      - Fix `Plasma` layout with `ScreenSplit` by implementing `get_windows`
      - Fix border bug in fullscreening/maximizing wayland windows
      - Fix automatic fullscreening for many XWayland applications (e.g. games) by ...
→checking if they want to fullscreen on map
Qtile 0.26.0, released 2024-05-21:
    !!! breaking changes !!!
      - this release drops support for python 3.9

    deleted the (very old) libqtile/command_* deprecation wrappers

    SIGUSR2 no longer restarts qtile, instead it dumps stack traces

    lazy.<object>.when(when_floating=X) now behaves differently: the lazy call will.

→be executed
```

```
independently of the current window's float state by default, and can be limited.
→to when it
        is floating or tiled by passing when_floating as True or False respectively.
      - Dropped support for KDE idle protocol on Wayland
    !!! Notice for packagers - Wayland backend !!!
      - Qtile's Wayland backend now requires wlroots 0.17.x, pywlroots 0.17.x and.
\rightarrowpywayland >= 0.4.17.
    !!! Notice for pip package - Pypy !!!
      - We currently do not build for pypy-3.10 as there seems to be a resolution error.
→in either pypy or pip (https://github.com/pypy/pypy/issues/4956)
    * features
      - For Wayland you can now set the cursor theme and size to forcefully use in Qtile,
        set `wl_xcursor_theme` and `wl_xcursor_size` in the configuration
      - automatically lift types to their annotated type when specified via
        the `qtile cmd-obj` command line
      - Add `Plasma` layout. The original layout (https://github.com/numirias/qtile-
⇒plasma) appears to be unmaintained
        so we have added this to the main codebase.
      - Add ability to specify muted and unmuted formats for `Volume` and `PulseVolume`...
      - Add back server-side opacity support for Wayland backend
    * bugfixes
Qtile 0.25.0, released 2024-04-06:
    * features
      - The Battery widget now supports dynamic charge control, allowing for
        protecting battery life.
      - To support the above (plus the other widgets that modify sysfs), qtile
        now ships with its own udev rules, located at
        /resources/99-qtile.rules; distro packagers will probably want to
        install this rule set.
    * bugfixes
      - Fix groups marked with `persist=False` not being deleted when their last window
⇒is moved to another group.

    Fallback icon in StatusNotifier widget

Qtile 0.24.0, released 2024-01-20:
    !!! config breakage/changes !!!
      - Matches no longer use "include/substring" style matching. But match the string
→exactly. Previously on X11, if the WM_TYPE of a spawned window is e.g. dialog a match
→with wm_type dialognoonereadschangelogs would return true. Additionally a window with
\hookrightarrowan empty WM_CLASS (which can happen) would match anything. If you rely this style of
⇒substring matching, pass a regex to your match or use a function with func=.
        Using a list of strings inside Match with role, title, wm_class, wm_instance_
→class, wm_type are also deprecated, use a regex. Right now we replace the property_
→with a regex if it's a list and warn with a deprecation message. You can use "qtile"
→migrate" to migrate your config to this.
    * features
      - Change how `tox` runs tests. See https://docs.qtile.org/en/latest/manual/
→contributing.html#running-tests-locally
      for more information on how to run tests locally.

    Add `ScreenSplit` layout which allows multiple layouts per screen. Also adds.

                                                                            (continues on next page)
```

```
→ `ScreenSplit`
       widget to display name of active split.
      - Updated `Bluetooth` widget which allows users to manage multiple devices in au
→single widget
      - Add `align` option to `Columns` layout so new windows can be added to left or ...
→right column.
      - `.when()` have two new parameters:
        - `func: Callable`: Enable call when the result of the callable evaluates to True
        - `condition: bool`: a boolean value to determine whether the lazy object should.
⇒be run. Unlike `func`, the
          condition is evaluated once when the config file is first loaded.
      - Add ability to have bar drawns over windows by adding `reserve=False` to bar's.
stop the bar reserving screen space.
      - Add ability for third-party code (widgets, layouts) to create hooks
      - Add ability to create user-defined hooks which can be fired from external scripts
    * bugfixes
      - Fix two bugs in stacking transient windows in X11
      - Checking configs containing `qtile.core.name` with `python config.py` don't fail.
→anymore (but `qtile.core.name`
       will be `None`)
      - Fix an error if a wayland xwindow has unknown wm_type
Qtile 0.23.0, released 2023-09-24:
    !!! Dependency Changes !!!
      - xcffib must be upgraded to >= 1.4.0
      - cairocffi must be upgraded to >= 1.6.0
      - New optional dependency `pulsectl-asyncio` required for `PulseVolume` widget
    !!! Notice for packagers - wlroots (optional dependency) bump !!!
      - Qtile's wayland backend now requires on wlroots 0.16 (and pywlroots 0.16)
    !!! config breakage/changes !!!
      - The `cmd_` prefix has been dropped from all commands (this means command names_
→are common when accessed
       via the command interface or internal python objects).

    Custom widgets should now expose command methods with the `@expose_command`_

→decorator (available via
        `from libqtile.command.base import expose_command`).
      - Some commands have been renamed (in addition to dropping the 'cmd_' prefix):
          `hints` -> `get_hints`
          `groups` -> `get_groups`
          `screens` -> `get_screens`
      - Layouts need to rename some methods:
        - `add` to `add_client`
        - `cmd_next` to `next`
        - `cmd_previous` to `previous`
      - Layouts or widgets that redefine the `commands` property need to update the
→signature:
           @expose_command()`
          `def commands(self) -> list[str]:`

    `Window.getsize` has been renamed `Window.get_size` (i.e. merged with the get_

    `Window.getposition` has been renamed `Window.get_position` (i.e. merged with_
```

```
→ the get_position command).

      - The `StockTicker` widget `function` option is being deprecated: rename it to..
→ `func`.
     - The formatting of `NetWidget` has changed, if you use the `format` parameter in
→your config include
       `up_suffix`, `total_suffix` and `down_suffix` to display the respective units.
     - The `Notify` widget now has separate `default_timeout` properties for differenct...
→urgency levels. Previously,
       `default_timeout` was `None` which meant that there was no timeout for all_
→notifications (unless this had been
       set by the client sending the notification). Now, `default_timeout` is for_
→normal urgency notifications and this
       has been set to a default of 10 seconds. `default_timeout_urgent`, for critical_
→notifications, has a timeout of `None`.
     - The `PulseVolume` widget now depends on a third party library, `pulsectl-
→asyncio`, to interact with the pulse audio
       server. Users will now see an `ImportError` until they install that library.
   * features
       - Add ability to set icon size in `LaunchBar` widget.
       - Add 'warp_pointer' option to `Drag` that when set will warp the pointer to the.
→bottom right of
         the window when dragging begins.
       - Add `currentsong` status to `Mpd2` widget.
       - Add ability to disable group toggling in `GroupBox` widget
       - Add ability to have different border color when windows are stacked in Stack.
→layout. Requires
         setting `border_focus_stack` and `border_normal_stack` variables.
       - Add ability to have different single border width for Columns layout by.
⇒setting 'single_border_width' key.
       - Add ability to have different border and margin widths when VerticalTile.
→layout only contains 1 window by
         setting 'single_border_width' and 'single_margin' keys.
       - New widget: GenPollCommand
       - Add `format` and `play_icon` parameters for styling cmus widget.
       - Add ability to add a group at a specified index
       - Add ability to spawn the `WidgetBox` widget opened.
       - Add ability to swap focused window based on index, and change the order of
→windows inside current group
       - Add ability to update the widget only once if `update_interval` is None.
       - Add `move_to_slice` command to move current window to single layout in `Slice`...
→layout
       - Made the `NetWidget` text formattable.
       - Qtile no longer floods the log following X server disconnection, instead.
→handling those errors.
       - `Key` and `KeyChord` bindings now have another argument `swallow`.
         It indicates whether or not the pressed keys should be passed on to the
→focused client.
         By default the keys are not passed (swallowed), so this argument is set to.
→`True`.
         When set to `False`, the keys are passed to the focused client. A key is never.
→swallowed if the
         function is not executed, e.g. due to failing the `.when()` check.
```

```
    Add ability to set custom "Undefined" status key value to `Mpd2Widget`.

        - `Mpd2Widget` now searches for artist name in all similar keys (i.e.
→ `albumartist`, `performer`, etc.).
        - Add svg support to `CustomLayoutIcon`
        - added layering controls for X11 (Wayland support coming soon!):
          - `lazy.window.keep_above()/keep_below()` marks windows to be kept above/below_
→other windows permanently.
             Calling the functions with no arguments toggles the state, otherwise pass.
→ `enable=True` or `enable=False`.
          - `lazy.window.move_up()/move_down()` moves windows up and down the z axis.
          - added `only_focused` setting to Max layout, allowing to draw multiple...
⇒clients on top of each other when
            set to False
        - Add `suspend` hook to run functions before system goes to sleep.
    * bugfixes
        - Fix bug where Window.center() centers window on the wrong screen when using_
→multiple monitors.
        - Fix `Notify` bug when apps close notifications.
        - Fix `CPU` precision bug with specific version of `psutil`
        - Fix config being reevaluated twice during reload (e.g. all hooks from config.
→were doubled)
        - Fix `PulseVolume` high CPU usage when update_interval set to 0.
        - Fix `Battery` widget on FreeBSD without explicit `battery` index given.
        Fix XMonad layout faulty call to nonexistent _shrink_up
        - Fix setting tiled position by mouse for layouts using _SimpleLayoutBase. To_
→support this in other layouts, add a swap method taking two windows.
        - Fix unfullscreening bug in conjunction with Chromium based clients when auto_

→fullscreen is set to `False`.

        - Ensure `CurrentLayoutIcon` expands paths for custom folders.
        - Fix vertical alignment of icons in `TaskList` widget
        - Fix laggy resize/positioning of floating windows in X11 by handling motion.
→notify events later. We also introduced a cap setting if you want to limit these.
→events further, e.g. for limiting resource usage. This is configurable with the x11_
→drag_polling_rate variable for each `Screen` which is set to None by default,
→indicating no cap.
    * python version support
        - We have added support for python 3.11 and pypy 3.9.
        - python 3.7, 3.8 and pypy 3.7 are not longer supported.
        - Fix bug where `StatusNotifier` does not update icons
Qtile 0.22.0, released 2022-09-22:
    !!! Config breakage !!!
        - lazy.qtile.display_kb() no longer receives any arguments. If you passed it any_
→arguments
          (which were ignored previously), remove them.
        - If you have a custom startup Python script that you use instead of `qtile_
→start` and run init_log
         manually, the signature has changed. Please check the source for the updated
→arguments.
        - `KeyChord`'s signature has changed. ``mode`` is now a boolean to indicate...
→whether the mode should persist.
          The ``name`` parameter should be used to name the chord (e.g. for the
```

```
→ ``Chord`` widget).
    * features
        - Add ability to draw borders and add margins to the `Max` layout.
        - The default XWayland cursor is now set at startup to left_ptr, so an xsetroot_
→call is not needed to
          avoid the ugly X cursor.
        - Wayland: primary clipboard should now behave same way as with X after.
⇒selecting something it
          should be copied into clipboard
        - Add `resume` hook when computer resumes from sleep/suspend/hibernate.
        Add `text_only` option for `LaunchBar` widget.
        - Add `force_update` command to `ThreadPoolText` widgets to simplify updating_
→from key bindings
        - Add scrolling ability to `_TextBox`-based widgets.
        - Add player controls (via mouse callbacks) to `Mpris2` widget.
        - Wayland: input inhibitor protocol support added (pywayland>=0.4.14 & pywlroots>
\rightarrow = 0.15.19
        - Add commands to control Pomodoro widget.
        - Add icon theme support to `TaskList` widget (available on X11 and Wayland...
→backends).
        - Wayland: Use `qtile cmd-obj -o core -f get_inputs` to get input device_
          configuring inputs. Also input configs will be updated by config reloads.
\hookrightarrow (pywlroots>=0.15.21)
    * bugfixes
        - Widgets that are incompatible with a backend (e.g. Systray on Wayland) will no.
→longer show
          as a ConfigError in the bar. Instead the widget is silently removed from the
→bar and a message
          included in the logs.
        - Reduce error messages in `StatusNotifier` widget from certain apps.
        - Reset colours in `Chord` widget
        - Prevent crash in `LaunchBar` when using SVG icons
        - Improve scrolling in `Mpris2` widget (options to repeat scrolling etc.)
Qtile 0.21.0, released 2022-03-23:
    * features
        - Add `lazy.window.center()` command to center a floating window on the screen.
        - Wayland: added power-output-management-v1 protocol support, added idle__
⇒protocol,
          added idle inhibit protocol
        - Add MonadThreeCol layout based on XMonad's ThreeColumns.
        Add `lazy.screen.set_wallpaper` command.
        - Added ability to scale the battery icon's size
        - Add Spiral layout
        - Add `toggle` argument to `Window.togroup` with the same functionality as in_
→ `Group.toscreen`.
        - Added `margin_on_single` and `border_on_single` to Bsp layout
    * bugfixes
        - Fix `Systray` crash on `reconfigure_screens`.
        - Fix bug where widgets can't be mirrored in same bar.
        - Fix various issues with setting fullscreen windows floating and vice versa.
```

 Fix a bug where a .when() check for lazy functions errors out when matching on focused windows when none is focused. By default we do not match on focused. →windows,

to change this set `if_no_focused` to True.

- - Fix resizing of wallpaper when screen scale changes (X11)
 - Two small bugfixes for `StatusNotifier` better handling of Ayatana indicators
- Fix bug where StatusNotifierItem crashes due to invalid object paths (e.g., \angle Zoom)

Qtile 0.20.0, released 2022-01-24:

- * features
- Add `place_right` option in the TreeTab layout to place the tab panel on the →right side
- X11: Add support for _NET_DESKTOP_VIEWPORT. E.g. can be used by rofi to map on _ current output.
- Wayland: Bump wlroots version. 0.15.x wlroots and 0.15.2+ pywlroots are \rightarrow required.
- Add XWayland support to the Wayland backend. XWayland will start up as needed, \Box \to if it is installed.
 - * bugfixes
- Remove non-commandable windows from IPC. Fixes bug where IPC would fail when → trying to get info
 - on all windows but Systray has icons (which are non-commandable `_Window`s.)
 - Fix bug where bars were not reconfigured correctly when screen layout changes.
- Fix a Wayland bug where layer-shell surface like dunst would freeze up and stop updating.
- Change timing of `screens_reconfigured` hook. Will now be called ONLY if `cmd_
 -reconfigure_screens`

has been called and completed.

- Fix order of icons in Systray widget when restarting/reloading config.
- Fix rounding error in PulseVolume widget's reported volume.
- Fix bug where Volume widget did not load images where `theme_path` had been_ ⇒set in `widget_defaults`.
- - ConfigError.
- - managers to request the name.
- Fix bug where `Battery` widget did not retrieve `background` from `widget_ →defaults`.
 - Fix bug where widgets in a `WidgetBox` are rendered on top of bar borders.
- Add ability to swap focused window based on index, and change the order of windows inside current group Qtile 0.19.0, released 2021-12-22:
 - * features
 - Add ability to draw borders to the Bar. Can customise size and colour per edge.
- Add `StatusNotifier` widget implementing the `StatusNotifierItem` ⊔ ⇒ specification.

- NB Widget does not provide context menus.
- Add `total` bandwidth format value to the Net widget.
- Scratchpad groups could be defined as single so that only one of the u→scratchpad in the group is visible
 - at a given time.
 - All scratchpads in a Scratchpad group can be hidden with hide_all() function.
 - For saving states of scratchpads during restart, we use wids instead of pids.
- Scratchpads can now be defined with an optional matcher to match with window_ → properties.
- `Qtile.cmd_reload_config` is added for reloading the config without completely_ →restarting.
 - Window.cmd_togroup's argument `groupName` should be changed to `group_name`. For the time being a log warning is in place and a migration is added. In the future `groupName` will fail.
- Add `min/max_ratio` to Tile layout and fix bug where windows can extend.
 →offscreen.
- Add ability for widget `mouse_callbacks` to take `lazy` calls (similar to∟ ⇒keybindings)
- Add `aliases` to `lazy.spawncmd()` which takes a dictionary mapping convenient.
 →aliases
 - to full command lines.
- Add a new 'prefix' option to the net widget to display speeds with a static ω unit (e.g. MB).
- `lazy.group.toscreen()` now does not toggle groups by default. To get this ⇒behaviour back, use
 - `lazy.group.toscreen(toggle=True)`
 - Tile layout has new `margin_on_single` and `border_on_single` option to specify whether to draw margin and border when there is only one window.
 - Thermal zone widget.
 - Allow TextBox-based widgets to display in vertical bars.
- - Allow to update Image widget with update() function by giving a new path.
 * bugfixes

Qtile 0.18.1, released 2021-09-16:

- * features
 - All layouts will accept a list of colors for border_* options with which they will draw multiple borders on the appropriate windows.

Qtile 0.18.0, released 2021-07-04:

- !!! Config breakage !!!
 - The `qtile` entry point doesn't run `qtile start` by default anymore
 - New optional dependency for dbus related features: dbus-next.
 Replaces previous reliance on dbus/Glib and allows qtile to use async dbus calls within asyncio's eventloop.
 - widget.BatteryIcon no longer has a fallback text mode; use widget.Battery instead
 - MonadX layout key new_at_current is deprecated, use new_client_position.
 - `libqtile.window` has been moved to `libqtile.backend.x11.window`; a migration.

```
→has been added for this.
    !!! deprecation warning !!!
        - 'main' config functions, deprecated in 0.16.1, will no longer be executed.
    !!! Notice for packagers - new dependencies !!!
        - Tests now require the 'dbus-next' python module plus 'dbus-launch' and 'notify-
→send' applications
    * features
        - added transparency in x11 and wayland backends
        - added measure_mem and measure_swap attributes to memory widget to allow user_
→to choose measurement units.
        - memory widget can now be displayed with decimal values
        - new "qtile migrate" command, which will attempt to upgrade previous
          configs to the current version in the case of qtile API breaks.
        - A new `reconfigure_screens` config setting. When `True` (default) it
          hooks `Qtile.reconfigure_screens` to the `screen_change` hook,
          reconfiguring gtile's screens in response to randr events. This
          removes the need to restart qtile when adding/removing external
          monitors.
        improved key chord / sequence functionality. Leaving a chord with `mode`
          set brings you to a named mode you activated before, see #2264.
          A new command, `lazy.ungrab_all_chords`, was introduced to return to the root...
⇒bindinas.
          The `enter_chord` hook is now always called with a string argument.
          The third argument to `KeyChord` was renamed from `submapping` to `submapping` __
\hookrightarrow (typo fix).
        - added new argument for CheckUpdates widget: `custom_command_modify` which_
→allows user to modify the
          the line count of the output of `custom_command` with a lambda function (i.e._
\rightarrow lambda x: x-3).
          Argument defaults to `lambda x: x` and is overridden by `distro` argument's...
→internal lambda.

    added new argument for the WindowName, WindowTabs and Tasklist widgets: `parse_

→text` which allows users to
          define a function that takes a window name as an input, modify it in some way.
→(e.g. str.replace(), str.upper() or regex)
          and show that modification on screen.
        - A Wayland backend has been added which can be used by calling `qtile start -b..
→wayland` directly in your TTY.
         It requires the latest releases of wlroots, python-xkbcommon, pywayland and
→pywlroots. It is expected to be
          unstable so please let us know if you find any bugs!
        - The 'focus' argument to 'Click' and 'Drag' objects in your config are no.
→longer necessary (and are ignored).
Qtile 0.17.0, released 2021-02-13:
    !!! Python version breakage !!!
        - Python 3.5 and 3.6 are no longer supported
    !!! Config breakage !!!
        - Pacman widget has been removed. Use CheckUpdates instead.
        - Mpris widget has been removed. Use Mpris2 instead.
        - property "masterWindows" of Tile layout renamed to master_length
        - Match objects now only allow one string argument for their wm
```

```
name/class/etc. properties. to update your config, do e.g.
                  Group('www', spawn='firefox', layout='xmonad',
                        matches=[Match(wm_class=['Firefox', 'google-chrome', 'Google-
→chrome'])]),
                        matches=[Match(wm_class='Firefox'), Match(wm_class='google-
- properties wname, wmclass and role of Slice-layout replaced by Match-
         type property "match"
       - rules specified in `layout.Floating`'s `float_rules` are now evaluated with
         AND-semantics instead of OR-semantics, i.e. if you specify 2 different
         property rules, both have to match
       - check the new `float_rules` for `floating_layout` in the default config and
         extend your own rules appropriately: some non-configurable auto-floating rules
         were made explicit and added to the default config
       - using `dict`s for `layout.Floating`'s `float_rules` is now deprecated, please
         use `config.Match` objects instead
       - `no_reposition_match` in `layout.Floating` has been removed; use the list of
          config.Match`-objects `no_reposition_rules` instead
       - Command line has been modernized to a single entry point, the `qtile`
         binary. Translations are below:
               qtile
                         -> qtile start
               qtile-cmd -> qtile cmd-obj
               qtile-run -> qtile run-cmd
               qtile-top -> qtile top
               qshell
                         -> qtile shell
         iqshell and dqtile-cmd are no longer distributed with the
         package, as they were either user or developer scripts. Both are
         still available in the qtile repo in /scripts.
         Running `qtile` without arguments will continue to work for the
         forseeable future, but will be eventually deprecated. qtile prints a
         warning when run in this configuration.

    Otile.cmd_focus_by_click is no longer an available command.

       - Qtile.cmd_get_info is no longer an available command.
       - libqtile.command_* has been deprecated, it has been moved to
         libqtile.command.*
       - libqtile.widget.base.ThreadedPollText has been removed; out of tree
         widgets can use ThreadPoolText in the same package instead.
       - the YahooWeather widget was removed since Yahoo retired their free
         tier of the weather API
       - Deprecated hook `window_name_change` got removed, use
         `client_name_updated` instead.
       - show_state attribute from WindowName widget has been removed. Use format_
→attribute instead.
               show_state = True -> format = '{state}{name}'
               show_state = False -> format = '{name}'
       - mouse_callbacks no longer receives the qtile object as an argument
         (they receive no arguments); import it via `from libqtile import
         qtile` instead.
   * features

    new WidgetBox widget

       - new restart and shutdown hooks
                                                                          (continues on next page)
```

- rules specified in `layout.Floating`'s `float_rules` are now evaluated with AND-semantics, allowing for more complex and specific rules
- Python 3.9 support
- switch to Github Actions for CI
- Columns layout has new `margin_on_single` option to specify margin size when there is only one window (default -1: use `margin` option).
- new OpenWeather widget to replace YahooWeather
- new format attribute for WindowName widget
- new max_chars attribute for WindowName widget
- libqtile now exports type information
- add a new `qtile check` subcommand, which will check qtile configs for various things:
 - validates configs against the newly exported type information if mypy is present in the environment
 - validates that qtile can import the config file (e.g. that syntax is correct, ends in a .py extension, etc.)
 - validates Key and Mouse mod/keysym arguments are ok.
- Columns layout now enables column swapping by using swap_column_left and swap_

 → column_right
 - !!! warning !!!
 - When (re)starting, Qtile passes its state to the new process in a file now, where previously it passed state directly as a string. This fixes a bug where some character encodings (i.e. in group names) were getting messed up in the conversion to/from said string. This change will cause issues if you update Qtile then restart it, causing the running old version to pass state in the previous format to the new process which recognises the new.

Qtile 0.16.1, released 2020-08-11:

- !!! Config breakage !!!
 - Hooks 'addgroup', 'delgroup' and 'screen_change' will no longer receive the qtile object as an argument. It can be accessed directly at libqtile.qtile.
- !!! deprecation warning !!!
 - defining a main function in your config is deprecated. You should use @hook.subscribe.startup_complete instead. If you need access to the qtile object, import it from libqtile directly.
- * bugfixes
 - include tests in the release for distros to consume
 - don't resize Oth screen incorrectly on root ConfigureNotify
 - expose qtile object as libqtile.qtile (note that we still consider anything not prefixed with cmd_ to be a private API)
 - fix transparent borders
 - MonadTall, MonadWide, and TreeTab now work with Slice

Qtile 0.16.0, released 2020-07-20:

- !!! Config breakage !!!
 - Imports from libqtile.widget are now made through a function proxy to avoid the side effects of importing all widgets at once. If you subclass a widget in your config, import it from its own module.
 - e.g. from libqtile.widget.pomodoro import Pomodoro

```
* features
        added `guess_terminal` in utils
        - added keybinding cheet sheet image generator

    custom keyboardlayout display

        - added native support for key chords
        - validate config before restart and refuse to restart with a bad
        - added a bunch of type annotations to config objects (more to come)
    * bugfixes
        - major focus rework; Java-based IDEs such as PyCharm, NetBrains, etc.
          now focus correctly
        - fix a bug where spotify (or any window with focus-to=parent) was
          closed, nothing would be focused and no hotkeys would work
        - support windows unsetting the input hint
        - respects window's/user's location setting if present (WM_SIZE_HINTS)
        - fixed YahooWeather widget for new API
        - fix a bug where _NET_WM_DESKTOPS wasn't correctly updated when
          switching screens in some cases
        - fix a crash in the BSP layout
        - fix a stacktrace when unknown keysyms are encounted
        - make qtile --version output more sane
        - fix a rendering issue with special characters in window names
        - keyboard widget no longer re-sets the keyboard settings every second
        - fix qtile-top with the new IPC model
        - Image widget respects its background setting now
        - correctly re-draw non-focused screens on gtile restart
        - fix a crash when decoding images
        - fix the .when() constraint for lazy objects
Qtile 0.15.1, released 2020-04-14
    * bugfixes

    fix qtile reload (it was crashing)

Qtile 0.15.0, released 2020-04-12:
    !!! Config breakage !!!
        - removed the mpd widget, which depended on python-mpd.
        - the Clock widget now requires pytz to handle timezones that are
          passed as string
        - libgtile.command.Client does not exist anymore and has been
          replaced by libgtile.command_client.CommandClient
    !!! deprecation warning !!!
        - libqtile.command.lazy is deprecated in favor of libqtile.lazy.lazy
    * features
        - Python 3.8 support
        - `wallpaper` and `wallpaper_mode` for screens
        - bars can now have margins
        - `lazy.toscreen` called twice will now toggle the groups
          (optional with the `toggle` parameter)
        - `lazy.window.togroup` now has `switch_group` parameter to follow
          the window to the group it is sent to
        - qtile now copies the default config if the config file does not exist
        - all widgets now use Pango markup by default
```

 add an `fmt` option for all textbox widgets new PulseVolume widget for controlling PulseAudio - new QuickExit widget, mainly for the default config - new non-graph CPU widget - KeyboardLayout widget: new `options` parameter - CheckUpdates widget: support ArchLinux yay - GroupBox widget: new `block_highlight_text_color` parameter - Mpd2 widget: new `color_progress` parameter - Maildir widget can now display the inbox grand total - the Net widget can now use bits as unit Spacer widget: new `background_color` parameter - More consistent resize behavior in Columns layout - various improvements of the default config - large documentation update and improvements (e.g. widget dependencies) * bugfixes - qtile binary: don't fail if we can't set the locale - don't print help if qtile-cmd function returns nothing - Monad layout: fix margins when flipped Qtile 0.14.2, released 2019-06-19: * buafixes - previous release still exhibited same issues with package data, really fix it this time Qtile 0.14.1, released 2019-06-19: * bugfixes - properly include png files in the package data to install included icons Qtile 0.14.0, released 2019-06-19: !!! Python version breakage !!! - Python 2 is no longer supported - Python 3.4 and older is no longer supported !!! Config breakage !!! - Many internal things were renamed from camel case to snake case. If your config uses main(), or any lazy.function() invocations that interact directly with the qtile object, you may need to forward port them. Also note that we do *not* consider the qtile object to be a stable api, so you will need to continue forward porting these things for future refactorings (for wayland, etc.). A better approach may be to add an upstream API for what you want to do ;) - Maildir's subFolder and maildirPath changed to maildir_path and sub_folder. - the graph widget requires the psutil library to be installed * features - add custom `change_command` to backlight widget - add CommandSet extension to list available commands - simplify battery monitoring widget interface and add freebsd compatible battery widget implementation - track last known mouse coordinates on the qtile manager - allow configuration of warping behavior in columns layout

(continues on next page)

474

* bugfixes

- with cursor warp enabled, the cursor is warped on screen change
- fix stepping groups to skip the scratch pad group
- fix stack layout to properly shuffle
- silence errors when unmapping windows

Qtile 0.13.0, released 2018-12-23:

!!! deprecation warning !!!

 wmii layout is deprecated in terms of columns layout, which has the same behavior with different defaults, see the wmii definition for more details

* features

- add svg handling for images
- allow addgroup command to set the layout
- add command to get current log level
- allow groupbox to hide unused groups
- add caps lock indicator widget
- add custom_command to check_update widget

* bugfixes

- better shutdown handling
- fix clientlist current client tracking
- fix typo in up command on ratiotile layout
- various fixes to check_update widget
- fix 0 case for resize screen

Qtile 0.12.0, released 2018-07-20:

!!! Config breakage !!!

- Tile layout commands up/down/shuffle_up/shuffle_down changed to be more consistent with other layouts
- move qcmd to qtile-cmd because of conflict with renameutils, move dqcmd to dqtile-cmd for symmetry

* features

- add `add_after_last` option to Tile layout to add windows to the end of the list.
- add new formatting options to TaskList
- allow Volume to open app on right click

* bugfixes

- fix floating of file transfer windows and java drop-downs
- fix exception when calling `cmd_next` and `cmd_previous` on layout without windows
- fix caps lock affected behaviour of key bindings
- re-create cache dir if it is deleted while qtile is running
- fix CheckUpdates widget color when no updates
- handle cases where BAT_DIR does not exist
- fix the wallpaper widget when using `wallpaper_command`
- fix Tile layout order to not reverse on reset
- fix calling `focus_previous/next` with no windows
- fix floating bug is BSP layout

Otile 0.11.1, released 2018-03-01:

* bug fix

- fixed pip install of qtile

```
Qtile 0.11.0, released 2018-02-28:
    !!! Completely changed extension configuration, see the documentation !!!
    !!! `extention` subpackage renamed to `extension` !!!
    !!! `extentions` configuration variable changed to `extension_defaults` !!!
    * features
        - qshell improvements
        - new MonadWide layout
        - new Bsp layout
        - new pomodoro widget
        - new stock ticker widget
        - new `client_name_updated` hook
        - new RunCommand and J4DmenuDesktop extension
        - task list expands to fill space, configurable via `spacing` parameter
        - add group.focus_by_name() and group.info_by_name()
        - add disk usage ratio to df widget
        - allow displayed group name to differ from group name
        - enable custom TaskList icon size
        - add qcmd and dqcmd to extend functionality around qtile.command
          functionality
        - add ScratchPad group that has configurable drop downs
    * buafixes
        - fix race condition in Window.fullscreen
        - fix for string formatting in gtile top
        - fix unicode literal in tasklist
        - move mpris2 initialization out of constructor
        - fix wlan widget variable naming and division
        - normalize behavior of layouts on various commands
        - add better fallback to default config
        - update btc widget to use coinbase
        - fix cursor warp when using default layout implementation
        - don't crash when using widget with unmet dependencies
        - fix floating window default location
Otile 0.10.7, released 2017-02-14:
    * features
        - new MPD widget, widget.MPD2, based on `mpd2` library
        - add option to ignore duplicates in prompt widget
        - add additional margin options to GroupBox widget
        - add option to ignore mouse wheel to GroupBox widget
        - add `watts` formatting string option to Battery widgets
        - add volume commands to Volume widget
        - add Window.focus command
    * bugfixes
        - place transient windows in the middle of their parents
        - fix TreeTab layout
        - fix CurrentLayoutIcon in Python 3
        - fix xcb handling for xcffib 0.5.0
        - fix bug in Screen.resize
        - fix Qtile.display_kb command
Qtile 0.10.6, released 2016-05-24:
```

```
!!! qsh renamed to qshell !!!
        This avoids name collision with other packages
    * features
        - Test framework changed to pytest
        - Add `startup_complete` hook
    * bugfixes
        - Restore dynamic groups on restart
        - Correct placement of transient_for windows
        - Major bug fixes with floating window handling
    * file path changes (XDG Base Directory specification)
        - the default log file path changed from ~/.qtile.log to
          ~/.local/share/qtile/qtile.log
        - the cache directory changed from ~/.cache to ~/.cache/qtile
        - the prompt widget's history file changed from ~/.qtile_history to
          ~/.cache/qtile/prompt_history
Qtile 0.10.5, released 2016-03-06:
    !!! Python 3.2 support dropped !!!
    !!! GoogleCalendar widget dropped for KhalCalendar widget !!!
    !!! qtile-session script removed in favor of qtile script !!!
    * features
        - new Columns layout, composed of dynamic and configurable columns of
          windows
        - new iPython kernel for qsh, called iqsh, see docs for installing
        - new qsh command `display_kb` to show current key binding
        - add json interface to IPC server
        - add commands for resizing MonadTall main panel
        - wlan widget shows when you are disconnected and uses a configurable
          format
    * bugfixes
        - fix path handling in PromptWidget

    fix KeyboardLayout widget cycling keyboard

        - properly guard against setting screen to too large screen index
Otile 0.10.4, released 2016-01-19:
    !!! Config breakage !!!
        - positional arguments to Slice layout removed, now `side` and `width`
          must be passed in as keyword arguments

    add alt coin support to BitcoinTracker widget

    * buafixes
        - don't use six.moves assignment (fix for >=setuptools-19.3)
        - improved floating and fullscreen handling
        - support empty or non-charging secondary battery in BatteryWidget
        - fix GoogleCalendar widget crash
Qtile 0.10.3, released 2015-12-25:
    * features
        - add wmii layout
        - add BSD support to graph widgets
    * bugfixes
        - fix (some) fullscreen problems
```

```
- update google calendar widget to latest google api
        - improve multiple keyboard layout support
        - fix displaying Systray widget on secondary monitor
        - fix spawn file descriptor handling in Python 3
        remove duplicate assert code in test_verticaltile.py
        - allow padding_{x,y} and margin_{x,y} widget attrs to be set to 0
Qtile 0.10.2, released 2015-10-19:
    * features
        - add qtile-top memory monitoring
        - GroupBox can set visible groups
        - new GroupBox highlighting, line
        - allow window state to be hidden on WindowName widget
        - cmd_togroup can move to current group when None sent
        - added MOC playback widget
        - added memory usage widget
        - log truncation, max log size, and number of log backups configurable
        - add a command to change to specific layout index
          (lazy.to_layout_index(index))
    * bugfixes
        - fixed memory leak in dgroups
        - margin fixes for MonalTall layout

    improved cursor warp

        - remove deprecated imp for Python >= 3.3
        - properly close file for NetGraph
        - fix MondadTall layout grow/shrink secondary panes for Python 2
        - Clock widget uses datetime.now() rather than .fromtimestamp()
        - fix Python 3 compatibility of ThermalSensor widget
        - various Systray fixes, including implementing XEMBED protocol
        - print exception to log during loading config
        - fixed xmonad layout margins between main and secondary panes
        - clear last window name from group widgets when closed

    add toggleable window border to single xmonad layout

    * config breakage
        - layouts.VerticalTile `windows` is now `clients`
        - layouts. VerticalTile focus_next/focus_previous now take a single
          argument, similar to other layouts
Qtile 0.10.1, released 2015-07-08:
    This release fixes a problem that made the PyPI package uninstallable,
   qtile will work with a pip install now
Qtile 0.10.0, released 2015-07-07:
    !!! Config breakage !!!
        - various deprecated commands have been removed:
            Screen.cmd_nextgroup: use cmd_next_group
            Screen.cmd_prevgroup: use cmd_prev_group
            Qtile.cmd_nextlayout: use cmd_next_layout
            Qtile.cmd_prevlayout: use cmd_prev_layout
            Otile.cmd_to_next_screen: use cmd_next_screen
            Qtile.cmd_to_prev_screen: use cmd_prev_screen

    Clock widget: remove fmt kwarg, use format kwarg
```

- GmailChecker widget: remove settings parameter
- Maildir widget: remove maildirPath, subFolders, and separator kwargs
- * Dependency updates
 - cffi>=1.1 is now required, along with xcffib>=0.3 and cairocffi>=0.7
 (the cffi 1.0 compatible versions of each)
 - Care must be taken that xcffib is installed *before* cairocffi
- * features
 - add support for themed cursors using xcb-cursor if available
 - add CheckUpdate widget, for checking package updates, this deprecates the Pacman widget
 - add KeyboardKbdd widget, for changing keyboard layouts
 - add Cmus widget, for showing song playing in cmus
 - add Wallpaper widget, for showing and cycling wallpaper
 - add EzConfig classes allowing shortcuts to define key bindings
 - allow GroupBox urgent highlighting through text
 - Bar can be placed vertically on sides of screens (widgets must be adapted for vertical viewing)
 - add recognizing brightness keys
- * bugfixes
 - deprecation warnings were not printing to logs, this has been fixed
 - fix calculation of y property of Gap
 - fix focus after closing floating windows and floating windows
 - fix various Python 3 related int/float problems
 - remember screen focus across restarts
 - handle length 1 list passed to Drawer.set_source_rgb without raising divide by zero error
 - properly close files opened in Graph widget
 - handle _NET_WM_STATE_DEMANDS_ATTENTION as setting urgency
 - fix get_wm_transient_for, request WINDOW, not ATOM

Qtile 0.9.1, released 2015-02-13:

This is primarily a unicode bugfix release for 0.9.0; there were several nits related to the python2/3 unicode conversion that were simply wrong. This release also adds license headers to each file, which is necessary for distro maintainers to package Qtile.

- * bugfixes
 - fix python2's importing of gobject
 - fix unicode handling in several places

Qtile 0.9.0, released 2015-01-20:

* !!! Dependency Changes !!!

New dependencies will need to be installed for Qtile to work

- drop xpyb for xcffib (XCB bindings)
- drop py2cairo for cairocffi (Cairo bindings)
- drop PyGTK for asyncio (event loop, pangocairo bindings managed internally)
- Qtile still depends on gobject if you want to use anything that uses dbus (e.g. the mpris widgets or the libnotify widget)
- * features
 - add Python 3 and pypy support (made possible by dependency changes)
 - new layout for vertical monitors
 - add startup_once hook, which is called exactly once per session (i.e.

- it is not called when qtile is restarted via lazy.restart()). This eliminates the need for the execute_once() function found in lots of user configs.
- add a command for showing/hiding the bar (lazy.hide_show_bar())
- warn when a widget's dependencies cannot be imported
- make qtile.log more useful via better warnings in general, including deprecation and various other warnings that were previously nonexistent
- new text-polling widget super classes, which enable easy implementation of various widgets that need to poll things outside the event loop.
- add man pages
- large documentation update, widget/layout documentation is now autogenerated from the docstrings
- new ImapWidget for checking imap mailboxes

* bugfixes

- change default wmname to "LG3D" (this prevents some java apps from not working out of the box)
- all code passes flake8
- default log level is now WARNING
- all widgets now use our config framework
- windows with the "About" role float by default
- got rid of a bunch of unnecessary bare except: clauses

Qtile 0.8.0, released 2014-08-18:

* features

- massive widget/layout documentation update
- new widget debuginfo for use in Qtile development
- stack has new autosplit, fair options
- matrix, ratiotile, stack, xmonad, zoomy get 'margin' option
- new launchbar widget
- support for matching WM_CLASS and pid in Match
- add support for adding dgroups rules dynamically and via ipc
- Clock supports non-system timezones
- new mpris2 widget
- volume widget can use emoji instead of numbers
- add an 'eval' function to qsh at every object level
- bar gradients support more colors
- new Clipboard widget (very handy!)

* bugfixes

- bitcoin ticker widget switched from MtGox (dead) to btc-e
- all widgets now use Qtile's defaults system, so their defaults are settable globally, etc.
- fix behavior when screens are cloned
- all widgets use a unified polling framework
- "dialog" WM_TYPEs float by default
- respect xrandr --primary
- use a consistent font size in the default config
- default config supports mouse movements and floating
- fix a bug where the bar was not redrawn correctly in some multiscreen environments
- add travis-ci support and make tests vastly more robust

```
* config breakage
        - libqtile.layout.Stack's `stacks` parameter is now `num_stacks`
Qtile 0.7.0, released 2014-03-30:
    * features
        - new disk free percentage widget
        - new widget to display static image
        - per core CPU graphs
        - add "screen affinity" in dynamic groups

    volume widget changes volume linear-ly instead of log-ly

        - only draw bar when idle, vastly reducing the number of bar draws and
          speeding things up
        - new Gmail widget
        - Tile now supports automatically managing master windows via the
          `master_match` parameter.
        - include support for minimum height, width, size increment hints
    * bugfixes
        - don't crash on any exception in main loop
        - don't crash on exceptions in hooks
        - fix a ZeroDivisionError in CPU graph
        - remove a lot of duplicate and unused code
        - Steam windows are placed more correctly
        - Fixed several crashes in qsh
        - performance improvements for some layouts
        - keyboard layout widget behaves better with multiple keyboard
          configurations
    * config breakage
        - Tile's shuffleMatch is renamed to resetMaster
Qtile 0.6, released 2013-05-11:
    !!! Config breakage !!!
    This release breaks your config file in several ways:
        - The Textbox widget no longer takes a ``name'' positional parameter,
          since it was redundant; you can use the ``name'' kwarg to define it.
        - manager.Group (now _Group) is not used to configure groups any more;
          config.Group replaces it. For simple configurations (i.e.
          Group("a") type configs), this should be a drop in replacement.
          config. Group also provides many more options for showing and hiding
          groups, assigning windows to groups by default, etc.
        - The Key, Screen, Drag, and Click objects have moved from the manager
          module to the config module.
        - The Match object has moved from the dgroups module to the config
          module.
        - The addgroup hook now takes two parameters: the qtile object and the
          name of the group added:
              @hook.subscribe
              def addgroup_hook(qtile, name):
        - The nextgroup and prevgroup commands are now on Screen instead of
   For most people, you should be able to just:
        sed -i -e 's/libqtile.manager/libqtile.config' config.py
```

```
...dgroups users will need to go to a bit more work, but hopefully
    configuration will be much simpler now for new users.
    * features
        - New widgets: task list,
        - New layout: Matrix

    Added ability to drag and drop groups on GroupBox

        - added "next urgent window" command
        - added font shadowing on widgets
        - maildir widget supports multiple folders
        - new config option log_level to set logging level (any of
          logging.{DEBUG, INFO, WARNING, ERROR, CRITICAL})
        - add option to battery widget to hide while level is above a certain
          amount
        - vastly simplify configuration of dynamic groups
        - MPD widget now supports lots of metadata options
    * bugfixes
        - don't crash on restart when the config has errors
        - save layout and selected group state on restart
        - varous EWMH properties implemented correctly
        - fix non-black systray icon backgrounds
        - drastically reduce the number of timeout_add calls in most widgets
        - restart on RandR attach events to allow for new screens
        - log level defaults to ERROR
        - default config options are no longer initialized when users define
          their corresponding option (preventing duplicate widgets, etc.)
        don't try to load config in qsh (not used)
        - fix font alignment across Textbox based widgets
Qtile 0.5, released 2012-11-11:
    (Note, this is not complete! Many, many changes have gone in to 0.5, by a
    large number of contributors. Thanks to everyone who reported a bug or
    fixed one!)
    * features
        - Test framework is now nose
        - Documentation is now in sphinx
        - Several install guides for various OSes
        - New widgets: battery based icon, MPRIS1, canto, current layout, yahoo
          weather, sensors, screen brightness, notifiy, pacman, windowtabs,
          she, crashme, wifi.
        - Several improvements to old widgets (e.g. battery widget displays low
          battery in red, GroupBox now has a better indication of which screen
          has focus in multi-screen setups, improvements to Prompt, etc.)
        - Desktop notification service.
        - More sane way to handle configuration files
        - Promote dgroups to a first class entity in libqtile
        - Allow layouts to be named on an instance level, so you can:
            layouts = [
                # a layout just for gimp
                layout.Slice('left', 192, name='gimp', role='gimp-toolbox',
                    fallback=layout.Slice('right', 256, role='gimp-dock',
                    fallback=layout.Stack(stacks=1, **border_args)))
            ]
```

```
dynamic_groups = { 'gimp': {'layout': 'gimp'} }
            Dgroups(..., dynamic_groups, ...)
        - New Layout: Zoomy
        - Add a session manager to re-exec qtile if things go south

    Support for WM_TAKE_FOCUS protocol

        - Basic .desktop file for support in login managers
        - Qsh reconnects after qtile is restarted from within it
        - Textbox supports pango markup
        - Examples moved to qtile-examples repository.
    * bugfixes
        - Fix several classes of X races in a more sane way
        - Minor typo fixes to most widgets
        - Fix several crashes when drawing systray icons too early
        - Create directories for qtile socket as necessary
        - PEP8 formatting updates (though we're not totally there yet)
        - All unit tests pass
        - Lots of bugfixes to MonadTall
        - Create IPC socket directory if necessary
        - Better error if two widgets have STRETCH length
        - Autofloat window classes can now be overridden
        - xkeysyms updated
# vim :set ts=4 sw=4 sts=4 et :
```

INDEX

Symbols _Group (class in libqtile.group), 294	charge_dynamically() (libqtile.widget.battery.Battery method), 303
_window_mask() (libqtile.widget.systray.Systray method), 377	charge_to_full() (libqtile.widget.battery.Battery method), 303
A	CheckUpdates (class in libqtile.widget.check_updates), 311
add() (libqtile.layout.matrix.Matrix method), 258 add() (libqtile.layout.stack.Stack method), 280 add_rule() (libqtile.core.manager.Qtile method), 244 add_section() (libqtile.layout.tree.TreeTab method),	Chord (class in libqtile.widget.chord), 312 clear() (libqtile.widget.notify.Notify method), 355 click() (libqtile.widget.bluetooth.Bluetooth method), 306 click() (libqtile.widget.redshift.Redshift method), 366 client_focus() (libqtile.hook.subscribe method), 205 client_killed() (libqtile.hook.subscribe method), 206 client_managed() (libqtile.hook.subscribe method), 206
В	client_mouse_enter() (libqtile.hook.subscribe method), 206
Backlight (class in libqtile.widget.backlight), 302 Bar (class in libqtile.bar), 298 Battery (class in libqtile.widget.battery), 303 BatteryIcon (class in libqtile.widget.battery), 304 Bluetooth (class in libqtile.widget.bluetooth), 305	client_name_updated() (libqtile.hook.subscribe method), 206 client_new() (libqtile.hook.subscribe method), 207 client_to_next() (libqtile.layout.stack.Stack method), 280
bring_to_front() (libqtile.backend.base.window.Windownethod), 290	"client_to_previous() (libqtile.layout.stack.Stack method), 280
bring_to_front() (libqtile.widget.systray.Systray method), 377	client_to_stack() (libqtile.layout.stack.Stack method), 280
Bsp (class in libqtile.layout.bsp), 251	<pre>client_urgent_hint_changed()</pre>
C Canto (class in libqtile.widget.canto), 309	(libqtile.hook.subscribe method), 207 Clipboard (class in libqtile.widget.clipboard), 313 Clock (class in libqtile.widget.clock), 315
CapsNumLockIndicator (class in libqtile.widget.caps_num_lock_indicator),	close() (libqtile.widget.widgetbox.WidgetBox method), 389
310 center() (libqtile.backend.base.window.Window method), 290	Cmus (class in libqtile.widget.cmus), 316 collapse_branch() (libqtile.layout.tree.TreeTab method), 284
<pre>change_backlight() (libqtile.widget.backlight.Backlight</pre>	
method), 400 change_window_order() (libqtile.core.manager.Qtile method), 244 changegroup() (libqtile.hook.subscribe method), 205	commands() (libqtile.backend.wayland.core.Core method), 400 commands() (libqtile.backend.x11.core.Core method), 399
caracteristics (modification), 200	3//

commands() (libatile.bar.Bar method), 299 method), 319 commands() (libqtile.widget.currentlayout.CurrentLayout commands() (libqtile.config.Screen method), 397 commands() (libqtile.core.manager.Qtile method), 244 method), 320 commands() (libqtile.group._Group method), 295 commands() (libqtile.widget.currentscreen.CurrentScreen commands() (libqtile.layout.bsp.Bsp method), 252 *method*), 321 commands() (libqtile.layout.columns.Columns method), commands() (libqtile.widget.df.DF method), 322 255 commands() (libqtile.widget.do not disturb.DoNotDisturb commands() (libqtile.layout.floating.Floating method), method), 323 257 commands() (libqtile.widget.generic_poll_text.GenPollCommand commands() (libqtile.layout.matrix.Matrix method), 258 method), 324 commands() (libqtile.layout.max.Max method), 260 commands() (libqtile.widget.generic_poll_text.GenPollText (libqtile.layout.plasma.Plasma method), *method*), 326 commands() commands() (libqtile.widget.generic_poll_text.GenPollUrl 271 commands() (libqtile.layout.ratiotile.RatioTile method), method), 327 274 commands() (libqtile.widget.gmail_checker.GmailChecker commands() (libqtile.layout.screensplit.ScreenSplit method), 328 method), 275 commands() (libqtile.widget.graph.CPUGraph method), commands() (libqtile.layout.slice.Slice method), 277 308 commands() (libqtile.layout.spiral.Spiral method), 278 commands() (libqtile.widget.graph.HDDBusyGraph commands() (libqtile.layout.stack.Stack method), 280 method), 332 commands() (libqtile.layout.tile.Tile method), 282 commands() (libqtile.widget.graph.HDDGraph method), commands() (libqtile.layout.tree.TreeTab method), 284 333 (libqtile.layout.verticaltile.VerticalTile commands() commands() (libqtile.widget.graph.MemoryGraph method), 286 method), 345 (libqtile.layout.xmonad.MonadTall commands() (libqtile.widget.graph.NetGraph method), commands() *method*), 262 352 commands() (libqtile.layout.xmonad.MonadThreeColcommands() (libqtile.widget.graph.SwapGraph method), method), 265 374 (libqtile.layout.xmonad.MonadWide commands() commands() (libqtile.widget.groupbox.AGroupBox method), 268 method), 301 commands() (libqtile.layout.zoomy.Zoomy method), 288 commands() (libqtile.widget.groupbox.GroupBox commands() (libqtile.widget.backlight.Backlight method), 329 commands() (libqtile.widget.hdd.HDD method), 330 method), 302 commands() (libqtile.widget.base.Mirror method), 346 commands() (libqtile.widget.idlerpg.IdleRPG method), (libatile.widget.battery.Battery method), commands() 334 303 commands() (libqtile.widget.image.Image method), 335 commands() (libqtile.widget.battery.BatteryIcon commands() (libqtile.widget.imapwidget.ImapWidget method), 304 method), 336 commands() (libqtile.widget.bluetooth.Bluetooth commands() (libqtile.widget.keyboardkbdd.KeyboardKbdd method), 337 method), 306 commands() (libqtile.widget.canto.Canto method), 309 commands() (libqtile.widget.keyboardlayout.KeyboardLayout commands() (libqtile.widget.caps_num_lock_indicator.CapsNumLock_inathaday338 method), 310 commands() (libqtile.widget.khal calendar.KhalCalendar commands() (libqtile.widget.check_updates.CheckUpdates method), 340 method), 311 commands() (libqtile.widget.launchbar.LaunchBar commands() (libqtile.widget.chord.Chord method), 312 method), 341 commands() (libatile.widget.clipboard.Clipboard commands() (libqtile.widget.load.Load method), 342 method), 314 commands() (libqtile.widget.maildir.Maildir method), commands() (libqtile.widget.clock.Clock method), 315 343 commands() (libqtile.widget.cmus.Cmus method), 316 commands() (libqtile.widget.memory.Memory method), commands() (libqtile.widget.countdown.Countdown method), 317 commands() (libqtile.widget.moc.Moc method), 348 commands() (libqtile.widget.mpd2widget.Mpd2 method), commands() (libqtile.widget.cpu.CPU method), 307

486 Index

349

commands() (libqtile.widget.crypto ticker.CryptoTicker

commands() (libatile.widget.mpris2widget.Mpris2 commands() (libatile.widget.windowname.WindowName method), 350 method), 391 (libqtile.widget.windowtabs.WindowTabs commands() (libqtile.widget.net.Net method), 351 commands() commands() (libqtile.widget.netup.NetUP method), 354 method), 392 commands() (libqtile.widget.notify.Notify method), 355 commands() (libqtile.widget.wlan.Wlan method), 393 commands() (libqtile.widget.nvidia sensors.NvidiaSensors commands() (libqtile.widget.wttr.Wttr method), 394 *method*), 356 Core (class in libqtile.backend.wayland.core), 400 commands() (libqtile.widget.open weather.OpenWeather Core (class in libgtile.backend.x11.core), 399 method), 357 Countdown (class in libqtile.widget.countdown), 317 commands() (libqtile.widget.plasma.Plasma method), CPU (class in libqtile.widget.cpu), 306 359 CPUGraph (class in libqtile.widget.graph), 308 commands() critical() (libqtile.core.manager.Qtile method), 244 (libqtile.widget.pomodoro.Pomodoro method), 360 CryptoTicker (class in libqtile.widget.crypto_ticker), commands() (libqtile.widget.prompt.Prompt method), 318 361 current_screen_change() (libqtile.hook.subscribe commands() (libqtile.widget.pulse_volume.PulseVolume method), 207 *method*), 363 CurrentLayout (class in libqtile.widget.currentlayout), commands() (libqtile.widget.quick_exit.QuickExit CurrentScreen (class in libqtile.widget.currentscreen), method), 364 commands() (libqtile.widget.redshift.Redshift method), 366 D commands() (libqtile.widget.screensplit.ScreenSplit method), 368 debug() (libqtile.core.manager.Qtile method), 244 commands() (libqtile.widget.sensors.ThermalSensor decrease_brightness() method), 381 (libqtile.widget.redshift.Redshift method), commands() (libqtile.widget.sep.Sep method), 369 commands() (libqtile.widget.she.She method), 370 decrease_nmaster() (libqtile.layout.tile.Tile method), commands() (libqtile.widget.spacer.Spacer method), 371 282 commands() (libqtile.widget.statusnotifier.StatusNotifier decrease_ratio() (libqtile.layout.ratiotile.RatioTile *method*), 372 *method*), 274 commands() (libqtile.widget.stock_ticker.StockTicker decrease_ratio() (libqtile.layout.spiral.Spiral *method*), 373 method), 278 (libqtile.layout.tile.Tile method), commands() (libqtile.widget.swaync.SwayNC method), decrease_ratio() 375 282 commands() (libqtile.widget.systray.Systray method), decrease_ratio() (libqtile.layout.tree.TreeTab 377 method), 284 commands() (libqtile.widget.tasklist.TaskList method), decrease_temperature() 379 (libqtile.widget.redshift.Redshift method), commands() (libqtile.widget.textbox.TextBox method), 366 380 decrease_vol() (libqtile.widget.pulse volume.PulseVolume commands() (libqtile.widget.thermal zone.ThermalZone method), 363 method), 382 decrease_vol() (libqtile.widget.volume.Volume commands()(libqtile.widget.tuned manager.TunedManager method), 386 *method*), 383 del_section() (libqtile.layout.tree.TreeTab method), commands() (libqtile.widget.vertical_clock.VerticalClock 284 method), 385 delete() (libatile.layout.matrix.Matrix method), 259 (libqtile.widget.volume.Volume method), commands() delete() (libqtile.layout.stack.Stack method), 280 386 delgroup() (libqtile.core.manager.Qtile method), 245 commands() (libqtile.widget.wallpaper.Wallpaper delgroup() (libqtile.hook.subscribe method), 208 method), 387 DF (class in libqtile.widget.df), 322 (libqtile.widget.widgetbox.WidgetBox commands() disable_floating() (libqtile.backend.base.window.Window method), 389 method), 291 $\verb|commands(|)| (libqtile.widget.window_count.WindowCount| | \verb|disable_fullscreen(|)| |$ method), 390 (libqtile.backend.base.window.Window

method), 291	doc() (libqtile.widget.currentscreen.CurrentScreen
display() (libqtile.widget.notify.Notify method), 355	method), 321
<pre>display_kb() (libqtile.core.manager.Qtile method), 245</pre>	doc() (libqtile.widget.df.DF method), 322
<pre>doc() (libqtile.backend.base.window.Window method),</pre>	<pre>doc() (libqtile.widget.do_not_disturb.DoNotDisturb</pre>
291	method), 323
doc() (libqtile.backend.wayland.core.Core method), 400	$\verb"doc()" (libqtile.widget.generic_poll_text.GenPollCommand")$
doc() (libqtile.backend.x11.core.Core method), 399	method), 325
doc() (libqtile.bar.Bar method), 299	doc() (libqtile.widget.generic_poll_text.GenPollText
doc() (libqtile.config.Screen method), 397	method), 326
doc() (libqtile.core.manager.Qtile method), 245	doc() (libqtile.widget.generic_poll_text.GenPollUrl
doc() (libqtile.groupGroup method), 295	method), 327
doc() (libqtile.layout.bsp.Bsp method), 253	doc() (libqtile.widget.gmail_checker.GmailChecker
doc() (libqtile.layout.columns.Columns method), 255	method), 328
doc() (libqtile.layout.floating.Floating method), 257	doc() (libqtile.widget.graph.CPUGraph method), 308
doc() (libqtile.layout.matrix.Matrix method), 259	doc() (libqtile.widget.graph.HDDBusyGraph method),
doc() (libqtile.layout.max.Max method), 260	332
doc() (libqtile.layout.plasma.Plasma method), 271	doc() (libqtile.widget.graph.HDDGraph method), 333
doc() (libqtile.layout.ratiotile.RatioTile method), 274	doc() (libqtile.widget.graph.MemoryGraph method),
doc() (libqtile.layout.screensplit.ScreenSplit method),	346
275	doc() (libqtile.widget.graph.NetGraph method), 353
doc() (libqtile.layout.slice.Slice method), 277	doc() (libqtile.widget.graph.SwapGraph method), 374
doc() (libqtile.layout.spiral.Spiral method), 278	doc() (libqtile.widget.groupbox.AGroupBox method),
doc() (libqtile.layout.stack.Stack method), 280	301
doc() (libatile layout tree Tree Tab method), 282	doc() (libatile widget groupbox. GroupBox method), 329
doc() (libqtile.layout.tree.TreeTab method), 284	doc() (libqtile.widget.hdd.HDD method), 331 doc() (libqtile.widget.idlerpg.IdleRPG method), 334
<pre>doc() (libqtile.layout.verticaltile.VerticalTile method),</pre>	doc() (libqtile.widget.image.Image method), 335
doc() (libqtile.layout.xmonad.MonadTall method), 262	doc() (libqtile.widget.image.Image memod), 555 doc() (libqtile.widget.imapwidget.ImapWidget method),
doc() (libqtile.layout.xmonad.MonadThreeCol method),	336
265	doc() (libqtile.widget.keyboardkbdd.KeyboardKbdd
doc() (libqtile.layout.xmonad.MonadWide method), 268	method), 337
doc() (libqtile.layout.zoomy.Zoomy method), 288	doc() (libqtile.widget.keyboardlayout.KeyboardLayout
doc() (libqtile.widget.backlight.Backlight method), 302	method), 338
doc() (libqtile.widget.base.Mirror method), 347	doc() (libqtile.widget.khal_calendar.KhalCalendar
doc() (libqtile.widget.battery.Battery method), 303	method), 340
doc() (libqtile.widget.battery.BatteryIcon method), 305	<pre>doc() (libqtile.widget.launchbar.LaunchBar method),</pre>
doc() (libqtile.widget.bluetooth.Bluetooth method), 306	341
doc() (libqtile.widget.canto.Canto method), 309	doc() (libqtile.widget.load.Load method), 342
<pre>doc() (libqtile.widget.caps_num_lock_indicator.CapsNum</pre>	
method), 310	doc() (libqtile.widget.memory.Memory method), 344
<pre>doc() (libqtile.widget.check_updates.CheckUpdates</pre>	doc() (libqtile.widget.moc.Moc method), 348
method), 311	doc() (libqtile.widget.mpd2widget.Mpd2 method), 349
doc() (libqtile.widget.chord.Chord method), 313	<pre>doc() (libqtile.widget.mpris2widget.Mpris2 method),</pre>
doc() (libqtile.widget.clipboard.Clipboard method), 314	350
doc() (libqtile.widget.clock.Clock method), 315	doc() (libqtile.widget.net.Net method), 351
doc() (libqtile.widget.cmus.Cmus method), 316	doc() (libqtile.widget.netup.NetUP method), 354
doc() (libqtile.widget.countdown.Countdown method),	doc() (libqtile.widget.notify.Notify method), 355
318	doc() (libqtile.widget.nvidia_sensors.NvidiaSensors
doc() (libqtile.widget.cpu.CPU method), 307	method), 356
doc() (libqtile.widget.crypto_ticker.CryptoTicker	doc() (libqtile.widget.open_weather.OpenWeather
method), 319	method), 358
doc() (libqtile.widget.currentlayout.CurrentLayout	doc() (libqtile.widget.plasma.Plasma method), 359
method), 320	doc() (libatile widget prompt Prompt method), 360
	aoca annane waget brombt Prombt Method) 301

doc() (libqtile.widget.pulse_volume.PulseVolume	E
method), 363	$\verb"enable_floating" (\it libqtile.backend.base.window.Window")$
doc() (libatile.widget.quick_exit.QuickExit method), 364	method), 291
<pre>doc() (libqtile.widget.redshift.Redshift method), 366 doc() (libqtile.widget.screensplit.ScreenSplit method),</pre>	enable_fullscreen()
368	(libqtile.backend.base.window.Window
<pre>doc() (libqtile.widget.sensors.ThermalSensor method),</pre>	method), 291
381	enter_chord() (libqtile.hook.subscribe method), 208
doc() (libqtile.widget.sep.Sep method), 369	error() (libqtile.core.manager.Qtile method), 245
doc() (libqtile.widget.she.She method), 370	eval() (libqtile.backend.base.window.Window method),
doc() (libqtile.widget.spacer.Spacer method), 371	291 eval() (libatile.backend.wayland.core.Core method),
doc() (libqtile.widget.statusnotifier.StatusNotifier	eval() (libqtile.backend.wayland.core.Core method), 400
method), 372	eval() (libqtile.backend.x11.core.Core method), 399
<pre>doc() (libqtile.widget.stock_ticker.StockTicker method),</pre>	eval() (libqtile.bar.Bar method), 299
373	eval() (libqtile.config.Screen method), 397
doc() (libqtile.widget.swaync.SwayNC method), 375	eval() (libqtile.core.manager.Qtile method), 245
<pre>doc() (libqtile.widget.systray.Systray method), 377</pre>	eval() (libqtile.groupGroup method), 295
doc() (libqtile.widget.tasklist.TaskList method), 379	eval() (libqtile.layout.bsp.Bsp method), 253
doc() (libqtile.widget.textbox.TextBox method), 380	eval() (libqtile.layout.columns.Columns method), 256
doc() (libqtile.widget.thermal_zone.ThermalZone	eval() (libqtile.layout.floating.Floating method), 257
method), 382	eval() (libqtile.layout.matrix.Matrix method), 259
doc() (libqtile.widget.tuned_manager.TunedManager	eval() (libqtile.layout.max.Max method), 260
method), 384	eval() (libqtile.layout.plasma.Plasma method), 271
doc() (libqtile.widget.vertical_clock.VerticalClock	eval() (libqtile.layout.ratiotile.RatioTile method), 274
method), 385	eval() (libqtile.layout.screensplit.ScreenSplit method),
doc() (libqtile.widget.volume.Volume method), 386	275
doc() (libqtile.widget.wallpaper.Wallpaper method), 387	eval() (libqtile.layout.slice.Slice method), 277
doc() (libqtile.widget.widgetbox.WidgetBox method),	eval() (libqtile.layout.spiral.Spiral method), 278
doc() (libqtile.widget.window_count.WindowCount	eval() (libqtile.layout.stack.Stack method), 280
doc() (libqtile.widget.window_count.WindowCount method), 390	eval() (libqtile.layout.tile.Tile method), 282
doc() (libqtile.widget.windowname.WindowName	eval() (libqtile.layout.tree.TreeTab method), 284
method), 391	eval() (libqtile.layout.verticaltile.VerticalTile method),
doc() (libqtile.widget.windowtabs.WindowTabs method),	286
392	eval() (libqtile.layout.xmonad.MonadTall method), 262
doc() (libqtile.widget.wlan.Wlan method), 393	eval() (libqtile.layout.xmonad.MonadThreeCol
doc() (libqtile.widget.wttr.Wttr method), 394	method), 265 eval() (libqtile.layout.xmonad.MonadWide method),
DoNotDisturb (class in libqtile.widget.do_not_disturb),	268
323	eval() (libqtile.layout.zoomy.Zoomy method), 288
down() (libqtile.layout.bsp.Bsp method), 253	eval() (libqtile.widget.backlight.Backlight method), 302
down() (libqtile.layout.columns.Columns method), 256	eval() (libqtile.widget.base.Mirror method), 347
down() (libqtile.layout.matrix.Matrix method), 259	eval() (libqtile.widget.battery.Battery method), 303
down() (libqtile.layout.max.Max method), 260	eval() (libqtile.widget.battery.BatteryIcon method), 305
down() (libqtile.layout.plasma.Plasma method), 271	eval() (libqtile.widget.bluetooth.Bluetooth method), 306
down() (libqtile.layout.stack.Stack method), 280	eval() (libqtile.widget.canto.Canto method), 309
down() (libqtile.layout.xmonad.MonadTall method), 262	eval() (libqtile.widget.caps_num_lock_indicator.CapsNumLockIndicator
down() (libqtile.layout.xmonad.MonadThreeCol	method), 310
method), 265	eval() (libqtile.widget.check_updates.CheckUpdates
down() (libqtile.layout.xmonad.MonadWide method),	method), 311
268	eval() (libqtile.widget.chord.Chord method), 313
down_opacity() (libqtile.backend.base.window.Window method), 291	eval() (libqtile.widget.clipboard.Clipboard method),
<i>тетоа), 271</i>	314
	eval() (libqtile.widget.clock.Clock method), 315
	eval() (libqtile.widget.cmus.Cmus method), 316

eval() (libqtile.widget.countdown.Countdown method), eval() (libqtile.widget.notify.Notify method), 355 318 eval() (libqtile.widget.cpu.CPU method), 307 (libqtile.widget.crypto_ticker.CryptoTicker eval() method), 319 eval() (libqtile.widget.currentlayout.CurrentLayout method), 320 (libqtile.widget.currentscreen.CurrentScreen eval() method), 321 eval() (libqtile.widget.df.DF method), 322 eval() (libqtile.widget.do_not_disturb.DoNotDisturb *method*), 323 eval() (libqtile.widget.generic_poll_text.GenPollCommand *method*), 325 eval() (libqtile.widget.generic_poll_text.GenPollText method), 326 (libqtile.widget.generic_poll_text.GenPollUrl eval() method), 327 eval() (libqtile.widget.gmail checker.GmailChecker *method*), 328 eval() (libqtile.widget.graph.CPUGraph method), 308 eval() (libqtile.widget.graph.HDDBusyGraph method), 332 eval() (libqtile.widget.graph.HDDGraph method), 333 eval() (libqtile.widget.stock ticker.StockTicker method), eval() (libqtile.widget.graph.MemoryGraph method), eval() (libqtile.widget.graph.NetGraph method), 353 eval() (libqtile.widget.graph.SwapGraph method), 374 eval() (libqtile.widget.groupbox.AGroupBox method), eval() (libqtile.widget.groupbox.GroupBox method), eval() (libqtile.widget.hdd.HDD method), 331 eval() (libqtile.widget.idlerpg.IdleRPG method), 334 eval() (libatile.widget.image.Image method), 335 eval() (libqtile.widget.imapwidget.ImapWidget method), 336 eval() (libqtile.widget.keyboardkbdd.KeyboardKbdd method), 337 eval() (libqtile.widget.keyboardlayout.KeyboardLayout *method*), 339 eval() $(libqtile.widget.khal_calendar.KhalCalendar$ method), 340 eval() (libqtile.widget.launchbar.LaunchBar method), eval() (libqtile.widget.load.Load method), 342 eval() (libqtile.widget.maildir.Maildir method), 343 eval() (libqtile.widget.memory.Memory method), 344 eval() (libqtile.widget.moc.Moc method), 348 eval() (libqtile.widget.mpd2widget.Mpd2 method), 349

eval() (libqtile.widget.mpris2widget.Mpris2 method),

eval() (libqtile.widget.net.Net method), 351 eval() (libqtile.widget.netup.NetUP method), 354

- eval() (libqtile.widget.nvidia sensors.NvidiaSensors method), 356 $(libqtile.widget.open_weather.OpenWeather$ eval() method), 358 eval() (libqtile.widget.plasma.Plasma method), 359 eval() (libqtile.widget.pomodoro.Pomodoro method), eval() (libqtile.widget.prompt.Prompt method), 361 eval() (libqtile.widget.pulse_volume.PulseVolume method), 363 eval() (libqtile.widget.quick_exit.QuickExit method), eval() (libqtile.widget.redshift.Redshift method), 366 eval() (libqtile.widget.screensplit.ScreenSplit method), eval() (libqtile.widget.sensors.ThermalSensor method), eval() (libqtile.widget.sep.Sep method), 369 eval() (libqtile.widget.she.She method), 370 eval() (libqtile.widget.spacer.Spacer method), 371 (libqtile.widget.statusnotifier.StatusNotifier
- 373 eval() (libqtile.widget.swaync.SwayNC method), 375 eval() (libqtile.widget.systray.Systray method), 378 eval() (libqtile.widget.tasklist.TaskList method), 379 eval() (libqtile.widget.textbox.TextBox method), 380

method), 372

- eval() (libqtile.widget.thermal_zone.ThermalZone method), 382
- eval() (libqtile.widget.tuned_manager.TunedManager method), 384
- $(libqtile.widget.vertical_clock.VerticalClock$ eval() method), 385
- eval() (libqtile.widget.volume.Volume method), 386
- eval() (libatile.widget.wallpaper.Wallpaper method),
- eval() (libqtile.widget.widgetbox.WidgetBox method),
- eval() (libqtile.widget.window count.WindowCount method), 390
- (libqtile.widget.windowname.WindowName eval() method), 391
- (libqtile.widget.windowtabs.WindowTabs eval() method), 392
- eval() (libqtile.widget.wlan.Wlan method), 393
- eval() (libqtile.widget.wttr.Wttr method), 394
- exec_general() (libqtile.widget.prompt.Prompt method), 362
- expand_branch() (libqtile.layout.tree.TreeTab method), 285

F	<pre>force_update() (libqtile.widget.keyboardkbdd.KeyboardKbdd</pre>
<pre>fake_button_press() (libqtile.bar.Bar method), 299</pre>	method), 337
fake_keypress() (libqtile.widget.prompt.Prompt method), 362	<pre>force_update() (libqtile.widget.khal_calendar.KhalCalendar</pre>
findwindow() (libqtile.core.manager.Qtile method), 245	${\tt force_update()} ({\it libqtile.widget.load.Load} {\it method}),$
<pre>fire_user_hook() (libqtile.core.manager.Qtile</pre>	342
method), 245	force_update() (libqtile.widget.maildir.Maildir
flip() (libqtile.layout.xmonad.MonadTall method), 263	<pre>method), 343 force_update() (libqtile.widget.memory.Memory</pre>
flip() (libqtile.layout.xmonad.MonadThreeCol	method), 345
method), 266 flip() (libqtile.layout.xmonad.MonadWide method),	force_update() (libqtile.widget.moc.Moc method), 348
flip() (libqtile.layout.xmonad.MonadWide method), 269	<pre>force_update() (libqtile.widget.mpd2widget.Mpd2</pre>
flip_down() (libqtile.layout.bsp.Bsp method), 253	method), 349
flip_left() (libqtile.layout.bsp.Bsp method), 253	<pre>force_update() (libqtile.widget.net.Net method), 352</pre>
flip_right() (libqtile.layout.bsp.Bsp method), 253	<pre>force_update() (libqtile.widget.netup.NetUP method),</pre>
flip_up() (libqtile.layout.bsp.Bsp method), 253	354
<pre>float_change() (libqtile.hook.subscribe method), 208</pre>	force_update() (libqtile.widget.nvidia_sensors.NvidiaSensors
Floating (class in libqtile.layout.floating), 257	method), 357
focus() (libqtile.backend.base.window.Window method), 291	<pre>force_update() (libqtile.widget.open_weather.OpenWeather</pre>
focus() (libqtile.widget.systray.Systray method), 378	<pre>force_update() (libqtile.widget.pomodoro.Pomodoro</pre>
focus_back() (libqtile.groupGroup method), 295	method), 360
<pre>focus_by_index() (libqtile.groupGroup method),</pre>	force_update() (libqtile.widget.sensors.ThermalSensor
295	method), 381
focus_by_name() (libqtile.groupGroup method), 296	<pre>force_update() (libqtile.widget.stock_ticker.StockTicker method), 373</pre>
focus_change() (libqtile.hook.subscribe method), 209	force_update() (libqtile.widget.thermal_zone.ThermalZone
force_update() (libqtile.widget.battery.Battery	method), 383
<pre>method), 304 force_update() (libqtile.widget.canto.Canto method),</pre>	<pre>force_update() (libqtile.widget.tuned_manager.TunedManager</pre>
309	method), 384
<pre>force_update() (libqtile.widget.caps_num_lock_indicato</pre>	reass Aundate (malicipatile.widget.wttr.Wttr method), 394
method), 310	Tunction() (noquie.backena.base.winaow.winaow
<pre>force_update() (libqtile.widget.check_updates.CheckUpd</pre>	lates method), 291
method), 312	function() (libqtile.backend.wayland.core.Core
<pre>force_update() (libqtile.widget.cmus.Cmus method),</pre>	<pre>method), 400 function() (libqtile.backend.x11.core.Core method),</pre>
317	399
force_update() (libqtile.widget.cru.CPU method), 307 force_update() (libqtile.widget.crypto_ticker.CryptoTicket.CryptoTick	
method), 319	function() (libqtile.config.Screen method), 397
force_update() (libqtile.widget.df.DF method), 322	function() (libqtile.core.manager.Qtile method), 245
force_update() (libqtile.widget.generic_poll_text.GenPol	
method) 325	function() (libquie.layout.bsp.bsp methoa), 255
force_update() (libqtile.widget.generic_poll_text.GenPol	function() (libqtile.layout.columns.Columns method),
mathad) 226	230
force_update() (libqtile.widget.generic_poll_text.GenPol method), 327	251
force_update() (libqtile.widget.gmail_checker.GmailChe	function() (libqtile.layout.matrix.Matrix method), 259
method), 328	function() (libqtile.layout.max.max method), 200
<pre>force_update() (libqtile.widget.hdd.HDD method),</pre>	function() (libqtile.layout.plasma.Plasma method),
331	271
<pre>force_update() (libqtile.widget.idlerpg.IdleRPG</pre>	function() (libqtile.layout.ratiotile.RatioTile method), 274
force_update() (libqtile.widget.imapwidget.ImapWidget	$function () {\it (libqtile.layout.screensplit.ScreenSplit)}\\$
method) 336	method), 275

function() (libqtile.layout.slice.Slice method), 277	308
function() (libqtile.layout.spiral.Spiral method), 278	<pre>function() (libqtile.widget.graph.HDDBusyGraph</pre>
function() (libqtile.layout.stack.Stack method), 281	method), 332
function() (libqtile.layout.tile.Tile method), 282	<pre>function() (libqtile.widget.graph.HDDGraph method),</pre>
function() (libqtile.layout.tree.TreeTab method), 285	333
function() (libqtile.layout.verticaltile.VerticalTile	<pre>function() (libqtile.widget.graph.MemoryGraph</pre>
method), 286	method), 346
function() (libqtile.layout.xmonad.MonadTall	<pre>function() (libqtile.widget.graph.NetGraph method),</pre>
method), 263	353
function() (libqtile.layout.xmonad.MonadThreeCol	<pre>function() (libqtile.widget.graph.SwapGraph method),</pre>
method), 266	374
function() (libqtile.layout.xmonad.MonadWide	<pre>function() (libqtile.widget.groupbox.AGroupBox</pre>
method), 269	method), 301
function() (libqtile.layout.zoomy.Zoomy method), 288	function() (libqtile.widget.groupbox.GroupBox
function() (libqtile.widget.backlight.Backlight	method), 330
method), 302	function() (libqtile.widget.hdd.HDD method), 331
function() (libqtile.widget.base.Mirror method), 347	<pre>function() (libqtile.widget.idlerpg.IdleRPG method),</pre>
function() (libqtile.widget.battery.Battery method),	334
304	function() (libqtile.widget.image.Image method), 335
function() (libqtile.widget.battery.BatteryIcon	function() (libqtile.widget.imapwidget.ImapWidget
method), 305	method), 336
function() (libqtile.widget.bluetooth.Bluetooth	<pre>function() (libqtile.widget.keyboardkbdd.KeyboardKbdd</pre>
method), 306	method), 338
function() (libqtile.widget.canto.Canto method), 309	$\verb function() (libqtile.widget.keyboardlayout.KeyboardLayout $
function() (libqtile.widget.caps_num_lock_indicator.Cap	
method), 310	function() (libqtile.widget.khal_calendar.KhalCalendar
function() (libqtile.widget.check_updates.CheckUpdates	method), 340
method), 312	function() (libqtile.widget.launchbar.LaunchBar
function() (libqtile.widget.chord.Chord method), 313	method), 341
function() (libqtile.widget.clipboard.Clipboard	function() (libqtile.widget.load.Load method), 342
method), 314	function() (libqtile.widget.maildir.Maildir method),
function() (libqtile.widget.clock.Clock method), 315	343
function() (libqtile.widget.cmus.Cmus method), 317	function() (libqtile.widget.memory.Memory method),
function() (libqtile.widget.countdown.Countdown	345
method), 318	function() (libqtile.widget.moc.Moc method), 348
function() (libqtile.widget.cpu.CPU method), 307	function() (libqtile.widget.mpd2widget.Mpd2 method),
function() (libqtile.widget.crypto_ticker.CryptoTicker	349
method), 319	function() (libqtile.widget.mpris2widget.Mpris2
function() (libqtile.widget.currentlayout.CurrentLayout	method), 350
method), 320	function() (libqtile.widget.net.Net method), 352
Function() (libqtile.widget.currentscreen.CurrentScreen method), 321	function() (libqtile.widget.netup.NetUP method), 354
**	function() (libqtile.widget.notify.Notify method), 355
function() (libqtile.widget.df.DF method), 322	function() (libqtile.widget.nvidia_sensors.NvidiaSensors
<pre>function() (libqtile.widget.do_not_disturb.DoNotDisturb</pre>	
memoa), 324 function() (libqtile.widget.generic_poll_text.GenPollCon	function() (libqtile.widget.open_weather.OpenWeather mand method), 358
method), 325	function() (libgtile.widget.plasma.Plasma method),
memoa), 323 function() (libgtile.widget.generic_poll_text.GenPollText	
method), 326	
metmoa), 320 function() (libqtile.widget.generic_poll_text.GenPollUrl	function() (libqtile.widget.pomodoro.Pomodoro method), 360
method), 327	function() (libqtile.widget.prompt.Prompt method),
memoa), 527 function() (libqtile.widget.gmail_checker.GmailChecker	362 (ttoquie.wiaget.prompt.Frompt method),
method), 328	function() (libqtile.widget.pulse_volume.PulseVolume
function() (libatile.widget.graph.CPUGraph method),	method), 363
Laric Crori() (iiogiiic.wiazci.grapii.Cr OOrabii iileliiba).	memou j, sos

function() (libqtile.widget.quick_exit.QuickExit get() (libqtile.widget.window count.WindowCount method), 365 method), 390 get_groups() (libqtile.core.manager.Qtile method), 245 function() (libqtile.widget.redshift.Redshift method), 366 get_hints() (libqtile.widget.systray.Systray method), function() (libqtile.widget.screensplit.ScreenSplit 378 method), 368 get_inputs() (libqtile.backend.wayland.core.Core function() (libqtile.widget.sensors.ThermalSensor method), 400 get_position() (libqtile.backend.base.window.Window method), 381 function() (libqtile.widget.sep.Sep method), 369 method), 291 function() (libqtile.widget.she.She method), 370 get_screens() (libqtile.core.manager.Qtile method), function() (libqtile.widget.spacer.Spacer method), 371 245 function() (libqtile.widget.statusnotifier.StatusNotifier get_size() (libqtile.backend.base.window.Window *method*), 372 method), 291 function() (libqtile.widget.stock_ticker.StockTicker get_state() (libqtile.core.manager.Qtile method), 245 *method*), 373 get_test_data() (libqtile.core.manager.Qtile method), function() (libqtile.widget.swaync.SwayNC method), 376 GmailChecker (class in libqtile.widget.gmail_checker), function() (libatile.widget.systray.Systray method), 378 group_window_add() (libqtile.hook.subscribe method), function() (libqtile.widget.tasklist.TaskList method), 379 group_window_remove() (libqtile.hook.subscribe function() (libqtile.widget.textbox.TextBox method), method), 209 380 GroupBox (class in libqtile.widget.groupbox), 329 function() (libqtile.widget.thermal zone.ThermalZone grow() (libqtile.layout.plasma.Plasma method), 271 *method*), 383 grow() (libqtile.layout.verticaltile.VerticalTile method), function() (libqtile.widget.tuned_manager.TunedManager method), 384 grow() (libqtile.layout.xmonad.MonadTall method), 263 function() (libqtile.widget.vertical_clock.VerticalClock (libqtile.layout.xmonad.MonadThreeCol grow() *method*), 385 method), 266 (libqtile.layout.xmonad.MonadWide method), function() (libqtile.widget.volume.Volume method), grow() 386 269 function() (libqtile.widget.wallpaper.Wallpaper grow_down() (libqtile.layout.bsp.Bsp method), 253 method), 388 grow_down() (libqtile.layout.columns.Columns method), (libqtile.widget.widgetbox.WidgetBox 256 function() method), 389 grow_height() (libatile.layout.plasma.Plasma function() (libqtile.widget.window count.WindowCount method), 271 *method*), 390 grow_left() (libqtile.layout.bsp.Bsp method), 253 function() (libqtile.widget.windowname.WindowName grow_left() (libqtile.layout.columns.Columns method), method), 391 256 function() (libqtile.widget.windowtabs.WindowTabsgrow_main() (libqtile.layout.spiral.Spiral method), 279 method), 392 (libqtile.layout.xmonad.MonadTall grow_main() function() (libqtile.widget.wlan.Wlan method), 393 method), 263 function() (libqtile.widget.wttr.Wttr method), 395 (libqtile.layout.xmonad.MonadThreeCol grow_main() method), 266 G (libqtile.layout.xmonad.MonadWide grow_main() method), 269 GenPollCommand (class ingrow_right() (libqtile.layout.bsp.Bsp method), 253 libqtile.widget.generic_poll_text), 324 (libqtile.layout.columns.Columns grow_right() GenPollText (class in libqtile.widget.generic_poll_text), method), 256 325 grow_up() (libqtile.layout.bsp.Bsp method), 253 GenPollUrl (class in libqtile.widget.generic_poll_text), grow_up() (libqtile.layout.columns.Columns method), 256 get() (libqtile.widget.screensplit.ScreenSplit method), grow_width() (libqtile.layout.plasma.Plasma method),

Index 493

get() (libqtile.widget.textbox.TextBox method), 380

271

H	info() (libqtile.layout.tree.TreeTab method), 285
HDD (class in libqtile.widget.hdd), 330	info() (libqtile.layout.verticaltile.VerticalTile method),
HDDBusyGraph (class in libqtile.widget.graph), 331	287
HDDGraph (class in libqtile.widget.graph), 332	info() (libqtile.layout.xmonad.MonadTall method), 263
hide_cursor() (libqtile.backend.wayland.core.Core	<pre>info() (libqtile.layout.xmonad.MonadWide method),</pre>
method), 400	269
hide_show_bar() (libqtile.core.manager.Qtile method),	info() (libqtile.layout.zoomy.Zoomy method), 288
245	<pre>info() (libqtile.widget.backlight.Backlight method), 302</pre>
2.0	info() (libqtile.widget.base.Mirror method), 347
	info() (libqtile.widget.battery.Battery method), 304
IdleRPG (class in libqtile.widget.idlerpg), 333	info() (libqtile.widget.battery.BatteryIcon method), 305
Image (class in libqtile.widget.image), 335	info() (libqtile.widget.bluetooth.Bluetooth method), 306
ImapWidget (class in libqtile.widget.imapwidget), 336	info() (libqtile.widget.canto.Canto method), 309
increase_brightness()	$\verb"info" () (libqtile.widget.caps_num_lock_indicator. CapsNumLockIndicator$
(libqtile.widget.redshift.Redshift method),	method), 310
366	info() (libqtile.widget.check_updates.CheckUpdates
<pre>increase_nmaster() (libqtile.layout.tile.Tile method),</pre>	method), 312
282	info() (libqtile.widget.chord.Chord method), 313
<pre>increase_ratio() (libqtile.layout.ratiotile.RatioTile</pre>	<pre>info() (libqtile.widget.clipboard.Clipboard method),</pre>
method), 274	314
increase_ratio() (libqtile.layout.spiral.Spiral	info() (libqtile.widget.clock.Clock method), 315
method), 279	info() (libqtile.widget.cmus.Cmus method), 317
increase_ratio() (libqtile.layout.tile.Tile method),	<pre>info() (libqtile.widget.countdown.Countdown method),</pre>
282	318
increase_ratio() (libqtile.layout.tree.TreeTab	info() (libqtile.widget.cpu.CPU method), 307
method), 285	info() (libqtile.widget.crypto_ticker.CryptoTicker
<pre>increase_temperature()</pre>	method), 319
(libqtile.widget.redshift.Redshift method),	info() (libqtile.widget.currentlayout.CurrentLayout
366	method), 320
increase_vol() (libqtile.widget.pulse_volume.PulseVolume.	info() (libqtile.widget.currentscreen.CurrentScreen
method), 363	,,
<pre>increase_vol() (libqtile.widget.volume.Volume</pre>	info() (libqtile.widget.df.DF method), 322
method), 387	info() (libqtile.widget.do_not_disturb.DoNotDisturb
<pre>info() (libqtile.backend.base.window.Window method),</pre>	method), 324
291	info() (libqtile.widget.generic_poll_text.GenPollCommand
<pre>info() (libqtile.backend.wayland.core.Core method),</pre>	method), 325
400	info() (libqtile.widget.generic_poll_text.GenPollText
<pre>info() (libqtile.backend.x11.core.Core method), 399</pre>	method), 326
info() (libqtile.bar.Bar method), 299	info() (libqtile.widget.generic_poll_text.GenPollUrl
info() (libqtile.config.Screen method), 397	method), 327
info() (libqtile.core.manager.Qtile method), 246	info() (libqtile.widget.gmail_checker.GmailChecker
info() (libqtile.groupGroup method), 296	method), 328
info() (libqtile.layout.bsp.Bsp method), 253	info() (libqtile.widget.graph.CPUGraph method), 308
info() (libqtile.layout.columns.Columns method), 256	info() (libqtile.widget.graph.HDDBusyGraph method),
info() (libqtile.layout.floating.Floating method), 257	332
info() (libqtile.layout.matrix.Matrix method), 259	info() (libqtile.widget.graph.HDDGraph method), 333
info() (libqtile.layout.max.Max method), 260	info() (libqtile.widget.graph.MemoryGraph method),
<pre>info() (libqtile.layout.plasma.Plasma method), 272</pre>	346
info() (libqtile.layout.ratiotile.RatioTile method), 274	info() (libqtile.widget.graph.NetGraph method), 353
$\verb"info" (libqtile.layout.screensplit.ScreenSplit method),$	info() (libqtile.widget.graph.SwapGraph method), 375
275	<pre>info() (libqtile.widget.groupbox.AGroupBox method), 301</pre>
info() (libqtile.layout.slice.Slice method), 277	info() (libqtile.widget.groupbox.GroupBox method),
info() (libqtile.layout.stack.Stack method), 281	(libquie.wiagei.groupbox.GroupBox meinoa),
info() (libqtile.layout.tile.Tile method), 282	330

info() (libatile.widget.hdd.HDD method), 331 info() (libqtile.widget.idlerpg.IdleRPG method), 334 info() (libqtile.widget.image.Image method), 335 info() (libqtile.widget.imapwidget.ImapWidget method), info() (libqtile.widget.keyboardkbdd.KeyboardKbdd *method*), 338 info() (libqtile.widget.keyboardlayout.KeyboardLayout method), 339 (libqtile.widget.khal_calendar.KhalCalendar info() *method*), 340 info() (libqtile.widget.launchbar.LaunchBar method), info() (libqtile.widget.load.Load method), 342 info() (libqtile.widget.maildir.Maildir method), 344 info() (libqtile.widget.memory.Memory method), 345 info() (libqtile.widget.moc.Moc method), 348 info() (libatile.widget.mpd2widget.Mpd2 method), 349 info() (libqtile.widget.mpris2widget.Mpris2 method), info() (libqtile.widget.net.Net method), 352 info() (libqtile.widget.netup.NetUP method), 354 info() (libqtile.widget.notify.Notify method), 355 info() (libqtile.widget.nvidia sensors.NvidiaSensors method), 357 info() (libqtile.widget.open weather.OpenWeather *method*), 358 info() (libqtile.widget.plasma.Plasma method), 359 info() (libqtile.widget.pomodoro.Pomodoro method), 360 info() (libqtile.widget.prompt.Prompt method), 362 info() (libqtile.widget.pulse_volume.PulseVolume *method*), 363 info() (libqtile.widget.quick_exit.QuickExit method), info() (libqtile.widget.redshift.Redshift method), 366 info() (libqtile.widget.screensplit.ScreenSplit method), info() (libqtile.widget.sensors.ThermalSensor method), 382 info() (libqtile.widget.sep.Sep method), 369 info() (libqtile.widget.she.She method), 370 info() (libqtile.widget.spacer.Spacer method), 371 info() (libqtile.widget.statusnotifier.StatusNotifier *method*), 372 info() (libqtile.widget.stock_ticker.StockTicker method), info() (libqtile.widget.swaync.SwayNC method), 376 info() (libqtile.widget.tasklist.TaskList method), 379 info() (libqtile.widget.textbox.TextBox method), 380 info() $(libqtile.widget.thermal_zone.ThermalZone$ *method*), 383 info() (libqtile.widget.tuned manager.TunedManager

method), 384

info() (libatile.widget.vertical clock.VerticalClock method), 385 info() (libqtile.widget.volume.Volume method), 387 (libqtile.widget.wallpaper.Wallpaper method), info() info() (libqtile.widget.widgetbox.WidgetBox method), (libqtile.widget.window_count.WindowCount info() method), 390 (libqtile.widget.windowname.WindowName info() *method*), 391 info() (libatile.widget.windowtabs.WindowTabs method), 392 info() (libqtile.widget.wlan.Wlan method), 393 info() (libqtile.widget.wttr.Wttr method), 395 info_by_name() (libqtile.group._Group method), 296 inspect() (libqtile.widget.systray.Systray method), 378 integrate_down() (libatile.layout.plasma.Plasma method), 272 integrate_left() (libqtile.layout.plasma.Plasma method), 272 integrate_right() (libqtile.layout.plasma.Plasma method), 272 integrate_up() (libqtile.layout.plasma.Plasma method), 272 internal_windows() (libqtile.core.manager.Qtile method), 246 invoke() (libqtile.widget.notify.Notify method), 355 is_visible() (libqtile.backend.base.window.Window method), 291 items() (libqtile.backend.base.window.Window method), 291 items() (libqtile.backend.wayland.core.Core method), items() (libatile.backend.x11.core.Core method), 399 items() (libqtile.bar.Bar method), 299 items() (libatile.config.Screen method), 397 items() (libqtile.core.manager.Qtile method), 246 items() (libatile.group. Group method), 296 items() (libqtile.layout.bsp.Bsp method), 253 items() (libqtile.layout.columns.Columns method), 256 items() (libqtile.layout.floating.Floating method), 257 items() (libqtile.layout.matrix.Matrix method), 259 items() (libqtile.layout.max.Max method), 260 items() (libqtile.layout.plasma.Plasma method), 272 items() (libqtile.layout.ratiotile.RatioTile method), 274 items() (libatile.layout.screensplit.ScreenSplit method), 276 items() (libqtile.layout.slice.Slice method), 277 items() (libqtile.layout.spiral.Spiral method), 279 items() (libqtile.layout.stack.Stack method), 281 items() (libqtile.layout.tile.Tile method), 283

items() (libqtile.layout.tree.TreeTab method), 285

items() (libqtile.layout.verticaltile.VerticalTile method),

287 items() (libatile.widget.groupbox.AGroupBox method), items() (libqtile.layout.xmonad.MonadTall method), items() (libqtile.widget.groupbox.GroupBox method), (libqtile.layout.xmonad.MonadThreeColitems() method), 266 items() (libqtile.widget.hdd.HDD method), 331 items() (libqtile.layout.xmonad.MonadWide method), items() (libqtile.widget.idlerpg.IdleRPG method), 334 items() (libqtile.widget.image.Image method), 335 items() (libqtile.layout.zoomy.Zoomy method), 288 items() (libqtile.widget.imapwidget.ImapWidget *method*), 336 items() (libqtile.widget.backlight.Backlight method), (libqtile.widget.keyboardkbdd.KeyboardKbdd items() items() (libqtile.widget.base.Mirror method), 347 method), 338 items() (libatile.widget.battery.Battery method), 304 items() (libqtile.widget.keyboardlayout.KeyboardLayout items() (libqtile.widget.battery.BatteryIcon method), method), 339 305 (libqtile.widget.khal_calendar.KhalCalendar items() items() (libqtile.widget.bluetooth.Bluetooth method), method), 340 306 items() (libqtile.widget.launchbar.LaunchBar method), items() (libqtile.widget.canto.Canto method), 309 items() (libqtile.widget.caps_num_lock_indicator.CapsNurirLemks(i)liditqtile.widget.load.Load method), 342 method), 311 items() (libqtile.widget.maildir.Maildir method), 344 (libqtile.widget.check updates.CheckUpdates items() (libqtile.widget.memory.Memory method), 345 items() *method*), 312 items() (libqtile.widget.moc.Moc method), 348 items() (libqtile.widget.chord.Chord method), 313 items() (libqtile.widget.mpd2widget.Mpd2 method), 349 items() (libqtile.widget.clipboard.Clipboard method), items() (libqtile.widget.mpris2widget.Mpris2 method), items() (libqtile.widget.clock.Clock method), 315 items() (libqtile.widget.net.Net method), 352 items() (libqtile.widget.cmus.Cmus method), 317 items() (libqtile.widget.netup.NetUP method), 354 items() (libqtile.widget.countdown.Countdown items() (libqtile.widget.notify.Notify method), 355 (libqtile.widget.nvidia_sensors.NvidiaSensors *method*), 318 items() items() (libqtile.widget.cpu.CPU method), 307 method), 357 (libqtile.widget.crypto_ticker.CryptoTicker (libqtile.widget.open_weather.OpenWeather items() items() method), 319 method), 358 items() (libqtile.widget.currentlayout.CurrentLayout items() (libqtile.widget.plasma.Plasma method), 359 method), 320 items() (libqtile.widget.pomodoro.Pomodoro method), (libqtile.widget.currentscreen.CurrentScreen items() items() (libatile.widget.prompt.Prompt method), 362 method), 321 items() (libqtile.widget.df.DF method), 323 items() (libqtile.widget.pulse volume.PulseVolume *method*), 363 (libqtile.widget.do not disturb.DoNotDisturb method), 324 items() (libqtile.widget.quick_exit.QuickExit method), items() (libqtile.widget.generic_poll_text.GenPollCommand *method*), 325 items() (libqtile.widget.redshift.Redshift method), 367 (libqtile.widget.generic poll text.GenPollText items() (libqtile.widget.screensplit.ScreenSplit method), items() method), 326 368 (libqtile.widget.generic poll text.GenPollUrl (libqtile.widget.sensors.ThermalSensor items() items() method), 327 method), 382 (libqtile.widget.gmail_checker.GmailChecker items() (libqtile.widget.sep.Sep method), 369 items() items() (libqtile.widget.she.She method), 370 method), 329 items() (libqtile.widget.graph.CPUGraph method), 308 items() (libqtile.widget.spacer.Spacer method), 371 items() (libqtile.widget.graph.HDDBusyGraph items() (libqtile.widget.statusnotifier.StatusNotifier *method*), 332 method), 372 items() (libqtile.widget.graph.HDDGraph method), 333 (libqtile.widget.stock_ticker.StockTicker items() items() (libqtile.widget.graph.MemoryGraph method), method), 373 items() (libqtile.widget.swaync.SwayNC method), 376 items() (libqtile.widget.graph.NetGraph method), 353 items() (libqtile.widget.systray.Systray method), 378 items() (libqtile.widget.graph.SwapGraph method), 375 items() (libqtile.widget.tasklist.TaskList method), 379

<pre>items() (libqtile.widget.textbox.TextBox method), 380 items() (libqtile.widget.thermal_zone.ThermalZone</pre>	list_widgets() (libqtile.core.manager.Qtile method), 246 Load (class in libqtile.widget.load), 342
<pre>items() (libqtile.widget.tuned_manager.TunedManager</pre>	loglevel() (libqtile.core.manager.Qtile method), 246 loglevelname() (libqtile.core.manager.Qtile method),
<pre>items() (libqtile.widget.vertical_clock.VerticalClock</pre>	246
<pre>items() (libqtile.widget.volume.Volume method), 387</pre>	M
items() (libqtile.widget.wallpaper.Wallpaper method), 388	Maildir (class in libqtile.widget.maildir), 343 Matrix (class in libqtile.layout.matrix), 258
<pre>items() (libqtile.widget.widgetbox.WidgetBox method),</pre>	Max (class in libqtile.layout.max), 259 maximize() (libqtile.layout.verticaltile.VerticalTile
<pre>items() (libqtile.widget.window_count.WindowCount</pre>	method), 287 maximize() (libqtile.layout.xmonad.MonadTall
<pre>items() (libqtile.widget.windowname.WindowName</pre>	method), 263 maximize() (libqtile.layout.xmonad.MonadThreeCol
<pre>items() (libqtile.widget.windowtabs.WindowTabs</pre>	method), 266
method), 392 items() (libqtile.widget.wlan.Wlan method), 393	maximize() (libqtile.layout.xmonad.MonadWide method), 269
items() (libqtile.widget.wttr.Wttr method), 395	Memory (class in libqtile.widget.memory), 344
K	MemoryGraph (class in libqtile.widget.graph), 345 Mirror (class in libqtile.widget.base), 346
keep_above() (libqtile.backend.base.window.Window	Moc (class in libqtile.widget.moc), 347
method), 291	mode_horizontal() (libqtile.layout.plasma.Plasma
keep_above() (libqtile.widget.systray.Systray method),	method), 272
378	<pre>mode_horizontal_split()</pre>
keep_below() (libqtile.backend.base.window.Window method), 292	(libqtile.layout.plasma.Plasma method), 272
keep_below() (libqtile.widget.systray.Systray method), 378	<pre>mode_vertical() (libqtile.layout.plasma.Plasma method), 272</pre>
KeyboardKbdd (class in libqtile.widget.keyboardkbdd), 337	<pre>mode_vertical_split()</pre>
KeyboardLayout (class in	272
libqtile.widget.keyboardlayout), 338	MonadTall (class in libqtile.layout.xmonad), 261
KhalCalendar (class in libqtile.widget.khal_calendar), 339	MonadThreeCol (class in libqtile.layout.xmonad), 264 MonadWide (class in libqtile.layout.xmonad), 267
kill() (libqtile.backend.base.window.Window method), 292	move_down() (libqtile.backend.base.window.Window method), 292
kill() (libqtile.widget.systray.Systray method), 378	move_down() (libqtile.layout.plasma.Plasma method), 272
L	move_down() (libqtile.layout.tree.TreeTab method), 285
labelgroup() (libqtile.core.manager.Qtile method), 246 LaunchBar (class in libqtile.widget.launchbar), 341	move_down() (libqtile.widget.systray.Systray method), 378
layout_change() (libqtile.hook.subscribe method), 210 leave_chord() (libqtile.hook.subscribe method), 210	<pre>move_floating() (libqtile.backend.base.window.Window</pre>
left() (libqtile.layout.bsp.Bsp method), 253	<pre>move_left() (libqtile.layout.plasma.Plasma method),</pre>
left() (libqtile.layout.columns.Columns method), 256	272
left() (libqtile.layout.matrix.Matrix method), 259	move_left() (libqtile.layout.tree.TreeTab method), 285
left() (libqtile.layout.plasma.Plasma method), 272	move_right() (libqtile.layout.plasma.Plasma method),
left() (libqtile.layout.xmonad.MonadTall method), 263	272 move right () (libetile layout tree TreeTab method)
left() (libqtile.layout.xmonad.MonadThreeCol method), 266	move_right() (libqtile.layout.tree.TreeTab method), 285
<pre>left() (libqtile.layout.xmonad.MonadWide method),</pre>	move_to_bottom() (libqtile.backend.base.window.Windownethod), 292

move_to_bottom() (libqtile.widget.systray.Systray method), 378	<pre>next() (libqtile.widget.mpris2widget.Mpris2 method),</pre>
move_to_slice() (libqtile.layout.slice.Slice method), 277	<pre>next() (libqtile.widget.notify.Notify method), 356 next_group() (libqtile.config.Screen method), 397</pre>
move_to_top() (libqtile.backend.base.window.Window method), 292	next_keyboard() (libqtile.widget.keyboardlayout.KeyboardLayout method), 339
move_to_top() (libqtile.widget.systray.Systray method), 378	next_layout() (libqtile.core.manager.Qtile method), 246
move_up() (libqtile.backend.base.window.Window method), 292	next_load() (libatile.widget.load.Load method), 343
move_up() (libqtile.layout.plasma.Plasma method), 272	<pre>next_mode() (libqtile.widget.plasma.Plasma method), 359</pre>
move_up() (libqtile.layout.tree.TreeTab method), 285 move_up() (libqtile.widget.systray.Systray method), 378	next_screen() (libqtile.core.manager.Qtile method), 246
<pre>move_window_to_next_split()</pre>	<pre>next_split() (libqtile.layout.screensplit.ScreenSplit</pre>
(libqtile.layout.screensplit.ScreenSplit method), 276	<pre>method), 276 next_urgent() (libqtile.core.manager.Qtile method),</pre>
move_window_to_previous_split()	246
(libqtile.layout.screensplit.ScreenSplit method),	<pre>next_window() (libqtile.groupGroup method), 296</pre>
276	normalize() (libqtile.layout.bsp.Bsp method), 253
Mpd2 (class in libqtile.widget.mpd2widget), 348	normalize() (libqtile.layout.columns.Columns method),
Mpris2 (class in libqtile.widget.mpris2widget), 350	256
mute() (libqtile.widget.pulse_volume.PulseVolume method), 364	normalize() (libqtile.layout.verticaltile.VerticalTile method), 287
mute() (libqtile.widget.volume.Volume method), 387	normalize() (libqtile.layout.xmonad.MonadTall
	method), 263
N	normalize() (libqtile.layout.xmonad.MonadThreeCol
Net (class in libqtile.widget.net), 351	method), 266
net_wm_icon_change() (libqtile.hook.subscribe method), 210	normalize() (libqtile.layout.xmonad.MonadWide method), 269
NetGraph (class in libqtile.widget.graph), 352	Notify (class in libqtile.widget.notify), 354 NvidiaSensors (class in libqtile.widget.nvidia_sensors),
NetUP (class in libqtile.widget.netup), 353	356
next() (libqtile.layout.bsp.Bsp method), 253	330
next() (libqtile.layout.columns.Columns method), 256 next() (libqtile.layout.floating.Floating method), 258	0
next() (libqtile.layout.matrix.Matrix method), 259	open() (libqtile.widget.widgetbox.WidgetBox method),
next() (libqtile.layout.max.Max method), 260	389
next() (libqtile.layout.plasma.Plasma method), 272	OpenWeather (class in libqtile.widget.open_weather),
next() (libqtile.layout.ratiotile.RatioTile method), 274	357
next() (libqtile.layout.screensplit.ScreenSplit method), 276	P
next() (libqtile.layout.slice.Slice method), 277	pause() (libqtile.core.manager.Qtile method), 246
next() (libqtile.layout.spiral.Spiral method), 279	place() (libqtile.backend.base.window.Window
next() (libqtile.layout.stack.Stack method), 281	method), 292
next() (libqtile.layout.tile.Tile method), 283	place() (libqtile.widget.systray.Systray method), 378
next() (libqtile.layout.tree.TreeTab method), 285	Plasma (class in libgtile.layout.plasma), 270
next() (libqtile.layout.verticaltile.VerticalTile method), 287	Plasma (class in libqtile.widget.plasma), 358 plasma_add_mode() (libqtile.hook.subscribe method),
next() (libqtile.layout.xmonad.MonadTall method), 263	211
next() (libqtile.layout.xmonad.MonadThreeCol method), 266	play_pause() (libqtile.widget.mpris2widget.Mpris2 method), 351
next() (libqtile.layout.xmonad.MonadWide method),	Pomodoro (class in libqtile.widget.pomodoro), 360
269	prev() (libqtile.widget.notify.Notify method), 356
nov+() (libatile layout zoomy Zoomy method) 288	nrey groun() (libatile config Screen method) 397

<pre>prev_layout() (libqtile.core.manager.Qtile method),</pre>	<pre>reload_config() (libqtile.core.manager.Qtile method),</pre>
prev_screen() (libqtile.core.manager.Qtile method), 247	remove_rule() (libqtile.core.manager.Qtile method), 247
<pre>prev_window() (libqtile.groupGroup method), 296</pre>	reset() (libqtile.layout.columns.Columns method), 256
previous() (libqtile.layout.bsp.Bsp method), 253	reset() (libqtile.layout.spiral.Spiral method), 279
<pre>previous() (libqtile.layout.columns.Columns method),</pre>	reset() (libqtile.layout.tile.Tile method), 283
256	reset() (libqtile.layout.xmonad.MonadTall method),
<pre>previous() (libqtile.layout.floating.Floating method),</pre>	263
258	reset() (libqtile.layout.xmonad.MonadThreeCol
previous() (libqtile.layout.matrix.Matrix method), 259	method), 266
previous() (libqtile.layout.max.Max method), 260	reset() (libqtile.layout.xmonad.MonadWide method),
previous() (libqtile.layout.plasma.Plasma method),	269
272	reset_redshift() (libqtile.widget.redshift.Redshift
previous() (libqtile.layout.ratiotile.RatioTile method),	method), 367
275	reset_size() (libqtile.layout.plasma.Plasma method),
previous() (libqtile.layout.screensplit.ScreenSplit	273
method), 276	resize() (libqtile.config.Screen method), 397
**	
previous() (libqtile.layout.slice.Slice method), 277	resize_floating() (libqtile.backend.base.window.Window
previous() (libqtile.layout.spiral.Spiral method), 279	method), 292
previous() (libqtile.layout.stack.Stack method), 281	restart() (libqtile.core.manager.Qtile method), 247
previous() (libqtile.layout.tile.Tile method), 283	restart() (libqtile.hook.subscribe method), 211
previous() (libqtile.layout.tree.TreeTab method), 285	resume() (libqtile.hook.subscribe method), 211
previous() (libqtile.layout.verticaltile.VerticalTile	right() (libqtile.layout.bsp.Bsp method), 253
method), 287	right() (libqtile.layout.columns.Columns method), 256
previous() (libqtile.layout.xmonad.MonadTall	right() (libqtile.layout.matrix.Matrix method), 259
method), 263	right() (libqtile.layout.plasma.Plasma method), 273
previous() (libqtile.layout.xmonad.MonadThreeCol method), 266	right() (libqtile.layout.xmonad.MonadTall method), 263
previous() (libqtile.layout.xmonad.MonadWide	right() (libqtile.layout.xmonad.MonadThreeCol
method), 269	method), 266
previous() (libqtile.layout.zoomy.Zoomy method), 288	right() (libqtile.layout.xmonad.MonadWide method),
previous() (libqtile.widget.mpris2widget.Mpris2	269
method), 351	right_click() (libqtile.widget.redshift.Redshift
$\verb"previous_split"() (\it libqtile.layout.screensplit.ScreenSplit") (\it libqtile.layout.screensplit.ScreenSplit") (\it libqtile.layout.screensplit) (\it libqtile.la$	
method), 276	rotate() (libqtile.layout.stack.Stack method), 281
Prompt (class in libqtile.widget.prompt), 361	run_app() (libqtile.widget.pulse_volume.PulseVolume
PulseVolume (class in libqtile.widget.pulse_volume),	method), 364
363	run_app() (libqtile.widget.volume.Volume method), 387
	<pre>run_extension() (libqtile.core.manager.Qtile method),</pre>
Q	247
Qtile (class in libqtile.core.manager), 242	<pre>run_redshift() (libqtile.widget.redshift.Redshift</pre>
<pre>qtile_info() (libqtile.core.manager.Qtile method), 247</pre>	method), 367
qtilecmd() (libqtile.core.manager.Qtile method), 247	
<pre>query_tree() (libqtile.backend.wayland.core.Core</pre>	S
method), 401	Screen (class in libqtile.config), 396
QuickExit (class in libqtile.widget.quick_exit), 364	screen_change() (libqtile.hook.subscribe method), 211
	screens_reconfigured() (libqtile.hook.subscribe
R	method), 212
RatioTile (class in libqtile.layout.ratiotile), 273	ScreenSplit (class in libqtile.layout.screensplit), 275
recent() (libqtile.layout.plasma.Plasma method), 273	ScreenSplit (class in libqtile.widget.screensplit), 367
	scroll_down() (libqtile.widget.bluetooth.Bluetooth
reconfigure_screens() (libqtile.core.manager.Qtile method), 247	method), 306
Redshift (class in libqtile.widget.redshift), 365	monouj, 500
neasitte (ems in noquie.wingenreasing), 303	

method), 330 scroll_down() (libqtile.widget.redshift.Redshift method), 367 set_font() (libqtile.widget.hdd.HDD method), 331 set_font() (libqtile.widget.idlerpg.IdleRPG method), scroll_up() (libqtile.widget.bluetooth.Bluetooth 334 method), 306 scroll_up() (libqtile.widget.redshift.Redshift method), set_font() (libqtile.widget.imapwidget.ImapWidget method), 337 section_down() (libqtile.layout.tree.TreeTab method), set_font() (libqtile.widget.keyboardkbdd.KeyboardKbdd method), 338 section_up() (libqtile.layout.tree.TreeTab method), set_font() (libqtile.widget.keyboardlayout.KeyboardLayout method), 339 285 selection_change() (libqtile.hook.subscribe method), set_font() (libqtile.widget.khal_calendar.KhalCalendar method), 340selection_notify() (libqtile.hook.subscribe method), set_font() (libqtile.widget.load.Load method), 343 set_font() (libqtile.widget.maildir.Maildir method), 212 Sep (class in libqtile.widget.sep), 369 344 set_font() (libqtile.widget.backlight.Backlight set_font() (libqtile.widget.memory.Memory method), method), 303 set_font() (libqtile.widget.battery.Battery method), set_font() (libatile.widget.moc.Moc method), 348 304 set_font() (libqtile.widget.mpd2widget.Mpd2 method), (libqtile.widget.bluetooth.Bluetooth set_font() 349 method), 306 set_font() (libqtile.widget.mpris2widget.Mpris2 set_font() (libqtile.widget.canto.Canto method), 310 method), 351 set_font() (libqtile.widget.caps_num_lock_indicator.Caps\textrn\textford\textford\tex method), 311 set_font() (libqtile.widget.netup.NetUP method), 354 set_font() (libqtile.widget.check updates.CheckUpdates set_font() (libqtile.widget.notify.Notify method), 356 *method*), 312 set_font() (libqtile.widget.nvidia sensors.NvidiaSensors set_font() (libqtile.widget.chord.Chord method), 313 method), 357 set_font() (libqtile.widget.clipboard.Clipboard set_font() (libqtile.widget.open_weather.OpenWeather method), 314 method), 358 (libqtile.widget.plasma.Plasma method), set_font() (libqtile.widget.clock.Clock method), 315 set_font() set_font() (libqtile.widget.cmus.Cmus method), 317 359 set_font() (libqtile.widget.countdown.Countdown set_font() (libqtile.widget.pomodoro.Pomodoro *method*), 318 method), 361 set_font() (libqtile.widget.cpu.CPU method), 307 (libqtile.widget.prompt.Prompt method), set_font() set_font() (libatile.widget.crypto ticker.CryptoTicker 362 method), 319 set_font() (libqtile.widget.pulse volume.PulseVolume set_font() (libqtile.widget.currentlayout.CurrentLayout method), 364 method), 320 set_font() (libqtile.widget.quick_exit.QuickExit set_font() (libqtile.widget.currentscreen.CurrentScreen method), 365 method), 322 set_font() (libqtile.widget.redshift.Redshift method), set_font() (libqtile.widget.df.DF method), 323 367 set_font() (libqtile.widget.do_not_disturb.DoNotDisturb set_font() (libqtile.widget.screensplit.ScreenSplit method), 324 method), 368 set_font() (libqtile.widget.generic_poll_text.GenPollCommentedfont() (libqtile.widget.sensors.ThermalSensor *method*), 325 method), 382 set_font() (libqtile.widget.generic_poll_text.GenPollText set_font() (libqtile.widget.she.She method), 370 (libqtile.widget.stock_ticker.StockTicker method), 326 set_font() set_font() (libqtile.widget.generic_poll_text.GenPollUrl *method*), 374 method), 328 set_font() (libqtile.widget.swaync.SwayNC method), set_font() (libqtile.widget.gmail_checker.GmailChecker 376 *method*), 329 (libqtile.widget.textbox.TextBox method), set_font() (libqtile.widget.groupbox.AGroupBox set_font() 381 method), 301 set_font() (libqtile.widget.thermal zone.ThermalZone

500 Index

method), 383

(libqtile.widget.groupbox.GroupBox

set_font()

- set_font()(libatile.widget.tuned manager.TunedManagershrink() (libqtile.layout.xmonad.MonadThreeCol method), 384 method), 266
- set_font() (libqtile.widget.vertical clock.VerticalClock 269 *method*), 385
- set_font() (libqtile.widget.volume.Volume method),
- set_font() (libqtile.widget.wallpaper.Wallpaper method), 388
- (libqtile.widget.widgetbox.WidgetBox set_font() method), 389
- set_font() (libqtile.widget.window_count.WindowCount shrink_main() method), 390
- set_font() (libatile.widget.windowname.WindowName *method*), 391
- set_font() (libqtile.widget.windowtabs.WindowTabs *method*), 393
- set_font() (libqtile.widget.wlan.Wlan method), 394
- set_font() (libatile.widget.wttr.Wttr method), 395
- set_height() (libqtile.layout.plasma.Plasma method), 273
- set_keymap() (libqtile.backend.wayland.core.Core method), 401
- set_label() (libqtile.group._Group method), 296
- set master ratio() (libqtile.layout.spiral.Spiral *method*), 279
- set_opacity() (libqtile.backend.base.window.Window method), 292
- $set_position()$ (libqtile.backend.base.window.Window *method*), 292
- set_position_floating()
 - (libqtile.backend.base.window.Window method), 292
- set_ratio() (libqtile.layout.spiral.Spiral method), 279
- (libqtile.layout.xmonad.MonadTall set_ratio() method), 263
- (libqtile.layout.xmonad.MonadThreeCol set_ratio() method), 266
- set_ratio() (libqtile.layout.xmonad.MonadWide method), 269
- set_size() (libqtile.layout.plasma.Plasma method), 273
- set_size_floating()
 - (libqtile.backend.base.window.Window method), 292
- set_wallpaper() (libqtile.config.Screen method), 397 set_width() (libqtile.layout.plasma.Plasma method),
- setgroup() (libqtile.hook.subscribe method), 213
- setlayout() (libqtile.group._Group method), 296
- She (class in libqtile.widget.she), 370 shrink() (libqtile.layout.verticaltile.VerticalTile
- method), 287
- shrink() (libqtile.layout.xmonad.MonadTall method), 263

- shrink() (libqtile.layout.xmonad.MonadWide method),
- shrink_main() (libqtile.layout.spiral.Spiral method), 279
- (libqtile.layout.xmonad.MonadTall shrink_main() method), 263
- shrink_main() (libqtile.layout.xmonad.MonadThreeCol method), 266
- (libqtile.layout.xmonad.MonadWide method), 269
- shuffle_down() (libqtile.layout.bsp.Bsp method), 253
- shuffle_down() (libqtile.layout.columns.Columns method), 256
- shuffle_down() (libqtile.layout.ratiotile.RatioTile method), 275
- shuffle_down() (libqtile.layout.spiral.Spiral method), 279
- shuffle_down() (libqtile.layout.stack.Stack method), 281
- shuffle_down() (libqtile.layout.tile.Tile method), 283
- $shuffle_down()$ (libqtile.layout.verticaltile.VerticalTile method), 287
- shuffle_down() (libqtile.layout.xmonad.MonadTall method), 264
- $\verb|shuffle_down()| (libqtile.layout.xmonad.MonadThreeCol|$ method), 267
- shuffle_down() (libqtile.layout.xmonad.MonadWide method), 270
- shuffle_left() (libqtile.layout.bsp.Bsp method), 253
- shuffle_left() (libqtile.layout.columns.Columns method), 256
- shuffle_right() (libqtile.layout.bsp.Bsp method), 253
- (libatile.layout.columns.Columns shuffle_right() method), 256
- shuffle_up() (libqtile.layout.bsp.Bsp method), 254
- (libqtile.layout.columns.Columns shuffle_up() method), 256
- (libqtile.layout.ratiotile.RatioTile shuffle_up() method), 275
- shuffle_up() (libqtile.layout.spiral.Spiral method), 279
- shuffle_up() (libqtile.layout.stack.Stack method), 281 shuffle_up() (libqtile.layout.tile.Tile method), 283
- (libqtile.layout.verticaltile.VerticalTile shuffle_up() method), 287
- shuffle_up() (libqtile.layout.xmonad.MonadTall method), 264
- shuffle_up() (libqtile.layout.xmonad.MonadThreeCol method), 267
- (libqtile.layout.xmonad.MonadWide shuffle_up() method), 270
- shutdown() (libqtile.core.manager.Qtile method), 247

shutdown() (libqtile.hook.subscribe method), 213	method), 267
<pre>simple_key_binder() (in module libqtile.dgroups), 50 simulate_keypress() (libqtile.core.manager.Qtile</pre>	<pre>swap_right() (libqtile.layout.xmonad.MonadWide</pre>
method), 247	swap_window_order() (libqtile.groupGroup method),
Slice (class in libqtile.layout.slice), 276	296
$\verb sort_windows() (libqtile.layout.tree.TreeTab method),$	SwapGraph (class in libqtile.widget.graph), 374
285	SwayNC (class in libqtile.widget.swaync), 375
Spacer (class in libqtile.widget.spacer), 371 spawn() (libqtile.core.manager.Qtile method), 248	<pre>switch_groups() (libqtile.core.manager.Qtile method),</pre>
spawncmd() (libqtile.core.manager.Qtile method), 248	<pre>switch_groups() (libqtile.groupGroup method), 296</pre>
Spiral (class in libqtile.layout.spiral), 278	<pre>switch_window() (libqtile.core.manager.Qtile method),</pre>
Stack (class in libqtile.layout.stack), 279	249
<pre>start_repl_server() (libqtile.core.manager.Qtile</pre>	switchgroup() (libqtile.core.manager.Qtile method), 249
<pre>startup() (libqtile.hook.subscribe method), 213</pre>	sync() (libqtile.core.manager.Qtile method), 249
<pre>startup_complete() (libqtile.hook.subscribe method),</pre>	Systray (class in libqtile.widget.systray), 376
startup_once() (libqtile.hook.subscribe method), 214	T
static() (libqtile.backend.base.window.Window	TaskList (class in libqtile.widget.tasklist), 379
method), 292	TextBox (class in libqtile.widget.textbox), 380
status() (libqtile.core.manager.Qtile method), 249	ThermalSensor (class in libqtile.widget.sensors), 381
StatusNotifier (class in libqtile.widget.statusnotifier), 372	ThermalZone (class in libqtile.widget.thermal_zone), 382
StockTicker (class in libqtile.widget.stock_ticker), 373	Tile (class in libqtile.layout.tile), 281
<pre>stop() (libqtile.widget.mpris2widget.Mpris2 method),</pre>	to_layout_index() (libqtile.core.manager.Qtile method), 249
<pre>stop_repl_server() (libqtile.core.manager.Qtile</pre>	to_screen() (libqtile.core.manager.Qtile method), 249
method), 249	toggle() (libqtile.widget.notify.Notify method), 356
suspend() (libqtile.hook.subscribe method), 214	toggle() (libqtile.widget.widgetbox.WidgetBox method),
swap() (libqtile.layout.xmonad.MonadTall method), 264	389
swap() (libqtile.layout.xmonad.MonadThreeCol method), 267	toggle_active() (libqtile.widget.pomodoro.Pomodoro
swap() (libqtile.layout.xmonad.MonadWide method),	method), 361
270	<pre>toggle_auto_maximize()</pre>
<pre>swap_column_left() (libqtile.layout.columns.Columns</pre>	264
method), 256	toggle_auto_maximize()
<pre>swap_column_right()</pre>	(libqtile.layout.xmonad.MonadThreeCol
(libqtile.layout.columns.Columns method),	method), 267
256 swap_left() (libqtile.layout.xmonad.MonadTall	toggle_auto_maximize()
method), 264	(libqtile.layout.xmonad.MonadWide method), 270
<pre>swap_left() (libqtile.layout.xmonad.MonadThreeCol</pre>	toggle_break() (libqtile.widget.pomodoro.Pomodoro
swap_left() (libqtile.layout.xmonad.MonadWide	method), 361 toggle_dnd() (libqtile.widget.swaync.SwayNC
method), 270	method), 376
swap_main() (libqtile.layout.xmonad.MonadTall method), 264	<pre>toggle_floating() (libqtile.backend.base.window.Window</pre>
$\verb swap_main() (libqtile.layout.xmonad.MonadThreeCol $	toggle_fullscreen()
method), 267	(libqtile.backend.base.window.Window
swap_main() (libqtile.layout.xmonad.MonadWide	method), 293
method), 270	toggle_group() (libqtile.config.Screen method), 398
<pre>swap_right() (libqtile.layout.xmonad.MonadTall method), 264</pre>	toggle_maximize() (libqtile.backend.base.window.Window
swap_right() (libqtile.layout.xmonad.MonadThreeCol	method), 293
Swap_right() (libqtile.layout.xmonad.MonadIhreeCol	

```
toggle_minimize() (libatile.backend.base.window.Windowse_system_timezone()
                                                                                    (libqtile.widget.clock.Clock
         method), 293
                                                                 method), 316
toggle_panel()
                       (libqtile.widget.swaync.SwayNC use_system_timezone()
                                                                 (libqtile.widget.vertical_clock.VerticalClock
         method), 376
toggle_split() (libqtile.layout.bsp.Bsp method), 254
                                                                 method), 386
toggle_split()
                      (libqtile.layout.columns.Columns
                                                       user() (libqtile.hook.subscribe method), 215
         method), 256
toggle_split() (libqtile.layout.stack.Stack method),
         281
                                                        validate_config()
                                                                                    (libqtile.core.manager.Qtile
togroup()
                 (libqtile.backend.base.window.Window
                                                                 method), 250
         method), 293
                                                        VerticalClock (class in libqtile.widget.vertical clock),
togroup() (libqtile.core.manager.Qtile method), 250
                 (libatile.backend.base.window.Window
toscreen()
                                                        VerticalTile (class in libqtile.layout.verticaltile), 286
         method), 293
                                                        Volume (class in libqtile.widget.volume), 386
toscreen() (libqtile.group._Group method), 296
                                                        W
tracemalloc_dump()
                           (libqtile.core.manager.Qtile
         method), 250
                                                        Wallpaper (class in libqtile.widget.wallpaper), 387
tracemalloc_toggle()
                           (libatile.core.manager.Otile
                                                        warning() (libqtile.core.manager.Qtile method), 250
         method), 250
                                                        WidgetBox (class in libqtile.widget.widgetbox), 388
TreeTab (class in libgtile.layout.tree), 283
                                                        Window (class in libgtile.backend.base.window), 289
trigger()
                   (libqtile.widget.quick_exit.QuickExit
                                                        WindowCount (class in libatile.widget.window count),
         method), 365
                                                                 389
TunedManager (class in libqtile.widget.tuned_manager),
                                                        WindowName (class in libqtile.widget.windowname), 391
         383
                                                        windows() (libqtile.core.manager.Qtile method), 250
                                                        WindowTabs (class in libqtile.widget.windowtabs), 392
U
                                                        Wlan (class in libatile.widget.wlan), 393
ungrab_all_chords()
                           (libqtile.core.manager.Qtile
                                                        Wttr (class in libqtile.widget.wttr), 394
         method), 250
ungrab_chord() (libqtile.core.manager.Qtile method),
                                                        Ζ
         250
                                                        Zoomy (class in libqtile.layout.zoomy), 287
unhide_cursor() (libqtile.backend.wayland.core.Core
         method), 401
unminimize_all() (libqtile.group._Group method),
up() (libqtile.layout.bsp.Bsp method), 254
up() (libqtile.layout.columns.Columns method), 257
up() (libqtile.layout.matrix.Matrix method), 259
up() (libqtile.layout.max.Max method), 261
up() (libqtile.layout.plasma.Plasma method), 273
up() (libqtile.layout.stack.Stack method), 281
up() (libqtile.layout.xmonad.MonadTall method), 264
up() (libqtile.layout.xmonad.MonadThreeCol method),
up() (libqtile.layout.xmonad.MonadWide method), 270
up_opacity() (libqtile.backend.base.window.Window
         method), 293
update() (libqtile.widget.image.Image method), 335
update()
                 (libqtile.widget.screensplit.ScreenSplit
         method), 368
update() (libqtile.widget.textbox.TextBox method), 381
                            (libqtile.widget.clock.Clock
update_timezone()
         method), 316
update_timezone() (libqtile.widget.vertical_clock.VerticalClock
         method), 385
```