## Summary: How to access PostgreSQL from Oracle database

## **Prerequisites**

unixODBC and unixODBC-devel

### Download the Postgresql Repository

on Oracle server set up ODBC data source for PostgreSQL database

```
# wget https://download.postgresql.org/pub/repos/yum/9.4/redhat/rhel-7-
x86 64/pgdg-centos94-9.4-3.noarch.rpm #or file attachments
# rpm -ivh pgdg-centos94-9.4-3.noarch.rpm
```

## Configure the PostgreSQL ODBC Driver in the Odbcinst.ini File (/etc/odbcinst.ini)

```
[PostgreSQL]
Description = ODBC for PostgreSQL
Driver = /usr/pgsql-9.4/lib/psqlodbc.so
Setup = /usr/lib64/libodbcpsqlS.so
FileUsage = 1
```

#### Test Your ODBC Driver

```
# odbcinst -q -d
```

# Configure Our ODBC Connections in /etc/odbc.ini

```
[ODBC Data Sources]
PG_LINK = PostgreSQL

[PG_LINK]
Description = Postgres DB
Driver = PostgreSQL
Database = homestead
Servername = 127.0.0.1
UserName = homestead
Password = secret
Port = 5432
Protocol = 9.4 #follow version install
ReadOnly = No
RowVersioning = No
ShowSystemTables = No
ConnSettings =
```

\*remark: [<your\_ODBC\_NAME>]

# Connect to PostgreSQL with ODBC isql Command

```
# isql -v PG_LINK
+-----+
| Connected!
```

Configure HS for Oracle database: create file initPG\_LINK.ora under \$ORACLE\_HOME/hs/admin directory

```
HS_FDS_CONNECT_INFO = PG_LINK
HS_FDS_TRACE_LEVEL = 0
HS_FDS_SHAREABLE_NAME = /usr/lib64/libodbc.so
HS_LANGUAGE=AMERICAN_AMERICA.WE8ISO8859P1
set ODBCINI=/etc/odbc.ini
```

\*remark: filename init<your\_ODBC\_NAME>.ora

HS\_FDS\_CONNECT\_INFO = <your\_ODBC\_NAME>

Modify \$ORACLE\_HOME /network/admin/tnsnames.ora; add the following entry:

```
PG_LINK =
  (DESCRIPTION =
          (ADDRESS = (PROTOCOL = TCP) (HOST = testbed.localdomain) (PORT = 1521))
          (CONNECT_DATA =
                (SID = PG_LINK)
          )
          (HS=OK)
          )
```

\*remark: <your\_ODBC\_NAME> = ...

HOST = <ORA\_DB\_HOSTNAME>

SID = <your ODBC NAME>

Modify \$ORACLE\_HOME /network/admin/listener.ora; add the following static entry in the SID\_LIST:

```
*remark: SID_NAME = <your_ODBC_NAME>

SID_LIST_<your_LISTENER_NAME> = ...

ORACLE_HOME = $ORACLE_HOME
```

Reload listener configuraction

```
lsnrctl reload LISTENER #<your_LISTENER_NAME>
```

Create database link: (PL SQL)

```
# create database link <your_LISTENER_NAME> connect to "<uname>" identified by
"<pname>" using 'PG_LINK';
```

Thank you. Gif your enjoy!

#### Thank for Ref:

http://www.uptimemadeeasy.com/linux/install-postgresql-odbc-driver-on-linux/

https://dbaspot.wordpress.com/2013/05/29/how-to-access-postgresql-from-oracle-database/

