```
stream.mark();
 }
 @Override
 public void reset() throws IOException {
   throwIfClosed();
   stream.reset();
 }
 @Override
 public void close() throws IOException {
   isOpen = false;
   stream.close();
 }
 private void throwIfClosed() {
   Preconditions.checkState(isOpen, "Serializer is closed!");
 }
 public static class ProtobufDeserializerBuilder implements Builder {
   @Override
   public EventDeserializer build(Context context,
     ResettableInputStream resettableInputStream) {
     // The serializer does not need any configuration,
     // so ignore the Context instance. If some configuration has
     // to be passed to the serializer, this Context instance can be used.
      return new ProtobufDeserializer(resettableInputStream);
   }
 }
}
```

ProtobufDeserializer 类从文件中读取 Protobuf-serialized 事件,并在 readEvent 方法中将它们转换为 Flume 事件,返回为 null 时表示没有可用的事件读取。如果 readEvents 方法没有事件可以读取,将返回一个空列表,就如 EventDeserializer 接口强制要求的那样。

由于文件是不可变的,一旦我们达到一个阶段,即文件中没有更多的可用的事件,这意味着所有的事件已经从文件读取完,此时 Source 通过调用 close 方法关闭反序列化器。如果序列化器保持任何内部状态或有一些清理工作要做,这种方法有望做到这一点。在这种情况下,我们只是简单地关闭流。mark和 reset 方法只是检查反序列化器是否打开和转发调用方法给流。序列化器特定的实现不需要任何配置,但反序列化器可以通过

< 56