# RUNOOB.COM

搜索·····

**JAVASCRIPT** 首页 **CSS** Docker 教程 HTML / CSS ◆ Docker 架构 CentOS Docker 安装 → Docker 教 **JavaScript** 程 Ubuntu Docker 安装 服务端 Docker 架 构 Docker 支持以下的 Ubuntu 版本: 数据库 Ubuntu Precise 12.04 (LTS) Docker 移动端 安装 Ubuntu Trusty 14.04 (LTS) XML 教程 Ubuntu Wily 15.10 Docker 安 **ASP.NET** Xenial 16.04 (LTS) CentOS **Web Service** 其他更新的版本…… Docker 安 开发工具 如果安装 Docker ce 需要 16.04 及以上版本,安装步骤可以查看笔记部 Windows 分: 网站建设 Docker 安 Cosmic 18.10 装 MacOS Bionic 18.04 (LTS) Docker 安 Xenial 16.04 (LTS) 装 Docker 前提条件 使用 Docker Docker 要求 Ubuntu 系统的内核版本高于 3.10 , 查看本页面的前提条件来验证你的 Hello Ubuntu 版本是否支持 Docker。 World 通过 uname -r 命令查看你当前的内核版本 Docker 容 器使用 runoob@runoob:~\$ uname -r Docker 镜 像使用 unoob@runoob:~\$ uname -r Docker 容 .2.0-16-generic 器连接 unoob@runoob:~\$ Docker 使用脚本安装 Docker 实例 Docker 安 1、获取最新版本的 Docker 安装包 装 Nginx Docker 安 runoob@runoob:~\$ wget -qO- https://get.docker.com/ | sh 装 PHP

unoob@runoob:~\$ wget -qO- https://get.docker.com/

password for runoob:

sudo]

Docker 安

装 MySQL

Docker 安 装 Tomcat

Docker 安 装 Python

Docker 安 装 Redis

Docker 安 装

MongoDB

Docker 安 装 Apache

Docker 参考手册

Docker 命 令大全

Docker 资 源汇总

```
输入当前用户的密码后,就会下载脚本并且安装Docker及依赖包。
```

```
[sudo] password for runoob:
apparmor is enabled in the kernel, but apparmor_parser missing
+ sudo -E sh -c sleep 3; apt-get update
Hit http://hk.archive.ubuntu.com wily InRelease
Get:1 http://hk.archive.ubuntu.com wily-updates InRelease [65.9 kB]
Get:2 http://security.ubuntu.com wily-backports InRelease [65.9 kB]
Get:3 http://hk.archive.ubuntu.com wily-backports InRelease [65.9 kB]
Get:4 http://hk.archive.ubuntu.com wily-backports InRelease [65.9 kB]
Get:5 http://security.ubuntu.com wily-security/restricted Sources [2,854 B]
Get:6 http://security.ubuntu.com wily-security/universe Sources [11.2 kB]
Get:7 http://security.ubuntu.com wily-restricted Sources [7,181 B]
Get:8 http://hk.archive.ubuntu.com wily-restricted Sources [7,238 kB]
Get:9 http://security.ubuntu.com wily-security/main Sources [44.2 kB]
Get:10 http://security.ubuntu.com wily-security/main amd64 Packages [143 kB]
Get:11 http://security.ubuntu.com wily-security/main amd64 Packages [10.9 kB]
Get:12 http://security.ubuntu.com wily-security/multiverse samd64 Packages [6,253 B]
Get:13 http://security.ubuntu.com wily-security/multiverse amd64 Packages [6,253 B]
Get:14 http://security.ubuntu.com wily-security/main i386 Packages [10.9 kB]
Get:15 http://security.ubuntu.com wily-security/main i386 Packages [10.8 kB]
Get:16 http://security.ubuntu.com wily-security/main rranslation-en [69.2 kB]
Get:17 http://security.ubuntu.com wily-security/main rranslation-en [69.2 kB]
Get:18 http://security.ubuntu.com wily-security/multiverse Translation-en [2,806 B]
Get:20 http://security.ubuntu.com wily-security/multiverse i386 Packages [6,430 B]
Get:21 http://security.ubuntu.com wily-security/multiverse i386 Packages [6,430 B]
Get:22 http://security.ubuntu.com wily-security/multiverse i386 Packages [6,430 B]
Get:21 http://security.ubuntu.com wily-security/multiverse i386 Packages [6,430 B]
Get:22 http://security.ubuntu.com wily-security/multiverse i386 Packages [6,430 B]
Get:22 http://security.ubuntu.com wily-security/multiverse i386 Packages [6,430 B]
Get:22 http://secu
```

```
ient:
 Version:
 API version:
                  go1.5.4
4dc5990
 Go version:
Git commit:
                  wed Apr 13 18:38:59 2016
linux/amd64
os/Arch:
erver:
API version:
Go version:
                   Wed Apr 13 18:38:59 2016
linux/amd64
os/Arch:
If you would like to use Docker as a non-root user, you should now consider adding your user to the "docker" group with something like:
  sudo usermod -aG docker runoob
Remember that you will have to log out and back in for this to take effect!
```

### 安装完成后有个提示:

If you would like to **use Docker as** a non-root user, you should now consider adding your user to the "docker" **group with** something like:

sudo usermod -aG docker runoob

Remember that you will have to log out and back in for this to take effect!

当要以非root用户可以直接运行docker时,需要执行 **sudo usermod -aG docker ru noob** 命令,然后重新登陆,否则会有如下报错

```
runoob@runoob:~$ docker run hello-world
docker: Cannot connect to the Docker daemon. Is the docker daemon running on this host?.
See 'docker run_--help'.
```

## 2、启动docker 后台服务

runoob@runoob:~\$ sudo service docker start

```
runosbilrunosb:-$ sudo service docker start
runosbilrunosb:-$ ps -efigrep docker
root 15123 1 2 15153 7 00:00:00 /usr/bin/docker daemon -H fd://
root 15128 12:13:13 7 00:00:00 docker-containerd -1 /var/run/docker/libcontainerd/docker-containerd.sock --runtime docker-runc
runosb 13180 134743 0 15133 pts/1 00:00:00 dps--colorasuic docker
```

3、测试运行hello-world

runoob@runoob:~\$ docker run hello-world

## 镜像加速

鉴于国内网络问题,后续拉取 Docker 镜像十分缓慢,我们可以需要配置加速器来解决,我使用的是网易的镜像地址: http://hub-mirror.c.163.com。

新版的 Docker 使用 /etc/docker/daemon.json(Linux) 或者 %programdata%\docker\config\daemon.json(Windows) 来配置 Daemon。

请在该配置文件中加入(没有该文件的话,请先建一个):

```
{
    "registry-mirrors": ["http://hub-mirror.c.163.com"]
}
```

◆ Docker 架构

CentOS Docker 安装 →



## 2 篇笔记

② 写笔记



## Ubuntu 16.04 安装 Docker

1.选择国内的云服务商,这里选择阿里云为例

10

curl -sSL http://acs-public-mirror.oss-cn-hangzhou.aliyuncs.co m/docker-engine/internet | sh -

2.安装所需要的包

sudo apt-**get** install linux-image-extra-\$(uname -r) linux-image-extra-**virtual** 

3.添加使用 HTTPS 传输的软件包以及 CA 证书

sudo apt-**get** update sudo apt-**get** install apt-transport-https ca-certificates

4.添加GPG密钥

sudo apt-key adv --keyserver hkp://p80.pool.sks-keyservers.net: 80 --recv-keys 58118E89F3A912897C070ADBF76221572C52609D

5.添加软件源

echo "deb https://apt.dockerproject.org/repo ubuntu-xenial mai n" | sudo tee /etc/apt/sources.list.d/docker.list

6.添加成功后更新软件包缓存

sudo apt-get update

7.安装docker

sudo apt-**get** install docker-engine

8.启动 docker

sudo systemctl enable docker sudo systemctl start docker

欧迪芬 1年前 (2018-06-23)



## Ubuntu 18.04 安装 Docker-ce

1.更换国内软件源,推荐中国科技大学的源,稳定速度快(可 选)

sudo cp /etc/apt/sources.list /etc/apt/sources.list.bak sudo sed -i 's/archive.ubuntu.com/mirrors.ustc.edu.cn/g' /etc/ap t/sources.list sudo apt update

2.安装需要的包

sudo apt install apt-transport-https ca-certificates software-prop erties-common curl

3.添加 GPG 密钥,并添加 Docker-ce 软件源,这里还是以中国 科技大学的 Docker-ce 源为例

curl -fsSL https://mirrors.ustc.edu.cn/docker-ce/linux/ubuntu/gp g | sudo apt-key add -

sudo add-apt-repository "deb [arch=amd64] https://mirrors.ust c.edu.cn/docker-ce/linux/ubuntu \ \$(lsb\_release -cs) stable"

4.添加成功后更新软件包缓存

sudo apt update

5.安装 Docker-ce

sudo apt install docker-ce

6.设置开机自启动并启动 Docker-ce(安装成功后默认已设置 并启动,可忽略)

sudo systemctl enable docker sudo systemctl start docker

7.测试运行

sudo docker run hello-world

8.添加当前用户到 docker 用户组,可以不用 sudo 运行 docker (可选)

sudo groupadd docker sudo usermod -aG docker \$USER

9.测试添加用户组(可选)

docker run hello-world

路人码农 1年前 (2018-07-16)



在线实例 · HTML实

具

字符集&工

最新更新

• 编程的魅 力

站点信息

• 意见反馈