## ;; 鏈上費用計算

- ;; 繁體中文註解版 by <u>Y.C.</u>
- ;; 所有中文均經過人腦編譯,不存在 AI 製造的奇怪語法,並可取代原有的 op-code.fc 及 workchain.fc 服用。
- ;; 如複製此頁貼上到原有項目, 需要修改路徑至工具庫擺放的資料夾位置;
- ;; 在原版文檔中, op-code\_workchain\_zh.fc 內容分別以 op-code.fc 及 workchain.fc 擺放。 #include "op-code\_workchain\_zh.fc";
- ;; 定義 1 TON 為 1,000,000,000 nano-TON (也就是 1 TON) const ONE\_TON = 10000000000;
- ;; 把智能合約帳戶的最小存儲時間設定為 5 年(轉換為秒數)

const MIN STORAGE DURATION = 5 \* 365 \* 24 \* 3600; ;; 5 years

{ -

- # 預編譯常量
- 以下內容均為合約模擬測試的結果
  - ## 最小手續費
  - 轉帳手續費 [/sandbox\_tests/JettonWallet.spec.ts#L935](L935) `0.028627415`
- **燃燒手續費** [/sandbox\_tests/JettonWallet.spec.ts#L1185](L1185) `0.016492002`TON
  - ## 存儲費用
  - 存儲費用在單獨的測試文件中計算

[/sandbox\_tests/StateInit.spec.ts] (StateInit.spec.ts)

在 JETTON\_WALLET\_BITS 和 JETTON\_WALLET\_INITSTATE\_BITS 之間的區別正正是 StateInit 和 AccountStorage 的差異 詳情請參考

https://github.com/ton-blockchain/ton/blob/master/crypto/block/block.tlb

這裡按照最大可能的餘額計算位元的數量。

而 Gas 常量通過主測試套件計算;先找到相關交易,再將其 gas 消耗結果顯示到 console。

**-** }

```
;; jetton-wallet.fc#L163 - 手動計算位元數
const BURN NOTIFICATION BITS
                              = 1; ;; body 始終存放於引用中
const BURN NOTIFICATION CELLS
;; Jetton 錢包佔用的位元數 [/sandbox tests/StateInit.spec.ts#L92](L92)
const JETTON_WALLET_BITS
;; Jetton 錢包佔用的 cell 數 [/sandbox tests/StateInit.spec.ts#L92](L92)
const JETTON_WALLET_CELLS
;; Jetton 錢包的初始狀態位元數 [/sandbox_tests/StateInit.spec.ts#L95](L95)
;; Jetton 錢包的初始狀態的 cell 數量 [/sandbox_tests/StateInit.spec.ts#L95](L95)
const JETTON_WALLET_INITSTATE_CELLS = 3;
;; 發送轉帳的 Gas 消耗 [/sandbox tests/JettonWallet.spec.ts#L853](L853)
const SEND_TRANSFER_GAS_CONSUMPTION = 9255;
;; 接收轉帳的 Gas 消耗 [/sandbox tests/JettonWallet.spec.ts#L862](L862)
;; 發送燃燒的 Gas 消耗 [/sandbox tests/JettonWallet.spec.ts#L1154](L1154)
const SEND_BURN_GAS_CONSUMPTION
                                    = 5791;
;; 接收燃燒的 Gas 消耗 [/sandbox tests/JettonWallet.spec.ts#L1155](L1155)
const RECEIVE BURN GAS CONSUMPTION = 6775;
;; 計算 Jetton 錢包的最小存儲費用
int calculate_jetton_wallet_min_storage_fee() inline {
        ;; 引用 stdlib.fc / stdlib zh.fc 當中的:
        return get_storage_fee(MY_WORKCHAIN, MIN_STORAGE_DURATION, JETTON_WALLET_BITS,
      JETTON_WALLET_CELLS);
```

## ;; 計算初始狀態轉發的額外費用

## ;; 檢查轉帳金額是否足夠進行轉帳

```
() check_amount_is_enough_to_transfer(int msg_value, int forward_ton_amount, int
fwd fee) impure inline {
          ;; 如果有需要轉發的 TON, 則設置轉發次數為 2, 否則為 1。
          ;; 獲取 Jetton 錢包的 Gas 消耗, 若無預編譯數據則使用默認值
          int jetton_wallet_gas_consumption = get_precompiled_gas_consumption();
          int send_transfer_gas_consumption = null?(jetton_wallet_gas_consumption)
                ? SEND_TRANSFER_GAS_CONSUMPTION : jetton_wallet_gas_consumption;
          int receive transfer gas consumption = null?(jetton wallet gas consumption)
                ? RECEIVE TRANSFER GAS CONSUMPTION : jetton_wallet_gas_consumption;
          ;; 檢查 msg value 是否足夠支付所有轉帳相關費用。
          throw_unless(error::not_enough_gas, msg_value >
          ;; 轉帳涉及 3 條消息:從 wall -> wal2, wal2 -> owner, wal2 -> response
          ;; 最後一條消息是可選的, 如果失敗也沒問題。
          fwd_count * fwd_fee +
          get compute fee (MY WORKCHAIN, send transfer gas consumption) +
          get_compute_fee(MY_WORKCHAIN, receive_transfer_gas_consumption) +
          calculate_jetton_wallet_min_storage_fee() );
```

## ;;檢查燃燒操作的金額是否足夠

```
() check_amount_is_enough_to_burn(int msg_value) impure inline {
    int jetton_wallet_gas_consumption = get_precompiled_gas_consumption();
    int send_burn_gas_consumption = null?(jetton_wallet_gas_consumption)
        ? SEND_BURN_GAS_CONSUMPTION : jetton_wallet_gas_consumption;
    ;; 檢查 msg_value 是否足夠支付燃燒操作的轉發費用和 gas 費用
        throw_unless(error::not_enough_gas, msg_value > get_forward_fee(MY_WORKCHAIN,
        BURN_NOTIFICATION_BITS,
        BURN_NOTIFICATION_CELLS) + get_compute_fee(MY_WORKCHAIN, send_burn_gas_consumption)
        + get_compute_fee(MY_WORKCHAIN, RECEIVE_BURN_GAS_CONSUMPTION));
```