priority class & Preemption

priority class is a way to assign a priority value to a Pod, which determines its relative importance compared to other Pods. The priority value can be any integer between O and IOOOOOO, with higher values indicating higher priority.

Preemption policies determine whether a higher priority Pod can preempt(evict) a lower priority Pod to be scheduled on a node. There are three preemption policies:



Pod disruption budget

Pod Disruption Budget (PDB) in Kubernetes is a way to ensure that a certain number or percentage of pods with an application are not voluntarily evicted at the same time. This can help to maintain high availability during voluntary disruptions like upgrades and maintenance.

oluntary disruptions like upgrades and maintenance.

In this example, the Pod Disruption Budget named my-pdb specifies that at least two pods with the label app=my-app should be available at all times app: my-app

apiVersion: policy/v1

Bin packing

Bin packing in k8s refers to the process of efficiently utilizing resources by scheduling pods on nodes in a way that maximizes resource usage and minimizes wasted resources. Kubernetes achieves bin packing through its scheduler, which considers factors such as resource requests, limits, and available resources on nodes to make optimal scheduling decisions. Kubernetes scheduler follows two strategies to decide the scheduling of Pods:

BestFit: In this approach, the scheduler places the incoming Pod in the node with the least amount of free resources after placement. This strategy aims to leave as much space free as possible on every other node.

WorstFit: In this approach, the scheduler places the incoming Pod in the node with the most amount of free resources after placement. This strategy aims to fill up nodes as much as possible.

Placement failures can occur in bin packing scenarios in Kubernetes when the scheduler is unable to find a suitable node to schedule a pod due to resource constraints or other constraints defined in the cluster.

SCENATIO: there are three nodes in the cluster, each with 1000m of CPU and 2GB RAM. Currently, there are nine running pods (blue) with their allocated resource requests. However, a new pod (orange) with a request of 300m CPU and 600MB RAM cannot be scheduled. This is due to the unavailability of any node that satisfies both the CPU and RAM requirements of the new pod. Surprisingly, even though the entire cluster has a total of 600m CPU and 1200MB RAM available, the scheduler is unable to find a suitable node.



The operation of moving Pod A from Nodel to Node2 can be performed manually by directly interacting with the Kubernetes API.this can be done using command.Additionally, adjusting the priorities of your pods can help in scenarios where resources are scarce. By assigning appropriate priorities to your pods, you can

lly by directly interacting
ng the priorities of your pods
riorities to your pods, you can

YCPU 1 350

Mem 1 500

Mem 1 800

Mem 1

Problem 2: imbalanced placement

Total available capacity across keep vCPU: 300 mC memory: 600

ensure that critical pods have higher priorities compared to less critical pods. When resources become limited,
the Kubernetes scheduler can use these priorities to make decisions about which pods to preempt in order to make room for higher priority pods. By preempting lower
priority pods, Kubernetes ensures that critical pods get scheduled and receive the necessary resources. This helps in optimizing resource utilization and ensuring that
important workloads are given priority even in resource-constrained environments.

Pod X

Imbalanced placement in Kubernetes refers to a situation where the distribution of pods or workloads across the nodes in a Kubernetes cluster is uneven or skewed. This can lead to certain nodes being overloaded while others are underutilized, resulting in inefficient resource allocation and potential performance issues. There are a few common causes of imbalanced placement in Kubernetes:

There are a few common causes of imbalanced placement in Kubernetes:


Node labels and pod affinity/anti-affinity: Kubernetes provides mechanisms like node labels and pod affinity/anti-affinity rules to influence the placement of pods. If these rules are not properly configured or if there are inconsistencies in the labels, pods may not be distributed evenly across nodes. Resource requests and limits: Kubernetes allows you to specify resource requests and limits for pods, indicating the minimum and maximum amount of resources (CPU, memory) they require. If these values are set incorrectly or if there is a wide variation in the resource requirements of pods, it can lead to imbalanced placement.

Node capacity and utilization: If the nodes in a Kubernetes cluster have different capacities in terms of CPU, memory, or other resources, it can result in imbalanced placement. Nodes with higher capacity may end up hosting more pods, while nodes with lower capacity may remain underutilized.

scenario: Node! has high CPU usage (90%) but relatively low memory usage (25%). On the other hand, Node3 has low CPU usage (20%) but high memory usage (85%). This imbalance in resource utilization across the nodes can have the following impacts:

Pod B on Nodel: Since Pod B is a CPU-intensive process, the high CPU usage on Nodel indicates that there might be limited CPU resources available for Pod B during peak load situations. This can result in Pod B experiencing CPU starvation, leading to degraded performance or even failures if it requires more CPU resources than what is available.

Pod E on Node3: As Node3 has high memory usage (85%), Pod E, which is running on Node3, might face memory starvation during peak load scenarios. If Pod E requires additional memory resources that are not available due to high memory usage on Node3, it can lead to out-of-memory errors or performance degradation



If we swap Pod B and Pod F between Nodel and Node3, the observation and impact remain the same. Nodel still has 40% CPU usage and 48% memory usage, while Node3 has 50% CPU usage and 55% memory usage. With these resource utilization levels, any pods on these two nodes should still be able to handle any kind of peak load without experiencing resource starvation or performance degradation

Daemonset

A DaemonSet is a type of controller that ensures that all (or some) nodes in a cluster run a copy of a specific pod. It is often used for system-level tasks that should be run on every node, such as log collection, monitoring, or other types of background tasks

When you create a DaemonSet, Kubernetes automatically creates a pod on each node that matches the specified label selector. If a new node is added to the cluster, Kubernetes automatically creates a new pod on that node as well

By using labels and node selectors, you can specify which nodes in the Kubernetes cluster should run a particular DaemonSet. This allows you to restrict the execution of the DaemonSet to specific nodes

Only on nodes that have this label, a pod of the DaemonSet type is automatically created

what is the best way to test a Daemon Set on a limited number of nodes without consuming too many resources from the customer's service?

One approach could be to create a separate namespace with a ResourceQuota that limits the amount of resources that can be used by the DaemonSet. This will ensure that the DaemonSet does not consume too many resources from the customer's service

metadata:
name: monitoring-deamon
namespace: dev-drive-monitor
spec:
template:
metadata:
labels:
app: monitoring
spec:
containers:
- name: monitoring-agent
image: monitoring-agent
nodeSelector:
Drive: ssd

selector:
matchLabels:
app: monitoring

apiVersion: apps/v1 kind: DaemonSet

selector used to identify which pods are managed by the DaemonSet



Add a new node:


DaemonSet automatically create a new pod on the node

Static Pod

A static pod is a pod that is managed directly by the kubelet on a specific node, rather than by the Kubernetes API server. A static pod is defined by a YAML manifest file that is placed in a specific directory on the node, and the kubelet monitors that directory for changes to the manifest file

The containers come up statically, and their manifest file is located in the directory /etc/kubernetes/manifests. This means that the Kubernetes components, such as the API server, controller manager, and scheduler, are started as containers using pre-defined manifests located in the /etc/kubernetes/manifests directory





l	kubectlnamespace kube-system get pods -o wide						
l	NAME	READY	STATUS	RESTARTS	AGE	IP	NODE
l	etcd-kubemaster-1	1/1	Running	4	6d2h	192.168.100.11	kubemaster-1
	kube-apiserver-kubemaster-1	1/1	Running	3	6d2h	192.168.100.11	kubemaster-1
l	kube-controller-manager-kubemaster-1	1/1	Running	3	6d2h	192.168.100.11	kubemaster-1
	kube-scheduler-kubemaster-1	1/1	Running	3	6d2h	192.168.100.11	kubemaster-1

To delete a static pod in Kubernetes, you can either delete its corresponding manifest file from StaticPodPath or move the manifest file file to another path. Use the following command to remove the manifest file:

[sudo rm /etc/kubernetes/manifests/static-pod-manifest.yaml>]

Replace <static-pod-manifest.yaml> with the filename of the manifest associated with the static pod you want to delete.

After performing either of these operations, the kubelet running on the node will detect the change in the static pod directory. It will stop managing the static pod associated with the deleted or moved YAML file, and Kubernetes will initiate the termination process for that pod.

Static PODs	DaemonSets			
Created by the kubelet	Created by Kube-API server			
Deploy Control Plane components as static pods	Deploy Monitoring Agents, logging Agents on nodes			
ignored by the kube-scheduler				

Metrics Server

The Metrics Server is a component of Kubernetes that provides container resource metrics for built-in autoscaling pipelines. It collects resource metrics from Kubelets and exposes them through the Metrics API in the Kubernetes API server. These metrics can be used by the Horizontal Pod Autoscaler and Vertical Pod Autoscaler for autoscaling purposes

