



Amazon EC2 provides a broad selection of instance types to accommodate a diverse mix of workloads. In this session, we provide an overview of the Amazon EC2 instance platform, key platform features, and the concept of instance generations. We dive into the current generation design choices of the different instance families, including the General Purpose, Compute Optimized, Storage Optimized, Memory Optimized, and GPU instance families. We also detail best practices and share performance tips for getting the most out of your Amazon EC2 instances.

### What to Expect from the Session

- Understanding the factors that going into choosing an EC2 instance
- Defining system performance and how it is characterized for different workloads
- How Amazon EC2 instances deliver performance while providing flexibility and agility
- How to make the most of your EC2 instance experience through the lens of several instance types


Customers for HPC using Ec2 instances are doing things like CFD, Gene Sequencing and Semiconductor design and performance is really important to them.






An EC2 instance is a VM, they are the guests sitting on a hypervisor on a host server.


### In the past First launched in August 2006 M1 instance One size fits all"



The introduction of the cc2 instance types came with the features that gives you the ability to define the physical topology of your EC2 instances using *Placement Groups*, where you can now define that your instances be located physically close together for the best possible bandwidth and lowest latency. This is also when we introduce Hardware Assisted Virtualization *HVM*, that allows you to use much of the underlying hardware and not spend so much time talking to the hypervisor.



C for compute, R for RAM, I for IOPS, etc.




You have so many instance options to choose from when trying to launch your EC2 instance. Find the right instance family, for an application needed lots of memory then start with something like the R3 instance, if you need a lot of compute then start with a C4 instance, if you have an application that is pretty well balanced then you should start with a general-purpose family like a M4 or T2 instance. You can then do some testing to find the correct instance size to use within the chosen family. Check the EC2 documentation for a list of workload and types to use.

### What's a Virtual CPU? (vCPU)

- A vCPU is typically a hyper-threaded physical core\*
- On Linux, "A" threads enumerated before "B" threads
- On Windows, threads are interleaved
- Divide vCPU count by 2 to get core count
- Cores by EC2 & RDS DB Instance type: https://aws.amazon.com/ec2/virtualcores/

\* The "t" family is special


Hyper-threading is a technology that lets you get more out of your CPU, it lets your CPU do almost 2 things at once such as a process that can get blocked on I/O.




To visualize what a vCPU looks like, here is the output of a program called LS-Topo that gives you a visual representation of the underlying hardware of your instance. Above is the output for a *m4.10xlarge* instance, you can see how many sockets it has and how much memory is attached to each socket, the L1 to L3 cache that it has, the physical core count and the threads attached to each core.

```
Disable Hyper-Threading If You Need To
   Useful for FPU heavy applications
                                                     [ec2-user@ip-172-31-7-218 ~]$ lscpu
   Use 'Iscpu' to validate layout
                                                    Thread(s) per core:
                                                    Core(s) per socket:
   Hot offline the "B" threads
                                                    NUMA node (s):
for i in `seq 64 127`; do
                                                                       Xen
                                                     Virtualization type:
   echo 0 > /sys/devices/system/cpu/cpu${i}/online
                                                    NUMA node0 CPU(s):
                                                    NUMA node2 CPU(s):
   Set grub to only initialize the first half of
   all threads
```

Compute heavy applications like financial risk and engineering simulations do not benefit from hyper-threading due to the very many contexts switching they do. They normally disable hyper-threading in these cases using the commands above by turning off the 'B' threads or set a grub boot parameter on the instances.



This is with hyper-threading disabled



### **Resource Allocation**

- All resources assigned to you are dedicated to your instance with no over commitment\*
  - All vCPUs are dedicated to you
  - Memory allocated is assigned only to your instance
  - Network resources are partitioned to avoid "noisy neighbors"
- Curious about the number of instances per host? Use "Dedicated Hosts" as a guide.

\*Again, the "T" family is special

"Launching new instances and running tests in parallel is easy...[when choosing an instance] there is no substitute for measuring the performance of your full application."

- EC2 documentation

### **Timekeeping Explained**

- Timekeeping in an instance is deceptively hard
- gettimeofday(), clock\_gettime(), QueryPerformanceCounter()
- The TSC
  - CPU counter, accessible from userspace
  - Requires calibration, vDSO
  - Invariant on Sandy Bridge+ processors
- Xen pvclock; does not support vDSO
- On current generation instances, use TSC as clocksource

**Most instances will use the Xen clock source by default** because this is compatible with every single instance that is available from AWS.

### **Benchmarking - Time Intensive Application**

This demo app performs a lot of getTimeOfDay() calls and a little bit of floating point math.

Contract of the Contract of th		1-77 testbend	cn] strace	-c ./tes	· L
		00 seconds. usecs/call	calls	errors	syscall
99.99	3.322956	2	2001862		gettimeofday
0.00	0.000096	6	16		mmap
0.00	0.000050	5	10		mprotect
0.00	0.000038	8	5		open
0.00	0.000026	5	5		fstat
0.00	0.000025	5	5		close
0.00	0.000023	6	4		read
0.00	0.000008	8	1	1	access
0.00	0.000006	6	1		brk
0.00	0.000006	6	1		execve
0.00	0.000005	5	1		arch_prct1
0.00	0.000000	0	1		munmap

This is the result with the **Xen clock source** using the **strace** profiling tool

### **Using the TSC Clock Source**

[centos@ip-192-168-1-77 testbench]\$ strace -c ./test Elasped time is 2.00 seconds.

% time	seconds	usecs/call	calls	errors	syscall
32.97	0.000121	7	17		mmap
20.98	0.000077	8	10		mprotect
11.72	0.000043	9	5		open
10.08	0.000037	7	5		close
7.36	0.000027	5	6		fstat
6.81	0.000025	6	4		read
2.72	0.000010	10	1		munmap
2.18	0.000008	8	1	1	access
1.91	0.000007	7	1		execve
1.63	0.000006	6	1		brk
1.63	0.000006	6	1		arch_prctl
0.00	0.000000	0	1		write
100.00	0.000367		53	1	total

This is the result of using the *TSC clock source*, this is so fast just by switching the clock source.

### Tip: Use TSC as clocksource



```
# cat /sys/devices/system/cl*/cl*/available_clocksource
xen tsc hpet acpi_pm
```

# cat /sys/devices/system/cl\*/cl\*/current\_clocksource
xen


### Change with:

# echo tsc > /sys/devices/system/cl\*/cl\*/current\_clocksource

The change is easy to make on Linux, choose TSC if you have it to get up to 40% better performance for an app that does a lot of time keeping calls

### P-state and C-state Control

- c4.8xlarge, d2.8xlarge, m4.10xlarge, m4.16xlarge, p2.16xlarge, x1.16xlarge, x1.32xlarge
- By entering deeper idle states, non-idle cores can achieve up to 300MHz higher clock frequencies
- But... deeper idle states require more time to exit, may not be appropriate for latency-sensitive workloads
- Limit c-state by adding "intel\_idle.max\_cstate=1" to grub



### Tip: P-state Control for AVX2

- If an application makes heavy use of AVX2 on all cores, the processor may attempt to draw more power than it should
- Processor will transparently reduce frequency
- Frequent changes of CPU frequency can slow an application

sudo sh -c "echo 1 > /sys/devices/system/cpu/intel\_pstate/no\_turbo"

See also: http://docs.aws.amazon.com/AWSEC2/latest/UserGuide/processor\_state\_control.html


### **Review: T2 Instances**


- Lowest cost EC2 instance at \$0.0065 per hour
- Burstable performance
- Fixed allocation enforced with CPU credits

Model	vCPU	Baseline	CPU Credits / Hour	Memory (GiB)	Storage
t2.nano	1	5%	3	.5	EBS Only
t2.micro	1	10%	6	1	EBS Only
t2.small	1	20%	12	2	EBS Only
t2.medium	2	40%**	24	4	EBS Only
t2.large	2	60%**	36	8	EBS Only

General purpose, web serving, developer environments, small databases

These are great for workloads that have burstable CPU performance like database servers, websites, and dev environments.





There are 2 different CloudWatch metrics that you can monitor to see your available credit for boosting in your EC2 t2 instances.


### **Review: X1 Instances**

- Largest memory instance with 2 TB of DRAM
- Quad socket, Intel E7 processors with 128 vCPUs

Model	vCPU	Memory (GiB)	Local Storage	Network
x1.16xlarge	64	976	1x 1920GB SSD	10Gbps
x1.32xlarge	128	1952	2x 1920GB SSD	20Gbps


In-memory databases, big data processing, HPC workloads

## Non-uniform memory access Each processor in a multi-CPU system has local memory that is accessible through a fast interconnect Each processor can also access memory from other CPUs, but local memory access is a lot faster than remote memory Performance is related to the number of CPU sockets and how they are connected -



Intel QuickPath Interconnect (QPI)

This is a 2-socket box with 122GB RAM attached to each socket to give 16 vCPUs, the sockets can communicate over the QPI paths. So, if you have an application that is running on the socket on the left that is copying data from the memory on the socket on the right, its going to send/get that data over those QPI paths which while fast, are never going to be as fast as accessing memory that is local to that socket.



There are 4 sockets in the x1 instance and things get more complex and NUMA is even more important. We now have far more memory per socket and just 1 QPI connecting each socket to any other socket. This means that memory transfer from one NUMA zone to another NUMA zone are going to take longer here on the x1 instance than they would take on the r3 instance. What can you do about this?

### Tip: Kernel Support for NUMA Balancing

- An application will perform best when the threads of its processes are accessing memory on the same NUMA node.
- NUMA balancing moves tasks closer to the memory they are accessing.
- This is all done automatically by the Linux kernel when automatic NUMA balancing is active: version 3.8+ of the Linux kernel.
- Windows support for NUMA first appeared in the Enterprise and Data Center SKUs of Windows Server 2003.
- Set "numa=off" or use numactl to reduce NUMA paging if your application uses more memory than will fit on a single socket or has threads that move between sockets

### **Operating Systems Impact Performance**

- Memory intensive web application
  - Created many threads
  - Rapidly allocated/deallocated memory
- Comparing performance of RHEL6 vs RHEL7
- Notice high amount of "system" time in top
- Found a benchmark tool (ebizzy) with a similar performance profile
- Traced it's performance with "perf"


```
On RHEL6

[ec2-user@ip-172-31-12-150-RHEL6 ebizzy-0.3]$ sudo perf stat ./ebizzy -S 10
12,409 records/s
real 10.00 s
user 7.37 s
sys 341.22 s


Performance counter stats for './ebizzy -S 10':

361458.371052 task-clock (msec) # 35.880 CPUs utilized
10,343 context-switches # 0.029 K/sec
2,582 cpu-migrations # 0.007 K/sec
1,418,204 page-faults # 0.004 M/sec
```

We used a performance testing tool called *ebizzy* that we used to test the web application on the RHEL 6 operating system, we used the *\$ sudo perf stat./ebizzy -s 10* command for a 10 second run. We also profiled the same application using the *perf* tool that can help us understand what is going on at the system level on the web application also as seen above. We are getting a lot of context switches for this 10 sec run.



We also used the Flame graph tool to understand where the time is being spent in the web app and the code paths.




We then took this same exact code and recompiled it for RHEL 7 and ran the exact same test, our performance went from 12,000 records to 425,000 records


## Flame Graph Flame Graph Flame Graph Flame Graph Flame Graph Function: \_\_memcpy\_ssse3\_back (39,290 samples, 99,02%)

Again, we see the flame graph for this case, in RHEL 7, glibc changed the way some things were being done. Always try to run your application on the latest AWS images available

## Hugepages Disable Transparent Hugepages # echo never > /sys/kernel/mm/redhat\_transparent\_hugepage/enabled # echo never > /sys/kernel/mm/redhat\_transparent\_hugepage/defrag Use Explicit Huge Pages sudo mkdir /dev/hugetlbfs sudo mount -t hugetlbfs none /dev/hugetlbfs sudo sysctl -w vm.nr\_hugepages=10000 HUGETLB\_MORECORE=yes LD\_PRELOAD=libhugetlbfs.so numactl --cpunodebind=0 \ --membind=0 /path/to/application See also: https://lwn.net/Articles/375096/



There are a few I instance families that are optimized for I/O usage, they have a bunch of SSD drives. The D2 instances have dense storage that use magnetic drives. To get the best performance from these instances you need to be running a modern Linux kernel on a modern OS, this is because of the split driver model that Xen uses.



This is very cumbersome and not easy to do on your own

# Granting in 3.8.0+ Kernels, Persistent and Indirect I/O domain Instance Copy to and from grant pool Grant mappings are set up in a pool one time Data is copied in and out of the grant pool

This approach will help you solve that problem

### **Validating Persistent Grants**

[ec2-user@ip-172-31-4-129 ~]\$ dmesg | egrep -i 'blkfront'

Blkfront and the Xen platform PCI driver have been compiled for this kernel: unplug emulated disks.

blkfront: xvda: barrier or flush: disabled; persistent grants: enabled; indirect descriptors: enabled; blkfront: xvdb: flush diskcache: enabled; persistent grants: enabled; indirect descriptors: enabled; blkfront: xvdc: flush diskcache: enabled; persistent grants: enabled; indirect descriptors: enabled; blkfront: xvdd: flush diskcache: enabled; persistent grants: enabled; indirect descriptors: enabled; blkfront: xvde: flush diskcache: enabled; persistent grants: enabled; indirect descriptors: enabled; blkfront: xvdf: flush diskcache: enabled; persistent grants: enabled; indirect descriptors: enabled; blkfront: xvdg: flush diskcache: enabled; persistent grants: enabled; indirect descriptors: enabled; blkfront: xvdh: flush diskcache: enabled; persistent grants: enabled; indirect descriptors: enabled; blkfront: xvdh: flush diskcache: enabled; persistent grants: enabled; indirect descriptors: enabled; blkfront: xvdi: flush diskcache: enabled; persistent grants: enabled; indirect descriptors: enabled;

### 2009 - Longer ago than you think

- Avatar was the top movie in the theaters
- Facebook overtook MySpace in active users
- President Obama was sworn into office
- The 2.6.32 Linux kernel was released

### Tip: Use 3.10+ kernel

- Amazon Linux 13.09 or later
- Ubuntu 14.04 or later
- RHEL/Centos 7 or later
- Etc.




Please use a modern OS with a modern kernel

### **Device Pass Through: Enhanced Networking**


- SR-IOV eliminates need for driver domain
- Physical network device exposes virtual function to instance
- Requires a specialized driver, which means:
  - Your instance OS needs to know about it
  - EC2 needs to be told your instance can use it



Enhanced Networking is a new way to talk to networked devices, it uses the technology called *Single Root I/O Virtualization SR-IOV* to allow the physical network device be exposed directly to your OS so that your calls do not need to go through the hypervisor. You need a special driver to be installed in your OS and EC2 needs to be told to expose the networked device in the correct way



The networked path is much simpler and packets don't need to go through the hypervisor anymore. Also, because you are now talking to bare metal, you will get a higher rate of packets per second and decreased jitter because the CPU is no longer involved in the process. Enhanced Networking is free on all supported instances and is enabled by default in most AMIs, it is highly to have enhanced networking feature turned on if you are doing anything that touches the network on an EC2 instance.



The Elastic Network Adapter ENA is on some bigger instances, it offers you up to 20 Gbps as opposed to the 10Gbps that you get with enhanced networking communication between instances in the same placement groups. It also has some other features that help you get more packets per second moved.

### **Network Performance**

- 20 Gigabit & 10 Gigabit
  - Measured one-way, double that for bi-directional (full duplex)
- High, Moderate, Low A function of the instance size and EBS optimization
  - Not all created equal Test with iperf if it's important!
- Use placement groups when you need high and consistent instance to instance bandwidth
- All traffic limited to 5 Gb/s when exiting EC2

When talking to S3 from an EC2 instance, you will be capped at 5 Gbps

### **EBS Performance**

- Instance size affects throughput
- Match your volume size and type to your instance
- Use EBS optimization if EBS performance is important

Instance type	EBS-optimized by default	Max. bandwidth (MiB/s)*	Max. IOPS (16 KIB I/O size)*	Throughput (Mbps)**
dl.wlarge		62.5	4,000	500
m2.Zalarge		125	8,000	1,000
dl. Calarge		250	16,000	2,000
C4.large	Yes	62.5	4,000	500
Of.wlarge	Yes	93.75	6,000	750
ot.telarge	Yes	250	16,000	2,000
pi.fslarps	Yes	500	32,000	4,000
dliminrow	Yes	93.75	6.000	750
d2.2xlarge	Yes	125	8,000	1,000
dl.4slarge	Yes.	250	16,000	2,000
d7.Existge	Ves	500	32,000	4.000
g2.Zxlarge		125	8,000	1,000
17. rlarge		62.5	4,000	500
12.2xlarge		125	8,000	1,000
17. Criarge		250	16,000	2,000
m3.xlarge		62.5	4,000	500
m3.7xlarge		125	8,000	1,000
mi-large	Yes	56.25	3,600	450
milarque	Yes	93.75	6,000	750
m4.7slarge	Yes	125	8,000	1,000
mt. txlange	Yes	250	16,000	2,000
m4.TOxlarge	Yes	500	32,000	4,000

EBS optimization is fast because it uses a separate connection that that used to communicate with other EC2 instances, this is good when you are doing a lot of data storage heavily. It is enabled by default on a lot of instances.

### Summary: Getting the Most Out of EC2 Instances

- Choose HVM AMIs
- Timekeeping: use TSC
- C state and P state controls
- Monitor T2 CPU credits
- Use a modern Linux OS
- NUMA balancing
- Persistent grants for I/O performance
- Enhanced networking
- Profile your application

### **Virtualization Themes**

- Bare metal performance goal, and in many scenarios already there
- History of eliminating hypervisor intermediation and driver domains
  - Hardware assisted virtualization
  - Scheduling and granting efficiencies
  - Device pass through



### **Next Steps**

- Visit the Amazon EC2 documentation
- Launch an instance and try your app!