数据链路层7: 以太通道配置

实验目的

- 1. 理解以太通道的目的和作用。
- 2. 掌握以太通道的要求和条件。
- 3. 掌握以太通道的配置。

实验内容

1、以太通道基础知识。

以太通道(EthernetChannel)是交换机将多个物理端口聚合成一个逻辑端口,可将其理解为一个端口。通过端口聚合,可以提高交换机间的带宽。例如,当2个100M带宽的端口聚合后,就可生成一个200M带宽的逻辑端口。在某种情况下,当带宽不够而又有多余端口时,可以通过聚合来满足需求,节省费用。

一个以太通道内的几个物理端口还可以实现负载均衡,当某个端口出现故障时,逻辑端口内的其他端口 将自动承载其余的流量。

参与聚合的各端口必须具有相同的属性,如速率、trunk模式和单双工模式等。

端口聚合可以采用手工方式配置,也可使用动态协议来聚合。PAgP端口聚合协议是Cisco专有的协议,LACP协议是公共的标准。

常用配置命令如下表所示。

表常用配置命令

命令格式	含义
interface port- channel 聚合逻辑端口号	用来在全局配置模式下创建聚合端口号,如switch(config)#int port-channel 1,该命令创建聚合逻辑端口号1
channel-group 聚合逻辑端口号 mode on{auto desirable}	该命令在接口模式下用来应用聚合端口。有三种模式可选, 其中auto表示交换机被动形成一个聚合端口,不发送 PAgP分组, 是默认值。on表示不发送PAgP分组。desirable表示发送 PAgP分组

命令格式	含义
port-channel load- balance 负载平衡方式	可按源IP地址、目的IP地址、源MAC地址、目的MAC地址进行负载平衡
show interfaces ethernetchannel	用来查看以太通道状态
show ethernetchannel summary	查看以太通道汇总信息


2、实验流程



实验步骤

1、布置拓扑。

如下图所示,拓扑中两台交换机的Fa0/1、Fa0/2和Fa0/3三个端口分别对应连接,但只有一条链路是通的,这是因为生成树默认开启的原因,另两条链路被阻塞了。



2、配置以太通道。

通过配置以太通道,使连接交换机的3条链路全部起作用,如下图所示。 交换机Switch0:

```
Switch>en
Switch#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Switch(config)#int port-channel 5
Switch(config-if)#exit
Switch(config)#int range f0/1-3
Switch(config-if-range)#channel-group 5 mode on
Switch(config-if-range)#exit
Switch(config)#port-channel load-balance
% Incomplete command.
Switch(config)#port-channel load-balance src-mac
Switch(config)#int port-channel 5
Switch(config-if)#switch mode trunk
Switch(config-if)#
```

交换机Switch1:

```
Switch>en
Switch#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Switch(config)#int port-channel 5
Switch(config-if)#exit
Switch(config)#int range f0/1-3
Switch(config-if-range)#channel-group 5 mode on
Switch(config-if-range)#
%LINK-5-CHANGED: Interface Port-channel5, changed state to up
```

%LINEPROTO-5-UPDOWN: Line protocol on Interface Port-channel5, changed state to up

 $\&EC-5-CANNOT_BUNDLE2$: Fa0/3 is not compatible with Fa0/1 and will be suspended (dtp mode of Fa0/3 is off, Fa0/1is).

%EC-5-CANNOT_BUNDLE2: Fa0/3 is not compatible with Fa0/2 and will be suspended (dtp mode of Fa0/3 is off, Fa0/2is


%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/3, changed state to down exit

Switch(config)#port-channel load-balance src-mac


Switch(config)#int port-channel 5

Switch(config-if)#

Switch(config-if)#switch mode trunk



3、验证两台主机能否ping通。请截图。



4、查看以太通道的汇总信息。

交换机 Switch0的信息如下:

```
Switch>en
Switch#show etherchannel summary
Flags: D - down
                        P - in port-channel
        I - stand-alone s - suspended
        H - Hot-standby (LACP only)
        R - Layer3
                        S - Layer2
        U - in use
                        f - failed to allocate aggregator
        u - unsuitable for bundling
        w - waiting to be aggregated
        d - default port
Number of channel-groups in use: 1
Number of aggregators:
Group Port-channel Protocol
                                 Ports
       Po5(SU)
                                Fa0/1(P) Fa0/2(P) Fa0/3(P)
Switch#
```