

## Managing Licenses Across Server

[https://www.mathworks.com/help/polyspace\\_access/install/configure-polyspace-access-license.html](https://www.mathworks.com/help/polyspace_access/install/configure-polyspace-access-license.html)


### Prerequisites

- Install the license manager and configure the Polyspace Access license

Navigate to license manager directory and use the command below to check if licenses have been setup correctly

```
lmutil.exe lmstat -c "C:\Program Files\MATLAB\R2025b_PolyspaceServer\etc\license.dat" -a
```

Check and note down the hostname and port number.



```
C:\Windows\System32\cmd.exe
C:\Program Files\MATLAB\R2025b_PolyspaceServer\etc\win64>lmutil.exe lmstat -c "C:\Program Files\MATLAB\R2025b_PolyspaceServer\etc\license.dat" -a
lmutil - Copyright (c) 1989-2024 Flexera. All Rights Reserved.
Flexible License Manager status on Mon 12/29/2025 15:52

[Detecting lmgrd processes...]
license server status: 27000@TSA-06
  License file(s) on TSA-06: C:\Program Files\MATLAB\R2025b_PolyspaceServer\etc\license.dat:
    TSA-06: license server UP (MASTER) v11.19.6

Vendor daemon status (on TSA-06):
  MLM: UP v11.19.6
Feature usage info:
Users of Polyspace_BF_Access: (Total of 6 licenses issued; Total of 1 license in use)

"Polyspace_BF_Access" v54, vendor: MLM, expiry: 11-feb-2026
  vendor_string: vi=0:at=276:lu=100:ei=13518889:lr=1:ep=7:sl=5:
  floating license
    Demo b474a6928062 /dev/tty (v54) (TSA-06/27000 409), start Mon 12/29 12:30, PID: 14
Users of Polyspace_BF_Server: (Total of 3 licenses issued; Total of 0 licenses in use)
Users of Polyspace_CP_Server: (Total of 3 licenses issued; Total of 0 licenses in use)
Users of Polyspace_BF: (Total of 6 licenses issued; Total of 1 license in use)

"Polyspace_BF" v54, vendor: MLM, expiry: 11-feb-2026
  vendor_string: vi=0:at=276:lu=100:ei=13518919:lr=1:ep=7:
  floating license
    Demo TSA-06 TSA-06 (v54) (TSA-06/27000 105), start Mon 12/29 15:30, PID: 11932
Users of Polyspace_BF_Engine: (Total of 6 licenses issued; Total of 0 licenses in use)
Users of Polyspace_CP: (Total of 6 licenses issued; Total of 0 licenses in use)
Users of Polyspace_Test: (Total of 1 license issued; Total of 0 licenses in use)
```

### Configure Network License Manager Access

On your Ubuntu, you need to specify the license server location:

```
export MLM_LICENSE_FILE=port@hostname
```

Replace port with your license manager port and hostname with your Windows machine's IP address or hostname.

To make this permanent, add it to your ~/.bashrc:

```
echo 'export MLM_LICENSE_FILE=27000@TSA-06' >> ~/.bashrc
source ~/.bashrc
```

```
/usr/local/Polyspace_Server/R2025b/polyspace/bin$ export MLM_LICENSE_FILE=27000@TSA-06
/usr/local/Polyspace_Server/R2025b/polyspace/bin$ echo 'export MLM_LICENSE_FILE=27000@TSA-06' >> ~/.bashrc
/usr/local/Polyspace_Server/R2025b/polyspace/bin$ source ~/.bashrc
```


Navigate to /usr/local/ to update or create the license file:

```
sudo mkdir MATLAB
cd MATLAB/
sudo mkdir licenses
sudo nano network.lic
```

```
polyspace-server-06@polyspace-server-06-VMware-Virtual-Platform:/usr/local$ sudo mkdir MATLAB
polyspace-server-06@polyspace-server-06-VMware-Virtual-Platform:/usr/local$ cd MATLAB/
polyspace-server-06@polyspace-server-06-VMware-Virtual-Platform:/usr/local/MATLAB$ sudo mkdir licenses
polyspace-server-06@polyspace-server-06-VMware-Virtual-Platform:/usr/local/MATLAB$ cd licenses/
polyspace-server-06@polyspace-server-06-VMware-Virtual-Platform:/usr/local/MATLAB/licenses$ sudo nano network.lic
```

Add and save:

```
SERVER <windows_hostname> ANY 27000
USE_SERVER
```



```
GNU nano 8.4
SERVER TSA-06 ANY 27000
USE_SERVER
```

## Configure Firewall Rules

### 1. Open Windows Defender Firewall

1. Press Windows Key + R
2. Type wf.msc and press Enter
3. Or navigate: Control Panel → System and Security → Windows Defender Firewall → Advanced settings

### 2. Create New Inbound Rule

1. In the left pane, click **Inbound Rules**
2. In the right pane, click **New Rule...**
3. Select **Port** and click **Next**
4. Select **TCP** and enter **27000** in "Specific local ports" (or your license manager port)
5. Click **Next**
6. Select **Allow the connection** and click **Next**
7. Check all three options: Domain, Private, and Public
8. Click **Next**
9. Give it a name like "MATLAB License Manager" and click **Finish**


### 3. Find the License Manager Executable

Typically located at:

- C:\Program Files\MATLAB\R20XXx\etc\win64\lmgrd.exe
- C:\Program Files\MATLAB\R20XXx\etc\win64\MLM.exe

## 4. Create Program Rule

1. In Windows Defender Firewall (Advanced Settings)
2. Click **Inbound Rules** → **New Rule...**
3. Select **Program** and click **Next**
4. Click **Browse** and navigate to `lmgrd.exe`
5. Click **Next**
6. Select **Allow the connection**
7. Check Domain, Private, and Public
8. Name it "MATLAB lmgrd" and click **Finish**
9. Repeat for MLM.exe



## Restarting License Manager on Windows

### 1. Open Services


- Press Windows Key + R
- Type `services.msc` and press Enter

### 2. Find and Restart the Service

Scroll down to find one of these services:

- "MATLAB License Manager"

Right-click on the service. Select **Restart**



## Connection Test from Server

Verify if the Ubuntu server can reach the license manager and port



ping hostname

```
polyspace-server-06@polyspace-server-06-VMware-Virtual-Platform:~/Documents/sources$ ping TSA-06
PING TSA-06.localdomain (169.254.178.231) 56(84) bytes of data.
64 bytes from 169.254.178.231: icmp_seq=1 ttl=128 time=0.429 ms
64 bytes from 169.254.178.231: icmp_seq=2 ttl=128 time=0.490 ms
64 bytes from 169.254.178.231: icmp_seq=3 ttl=128 time=0.568 ms
64 bytes from 169.254.178.231: icmp_seq=4 ttl=128 time=0.516 ms
64 bytes from 169.254.178.231: icmp_seq=5 ttl=128 time=0.476 ms
64 bytes from 169.254.178.231: icmp_seq=6 ttl=128 time=0.444 ms
64 bytes from 169.254.178.231: icmp_seq=7 ttl=128 time=0.450 ms
64 bytes from 169.254.178.231: icmp_seq=8 ttl=128 time=0.512 ms
```

nc -zv hostname port

```
polyspace-server-06@polyspace-server-06-VMware-Virtual-Platform:~/Downloads/polyspace-access-R2025b/ln/glnxa64$ nc -zv TSA-06 27000
Connection to TSA-06 (169.254.178.231) 27000 port [tcp/*] succeeded!
```

Once succeeded, verify if Ubuntu server can reach the license manager

./lmutil lmstat -a -c "port@hostname"

```
polyspace-server-06@polyspace-server-06-VMware-Virtual-Platform:~/Downloads/polyspace-access-R2025b/ln/glnxa64$ ./lmutil lmstat -a -c "27000@TSA-06"
lmutil - Copyright (c) 1989-2024 Flexera. All Rights Reserved.
Flexible License Manager status on Tue 12/30/2025 10:40

License server status: 27000@TSA-06
  License file(s) on TSA-06: C:\Program Files\MATLAB\R2025b_PolyspaceServer\etc\license.dat:

  TSA-06: license server UP (MASTER) v11.19.6

Vendor daemon status (on TSA-06):

  MLM: UP v11.19.6
Feature usage info:

Users of Polyspace_BF_Access: (Total of 6 licenses issued; Total of 1 license in use)

"Polyspace_BF_Access" v54, vendor: MLM, expiry: 11-feb-2026
  vendor_string: vi=0:at=276:lu=100:ei=13518889:lr=1:ep=7:sl=5:
  floating license

  Demo b474a6928062 /dev/tty (v54) (TSA-06/27000 201), start Tue 12/30 10:39, PID: 14

Users of Polyspace_BF_Server: (Total of 3 licenses issued; Total of 0 licenses in use)

Users of Polyspace_CP_Server: (Total of 3 licenses issued; Total of 0 licenses in use)

Users of Polyspace_BF: (Total of 6 licenses issued; Total of 1 license in use)

"Polyspace_BF" v54, vendor: MLM, expiry: 11-feb-2026
  vendor_string: vi=0:at=276:lu=100:ei=13518919:lr=1:ep=7:
  floating license

  Demo TSA-06 TSA-06 (v54) (TSA-06/27000 101), start Tue 12/30 10:28, PID: 5140

Users of Polyspace_BF_Engine: (Total of 6 licenses issued; Total of 0 licenses in use)

Users of Polyspace_CP: (Total of 6 licenses issued; Total of 0 licenses in use)

Users of Polyspace_Test: (Total of 1 license issued; Total of 0 licenses in use)
```