



AutoProgression

Complete Manual

Ascension, purchases, quests, craftables, minions, resources, configuration, and troubleshooting

Version 1.0.0 | Tashi

AutoProgression is the account-progression and maintenance module in Tashi's Full Automation Suite. It coordinates normal Ascension, purchases, craftables, materials, eggs, paid bonuses, and quest maintenance.

This manual covers configuration version 10. New users should begin with the User Guide.

Reference Chapters

- 1 Installation and Upgrading
- 2 Quick Start and Global Control
- 3 Ascension and Purchases
- 4 Craftables and Materials
- 5 Quest Maintenance
- 6 Minions, Eggs, and Paid Bonuses
- 7 Runtime Scope and Safety
- 8 Configuration Reference
- 9 Logging Reference
- 10 Troubleshooting

Module Responsibilities

- AutoProgression handles purchases, normal Ascension, craftables, materials, eggs, and quest maintenance.
- AutoAdventurer selects and performs supported quest objectives, travels between dimensions, and controls Rage and movement helpers.
- AutoClimber controls Ascending Heights routes, enemies, and rewards.

The mods can be used independently or together.

Default Control

Key	Action
T	Toggle the AutoProgression runtime

The runtime starts disabled. Feature preferences remain saved when T is turned off.

Safety Principles

- Ultra Ascension is never invoked.
- Automation runs only in a stable central Runner or Rage scene.
- Ascension applies a global two-second lock and clears cached game objects.
- Item actions are limited to one per second.
- Missing IL2CPP objects cause a safe retry instead of a forced action.
- Jewel-spending behavior is explicit in configuration descriptions and logs.
- Quest filters react to generated sets rather than continuously rewriting existing or manually rerolled tasks.

Support Development

If these mods save you time, you can support continued development through [PayPal](#).

Installation and Upgrading

Requirements

- Idle Slayer Mod Manager with MelonLoader initialized
- Idle Slayer Mods Core
- A compatible AutoProgression ZIP or DLL

Mod Manager Installation

- 1 Import `AutoProgression.zip` without extracting it.
- 2 Enable AutoProgression in the manager.
- 3 Start Idle Slayer through the configured loader.

Manual Installation

Copy `AutoProgression.dll` to:

```
%LOCALAPPDATA%\IdleSlayerModManager\ModLoader\Mods\
```

The generated configuration is stored at:

```
%LOCALAPPDATA%\IdleSlayerModManager\ModLoader\UserData\AutoProgression.cfg
```

Upgrading

Replace the old DLL or import the new ZIP, then restart the game. Configuration schema migrations preserve supported existing values and add new entries. Keeping a backup of the configuration is still recommended.

Quick Start and Global Control

- 1 Start the game and enter a normal running dimension.
- 2 Review Jewel-spending settings before enabling automation.
- 3 Press T to enable AutoProgression.
- 4 Wait for the three-second stable-screen check.
- 5 Press T again whenever you want to pause runtime automation.

The runtime starts disabled. The toggle does not overwrite configuration.

Recommended First Review

- Use Paid 500x Bonuses
- Buy Missing With Jewels
- Egg Opening > Enabled
- normal Ascension threshold
- Dragon and Simurgh Egg automation and reserves
- Scrap and Dragon Scale overflow thresholds
- automatic Minion maximum-level prestige behavior

Global Toggle Scope

Periodic features require the global T toggle. Turning it off stops unlimited reroll enforcement, but configured vertical Random Box magnet blocking remains active to protect both automatic and manual purchases.

Ascension and Purchases

Normal Ascension

AutoProgression compares pending Slayer Points with lifetime Slayer Points. At the default 50% threshold, pending points must reach half of lifetime points. The check runs immediately after enabling and every 5 minutes by default.

Only normal Ascension is supported. Ultra Ascension is never invoked.

After Ascension, the optional Buy All phase repeatedly spends available Slayer Points until two stable passes make no further progress. Other services pause behind a two-second post-Ascension lock while game objects are rebuilt.

Skills

Available shop skills are purchased every 10 seconds. Debug output aggregates successful purchases into a 30-second summary instead of logging every click.

Normal Equipment

Only unlocked normal shop equipment is considered. The service begins with the newest unlocked item and exhausts its valid purchase amount before moving up. Purchases are made in supported 10- and 50-level increments rather than a long sequence of single levels.

If no equipment meets the minimum purchase threshold for the configured idle period, equipment purchasing sleeps temporarily. Skill purchasing continues during this sleep. Purchase priority determines which service receives the first opportunity when both are enabled.

Craftables and Materials

Craftables > Enabled is the master switch for this chapter. When disabled, no craftable is used and no material is purchased on behalf of a craftable. Egg opening remains controlled separately.

Timed Craftables

Whetstone, Alternate Dimension Staff, Bidimensional Staff, and Deathwave Scepter use a shared refill policy. By default, refilling starts below 3 minutes and continues toward 6 minutes, at most one item action per second. Deathwave Scepter also preserves the configured Simurgh Feather reserve.

Rage Pill is checked without the normal item startup delay and uses its own minimum interval. It may refresh Rage while Rage Mode is already active.

Inventory-Overflow Craftables

- Shards Necklace consumes excess Scrap.
- Random Box Staff, Necklace of Collectables, CpS Compass, and Souls Compass consume excess Dragon Scales as one group.

Their percentage thresholds use the player's current unlocked storage capacity. Although inventory percentage triggers them, each effect also stops at the shared maximum-duration target.

Quest-Assist Craftables

- Specialization reacts to active normal Goblin and Bonus Stage objectives.
- Key Manifest reacts to active normal Chest Hunt objectives.

Daily and Weekly Quests are ignored. The items have independent cooldowns, 5 minutes by default.

Specialization has a fixed safety reserve: it is not crafted if the resulting Scrap amount would be below 50% of the player's current unlocked storage capacity. This threshold is deliberately hidden rather than configurable, so an unsafe setting cannot permanently starve the Scrap-overflow craftable. Key Manifest is unaffected because it does not consume Scrap.

Missing Materials

When enabled, ordinary missing materials can be purchased with Jewels of Soul at 25%, 50%, or 100% capacity. Scrap, Simurgh Feathers, and Dragon Scales must already be available where required and are never substituted by this path.

> Buy Missing With Jewels spends premium currency automatically. Review it > before enabling the runtime on an unmodified save.

Quest Maintenance

Quests > Enabled is the master switch for all behavior in this chapter. Individual quest settings are ignored while it is disabled.

AutoProgression maintains quest data; it does not travel or perform objectives.

Claiming and Regeneration

Completed Daily and Weekly Quests can be claimed automatically. When a quest type is exhausted, the mod can generate its next set. Claims reacquire current game data after each successful action to avoid reusing invalid IL2CPP quest objects.

Weekly Selection

Five seconds after a newly generated Weekly set becomes stable, the generated slot can be rerolled until the 180,000 Rage Mode kill objective appears. Existing additional Weekly slots are preserved. Existing sets and later manual rerolls do not trigger this process.

Daily Filtering

Five seconds after a newly generated Daily set becomes stable, these objectives can be rerolled:

- Goblin kills
- material collection
- Chest Hunt chests
- normal and Silver Random Boxes
- normal Boost uses (Wind Dash kill objectives remain)
- Rage Mode uses (Rage Mode kill objectives remain)
- Bonus Stage entries, full completions, or section completions
- Ascending Heights completions
- Grapple Run completions

Filtering is generation-triggered. Existing Daily Quests and manual rerolls are not continuously rewritten. Whenever the game generates or adds Daily Quests, all currently active Daily slots receive one filtering pass; this also covers an older slot retained while the game fills empty slots. Manual rerolls still do not trigger another pass. Completed quests waiting to be claimed are always skipped, including when completion occurs after a filtering target was selected. After every native reroll, the service waits briefly for the replacement object and performs a second completion check so a late-appearing filtered objective is not missed. The generated-set event is retained while the native reroll UI object is unavailable, and inactive loaded objects are resolved directly, so opening the Quest menu is not required. A normal Ascension pauses filtering behind the global lock but preserves the captured generation event and resumes it afterward. If quest claiming and a native reroll overlap, an unchanged target triggers another delayed full scan instead of terminating the whole filtering pass.

If the native game reroll repeatedly leaves the same Daily Quest active, the service waits one second and reacquires both the quest and reroll objects. After five consecutive failures, that slot is left unchanged and filtering continues with the remaining generated slots. The 500-attempt per-generation limit remains as a final safeguard.

Other Options

The mod can keep Daily and Weekly rerolls available and reset the normal Portal cooldown. Unlimited rerolls remain active only while the global T toggle is on.

Minions, Eggs, and Paid Bonuses

Minion Automation

Two independent settings control Minions, and both require the global T runtime to be active.

- `Auto Claim` and `Send` claims completed unlocked Minion missions and sends a standing Minion when its mission cost is lower than available Slayer Points.
- `Automatic Maximum-Level Prestige` checks standing Minions with a level above 1 and a maximum level of at least 70. When Minion Prestige is unlocked, the eligible Minion is raised to maximum level for that prestige action.

When both are enabled, the order is claim, prestige, then send. When only automatic prestige is enabled, a mission must be claimed manually before its standing Minion can be processed. Locked Minions and an unavailable Prestige system are skipped safely.

Background Egg Opening

Eggs are opened directly in the background without playing the normal opening animation when `Egg Opening > Enabled` is turned on. It is disabled by default.

- Dragon Eggs open only above their reserve and only while Dragon Scale storage is not full.
- Simurgh Eggs open only above their reserve. Simurgh Feathers have no storage cap, so no equivalent full-storage check is needed.

Default reserves are 300 Dragon Eggs and 10 Simurgh Eggs.

Paid 500x Bonuses

The Souls and CpS 500x bonuses can be purchased automatically. A timer avoids constant checks, but when it expires the service reads the real remaining effect duration and updates the next check conservatively. This also tolerates time-changing effects.

> Use `Paid 500x Bonuses` directly spends Jewels of Soul. It is intended only > for players who explicitly want that behavior and is disabled by default.

Runtime Scope and Safety

AutoProgression operates only in the stable central gameplay screen, including normal Runner and Rage states. Shops, Ascension panels, Portals, minigames, and other unsupported scenes pause runtime actions.

Stability Guards

- The central screen must remain valid for three seconds before actions begin.
- Normal Ascension applies a two-second global transaction lock.
- Cached IL2CPP objects are cleared across scene and Ascension boundaries.
- Missing or invalid objects cause a retry instead of a forced call.
- Item automation has a short startup delay and permits at most one item action per second. Rage Pill is intentionally exempt from the startup delay.
- Egg opening is lower priority than craftable maintenance.

Quest-set rerolls wait five seconds after generation and verify that quest data is in a normal state before modifying it. While a generated-set filter is running, conflicting quest maintenance is paused. Daily replacements receive a short post-reroll settle delay and a final second scan before filtering ends. Missing Daily reroll objects are retried without discarding the generation. Normal Ascension also preserves pending Daily and Weekly generation events; explicit runtime shutdown still clears them. A native Daily reroll that leaves its target active is treated as a transient claim/list race and retried within the existing per-generation safety limit.

Configuration Reference

The configuration schema is version 21. Entries are grouped by purpose.

General and Ascension

Setting	Default	Meaning
Debug Mode	false	Enables detailed diagnostic logs.
Automatic Ascension Enabled	true	Allows normal Ascension.
Soul Bonus Threshold Percent	50	Required pending-to-lifetime SP percentage.
Check Interval Minutes	5	Time between checks; enabling also checks once immediately.
Buy Skills After Automatic Ascension	true	Spends remaining SP after an automatic Ascension only; manual Ascension is unaffected.

Premium Currency and Eggs

Setting	Default	Meaning
Use Paid 500x Bonuses	false	Buys Souls and CpS 500x effects with Jewels of Soul.
Egg Opening Enabled	false	Master switch for background Dragon and Simurgh Egg opening.
Dragon Egg Reserve Amount	300	Eggs kept unopened while egg opening is enabled.
Simurgh Egg Reserve Amount	10	Eggs kept unopened while egg opening is enabled.

Minions

Setting	Default	Meaning
Auto Claim and Send	true	Claims completed unlocked Minion missions and sends affordable missions again.
Automatic Maximum-Level Prestige	false	When Prestige is unlocked, raises eligible standing Minions with <code>maxLevel >= 70</code> to maximum level for automatic prestige.

The prestige option deliberately changes the Minion level used for prestige; disable it if normal Minion level progression should be preserved.

Armory Boxes

Setting	Default	Meaning
Boxes Per Press	10	Maximum boxes opened by one trigger.
Select Box Key	I	Records the highlighted one of the five Armory boxes.
Open Boxes Key	0	Opens the selected box in the background; independent from T.

The selection and opening keys must be different. Opening stops when materials or free Armory slots run out.

Silver Boxes

Setting	Default	Meaning
Auto Claim Reward	true	Claims an available Silver Box reward automatically.

This setting takes effect after entering the game and is independent from the T automation toggle. The game's native Silver Box maximum is unchanged.

Quests

Setting	Default	Meaning
Enabled	true	Master switch for every quest option below.
Auto Claim Completed Quests	true	Claims completed Daily and Weekly Quests.
Regenerate Daily Quests	true	Generates a new Daily set when available.
Regenerate Weekly Quests	true	Generates a new Weekly set when available.
Unlimited Quest Rerolls	true	Keeps Daily/Weekly rerolls available while T automation is active.
Prefer 180000 Rage Weekly	false	Rerolls a newly generated Weekly slot to the minimum Rage-kill target.
Filter Generated Daily Quests	false	Rerolls selected inconvenient objectives in a new Daily set.
Reset Portal Cooldown	true	Removes the normal Portal cooldown.

Craftables

Setting	Default	Meaning
Enabled	false	Master switch for all craftables and their automatic material purchases.
Use Rage Pill	true	Refreshes Rage cooldown.
Rage Pill Minimum Interval Seconds	10	Minimum time between attempts.
Use Whetstone	true	Maintains Whetstone duration.
Use Alternate Dimension Staff	true	Maintains its duration.
Use Bidimensional Staff	true	Maintains its duration.
Use Deathwave Scepter	true	Maintains it while preserving feathers.
Deathwave Scepter Feather Reserve	300	Minimum Simurgh Feathers retained.
Use Shards Necklace	true	Consumes excess Scrap.
Shards Necklace Scrap Threshold Percent	95	Scrap percentage trigger.
Use Dragon Scale Overflow Items	true	Consumes excess scales with four effects.
Dragon Scale Threshold Percent	95	Dragon Scale percentage trigger.
Timed Item Refill Below Minutes	3	Lower refill trigger.
Timed Item Target Maximum Minutes	6	Shared target and overflow-effect ceiling.
Use Quest Assist Craftables	true	Enables Specialization and Key Manifest. Specialization will not craft if its cost would leave Scrap below the fixed 50% reserve.
Quest Assist Cooldown Minutes	5	Independent cooldown for each item.
Buy Missing With Jewels	false	Buys eligible ordinary materials with Jewels only while the Craftables master switch is enabled.
Material Purchase Percent	100	Purchase option: 25, 50, or 100 percent.

Purchases

Setting	Default	Meaning
Buy Skills	true	Enables shop-skill purchasing.
Buy Equipment	true	Enables unlocked normal equipment purchasing.
Block Vertical Magnet Skills	true	Always blocks two vertical Random Box magnet upgrades, independently from T.
Equipment Idle Minutes Before Sleep	1	No-valid-purchase time before sleeping.
Equipment Sleep Minutes	10	Equipment-only sleep duration.

> The two Jewel settings can spend premium currency. Their defaults favor the > development environment and should be reviewed before normal play.

Logging Reference

AutoProgression separates player-facing information from diagnostics.

Always Visible

- runtime enabled and disabled messages
- Jewels of Soul purchases and remaining paid-bonus duration
- notable resource actions such as Shards Necklace crafting
- generated quest sets and selected Weekly results
- warnings and safely caught errors

Debug Mode

When Debug Mode is enabled, logs include object availability, timers, craftable duration, purchase summaries, quest-reroll state, and screen-guard transitions. Repetitive status messages are rate-limited where practical.

MelonLoader RemoteAPI HTTP failures and messages explicitly attributed to another mod are not AutoProgression failures. Native IL2CPP exceptions should be evaluated using the service and stack trace named in the same entry.

The main log directory is:

```
%LOCALAPPDATA%\IdleSlayerModManager\ModLoader\MelonLoader\Logs\
```

Troubleshooting

T toggles the mod but nothing happens

Use a normal Runner or Rage dimension and wait three seconds. Unsupported UI, scene transitions, and post-Ascension reconstruction pause the runtime.

A craftable is skipped

Confirm that it is unlocked, enabled, below its applicable duration or above its inventory trigger, and has the required non-purchasable resources. Also check the shared maximum duration and the global Jewel-material option.

Automatic Ascension is delayed

Verify pending versus lifetime Slayer Points, the configured percentage, and the check interval. Enabling performs one immediate check; later checks use the configured schedule.

Quest claiming or rerolling is delayed

New-set filtering intentionally waits five seconds for native quest data to stabilize. It does not revisit old sets or react to manual rerolls. A claim reacquires the list after every successful quest to avoid stale objects.

Eggs do not open

The count must be above its reserve. Dragon Eggs additionally stop when Dragon Scale storage is full. Eggs also yield to higher-priority item actions.

Skills require opening a shop once

Some game versions initialize shop data lazily. AutoProgression attempts to resolve the required objects safely, but opening the relevant shop once may be necessary after a game update or unusual reset state.

The game crashes or freezes

- 1 Disable AutoProgression with T if possible.
- 2 Reproduce with other automation mods disabled.
- 3 Save the latest MelonLoader log.
- 4 Record the scene, open panel, and action immediately before the issue.
- 5 Check whether the stack trace names AutoProgression or another mod.