



AutoProgression

Complete Manual

Ascension, purchases, quests, craftables, minions, resources, configuration, and troubleshooting
Version 2.0.0 | Tashi

AutoProgression is the account-progression and maintenance module in Tashi's Full Automation Suite. It coordinates normal Ascension, purchases, craftables, materials, eggs, paid bonuses, and quest maintenance.

This manual covers configuration version 32. New users should begin with the User Guide.

Reference Chapters

- 1 Installation and Upgrading
- 2 Quick Start and Global Control
- 3 Ascension and Purchases
- 4 Craftables and Materials
- 5 Quest Maintenance
- 6 Minions, Eggs, and Paid Bonuses
- 7 Runtime Scope and Safety
- 8 Configuration Reference
- 9 Logging Reference
- 10 Troubleshooting

Module Responsibilities

- AutoProgression handles purchases, normal Ascension, craftables, materials, eggs, and quest maintenance.
- AutoAdventurer selects and performs supported quest objectives, travels between dimensions, and controls Rage and movement helpers.
- AutoClimber controls Ascending Heights routes, enemies, and rewards.
- AutoBonusRunner controls Bonus Stage routes, jumping, sphere requirements, Spirit Boost sections, and retry.

The mods can be used independently or together.

AutoAdventurer 2.0 includes automatic attacking. AutoBonusRunner should not run alongside Auto Jump or Bonus Stage Completer because they can compete for Bonus Stage input. Its Skip mode provides the same fast-completion behavior as Bonus Stage Completer.

Default Control

Key	Action
T	Toggle the AutoProgression runtime

The runtime starts disabled. Feature preferences remain saved when T is turned off.

Safety Principles

- Ultra Ascension is disabled by default and requires both the game's native prerequisite state and at least 24 Astral Keys when explicitly enabled.
- Automation runs only in a stable central Runner or Rage scene.
- Ascension applies a global two-second lock and clears cached game objects.
- Item actions are limited to one per second.

- Missing IL2CPP objects cause a safe retry instead of a forced action.

Installation and Upgrading

Requirements

- Idle Slayer Mod Manager with MelonLoader initialized
- Idle Slayer Mods Core
- A compatible AutoProgression ZIP or DLL

Mod Manager Installation

- 1 Import `AutoProgression.zip` without extracting it.
- 2 Enable AutoProgression in the manager.
- 3 Start Idle Slayer through the configured loader.

Manual Installation

Copy `AutoProgression.dll` to:

```
%LOCALAPPDATA%\IdleSlayerModManager\ModLoader\Mods\
```

The generated configuration is stored at:

```
%LOCALAPPDATA%\IdleSlayerModManager\ModLoader\UserData\AutoProgression.cfg
```

Upgrading

Replace the old DLL or import the new ZIP, then restart the game. Configuration schema migrations preserve supported existing values and add new entries. Keeping a backup of the configuration is still recommended.

Quick Start and Global Control

- 1 Start the game and enter a normal running dimension.
- 2 Review Jewel-spending settings before enabling automation.
- 3 Press the configured toggle key (T by default) to enable AutoProgression.
- 4 Wait for the three-second stable-screen check.
- 5 Press the same key again whenever you want to pause runtime automation.

The runtime starts disabled. Change the key with General > Toggle Key. The toggle does not overwrite configuration.

Recommended First Review

- Use Paid 500x Bonuses
- Buy Missing With Jewels
- Egg Opening > Enabled
- normal Ascension threshold
- Dragon and Simurgh Egg automation and reserves
- Scrap and Dragon Scale overflow thresholds
- automatic Minion maximum-level prestige behavior

Global Toggle Scope

Periodic features require the global runtime toggle. Turning it off stops unlimited reroll enforcement, but configured vertical Random Box magnet blocking remains active to protect both automatic and manual purchases.

Ascension and Purchases

Normal Ascension

AutoProgression compares pending Slayer Points with lifetime Slayer Points. At the default 50% threshold, pending points must reach half of lifetime points. The check runs immediately after enabling and every 5 minutes.

Normal Ascension is enabled by default. Optional Ultra Ascension is disabled by default and is invoked only after the game's native prerequisite state is active and `GetAstralKeys()` reports at least 24 keys. Ultra Ascension takes priority when both automatic Ascension paths are eligible in the same check.

After Ascension, the optional Buy All phase repeatedly spends available Slayer Points until two stable passes make no further progress. Other services pause behind a two-second post-Ascension lock while game objects are rebuilt.

Skills

Available shop skills are purchased every 5 seconds. Debug output aggregates successful purchases into a 30-second summary instead of logging every click.

Normal Equipment

Only unlocked normal shop equipment is considered. The service begins with the newest unlocked item and exhausts its valid purchase amount before moving up. Purchases are made in supported 10- and 50-level increments rather than a long sequence of single levels.

If no equipment meets the minimum purchase threshold for one minute, equipment purchasing sleeps for ten minutes. Skill purchasing continues during this sleep.

Craftables and Materials

Craftables > Enabled is the master switch for this chapter. When disabled, no craftable is used and no material is purchased on behalf of a craftable. Egg opening remains controlled separately.

Timed Craftables

Whetstone, Alternate Dimension Staff, Bidimensional Staff, and Deathwave Scepter use a shared refill policy. By default, refilling starts below 3 minutes and continues toward 6 minutes, at most one item action per second. Deathwave Scepter also preserves the configured Simurgh Feather reserve.

Rage Pill is checked without the normal item startup delay and uses its own minimum interval. It may refresh Rage while Rage Mode is already active.

Inventory-Overflow Craftables

Ascendant Badge Boost is a one-use effect rather than a timed stack. It is controlled by its own switch, which is disabled by default. When enabled, it is crafted whenever its native condition permits use and Dragon Scales are strictly above the fixed 50% capacity threshold. Dragon Scales are never purchased; other eligible missing materials follow the global Jewel purchase setting.

- Shards Necklace consumes excess Scrap.
- Random Box Staff, Necklace of Collectables, CpS Compass, and Souls Compass consume excess Dragon Scales as one group.

Their percentage thresholds use the player's current unlocked storage capacity. Shards Necklace ignores the shared duration target and continues until Scrap falls below its threshold. Dragon Scale duration effects still stop at the shared maximum-duration target.

Quest-Assist Craftables

- Specialization reacts to active normal Goblin and Bonus Stage objectives.
- Key Manifest reacts to active normal Chest Hunt objectives.

Every Specialization use requires Dragon Scales to be strictly above 50% of current unlocked capacity, including quest-triggered uses.

Specialization can also be used without a matching quest when Scrap is above 80%. This resource path neither reads nor starts the quest-assist cooldown. Native availability and protected-material checks still apply. It pauses while any active quest requires normal, Silver, or Golden Random Boxes.

Specialization and Key Manifest share `Quest Assist Feather Threshold Amount` (1,000 by default). Setting it to 0 disables both items completely. Above zero, Feathers must be strictly greater than the value and crafting must leave at least that amount. Key Manifest also uses the shared value as its independent Feather-overflow trigger. Both items require the quest-assist switch, the Craftables master switch, and global T.

Daily and Weekly Quests are ignored. Quest-triggered uses have independent fixed five-minute cooldowns.

Specialization has a fixed safety reserve: it is not crafted if the resulting Scrap amount would be below 50% of the player's current unlocked storage capacity. This threshold is deliberately hidden rather than configurable, so an unsafe setting cannot permanently starve the Scrap-overflow craftable. Key Manifest is unaffected because it does not consume Scrap.

Missing Materials

When enabled, ordinary missing materials can be purchased with Jewels of Soul at 25%, 50%, or 100% capacity. Scrap, Simurgh Feathers, and Dragon Scales must already be available where required and are never substituted by this path.

> **Buy Missing With Jewels** spends premium currency automatically. Review it > before enabling the runtime on an unmodified save.

Quest Maintenance

Quests > Enabled is the master switch for all behavior in this chapter. Individual quest settings are ignored while it is disabled.

AutoProgression maintains quest data; it does not travel or perform objectives.

Claiming and Regeneration

Completed Daily and Weekly Quests can be claimed automatically. When a quest type is exhausted, the mod can generate its next set. Claims reacquire current game data after each successful action to avoid reusing invalid IL2CPP quest objects.

Weekly Selection

Five seconds after a newly generated Weekly set becomes stable, the generated slot can be rerolled until the 180,000 Rage Mode kill objective appears. Existing additional Weekly slots are preserved. Existing sets and later manual rerolls do not trigger this process.

Daily Filtering

Five seconds after a newly generated Daily set becomes stable, these objectives can be rerolled:

- Goblin kills
- material collection
- temporary-craftable crafting
- Chest Hunt chests
- normal and Silver Random Boxes
- normal Boost uses (Wind Dash kill objectives remain)
- Rage Mode uses (Rage Mode kill objectives remain)
- Bonus Stage entries, full completions, or section completions
- Ascending Heights completions
- Grapple Run completions

Filtering is generation-triggered. Existing Daily Quests and manual rerolls are not continuously rewritten. Whenever the game generates or adds Daily Quests, all currently active Daily slots receive one filtering pass; this also covers an older slot retained while the game fills empty slots. Manual rerolls still do not trigger another pass. Completed quests waiting to be claimed are always skipped, including when completion occurs after a filtering target was selected. After every native reroll, the service waits briefly for the replacement object and performs a second completion check so a late-appearing filtered objective is not missed. The generated-set event is retained while the native reroll UI object is unavailable, and inactive loaded objects are resolved directly, so opening the Quest menu is not required. A normal Ascension pauses filtering behind the global lock but preserves the captured generation event and resumes it afterward. If quest claiming and a native reroll overlap, an unchanged target triggers another delayed full scan instead of terminating the whole filtering pass.

If the native game reroll repeatedly leaves the same Daily Quest active, the service waits one second and reacquires both the quest and reroll objects. After five consecutive failures, that slot is left unchanged and filtering continues with the remaining generated slots. The 500-attempt per-generation limit remains as a final safeguard.

Other Options

The mod can keep Daily and Weekly rerolls available and reset the normal Portal cooldown. Unlimited rerolls remain active only while the global T toggle is on.

Minions, Eggs, and Paid Bonuses

Minion Automation

Two independent settings control Minions, and both require the global T runtime to be active.

- `Auto Claim` and `Send` claims completed unlocked Minion missions and sends a standing Minion when its mission cost is lower than available Slayer Points.
- `Automatic Maximum-Level Prestige` checks standing Minions with a level above 1 and a maximum level of at least 70. When Minion Prestige is unlocked, the eligible Minion is raised to maximum level for that prestige action.

When maximum-level prestige is enabled, every manually triggered Minion prestige uses that Minion's maximum level, including Minions below the automatic 70 maximum-level threshold. This manual enhancement is controlled by the setting directly and does not require the global T automation toggle.

When both are enabled, the order is claim, prestige, then send. When only automatic prestige is enabled, a mission must be claimed manually before its standing Minion can be processed. Locked Minions and an unavailable Prestige system are skipped safely.

Background Egg Opening

Eggs are opened directly in the background without playing the normal opening animation when `Egg Opening > Enabled` is turned on. It is disabled by default.

- Dragon Eggs open only above their reserve and only while Dragon Scale storage is not full.
- Simurgh Eggs open only above their reserve. Simurgh Feathers have no storage cap, so no equivalent full-storage check is needed.

Default reserves are 300 Dragon Eggs and 10 Simurgh Eggs.

Paid 500x Bonuses

The Souls and CpS 500x bonuses can be purchased automatically. A timer avoids constant checks, but when it expires the service reads the real remaining effect duration and updates the next check conservatively. This also tolerates time-changing effects.

> Use `Paid 500x Bonuses` directly spends Jewels of Soul. It is intended only > for players who explicitly want that behavior and is disabled by default.

Runtime Scope and Safety

AutoProgression operates only in the stable central gameplay screen, including normal Runner and Rage states. Shops, Ascension panels, Portals, minigames, and other unsupported scenes pause runtime actions.

Stability Guards

- The central screen must remain valid for three seconds before actions begin.
- Normal Ascension applies a two-second global transaction lock.
- Cached IL2CPP objects are cleared across scene and Ascension boundaries.
- Missing or invalid objects cause a retry instead of a forced call.
- Item automation has a short startup delay and permits at most one item action per second. Rage Pill is intentionally exempt from the startup delay.
- Egg opening is lower priority than craftable maintenance.

Quest-set rerolls wait five seconds after generation and verify that quest data is in a normal state before modifying it. While a generated-set filter is running, conflicting quest maintenance is paused. Daily replacements receive a short post-reroll settle delay and a final second scan before filtering ends. Missing Daily reroll objects are retried without discarding the generation. Normal Ascension also preserves pending Daily and Weekly generation events; explicit runtime shutdown still clears them. A native Daily reroll that leaves its target active is treated as a transient claim/list race and retried within the existing per-generation safety limit.

Configuration Reference

AutoProgression 2.0 uses configuration schema 32. The generated file is:

```
%LOCALAPPDATA%\IdleSlayerModManager\ModLoader\UserData\AutoProgression.cfg
```

Routine polling and sleep intervals are managed internally so the public configuration focuses on progression, resources, and feature behavior.

General

Setting	Default	Meaning
Configuration Version	32	Internal migration value. Do not edit.
Toggle Key	T	Key used to enable or pause the main runtime. Accepts Unity KeyCode names such as T, F8, or Keypad0.
Debug Mode	false	Adds detailed subsystem diagnostics and aggregated activity summaries.

Ascension

Setting	Default	Meaning
Automatic Ascension Enabled	true	Performs normal Ascension at the configured threshold while T is active.
Automatic Ultra Ascension Enabled	false	Major reset. Requires native eligibility and at least 24 Astral Keys.
Soul Bonus Threshold Percent	50	Required pending-to-lifetime Slayer Point percentage for normal Ascension.
Buy Skills After Automatic Ascension	true	Uses Ascension-tree Buy All after an automatic normal Ascension only.

The threshold is checked immediately when T is enabled and every five minutes afterward.

Purchases

Setting	Default	Meaning
Skills Enabled	true	Buys eligible and affordable shop skills every five seconds while T is active.
Equipment Enabled	true	Buys levels for unlocked normal equipment, newest first.
Disable Vertical Magnet Upgrades	true	Blocks two unwanted Random Box vertical magnet upgrades from automatic and manual purchase, independently from T.

The equipment buyer sleeps for ten minutes after one minute without an eligible bulk purchase. Skill purchasing continues during that sleep.

Paid Bonuses

Setting	Default	Meaning
Use Paid 500x Bonuses	false	Spends Jewels of Soul to maintain both Souls and CpS 500x effects.

Minions

Setting	Default	Meaning
Auto Claim and Send	true	Claims completed unlocked missions and sends affordable missions again while T is active.
Automatic Maximum-Level Prestige	false	Automatically prestiges standing Minions with maximum level at least 70; also makes every manual prestige use the selected Minion's maximum level independently from T.

Egg Opening

Setting	Default	Meaning
Enabled	false	Master switch for background Dragon and Simurgh Egg opening while T is active.
Dragon Egg Reserve Amount	300	Dragon Eggs kept unopened. Opening also stops when Dragon Scale storage is full.
Simurgh Egg Reserve Amount	10	Simurgh Eggs kept unopened.

Silver Boxes

Setting	Default	Meaning
Auto Claim Reward	true	Claims an available Silver Box reward independently from T.

The native Silver Box storage maximum and consumption behavior are unchanged.

Quests

Setting	Default	Meaning
Enabled	true	Master switch for every quest option below.
Auto Claim Completed Quests	true	Claims completed Daily and Weekly Quests.
Regenerate Daily Quests	true	Generates another Daily set when no active Daily Quests remain.
Regenerate Weekly Quests	true	Generates another Weekly set when no active Weekly Quests remain.
Unlimited Quest Rerolls	true	Keeps Daily and Weekly rerolls available while T is active.
Prefer 180k Rage Weekly Quest	false	Rerolls one newly generated Weekly slot until the 180,000 Rage Mode kill objective appears.
Filter Generated Daily Quests	false	Rerolls documented inconvenient objectives in newly generated Daily slots.
Reset Portal Cooldown	true	Keeps the normal Portal cooldown at zero while T is active.

Generated-set filtering does not rewrite old quests or react to later manual rerolls. Completed quests are skipped.

Craftables

Setting	Default	Meaning
Enabled	false	Master switch for all automatic craftables and material purchases in this section.
Buy Missing With Jewels	false	Spends Jewels of Soul on eligible ordinary missing recipe materials. Never buys Scrap, Simurgh Feathers, or Dragon Scales.
Material Purchase Percent	100	Jewel refill size. Supported values: 25, 50, or 100 percent.
Timed Items Target Minutes	6	Shared target; timed refilling begins automatically at half this value.
Rage Pill Enabled	true	Refreshes an active Rage cooldown.
Whetstone Enabled	true	Maintains Whetstone duration.
Alternate Dimension Staff Enabled	true	Maintains Alternate Dimension Staff duration.
Bidimensional Staff Enabled	true	Maintains Bidimensional Staff duration.
Deathwave Scepter Enabled	true	Maintains Deathwave Scepter duration while preserving its Feather reserve.
Deathwave Scepter Feather Reserve Amount	300	Minimum Simurgh Feather amount preserved for Deathwave Scepter.
Shards Necklace Scrap Overflow Enabled	true	Consumes excess Scrap without using the timed duration cap.
Shards Necklace Scrap Threshold Percent	97	Starts at or above this Scrap percentage and stops below it.
Dragon Scale Overflow Craftables Enabled	true	Enables Random Box Staff, Necklace of Collectables, CpS Compass, and Souls Compass as one overflow group.
Dragon Scale Overflow Threshold Percent	95	Starts one overflow cycle above this Dragon Scale percentage.
Ascendant Badge Boost Enabled	false	Arms the one-use Armory boost when Dragon Scales are strictly above the fixed 50% requirement.
Quest Assist Craftables Enabled	true	Enables Specialization and Key Manifest under their task and resource rules.
Quest Assist Feather Threshold Amount	1000	Shared Feather threshold. 0 disables both items; crafting must preserve this amount.

Rage Pill attempts are limited internally to once every ten seconds. Quest-triggered Specialization and Key Manifest have separate fixed five-minute cooldowns.

Quest Assist Feather Threshold Amount controls both quest-assist items:

- 0 disables Specialization and Key Manifest completely.
- Above zero, current Feathers must be strictly greater than the value.
- Crafting must leave at least the configured amount.

- Key Manifest also uses it as an independent Feather-overflow trigger.
- Specialization still requires a normal quest or its Scrap/Dragon Scale overflow conditions.

Manual Armory Boxes

Setting	Default	Meaning
Boxes Per Press	10	Maximum selected Armory boxes or eggs opened per trigger.
Select Box Key	B	Records the highlighted Armory box, Dragon Egg, or Simurgh Egg.
Open Boxes Key	N	Opens the selected item in the background independently from T.

The two keys must differ. Opening stops when materials, eggs, or free Armory slots run out.

Manual Casino Crawler Eyes

Setting	Default	Meaning
Enabled	false	Enables the manual Jewel-spending bulk-purchase tool independently from T.
Purchase Key	M	Starts one operation on the correct Village Casino purchase screen.
Eyes Per Press	1000	Requested amount, rounded down to a multiple of ten.

The service uses sequential native 10-eye transactions and stops on insufficient Jewels, a closed screen, or a safety timeout.

Premium-Currency Warning

These settings can spend Jewels of Soul:

- Use Paid 500x Bonuses
- Buy Missing With Jewels
- Manual Casino Crawler Eyes > Enabled

All three are disabled by default. Enable them only after understanding their cost.

Logging Reference

AutoProgression separates player-facing information from diagnostics.

Always Visible

- runtime enabled and disabled messages
- Jewels of Soul purchases and remaining paid-bonus duration
- normal and Ultra Ascension starts
- manual Armory/egg opening and Crawler Eye purchase results
- Minion prestige, Silver Box claims, and Shards Necklace overflow crafting
- completed generated-quest filtering and selected Weekly results
- warnings and safely caught errors

Debug Mode

When Debug Mode is enabled, logs include object availability, timers, purchase summaries, quest-reroll state, and screen-guard transitions. Each diagnostic is labeled with its subsystem, for example [Debug][Ascension], [Debug][Craftables], [Debug][Purchases], [Debug][Quests], or [Debug][Runtime]. High-frequency activity is summarized: quest claims, timed craftables, eggs, and skill purchases are emitted as periodic totals instead of one line per action. Expected native lifecycle misses are logged once or rate-limited.

Safely caught exceptions produce one concise error line in every mode. The full managed/native exception detail is emitted only when Debug Mode is enabled.

Exact repeated Debug messages are emitted at most once every 10 seconds. Warnings and errors use a 30-second duplicate window. When logging resumes, the message includes the number of identical repeats that were suppressed.

MelonLoader RemoteAPI HTTP failures and messages explicitly attributed to another mod are not AutoProgression failures. Native IL2CPP exceptions should be evaluated using the service and stack trace named in the same entry.

The main log directory is:

```
%LOCALAPPDATA%\IdleSlayerModManager\ModLoader\MelonLoader\Logs\
```

Troubleshooting

T toggles the mod but nothing happens

Use a normal Runner or Rage dimension and wait three seconds. Unsupported UI, scene transitions, and post-Ascension reconstruction pause the runtime.

A craftable is skipped

Confirm that it is unlocked, enabled, below its applicable duration or above its inventory trigger, and has the required non-purchasable resources. Also check the shared maximum duration and the global Jewel-material option.

Automatic Ascension is delayed

Verify pending versus lifetime Slayer Points, the configured percentage, and the stable central gameplay state. Enabling performs one immediate check; later checks use the fixed five-minute interval.

Quest claiming or rerolling is delayed

New-set filtering intentionally waits five seconds for native quest data to stabilize. It does not revisit old sets or react to manual rerolls. A claim reacquires the list after every successful quest to avoid stale objects.

Eggs do not open

The count must be above its reserve. Dragon Eggs additionally stop when Dragon Scale storage is full. Eggs also yield to higher-priority item actions.

Skills require opening a shop once

Some game versions initialize shop data lazily. AutoProgression attempts to resolve the required objects safely, but opening the relevant shop once may be necessary after a game update or unusual reset state.

The game crashes or freezes

- 1 Disable AutoProgression with T if possible.
- 2 Reproduce with other automation mods disabled.
- 3 Save the latest MelonLoader log.
- 4 Record the scene, open panel, and action immediately before the issue.
- 5 Check whether the stack trace names AutoProgression or another mod.