

Starting and Accessing Jenkins

Added by Derek Basch, last edited by MICHAEL LUPO on Sep 03, 2014

Starting Jenkins

The easiest way to execute Jenkins is through the built in Jetty servlet container. You can execute Jenkins like this:

```
$ java -jar jenkins.war
```

Of course, you probably want to send the output of Jenkins to a log file, and if you're on Unix, you probably want to use **nohup**:

```
$ nohup java -jar jenkins.war > $LOGFILE 2>&1
```

Accessing Jenkins

To see Jenkins, simply bring up a web browser and go to URL http://myServer:8080 where myServer is the name of the system running Jenkins.

Top of page

Command Line Parameters

Jenkins normally starts up using port 8080. However, if you have other web services starting up you might find that this port is already taken. You can specify a different port by using --httpPort=\$HTTP_PORT where \$HTTP_PORT is the port you want Jenkins to run on. Other command line parameters include:

Command Line Parameter	Description
httpPort=\$HTTP_PORT	Runs Jenkins listener on port \$HTTP_PORT using standard <i>http</i> protocol. The default is port 8080. To disable (because you're using <i>https</i>), use port -1.
httpListenAddress=\$HTTP_HOST	Binds Jenkins to the IP address represented by \$HTTP_HOST. The default is 0.0.0.0 — i.e. listening on all available interfaces. For example, to only listen for requests from localhost, you could use: httpListenAddress=127.0.0.1
httpsPort=\$HTTP_PORT	Uses HTTPS protocol on port \$HTTP_PORT
httpsListenAddress=\$HTTPS_HOST	Binds Jenkins to listen for HTTPS requests on the IP address represented by \$HTTPS_HOST.
prefix=\$PREFIX	Runs Jenkins to include the \$PREFIX at the end of the URL. For example, to make Jenkins accessible at http://myServer:8080/jenkins, setprefix=/jenkins
ajp13Port=\$AJP_PORT	Runs Jenkins listener on port \$AJP_PORT using standard <i>AJP13</i> protocol. The default is port 8009. To disable (because you're using <i>https</i>), use port -1.
ajp13ListenAddress=\$AJP_HOST	Binds Jenkins to the IP address represented by \$AJP_HOST. The default is 0.0.0.0 — i.e. listening on all available interfaces.
argumentsRealm.passwd.\$ADMIN_USER	Sets the password for user \$ADMIN_USER. If Jenkins security is turned on, you must log in as the \$ADMIN_USER in order to configure Jenkins or a Jenkins project. NOTE: You must also specify that this user has an <i>admin</i> role. (See next argument below).
argumentsRealm.roles.\$ADMIN_USER=admin	Sets that \$ADMIN_USER is an administrative user and can configure Jenkins if Jenkins' security is turned on. See Securing Jenkins for more information.
-Xdebug - Xrunjdwp:transport=dt_socket,address=\$DEBUG_PORT,server=y,suspend=n	Sets debugging on and you can access debug on \$DEBUG_PORT.
-logfile=\$LOG_PATH/winstone_`date +"%Y%m-%d_%H-%M"`.log	Logging to desired file
-XX:PermSize=512M -XX:MaxPermSize=2048M -Xmn128M -Xms1024M - Xmx2048M	referring to these options for Oracle Java

Jenkins passes all (or just leading parameters until the first Jenkins-specific parameter?) command line parameters to the Winstone servlet container, so you can get more information by looking at the <u>Winstone Command Line Parameter Reference</u>



Be Careful with Command Line Parameters

Jenkins ignores command line parameters it doesn't understand instead of producing an error. Be careful when using command line parameters and make sure you have the correct spelling. For example, the parameter needed for defining the Jenkins administrative user is --argumentsRealm and not --argumentRealm.

A very simple init script

The following script is for Ubuntu based systems. The RedHat Jenkins distribution contains a startup script.

```
#!/bin/sh
DESC="Jenkins CI Server"
NAME=jenkins
PIDFILE=/var/run/$NAME.pid
RUN AS=jenkins
COMMAND=/usr/bin/java -- -jar /home/jenkins/jenkins.war
        start-stop-daemon --start --quiet --background --make-pidfile --pidfile $PIDFILE --chuid $RUN AS --exec $COMMAND
}
d stop() {
        start-stop-daemon --stop --quiet --pidfile $PIDFILE
        if [ -e $PIDFILE ]
               then rm $PIDFILE
case $1 in
        start)
        echo -n "Starting $DESC: $NAME"
        d start
        echo "."
        ;;
        stop)
        echo -n "Stopping $DESC: $NAME"
        d stop
        echo "."
        ;;
        restart)
        echo -n "Restarting $DESC: $NAME"
        d stop
        sleep 1
        d start
        echo "."
        ;;
        *)
        echo "usage: $NAME {start|stop|restart}"
        exit 1
        ; ;
esac
```

Using HTTPS with an existing certificate

If you're setting up Jenkins using the built-in Winstone server and want to use an existing certificate for HTTPS:

```
--httpPort=-1 --httpsPort=443 --httpsKeyStore=path/to/keystore --httpsKeyStorePassword=keystorePassword
```

The keystore should be in JKS format (as created by the JDK 'keytool') and the keystore and target key must have the same password. (Placing the keystore arguments after Jenkins-specific parameters does not seem to work; either they are not forwarded to Winstone or Winstone ignores them coming after unknown parameters. So, make sure they are adjacent to the working --httpsPort argument.)

If your keystore contains multiple certificates (e.g. you are using CA signed certificate) Jenkins might end-up using a incorrect one. In this case you can convert the keystore to PEM and use following command line options:

```
--httpPort=-1 --httpsPort=443 --httpsCertificate=path/to/cert --httpsPrivateKey=path/to/privatekey
```

Passing the Command Line Parameters to an instance on a Mac OSX (Currently is Mavericks 10.9.4) that uses launchctl (rather than using Jenkins.jar to start up)

In this example, we set the Jenkins server to listen for HTTPS on port 8443. Not we do not disable the httpPort by passing in -1. So in this example, your server would answer on both http and https. We also assume that the user has already created the keystore (see the "Using SSL" section from http://wiki.wocommunity.org/display/documentation/Installing+and+Configuring+Jenkins)

```
sudo launchctl unload /Library/LaunchDaemons/org.jenkins-ci.plist

sudo defaults write /Library/Preferences/org.jenkins-ci httpsPort 8443

sudo defaults write /Library/Preferences/org.jenkins-ci httpsKeyStore /path/to/your/keystore/file
sudo defaults write /Library/Preferences/org.jenkins-ci httpsKeyStorePassword <keystore password>

sudo launchctl load /Library/LaunchDaemons/org.jenkins-ci.plist
```

Top of page

Child Pages (1)

Comments (8) Show Comments | Add Comment

Powered by a free Atlassian Confluence Open Source Project License granted to Jenkins. Evaluate Confluence today.

Printed by Atlassian Confluence 3.4.7, the Enterprise Wiki.