
IT3030 - Biostatistics

Week #2 (3/1/2022)



Chapter 3 Numerical Summary Measures



Outline

- 3.1 Measures of *Central Tendency*
 - 3.1.1. Mean
 - 3.1.2. Median
 - 3.1.3 Mode
- 3.2 Measures of *Dispersion*
 - 3.2.1. Range
 - 3.2.2. Interquartile Range
 - 3.2.3. Variance and Standard Deviation (STD)
 - 3.2.4. Coefficient of Variation
- 3.3 Grouped Data
- 3.4 Chebychev's Inequality

Introduction

- In Chapter 2 we learned various ways of Summarizing data into tables, charts or graphs. These help people to better "see" or "visualize" what data are collected, including adequate reasoning of these data.
- They, however, do not allow us to make concise, *quantitative* statements that characterize the distribution of values as a whole.

- In this chapter we focus on <u>numerical</u> summary measures.
- Together (techniques introduced in Chapters 2 and 3), these various types of descriptive statistics can provide a great deal of information about a set of observations.

3.1 Central Tendency

- A <u>center</u> within a set of observations (measurements) usually represents the point about which the observations <u>tend</u> to <u>cluster</u>.
- In a way, center can be interpreted more or less as the <u>average value</u> that can adequately <u>represent</u> this group of observations.

3.1.1. Mean

- "Mean" is often <u>the arithmetic</u>
 <u>mean</u>, or called <u>average</u>, of a collection of numerical values.
- It is the **Summation** of all divided by the count.
- It is apparent that a mean is applicable in <u>discrete</u> and <u>continuous</u> data, but is generally not adequate for either <u>nominal</u> or ordinal data.

TABLE 3.1

Forced expiratory volumes in 1 second for 13 adolescents suffering from asthma

Subject	FEV ₁ (liters)		
Subject	12.1 (2002)		
1	2.30		
2	2.15		
3	3.50		
4	2.60		
5	2.75		
6	2.82		
7	4.05		
8	2.25		
9	2.68		
10	3.00		
11	4.02		
12	2.85		
13	3.38		

FEV₁: This is the amount of air that you can forcibly blow out in one second, measured in liters, and is considered one of the primary indicators of lung function.

肺量計檢查 (Spirometry)

- 做肺量計檢查時,要先 夾住鼻子,口含儀器之 吸管,盡最大能力吸滿 氣後,再用力快速且完 全地吐氣。
- 如此可知肺活量,第一秒吐氣量(FEV1)及 吐氣流速,而了解是否 有氣流阻塞之現象。



 One can easily compute the mean value for these 13 observations.

TABLE 3.1

Forced expiratory volumes in 1 second for 13 adolescents suffering from asthma

Subject	FEV ₁ (liters)		
1	2.30		
2	2.15		
3	3.50		
4	2.60		
5	2.75		
6	2.82		
7	4.05		
8	2.25		
9	2.68		
10	3.00		
11 -	→ 40.2 4.02		
12	2.85		
13	3.38		

- Assuming that the value for subject #11 was
 mistakenly recorded as 40.2.
- One can also compute the mean value for "these" 13 values.
- How are the two mean values different?

Comments

- What happens if one value is <u>Very</u>
 <u>different</u> from the others? (This might be true, or might be a mistake.) Should we use it or discard it?
- How "different" is "very" different?
- For any statistical analysis, it should be taken into consideration how the magnitude of every observation in a set of data is distributed.

- A mean value is very sensitive to every observation. (Can you see this?)
- In this case, we may want to use a summary measure that is NOT as sensitive to every observation (or more resistant to errors).

More about calculating mean

- We mentioned that arithmetic mean is the total of the sum of all values in a collection of numbers divided by the number of numbers in a collection.
- Geometric mean is an nth root of the product of all numbers in a collection. The formula for the geometric mean is:

Geometric mean =
$$\sqrt[n]{X_1 \times X_2 \times ... \times X_n}$$

Difference between the two means

Geometric Mean vs Arithmetic Mean | Top 9 Differences (with Infographics) (wallstreetmojo.com)

Basis	Geometric Mean	Arithmetic Mean		
Meaning	Geometric Mean is known as the Multiplicative Mean.	Arithmetic Mean is known as Additive Mean.		
Formula	{[(1+Return1) x (1+Return2) x (1+Return3))]^(1/n)]} – 1	(Return1 + Return2 + Return3 + Return4)/ 4		
Values	The geometric mean is always lower than the arithmetic means due to the compounding effect.	The arithmetic mean is always higher than the geometric mean as it is calculated as a simple average.		
Calculation	Suppose a dataset has the following numbers – 50, 75, 100. Geometric mean is calculated as cube root of (50 x 75 x 100) = 72.1	Similarly, for a dataset of 50, 75, and 100, arithmetic mean is calculated as (50+75+100)/3 = 75		
Dataset	It is applicable only to only a positive set of numbers.	It can be calculated with both positive and negative sets of numbers.		
Usefulness	Geometric mean can be more useful when the dataset is logarithmic. The difference between the two values is the length.	This method is more appropriate when calculating the mean value of the outputs of a set of independent events .		
Effect of Outlier	The effect of outliers on the Geometric mean is mild. Consider the dataset 11,13,17 and 1000. In this case, 1000 is the outlier. Here, the average is 39.5	The arithmetic mean has a severe effect of outliers. In the dataset 11,13,17 and 1000, the average is 260.25		
Uses	The geometric mean is used by biologists, economists, and also majorly by <u>financial</u> <u>analysts</u> . It is most appropriate for a dataset that exhibits correlation.	The arithmetic mean is used to represent average temperature as well as for car speed.		

3.1.2. Median

- A median is defined as the 50th percentile of a set of measurement.
- If the list of values is ranked from smallest to largest, half of the values are greater than or equal to the median, whereas the other half are less or equal to it.
- In short, it is the "middle value" for a set of ranked values.

- ☑ Can you find the median from both the "true" Table 3.1 and the "contaminated" Table 3.1?
- ☑ Can you see that median is "less sensitive" than the mean from this example?

TABLE 3.1

Forced expiratory volumes in 1 second for 13 adolescents suffering from asthma


Subject	FEV ₁ (liters)	
1	2.30	
2	2.15	
3	3.50	
4	2.60	
5	2.75	
6	2.82	
7	4.05	
8	2.25	
9	2.68	
10	3.00	
→ 11	40.2 4.02	
12	2.85	
13	3.38 15	

How to compute mean and median?


- From hand calculation.
- From MS-Excel or other spreadsheet applications.
- From MATLAB. (Google for something like "MATLAB mean" or "MATLAB median"...)
- Other tools that you know? (For example, some scientific hand calculators)
- Write your own computer program for doing so?

3.1.3. Mode

- The mode is <u>a set of values</u> (not necessarily a single value) in the observation that
 occur(s) most frequently.
- Alternatively, we may say a mode is a set of values that dominate the observation.
- Whether a mode exists, or what should be chosen as a mode for the entire set of observations pretty much depends on the distribution itself.



- (a) <u>Unimodal</u> single peak and symmetric. The mean, median and mode should all be roughly the same.
- (b) <u>Bimodal</u> two symmetric peaks. Mean and median will be roughly the same, which is possibly located in the middle. <u>This is</u> mathematically correct, but definitely not a "dominant" value.
- (c)&(d) Data is **Skewed** (to right and left, respectively). A median is better to measure the central tendency rather than a mean on mode.



- What is x-axis? What is y-axis?
- What are the heights?
- Is a mode (dominant value) occurring on the x-axis (e.g., blood pressure) or y-axis (e.g., frequency)?


Example: 57 scores listed below (ranked from top to bottom and left to right) with

mean = 48.98 and median = 43.

	19	35	38	45	59	74
	25	36	39	45	59	74
	26	36	41	46	59	85
	28	36	41	48	62	87
	28	36	41	49	63	89
	33	37	43	50	63	91
	34	37	43	51	63	92
Ť	34	37	43	51	65	
	34	37	43	53	65	
	35	37	44	58	70	

Category	frequency (heads)
0~10 (1)	0
11~20(2)	1
21~30(3)	4
31~40(4)	17
41~50(5)	13
51~60(6)	8
61~70(7)	6
71~80(8)	3
81~90(9)	3
1~100(10)	2


20



Since the distribution is slightly skewed to the right, median=43 is apparently closer to the mode (between Category '4', or 31~40, to Category '5', or 41~50) than to the mean=48.98.

Comments

- It must be careful not to wrongfully interpret that the measure of central tendency (previously mentioned mean, median or mode) is the representative of ALL observations in the group.
- A rule of thumb is to seriously consider what this "center" means when there are considerable variance (not normal distribution) involved.
- Remember that when we summarize the center of a set of data, information is always lost.



*Recall that a mode is the peak <u>location</u> (on the horizontal axis), not the height of this peak on the vertical axis. ²³

Comments

- To know how good our measurement of central tendency actually is, we need to have some idea about the <u>variation</u> among the measurements.
- Do all the observations tend to be quite similar and therefore lie close to the center (graph (a) from previous slide), or are they spread out across a broad range of values (graph (b) from previous slide)?

- We have discussed about how to determine the measures of central tendency, with the purpose of knowing what our observations are <u>centered</u> <u>to</u>.
- That is, what value(s) are most appropriate to <u>represent</u> the whole collection of observations.


- Following these, we now proceed to investigate the overall distribution of these observations, to better let people understand the quantitative features in addition to the center values (such as mean, median, etc.)
- Range, percentile, interquartile range, variance, etc.

3.2.1 - Range


- A <u>range</u> is a number that describes how "wide" our collections is.
- This is basically the difference between the largest observation and the smallest.
- This "range", however, considers ALL data including the <u>extreme values</u>
 rather than the <u>majority</u> of the observations.

3.2.2 – Interquartile Range

- Recall that Q1 is the 25th percentile, and Q3 the 75th percentile. All data are <u>sorted</u> from smallest to largest.
- Interquartile range is defined as Q3–Q1, which encompasses the middle 50% (Q2, or the median).
- This is more or less like an "effective" or "major" range, since it excludes both 25% of extremes.
- In fact, this is the height (or width) of the box we have seen in a box plot.




☑ What information can you get from organizing these measurements like this?☑ What cities are considered safe?




Range (not boxplot) of annual sulphur dioxide (二氧化硫) average.

Comments to Fig. 3.3

- The <u>averaged</u> SO₂ are still above the lower safety mark for 23rd Dublin and above.
- Although the average for 31st Tokyo is below the mark and considered safe, still a good portion of these readings are polluted.
- While the average of 21st Shanghai is hazardous, most of the readings are below the safety mark (less polluted).
- A few cities, such as Kuala Lumpur, has very limited range.





3.2.3 – Variance and Standard Deviation (STD)

- Variance is a common way of quantifying the amount of *variability*, or *spread*, around the *mean* of the measurements.
- It can be <u>intuitively</u> represented by the following formula, where \bar{x} is the mean value, and x_i the individual measurement for n observations.

$$\frac{1}{n}\sum_{i=1}^{n}(x_i-\overline{x})$$

- In short, variance represented this way is the average distance of the individual observations from its mean value.
- Can you see, however, this formula would always give zero value?

$$\frac{1}{n} \sum_{i=1}^{n} (x_i - \overline{x})$$

- Although we can conveniently use the
 absolute value for these distances, a
 more widely used procedure is to
 Square the deviations from the mean,
 and then find the average of the squared
 distances.
- This summary measure is the
 Variance of the observations
 s². (See next slide.)

The commonly known standard
 deviation (STD), now, is the value s itself
 (or the positive square root of the
 variance).


$$s^{2} = \frac{1}{(n-1)} \sum_{i=1}^{n} (x_{i} - \overline{x})^{2}$$


This is not the number of observations n. (Losing one degree of freedom by estimating the sample mean, \bar{x})

- It can be seen that <u>STD has the same</u> units of measurements as the mean.
- As a result, it is more used than the variance itself (squared units).

Using Excel

- The variance described here can be computed using Excel's function <u>VAR</u>.
- The standard deviation can be computed using Excel's function <u>STDEV</u>.





P: Population. S: Sample.

Using Excel 2016 (left) and MATLAB (right)

It is clear that both Excel's STDEV and MATLAB's std use sample (S) rather than population (P).

```
>> a=1:10
a =
  9 10
>> mean(a)
ans = 5.5000
>> var(a)
ans = 9.1667
>> std(a)
ans = 3.0277
>>
```

3.3.1 — Grouped Mean

- We can compute a mean value by summarizing all values and divided by the count.
- Or we can group them into adequate
 partitions and compute the sum in
 each group individually, followed by the
 division of the total sum by the total
 count.

TABLE 3.3

Duration of transfusion therapy for ten patients with sickle cell disease

Subject	Duration (years)
1	12
2	11
3	12
4	6
5	11
6	11
7	8
8	5
9	5
10	5

3(5)+1(6)+1(8)+3(11)+2(12)=86

Compute the mean value by the following two approaches:

☑ Sum all 10 measurements and divided by the count (which is apparently 10).

☑ Group the measurements into partitions according to the value. For example, subjects 8, 9 and 10 are grouped together because they all have a value of 5 years. Compute the sum of values and sum of counts for each group, then use them to compute the mean value of the complete data set.

- Certainly there is no reason that the two answers you have obtained from the previous exercise in computing the averaged duration would be different.
- The technique of grouping measurements that have equal values before calculating the mean has one distinct advantage over the standard method: this procedure can be applied to data that have been summarized in the form of a frequency distribution.

TABLE 3.4

Absolute frequencies of serum cholesterol levels for U.S. males, aged 25 to 34 years, 1976–1980

Cholesterol Level (mg/100 ml)	Number of Men
80–119	13
120–159	150
160-199	442
200-239	299
240-279	115
280-319	34
320-359	9
360–399	5
Total	1067

Grouped mean is the mean obtained from a grouped data set as seen here.

$$\overline{x} = \frac{\sum_{i=1}^k m_i f_i}{\sum_{i=1}^k f_i},$$

Here k is the count for group, that is 8 in this case, m_i is the midpoint of the i^{th} interval, and f_i is the frequency associated with the i^{th} interval. For example, when i=1, we have $m_1 = (80+119)/2=99.5$ and $f_1 = 13$.

According to this formula, we may have the grouped mean as 198.8 mg/100 ml in this case. (Verify this by yourself.)

Comments

- The grouped mean computed earlier is actually a weighted average of the interval midpoints; each mid-point is weighted by the frequency of observations within the interval.
- This, of course, would likely to be less accurate than computing the average by dividing the grand total by the count of 1,067 US males.

3.3.2 — Grouped Variance

• Likewise we may compute a grouped variance based on the same concept in computing for grouped mean, as well as the definition for the standard variation s^2 we seen earlier. The formula is given below.

$$s^{2} = \frac{\sum_{i=1}^{k} (m_{i} - \overline{x})^{2} f_{i}}{\left[\sum_{i=1}^{k} f_{i}\right] - 1},$$

- Accordingly, the grouped variance s^2 for Table 3.4 can be computed as 1930.9, or s = 43.9 mg/100 ml.
- Together with the grouped mean computer earlier, we may interpret Table 3.4 as "The averaged serum cholesterol level for US males, aged 25 to 34 years, 1976-1980, is

198.8±43.9 mg/100 ml.".

3.4 Chebychev's Inequality

TABLE 3.4

Absolute frequencies of serum cholesterol levels for U.S. males, aged 25 to 34 years, 1976–1980

Cholesterol Level (mg/100 ml)	Number of Men	
80–119	13	
120-159	150	
160-199	442	
200-239	299	
240-279	115	
280-319	34	
320-359	9	
360–399	5	
Total	1067	

Observing that the previous result we had regarding the serum cholesterol level, 198.8±43.9, does not imply that the lowest cholesterol level is 198.8–43.9=**154.9** and highest is 198.8+43.9=**242.7**. (From Table 3.4 you can surely see that there are extreme values beyond that.)

- We *usually* estimate 2*STD from the mean is roughly OK for representing most of the data, assuming that the data distribution is "OK".
- Of course, if we knew something about the actual distribution, we can do better estimation than that.

• If the data are symmetric and unimodal, we can say that approximately 67% of the observations are within $\pm 1*STD$, 95% are within $\pm 2*STD$, and 99% are within $\pm 3*STD$.

This is called a Gaussian distribution, or a bell-shape distribution.

- If, however, we know nothing about the distribution in advance, we may use Chebychev's inequality to have a conservative estimate of that.
- For any number *k* that is greater than 1, at least [1-(1/*k*)²] measurements lie within *k* STDs of their mean.

[1-(1/*k*)²]

$$1 - (\frac{1}{2})^2 = \frac{3}{4}$$

$$1 - (\frac{1}{3})^2 = \frac{8}{9}$$

For k = 2. This value of $\frac{3}{4}$ means that the interval of 2*STD from the mean value encompasses at least 75% of the observation in the group. (Recall for a normal distribution we have 95%.)

For k = 3. This value of 8/9 means that the interval of 3*STD from the mean value encompasses at least 88.9% of the observation in the group. (Recall for a normal distribution we have 99%.)