ffplay播放器-7-8 音频输出和音频重采样

7音频输出模块

打开SDL音频设备

打开音频设备audio_open

回调函数逻辑sdl_audio_callback

回调函数读取数据

8音频重采样

重采样逻辑

样本补偿

《FFmpeg/WebRTC/RTMP音视频流媒体高级开发教程》 - Darren老师: QQ326873713

课程链接: https://ke.qq.com/course/468797?tuin=137bb271

7 音频输出模块

ffplay的音频输出通过SDL实现。

音频输出的主要流程:


- 打开SDL音频设备,设置参数
- 启动SDL音频设备播放
- SDL音频回调函数读取数据,这个时候我们就要从FrameQueue读取frame填充回调函数提供的buffer空间。

audio的输出在SDL下是被动的,即在开启SDL音频后,当SDL需要数据输出时则通过回调函数的方式 告诉应用者需要传入多少数据,但这里存在一些问题:

- ffmpeg解码一个AVPacket的音频到AVFrame后,在AVFrame中存储的音频数据大小与SDL回调所需要的数据不一定相等 (回调函数每次要获取的数据量都是固定);
- 特别是如果要实现声音变速播放功能,那每帧AVFrame做变速后的数据大小大概率和SDL回调锁需要的数据大小不一致。

这就需要再增加一级缓冲区解决问题,即是从FrameQueue队列读取到Frame的数据后,先缓存到一个buffer里,然后再从该buffer读取数据给到SDL回调函数。

在audio输出时,主要模型如下图:



在这个模型中,sdl通过sdl_audio_callback函数向ffplay要音频数据,ffplay将sampq中的数据通过audio_decode_frame 函数取出,放入is->audio_buf,然后送出给sdl。在后续回调时先找audio buf 要数据,数据不足的情况下,再调用audio decode frame补充audio buf

注意 audio_decode_frame 这个函数名很具有迷惑性,实际上,这个函数是没有解码功能的!这个函数主要是处理sampq到audio_buf的过程,最多只是执行了重采样(数据源和输出参数不一致时则做重采样)。

打开SDL音频设备

SDL<mark>音频输出的参数是一开始就设置好的</mark>,当码流的解出来的音频参数和预设的输出参数不一致时,则需要重采样成

预设参数一致数据,这样才能正常播放。

音频设备的打开实际是在解复用线程中实现的。解复用线程中先打开音频设备(设定音频回调函数供 SDL音频播放线程回调),然后再创建音频解码线程。调用链如下:

```
1 main() -->
2 stream_open() -->
3 read_thread() -->
4 stream_component_open() -->
5    audio_open(is, channel_layout, nb_channels, sample_rate, &is->audio_tgt);
```

先看打开sdl音频输出的代码 (stream component open函数):

```
1 //代码在stream component open
2 //先不看filter相关代码,即默认CONFIG_AVFILTER宏为0
3 //从avctx(即AVCodecContext)中获取音频格式参数
4 sample_rate = avctx->sample_rate;
5 nb channels = avctx->channels;
6 channel layout = avctx->channel layout;
7 //调用audio open打开sdl音频输出,实际打开的设备参数保存在audio tgt,返回值表示
  输出设备的缓冲区大小
8 if ((ret = audio_open(is, channel_layout, nb_channels, sample_rate,
  &is->audio tat)) < 0)
10 is->audio hw buf size = ret;
11 is->audio_src = is->audio_tgt; //暂且将数据源参数等同于目标输出参数
12 //初始化audio buf相关参数
13 is->audio_buf_size = 0;
14 is->audio buf index = 0;
```

由于不同的音频输出设备支持的参数不同,音轨的参数不一定能被输出设备支持(此时就需要重采样了), audio tgt 就保存了输出设备参数。

audio_open是ffplay封装的函数,会优先尝试请求参数能否打开输出设备,尝试失败后会自动查找最佳的参数重新尝试。不再具体分析。

audio_src 一开始与audio_tgt 是一样的,如果输出设备支持音轨参数,那么audio_src 可以一直保持与audio tgt 一致,否则将在后面代码中自动修正为音轨参数,并引入重采样机制。

最后初始化了几个audio buf相关的参数。这里介绍下audio buf相关的几个变量:

- audio buf: 从要输出的AVFrame中取出的音频数据(PCM),如果有必要,则对该数据重采样。
- audio_buf_size: audio_buf的总大小
- audio buf index: 下一次可读的audio buf的index位置。
- audio_write_buf_size: audio_buf剩余的buffer长度,即audio_buf_size audio_buf_index

在 audio_open 函数内,通过通过 SDL_OpenAudioDevice 注册 sdl_audio_callback 函数为音频输出的回调函数。那么,主要的音频输出的逻辑就在 sdl audio callback 函数内了。

打开音频设备audio_open

audio_open()函数填入期望的音频参数,打开音频设备后,将实际的音频参数存入输出参数is->audio_tgt中,后面音频播放线程用会用到此参数,使用此参数将原始音频数据重采样,转换为音

```
1 static int audio open(void *opaque, int64 t wanted channel layout,
  int wanted nb channels, int wanted sample rate, struct AudioParams
  *audio_hw_params)
2 {
3
      SDL AudioSpec wanted spec, spec;
      const char *env;
5
      static const int next_nb_channels[] = {0, 0, 1, 6, 2, 6, 4, 6};
      static const int next sample rates[] = {0, 44100, 48000, 96000,
  192000}:
      int next_sample_rate_idx = FF_ARRAY_ELEMS(next_sample_rates) -
  1;
8
      env = SDL getenv("SDL AUDIO CHANNELS");
      if (env) { // 若环境变量有设置, 优先从环境变量取得声道数和声道布局
10
11
          wanted_nb_channels = atoi(env);
          wanted_channel_layout = av_get_default_channel_layout(wante
12
  d_nb_channels);
13
      }
14
      if (!wanted channel layout | | wanted nb channels != av get chan
  nel layout nb channels(wanted channel layout)) {
15
          wanted_channel_layout = av_get_default_channel_layout(wante
  d_nb_channels);
16
          wanted channel layout &= ~AV CH LAYOUT STEREO DOWNMIX;
17
      }
18
      // 根据channel_layout获取nb_channels, 当传入参数wanted_nb_channels不
  匹配时, 此处会作修正
      wanted_nb_channels = av_get_channel_layout_nb_channels(wanted_c
  hannel layout);
20
      wanted_spec.channels = wanted_nb_channels;
21
      wanted spec.freg = wanted sample rate;
      if (wanted_spec.freq <= 0 || wanted_spec.channels <= 0) {</pre>
22
          av_log(NULL, AV_LOG_ERROR, "Invalid sample rate or channel
23
   count!\n");
24
          return -1:
25
      }
26
      while (next_sample_rate_idx && next_sample_rates[next_sample_ra
  te_idx] >= wanted_spec.freq)
```

```
next sample rate idx--; // 从采样率数组中找到第一个不大于传入参数w
  anted sample rate的值
     // 音频采样格式有两大类型: planar和packed, 假设一个双声道音频文件, 一个左声
  道采样点记作L,一个右声道采样点记作R,则:
    // planar存储格式: (plane1)LLLLLLLL...LLLL (plane2)RRRRRRRR...RRR
  R
     // packed存储格式: (plane1)LRLRLRLR.....LRL
30
  R
31
      // 在这两种采样类型下,又细分多种采样格式,如AV SAMPLE FMT S16、AV SAMPL
  E FMT S16P等,
32
    // 注意SDL2.0目前不支持planar格式
     // channel layout是int64 t类型,表示音频声道布局,每bit代表一个特定的声
33
  道,参考channel_layout.h中的定义,一目了然
34
     // 数据量(bits/秒) = 采样率(Hz) * 采样深度(bit) * 声道数
     wanted_spec.format = AUDIO_S16SYS;
36
     wanted spec.silence = 0;
    /*
37
     * 一次读取多长的数据
39
      * SDL AUDIO MAX CALLBACKS PER SEC一秒最多回调次数,避免频繁的回调
40
      * Audio buffer size in samples (power of 2)
41
      */
42
      wanted_spec.samples = FFMAX(SDL_AUDIO_MIN_BUFFER_SIZE, 2 << av_</pre>
  log2(wanted spec.freg / SDL AUDIO MAX CALLBACKS PER SEC));
43
      wanted spec.callback = sdl audio callback;
44
      wanted_spec.userdata = opaque;
      // 打开音频设备并创建音频处理线程。期望的参数是wanted_spec,实际得到的硬件
45
  参数是spec
      // 1) SDL提供两种使音频设备取得音频数据方法:
46
          a. push, SDL以特定的频率调用回调函数, 在回调函数中取得音频数据
47
           b. pull, 用户程序以特定的频率调用SDL QueueAudio(), 向音频设备提供
48
  数据。此种情况wanted spec.callback=NULL
49 // 2) 音频设备打开后播放静音,不启动回调,调用SDL PauseAudio(0)后启动回
  调,开始正常播放音频
50 // SDL OpenAudioDevice()第一个参数为NULL时,等价于SDL OpenAudio()
      while (!(audio dev = SDL OpenAudioDevice(NULL, 0, &wanted spec,
  &spec, SDL_AUDIO_ALLOW_FREQUENCY_CHANGE | SDL_AUDIO_ALLOW_CHANNELS_
  CHANGE))) {
         av log(NULL, AV LOG WARNING, "SDL OpenAudio (%d channels, %
  d Hz): %s\n",
               wanted_spec.channels, wanted_spec.freq, SDL_GetError
53
```

```
());
54
          wanted spec.channels = next nb channels[FFMIN(7, wanted spe
  c.channels)];
         if (!wanted_spec.channels) {
55
56
              wanted spec.freq = next sample rates[next sample rate i
  dx--];
              wanted_spec.channels = wanted_nb_channels;
57
              if (!wanted spec.freg) {
59
                  av log(NULL, AV LOG ERROR,
                        "No more combinations to try, audio open fai
60
  led\n");
61
                  return -1;
              }
62
63
          }
          wanted_channel_layout = av_get_default_channel_layout(wante
64
  d spec.channels);
      }
6.5
      // 检查打开音频设备的实际参数:采样格式
66
      if (spec.format != AUDIO S16SYS) {
67
          av log(NULL, AV LOG ERROR,
68
69
                 "SDL advised audio format %d is not supported!\n", s
pec.format);
70
         return -1;
71
      }
      // 检查打开音频设备的实际参数: 声道数
72
      if (spec.channels != wanted_spec.channels) {
73
74
          wanted channel layout = av get default channel layout(spec.
  channels):
         if (!wanted_channel_layout) {
75
              av_log(NULL, AV_LOG_ERROR,
76
77
                    "SDL advised channel count %d is not supported!
  \n", spec.channels);
78
             return -1;
          }
79
80
      }
      // wanted_spec是期望的参数, spec是实际的参数, wanted_spec和spec都是SDL
  中的结构。
      // 此处audio_hw_params是FFmpeg中的参数,输出参数供上级函数使用
82
      // audio_hw_params保存的参数,就是在做重采样的时候要转成的格式。
      audio hw params->fmt = AV SAMPLE FMT S16;
84
```

```
audio hw params->freq = spec.freq;
       audio_hw_params->channel_layout = wanted_channel_layout;
       audio hw params->channels = spec.channels;
87
       /* audio_hw_params->frame_size这里只是计算一个采样点占用的字节数 */
       audio_hw_params->frame_size = av_samples_get_buffer_size(NULL,
89
   audio_hw_params->channels,
90
                                                               1, aud
   io hw params->fmt, 1);
       audio_hw_params->bytes_per_sec = av_samples_get_buffer_size(NUL)
   L, audio_hw_params->channels,
92
                                                                  aud
   io_hw_params->freq,
93
                                                                  aud
   io_hw_params->fmt, 1);
       if (audio_hw_params->bytes_per_sec <= 0 || audio_hw_params->fra
   me size <= 0) {
          av_log(NULL, AV_LOG_ERROR, "av_samples_get_buffer_size fail
   ed\n");
          return -1;
97
       }
       // 比如2帧数据, 一帧就是1024个采样点, 1024*2*2 * 2 = 8096字节
      return spec.size; /* 硬件内部缓存的数据字节, samples * channels *b
99
  yte_per_sample */
100 }
```

回调函数逻辑 sdl audio callback

再来看 sdl audio callback


```
1 static void sdl_audio_callback(void *opaque, Uint8 *stream, int len)
2 {
3     VideoState *is = opaque;
4     int audio_size, len1;
5
6     audio_callback_time = av_gettime_relative();
7
8     while (len > 0) { // 循环读取, 直到读取到足够的数据
```

```
/* (1)如果is->audio buf index < is->audio buf size则说明上次拷贝
  还剩余一些数据,
           * 先拷贝到stream再调用audio decode frame
10
           * (2)如果audio_buf消耗完了,则调用audio_decode_frame重新填充audio
11
  buf
12
          */
          if (is->audio buf index >= is->audio buf size) {
13
              audio size = audio decode frame(is);
14
              if (audio size < 0) {</pre>
15
                  /* if error, just output silence */
16
17
                  is->audio buf = NULL;
                  is->audio buf size = SDL AUDIO MIN BUFFER SIZE / is-
18
  >audio tgt.frame size
                         * is->audio tgt.frame size;
19
20
              } else {
21
                  if (is->show mode != SHOW MODE VIDEO)
22
                      update sample display(is, (int16 t *)is->audio b
  uf, audio size);
23
                  is->audio buf size = audio size;
24
              }
25
              is->audio buf index = 0;
26
          }
27
          //根据缓冲区剩余大小量力而行
          len1 = is->audio buf size - is->audio buf index;
28
          if (len1 > len)
29
              len1 = len;
30
          //根据audio volume决定如何输出audio buf
31
          /* 判断是否为静音,以及当前音量的大小,如果音量为最大则直接拷贝数据 */
32
          if (!is->muted && is->audio_buf && is->audio_volume == SDL_M
33
  IX MAXVOLUME)
              memcpy(stream, (uint8 t *)is->audio buf + is->audio buf
34
  index, len1);
35
          else {
              memset(stream, 0, len1);
              // 调整音量
37
              /* 如果处于mute状态则直接使用stream填0数据, 暂停时is->audio buf
  = NULL */
              if (!is->muted && is->audio buf)
39
                  SDL MixAudioFormat(stream, (uint8 t *)is->audio buf
 + is->audio_buf_index,
```

```
41
                                      AUDIO S16SYS, len1, is->audio vol
  ume):
42
           }
           len -= len1;
43
           stream += len1:
44
45
           /* 更新is->audio buf index, 指向audio buf中未被拷贝到stream的数据
   (剩余数据) 的起始位置 */
46
           is->audio buf index += len1;
       }
47
      is->audio_write_buf_size = is->audio_buf_size - is->audio_buf_in
48
  dex;
      /* Let's assume the audio driver that is used by SDL has two per
49
   iods. */
       if (!isnan(is->audio clock)) {
50
           set_clock_at(&is->audclk,
51
                        is->audio clock - (double)(2 * is->audio hw buf
52
  _size + is->audio_write_buf_size) / is->audio_tgt.bytes_per_sec,
53
                        is->audio clock serial,
                        audio callback time / 1000000.0);
54
           sync clock to slave(&is->extclk, &is->audclk);
55
56
      }
57 }
```


sdl_audio_callback 函数是一个典型的缓冲区输出过程,看代码和注释应该可以理解。具体看3个细节:

- 输出audio_buf到stream,如果audio_volume为最大音量,则只需memcpy复制给stream即可。否则,可以利用SDL_MixAudioFormat进行音量调整和混音
- 如果audio_buf消耗完了,就调用 audio_decode_frame 重新填充audio_buf。接下来会继续分析 audio decode frame函数
- set_clock_at更新audclk时, audio_clock是当前audio_buf的显示结束时间(pts+duration),由于audio driver本身会持有一小块缓冲区,典型地会是两块交替使用,所以有2 * is->audio hw buf size,至于为什么还要audio_write_buf_size,一图胜千言。



我们先来is->audio_clock是在audio_decode_frame赋值:

is->audio_clock = af->pts + (double) af->frame->nb_samples / af->frame->sample_rate; 从这里可以看出来,这里的时间戳是audio_buf结束位置的时间戳,而不是audio_buf起始位置的时间戳,所以当audio_buf有剩余时(),那实际数据的pts就变成is->audio_clock - (double)(is->audio_write_buf_size) / is->audio_tgt.bytes_per_sec,即是



再考虑到,实质上audio_hw_buf_size*2这些数据实际都没有播放出去,所以就有 is->audio_clock - (double)(2 * is->audio_hw_buf_size + is->audio_write_buf_size) / is->audio_tgt.bytes_per_sec。



的时候, 那相对时间实际也在走。

```
static void sdl_audio_callback(void *opaque, Uint8 *stream, int len)

VideoState *is = opaque;
int audio_size, len1;

audio_callback_time = av_gettime_relative();

最终

set_clock_at(&is->audclk, is->audio_clock - (double)(2 * is->audio_hw_buf_size + is->audio_write_buf_size) / is->audio_tgt.bytes_per_sec, is->audio_clock_serial,
```

回调函数读取数据

audio callback time / 1000000.0);

接下来看下 audio decode frame (省略重采样代码):

```
1 static int audio decode frame(VideoState *is)
 2 {
      int data size, resampled data size;
 3
      int64 t dec channel layout;
 4
      av_unused double audio_clock0;
 5
      int wanted nb samples;
 7
      Frame *af:
      if (is->paused)//暂停状态,返回-1, sdl audio callback会处理为输出静音
 9
          return -1;
      do {//1. 从sampq取一帧,必要时丢帧
10
          if (!(af = frame_queue_peek_readable(&is->sampq)))
11
12
              return -1:
13
          frame queue next(&is->sampg);
14
      } while (af->serial != is->audiog.serial);
      //2』 计算这一帧的字节数
15
16
      data_size = av_samples_get_buffer_size(NULL, af->frame->channels
17
                                             af->frame->nb samples,
                                             af->frame->format, 1);
18
19
      //[]计算dec_channel_layout, 用于确认是否需要重新初始化重采样(难道af->cha
  nnel layout不可靠?不理解)
```

```
dec channel layout =
          (af->frame->channel layout && af->frame->channels == av get
21
  channel layout nb channels(af->frame->channel layout)) ?
          af->frame->channel_layout : av_get_default_channel_layout(af
22
  ->frame->channels):
23
      wanted nb samples = synchronize audio(is, af->frame->nb samples)
  ;
24
      //[]判断是否需要重新初始化重采样
      if (af->frame->format
                             != is->audio src.fmt
                                                                  П
25
          dec channel layout
                                 != is->audio src.channel layout ||
26
27
          af->frame->sample_rate != is->audio_src.freq
                                                                  Ш
          (wanted nb samples != af→frame→nb samples && !is→sw
28
   r ctx)) {
29
          //.....
30
      }
31
      //3. 获取这一帧的数据
      if (is->swr_ctx) {//[]如果初始化了重采样,则对这一帧数据重采样输出
32
33
      }else {
          is->audio buf = af->frame->data[0];
34
35
          resampled data size = data size;
      }
37
      audio_clock0 = is->audio_clock;//audio_clock0用于打印调试信息
      //4. 更新audio clock, audio clock serial
      /* update the audio clock with the pts */
39
      if (!isnan(af->pts))
40
          is->audio_clock = af->pts + (double) af->frame->nb_samples /
41
  af->frame->sample rate;
42
      else
          is->audio clock = NAN;
43
44
      is->audio clock serial = af->serial;
45
      return resampled data size; //返回audio buf的数据大小
46 }
```

audio decode frame 并没有真正意义上的 decode 代码,最多是进行了重采样。主流程有以下步骤:

- 1. 从sampq取一帧,必要时丢帧。如发生了seek,此时serial会不连续,就需要丢帧处理
- 2. 计算这一帧的字节数。通过av_samples_get_buffer_size可以方便计算出结果
- 3. 获取这一帧的数据。对于frame格式和输出设备不同的,需要重采样;如果格式相同,则直接拷贝指针输出即可。总之,需要在audio buf中保存与输出设备格式相同的音频数据
- 4. 更新audio_clock, audio_clock_serial。用于设置audclk.

在省略了重采样代码后看,相对容易理解。

8 音频重采样

FFmpeg解码得到的音频帧的格式未必能被SDL支持,在这种情况下,需要进行音频重采样,即将音频帧格式转换为SDL支持的音频格式,否则是无法正常播放的。

音频重采样涉及两个步骤:

- 1. 打开音频设备时进行的准备工作:确定SDL支持的音频格式,作为后期音频重采样的目标格式。这一部分内容参考《7 音频输出模块》
- 2. 音频播放线程中,取出音频帧后,若有需要(音频帧格式与SDL支持音频格式不匹配)则进行重采样,否则直接输出

重采样逻辑

音频重采样在 audio_decode_frame() 中实现, audio_decode_frame() 就是从音频frame队列中取出一个frame,按指定格式经过重采样后输出(解码不是在该函数进行)。

重采样的细节很琐碎,直接看注释:

```
1 static int audio_decode_frame(VideoState *is)
2 {
 3
       int data size, resampled data size;
       int64_t dec_channel_layout;
       av_unused double audio_clock0;
 5
 6
       int wanted nb samples;
 7
       Frame *af:
8
9
       if (is->paused)
10
           return -1;
11
12
       do {
13 #if defined(_WIN32)
           while (frame queue nb remaining(\&is->sampg) == 0) {
14
15
               if ((av_gettime_relative() - audio_callback_time) > 100
  0000LL * is->audio_hw_buf_size / is->audio_tgt.bytes_per_sec / 2)
16
                   return -1;
               av usleep (1000);
17
18
           }
19 #endif
```

```
20
          // 若队列头部可读,则由af指向可读帧
          if (!(af = frame queue peek readable(&is->sampq)))
21
22
             return -1;
         frame_queue_next(&is->sampq);
23
24
      } while (af->serial != is->audioq.serial);
      // 根据frame中指定的音频参数获取缓冲区的大小
26
27
      data size = av samples get buffer size(NULL,
28
                                          af->frame->channels,
29
                                          af->frame->nb samples,
30
                                          af->frame->format, 1);
     // 获取声道布局
31
     dec channel layout =
32
33
             (af->frame->channel layout &&
34
              af->frame->channels == av_get_channel_layout_nb_channe
  ls(af->frame->channel layout)) ?
                 af->frame->channel_layout : av_get_default_channel_
  layout(af->frame->channels);
36 // 获取样本数校正值: 若同步时钟是音频,则不调整样本数;否则根据同步需要调整样
  本数
37
      wanted_nb_samples = synchronize_audio(is, af->frame->nb_samples
  );
      // is->audio tgt是SDL可接受的音频帧数,是audio open()中取得的参数
      // 在audio open()函数中又有"is->audio src = is->audio tgt""
39
      // 此处表示: 如果frame中的音频参数 == is->audio src == is->audio tg
40
  t,
41
      // 那音频重采样的过程就免了(因此时is->swr ctr是NULL)
42
      // 否则使用frame(源)和is->audio tgt(目标)中的音频参数来设置is->swr ct
  Χ,
      // 并使用frame中的音频参数来赋值is->audio src
43
44
      if (af->frame->format != is->audio_src.fmt
             dec_channel_layout != is->audio_src.channel_layou
45
  t ||
46
             af->frame->sample rate != is->audio src.freq
  47
             (wanted nb samples != af->frame->nb samples &&!i
  s->swr_ctx)) {
         swr free(&is->swr ctx);
48
         is->swr_ctx = swr_alloc_set_opts(NULL,
49
                                        is->audio tgt.channel layo
50
```

```
ut, // 目标输出
51
                                           is->audio tqt.fmt,
52
                                           is->audio_tgt.freq,
                                           dec_channel_layout,
53
  // 数据源
54
                                           af->frame->format,
                                           af->frame->sample_rate,
                                           0, NULL);
          if (!is->swr_ctx || swr_init(is->swr_ctx) < 0) {</pre>
57
              av_log(NULL, AV_LOG_ERROR,
59
                     "Cannot create sample rate converter for convers
  ion of %d Hz %s %d channels to %d Hz %s %d channels!\n",
                     af->frame->sample_rate, av_get_sample_fmt_name(a
60
  f->frame->format), af->frame->channels,
                     is->audio_tgt.freq, av_get_sample_fmt_name(is->a
61
  udio_tgt.fmt), is->audio_tgt.channels);
62
              swr_free(&is->swr_ctx);
63
              return -1;
          }
64
          is->audio src.channel layout = dec channel layout;
65
          is->audio_src.channels = af->frame->channels;
66
          is->audio_src.freq = af->frame->sample_rate;
67
          is->audio src.fmt = af->frame->format;
      }
69
70
71
      if (is->swr_ctx) {
          // 重采样输入参数1: 输入音频样本数是af->frame->nb samples
72
73
          const uint8_t **in = (const uint8_t **)af->frame->extended_
  data;
74
          // 重采样输入参数2: 输入音频缓冲区
          uint8 t **out = &is->audio buf1;
          // 重采样输出参数1:输出音频缓冲区尺寸
76
          int out_count = (int64_t)wanted_nb_samples *
77
                              is->audio_tgt.freq / af->frame->sample_
  rate + 256:
79
          // 重采样输出参数2:输出音频缓冲区
          int out_size = av_samples_get_buffer_size(NULL, is->audio_
  tgt.channels,
                                                     out_count, is->a
  udio_tgt.fmt, 0);
```

```
82
           int len2;
           if (out size < 0) {</pre>
               av_log(NULL, AV_LOG_ERROR, "av_samples_get_buffer_size
 84
    () failed\n");
               return -1;
           }
           // 如果frame中的样本数经过校正,则条件成立
           if (wanted nb samples != af->frame->nb samples) {
               if (swr set compensation(is->swr ctx,
 89
                                        (wanted nb samples - af->frame
 90
   ->nb_samples) *
 91
                                           is->audio tgt.freg / af->fr
   ame->sample_rate,
 92
                                        wanted_nb_samples * is->audio_
   tgt.freq /
 93
                                           af->frame->sample rate) < 0
    ) {
                   av_log(NULL, AV_LOG_ERROR, "swr_set_compensation()
 94
    failed\n");
                    return -1;
               }
 97
           av fast malloc(&is->audio buf1, &is->audio buf1 size, out s
   ize);
           if (!is->audio buf1)
99
               return AVERROR(ENOMEM);
100
           // 音频重采样:返回值是重采样后得到的音频数据中单个声道的样本数
101
102
           len2 = swr_convert(is->swr_ctx, out, out_count, in, af->fra
   me->nb_samples);
103
           if (len2 < 0) {</pre>
               av_log(NULL, AV_LOG_ERROR, "swr_convert() failed\n");
104
105
               return -1;
106
           }
           if (len2 == out count) {
107
                av_log(NULL, AV_LOG_WARNING, "audio buffer is probably
108
    too small\n");
               if (swr_init(is->swr_ctx) < 0)</pre>
109
                    swr free(&is->swr ctx);
110
111
           // 重采样返回的一帧音频数据大小(以字节为单位)
112
```

```
is->audio buf = is->audio buf1;
113
            resampled data size = len2 * is->audio tgt.channels * av ge
114
   t bytes per sample(is->audio tqt.fmt);
       } else {
115
116
           // 未经重采样,则将指针指向frame中的音频数据
117
            is->audio buf = af->frame->data[0];
            resampled_data_size = data_size;
118
119
       }
120
121
        audio_clock0 = is->audio_clock;
122
       /* update the audio clock with the pts */
123
       if (!isnan(af->pts))
            is->audio_clock = af->pts + (double) af->frame->nb_samples
124
   / af->frame->sample rate;
125
       else
126
            is->audio clock = NAN;
127
        is->audio clock serial = af->serial;
128 #ifdef DEBUG
129 {
130
            static double last clock;
            printf("audio: delay=%0.3f clock=%0.3f clock0=%0.3f\n",
131
132
                   is->audio_clock - last_clock,
                   is->audio clock, audio clock0);
133
            last clock = is->audio clock;
134
135
       }
136 #endif
        return resampled data size;
137
138 }
```

样本补偿

```
swr_set_compensation说明
/**

* Activate resampling compensation ("soft" compensation). This function is

* internally called when needed in swr_next_pts().

*

* @param[in,out] s allocated Swr context. If it is not initialized,

* or SWR_FLAG_RESAMPLE is not set, swr_init() is

* called with the flag set.
```

```
* @param[in]
               sample_delta delta in PTS per sample (每个样本的增量,单位pts)
* @param[in]
               compensation_distance number of samples to compensate for (要补偿的样本
数)
* @return
           >= 0 on success, AVERROR error codes if:
         @li @c s is NULL,
*
         @li @c compensation_distance is less than 0,
         @li @c compensation_distance is 0 but sample_delta is not,
*
         @li compensation unsupported by resampler, or
*
         @li swr_init() fails when called.
*/
int swr_set_compensation(struct SwrContext *s, int sample_delta, int compensation_distance);
sample_delta: (wanted_nb_samples - af->frame->nb_samples) * is->audio_tgt.freq / af-
>frame->sample_rate;
compensation_distance: wanted_nb_samples * is->audio_tgt.freq / af->frame->sample_rate)
注意是谁是除数,谁是被除数。
```