Reversing with **GDB** and **GEF**

Starting GDB

```
gdb program\ [core|pid] gdb gdb-options\ [--args\ program\ args] gdb -p\ pid
```

At startup, gdb reads the following init files and executes their commands: /etc/gdb/gdbinit and ~/.gdbinit, plus ./.gdbinit, if set auto-load local-gdbinit is set to on. In addition to reading its config from ~/.gef.rc, GEF can also be configured with gef config.

Some options are:

```
don't print version number on startup
-q/--quiet/--silent
-h/--help
                       print help
--tty=TTY
                       use TTY for I/O by debugged program
                      do not read ~/.gdbinit
--nh
-x FILE
                      execute GDB commands from FILE
-ix FILE
                      like -x but execute before loading inferior
-ex CMD
                      execute a single GDB command
-iex\ CMD
                      like -ex but before loading inferior
-s SYMFILE
                      read symbols from SYMFILE
                      set writing into executable and core files
--write
```

To quit, q[uit] or Ctrl-D. You can invoke commands on the standard shell by using: shell command-string or simply: !command-string Commands can be abbreviated, when unambiguous, and some commands can be repeated by typing just Return. Tab autocompletes. You can ask for information on commands by using h[elp] and gef help, or use apropos regexp to search for commands matching regexp. When GDB is spawn from a tmux session, tmux-setup splits the pane vertically, and configure the context to be redirected to the new pane.

Debugging targets target type param connects to machines, processs, or files; e.g. target remote | sshpass -ppw ssh -T [-p port] [user@host] gdbserver - prog [args]

gef-remote is a wrapper for the target remote command, which includes a QEMU-mode with -q.

Processes and threads When a program forks, gdb will continue to debug the parent. To follow the child, use set follow-fork-mode; to debug both processes, use set detach-on-fork off. Then, you can list the inferiors with info inferiors and switch among them with inferior id. If you issue a run after an exec call executes, the new target restarts. To restart the original one, use file with parent executable name as its argument.

info threads lists current threads, thread *id* selects the current one, thread name *name* gives a name and thread apply *range* all *cmd* runs *cmd* for each specified thread; e.g. thread apply all bt.

In (default) all-stop mode, whenever your program stops, all threads stop. Conversely, whenever you restart the program, all threads start executing, even when single-stepping. Set scheduler-locking to on or step to avoid this. To enable non-stop mode, use set pagination
off and set non-stop on, before starting/connecting-to a target.

Logging output Logging can be enabled/disabled with set logging on/off. set logging file file changes the current log-file (default: gdb.txt). show logging shows current logging settings; other settings are logging overwrite, and logging redirect to choose whether the output goes to both terminal and logfile.

Starting your program

r[un] [args], start [args] and starti [args]

start does the equivalent of setting a temporary breakpoint at the beginning of main and invoking run. starti does the equivalent of setting a temporary breakpoint at the first instruction of a program's execution and invoking run. For programs containing an elaboration phase, starti will stop execution at the start of the elaboration phase. args may include "*", or "[...]"; they are expanded using the shell that will start the program (specified by the \$SHELL environment variable). Input/output redirection with ">", "<", or ">>" are also allowed. With no arguments these commands use arguments last specified: to cancel previous arguments, use set args without arguments. To start the inferior without using a shell, use set startup-with-shell off. set disable-randomization on (enabled by default) turns off ASLR; equivalently: set exec-wrapper setarch 'uname -m' -R. Also, aslr. elf -info provides basic information on currently loaded program. checksec, inspired from checksec.sh, provides a convenient way to determine which security protections are enabled in a binary.

Environment

show environment [varname], set environment varname [=value] and unset environment varname

The changes are for your program (and the shell gdb uses to launch it), not for gdb itself. If your shell runs an initialization file when started non-interactively, it may affect your program.

set $\operatorname{cwd} [dir]$ sets the inferior's working directory to dir, while $\operatorname{cd} [dir]$ changes gdb working directory.

tty is an alias for set inferior-tty, which can be used to set the terminal terminal that will be used for future runs.

If debugged program was compiled with <code>-fstack-protector</code>, <code>canary</code> displays the value of the canary. <code>hijack-fd fd-num neufile</code> can be used to modify file descriptors of the debugged process. Permission rights on specific pages can be set by using <code>set-permission</code>.

Stopping execution

- breakpoints make your program stop whenever a certain point in the program is reached; you can add conditions to control whether your program stops. [t]b[reak] location [thread id] [if condition] sets a [temporary] breakpoint at the given location [, and given condition]. When called without any arguments, break sets a breakpoint at the next instruction to be executed. To use an address as a location, you must prepend it with *; e.g. *0x1234.
 - [t]hbreak args sets [temporary] hardware breakpoints
 - rbreak [file:] regex set breakpoints on all functions [of file] matching the regular expression regex.

info break[points] [list] prints all breakpoints, watchpoints, and catchpoints (or the ones specified in list). clear lccation and delete [breakpoints] list delete breakpoints.

ignore bnum n sets the ignore count of breakpoint bnum to n (0 to make it stop the next time breakpoint bnum is reached).

- format-string-helper creates a specific type of breakpoints dedicated to detecting potentially insecure format strings.
- pie ... handles PIE breakpoints.
- watchpoints, AKA data breakpoints, are special breakpoints that stop your program when the value of an expression changes. watch [-1[ocation]] expr [thread thread-id] sets a watchpoint for expression expr. If the command includes thread-id argument, gdb breaks only when the corresponding thread changes the value of expr. Ordinarily a watchpoint respects the scope of variables in expr; however, -location tells gdb to instead watch the memory referred to by expr.
 - rwatch sets a read watchpoint
 - awatch sets an access (i.e., read or write) watchpoint
 - info watchpoints [list] prints a list of watchpoints
- catchpoints stop your program when a certain kind of event occurs, such as throwing a C++ exception or loading a library.

 catch event stops when event occurs; it can be: an exception event; syscall [name | number | g[roup]:groupname], exec, fork, [un]load regexp, signal [signal... | all]. Use set stop-on-solib-events 1 to stop the target when a shared library is loaded or unloaded.
- To stop when your program receives a signal, use handle

A *point can have any of several different states of enablement:

- Enabled/Disabled— {enable|disable} [breakpoints] [list]
- Enabled once enable [breakpoints] once [list]
- Enabled for a count enable [breakpoints] count n [list]
- Enabled for deletion enable [breakpoints] delete [list]

condition bnum [expr] sets or removes a condition for *point bnum.

When a *point is hit, GEF displays the context (current instruction, registers, stack, ...) via its context command; to configure its layout see gef config context.layout. Any *point can execute a series of commands when hit; see commands.

save breakpoints filename saves all current *point definitions together with their commands and ignore counts, into filename. To read the saved breakpoint definitions, use source.

Checkpoints

checkpoint saves a snapshot; info checkpoints lists the checkpoints that have been saved, while restart checkpoint-id restores the state that was saved. A checkpoint only restores things that reside in the program being debugged, not in the debugger. Finally, delete check point checkpoint-id deletes the corresponding checkpoint.

Returning to a checkpoint restores the user state of the program being debugged, and a subset of the OS state including file pointers.

Getting information

i[nfo] is for describing the state of your program. For example, you can show the arguments passed to a function with info args; you can get a complete list of the info sub-commands with help info.

info program displays information about the status of your program. process-status provides an exhaustive description of the current running process, by extending the information provided by info proc. got displays the status of the GOT inside the process.

vmmap displays the entire memory space mapping (info shared just
the status of shared libraries); xfiles is a more convenient representation of info files to list the targets and files being debugged.

You can assign the result of an expression to an environment variable with **set**. For example, to set the prompt to a \$-sign: **set prompt** \$.

show is for describing the state of gdb itself. You can change most of things by using set; for example, what number system is used with set radix, or inquire it with show radix. To display all settable parameters and their values, you can use show with no arguments.

info address symbol shows where data for symbol is stored. info symbol addr prints the name of a symbol stored at the address addr. If no symbol is stored exactly at addr, gdb prints the nearest symbol and an offset from it. xinfo displays all information about a specific address. [add-]symbol-file loads different symbol tables.

Examining the stack

One of the stack frames is selected and many commands refer implicitly to it. There are commands to select whichever frame you are interested in (f[rame][n|addr], up[n] and down[n]). When your program stops, gdb automatically selects the currently executing frame and describes it briefly, similar to the f[rame] command (without argument; for a more verbose description, infof[rame][addr]).

info args prints the arguments of selected frame, while info locals the local variables.

A backtrace is a summary of how your program got where it is. To print a backtrace of the entire stack, use bt / backtrace [full]; for dumping the stacks of all threads: thread apply bt [full].

Examining code

disassemble dumps a range of memory as machine instructions, with the raw instructions in hex with the /r modifier. The arguments specify a range of addresses to dump, in one of two forms: start, end to disassemble from start (inclusive) to end (exclusive), and start, +length to disassemble from start (inclusive) to start+length (exclusive). See cs / capstone-disassemble (note: different args) for using Capstone. If you have Keystone, then GEE cap assemble native instructions dis

If you have Keystone, then GEF can assemble native instructions directly with $\verb"asm" / assembler"$.

Examining data

registers $[r_1 \ [r_2 \ \ldots]]$ displays registers and dereference any pointers (in plain gdb you can see register values with info registers); [edit-]flags [{+|-|-} flag-name [...]] shows/edits the flag register.

p[rint] [/f] expr prints the value of expression expr (in the source language). By default it's printed in a format appropriate to its type;

you can choose a different format by specifying f, where f is one of: o(octal), x(hex), d(decimal), u(unsigned decimal), t(binary), f(float), a(address), c(char), s(string) and z(hex, zero padded on the left).

ptype [/o] expr prints the type of expr [with field offsets/sizes]. The expression $\{t\}$ addr refers to an object of type t, stored at addr.

printed expressions may include function calls in the program being debugged; use **call** addr for calling functions without printing.

 $\mathbf{x}[/fmt]$ [addr] examines memory; default addr is usually just after the last address examined. fmt is a repeat count followed by a format letter and a size letter. Format letters are like print plus i(instruction). Sizes are b(byte), h(halfword), w(word), g(giant, 8 bytes). If a negative number is specified, memory is examined backward. With GEF you can use hexdump {qword|dword|word|byte} lecation [1size] [up|down].

dprintf $lcation, format-str[,a_1[,a_2...]]$ sets a dynamic printf at specified location; this is actually a dprintf-breakpoint and you can use **cond** to add a condition, for instance.

memory ... adds or removes address ranges to the memory view.

dereference / telescope simplifies the dereferencing of an address in GDB to determine the content it actually points to.

The \$ command mimics WinDBG ? command: when provided one argument, it evaluates the expression and displays the result in various formats. With two arguments, the delta between them.

heap... is a base command to get information about the Glibc heap structure; moreover, heap-analysis-helper aims to help the process of identifying Glibc heap inconsistencies by tracking and analyzing allocations and deallocations.

nop and patch writes values into memory.

dump, append, and restore copy data between target memory and a file. dump and append write data to a file, whereas restore reads data from a file back into the inferior's memory.

print-format / pf dumps an arbitrary location as an array of bytes following the syntax of the programming language specified.

shellcode is a client for @JonathanSalwan shellcodes database.

stub stubs out functions, optionally specifying the return value.

Automatic display If you find that you want to print the value of an expression frequently you might want to add it to the automatic display list so that gdb prints its value each time your program stops. display[/fmt] {expr|addr} adds the expression/address to such a list.

Searching in memory

find [/size-char] [/max-count] start-address, {end-address|+length}, expr1 [, expr2 ...] where size-char is one of b,h,w,g for 8,16,32,64 bit values respectively, and if not specified the size is taken from the type of the expression in the current language; in the case of C-like languages a search for an untyped 0x42 will search for "(int) 0x42" which is typically four bytes, and a search for a string "hello" will include the trailing '\0'. The null terminator can be removed from searching by using casts, e.g.: char[5]"hello".

The address of the last match is stored as the value of \$_. Convenience variable \$numfound is set to the number of matches.

search-pattern, alias grep, allows you to search for a specific pattern at runtime in all the segments of your process memory layout.

pattern... creates or searches a De Bruijn cyclic pattern to facilitate determining offsets in memory; the algorithm is the same as the one in *pwntools*, and can therefore be used in conjunction.

scan haystack needle searches for addresses that are located in memory mapping haystack that belonging to another, needle; its arguments are grepped against the processes memory mappings (just like vmmap to determine the memory ranges to search).

Resuming execution

c[ontinue] [ignore-count] resumes program execution; the optional argument ignore-count allows you to specify a further number of times to ignore a breakpoint at this location.

To resume execution at a different place, use <code>return [expr]</code> to go back to the calling function; or <code>j[ump]</code> to go to an arbitrary location. Note that <code>return</code> does not resume execution: it leaves the program stopped in the state that would exist if the function had just returned. In contrast, <code>fin[ish]</code> continues running until just after function in the selected stack frame returns. <code>u[ntil]</code>, without arguments, continues running until a source line past the current line is reached. It is like <code>next</code>, except that when <code>until</code> encounters a jump, it automatically continues execution until the program counter is greater than the address of the jump. <code>u[ntil] location</code> continue running until either the specified <code>location</code> is reached, or the current stack frame returns.

Stepping

s[tep] [count] continue running your program until control reaches a
different source line [count times]. n[ext] [count] continues to the
next source line in the current stack frame. stepi/si count and
nexti/ni count work on machine instructions, instead of source lines.

Emulation

If you have installed *Unicorn* emulation engine and its Python bindings, unicorn-emulate / emu replicates the current memory mapping, and by default (i.e. without any additional argument), it will emulate the execution of the instruction about to be executed (i.e. the one pointed by \$pc) and display which register(s) is(are) tainted by it.

Record, replay and reverse execution

record starts the process record and replay target; record stop stops.

record goto {begin | end | n} goes to {begin, end, instruction number n

record goto {begin|end|n} goes to {begin, end, instruction number i in instruction log}.

rc / reverse-continue count starts executing in reverse; similarly, for reverse-{step[i],next[i]} [count]. reverse-finish returns to a point where current function was called.

set exec-direction {reverse,forward} affects commands step[i],
next[i], continue and finish; note return cannot be used in reverse.

Copyright ©2018-2019 by zxgio; cheat-sheet built on January 14, 2020 This cheat-sheet may be freely distributed under the terms of the GNU General Public License; the latest version can be found at: https://github.com/zxgio/gdb_gef-cheatsheet