

Lesson Description - Installing Alertmanager

Prometheus Alertmanager provides useful functionality for managing alerts triggered by Prometheus metric data. However, before you can use Alertmanager, you need to get it up and running. In this lesson, we will install Alertmanager and configure our Prometheus server to connect to it.

Relevant Documentation

- Alertmanager
- Alertmanager GitHub

Lesson Reference

Install and Configure Alertmanager and amtool

Log in to your Prometheus server.

Create a user and group for Alertmanager:

sudo useradd -M -r -s /bin/false alertmanager

Download and install the Alertmanager binaries, move the files into the appropriate locations, and set ownership:

wget https://github.com/prometheus/alertmanager/releases/download/ v0.20.0/alertmanager-0.20.0.linux-amd64.tar.gz

tar xvfz alertmanager-0.20.0.linux-amd64.tar.gz

sudo cp alertmanager-0.20.0.linux-amd64/{alertmanager,amtool} /usr/
local/bin/

```
sudo chown alertmanager:alertmanager /usr/local/bin/
{alertmanager,amtool}

sudo mkdir -p /etc/alertmanager

sudo cp alertmanager-0.20.0.linux-amd64/alertmanager.yml /etc/
alertmanager

sudo chown -R alertmanager:alertmanager /etc/alertmanager
```

Create a data directory for Alertmanager:

```
sudo mkdir -p /var/lib/alertmanager

sudo chown alertmanager:alertmanager /var/lib/alertmanager
```

Create a configuration file for amtool:

```
sudo mkdir —p /etc/amtool

sudo vi /etc/amtool/config.yml
```

Enter the following content in the amtool config file:

```
alertmanager.url: http://localhost:9093
```

Create a systemd unit file for Alertmanager:

```
sudo vi /etc/systemd/system/alertmanager.service

[Unit]
Description=Prometheus Alertmanager
```

```
Wants=network-online.target

After=network-online.target

[Service]
User=alertmanager
Group=alertmanager
Type=simple
ExecStart=/usr/local/bin/alertmanager \
    --config.file /etc/alertmanager/alertmanager.yml \
    --storage.path /var/lib/alertmanager/

[Install]
WantedBy=multi-user.target
```

Start and enable the alertmanager service:

```
sudo systemctl enable alertmanager

sudo systemctl start alertmanager
```

Verify the service is running and you can reach it:

```
sudo systemctl status alertmanager

curl localhost:9093
```

You can also access Alertmanager in a web browser at http:// <PROMETHEUS_SERVER_PUBLIC_IP>:9093.

Verify amtool is able to connect to Alertmanager and retrieve the current configuration:

amtool config show

Configure Prometheus to Connect to Alertmanager

Edit the Prometheus config:

sudo vi /etc/prometheus.yml

Under alerting, add your Alertmanager as a target:

```
alerting:
   alertmanagers:
   - static_configs:
   - targets: ["localhost:9093"]
```

Restart Prometheus to reload the configuration:

```
sudo systemctl restart prometheus
```

Verify Prometheus is able to reach the Alertmanager. Access Prometheus in a web browser at http://<PROMETHEUS_SERVER_PUBLIC_IP>:9090.

Click Status > Runtime & Build Information.

Verify your Alertmanager instance appears under the Alertmanagers section.