
## **Chapter 8: Main Memory**





#### **Background**


- Program must be brought (from disk) into memory and placed within a process for it to be run
- Main memory and registers are only storage that CPU can access directly
- Memory unit only sees a stream of addresses + read requests, or address + data and write requests
- Register access in one CPU clock (or less)
- Main memory can take many cycles, causing a stall
- Cache sits between main memory and CPU registers
- Protection of memory required to ensure correct operation






#### **Base and Limit Registers**


- A pair of base and limit registers define the logical address space
- CPU must check every memory access generated in user mode to be sure it is between base and limit for that user







#### **Hardware Address Protection**







#### **Address Binding**

- Programs on disk, ready to be brought into memory to execute form an input queue
  - Without support, must be loaded into address 0000
- Inconvenient to have first user process physical address always at 0000
  - How can it not be?
- Further, addresses represented in different ways at different stages of a program's life
  - Source code addresses usually symbolic
  - Compiled code addresses bind to relocatable addresses
    - i.e. "14 bytes from beginning of this module"
  - Linker or loader will bind relocatable addresses to absolute addresses
    - i.e. 74014
  - Each binding maps one address space to another






#### Compiler, Linker, Loader

- A compiler reads, analyses and translates code into either an object file or a list of error messages.
- A linker combines one or more object files and possible some library code into either some executable, some library or a list of error messages.
- A loader reads the executable code into memory, does some address translation and tries to run the program resulting in a running program or an error message (or both).






#### **Binding of Instructions and Data to Memory**

- Address binding of instructions and data to memory addresses can happen at three different stages
  - Compile time: If memory location known a priori, absolute code can be generated; must recompile code if starting location changes
  - Load time: Must generate relocatable code if memory location is not known at compile time
  - Execution time: Binding delayed until run time if the process can be moved during its execution from one memory segment to another
    - Need hardware support for address maps (e.g., base and limit registers)





#### **Multistep Processing of a User Program**



Compiler converts source code to Assembly Code. You now have a object file.

Linker links the compiled code with libraries and load it into memory.

Running process has base address.





### Logical vs. Physical Address Space

- The concept of a logical address space that is bound to a separate physical address space is central to proper memory management
  - Logical address generated by the CPU; also referred to as virtual address
  - Physical address address seen by the memory unit
- Logical and physical addresses are the same in compile-time and load-time address-binding schemes; logical (virtual) and physical addresses differ in execution-time address-binding scheme
- Logical address space is the set of all logical addresses generated by a program
- Physical address space is the set of all physical addresses generated by a program





#### **Memory-Management Unit (MMU)**


- Hardware device that at run time maps virtual to physical address
- Many methods possible, covered in the rest of this chapter
- To start, consider simple scheme where the value in the relocation register is added to every address generated by a user process at the time it is sent to memory
  - Base register now called relocation register
  - MS-DOS on Intel 80x86 used 4 relocation registers
- The user program deals with *logical* addresses; it never sees the *real* physical addresses
  - Execution-time binding occurs when reference is made to location in memory
  - Logical address bound to physical addresses





#### Dynamic relocation using a relocation register

- Routine is not loaded until it is called
- Better memory-space utilization; unused routine is never loaded
- All routines kept on disk in relocatable load format
- Useful when large amounts of code are needed to handle infrequently occurring cases
- No special support from the operating system is required
  - Implemented through program design
  - OS can help by providing libraries to implement dynamic loading







#### **Dynamic Linking**

- Static linking system libraries and program code combined by the loader into the binary program image
- Dynamic linking –linking postponed until execution time
- Small piece of code, stub, used to locate the appropriate memory-resident library routine
- Stub replaces itself with the address of the routine, and executes the routine
- Operating system checks if routine is in processes' memory address
  - If not in address space, add to address space
- Dynamic linking is particularly useful for libraries
- System also known as shared libraries
- Consider applicability to patching system libraries
  - Versioning may be needed





#### **Swapping**

- A process can be swapped temporarily out of memory to a backing store, and then brought back into memory for continued execution
  - Total physical memory space of processes can exceed physical memory
- Backing store fast disk large enough to accommodate copies of all memory images for all users; must provide direct access to these memory images
- Roll out, roll in swapping variant used for priority-based scheduling algorithms; lower-priority process is swapped out so higher-priority process can be loaded and executed
- Major part of swap time is transfer time; total transfer time is directly proportional to the amount of memory swapped
- System maintains a ready queue of ready-to-run processes which have memory images on disk






#### **Swapping (Cont.)**

- Does the swapped out process need to swap back in to same physical addresses?
- Depends on address binding method
  - Plus consider pending I/O to / from process memory space
- Modified versions of swapping are found on many systems (i.e., UNIX, Linux, and Windows)
  - Swapping normally disabled
  - Started if more than threshold amount of memory allocated
  - Disabled again once memory demand reduced below threshold





#### **Schematic View of Swapping**



main memory





#### **Contiguous Allocation**

- Main memory must support both OS and user processes
- Limited resource, must allocate efficiently
- Contiguous allocation is one early method
- Main memory usually into two partitions:
  - Resident operating system, usually held in low memory with interrupt vector
  - User processes then held in high memory
  - Each process contained in single contiguous section of memory






#### **Contiguous Allocation (Cont.)**

- Relocation registers used to protect user processes from each other, and from changing operating-system code and data
  - Base register contains value of smallest physical address
  - Limit register contains range of logical addresses each logical address must be less than the limit register
  - MMU maps logical address dynamically






#### **Hardware Support for Relocation and Limit Registers**









# Multi programming with fixed tasks(MFT)


- fixed-partition allocation
  - Degree of multiprogramming limited by number of partitions
  - Variable-partition sizes for efficiency (sized to a given process' needs)
  - Hole block of available memory; holes of various size are scattered throughout memory
  - When a process arrives, it is allocated memory from a hole large enough to accommodate it
  - Process exiting frees its partition
  - Operating system maintains information about:
     a) allocated partitions
     b) free partitions (hole)






## Multi programming with variable number of tasks

- Multiple-partition allocation
  - As jobs come, the partitions are dynamically created as per need.
  - Process exiting frees its partition, adjacent free partitions combined
  - External fragmentation might still occur.
  - If total available space is enough for a job then compaction is done.





#### **Dynamic Storage-Allocation Problem**

How to satisfy a request of size *n* from a list of free holes?

- First-fit: Allocate the *first* hole that is big enough
- Best-fit: Allocate the smallest hole that is big enough; must search entire list, unless ordered by size
  - Produces the smallest leftover hole
- Worst-fit: Allocate the *largest* hole; must also search entire list
  - Produces the largest leftover hole

First-fit and best-fit better than worst-fit in terms of speed and storage utilization





#### **Fragmentation**

- External Fragmentation total memory space exists to satisfy a request, but it is not contiguous
- Internal Fragmentation allocated memory may be slightly larger than requested memory; this size difference is memory internal to a partition, but not being used
- First fit analysis reveals that given N blocks allocated, 0.5 N blocks lost to fragmentation





#### Fragmentation (Cont.)

- Reduce external fragmentation by compaction
  - Shuffle memory contents to place all free memory together in one large block
  - compaction is possible only if relocation is dynamic, and is done at execution time
  - I/O problem
    - Latch job in memory while it is involved in I/O
    - Do I/O only into OS buffers
- Now consider that backing store has same fragmentation problems





#### **Segmentation**

- Memory-management scheme that supports user view of memory
- A program is a collection of segments
  - A segment is a logical unit such as:

```
main program
```

procedure

function

method

object

local variables, global variables


common block

stack

symbol table


arrays








#### **Logical View of Segmentation**





physical memory space





#### **Segmentation Architecture**

- Logical address consists of a two tuple:
  - <segment-number, offset>,
- Segment table maps two-dimensional physical addresses; each table entry has:
  - base contains the starting physical address where the segments reside in memory
  - limit specifies the length of the segment
- Segment-table base register (STBR) points to the segment table's location in memory
- Segment-table length register (STLR) indicates number of segments used by a program;
  - segment number s is legal if s < STLR






### **Segmentation Architecture (Cont.)**

- Protection
  - With each entry in segment table associate:
    - validation bit =  $0 \Rightarrow$  illegal segment
    - read/write/execute privileges
- Protection bits associated with segments; code sharing occurs at segment level
- Since segments vary in length, memory allocation is a dynamic storage-allocation problem
- A segmentation example is shown in the following diagram






#### **Segmentation Hardware**








#### **Segmentation Drawback**

- Alows non-contagious memory but Suffers from external fragmentation
- Hence need for Compaction
- Needs to fit memory chunks of varying sizes onto the backing store where backing store has to now do compaction too which is very slow.

Alternative: Paging

 Alows non-contagious memory but has no external fragmentation and hence no need for Compaction





#### **Paging**

- Physical address space of a process can be noncontiguous; process is allocated physical memory whenever the latter is available
  - Avoids external fragmentation
  - Avoids problem of varying sized memory chunks
- Divide physical memory into fixed-sized blocks called frames
  - Size is power of 2, between 512 bytes and 16 Mbytes
- Divide logical memory into blocks of same size called pages
- Keep track of all free frames
- To run a program of size N pages, need to find N free frames and load program
- Set up a page table to translate logical to physical addresses
- Backing store likewise split into pages
- Still have Internal fragmentation





#### **Logical Space: Paging**

If size of logical address space is 2<sup>m</sup> bytes and page size is 2<sup>n</sup> bytes then,


Address generated by CPU is divided into:

- Page number (p) used as an index into a page table which contains base address of each page in physical memory
- Page offset (d) combined with base address to define the physical memory address that is sent to the memory unit

page number page offset


p d

For given logical address space z''' and page size 2<sup>n</sup>
m -n n







### **Paging Hardware**










#### Paging Model of Logical and Physical Memory















#### **Paging Example**



0	5	
1	6	
2	1	
3	2	




N=2(page/frame size) and m=4(logical mem size) 32-byte memory and 4-byte pages



#### Paging (Cont.)

- Calculating internal fragmentation
  - Page size = 2,048 bytes
  - Process size = 72,766 bytes
  - 35 pages + 1,086 bytes
  - Internal fragmentation of 2,048 1,086 = 962 bytes
  - Worst case fragmentation = 1 frame 1 byte
  - On average fragmentation = 1 / 2 frame size
  - So small frame sizes desirable?
  - But each page table entry takes memory to track
  - Page sizes growing over time
    - Solaris supports two page sizes 8 KB and 4 MB
- Process view and physical memory now very different
- By implementation process can only access its own memory







#### Paging (Cont.)

- No external fragmentation
- Internal fragmentation present





#### **Free Frames**



Before allocation

After allocation





#### Implementation of Page Table

- Page table is kept in main memory
- Page-table base register (PTBR) points to the page table
- Page-table length register (PTLR) indicates size of the page table
- In this scheme every data/instruction access requires two memory accesses
  - One for the page table and one for the data / instruction
- The two memory access problem can be solved by the use of a special fast-lookup hardware cache called associative memory or translation look-aside buffers (TLBs)





#### **Shared Pages**

#### Shared code

- One copy of read-only (reentrant) code shared among processes (i.e., text editors, compilers, window systems)
- Similar to multiple threads sharing the same process space
- Also useful for interprocess communication if sharing of read-write pages is allowed


#### Private code and data


- Each process keeps a separate copy of the code and data
- The pages for the private code and data can appear anywhere in the logical address space






#### **Shared Pages Example**







# Disadvantage of paging and segmentation

Paging :No external fragmentation but internal fragmentation present

Disadv: causes a loss in the logical structure of the job as data broken up

Lengthy page table search

 Segmetation: Every partition is modular making maintenance and debugging easier.

No internal fragmentation

Disadv: -Requires variable sized chunks to fit

- -Limited option to swap to disk since a swap now requires swapping a whole segment out. Paging provides greater flexibility with swaping.
- -No internal fragmentation but external fragmentation present that can be solved throught compaction.

## Paged Segmented memory management

- Map a logical segment onto multiple page frames by paging the segments
- Segment table contains not base address of segment but base adress of segments page table. Segment offset refers to page number and an offset on the page.
- Combines the ease of sharing and shorter segment tables from segments with efficient memory utilization we get from pages






- A virtual address becomes a segment number, a page within that segment, and an offset within the page.
- The segment number indexes into the segment table which yields the base address of the page table for that segment.
- Check the remainder of the address (page number and offset) against the limit of the segment.
- Use the page number to index the page table. The entry is the frame. (The rest of this is just like paging.)
- Add the frame and the offset to get the physical address



### Addresses in a Segmented Paging System





CS377: Operating Systems

Lecture 16, page 8

## Adv and Disadv of paged segmentation

- easy memory allocation, any frame can be used
- sharing at either the page or segment level

increased internal fragmentation over paging

two lookups per memory reference





■ 32 bit, byte addressed machine means that there are 2^32 possible addresses. So the array of 2^32 addresses can be of type byte or bit or word(12 bits). Most modern computers are byte addressed. Hence we have 2^32 bytes = 4GB

