## Promise and Future: Returning a Notification

This lesson teaches us how to return a notification while using std::promise and future in C++.

If we use promises and futures to synchronize threads, they have a lot in common with condition variables. Most of the time, promises and futures are the better choices. Before we present an example, here is the big picture.

Criteria	Condition Variables	Tasks
Multiple synchronizations	Yes	No
Critical section	Yes	No
Error handling in receiver	No	Yes
Spurious wakeup	Yes	No
Lost wakeup	Yes	No

The advantage of using a condition variable over a promise and future is that we can use condition variables to synchronize threads multiple times. In contrast to that, a promise can send its notification only once, so we have to use more promise and future pairs to get the functionality of a condition variable. If we use the condition variable for only one synchronization, the condition variable is a lot more difficult to use in the right way. A promise and

future pair needs no shared variable and, therefore, it doesn't have a lock, and

isn't prone to spurious or lost wakeups. In addition to that, tasks can handle exceptions. There are lots of reasons to prefer tasks to condition variables.

Remember how difficult it was to use condition variables? If not, here are the key parts required to synchronize two threads.

```
void waitingForWork(){
   std::cout << "Worker: Waiting for work." << std::endl;

   std::unique_lock<std::mutex> lck(mutex_);
   condVar.wait(lck, []{ return dataReady; });
   doTheWork();
   std::cout << "Work done." << std::endl;
}

void setDataReady(){
   std::lock_guard<std::mutex> lck(mutex_);
   dataReady=true;
   std::cout << "Sender: Data is ready." << std::endl;
   condVar.notify_one();
}</pre>
```

The function setDataReady performs the notification part of the
synchronization - with the function waitingForWork as the waiting part of the
synchronization.

Here is the same workflow with tasks.

```
// promiseFutureSynchronise.cpp
#include <future>
#include <iostream>
#include <utility>

void doTheWork(){
   std::cout << "Processing shared data." << std::endl;
}

void waitingForWork(std::future<void>&& fut){
   std::cout << "Worker: Waiting for work." << std::endl;
   fut.wait();
   doTheWork();
   std::cout << "Work done." << std::endl;
}

void setDataReady(std::promise<void>&& prom){
```

```
std::cout << "Sender: Data is ready." << std::endl;
prom.set_value();

}
int main(){
    std::cout << std::endl;
    std::promise<void> sendReady;
    auto fut = sendReady.get_future();

    std::thread t1(waitingForWork, std::move(fut));
    std::thread t2(setDataReady, std::move(sendReady));

t1.join();
t2.join();
std::cout << std::endl;
}</pre>
```







[]

That was quite easy.

Thanks to sendReady (line 32) we get a future fut (line 33). The promise communicates using its return value void (std::promise<void> sendReady) that it is only capable of sending notifications. Both communication endpoints are moved into threads t1 and t2 (lines 35 and 36). The future waits using the call fut.wait() (line 15) for the notification of the promise:

prom.set value() (line 24).

In the next lesson, we'll discuss std::shared\_future which is used in C++ for concurrency.