Mutex Types and Locking Methods

This lesson discusses different types of mutexes and their locking methods

WE'LL COVER THE FOLLOWING

- `std:shared_timed_mutex`
- Mutex `try_lock` methods

C++ has five different mutexes that can lock recursively (i.e., multiple layers of locking), tentative with and without time constraints.

Method	mutex	recursive_mutex	timed_mutex	recursive_timed_mutex	shared_timed_mutex
`m.lock`	yes	yes	yes	yes	yes
`m.unlock`	yes	yes	yes	yes	yes
`m.try_lock`	yes	yes	yes	yes	yes
`m.try_lock_for`	no	no	yes	yes	yes
`m.try_lock_until`	no	no	yes	yes	yes
`m.try_lock_shared`	yes	no	no	no	yes

`m.try_lock_shared_for`	no	no	no	no	yes
`m.try_lock_shared_until`	no	no	no	no	yes

`std:shared_timed_mutex`

With C++14 we have an `std::shared_timed_mutex` that is the base for reader-writer locks. It solves the infamous reader-writer problem.

The `std::shared_timed_mutex` enables you to implement reader-writer locks which means that you can use it for exclusive or shared locking. You will get an exclusive lock if you put the `std::shared_timed_mutex` into a `std::lock_guard`; you will get a shared lock if you put it into an `std::unique_lock`.

> **i `std::shared_mutex` with C++17**
>
> With C++17 we get a new mutex: `std::shared_mutex`. `std::shared_mutex` is similar to `std::shared_timed_mutex`. Like the `std::shared_timed_mutex`, you can use it for exclusive or shared locking, but you can not specify a time point or a time duration.

Mutex `try_lock` methods

The `m.try_lock_for(relTime)` (`m.try_lock_shared_for(relTime)`) method needs a relative time duration; the `m.try_lock_until(absTime)` (`m.try_lock_shared_until(absTime)`) method needs an absolute time point.

`m.try_lock` (`m.try_lock_shared`) tries to lock the mutex and returns immediately. On success, it returns true; otherwise, it's false. In contrast, the methods `try_lock_for` (`try_lock_shared_for`) and `try_lock_until` (`try_lock_shared_until`) try to lock until the specified timeout occurs or the lock is acquired, whichever comes first. You should use a steady clock for your time constraint. A steady clock cannot be adjusted.

Tip: You should not use mutexes directly; you should put mutexes into locks.