


Debian server Configurações de Redes

Configuração da Máquina Virtual

- As configurações dos cenários precisaremos utilizar 2 interfaces de rede na VM.
 - 1 interface no modo NAT (acesso a rede externa, Internet)
 - 2 interface no modo rede interna (acesso a rede interna, Local)



- Configuração na máquina Virtual.
- 1 rede NAT
- 2 Rede Interna




NetworkManager

 O NetworkManager é um daemon responsável por verificar as conexões de rede disponíveis (incluindo redes Wi-fi) para seu computador e configurá-las automaticamente sem a necessidade de

editar arquivos de configuração.

 Ele é uma excelente opção se você está sempre mudando de redes que tenha configurações diferentes.



Parando o NetworkManager

- Comando para interromper o daemon NetworkManager:
- Parando o serviço
- #systemctl stop NetworkManager.service
- Desabilitando o serviço, não irá startar com o Debian
- #systemctl disable NetworkManager.service
- Verificando o estado do serviço
- #systemctl status NetworkManager.service



Configuração de Rede no Debian Server

root@debian:~# ip a

 Para verificar a interfaces existentes e suas configurações, usamos o comando "ip a" ou "ip addr show".

```
#ip a
```

A imagem me retornou 3 interface de redes:

nome

IP/Mascara

```
lo loopback
enp0s3
enp0s8
```

```
1: lo: <LOOPBACK, UP, LOWER UP> mtu 65536 gdisc noqueue state UNKNOWN group defau
        lt glen 1000
            link/loopback 00:00:00:00:00:00 brd 00:00:00:00:00:00
            inet 127.0.0.1/8 scope host lo
               valid lft forever preferred lft forever
            inet6 ::1/128 scope host
               valid lft forever preferred lft forever
        2: enp0s3: <NO-CARRIER, BROADCAST, MULTICAST, UP> mtu 1500 gdisc pfifo fast state
        DOWN group default glen 1000
            link/ether 08:00:27:1d:34:22 brd ff:ff:ff:ff:ff
      →3: enp0s8: <BROADCAST,MULTICAST,UP,LOWER UP> mtu 1500 qdisc pfifo fast state UP
         group default glen 1000
MAC link/ether 08:00:27:e2:06:ba brd ff:ff:ff:ff:ff
            inet 192.168.0.3/24 brd 192.168.0.255 scope global noprefixroute enp0s8
               valid lft forever preferred lft forever
            inet6 fe80::a00:27ff:fee2:6ba/64 scope link noprefixroute
               valid lft forever preferred lft forever
         root@debian:~#
```



Configurando as interface de redes

 Para configurar as interfaces de redes é necessário editar o arquivo interfaces, que fica localizado dentro do diretório etc/network.

```
# This file describes the network interfaces available on your system
# and how to activate them. For more information, see interfaces(5).
source /etc/network/interfaces.d/*
# The loopback network interface
auto lo
iface lo inet loopback
auto enp0s3
iface enp0s3 inet dhcp
auto enp0s8
iface enp0s8 inet static
address 192.168.0.1
netmask 255.255.255.0
dns-nameserver 192.168.0.1
dns-nameserver 8.8.8.8
```

- Editando o arquivo com o editor VIM.
- # vim /etc/network/interfaces



Reiniciando as interfaces de Redes

- Comando para "ligar" as interfaces:
- #ifup enp0s3
- #ifup enp0s8
- Ou
- #systemctl restart networking

```
2: enp0s3: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc pfifo_fast state UP
group default qlen 1000
    link/ether 08:00:27:15:22:7e brd ff:ff:ff:ff:ff
    inet 10.0.2.15/24 brd 10.0.2.255 scope global dynamic enp0s3
        valid_lft 85194sec preferred_lft 85194sec
3: enp0s8: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc pfifo_fast state UP
group default qlen 1000
    link/ether 08:00:27:ac:3d:95 brd ff:ff:ff:ff:ff
    inet 192.168.0.1/24 brd 192.168.0.255 scope global enp0s8
    valid lft forever preferred lft forever
```