# CS420: Operating Systems Main Memory

James Moscola Department of Engineering & Computer Science York College of Pennsylvania




#### Background

- Program must be brought (from disk) into memory and placed within a process for it to be run
- Main memory and registers are only storage CPU can access directly
  - Register access takes one CPU clock cycle
  - Main memory access can take many CPU clock cycles
  - Cache sits between main memory and CPU registers
- Memory unit only sees a stream of addresses, doesn't know if addresses contain instructions or data
- Protection of memory required to ensure correct operation


### Base and Limit Registers

 A pair of base and limit registers define the logical address space for each process



#### Hardware Address Protection

- Base and limit registers provide memory protection
- Prevent a process from accessing memory outside of its own memory space
- Only the operating system can change the contents of the base and limit registers (must be done in kernel mode)




#### Address Binding

- Not very convenient to have first user process physical address always at memory address 0x0000 (and subsequent processes following that)
- Addresses are represented differently at different stages of a program's life
  - In source code addresses are usually symbolic (e.g. variables, function names)
  - In compiled code addresses bind to relocatable addresses (a relative address)
    - i.e. "8 bytes from beginning of this program module"
  - Linker or loader will bind relocatable addresses to absolute addresses when program is executed
    - i.e. address = 0x74000 + 0x00008 = 0x74008
      - program module starts at 0x74000
      - the 8th byte of the program is at 0x74008

# Binding of Program Instructions and Data to Memory

- Address binding of program instructions and data to memory addresses can happen at three different stages
  - Compile time: If memory location known a priori, absolute code can be generated; must recompile code if starting location changes
  - Load time: Must generate relocatable code if memory location is not known at compile time
  - Execution time: Binding delayed until run time if the process can be moved during its execution from one memory segment to another
    - Need hardware support for address maps (e.g., base and limit registers)




#### Logical vs. Physical Address Space

- The concept of a logical address space that is bound to a separate physical address space is central to proper memory management
  - Logical address generated by the CPU; also referred to as virtual address
  - Physical address address seen by the memory unit (refers to physical memory in the machine)
- Logical and physical addresses are:
  - the same in compile-time and load-time address-binding schemes
  - differ in execution-time address-binding scheme
- Logical address space is the set of all logical addresses generated by a program
- Physical address space is the set of all physical addresses that correspond to the physical addresses


# Memory-Management Unit (MMU)

- Hardware device that, at run time, maps logical addresses to physical addresses (for execution-time binding)
- Consider simple scheme where the value in a relocation register is added to every address generated by a user process at the time it is sent to memory
  - Base register now called relocation register
- The user program deals with logical addresses; it never sees the real physical addresses
  - Execution-time binding occurs when reference is made to location in memory
  - Logical address bound to physical addresses by MMU



#### Hardware Support for Relocation and Limit Registers

- Relocation registers used to protect user processes from each other, and from changing operating-system code and data
  - Relocation register contains value of smallest physical address
  - Limit register contains range of logical addresses each logical address must be less than the limit register
  - MMU maps logical address dynamically



#### Dynamic Loading

- To make better utilization of available memory dynamic loading can be used
  - A software routine is not loaded into memory until it is called
  - Unused routines are never loaded
- All routines kept on disk in relocatable load format
- Useful when large amounts of code are needed to handle infrequently occurring cases (e.g. error routines)
- No special support from the operating system is required
  - Implemented through program design
  - OS can help by providing libraries to implement dynamic loading


#### Dynamic Linking

- To reduce the size of programs, and thus the disk space required for storage and the memory required for execution, use dynamic linking
  - Static linking system libraries and program code combined by the loader into the binary program image (i.e. large executable files)
  - Dynamic linking linking postponed until execution time; smaller executable files that make use of dynamically linked libraries (e.g. .dll files)
- A stub is included in the binary image of a program for each reference to a library routine
  - Used to locate the appropriate library routine and load it into memory (if it hasn't already been loaded)
  - Stub replaces itself with the address of the routine, and executes the routine
  - Subsequent calls to the linked library do not incur a loading penalty
- Dynamic linking is particularly useful for libraries that are shared amongst many processes

# Swapping

- A process can be swapped temporarily out of memory to a backing store (a disk), and then brought back into memory to continue execution
  - Total physical memory space of processes can exceed physical memory
- Major part of swap time is transfer time to and from backing store; total transfer time is directly proportional to the amount of memory swapped
- System maintains a queue of ready-to-run processes which have memory images on disk
- If using execution-time binding, the process need not be swapped back into the same physical address from whence it came
- Versions of swapping are found on many systems (i.e., UNIX, Linux, and Windows)
  - Swapping is normally disabled
  - Started if memory allocation exceeds some threshold
  - Disabled again once memory demand reduced below threshold

# Schematic View of Swapping



# Context Switch Time Including Swapping

 If next processes to be put on CPU is not in memory, need to swap out a process and swap in target process

 Context switch time can be very high when swapping since process needs to be copied from disk storage into system memory


- 500 MB process swapping to hard disk with transfer rate of 500 MB/sec
  - Plus disk latency of 8 ms
  - Swap out time of 1008 ms
  - Plus swap in of same sized process
  - Total context switch swapping component time of 2016ms (> 2 seconds)

#### Memory Allocation: Contiguous Allocation

- Main memory usually divided into two partitions:
  - Resident operating system, usually held in low memory
  - User processes held in high memory
- Need to allocate memory efficiently, one approach is contiguous allocation
  - The logical address space for each process is contained in single contiguous section of physical memory
- It is desirable to allow these contiguous memory segments to move around in physical memory
  - Requires a single base/relocation register and a single limit register per process

# Memory Allocation: Partitioning

- When allocating memory, the physical memory is divided into multiple, variable-sized, partitions
  - Degree of multiprogramming is limited by number of partitions (how many process in memory)
  - A hole is a block of available memory; holes of various size are scattered throughout memory
  - When a process arrives, it is allocated memory from a hole large enough to accommodate it
  - When a process exits, it frees its partition, adjacent free partitions are combined
  - Operating system maintains information about:
     a) allocated partitions
     b) free partitions (holes)



#### Dynamic Storage-Allocation Problem

- How should a memory request of size n be satisfied from a list of free holes?
- Several approaches:
  - First-fit: Scan list and allocate the first hole that is big enough
  - Best-fit: Scan list and allocate the smallest hole that is big enough; must search entire list, unless ordered by size
    - Produces the smallest leftover hole
  - Worst-fit: Scan list and allocate the largest hole; must also search entire list
    - Produces the largest leftover hole
- First-fit and best-fit better than worst-fit in terms of speed and storage utilization
- First-fit is generally the fastest

#### Fragmentation

- Repeatedly allocating and deallocating memory can lead to fragmentation of available memory (fragmentation of holes)
  - External Fragmentation memory space exists to satisfy a request, but it is not contiguous; small holes are scattered throughout the physical address space
- Analysis of first fit allocation reveals that given N blocks allocated, another
   0.5 N blocks will be lost to fragmentation
  - 1/3 of memory may be unusable -> 50-percent rule
- Reduce external fragmentation by compaction
  - Shuffle memory contents to place all free memory together in one large block
  - Compaction is possible only if relocation is dynamic, and is done at execution time

# Fragmentation (Cont.)

- In some instances, may allocate a larger memory block than required by process
  - Extra space in memory block is unused by process
  - Internal Fragmentation allocated memory may be slightly larger than requested memory; this size difference is memory internal to a partition, but not being used