

UNIVERSITÀ DEGLI STUDI DI PADOVA

Implementing Deep Networks in Keras

Stefano Ghidoni







- Keras: what is it?
- Getting started in 30s
- Building blocks: models and layers
- Network training & related tools
- Convolutional Neural Networks (CNNs) in Keras



Keras: The Python Deep Learning library



You have just found Keras.



Keras: The Python Deep Learning library



You have just found Keras.

Keras is a high-level neural networks API, written in Python and capable of running on top of TensorFlow, CNTK, or Theano. It was developed with a focus on enabling fast experimentation. *Being able to go from idea to result with the least possible delay is key to doing good research.*

Use Keras if you need a deep learning library that:

- Allows for easy and fast prototyping (through user friendliness, modularity, and extensibility).
- Supports both convolutional networks and recurrent networks, as well as combinations of the two.
- Runs seamlessly on CPU and GPU.


Read the documentation at Keras.io.

Keras is compatible with: Python 2.7-3.6.

Keras in a nutshell

IAS-LAB

- A simplified interface to TensorFlow
- Backends
 - TensorFlow
 - Theano
 - CNTK
- Supports CPU & GPU



IAS-LAB

- User friendly
 - It is easy to do easy things
 - It is possible to do complex things
- Modularity
 - Modules: neural layers, cost functions, optimizers, activation functions, regularization schemes
- Extendible
 - Easy to add new modules
- Python-based
 - Interactive environment

Getting started

- Instantiate a sequential model
- Stack some layers
- Configure/tune the learning process
- Iterate on the training data
- Evaluate performance
- Generate predictions

IAS-LAB

Instantiate a sequential model

```
from keras.models import Sequential
model = Sequential()
```

IAS-LAB

Stack some layers

```
from keras.layers import Dense
model.add(Dense(units=64, activation='relu', input_dim=100))
model.add(Dense(units=10, activation='softmax'))
```

IAS-LAB

Configure/tune the learning process

IAS-LAB

Iterate on the training data

```
# x_train and y_train are Numpy arrays --just like in the Scikit-Learn API.
model.fit(x_train, y_train, epochs=5, batch_size=32)
```

```
model.train on batch(x batch, y batch)
```

IAS-LAB

Evaluate performance

```
loss_and_metrics = model.evaluate(x_test, y_test, batch_size=128)
```

IAS-LAB

Generate predictions

```
classes = model.predict(x_test, batch_size=128)
```

• The end


IAS-LAB

- A way to organize & handle layers
- Sequential model
 - Linear stack of layers
- Model class API
 - Given an input tensor a and an output tensor b, creates all layers required to compute b from a
- Methods
 - compile (configures the model for training)
 - fit (training on a dataset)
 - evaluate (evaluation at test time)

CNNs

IAS-LAB


Typical CNN



CNN - recall

IAS-LAB

Typical CNN



Source: Mathworks website

IAS-LAB


- Convolutional Neural Network
- Typical layers:
 - Convolutional + ReLU
 - Pooling
 - Fully connected
 - Activations (Softmax)



Layers in Keras

IAS-LAB

- Convolutional layers
 - 1D (typically temporal)
 - 2D (typically spatial)



2D convolution layer (e.g. spatial convolution over images).

This layer creates a convolution kernel that is convolved with the layer input to produce a tensor of outputs. If use_bias is True, a bias vector is created and added to the outputs. Finally, if activation is not None, it is applied to the outputs as well.

When using this layer as the first layer in a model, provide the keyword argument input_shape (tuple of integers, does not include the sample axis), e.g. input_shape=(128, 128, 3) for 128x128 RGB pictures in data format="channels last".

Conv2D arguments

IAS-LAB

Arguments

- filters: Integer, the dimensionality of the output space (i.e. the number of output filters in the convolution).
- **kernel_size**: An integer or tuple/list of 2 integers, specifying the width and height of the 2D convolution window. Can be a single integer to specify the same value for all spatial dimensions.
- **strides**: An integer or tuple/list of 2 integers, specifying the strides of the convolution along the width and height. Can be a single integer to specify the same value for all spatial dimensions. Specifying any stride value != 1 is incompatible with specifying any dilation_rate_value != 1.
- padding: one of "valid" or "same" (case-insensitive). Note that "same" is slightly inconsistent across backends with strides != 1, as described here
- data_format: A string, one of _channels_last (default) or _channels_first . The ordering of the dimensions in the inputs.

 channels_last _corresponds to inputs with shape _(batch, height, width, channels) while _channels_first _
 corresponds to inputs with shape _(batch, channels, height, width) . It defaults to the _image_data_format _value found in your Keras config file at _~/.keras/keras.json . If you never set it, then it will be "channels_last".
- dilation_rate: an integer or tuple/list of 2 integers, specifying the dilation rate to use for dilated convolution. Can be a single integer to specify the same value for all spatial dimensions. Currently, specifying any dilation_rate value != 1 is incompatible with specifying any stride value != 1.
- activation: Activation function to use (see activations). If you don't specify anything, no activation is applied (ie. "linear" activation:
 a(x) = x).
- use_bias: Boolean, whether the layer uses a bias vector.
- kernel_initializer: Initializer for the kernel weights matrix (see initializers).
- bias_initializer: Initializer for the bias vector (see initializers).
- kernel_regularizer: Regularizer function applied to the kernel weights matrix (see regularizer).
- bias_regularizer: Regularizer function applied to the bias vector (see regularizer).
- activity_regularizer: Regularizer function applied to the output of the layer (its "activation"). (see regularizer).
- kernel_constraint: Constraint function applied to the kernel matrix (see constraints).
- bias_constraint: Constraint function applied to the bias vector (see constraints).

Conv2D arguments

IAS-LAB

- The argument list is huge!
- Rely on default values (our best friends)
 - Specify only the desired arguments

Code examples:

Conv2D I/O

IAS-LAB

- Tensors & I/O
 - Tensor: typed multi-dimensional array (From TensorFlow)

Input shape

```
4D tensor with shape: (samples, channels, rows, cols) if data_format='channels_first' or 4D tensor with shape: (samples, rows, cols, channels) if data_format='channels_last'.
```

Output shape


```
4D tensor with shape: (samples, filters, new_rows, new_cols) if data_format='channels_first' or 4D tensor with shape: (samples, new_rows, new_cols, filters) if data_format='channels_last'. rows and cols values might have changed due to padding.
```



Layers in Keras

IAS-LAB

Pooling layers (1D and 2D)



MaxPooling2D

```
keras.layers.MaxPooling2D(pool_size=(2, 2), strides=None, padding='valid', data_format=None)
```

Max pooling operation for spatial data.

Arguments


- **pool_size**: integer or tuple of 2 integers, factors by which to downscale (vertical, horizontal). (2, 2) will halve the input in both spatial dimension. If only one integer is specified, the same window length will be used for both dimensions.
- strides: Integer, tuple of 2 integers, or None. Strides values. If None, it will default to pool_size.
- padding: One of "valid" or "same" (case-insensitive).
- data_format: A string, one of _channels_last (default) or _channels_first . The ordering of the dimensions in the inputs.

 _channels_last _corresponds to inputs with shape _(batch, height, width, channels) while _channels_first _corresponds to inputs with shape _(batch, channels, height, width) . It defaults to the _image_data_format _value found in your Keras config file at _v/.keras/keras.json . If you never set it, then it will be "channels last".

Layers in Keras

IAS-LAB

- Dense layers
 - AKA fully connected



```
keras.layers.Dense(units, activation=None, use_bias=True, kernel_initializer='glorot_uniform',
bias_initializer='zeros', kernel_regularizer=None, bias_regularizer=None, activity_regularizer=None,
kernel constraint=None, bias constraint=None)
```

Just your regular densely-connected NN layer.

Dense implements the operation: output = activation(dot(input, kernel) + bias) where activation is the element-wise activation function passed as the activation argument, kernel is a weights matrix created by the layer, and bias is a bias vector created by the layer (only applicable if use_bias is True).

• **Note**: if the input to the layer has a rank greater than 2, then it is flattened prior to the initial dot product with kernel.



- Activations
 - Standalone layers
 - Embedded in forward layers
- Softmax activation often at the end of the last FC layer

```
from keras.layers import Activation, Dense

model.add(Dense(64))
model.add(Activation('tanh'))

This is equivalent to:

model.add(Dense(64, activation='tanh'))
```

Compiling a model

IAS-LAB

- Compiling a model means configuring the learning process
- A model can be compiled by providing
 - An optimizer
 - A loss function
 - A list of metrics
- Depending on the problem at hand
 - Binary classification
 - Multi-class classification
 - Regression

Compiling a model

IAS-LAB

The compile function – examples

```
# For a multi-class classification problem
model.compile(optimizer='rmsprop',
              loss='categorical crossentropy',
              metrics=['accuracy'])
# For a binary classification problem
model.compile(optimizer='rmsprop',
              loss='binary crossentropy',
              metrics=['accuracy'])
# For a mean squared error regression problem
model.compile(optimizer='rmsprop',
              loss='mse')
# For custom metrics
import keras.backend as K
def mean_pred(y true, y pred):
    return K.mean(y pred)
model.compile(optimizer='rmsprop',
              loss='binary crossentropy',
              metrics=['accuracy', mean pred])
```

Optimizers

IAS-LAB

- Several optimizers are provided
- Example:

```
from keras import optimizers

model = Sequential()
model.add(Dense(64, kernel_initializer='uniform', input_shape=(10,)))
model.add(Activation('softmax'))

sgd = optimizers.SGD(lr=0.01, decay=1e-6, momentum=0.9, nesterov=True)
model.compile(loss='mean_squared_error', optimizer=sgd)
```

You can either instantiate an optimizer before passing it to model.compile(), as in the above example, or you can call it by its name. In the latter case, the default parameters for the optimizer will be used.

```
# pass optimizer by name: default parameters will be used
model.compile(loss='mean_squared_error', optimizer='sgd')
```

SGD (Stochastic Gradient Descent)

IAS-LAB

- SGD is a good starting point
 - Default values for every parameter!

SGD [source]

keras.optimizers.SGD(lr=0.01, momentum=0.0, decay=0.0, nesterov=False)

Stochastic gradient descent optimizer.

Includes support for momentum, learning rate decay, and Nesterov momentum.

Arguments

- Ir: float >= 0. Learning rate.
- momentum: float >= 0. Parameter that accelerates SGD in the relevant direction and dampens oscillations.
- decay: float >= 0. Learning rate decay over each update.
- nesterov: boolean. Whether to apply Nesterov momentum.

- Loss function
 - AKA objective function
 - AKA optimization score function
- Measures the distance between actual and desired output
 - Drives the training process
- Depends on the task / output type
 - Classification vs regression



Loss function

AS-LAB

- Can be selected from a set of predefined functions, or userdefined
- Good starting points
 - Classification: categorical/binary cross entropy
 - Regression: mean square error

Note: when using the <u>categorical_crossentropy</u> loss, your targets should be in categorical format (e.g. if you have 10 classes, the target for each sample should be a 10-dimensional vector that is all-zeros except for a 1 at the index corresponding to the class of the sample). In order to convert *integer targets* into *categorical targets*, you can use the Keras utility <u>to_categorical</u>:

```
from keras.utils.np_utils import to_categorical
categorical_labels = to_categorical(int_labels, num_classes=None)
```

Losses

Usage of loss functions

Available loss functions

mean_squared_error

mean_absolute_error

mean_absolute_percentage_error

mean_squared_logarithmic_error

squared_hinge

hinge

categorical_hinge

logcosh

categorical_crossentropy

sparse_categorical_crossentropy

binary_crossentropy

kullback_leibler_divergence

poisson

cosine_proximity

Metrics

IAS-LAB

 "A metric function is similar to a loss function, except that the results from evaluating a metric are not used when training the model"

Available metrics

binary_accuracy

categorical_accuracy

sparse_categorical_accuracy

top_k_categorical_accuracy

sparse_top_k_categorical_accuracy

Custom metrics

IAS-LAB

- Colab is similar to Jupyter, but:
 - A tool for online programming
 - A remote GPU is available
 - Remote environment (e.g., files you have access to)
 - Hard to tune/install new libs
 - Keras is available!



MNIST classification in Colab

IAS-LAB

- The next slides present the code needed to train a CNN on the MNIST dataset
- Try on your own
- An example is available at:

https://colab.research.google.com/github/Aviat orMoser/keras-mnisttutorial/blob/master/MNIST%20in%20Keras.ipy nb

IAS-LAB

- MNIST database of handwritten digits
 - Training set: 60k examples
 - Test set: 10k examples
- ML's hello world



IAS-LAB

Imports

```
from __future__ import print_function
import keras
from keras.datasets import mnist
from keras.models import Sequential
from keras.layers import Dense, Dropout, Flatten
from keras.layers import Conv2D, MaxPooling2D
from keras import backend as K
```

IAS-LAB

Set training parameters + read dataset + reshape

```
Input shape
batch size = 128
num classes = 10
                                                                     4D tensor with shape: (samples, channels, rows, cols) if data_format='channels_first' or 4D tensor with shape:
                                                                     (samples, rows, cols, channels) if data_format='channels_last'.
epochs = 12
                                                                     Output shape
                                                                     4D tensor with shape: (samples, filters, new rows, new cols) if data_format='channels_first' or 4D tensor
# input image dimensions
                                                                     with shape: (samples, new_rows, new_cols, filters) if data_format='channels_last'. rows and cols values
                                                                     might have changed due to padding.
img rows, img cols = 28, 28
# the data, split between train and test sets
(x train, y_train), (x_test, y_test) = mnist.load_data()
if K.image data format() == 'channels first':
     x_train = x_train.reshape(x_train.shape[0], 1, img_rows, img_cols)
     x test = x test.reshape(x test.shape[0], 1, img rows, img cols)
     input shape = (1, img rows, img cols)
else:
     x train = x train.reshape(x train.shape[0], img rows, img cols, 1)
     x test = x test.reshape(x test.shape[0], img rows, img cols, 1)
     input shape = (img rows, img cols, 1)
```

IAS-LAB

Type and format conversion, normalization

```
x_train = x_train.astype('float32')
x test = x test.astype('float32')
x train /= 255
x test /= 255
print('x_train shape:', x_train.shape)
print(x_train.shape[0], 'train samples')
print(x_test.shape[0], 'test samples')
# convert class vectors to binary class matrices
y_train = keras.utils.to_categorical(y_train, num_classes)
y_test = keras.utils.to_categorical(y_test, num_classes)
```


IAS-LAB

Model building

```
model = Sequential()
model.add(Conv2D(32, kernel size=(3, 3),
                 activation='relu'.
                 input_shape=input_shape))
model.add(Conv2D(64, (3, 3), activation='relu'))
model.add(MaxPooling2D(pool_size=(2, 2)))
model.add(Dropout(0.25))
model.add(Flatten())
model.add(Dense(128, activation='relu'))
model.add(Dropout(0.5))
model.add(Dense(num classes, activation='softmax'))
```

IAS-LAB

Model building



```
model.add(Flatten())
model.add(Dense(128, activation='relu'))
model.add(Dropout(0.5))
model.add(Dense(num_classes, activation='softmax'))
```

IAS-LAB

Compilation, fitting and output

```
model.compile(loss=keras.losses.categorical crossentropy,
              optimizer=keras.optimizers.Adadelta(),
              metrics=['accuracy'])
model.fit(x_train, y_train,
          batch size=batch size,
          epochs=epochs,
          verbose=1,
          validation data=(x test, y test))
score = model.evaluate(x test, y test, verbose=0)
print('Test loss:', score[0])
print('Test accuracy:', score[1])
```

Resources

Resources

IAS-LAB

- Getting started with Keras
 - https://keras.io/getting-started/sequential-model-guide/
 - https://blog.keras.io/keras-as-a-simplified-interface-to-tensorflow-tutorial.html
- Focus on optimization algorithms
 - https://towardsdatascience.com/types-of-optimization-algorithms-used-in-neural-networks-and-ways-to-optimize-gradient-95ae5d39529f
- Metrics
 - https://machinelearningmastery.com/custom-metrics-deep-learning-keraspython/
- Selected MNIST example
 - https://yashk2810.github.io/Applying-Convolutional-Neural-Network-on-the-MNIST-dataset/
 - https://elitedatascience.com/keras-tutorial-deep-learning-in-python
 - https://github.com/keras-team/keras/blob/master/examples/mnist_cnn.py

IAS-LAB

Dropout

 https://machinelearningmastery.com/dropoutregularization-deep-learning-models-keras/

Transfer learning

- https://medium.com/@14prakash/transferlearning-using-keras-d804b2e04ef8
- https://www.learnopencv.com/keras-tutorialtransfer-learning-using-pre-trained-models/
- http://cv-tricks.com/keras/fine-tuning-tensorflow/



UNIVERSITÀ DEGLI STUDI DI PADOVA

Implementing Deep Networks in Keras

Stefano Ghidoni



