These slides are being provided with permission from the copyright for CS2208 use only. The slides must not be reproduced or provided to anyone outside of the class.

All download copies of the slides and/or lecture recordings are for personal use only. Students must destroy these copies within 30 days after receipt of final course evaluations.

Tutorial 01: Number Systems

Computer Science Department

CS2208: Introduction to Computer Organization and Architecture

Fall 2022-2023

Instructor: Mahmoud R. El-Sakka

Office: MC-419

Email: elsakka@csd.uwo.ca

Phone: 519-661-2111 x86996



Number Systems

- In positional notation number systems
 - □ Numbers are *represented* (*encoded*) using digits
 - □ Each digit has a *value* and a *place*
 - □ Each *place* has a *weight*
 - for example, in decimal, we have the *ones place*, *tens place*, *hundreds place*, ...



Number Systems

- A radix or base is
 - □ the number of unique digits, *including zero*, used to represent numbers in a positional numeral system.
- With the use of a *radix point*, the notation can be extended to include *fractions* and *real numbers*.

You need to know how



Number Systems

- Examples of positional numeral systems
 - Decimal is base-10
- \rightarrow {0, 1, 2, 3, 4, 5, 6, 7, 8, and 9}

- Binary is base-2
- Quaternary is base-4 \rightarrow {0, 1, 2, and 3}
- Octal is base-8
- Trinary is base-3
- Quinary is base-5
- Senary is base-6
- ☐ Septenary is base-7
- Nonary is base-9

- \rightarrow {0, and 1}
- \rightarrow {0, 1, 2, 3, 4, 5, 6, and 7}
- Hexadecimal is base-16 \rightarrow {0, 1, 2, 3, 4, 5, 6, 7, 8, 9, A, B, C, D, E and F}
 - \rightarrow {0, 1, and 2}
 - \rightarrow {0, 1, 2, 3, and 4}
 - \rightarrow {0, 1, 2, 3, 4, and 5}
 - \rightarrow {0, 1, 2, 3, 4, 5, and 6}
 - \rightarrow {0, 1, 2, 3, 4, 5, 6, 7, and 8}
- Duodecimal is base-12 \rightarrow {0, 1, 2, 3, 4, 5, 6, 7, 8, 9, A, and B}
- Sexagesimal is base-60 \rightarrow {0, 1, 2, 3, 4, 5, ..., 58 and 59}

 \square If the original number in base b is:

$$(a_{n-1} a_{n-2} \dots a_i \dots a_1 a_0 \cdot a_{-1} a_{-2} \dots a_{-m})_b$$

□ The *decimal* value of this number is defined as

$$N_{10} = (a_{n-1}b^{n-1} + ... + a_{i}b^{i} + ... + a_{1}b^{1} + a_{0}b^{0} + a_{-1}b^{-1} + a_{-2}b^{-2} + ... + a_{-m}b^{-m})_{10}$$

Example 1: Convert 2E8₁₆ to decimal

$$2E8_{16} = 2 \times 16^{2} + E \times 16^{1} + 8 \times 16^{0}$$

$$= 2 \times 256 + 14 \times 16 + 8 \times 1$$

$$= 512 + 224 + 8$$

$$= 744_{10}$$

This question can be asked as follow:

Convert the hexadecimal value 2E8 to *decimal*

Calculators are not allowed during exams. You need to improve your mental math skills.

During exams, calculations will be simplified.

Yet, when you answer the assignment/quiz questions, you may want to use calculators, as simplifying the calculations are not considered in the assignment/quiz.

■ *Example 2*: Convert 361₈ to *decimal*

$$361_8 = 3 \times 8^2 + 6 \times 8^1 + 1 \times 8^0$$
$$= 3 \times 64 + 6 \times 8 + 1 \times 1$$
$$= 192 + 48 + 1$$
$$= 241_{10}$$

This question can be asked as follow:

Convert the octal value 361 to *decimal*

Example 3: Convert 0.361_8 to decimal

$$0.361_8 = 3 \times 8^{-1} + 6 \times 8^{-2} + 1 \times 8^{-3}$$

$$= 3 \times 0.125 + 6 \times 0.015625 + 1 \times 0.001953125$$

$$= 0.375 + 0.09375 + 0.001953125$$

$$= 0.470703125_{10}$$

Another method:

$$0.361_8 = 361_8 / 1000_8$$

$$= (3 \times 8^2 + 6 \times 8^1 + 1 \times 8^0) / (1 \times 8^3)$$

$$= (3 \times 64 + 6 \times 8 + 1 \times 1) / (1 \times 512)$$

$$= (192 + 48 + 1) / (512)$$

$$= 241 / 512$$

$$= 0.470703125_{10}$$

Example 4: 12.112_3 to decimal

$$12.112_{3}$$

$$= 1 \times 3^{1} + 2 \times 3^{0} + 1 \times 3^{-1} + 1 \times 3^{-2} + 2 \times 3^{-3}$$

$$= 1 \times 3 + 2 \times 1 + 1 \times 0.333333 + 1 \times 0.111111 + 2 \times 0.03703$$

$$= 3 + 2 + 0.333333 + 0.111111 + 0.07406 = 5.5185_{10}$$

Another method:

$$12.112_{3} = 12112_{3} / 1000_{3}$$

$$= (1 \times 3^{4} + 2 \times 3^{3} + 1 \times 3^{2} + 1 \times 3^{1} + 2 \times 3^{0}) / (1 \times 3^{3})$$

$$= (81 + 54 + 9 + 3 + 2) / 27$$

$$= 149 / 27 = 5.5185_{10}$$

- Division Method (for integer numbers)
 - □ Initialize the quotient by the value of the *decimal number*
 - □ *Repeat*:
 - Divide the quotient from the previous stage by the new base to get
 - ☐ A new quotient (the whole number)
 - □ A remainder
 - The *remainder* here is *the next <u>least</u> significant digit* in the new number *Until* the new quotient becomes 0.

- *Example 5*: Convert 14₁₀ to binary
 - Binary means the new base is 2
 - □ 14/2 = 7 Remainder: $0 \rightarrow$ This is the <u>least</u> significant binary digit Quotient = $7 \neq 0 \rightarrow$ continue
 - □ 7/2 = 3 Remainder: 1 → This is the <u>2nd least</u> significant binary digit Quotient = $3 \neq 0$ → continue
 - □ 3/2 = 1 Remainder: 1 → This is the 3^{rd} least significant binary digit Quotient = $1 \neq 0$ → continue
 - □ 1/2 = 0 Remainder: 1 → This is the 4^{th} least significant binary digit Quotient = 0 → exit the repeat-until control structure

 $\Box 14_{10} = 1110_2 \bullet \bullet \bullet$

Note that, it is 1110₂
It is NOT 0111₂

Example 6: Convert 2477₁₀ to hexadecimal:


Hexadecimal means the new base is 16

- □ 2477/16 = 154 Remainder: $13 \rightarrow$ This is the <u>least</u> significant Hex digit Quotient = $154 \neq 0 \rightarrow$ continue
- □ 154/16 = 9 Remainder: 10 → This is the 2^{nd} least significant Hex digit Quotient = 9 ≠ 0 → continue
- □ 9/16 = 0 Remainder: 9 → This is the 3^{rd} least significant Hex digit Quotient = 0 → exit the repeat-until control structure

$$\square 2477_{10} = 9AD_{16}$$
Note that, it is $9AD_{16}$
It is NOT DA9₁₆

- Multiplication Method (for fraction numbers)
 - ☐ Initialize the fraction by the value of the *fractional decimal number*
 - □ *Repeat*:
 - Multiply the fraction from the previous stage by the new base to get
 - □ A whole number
 - □ A new *fraction*
 - The *whole number* here is *the next digit to the right after the radix point* in the new number

Until the new fraction becomes 0.



■ *Example 7*: Convert 0.017578125₁₀ to hexadecimal

Hexadecimal means the new base is 16

- □ $0.01757812 \times 16 = 0.28125$ whole number: $0 \rightarrow the next digit to the right after the radix point fraction = <math>0.28125 \neq 0 \rightarrow continue$
- □ $0.28125 \times 16 = 4.5$ whole number: $4 \rightarrow$ the next digit to the right after the radix point fraction = $0.5 \neq 0 \rightarrow$ continue
- □ $0.5 \times 16 = 8.0$ whole number: $8 \rightarrow$ the next digit to the right after the radix point fraction = $0.0 \rightarrow$ exit the repeat-until control structure
- $\square 0.017578125_{10} = 0.048_{16}$

Example 8: Convert 255.017578125₁₀ to hexadecimal:

Hexadecimal means the new base is 16

$$255.017578125_{10} = 255_{10} + 0.017578125_{10}$$

Using the *division method*: $255_{10} \rightarrow FF_{16}$

Using the *multiplication method*: $0.017578125_{10} \rightarrow 0.048_{16}$

$$255.017578125_{10} = FF.048_{16}$$

- **Example 9**: Convert 0.85₁₀ to hexadecimal Hexadecimal means the new base is 16
 - □ $0.85 \times 16 = 13.6$ whole number: $13 \rightarrow the next digit to the right after the radix point fraction = <math>0.6 \neq 0 \rightarrow continue$
 - □ $0.6 \times 16 = 9.6$ whole number: $9 \rightarrow$ the next digit to the right after the radix point fraction = $0.6 \neq 0 \rightarrow$ continue
 - □ $0.6 \times 16 = 9.6$ whole number: $9 \rightarrow$ the next digit to the right after the radix point fraction = $0.6 \neq 0 \rightarrow$ continue

 - $\square 0.85_{10} = 0.D99999...9_{16}$
 - □ Can be approximated in 4 digits after the radix point, for example, as
 - $0.D999_{16}$ (using truncation) or as
 - $0.D99A_{16}$ (using rounding)

Conversion between any two bases, other than decimal

- This task can be done in two steps:
 - □ Convert from the source base to the decimal
 - □ Convert from the decimal to the destination base

Conversion between any two bases, other than decimal

■ Example 10: Convert $2E8_{16}$ to octal $2E8_{16} = 2 \times 16^2 + E \times 16^1 + 8 \times 16^0$ $= 2 \times 256 + 14 \times 16 + 8 \times 1$

 $= 512 + 224 + 8 = 744_{10}$

744/8 = 93 Remainder: 0 → This is the <u>least</u> significant octal digit Quotient = $93 \neq 0$ → continue

93/8 = 11 Remainder: $5 \rightarrow$ This is the <u>2nd least</u> significant octal digit Quotient = $11 \neq 0 \rightarrow$ continue

11/8 = 1 Remainder: $3 \rightarrow$ This is the 3^{rd} least significant octal digit Quotient = $1 \neq 0 \rightarrow$ continue

1/8 = 0 Remainder: $1 \rightarrow$ This is the 4^{th} least significant octal digit Quotient = $11 \neq 0 \rightarrow$ exit the repeat-until control structure

$$2E8_{16} = 744_{10} = 1350_8$$

Conversion between <u>any two bases</u>, <u>other than decimal</u> (Special cases)

- Binary to octal or hexadecimal:
 - □ Binary to octal conversion
 - Group bits in three's, <u>starting from the binary point</u> (<u>pad the last group with 0's, if needed</u>)
 - Convert each of these three-bit group into an octal digit
 - □ Binary to hexadecimal conversion
 - Group bits in four's, <u>starting from the binary point</u> (<u>pad the last group with 0's, if needed</u>)
 - Convert each of these four-bit group into a hexadecimal digit



Example 11: Convert 11001111₂ to octal

11001111₂

- → 011 001 111₂
- \rightarrow 317₈

$$0 = 000$$

$$1 = 001$$

$$2 = 010$$

$$3 = 011$$

$$4 = 100$$

$$5 = 101$$

$$6 = 110$$

$$7 = 111$$

Conversion between <u>any two bases</u>, <u>other than decimal</u> (Special cases)

(Special cases)

Example 12: Convert 1111010101₂ to hexadecimal

1111010101₂

 \rightarrow 0011 1101 0101₂

 \rightarrow 3D5₁₆

0 = 0000	8 = 1000
1 = 0001	9 = 1001
2 = 0010	A = 1010
3 = 0011	B = 1011
4 = 0100	C = 1100
5 = 0101	D = 1101
6 = 0110	E = 1110
7 = 0111	F = 1111

Conversion between <u>any two bases</u>, <u>other than decimal</u> (Special cases)

- Octal or hexadecimal to binary:
 - □ Octal to binary conversion
 - Expanding each octal digit into three bits
 - ☐ Hexadecimal to binary conversion
 - Expanding each hexadecimal digit into four bits



Example 13: Convert 743₈ to binary

743₈

- \rightarrow 111 100 011₂
- $\rightarrow 111100011_2$

```
0 = 000
1 = 001
2 = 010
```

$$4 = 100$$

$$5 = 101$$

$$6 = 110$$

$$7 = 111$$



(Special cases)■ *Example 14*: Convert FA9₁₆ to binary

FA9₁₆

- \rightarrow 1111 1010 1001₂
- **→**111110101001₂

0 = 0000	8 = 1000
1 = 0001	9 = 1001
2 = 0010	A = 1010
3 = 0011	B = 1011
4 = 0100	C = 1100
5 = 0101	D = 1101
6 = 0110	E = 1110
7 = 0111	F = 1111

Conversion between <u>any two bases</u>, <u>other than decimal</u> (Special cases)

- Octal to hexadecimal or hexadecimal to octal:
 - Convert from the source base to the binary
 - □ Expanding each digit into three bits (in case of octal) or four bits (in case of hexadecimal)
 - Convert from the binary to the destination base
 - □ Group bits in three's (in case of octal) or four's (in case of hexadecimal), *starting from the binary point* (*pad the last group from both sides* with 0's, if needed)



(Special cases)

Example 15: Convert ABC₁₆ to octal

ABC₁₆

 \rightarrow 1010 1011 1100₂

 \rightarrow 101010111100₂

 $\rightarrow 101 \ 010 \ 111 \ 100_2$

→5274₈

0 = 000
1 = 001
2 = 010
3 = 011
4 = 100
5 = 101
6 = 110
7 = 111

0 = 0000	8 = 1000
1 = 0001	9 = 100°
2 = 0010	A = 1010
3 = 0011	B = 101
4 = 0100	C = 1100

5 = 0101 D = 1101

E = 1110

F = 1111

6 = 0110

7 = 0111



(Special cases)

Example 16: Convert 0.AB₁₆ to octal

 $0.AB_{16}$

 \rightarrow 0.1010 1011₂

 \rightarrow 0.10101011₂

 \rightarrow 0000.101 010 110₂

→0.526₈

0 = 000
1 = 001
2 = 010
3 = 011
4 = 100
5 = 101
6 = 110
7 = 111

0 = 000

1 = 001

2 = 010

3 = 011

4 = 100

5 = 101

6 = 110

7 = 111

Conversion between any two bases, other than decimal

(Special cases)

■ Example 17: Convert AB.BA₁₆ to octal

AB.BA₁₆

 \rightarrow 1010 1011.1011 1010₂

 \rightarrow 10101011.1011101₂

 \rightarrow 010 101 011.101 110 100₂

→253.564₈

0 = 0000	8 = 1000
1 = 0001	9 = 1001
2 = 0010	A = 1010
3 = 0011	B = 1011
4 = 0100	C = 1100
5 = 0101	D = 1101
6 = 0110	E = 1110
7 - 0444	



(Special cases)

■ *Example 18*: Convert 123₈ to hexadecimal

123₈

 \rightarrow 001 010 011₂

→ 1010011₂

 \rightarrow 0101 0 011₂

→53₁₆

0 =	000
1 =	001
2 =	010
3 =	= 011
4 =	100

5 = 101

0 = 000

1 = 001

2 = 010

3 = 011

4 = 100

5 = 101

6 = 110



(Special cases)

Example 19: Convert 0.123₈ to hexadecimal

0.1238

 \rightarrow 0.001 010 011₂

 \rightarrow 0.001010011₂

 \rightarrow 00000.0010 1001 1000₂

→0.298₁₆

	7 = 111
0 = 0000	8 = 1000
1 = 0001	9 = 1001
2 = 0010	A = 1010
3 = 0011	B = 1011
4 = 0100	C = 1100
5 = 0101	D = 1101
6 = 0110	E = 1110
7 = 0111	F = 1111

Conversion between any two bases, other than decimal

(Special cases)

Example 20: Convert 321.123₈ to hexadecimal

321.123₈

011 010 001.001 010

11010001.001010011

1101 0001.0010 1001

→D1.298₁₆

0 = 00001 = 00012 = 00103 = 0011

4 = 01005 = 0101

6 = 0110

7 = 0111

0 = 000

1 = 001

2 = 010

3 = 011

4 = 100

5 = 101

6 = 110

7 = 111

8 = 1000

9 = 1001

A = 1010

B = 1011

C = 1100

D = 1101

E = 1110

F = 1111